(1) Is ^੫

To list the file or content

- -a : To display all files.
- > -I : To long listing details.
- -s : To print the allocated size of each file.
- > -C : To list entries by columns (Upercase C).
- > -c : To sort newly created file or directory.
- -larth : To display human readable file size.
- -r : To sort in reverse order (Increasing order).
- -alSrh : To sort the files by size.
- > -alShR: To sort file with list subdirectories recursively
- > -z : To see the file context.
- -i : To see the inode number.
- Is -Irt: to sort the file date wise

(2) cal 4


To display a calendar.

{cal day month year} Format

- 1 : Display 12 months cal of year 1
- > -1: To display a current month.
- > -3: to display previous, current, next month.
- > -s : To display Sunday as the first day of the week.
- -m : To display Monday as the first day of the week.
- -j : To display Julian dates.
- -y : To display cal of current year.

(3) Date [∠]

To display or set the system date and time.



(4) mv

To move (rename) files.

(Source) (Destination)

➤ mv /home/abhijeet/file1 /home/afridi/file1 4

➤ mv file1,file2, dir1 🖟 (Multiple file)

- > -f: do not prompt before overwriting.
- > -i : To prompt before overwrite.

(5) cp

To copy files and directories.

(Source) (Destination)

> cp -R /Abhifile1/files /home/user/ ←

6) touch <filename> < : To create file (It will create zero byte file)

```
Ex. touch {file1,file2} ← touch dir1/file1 ← :- it crete a file inside dir touch File{1..10} ← : It create file1 to file10
```

7) mkdir <directory name> ←: To create directories

-p : Make parent directories mkdir –p dir1/1/2/3 4

mkdir {dir1,dir2};touch{file1,file} <- : To create directory as well as files

- 8) rm <files> 4 or rm -r <dir> 4 :- To remove files and directories.
 - -r :- To remove directories
 - -f :- Never prompt before remove
- -d :- To remove empty directory

Ex. rm -rf * ← :- to remove everything rm -rf *file ← :- To remove everything which have or end with file

9) rmdir <dir name> ←: To remove empty directory

-p :- to remove directory and its ancestors.

10) echo "Any line of message" ← :- To display a line of text

-n :- It print text /line rowwise

Echo \$SHELL: - To see the current SHELL

Echo \$? :- To check command successfully run or not. If return 0 then executed

otherwise not

Echo \$DISPLAY :- To check how many display

11) Input Output Redirection

'>' Output redirection

'<' Input Redirection

Echo "Msg" > file1 :- It redirect the message into file1. Echo "msg2" >> file1 :- it redirect the message 2 into file1

'>' :- Redirect but overwrite

>> :- Redirect without overwrite

2> :- redirect the standard error

&> :- Redirect the standard error and standard output

2>&1	:- redirect th	ne standard	error and	standard	output to	the standard	output
Z/ G I	. Ioanoot ti	io otariaara	circi ana	otariaara	output to	ti io otaliaala	output

12) cat file1 file2 ← :- To concatenate files and print on the standard output

```
cat file1 file2 ←: It will display file1 and file2 content together.
```

cat file1 4 : It will display only file1 content

13) less <filename> ←: To display the file content in another output screen

14) more <filename> ←: It display contain of a file part wise a screenful at a time.

Space :- to next page or continue q :- for exit

15) tail <filename> ←: To print last 10 lines of files.

-n : To print last n lines tail -n 20 <filename> ↵

-f: To output appended data as the file grows.

tail <filename > > /root/dest/file1 ← : to redirect the filename data to file1

16) tailf <filename> ←: to print the last 10 lines of file and then wait for file to grow.

17) grep "pattern" <filename> ←: To display lines that matching a pattern.

\$: Show line who end with the pattern 'test\$'

#: Show line which contain #

^# : Show line who start with #

-i : Ignore case

-v : To display non-matching line.

-e: To display string in the file

grep -e <string1> -e <String2> -e <string3> <filename> ←: It will find 3 string from the filename and give output

grep -v '^#' /etc/ssh/sshd_config 4 // It will display the pattern or line that do not start with #

grep '^#' /etc/ssh/sshd_config 4 // It will display the line that start with #

18) nano <filename> 4 : To edit text file

19) emacs <filename> ←: To edit text file

20) vim <filename> ← : To edit text file "It is a text editor"

:! = immediate

:q = quit

:w = write

:wq! = It will write the file the quit

Vim has 3 Mode Command Mode Insert mode Escape mode

yy: Copy line nyy: copy n line dd: cut line

ndd : cut n line

p : Paste below (Lowercae P)P : paste above (Uppercase P)

G: Go to bottom line

nG: Go to n line

cw : Erase the word from line cc : To erase or remove line

: /word or :?word : search the word

:%s/old-word/new-Word : Change first word : %s/old-word/new-word/g : change all word :!xs : It display contain in standard output

:set nu : Display line number :set nonu : Remove line number

seq 100 > bigdata.txt ## To create 1 to 100 on bigdata.txt

21) tar -cvf myarchive.tar files..... ← : To create and unpack tar file

- -c: To create a new tar file
- -v : Display details/changes in standard output
- -f: Represent the specific name of tar file
- -t: To list the contain of the archive file
- -z : To compress / decompress tar file in creation time.
- -x: To extract / unpack .tar file
- -d: To see the changes of the file

tar -zxvf <Mytar.gz> <Specific file name> 4: To extract any specific file from tar file.

Note: It overwrite the updated file when we extract the archive file.

- 22) star -c -f=myarchive.tar filenames ←: To create tar file.
- -t: To list the contain of archive file.
- -c: To create tar file
- -f: Specific tar file name
- -x: To extract the tar file
- -z : To compress and decompress file without making .gz file

Ex: star -cvz -f=My.tar file1 file2 file3 ←

23) su - <username> ← : To switch user

Ex: su - abhijeet ← : abhijeet is the user name

'-' represent all privillage of the user / or login with home directory

su - ← : To login as root user

- 24) gzip <filename> ←: To compress a file
- -d: To decompress file
- -I: It provide compression info
- 25) gunzip <filename> ←: To decompress a file

26) In /1/2/3/filename ← <file link name or address> <Source> <Destination>

To make softlink and hardlink between files.

-s: To create soft link

Ex: In -s /1/2/3/filename <file link name or address> ← // It will create soft link

Notes: 1) Softlink is a shortcut of original file whereas hardlink is a backup of original file.

- 2) Hardlink attach to inode number of the file.
- 3) Hardlink can create within same file system but softlink can create within any file system.
 - 4) Hardlink can be applied on files only.
 - 5) 'l' attached indicates the softlink

chmod ugo+rwx <filename> ←

u = owner(user) read = r = 4 set uid = 4 = u+s g = group owner write = w = 2 set gid = 2 = g+so = other user execute = x = 1 sticky bit = 1 = o+t

'+' : To add permission '-' : To remove permission

a = all (user, Group & Other)

u+s: To set Uid // Uid can be set for files only & applicable for user only, 'x' will replace by 's'.

u+g: To set gid // gid can be set for directory only & applicable for group only 'x' will replace by 's'.

o+t: To set sticky bit // Sticky be can be set for directory and applicable for other 'x' will replace by 't'.

-R: To change permission recursively (Uppercase 'R').

-X: To change execute permission only for directory recursively (Uppercase 'X').

chattr +i/-i <Filename> 4 // To add & remove chattr permission "No user can del the even root user".

lsattr: This command use to see chattr is applied or not.

ex : chmod a+rwx file1 $\stackrel{\mbox{\tiny d}}{\mbox{\tiny left}}$ //It will give read, write and execute permission to all chmod 777 <filename> $\stackrel{\mbox{\tiny d}}{\mbox{\tiny left}}$ // Set all permission for all user.

chmod 4777 <filename> ← // Set all permission for all user and uid.

chmod 7777 <filename> ← // Set all permission for all user (Uid, Gid and Sticky bit)

chmod u+rwx <filename> ↵ // set read, write & execute permission for user.

chmod u-rwx <filename> 4 // set read, write & execute permission for user.

chmod +l <filename> ← // set chattr

28) chown ownername:groupname <filename> ←: To change File/Directory owner & group.

Ex: chown root:linuxgroup <File1> ←

29) umask 022 ← : to change default file/directory permission

File value: 666 directory value: 777

Normal user: 002 root user: 022

File: 666 - 022 = 644 (rw.r..r..)

Directory: 777 - 022 = 755 (drwxrx.rx.)

/etc/bashrc: Where the default umask value is set.

source /etc/bashrc ← or exec bash ← // To update configuration file

- 30) find /root/ -name <filename> ← : To search file in a directory
- -name: to search with name
- -user: To search with user name of file/dir.
- -uid : Search using uid.
- -size : search for size "n, -n = less then, +n more than"
- -mtime: Search for modify date.
- -atime: Search for access time
- -mmin: Modify minute ("-" below, "+" above)(-20 below min, +20 above min)
- Ex: find /root/ -user abhi 4 // it find a file/dir having user abhi.
 - find / -uid 1002 ←
 - find / -perm 644 ← // Find all file which have permission 644
- 31) stat <filename> ←: To show the modification details of file.
- 32) id <username> \checkmark : It show the id of the user.
 - Ex: id root ← // It will show user id, group id of root user.
- 33) which <command name> ← : Show the full path of shell command.

Ex: which passwd ←

Output: /usr/bin/passwd

- **34) whereis <commandname>** ←: To locate the binary, source and the location of manual page of the file.
- -b : Search only for binary.

```
-m: search manual page file location.
-s : Search only for source.
35) whatis <command name> ←: To display manual page description.
36) locate <filename> ←: To find file by name
 -i : Ignore case
/var/lib/mlocate/mlocatedb
updatedb ← // To update the mlocate database
37) updatedb ←: To update database for locate / mlocate.
38 ) info <commandname> ↵ To display the command documents
-n: For next page
39) wc <filename> ←: To count line, word, character of text file.
-l: count new line.
-w: count word.
-c: count Character
40) shutdown ←: To power off the system
init 0
power off
shutdown -P now (Uppercase P)
shutdown -P + 5
shutdown -P 00:00
shutdown -c
systemctl poweroff -i // Other user can shutdown the system using this system.
41) restart ←: To restart the system.
init 6
```

```
reboot
systemctl reboot
shutdown -r 00:00
shutdown -r now
shutdown -r + 5
shutdown -c
42) gpasswd <option> <groupname> ←: to assign password to the group.
gpasswd <group name> // To assign password to group
-a: add user to the group
gpasswd -a <username> <group name> // To add user to a group
-d : del user from tht group
-r: remove password from the group
gpasswd -r <gname> // remove the password from group
-R: restrict to access that group.
gpasswd -R <group name> // We cant not use that group
A: set the list of sdministrative users
-m: to set the list list of group mamber
gpasswd -d <username> <groupname> // To delete the user from the group
43) halt \leftarrow: To halt the system.
systemctl halt ←
halt ↵
shutdown -h +5 4
44) useradd <username> ←: To add new user.
-M: without create home dir (Uppercase M).
-d: To specify particular home dir of user manually on creation time
-u : Top add user id on creation time
useradd -o -u 0 -g root <username> //Create duplicate root user ##use root as primary group
45) userdel <username> ← : To delete user
```

```
-f: forcefull
-r: remove home directory and mail spool
46) passwd <username> ←: To give password
-l: to lock the user(Lowercase l)
-u : to unlock the user(Lowercase u)
47) groupadd <groupname> ←: To add new group
-g: group id
-r: system group
-R: root group
-n: Change group name
48) groupdel <groupname> ←: To remove group
-R: To delete group and apply changes to the root dir.
49) w 4: To show who is logged on and what they are doing
50) who \leftarrow: To show who is logged on.
-r: To show run level
-a: To see system boot time
-b: To see system last boot time.
cat /etc/passwd | grep user1 // To see current login shell of particular user.
51) usermod <option> <username> : To modify user account
-c: Modify comment
-md: to modify user home directory
```

```
-L: To lock the user (Uppercase L)
-U: To unlock the user (Uppercase U)
-g: To add primary group
-G: To add secondary group
-u: To change uid
-l : To change user name.
-s: To change login shell
-aG: to append secondary group
Ex: usermod -G <groupname> <username> //To add the secondary group
   usermod -u <uid> <username> // to change the uid of the username
   usermod -l <new user name> <old user name> // To rename the user name
   usermod -s </sbin/nologin or /bin/bash> <user name> // To change the user login shell
   usermod -G "" <username> //To remove all secondary remove
   usermod -aG <Secondary group name> <user name> // To append secondary group means more
than one secondary group.
   usermod -o -u 0 <username> // Duplicate root user
ps -cf:- display process information with PPID
ps -u <u.name> //to view the process of user
Ex:-ps axo pid,comm,nice | grap httpd
ps -G <g.name>/ /to view the process that is running by the group
Ex:-ps -ef |grep init
ps -ely cat // to view the nice value of the command
ps -p <pid> // to view the process name
pidof <p.name> //to view the process id
```

53. Kill: To terminate a process

```
(2373)
- kill % 1 :- It terminate the job 1.
      <job no.>
- kill -9 pid // To kill process immediately
- kill -SIG STOP/19 % 1 :- It stop job 1.
- kill -SIG CONT/18 % 1:- It continue job 1.
Note: "kill" terminate the process based on PID where as "pkill" terminate the process based on name or other
attributes.
-1 -SING UP
-9 -SIG KILL // Kill the process forcefully
-15 -SIGTERM // Kill the process gracefully
-18 -SIGCONT
-19 -SIG STOP
55) ip: To show ip address and show / manipulate rooting, device policy routing and tunnels.
- ip addr // It show ip address
- ip addr show ens37 // Show ip address of device ens37.
- ip -s link show ens 37 // show sending and receiving packets.
- ip a s eth0 // Show the pass of eth0
56) top: To display linux process and load average
    -20 :- High priority
    -19:- Low priority
Shift +n or cat/proc/loadavg :- short it high to low of PID
1:- To check the no of CPU
r:-To renice by PID
```

k:-To kill process by PID

-n 2:- To refresh screen 2(n) times and comes into terminal number.

```
-d \, 3 : - It set the time for refresh display.
```

u:- To see the process owned by the user

shift + m or M = it sort the memory utilization top to bottom

shift + p or P = It sort cpu utilization top to bottom

57) nice: To run/set a program with modified scheduling priority.

-20 :- Most Favouritable

-19 :- Least Favouritable

It cannot done if processs is running

58) renice
$$\,:\,$$
 To change the priority of running process.

59). time: To display the time taken to complete a process

Ex: time nice -n 10 tar -cvf mytar.tar // It display the time to create tar file.

du -sh * //estimate file space uses.

Note: du (command) for check file/directory size

60. df: To display the file system and disk space usages. -T :- To view the particular file system type. -h :- It show the disk space/in human readable 1) du : To estimate file space usage -a: To display all file sizes -h: human readable du -sh * 2) dd: To create a file dd if=/dev/zero of=/filename bs=1MB count=2048 // It will create 2GB empty file 61. chage: To change user password expiry information Or to change user password policy. -l :- show user password information i.e. chage -l < username> -E :- To change account expire date i.e. change -E 2015-06-05 <username> ## yy-mm-dd format -1 :- To remove account expire i.e. chage -E -1 <username> -M:- To modify password expire date. i.e. chage -M 90 <username> // (Uppercase M) days format -m :- minimum days ## Mininum days between password change

-d :- It expire everything

```
i.e. chage -d 0 <username>
-W :- To modify warning days // (Uppercase W)
-I :-set password inactive after expitation to inactive
Note: date -d "+40 days" +% F ## To find specific date
vim /etc/ passwd
<user name>: x:<vid>:<gid>:<comment>: <users home directory>:<loging cell>
vim /etc/shadow
Username:password :last changed:min.day:max.days:Warn days : inactive days :expire days:reserved for
future.
Inactive days: after few days of passwd expired, password will inactive then user have to contact admin team if
user miss this one also then after that account will expire.
Note: Minimum days always should be 0.
Note:-/etc/login.defs // Default password policy configuration file
passwd -x 1 <user name> // It put never expiry of user
                          // (to see the status of the password of that user. if root user is not assigned
passwd -S <uname>
                          // the password then the password status is locked)
                                     // To delete the password from user.
passwd -d <uname>
                                     // To set password of user
passwd <unmae>
63) fdisk: To manipulate MBR based disk partition / It means create, delete and modify the partition.
  -l: To list all details of disk
  fdisk -l /dev/sdb
  fdisk /dev/sdb : To create, delete and modify partition
  Options :- n : new partition, d : delete partition, t : type of partition
  Partition id: - 83: Linux File System, 82: Swap, 8e: LVM, fd: Raid
```

Note: fdisk can create only 4 partition "3 Primary partition and 1 extended partition". gdisk can create 128 partition fdisk: 32Bit gdisk: 64Bit 64) gdisk: To interactive GUID partition table (GPT) manipulator. ## Support UEFI Device 8300 - Linux Filesystem 8200 - Swap Filesystem 8e00 - LVM Filesystem 65) mkfs: To build a linux filesystem // By default it will create ext2 file system -t : Specify the type of file system to be build. -f: Forcefully mkfs -t xfs <partition name> mkfs.ext2/ext3/ext4/etc <device name> ex. mkfs.ext2 -f /dev/sdb1 : It will change the file system type by formatting the partition with a particular file system type mkfs.ext4 -m <no.> <partition no.> // To format a partition with a specific reserve % for superblock. By

default it will take 5-10% superblock.

66) blkid: To print block device attributes or to see block id.

```
67) mount: To mount a file system
-a: To mount all
## For temporary mount
mount <device name> <mount Point>
e.g. mount /dev/sdb1 /mnt/mymount
## For permanent mount
vim /etc/fstab //By make an entry in fstab file
<device name> <mount point> <filesystem type> <mount options> <take a backup or not> <fsck
value>
e.g. /dev/sdb1 /mnt/oracle xfs defaults 0 0 ## After make entry run mount -a command or reboot
mountpoint <Directory location> //To check particular directory is mount point or not
vim /etc/mtab ##Is the file that keep record of all recent mount point
mount // Will show all mounted device
68) umount: To unmount the file system.
-a: To unmount all
-f: To unmount forcefully
umount <mountpoint> //To unmount a file
umount /mnt/mymount
69) lsblk: To list block device of disk / device in tree view.
70) partprobe: To update partition table information
```

```
-s: Show summary of device and their partition.
e.g. partprobe -s /dev/sdb ## only disk name not partition name
71) pvcreate /dev/sdb1 /dev/sdc1 : To initialize physical volume(s) for use by LVM
72) pvremove /dev/sdb1 /dev/sdc1 : To rename LVM label(s) from physical volume(s).
pvremove <device name>
73) pvdisplay or pvs or pvscan: To display the physical volume.
-m: To display mapping of physical extents
74) vgcreate <vgname> /dev/sdb1 /dev/sdc1 : To create a volume group
vgcreate <vgname> /dev/sdb1 /dev/sdc1
Note: Vg is the composite of logical volume and physical volume.
75) vgdisplay or vgs or vgscan: To display volume group
Note: To reduce Lvm partition formatted with XFS filesystem
      xfsdump -f /location/name.dump <Mount Point>
     Then unmount, then reduce, then formate with mkfs, then mount
       xfsrestore -f /location/name.dump <mount point>
```

76) vgremove <vgname> : To remove volume group

```
77) lvcreate -n <lvname> -L <size> <vgname> : To create a logical volume
-n: To give lv name
-L: To give size
e.g. lvcreate -n lv1 -L 500M vgname1
   lvcreate -l 200 -n <lvname> /dev/vg1
   lvcreate -n <Lv name> -l 100% FREE <Vg Location>
78) lvdisplay or lvs or lvscan: To display information about a logical volume
79) lvremove /dev/vg1/lv_vg1 : To remove logical volume
LVM Snapshot
lvcreate -s -n <Lvm_snapshot> -L <20M> <Lv Location>
umout <file system>
lvconvert --merge </lvm_location>
lvchange -ay <lvname>
mount -a
80) vgextend <vgname> <device name> : To add physical volume to a volume group
e.g. vgextend vg1 /dev/sdd3
81) vgreduce <vgname> <device name> : To remove physical volume from a volume group
i.e. vgreduce vg1 /dev/sdd3
```

83) lvextend -L <size> <Location of lv> : To add or extend space to the logical volume.

i.e. lvextend -L 5G /dev/vg/lv

lvextend -L +5G /dev/vg/lv

lvextend -l +50% FREE /dev/vg/lv

84)lvreduce (for exit fire system)

To reduce the size of logical volume

Lvreduce -L -<size> <Lv name>

Lvreduce -L -1G /dev/vg1/lv1

Lvreduce -l 20/dev/vg1/Lv1//To remove using LEs

-r =resizefs

Lvreduce -l-500m-r <lv name> reduce est file system

85) pvmove <location whose data is store>

To move extents from one physical volume to another

Pvmove <old pv>

86) xfs_growfs <mount point>

To refresh/Expand on xgs file system

Xfs_growfs <mount point>

e.s. xfs_growfs /mnt/my volume

xfs_repair /dev/vg1/lv1//to repair xfs file system

87) resize2fs <mount point>

Ext2/ext3/ext4 file system resize

e.s. resize2fs /mnt/my volume

88) tune2fs

To change parameters of an ext2/ext3/est4 file system.

- -l:-To set level name
- e.s. tune2fs -l est4lebel /dev/sdc1
- -l <device name> :- To verify lable name
- 89) xfs_admin

To change parameter of an xfs file system

-l :- lable name

Xfs_admin -l <new lebel name> <partion name>

e.s. efs_admin -l lable1 /dev/sdd1

To verify

- -l <device name> :- lebel name of device
- 90) xfs_repair <device name>


 TO repair an xfs file system

 Xfs_repair /dev/sdc1
- vgcfgrestore: To restore volume group information
 vgcfgrestore: -list < Vg Name > //To see Vg backup list
 vgcfgrestore: -f < paste the backup file name > < vg name >
- 2) vgcfgbackup : To backup volume group configuration vgcfgbackup <volume group> //To take a backup
- 3) vgchange: To change volume group attributes/parameter

```
-l : Logical volume number
       vgchange -l <no> <vg name>
       -P: Max physical volume number
       vgchange -p <No.> <vg name>
       -s: To set physical extents size / block size
       vgchange -s <no.> <vgname>
       -a: Activate (n:no, y:yes)
       vgchange -an <Volume groups> //Activate, No
       vgchange -ay <Volume groups> //Activate, Yes
4) Ivchange: To change the attributes/ parameter of logical volume(s)
       -a : y|n
       -p: for permission: rw|r
       lvchange -Pr <Iv name> //To put the logical volume read only mode
       lvchange -Prw <lvname> // To put the logical volume read, write mode
5) vgrename: To rename volume group
       vgrename <existing vg> <new Vg name>
```

6) Ivrename: To rename logical volume

lvrename <existing lv> <new lvname>



93) mkswap <device or partition name>

To make a swap file system
e.g. mkswap /dev/battlestasr/swap

94) swapon/off <swap device partition name>

To enable/disable swap space

-a :-all

i.e. swap on -a //on swap off -a //off

i.e. swap /dev/battlestar/swap

-s :-show summary of swap

Swap -s //To see the swap space information

95) getfacl <file/dir/name>
Get file access list (ACL)
i.e. getfacl file1

96) setfacl

To set access control lists (ACL)

• -m u:username:permission filename // To modify ACL i.e. setfacl -m u:abhi:rw file1

- -b <filename> //remove all ACL permission i.e. setfacl -b file1
- -x u:abhi file1//rename ACL permission of user.
- --remove-default <file/dirname> //To remove all default ACL permission. i.e. setfacl --remove-default file1

```
    -d : for giving default ACL permission
    -d -m u:abhi:rw dir1
```

- Setfacl: -x d:v:<username> dirname// To remove default permission
- Setfacl -m m::r file2//To update mask permission
- Setfacl -m m::- file //remove all mask permission of the file
- Setfacl -x m:: filename // remove perm mask from file //mask perm. will be remove after remove all ACL permission
- Setfacl -R -m g:filename:rw; u:abhi:rw div1
- Getfacl filename | setfacl --set-file= file2 // copy filename1 permission to file
 We give defult permission only to the dir
 The acl mask defines the maximum effective permission for any entry in acl.
 CP command does not perserve ACL rules my command preserve ACL rules

m: max permission using we assigh to some particular user to access the file and directoroes.

97) nmcli: Command line tool for controlling network manager.

```
nmcli dev status // Show device network status
nmcli dev show // To show the device
nmcli con show // Show all connection
nmcli con add con-name "Mycon" autoconnect yes type ethernet ifname ens33 ipv4.method auto //
To add new connection
nmcli con up <con-name> // To up the connection
nmcli con down <con-name> // To down the connection
nmcli con del <con-name> // To delete the connection
```

nmcli con mod <con-name> // To modify the connection

e.g. nmcli con mod ens33 autoconnect yes // To update autoconnect as yes of ens33 connection

Note: /etc/sysconfig/network-scripts/ // device configuration file

Network Teaming

1) teamdctl: Team demon control tool

teamdctl lateam0 state: It will show the status of team "lateam0"

##Process to create teaming

nmcli con add con-name lateam0 type team ifname lateam0 config '{"runner": {"name": "activebackup" or "roundrobbin" }}'

nmcli con mode lateam0 ipv4.address 192.168.0.10/24

nmcli con mode lateam0 ipv4.method manual

##Now add the port with lateam0

nmcli con add type team-slave con-name lateam0_port1 ifname ens33 master lateam0 nmcli con add type team-slave con-name lateam0_port2 ifname ens34 master lateam0

nmcli con up lateam0/lateam0 port1/ lateam0 port1

Some other things related o teaming

Assign IP address to team0

nmcli con add con-name "name" type ethernet ifname ens33 autoconnect yes ipv4.address 192.168.1.15/24 ipv4.method manual gw4 <gatway id> ipv4.dns <dns Id> //Assign static ip

nmcli con mod dynamic ip ipv4.ignore-auto-dns yes nmcli con mod dynamic ip ipv4.dns <DNS Server ip> PEERDNS=no

- + add dns (we can have up to 3 nameserver configured)
- remove dns, without sign replace the current dns

98) nmtui: Text user interface for controlling network manager

99) nm-connection-editor: It show GUI for managing devices.

100) ss: To display listening port and establish connection. Or utility to investigate sockets.

-a: To display all sockets

-t: To display tcp sockets

-n: To display port number

-l: To display listening socket

101) netstat: To print network connection, routing tables, interface statistics.

netstat -ntulp // To check listening port

-r: Display kernel routing tables

-n: Show numerical addresses

t = Tcp u = udp, n = port number, l = port is listening or not, p = process id

Network monitoring connection both for incoming & outgoing as well as view routing table interface statistics etc.

netstat:-at:TCP port

netstat : -l : Listing port

netstat:-s:statistic

netstat : -r : routing table

netstat -an | grep 22 : To find all process running on 22

netstat -ap | grep ssh: To find ssh running process

```
1) ip route: Routing table management
       Ip route list: list all route
       Ip route add 216.58.217.0/24 via 192.168.1.11 dev ens33: To add ip route
##static route
       Vim /etc/sysconfig/static-route
       any net 173.194.205.0 netmask 255.255.255.0 gw 162.242.253.1 dev eth0
2) nslookup: To query internet name servers interactively
       nslookup google.com
3) nmap: To check the open port
       nmap -p <port nm.> <ip> // To check particular port for particular ip is open or not
       nmap <ip>// To see all open port of the ip
4) exportfs: To maintain table of exported NFS file system
       -a: Export or unexport all dir
       -v : List of exported dir
       -r : Re-export all directories
```

i.e. exportfs -avr 5) dig: DNS lookup utility dig -x <ip.address> // To query of ip address dig <FQDN> // To query of domain 101) traceroute: To print the route packets trace to network host - traceroute <ip address> 102) ping: Send ICMP ECHO_Request to network host. -c 5 : Show 5 ping and quit ping <ip address> : To ping ip address Bash: Is the command language interpreter for GNU OS. Shell: Is an interactive interface that allows user to execute command and utilities in linux os. 103) hostnamectl: To control the system hostname hostnamectl set-hostname <host name> // To change or set hostname hostnamectl status // To see hostname information hostname // It display the hostname hostname - i // To show ip exec bash // To apply the changes without reboot 104) getent: To get entries from name service switch libraries. 105) timedatectl: To control the system time and date.

```
- set-time zones 'Asia/kolkata' // To set the Kolkata time zone
   - set-time 12:32:15 // Set the time
   - timedatectl // It display current date and time
   - set-ntp false/true // To enable and disable ntp
106) tzselect: To select a time zone
107) at: To schedule task
- at now +10minutes // Schedule a task after 10 min
   at > init 6
ctrl + D - Two time to excute above command ?? It will execute the command after 10 minutes
- at 12:00 am // Schedule the job for the given time
- atq // To list the pending job
- atrm <job No.> // to remove job
vim /etc/at.deny // Here we can restrict user to use at utility by enter username in the file
vim /etc/at.allow // Here we can allow the user to use at utility by default this file not created
-r: To delete the jobs
-l: To list the jobs
## Try below
at 5:20 pm
at > logger "The system current uptime is $(uptime)"
ctrl+D (2times)
journalctl -xn
```

108) yumdownloader: to download rpm package

- list-time zones // To display time zone

```
yumdownloader <packagename> //It will install the rpm package in local storage
yum localinstall <rpm package location> // Then we can use this step to install above downloaded pckage
109) yum: yellowdog updater modifier REDHAT package management tool
yum check-update // To check all package updates
yum info <package name> // To gether info of the package
yum install <package name> // To install package
yum list installed // It show all install package
yum update <Packagename> // To update package
yum update -y //It update all
yum remove <packagename> // It remove the package
yum autoremove // To remove unnecessary package or dependency
yum clean all // to clean temporary, cache file.
Yum config-manager --disable/--enable <repos id> // To enable/disable repos
yum localinstall <package name> // To install downloaded package
yum update kernel //To update kernel
yum deplist <packagename> // To check dependency
yum install --downloadonly --downloader=downloads php
##How to roll back
yum history list all // check the history
yum history info <id> //Find the info id and check
yum history undo <id> // Then by entering previous id we can roll back to previous
```

Note: Yum download the package along with dependency.

```
110) rpm: Redhat package manager
rpm -ivh <package name>
-i <package name> // To install package
-e <package name> // To erase or remove package
-u <package name> // To upgrade package
-q <package name> // To query about package
-qa <package name> // All query
-ql <package name> // To show all file of the package
-R <package name> // To list package dependent ##NOT Sure
e.x.
rpm -i httpd
rpmquery httpd
rpm -qa httpd
rpm -e httpd
rpm -qf <filename> // To check which package is responsible for the file
rpm -qa kernel --last // To see kernel installation date time
rpm -ivh --test <package name> // To check the package consistency
Note: rpm not able to download the dependency along with package
110) uname: To print system information
-a: Print all information
-r : Print kernel version
-m: System architecture current bit
-0:0/S
```

112) firewall-cmd: Firewall command line client

- firewall-cmd --get-zones // It display all available zone
- firewall-cmd --get-default-zone //To show default zones
- firewall-cmd --list-all //To show default zone details
- firewall-cmd --zone=home --add-source=192.168.1.0/24 // To add ip address to the source of the zone
- firewall-cmd --reload or --complete-reload //To reload firewall configuration
- firewall-config // To show GUI based configuration
- firewall-cmd --zone=home --permanent --add-source=192.168.1.0/24 //To apply permanent we have to reload the configuration after apply
- firewall-cmd --zone=public --add-port=80/tcp // To add for runtime after reboot it will not survive
- firewall-cmd --panic-on // It looked everything on local console
- firewall-cmd --query-panic // To see panic mode status or query
- firewall-cmd -state // To see firewall status

If we want to copy a file that is reside, before the it 1st check or matches the both file size and creation/updation time of the file and then only copy the changes or new content.

```
rsync <source location> <destination location>
       rsync <source file location> root@192.168.1.12:~/ ## Upload
       rsync root@192.168.1.12:~/ <destination> ##Downloading
       rsync file1 root@192.168.1.11:/root/Documents
       -a = all (Copy the file with all permission except SELinux and ACL permission)
       -aA = Synchronize ACL permission
       -aAx = Synchronize ACL permission and selinux permission also
115) sftp: To secure file transfer program
sftp root@192.168.1.12
       sftp > ls : Display content
       sftp > get <filename with loaction> : To download or copy file from remote location to local
       sftp > put <Filenme with location> : To upload or send file from local to remote location
       bye: To exit
116) ssh-keygen: Authentication key generation.
       -t: Key type "rsa algorithm or dsa algorithm"
       ssh-keygen: By default It will create rsa type key
       ssh-keygen -t dsa: It will create dsa key
       /root/.ssh/ // Is the location of pub and private key
       id_rsa and id_rsa.pub
       Note: public key share with remote machine and compare with private key of local machine if all ok
then we can take access
```

then

```
117) ssh-copy-id: To copy the key to authorize login on a remote machine
ssh-copy-id root@192.168.1.11 // It copy the generated key by "ssh-keygen" to the remote IP
address
// It will copy the public key "id_rsa.pub" to the remote
118) ssh-add: Add private key identifies to the authenticate agent.
## Process to use key based authentication
Step 1: ssh-keygen or ssh-keygen -t dsa // It will create the key file "id_rsa & id_rsa.pub" in
/username/.ssh/ directory.
Step 2 : ssh-copy-id <u>root@192.168.1.11</u> // It will copy the key "id_rsa.pub" to the authorized_key to
the remote ip address.
Step 3: ssh-agent bash
Step 4: ssh-add // It will add the identity to the id_rsa file
119) getenforce: To display current mode of SELinux
120) setenforce: To change the mode of SELinux
       0 // Permissive mode // Disable mode but it will notify for unwanted access
       1 //Enforcing mode ## Means enable
```

```
setenforce 0
setenforce 1
vim /etc/selinux/config
SELINUX=enforcing/disabled // It will apply the changes for permanent after that need to reboot
To completely disable the SElinux we need to make changes in configuration file as
"SELINUX=disabled" then reboot
Or we can use directly sed command
sed -i 's/enforcing/disabled'
2) semanage: SELinux policy management tool
       semanage port -l // List all port
       semanage port -l | grep 80
       semanage port -a -t httpd_port_t -p tcp 8282 // To add port 8282 in Hpptd_port_t
       semanage fcontext -l : To list all context
       semanage fcontext -at httpd_sys_content_t "/mnt/check(/.*)?" // To change the context of a
file or dir.
       semanage fcontext -d "/mnt/file(/.*)?"
       -d: To restore default file context.
3) restorecon: Restore file default SElinux context.
       restorecon -R: Change selinux file context label recursively.
       restorecon -V: Show changes.
       e.x. restorecon -Rv /mnt/check
```

```
3a) chcon: To change file context "SELinux security context"
              chcon -R -t samba_share_t /file location
                     -R: Recursive
                     -t:type
4) getsebool : get seliux Boolean value
       -a: show all SELinux Booleans value
       getsebool -a | grep nfs_export
5) setsebool: set SELinux Boolean value
       setsebool -P nfs_export_all_ro=1
       -P: To set Boolean value for permanent
       1=enable 0=disable
       121) sysctl: To configure kernel parameter at runtime
              -a: Display all parameter value currently available
              -w kernel.sysrq=32 :- change parameter value
              sysctl -a | grep kernel
              cat /proc/sys/kernel/sysrq
       1) grub2-set-default <option> : To switch between the kernel
              0 : Means newly updated
              1: Means previous one
       grub2-set-default 0/1 // To switch between the kernel reboot is require
```

```
package-cleanup --oldkernels --count=1 // Remove old kernel
       vim /boot/grub/grub.conf // To load default kernel
        122) elinks : elinks is a text mode www browser.
                elinks <a href="https://localhost">https://localhost</a>
       configuration file of httpd.
       /etc/httpd/conf/httpd.conf
        /var/www/html
123) systemctl: Control the systemd system and service manager
       systemctl status <service name> // To check status
       systemctl start/stop <service name> // to start and stop the service
       systemctl enable/disable <service name> // To enable and disable the service
       systemctl restart <service name> // To restart the service.
       systemctl is-enabled / is-active httpd // to check httpd service is enable or not / active or not
       systemctl list-unit-files // to display enable and disable service
       systemctl isolate <target.name> // To change target for runtime
       systemctl list-units --type=target // To display all available target
       systemctl get-default // to show default target
```

systemctl set-default <target name> // to set the default target

systemctl list-dependencies <service name> // To list dependencies of particular services.

if we enable any service it will create a symlink between '/usr/lib/system/system/httpd.service' to '/etc/system/system/multi-user.target.wants/httpd.service'

124) mdadm: Multiple Disk and device administrator

```
It is used to manage and monitor software RAID devices.
- mdadm -Cv /dev/md0 -n 2 /dev/sdb /dev/sdc -l 0 //To create raid 0 using /dev/sd[b-c] //
"Uppercase C" & /dev/md0 is the device for raid always it should be same for all raid lavel.
- mdadm -E /dev/sdb1 /dev/sdb2
                                     //Enquiry about the device
- mdadm -D /dev/md0
                         //Details about the raid device
- mdadm /dev/md0 -a /dev/sdb1
                                    //To add disk
- mdadm --stop /dev/md0
                             //To stop the /dev/md0 raid device
- mdadm /dev/md0 -f /dev/sdb
                                    //(to failed the disk manually)
- mdadm /dev/md0 -r /dev/sdb
                                   // (to remove the above failed disk)
- mdadm /dev/md0 -a /dev/sdd
                                   // (to add the new disk in place of failed disk)
- mdadm /dev/md0 --add /dev/sde
                                      // (to add third disk to the RAID - 0 volume)
- mdadm --grow /dev/md0 --raid_device=3
                                             /// (to grow the RAID - 0 file system)
- mdadm --zero-superblock /dev/sdb1 //To remove md superblock from the partition or any specific Raid.
- mdadm -S /dev/md0 //To stop Raid0
- mdadm --assemble /dev/md0 /dev/sdb /dev/sdc //To restart the /dev/md0 raid device
- mdadm --detail --scan --verbose >> /etc/mdadm.conf // Save the raid configuration manually to
'mdadm.conf' file
- watch -n1 cat /proc/mdstat
                              // To monitor the current building process
```

```
125) smbpasswd : Change users smb password
smbpasswd -a <username> //Add samba password to user
smbpasswd -u <uname> //change password
-d : Disable samba user
-e : Enable samba user
```

-x: Delete samba user password

-r: remove samba user password

-n: null password

```
126) cpio: Copy files to and from archives
       o: To take backup
       i: To restore the cpio backup
       v : verbose (Display the output)
       t: To list the cpio content
We use cpio to take backup as a archive.
*.cpio is the extensions of cpio archive
e.x.
       ls | cpio -o > /root/backup.cpio //To take backup
       cpio i < /root/backup.cpio //It restore the backup at the current PWD
       cpio t < /root/backup.cpio // To list the content of the cpio archive
127) modprobe: Add and remove modules from the linux kernel
              modprobe <module name> // To install and re-install module name
              modprobe -r <module name> // To remove module
              modinfo <mod name> // To see the specified module information
              lsmod // To list the modules
              extension .ko
128) sar: To check system activity report ---- We can check current and previous dated system activity
report.
              sar 2 10
                             // system report for every 2 sec upto 10 times
```

-b: Report input output statistics sar -b 2 5 -s: Report swap statistics sar -s -1 //To check swap information of previous date. sar -s 2 3 //To check swap information of current time -p : Report cpu usages -q: Load average -r: Memory usages -d: Disk static sar -q -f /var/log/sa/sa17 // To see the back dated log file of load average configuration: Vim /etc/sysconfig/sysstat "HISTORY=28" log:/var/log/sa/sa.... 129) vmstat: It gives complete information about virtual memory like no of process, memory usage, paging memory, disk. vmstat -d // To see the statistics of disk used. vmstat -a // Active inactive process - fields procs: r: Running process b: Busy Process memory: swap: How much virtual memory used free: How much memory is free buff: How much temporary memory is using

cache: How much caching still using

swap: si: How much data transfer from RAM to SWAP

so: How much data transfer from SWAP to RAM

IO: bi: How much block input

bo: How much block output


```
130) sosreport: To store the system configuration and diagnostic report.
       system: in: The number of interrupts per second.
                cs: the number of context switches per second
       cpu: us: The cpu time spent in user space. i.e. Normal process
             sy: The cpu time spent in kernel space
             id: CPU idle time
             wa: CPU time spent waiting for I/O
131) iotop: To monitor the I/O statestic
       - o : High consumption I/O
       -p:PID
       -u: user
132) iostat: It reports cpu statistics and I/O statistics for device and partitions.
       -c: Display CPU utilization report: iostat -c
       -d: Display disk utilization report: iostat -d
       -m: display disk utilization in MB format.: iostat -m
       -p: Display static of disk in specified format: iostat -p or iostat -p <device or partition>
       -N: Display Lvm static: iostat -N
       -t : Display time stamp : iostat -t
       -X: Display extended information of the disk: iostat -x
133) dmidecode: It gives hardware related information of the sys.
       dmidecode -t memory // To see memory info
       dmidecode -t bios // BIOS's info
```

dmidecode -t system // system information

dmidecode -t processor // Processor info

```
134) crontab -e // To edit the cron jobs
       */2 * * * * touch file {1..2}
root user it will create file every two minutes.
<minutes> <hours> <day of the month> <month of the year>
                                                                <day of the week>
(0 - 59)
            (0 - 23)
                          (1 - 31)
                                          (1 - 12 or jan, feb, ...)
                                                                 (0 - 6 or sun, mon, ...)
// five star representing this time respectively.
           Is treated as a wild card. Meaning any possible value.
*/5
           Is treated as every 5 minutes, hours, days or months. Replacing he 5 with any numerical value will
           change this option.
2, 4, 6
           Treated as an OR, so if placed in the hours, this could mean at 2, 4 or 6 o-clock
9-17
           Treats for any value between 9 and 17. So if placed in day of the month this would be days 9 through
           17 or if put in hours, it would be between 9 AM and 5 PM.
crontab -r // To remove cron jobs
crontab -l // To list cron jobs
crontab -u <user name> -e or -r or -l
## How to reboot the system using crontab
crontab -e
43 12 * * *
                    /sbin/shutdown/ -r
                                              // It will reboot the system every day at 12:43
vim /etc/crontab ## configuration file
135) dump: To take backup
       -o: full backup
       -(1-9): Incremental backup
       dump -ouvf /opt/full.dump //To take backup
```

```
dump -ouvf /destination
       restore -tf /destination : To list the backup contain
       restore -rf /destination; To restore the file
       u : update
       v: verbose
       f: used to specify the dump or backup files
       t: list the contains
       r: to restore
       -u : update the entries in /etc/dumpdates conf file.
restore -rf /opt/full.dump // to restores
Some Extra Commands
growpart /dev/sdb 2
                             // to apply the changes in the partition size.
             // To find the VLAN of the interface (yum install lldpd -y)
lldpctl
ifdown eth1 // to down the interface
             // To up the interface
ifenslave -c bond0 p6p1 // To change the active interface.
smartctl
                      // To check the hard disk health
smartctl -i /dev/sdb
                                    // to check the info about the disk
smartctl -H /dev/sdb
                                    // to check the disk health
                                    // To check failed login
pam_tally2 -u <uname>
pam_tally2 -r <uname>
                                    // To reset user
/etc/pam.d/password-auth
                                  // pam_tally2 configuration files.
                                                  SUDO
Visudo /etc/sudoers
Go to 98 line
Username ALL=ALL NOPASSWD: ALL // It won't ask root password to user
:wq!
```



It means all the users that belong to the wheel group can execute all the commands like root

raju ALL=NOPASSWD:/usr/sbin/useradd, /usr/sbin/usermod

RAID

Raid stands for redundant array of independent or inexpensive disks, is a storage device that provides fault tolerance, load balancing using stripping, mirroring and parity concepts.

There are two types of Raid available

1) Hardware Raid 2) Software Raid

There are mainly five types of Raid which are generally used

- 1) Raid-0 (Stripping)
- In Raid-0 data is divided into multiple blocks and each of those blocks is stored on different disk. So, minimum 2 disk is required and partition id is "fd".
- It provide high read/write speed, but there is no redundancy and fault tolerance because if one of the disk fails, the entire data is lost.
- We can use 100% disk space of the total disk space.
- 2) Raid-1 (Mirroring)
- In Raid-1 the same data is stored in two disk, as like take the backup of the data into another disks. Minimum 2 disks are required and partition id is "fd'
- Write speed is slow as compared to Raid-0.
- It provide fault tolerance and more redundancy.
- But we can use only 50% space of the total disk space.

- 3) Raid-5 (Striping with parity)
- It striped the data across the multiple disks and on one disks a parity checksum of all the block data is written.
- Minimum 3 disks is required to configure raid-5 and partition id is "fd'.
- It provide high read speed but write speed is little bit slow because of parity checksum.
- If one of the disk fail we can recover the data from parity but if 2 disk fails, then we cannot recover the data. So, there is less fault tolerance.
- we can use approximately 70% space of the total disk space and remaining space is reserved for the parity.
- 4) Riad-6 -----(Striping with double parity)
- It striped the data across the multiple disks with dual parity.
- Minimum 4 disks are required and partition id is "fd" but we can use only 50% space of the total space because of dual parity.
- It provide more load balancing and fault tolerance as compare to Raid-5.
- R/W speed is also fast.
- if two disks are fail on the same time, then we can also recover the data but if 3 disks are fails at the same time then we cannot recover the data.
- 5) Raid-10 ----- (Mirroring + Stripping)
- Raid-10 is the combination of Raid-1 & Raid-0, To provide data mirroring with data stripping to protect our data.
- It requires minimum of four disks.
- We can use only 50% space of total space.
- Read Write speed is very fast.
- It provides fault tolerance and load balancing.

If one disk failed then we can recover the data but if two disk failed then we cannot recover the data.



FTP (File Transfer Protocol)

Ftp is used for transfer file between one host to another host in a network.

```
Server:
yum install vsftpd * -y
systemctl start vsftpd
firewall-cmd --permanent --add-service=ftp
firewall-cmd --complete-reload
vim /etc/vsftpd/vsftpd.conf
       anonymous_enable = no
       chroot_local_user = YES
       allow_writeable_chroot = YES
       writeable_enable = YES
       anon_upload_enable = YES // Do not use for secure ftp
       ftp_banner = "welcome to ftp"
       max_clients=<no>
:wq!
systemctl restart vsftpd
mkdir /etc/ftp/pub/files
chcon -t public_content_t "file(/.*)?"
setsebool -P ftpd_full_access=1
chmod 770 files
Client:
yum install -y ftp* lftp* filezilla(optional)
ftp <ip> or <hostname>
ftp > Is
   > get <filename> // downloading
   > put <file name> // uploading
  > mget f1 f2 // Multiple file get
  > buy
vim /etc/host.allow
vim /etc/host.deny
```

vim /etc/vsftpd/ftpusers

vim /etc/vsftpd/user_list

What is DHCP:

Dynamic Host configuration protocol assigns ip address to hosts. DHCP operations fall into four phases: (1) Discovery (2) Offer (3) Request (4) acknowledgement.

How does DHCP client find dhcp server?

The dhcp client discovers a DHCP server by broadcasting a discovery message to the limited broadcasting address on the local subnet. And if a router is present and configured to behave as Bootp relay agent, the request is passed to their DHCP servers on different subnets.

We have to use static NIC card parameter to configure dhcp server. and also close the vmware local dhcp server for dynamic NAT.

Broadcasting: In computer networking broadcasting refers to transmitting packet that will received by every device on the network.

For ex.: A radio station broadcasting a signal to many listeners, and digital t.v. subscriber receive signal that is broadcast by their T.V provider.

Firewall

- It allow certain packet which we want from authorized source or genuine application and it blocks the packet or communication from the unknown sources, In that manner it try to protect our system from unauthorized access of our services and resources.
- The service which control firewall is knows as firewalld.
- Firewall is a set of script and deamon that manages our netfilter.

Netfilter: Netfilter (kernel) is a framework provided by the Linux kernel that allows various networking related operations to be implemented in the form of customized handlers.

Zones: Is a set of pre-define rule that establish the security borders of a network. Whatever interface of the server in that zone those rule are apply for that interface.

/usr/lib/firewalld/services: Is the firewall services configuration file.

Rich Rule: Allow the administrator to specify custom rule for the zone.

```
firewall-cmd --get-active-zones // To show active zones
firewall-cmd --zone=home --list-all // To know about the rule of the zone.
firewall-cmd --zone=home --change-interface ens37 // To change the zone
firewall-cmd --zone=home --add-source=ip.addr // It allow every traffic from the host
firewall-cmd --get-zone-of-interface=ens33 // It display the specified device zone.
```

NAT (Network Address translation): Natting means that I am hiding my private id and if any request is going on to the network external sites it will be shown public id.

```
firewall-cmd --version // Check version of firewall firewall-cmd --get-zoneof-interface=ens33 //To check the zone of interface
```

Masquerade: Masquerading is assuming we have two network cards, moving traffic from one card to another card and in the process connecting two network. The other assumption is that we have an internal network with private ip address that we will change to an external address on the machine.

```
firewall-cmd --zone=<zone name> --add-masquerade //Add masquerade
firewall-cmd --zone=<zone name> --query-masquerade // Check masquerade status on particular zone
```

Masqurade should be on before port forwarding

```
firewall-cmd --permanent --zone=public \ "press enter" --add-forward-port=port=22:proto=tcp:toport=24 //lt redirect the incoming port 22 into the port 24
```

```
firewall-cmd --permanent --zone=public \ "press enter" --add-forward-port=port=22:proto=ssh:toaddr=<redirect ip addr> //It redirect the incoming portb 22 into the port 24
```

IP Addr + Port No. = Socket

Ip is an unique address which is provide for our machine.

port: port number is a unique id of a protocol in a computer network, all the protocol in a computer network are having a unique port number.

when our system is not connected with the internet still we have an ip which is 127.0.0.1, is nothing but our local host.

By using port host machine connect to the require protocol / services.

A port number is always associated with an IP address of a host and the protocol type of the communication. It completes the destination or origination network address of a message. specific port number are commonly reserved to identify specific services, so that an arriving packet can be easily forwarded to a running application.

Kerberos (KDC)

KDC: A key distribution centre is responsible for providing keys to users in a network that shares sensitive or private data.

- Each time a connection is established between two computers in a network, they both request to KDC to generate a unique password which can be used by the and system users for verification.
- The KDC system should be dedicated machine. The machine needs to be secure if possible, it should not run any services other than the KDC.

Confluence (Inventory Management): Store the server's information like ipaddress, name, console ip.

Jump Server: It used in linux as a gateway to access other Linux machines on a private network.

Server name Console Port Expansion name

1) DELL: DRAC or iDRAC: Dell Remote Access Control Integrated remote Access Controllers.

2) HP: ILO: Integrated Light Out (BL460)
3) IBM: HMC: Hardware Management Port

4) CISCO: CIMC

Why we need SSL Certificate or https

To encrypts the traffic between web server and user web browsers and enhance data security.

SSI: Secure Socket Layer
CSR: Certificate Sign Request
CA: Certificate Authority

CRT: Certificate Extension Name ".crt"

key: Key of the certificate "/etc/pki/tls/private/<domain name>.key"

TLS: Transport Layer Security

Virtual Host: Means using one Ip address to host, multiple websites or multiple websites hosting on same machine.

Web Server: The job of work server is accept request from client and send responses to those request. web server get a URL, translate it to a file name (For static requests) & send that file back over the internet from local hdd, or is translate it to a programe name (For dynamic request). ex: Ticket booking website changing is always going on, to connect the database and send the ouyput back to the request client.

In case webserver is not able to process requests or website is not available it will send error message.

- It controlled by the httpd daemon.
- Main configuration file /etc/httpd/conf/httpd.conf http:80 https:443

Quota

```
There are two types of quota: 1. Block Quota (Disk Quota) 2. Inode Quota (File Quota)

/dev/<disk name> // Create a partition

mkfs.file system <device> // Give file system

vim /etc/fstab // For permanent mount

<Device name> <Mount Point> <FileSystem> defaults,usrquota/grpquota 0 0 // XFS doesn't support quota

mount -o remount,usrquota /mnt/quota/ // Remount

usrquota: for user

grpquota: for group

quotacheck -cu <mountPoint> // To create quota database for user

quotaon <mount point>

edquota -u <username>

repquota -a // To display report of the quota.

edquota -t // To change the grace period.
```

Boot Process

There are 6 high level stages of a typical linux boot process.

BIOS: Basic I/O system executes MBR.

MBR: Master Boot record executes GRUB.

GRUB: Grand unified Bootloader Executes kernel.

Kernel: Kernel executes /sbin/init

init: Init executes run level programs

Run Level: Run level programs are executed from /etc/rc.d.rc*.d/

- 1. BIOS: Stand for Basic Input/output system.
 - Performs some system integrity checks.
 - Searches, load, and executes the boot loader program.
 - It looks for boot loader in hard drive, floppy, or cd-rom
 - Once the boot loader program is detected and loaded into the memory, BIOS gives the control to it.
 - So, in simple terms BIOS loads and executes the MBR boot loader.
- 2. MBR: Master Boot Record
 - It is located in the 1st sector of the bootable disk. Typical /dev/had, or /dev/sda
- MBR is less than 512 byte in size. This has three components a) primary boot loader info in 1st 446 bytes. b) partition table info in next 64 bytes. 3) MBR validation check in last 2

bytes.

- It contains information about GRUB.
- So in simple terms MBR loads and executes the GRUB boot loader.
- 3. GRUB: GRUB stand for grand unified bootloader.
 - If we have multiple kernel images installed on our system, then we can choose which one to be executed.
- GRUB displays a splash screen, waits for few seconds, if we don't enter anything. It we don't enter anythings it loads the default kernel image as specified in the grub configuration file.
 - GRUB configuration file is /boot/grub/grub.conf (/etc/grub.conf is a link to this.)

- So, in simple terms GRUB just loads and executes kernel and initrd images.
- 4. Kernel: Mounts the root file systems as specified in the "root=" in grub.conf
- Kernel execute the system program since system is the 1st program to be executed by linux kernel, it has process id(PID) of 1. Do a "ps –ef | grep init" and check the PID.
- initrd stands for initrd Ram Disk. Initrd is used by kernel as a temporary root file system utill kernel is booted and the root file system is mounted. It also contains necessary drivers compiled inside, which helps it to access the hard drive partitions, and other hardware.
- 5. systemd: Looks at the /etc/system file to decide the linux run level.
 - following are the available run levels.
 - 0 : halt / Info/shutdown.
 - 1 : Single user mode
 - 2 : multiuser without NFS.
 - 3 : Full multiuser mode.
 - 4 : Unused
 - 5 : GUI
 - -6: reboot

systemd identifies the defaults init level from /etc/inittab and uses that to load all appropriate programs. who -r : To check default run level.

- 6. run level programs: When the linux system is booting up, we might see various services getting started. For example it might say starting send mail..... ok. Those are the runlevel programs executed from the run level directory as defined by our run level.
- depending on our default init level setting. the system will execute the programs from one of the following directories.
 - Run level 0 /etc/rc.d/rc0.d/
 - Run level 1 /etc/rc.d/rc1.d/
 - Run level 2 /etc/rc.d/rc2.d/
 - Run level 3 /etc/rc.d/rc3.d/
 -
 - Run level 6 /etc/rc.d/rc6.d/
- There are also symbolic links available for these directory under /etc directory. So, /etc/rc0.d is linked to /etc/rc0.d
- Under the /etc/rc.d/rc*.d/ directories we would see programs that start with S and K.
- Programs starts with S are used during startup. S for startup.
- Programs starts with k are used during shutdown. K for kill
- There are numbers right next to S and K in the program names. Those are the sequence number in which the programs should be started to killed.
- For ex. S12 syslog is to start the syslog deamon, which has the sequence number of 12.

- S80 sendmail is to start the sendmail daemon, which has the sequence number of 80. So, syslog programs will be started before send mail.

Autofs

```
yum install -y autofs

vim /etc/auto.master
/root/mnt/samba /etc/auto.misc --timeoue=300

vim /etc/auto.misc
user_mount -fstype=cifs,multiuser,sec=ntlmssp,cred=/config/smb.txt :/192.168.86.131/S_Share
```

Logrotate

In IT log rotation is an automated process used in system administration in which log files are compressed, moved, renamed or deleted once they are too old or too big.

```
Conf File: /etc/logrotate.conf include /etc/logrotate.d
        vim /etc/logrotate.d/samba
               /var/log/samba {
                               daily
                               create 0644 root root
                               maxsize 1M
                               rotate 2
For forcefully rotate
logrotate -f /etc/logrotate.d/samba
## Custom log rotate file
vim custom
 /root/test/file {
                           // Here we specified the file location
 daily/monthly/weakly
                           // This is the rotate duration
 rotate 2
                           // 2 is the rotate number means how many file it makes
 create
                           // Create the file
}
```

logrotate -f /root/test/desktop/custom // This is the custom file location

Local Repo

```
Mount the CD or File.
mount /dev/sr0 /root/mnt/repo
cd /etc/yum.repos.d/ : move all repo file into another file
then, vim test.repo
       [test.repo]
       name = centos local repo
       baseurl = file:///root/mnt/repo
       enabled=1/0
       gpgcheck=0/1
       :wq!
Then try,
       yum remove httpd
       yum install httpd
                                         Reset/Change root password
1) Reboot
2) Press 'e' to edit grub configuration in boot menu.
3) rd.break then ctrl+x to continue
4) mount -oremont,rw /sysroot // It gives read write permission to the file sysroot.
5) chroot /sysroot // Change root into sysroot
6) then type passwd // command
7) touch /.autorelabel // The file carry autoreload when we reboot.
8) exit
9) exit
```

How to scan a harddisk

echo "---" > /sys/class/scsi host/host0 or host1 or host2/scan

To scan new harddisk where hostname may be different into different system.

"---" indicates "-= channel" "-= scsi target id" "-= lun"

How to flash or clear Ram

echo 1> /proc/sys/vm/drop_caches //To clear page cache only

echo 2> /proc/sys/vm/drop_caches // To clear dentries and inodes

echo 3> /proc/sys/vm/drop_caches //To clear cache, dentries & inode ##This is not recommend to run

SELinux

Security Enhance Linux (SELinux) is a security that enhance security that allows users and administrator more control over which applications and users can access which resources such as file.

If httpd or apache is compromised then attacker could access of file and folder qwned that have rw, permission for apache, that means anythings in web serving traffic.

If the SELinux on then the risk is limited to the compromised directories, files, services.

- 1. Document Root: It is a location of file which are accessible by clients. By default all request taken from this directory "/var/www/html".
- 2. ServerRoot: It simplfy where is web server are install. /etc/httpd
- 3. CGI (Common Gateway Interface): CGI is an interface between web client and web server.
- 4. Scripts Alias: The control which directory control script server /var/www/cgi_bin
- 5. TLS: Transport layer Security is a upper Layer protocol (ULP) that runs over TCP.

- 6. Http: Http/Https are used to transfer hyper text documents on the www or http is the protocol used to transfer data over the web.
- 7. Httpd: Is a software program that runs in the background of a web server and wait for incoming server requests. The daemon answers the request automatically.
- 8. DNS (Domain name system): DNS is a larger database which resides on various computers that contains the names and ip address of various hosts/domain.
- 9. NFS: Network file system is a way of mounting linux directories over a network. The main use of NFS is to share out data on a central server to all the PCS In the network.
- 10. SELinux: Security enhanced linux is a set of security policies which are going to apply on the machine to improve the overall security of the machine.
- 11. Bin(Binary): /bin contains the executable (i.e. ready to run) programs that must be available in order to attain minimal functionality for the purpose of booting (i.e. starting) and repairing a system.
- 12. Repository (repo): Is a storage location or contain the configuration of repos (i.e. disk location / web location) of disk or web from which our system retrives and install OS updates and applications.

 Each repository is a collection of software hosted on remote server and intended to be used for installing and updating software packages on linux.
- 13. SELinux Context: Is the mechanism used by SELinux to classify resources, such as files, on a SELinux-enabled system.
- 14. Boolean: Is a conditional rule that allows run time modification of the security policy without having to load a new policy.
- 15. Port : A port is a logical entity which acts as a endpoints of communication to identify a given process or application.

(It is a 16 bit number 0-65535)

- 16. gpgcheck : gpgcheck stands for signature verification from the central database. If signature verification is successful then we sure about the security if we set the value of gpgcheck is ! then it ask for signature verification else it doesnot.
- 17. / The root directory: Everything on our Linux system is located under the / directory, known as root directory.
- 18. /bin Essential user binaries: The /bin directory contain the essential user binaries 9Program) that must be present when the system in mounted in single-user mode.
- 19. /boot static boot files; The /boot directory contains the files needed to boot the system. like GRUB boot loader's files and our linux kernels are stored here.
- 20. /cdrom Historical mount point for CD-Roms: It is temporary location for CD-Roms inserted in the system.

- 21. /dev device file; Linux expose devices as files, and the /dev dir contains number of specified files that represent device.
- 22. /etc configuration file : the /etc directory contains configuration files, which can generally be edited by hand in a text editor.
- 23. /home Home folders: The /home dir contains a home folder for each user.
- 24. /lib- Essential shared libraries: The / lib dir contains libraries needed by the essential binaries in the /bin and /sbin folder.
- 25. /lost+found Recovery files
- 26. /media Removable media
- 27. /mnt Temporary mount point
- 28. /opt Optional packages
- 29. /proc kernel & process
- 30. /root root home dir
- 31. /run Applicatio state files
- 32. /sbin System administration Binaries
- 33. /selinux SELinux virtual file system
- 34. /srv Service data
- 35. /tmp Temporary files
- 36. /usr Use binaries & Read-only data
- 37. /var Variable data file
- 38. demon: Gives service to the process.
- 39. Kernel: Establish relationship between hardware and software.
- 40. dmidecode : desktop management interface table decoder "Retrives system hardware related information such as processor, RAM, BIOS details, Memory."
- 41. /root: It is root user home directory
- 42. /etc: It contains all system configuration files for linux.
- 43. /opt: This file system holds additional software installed on the system.
- 44. /bin: It contains command used by all users.
- 45. /sbin: It contains commands used by root user.

- 46. /var: contains data that frequently changes while the system is operational.
- 47. /proc : It contain process file.

server.hp.com <hostname> <Domain name> <Fully Qualified Domain Name>

Logical Volume management (LVM)

LVM means the combination of 2 or more physical disk in order to make a big logical disk.

- S1. Create / Delete a hard disk.
- S2. Make partition using fdisk and gdisk in the partition time give the partition label linux LVM '8e00' in gdisk '8e' in fdisk.
- S3. Create Physical volumes
 ## pvcreate /dev/sdb1 /dev/sdc1
 ## pvdisplay ; To display physical group
- S4. Create Volume group
 ## vgcreate <vg name> /dev/sdb1 /dev/sdc
 ## vgdisplay : To display the volume group
- S5. Create logical volume
 ## lvcreate -n <lv name> -L <size> <vgname>
 ## lvdisplay : To display logical volume
- S6. Then make file system of the LV. ## mkfs -t xfs <lv name>
- S7. Then mount the device to any directory ## mount /dev/vg/lv /mnt/mymount

For remove

1st unmount the file system, then lyremove then vgremove and then pyremove.

How many types of files.

-- device file, symbolic file, regular file, network file, binary file, executable file.

Port Numbers

- 1. 21 FTP
- 2. 22 SSH
- 3. 23 TELNET
- 4. 25 SMTP (Send mail)
- 5. 53 Domain (DNS)
- 6. 80 HTTP
- 7. 443 HTTPS
- 8. 110 POP3
- 9. 143 IMAP
- 10. 631 PRINTER
- 11. 2049 NFS Server
- 12. 1028 NFS Client
- 13. 3260 ISCSI_lqn
- 14. DHCP server 67
- 15. DHCP Client 68
- 16. Backup port no. 13782
- 17. NTP 123
- 18. 139 Samba Port Number: To establish connection
- 19. 137 Samba Port Number: To verify share name
- 20. 138 Samba Port Number: To data transfer
- 21. 445 Samba Port Number: For Authentication