API Changes

Content

- InputController class
- PaintManager class
- Brush class
- BasePaintObject class
- BasePaintTool class
- AverageColorCalculator class

InputController class

public bool IsVRMode field was moved to Settings class. To set VR mode, use the
following code: Settings.Instance.IsVRMode = value;.

PaintManager class

```
public bool ShouldOverrideCamera field was renamed to OverrideCamera and
moved to PaintController class;

public Camera Camera { ... } property was moved to PaintController class;

public event InitHandler OnInitialized signature was changed to public event
Action<PaintManager> OnInitialized;

public event DisposeHandler OnDisposed signature was changed to public
event Action OnDisposed;

public bool CopySourceTextureToPaintTexture field was renamed to
CopySourceTextureToLayer;

public void Bake() method was removed;
```

Brush class

```
public event ChangeColorHandler OnChangeColor() signature and name were
changed to: public Action < Color > On Color Changed;
    public event ChangeTextureHandler OnChangeTexture() signature and name
were changed to: public Action<Texture> OnTextureChanged;
    public Vector2 SourceTextureSize field was removed. To get texture size, use
SourceTexture.width/height fields.
BasePaintObject class
    public event PaintDataHandler (BasePaintObject sender, Vector2
paintPosition, float brushSize, float pressure, Color brushColor,
PaintTool tool) was removed;
    public event PaintHandler (BasePaintObject sender, Vector2
paintPosition, float pressure) was removed;
    public event TexturesKeeperHandler OnUndoHandler was removed, use
PaintManager.StatesController.OnUndo event instead;
    public event TexturesKeeperHandler OnRedoHandler was removed, use
PaintManager.StatesController.OnRedo event instead;
    public delegate void MouseUVHandler (BasePaintObject sender, Vector2
uv, Vector2 paintPosition, float pressure) signature was changed to:
Action<Vector2, Vector2, Vector2, float>;
    public delegate void DrawPointHandler (BasePaintObject sender, Vector2
position, float pressure) signature was changed to: Action < Vector 2, float >;
    public delegate void DrawLineHandler (BasePaintObject sender, Vector2
```

position, float pressure) signature was changed to: Action<Vector2, float>;
 public delegate void DrawLineHandler (BasePaintObject sender, Vector2
lineStartPosition, Vector2 lineEndPosition, float lineStartPressure, float
lineEndPressure) signature was changed to: Action<Vector2, Vector2, float, float>;
 public void RenderCombined() was removed, use Render() method instead;
 public void ClearTexture(bool writeToUndo=false) was removed, use
BrushTool.FillWithColor(Color.clear) method instead;

public TextureKeeper TextureKeeper get { ... } was removed, use
PaintManager.StatesController property instead.

BasePaintTool class

```
public void UpdateHover (BasePaintObject sender, Vector2 uv, Vector2
paintPosition, float pressure) signature was changed to: public void UpdateHover
(Vector2 screenPosition, Vector2 uv, Vector2 paintPosition, float
pressure);
   public void UpdateDown (BasePaintObject sender, Vector2 uv, Vector2
paintPosition, float pressure) signature was changed to: public void UpdateDown
```

(Vector2 screenPosition, Vector2 uv, Vector2 paintPosition, float
pressure);
 public void UpdatePress (BasePaintObject sender, Vector2 uv, Vector2
paintPosition, float pressure) signature was changed to: public void UpdatePress

(Vector2 screenPosition, Vector2 uv, Vector2 paintPosition, float pressure);

public void UpdateUp (BasePaintObject sender, bool inBounds) signature
was changed to: public void UpdateUp (Vector2 screenPosition, bool inBounds);

public void OnDrawPreProcess (BasePaintObject sender, CommandBuffer

commandBuffer, RenderTargetIdentifier rti, Material material) signature was
changed to: public void OnDrawPreProcess (RenderTargetIdentifier combined);

public void OnDrawProcess (BasePaintObject sender, CommandBuffer
commandBuffer, RenderTargetIdentifier rti, Material material) signature was
changed to: public void OnDrawProcess (RenderTargetIdentifier combined);

public void OnBakeInputToPaint (BasePaintObject sender, CommandBuffer commandBuffer, RenderTargetIdentifier rti, Material material) signature and name were changed to: public void OnBakeInputToLayer (RenderTargetIdentifier activeLayer);

public void OnPaint (BasePaintObject sender, Vector2 paintPosition,
float pressure) was removed;

public void void OnUndo (BasePaintObject sender) was removed;

```
public void void OnRedo (BasePaintObject sender) was removed;
public virtual bool RenderToPaintTexture { ... } was renamed to

RenderToLayer;
public virtual bool RenderToInputTexture { ... } was renamed to

RenderToInput;
public virtual bool DrawPreview { ... } was removed;
protected PaintManager PaintManager { ... } was removed, now all data for tool is
available in Data field.
```

AverageColorCalculator class

event ColorHandler OnGetAverageColor() signature was changed to: public
event Action<Color> OnGetAverageColor().

Please let me know if you have any questions.

E-mail: unitymedved@gmail.com