## Cisco Cheat Sheet

# Basic Configuration Initial Commands

Name the device:

Router# configure terminal

Router(config)# hostname [hostname]

Configure a banner:

R1(config)# banner motd \$Autorized Access Only\$

Save the Changes:

R1# copy running-config startup-config

Configure Interface IPv4:

R1(config)# interface gigabitethernet 0/0

R1(config-if)# description Link to LAN 1

R1(config-if)# ip address 192.168.10.1 255.255.255.0

R1(config-if)# no shutdown

-*or*-

R1(config)# interface serial 0/0/0

R1(config-if)# description Link to R2

R1(config-if)# ip address 209.165.200.225 255.255.255.252

R1(config-if)# clock rate 128000

R1(config-if)# no shutdown

#### Secure Management Access

R1(config)# enable secret class

R1(config)# line console 0

R1(config-line)# password cisco

R1(config-line)# login

R1(config-line)# exit

R1(config)# line vtv 0 4  $\leftarrow$  depending on the number of VTYs!

R1(config-line)# password cisco

R1(config-line)# login

R1(config-exit)# exit
R1(config)# service password-encryption

#### VLAN

#### Access Control Lists

This chapter describes how to configure Access Control Lists (ACLs).

Note! Each ACL contains an implicit DENY at the end!

## **Spanning Tree**

This chapter describes how to configure Spanning Tree.

# Link Aggregation

This chapter describes how to configure port channels and to apply and configure the Link Aggregation Control Protocol (LACP).

#### Configure Interfaces

```
s1(config)# interface range fe0/1-2
s1(config-if-range)# shutdown
s1(config-if-range)# channel-group 1 mode active
s1(config-if-range)# exit
s1(config)# interface port-channel 1
s1(config-if)# switchport mode trunk
s1(config-if)# switchport trunk allowed vlan 1,2,20
```

#### Verify Link Aggregation s1# show interface port-channel1

```
s1# show etherchannel summary
s1# show etherchannel port-channel
s1# show interfaces f0/1 etherchannel
More information about Link Aggregation Control Protocol (LACP)
(802.3ad) for Gigabit Interfaces.
```

#### **OSPF**

This chapter describes how to configure OSPF.

## Single-Area OSPF

```
R1(config)# interface GigabitEthernet0/0
R1(config-if)# bandwidth 1000000
R1(config-if)# exit
R1(config)# router ospf 10
R1(config-router)# router-id 1.1.1.1
R1(config-router)# auto-cost reference-bandwidth 1000
R1(config-router)# network 172.16.1.0 0.0.0.255 area 0
R1(config-router)# passive-interface g0/0
```

## Single-Area OSPFv3

```
R1(config)# ipv6 router ospf 10
R1(config-router)# router-id 1.1.1.1
R1(config-router)# auto-cost reference-bandwidth 1000
R1(config-if)# interface GigabitEthernet 0/0
R1(config-if)# bandwidth 1000000
R1(config-if)# ipv6 ospf 10 area 0
```

## Verifying Single-Area OSPF

```
Note: to verify Single-Area OSPFv3 please use the ipv6 command R1# show ip ospf neighbor R1# show ip protocols R1# show ip ospf R1# show ip ospf interface R1# show ip ospf interface brief
```

#### Multi-Area OSPF

https://github.com/roaldnefs/cisco-cheatsheet