COMP1521 21T2 — Integers

https://www.cse.unsw.edu.au/~cs1521/21T2/

10 types of students

There are only 10 types of students ...

- those that understand binary
- those that don't understand binary

Decimal Representation

• Can interpret decimal number 4705 as:

$$4 \times 10^3 + 7 \times 10^2 + 0 \times 10^1 + 5 \times 10^0$$

- The base or radix is $10 \dots$ digits 0 9
- Place values:

 1000	100	10	1
 10^{3}	10^{2}	10^{1}	10^{0}

- \bullet Write number as 4705_{10}
 - Note use of subscript to denote base

Representation in Other Bases

- base 10 is an arbitrary choice
- can use any base
- e.g. could use base 7
- Place values:

...
$$343$$
 49 7 1 ... 7^3 7^2 7^1 7^0

ullet Write number as 1216_7 and interpret as:

$$1 \times 7^3 + 2 \times 7^2 + 1 \times 7^1 + 6 \times 7^0 == 454_{10}$$

Binary Representation

- Modern computing uses binary numbers
 - because digital devices can easily produce high or low level voltages which can represent 1 or 0.
- The base or radix is 2 Digits 0 and 1
- Place values:

 \bullet Write number as 1011_2 and interpret as:

$$1 \times 2^3 + 0 \times 2^2 + 1 \times 2^1 + 1 \times 2^0 == 11_{10}$$

Hexadecimal Representation

- Binary numbers hard for humans to read too many digits!
- Conversion to decimal awkward and hides bit values
- Solution: write numbers in hexadecimal!
- The base or radix is 16 ... digits 0, 1, 2, 3, 4, 5, 6, 7, 8, 9, A, B, C, D, E, F
- Place values:

...
$$4096$$
 256 16 1 ... 16^3 16^2 16^1 16^0

 \bullet Write number as $3AF1_{16}$ and interpret as:

$$3 \times 16^3 + 10 \times 16^2 + 15 \times 16^1 + 1 \times 16^0 == 15089_{10}$$

• in C, 0x prefix denotes hexadecimal, e.g. 0x3AF1

Octal & Binary C constants

- Octal (based 8) representation used to be popular for binary numbers
- Similar advantages to hexadecimal
- in C a leading 0 denotes octal, e.g. 07563
- standard C doesn't have a way to write binary constants
- some C compilers let you write **0b**
 - OK to use **9b** in experimental code but don't use in important code

Binary Constants

In hexadecimal, each digit represents 4 bits

In octal, each digit represents 3 bits

In binary, each digit represents 1 bit

0b010010001111101010111110010010111

Binary to Hexadecimal

 \bullet Example: Convert 10111111000101001_2 to Hex:

 \bullet Example: Convert 101111010111100_2 to Hex:

Hexadecimal to Binary

- Reverse the previous process ...
- Convert each hex digit into equivalent 4-bit binary representation
- ullet Example: Convert $AD5_{16}$ to Binary:

Representing Negative Integers

- modern computers almost always use two's complement to represent integers
- positive integers and zero represented in obvious way
- negative integers represented in clever way to make arithmetic in silicon fast/simpler
- for an n-bit binary number the representation of -b is 2^n-b
- $\bullet\,$ e.g. in 8-bit two's complement -5 is represented as 2^8-5 == 11111011_2

Code example: printing all 8 bit twos complement bit patterns

• Some simple code to examine all 8 bit twos complement bit patterns.

```
for (int i = -128; i < 128; i++) {
    printf("%4d ", i);
    print_bits(i, 8);
    printf("\n");
}</pre>
```

source code for 8 bit twos complement.c

```
$ dcc 8_bit_twos_complement.c print_bits.c -o 8_bit_twos_complement
```

source code for print_bits.c source code for print_bits.h

```
$ ./8_bit_twos_complement
-128 10000000
-127 10000001
-126 10000010
. . .
  -3 11111101
  -2 11111110
  -1 11111111
    00000000
   1 00000001
   2 00000010
   3 00000011
 125 01111101
 126 01111110
 127 01111111
```

```
int a = 0;
printf("Enter an int: ");
scanf("%d", &a);
// sizeof returns number of bytes, a byte has 8 bits
int n_bits = 8 * sizeof a;
print_bits(a, n_bits);
printf("\n");
source code for print bits of int.c
$ dcc print_bits_of_int.c print_bits.c -o print_bits_of_int
$ ./print bits of int
Fnter an int: 42
$ ./print_bits_of_int
Enter an int: -42
```

11111111111111111111111111111111

```
$ ./print_bits_of_int
Enter an int: 0
$ ./print_bits_of_int
Enter an int: 1
$ ./print_bits_of_int
Fnter an int: -1
11111111111111111111111111111111111
$ ./print_bits_of_int
Enter an int: 2147483647
$ ./print bits of int
Enter an int: -2147483648
```

Bits in Bytes in Words

- Many hardware operations works with bytes: 1 byte == 8 bits
- C's **sizeof** gives you number of bytes used for variable or type
- sizeof variable returns number of bytes to store variable
- sizeof (type) returns number of bytes to store type
- On CSE servers, C types have these sizes
 - char = 1 byte = 8 bits, 42 is 00101010
 - short = 2 bytes = 16 bits, 42 is 000000000101010

 - double = 8 bytes = 64 bits, 42 = ?
- above are common sizes but not universal on a small embedded CPU sizeof (int) might be 2 (bytes)

Code example: integer_types.c - exploring integer types

We can use **sizeof** and **limits.h** to explore the range of values which can be represented by standard C integer types **on our machine**...

```
$ dcc integer_types.c -o integer_types
$ ./integer_types
             Type Bytes Bits
             char
                           8
      signed char 1
                           8
    unsigned char 1
                         16
            short
                        16
   unsigned short
              int
                  4 32
                          32
     unsigned int
             long
                          64
    unsigned long
                          64
         long long
                          64
unsigned long long
                          64
```

Code example: integer_types.c - exploring integer types

Туре	Min	Max
char	-128	127
signed char	-128	127
unsigned char	Θ	255
short	-32768	32767
unsigned short	Θ	65535
int	-2147483648	2147483647
unsigned int	Θ	4294967295
long	-9223372036854775808	9223372036854775807
unsigned long	Θ	18446744073709551615
long long	-9223372036854775808	9223372036854775807
unsigned long long	0	18446744073709551615

source code for integer_types.c

stdint.h - integer types with guaranteed sizes

#include <stdint.h>

- to get below integer types (and more) with guaranteed sizes
- we will use these heavily in COMP1521

```
// range of values for type
                           minimum
                                                 maximum
int8_t i1; //
                              -128
                                                     127
uint8 t i2; //
int16 t i3; //
                            -32768
                                                   32767
uint16 t i4: //
                                                   65535
int32 t i5: //
                       -2147483648
                                              2147483647
uint32 t i6: //
                                              4294967295
int64_t i7; // -9223372036854775808 9223372036854775807
uint64 t i8: //
                                  0 18446744073709551615
```

source code for stdint.c

Code example: char_bug.c

Common C bug:

```
char c; // c should be declared int
while ((c = getchar()) != EOF) {
   putchar(c);
}
```

Typically stdio.h contains:

```
#define EOF -1
```

- most platforms: char is signed (-128..127)
 - loop will incorrectly exit for a byte containing 0xFF
- rare platforms: char is unsigned (0..255)

• loop will never exit