

Red Hat Enterprise Linux 9

Automating system administration by using RHEL system roles

Consistent and repeatable configuration of RHEL deployments across multiple hosts with Red Hat Ansible Automation Platform playbooks

Last Updated: 2025-05-20

Red Hat Enterprise Linux 9 Automating system administration by using RHEL system roles

Consistent and repeatable configuration of RHEL deployments across multiple hosts with Red Hat Ansible Automation Platform playbooks

Legal Notice

Copyright © 2025 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

http://creativecommons.org/licenses/by-sa/3.0/

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java [®] is a registered trademark of Oracle and/or its affiliates.

XFS [®] is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL ® is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack [®] Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

The Red Hat Enterprise Linux (RHEL) system roles are a collection of Ansible roles, modules, and playbooks that help automate the consistent and repeatable administration of RHEL systems. With RHEL system roles, you can efficiently manage large inventories of systems by running configuration playbooks from a single system.

Table of Contents

| PROVIDING FEEDBACK ON RED HAT DOCUMENTATION | 7 |
|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------|
| CHAPTER 1. INTRODUCTION TO RHEL SYSTEM ROLES | 8 |
| CHAPTER 2. PREPARING A CONTROL NODE AND MANAGED NODES TO USE RHEL SYSTEM ROLES 2.1. PREPARING A CONTROL NODE ON RHEL 9 2.2. PREPARING A MANAGED NODE | 10 10 12 |
| CHAPTER 3. ANSIBLE VAULT | 15 |
| CHAPTER 4. JOINING RHEL SYSTEMS TO AN ACTIVE DIRECTORY BY USING RHEL SYSTEM ROLES 4.1. JOINING RHEL TO AN ACTIVE DIRECTORY DOMAIN BY USING THE AD_INTEGRATION RHEL SYSTEM ROLE | 18 |
| CHAPTER 5. CONFIGURING THE GRUB BOOT LOADER BY USING RHEL SYSTEM ROLES | 21 E 21 |
| 5.3. SETTING A TIMEOUT FOR THE BOOT LOADER MENU BY USING THE BOOTLOADER RHEL SYSTEM ROLE | 2325 |
| 5.4. COLLECTING THE BOOT LOADER CONFIGURATION INFORMATION BY USING THE BOOTLOADER RHEL SYSTEM ROLE | 28 |
| 6.1. REQUESTING A NEW CERTIFICATE FROM AN IDM CA BY USING THE CERTIFICATE RHEL SYSTEM ROL | 30 _E 30 |
| | 35 35 |
| 8.1. ENHANCING SECURITY WITH THE FUTURE CRYPTOGRAPHIC POLICY USING THE CRYPTO_POLICIES | 37 37 |
| CHAPTER 9. RESTRICTING THE EXECUTION OF APPLICATIONS BY USING THE FAPOLICYD RHEL SYSTE ROLE 9.1. PREVENTING USERS FROM EXECUTING UNTRUSTWORTHY CODE BY USING THE FAPOLICYD RHEL SYSTEM ROLE | |
| 10.1. RESETTING THE FIREWALLD SETTINGS BY USING THE FIREWALL RHEL SYSTEM ROLE 10.2. FORWARDING INCOMING TRAFFIC IN FIREWALLD FROM ONE LOCAL PORT TO A DIFFERENT LOCA PORT BY USING THE FIREWALL RHEL SYSTEM ROLE | 43 43 L 44 46 |
| 11.1. VARIABLES OF THE HA_CLUSTER RHEL SYSTEM ROLE 11.2. SPECIFYING AN INVENTORY FOR THE HA_CLUSTER RHEL SYSTEM ROLE 11.3. CREATING PCSD TLS CERTIFICATES AND KEY FILES FOR A HIGH AVAILABILITY CLUSTER 11.4. CONFIGURING A HIGH AVAILABILITY CLUSTER RUNNING NO RESOURCES 11.5. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH FENCING AND RESOURCES 11.6. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH RESOURCE AND RESOURCE OPERATION | 48 48 71 72 74 76 |

| 11.7. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH FENCING LEVELS | 82 |
|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------|
| 11.8. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH RESOURCE CONSTRAINTS | 85 |
| 11.9. CONFIGURING COROSYNC VALUES IN A HIGH AVAILABILITY CLUSTER | 89 |
| 11.10. EXPORTING A CLUSTER CONFIGURATION TO CREATE A RHEL SYSTEM ROLE PLAYBOOK | 92 |
| 11.11. CONFIGURING A HIGH AVAILABILITY CLUSTER THAT IMPLEMENTS ACCESS CONTROL LISTS (A BY USING THE HA_CLUSTER RHEL SYSTEM ROLE | CLS) 95 |
| 11.12. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH SBD NODE FENCING BY USING THE HA_CLUSTER_NODE_OPTIONS VARIABLE | 98 |
| 11.13. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH SBD NODE FENCING BY USING THE HA_CLUSTER VARIABLE | 101 |
| 11.14. CONFIGURING A PLACEMENT STRATEGY FOR A HIGH AVAILABILITY CLUSTER BY USING THE R | |
| HA_CLUSTER RHEL SYSTEM ROLE 11.15. CONFIGURING ALERTS FOR A HIGH AVAILABILITY CLUSTER BY USING THE HA_CLUSTER RHEL | 105 |
| SYSTEM ROLE | 108 |
| 11.16. CONFIGURING A HIGH AVAILABILITY CLUSTER USING A QUORUM DEVICE | 111 |
| 11.16.1. Configuring a quorum device | 112 113 |
| 11.16.2. Configuring a cluster to use a quorum device 11.17. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH NODE ATTRIBUTES | 115 |
| 11.18. CONFIGURING AN APACHE HTTP SERVER IN A HIGH AVAILABILITY CLUSTER WITH THE HA CLU | |
| RHEL SYSTEM ROLE | 117 |
| CHAPTER 12. CONFIGURING THE SYSTEMD JOURNAL BY USING RHEL SYSTEM ROLES 12.1. CONFIGURING PERSISTENT LOGGING BY USING THE JOURNALD RHEL SYSTEM ROLE | 123 123 |
| CHAPTER 13. CONFIGURING AUTOMATIC CRASH DUMPS BY USING RHEL SYSTEM ROLES | 125 |
| 13.1. CONFIGURING THE KERNEL CRASH DUMPING MECHANISM BY USING THE KDUMP RHEL SYSTEM ROLE | 125 |
| CHAPTER 14. CONFIGURING KERNEL PARAMETERS PERMANENTLY BY USING RHEL SYSTEM ROLES | S 127 |
| 14.1. APPLYING SELECTED KERNEL PARAMETERS BY USING THE KERNEL_SETTINGS RHEL SYSTEM F | |
| | 127 |
| CHAPTER 15. CONFIGURING LOGGING BY USING RHEL SYSTEM ROLES | 129 |
| 15.1. FILTERING LOCAL LOG MESSAGES BY USING THE LOGGING RHEL SYSTEM ROLE | 129 |
| 15.2. APPLYING A REMOTE LOGGING SOLUTION BY USING THE LOGGING RHEL SYSTEM ROLE | 131 |
| 15.3. USING THE LOGGING RHEL SYSTEM ROLE WITH TLS | 134 |
| 15.3.1. Configuring client logging with TLS | 135 |
| 15.3.2. Configuring server logging with TLS | 137 |
| 15.4. USING THE LOGGING RHEL SYSTEM ROLES WITH RELP | 140 |
| 15.4.1. Configuring client logging with RELP | 140 |
| 15.4.2. Configuring server logging with RELP | 143 |
| CHAPTER 16. CONFIGURING PERFORMANCE MONITORING WITH PCP BY USING RHEL SYSTEM ROL | ES 146 |
| 16.1. CONFIGURING PERFORMANCE CO-PILOT BY USING THE METRICS RHEL SYSTEM ROLE | 146 |
| 16.2. CONFIGURING PERFORMANCE CO-PILOT WITH AUTHENTICATION BY USING THE METRICS RHI SYSTEM ROLE | EL 147 |
| 16.3. SETTING UP GRAFANA BY USING THE METRICS RHEL SYSTEM ROLE TO MONITOR MULTIPLE H WITH PERFORMANCE CO-PILOT | |
| 16.4. CONFIGURING WEB HOOKS IN PERFORMANCE CO-PILOT BY USING THE METRICS RHEL SYSTE | |
| ROLE | 152 |
| CHAPTER 17. CONFIGURING NBDE BY USING RHEL SYSTEM ROLES | 155 |
| 17.1. USING THE NBDE_SERVER RHEL SYSTEM ROLE FOR SETTING UP MULTIPLE TANG SERVERS | 155 |
| 17.2. SETTING UP CLEVIS CLIENTS WITH DHCP BY USING THE NBDE_CLIENT RHEL SYSTEM ROLE 17.3. SETTING UP STATIC-IP CLEVIS CLIENTS BY USING THE NBDE_CLIENT RHEL SYSTEM ROLE | 156 158 |
| The state of the s | .55 |

| CHAPTER 18. CONFIGURING NETWORK SETTINGS BY USING RHEL SYSTEM ROLES | 161 |
|-------------------------------------------------------------------------------------------------------------------------------|-------------|
| 18.1. CONFIGURING AN ETHERNET CONNECTION WITH A STATIC IP ADDRESS BY USING THE NETWOR RHEL SYSTEM ROLE WITH AN INTERFACE NAME | K 161 |
| 18.2. CONFIGURING AN ETHERNET CONNECTION WITH A STATIC IP ADDRESS BY USING THE NETWOR RHEL SYSTEM ROLE WITH A DEVICE PATH | RK 163 |
| 18.3. CONFIGURING AN ETHERNET CONNECTION WITH A DYNAMIC IP ADDRESS BY USING THE NETW RHEL SYSTEM ROLE WITH AN INTERFACE NAME | ORK 165 |
| 18.4. CONFIGURING AN ETHERNET CONNECTION WITH A DYNAMIC IP ADDRESS BY USING THE NETW RHEL SYSTEM ROLE WITH A DEVICE PATH | ORK 168 |
| 18.5. CONFIGURING A STATIC ETHERNET CONNECTION WITH 802.1X NETWORK AUTHENTICATION BY USING THE NETWORK RHEL SYSTEM ROLE | |
| 18.6. CONFIGURING A WIFI CONNECTION WITH 802.1X NETWORK AUTHENTICATION BY USING THE NETWORK RHEL SYSTEM ROLE | 173 |
| 18.7. CONFIGURING A NETWORK BOND BY USING THE NETWORK RHEL SYSTEM ROLE | 175 |
| 18.8. CONFIGURING VLAN TAGGING BY USING THE NETWORK RHEL SYSTEM ROLE | 177 |
| 18.9. CONFIGURING A NETWORK BRIDGE BY USING THE NETWORK RHEL SYSTEM ROLE | 179 |
| 18.10. SETTING THE DEFAULT GATEWAY ON AN EXISTING CONNECTION BY USING THE NETWORK RH SYSTEM ROLE | |
| 18.11. CONFIGURING A STATIC ROUTE BY USING THE NETWORK RHEL SYSTEM ROLE | 183 |
| 18.12. ROUTING TRAFFIC FROM A SPECIFIC SUBNET TO A DIFFERENT DEFAULT GATEWAY BY USING T NETWORK RHEL SYSTEM ROLE | HE 185 |
| 18.13. CONFIGURING AN ETHTOOL OFFLOAD FEATURE BY USING THE NETWORK RHEL SYSTEM ROLE | 190 |
| 18.14. CONFIGURING AN ETHTOOL COALESCE SETTINGS BY USING THE NETWORK RHEL SYSTEM RO | LE 192 |
| 18.15. INCREASING THE RING BUFFER SIZE TO REDUCE A HIGH PACKET DROP RATE BY USING THE NETWORK RHEL SYSTEM ROLE | 193 |
| 18.16. CONFIGURING AN IPOIB CONNECTION BY USING THE NETWORK RHEL SYSTEM ROLE | 195 |
| 18.17. NETWORK STATES FOR THE NETWORK RHEL SYSTEM ROLE | 198 |
| CHAPTER 19. MANAGING CONTAINERS BY USING RHEL SYSTEM ROLES | 200 |
| 19.1. CREATING A ROOTLESS CONTAINER WITH BIND MOUNT BY USING THE PODMAN RHEL SYSTEM | ROLE 200 |
| 19.2. CREATING A ROOTFUL CONTAINER WITH PODMAN VOLUME BY USING THE PODMAN RHEL SYS' ROLE | TEM 202 |
| 19.3. CREATING A QUADLET APPLICATION WITH SECRETS BY USING THE PODMAN RHEL SYSTEM RO | LE 204 |
| CHAPTER 20. CONFIGURING POSTFIX MTA BY USING RHEL SYSTEM ROLES | 207 |
| 20.1. CONFIGURING POSTFIX AS A NULL CLIENT FOR ONLY SENDING OUTGOING EMAILS | 207 |
| CHAPTER 21. INSTALLING AND CONFIGURING A POSTGRESQL DATABASE SERVER BY USING RHEL SYSTEM ROLES | 210 |
| 21.1. CONFIGURING POSTGRESQL WITH AN EXISTING TLS CERTIFICATE BY USING THE POSTGRESQL RHEL SYSTEM ROLE | 210 |
| 21.2. CONFIGURING POSTGRESQL WITH A TLS CERTIFICATE ISSUED FROM IDM BY USING THE POSTGRESQL RHEL SYSTEM ROLE | 213 |
| CHAPTER 22. REGISTERING THE SYSTEM BY USING RHEL SYSTEM ROLES | 218 |
| 22.1. REGISTERING A SYSTEM BY USING THE RHC RHEL SYSTEM ROLE | 218 |
| 22.2. REGISTERING A SYSTEM WITH SATELLITE BY USING THE RHC RHEL SYSTEM ROLE | 220 |
| 22.3. DISABLING THE CONNECTION TO INSIGHTS AFTER THE REGISTRATION BY USING THE RHC RHE | L |
| SYSTEM ROLE | 221 |
| 22.4. MANAGING REPOSITORIES BY USING THE RHC RHEL SYSTEM ROLE | 222 |
| 22.5. LOCKING THE SYSTEM TO A PARTICULAR RELEASE BY USING THE RHC RHEL SYSTEM ROLE | 224 |
| 22.6. USING A PROXY SERVER WHEN REGISTERING THE HOST BY USING THE RHC RHEL SYSTEM ROL | .E |

| | 225 |
|----------------------------------------------------------------------------------------------------|--------------|
| 22.7. MANAGING AUTO UPDATES OF INSIGHTS RULES BY USING THE RHC RHEL SYSTEM ROLE | 226 |
| 22.8. CONFIGURING INSIGHTS REMEDIATIONS BY USING THE RHC RHEL SYSTEM ROLE | 228 |
| 22.9. CONFIGURING INSIGHTS TAGS BY USING THE RHC RHEL SYSTEM ROLE | 229 |
| 22.10. UNREGISTERING A SYSTEM BY USING THE RHC RHEL SYSTEM ROLE | 231 |
| | |
| CHAPTER 23. REMOTE MANAGEMENT WITH IPMI AND REDFISH BY USING THE RHEL_MGMT COLLEC | CTION 233 |
| 23.1. SETTING THE BOOT DEVICE BY USING THE RHEL_MGMT.IPMI_BOOT MODULE | 233 |
| 23.2. SETTING THE SYSTEM POWER STATE BY USING THE RHEL_MGMT.IPMI_POWER MODULE | 235 |
| 23.3. MANAGING OUT-OF-BAND CONTROLLERS BY USING THE RHEL_MGMT.REDFISH_COMMAND MODULE | 237 |
| 23.4. QUERYING INFORMATION FROM OUT-OF-BAND CONTROLLERS BY USING THE RHEL MGMT.REDFISH INFO MODULE | 239 |
| 23.5. MANAGING BIOS, UEFI, AND OUT-OF-BAND CONTROLLERS BY USING THE | 233 |
| RHEL_MGMT.REDFISH_CONFIG MODULE | 242 |
| TATILLE_MONT.INLEST ISTI_GOTATIO MODULE | 212 |
| CHAPTER 24. CONFIGURING SELINUX BY USING RHEL SYSTEM ROLES | 245 |
| 24.1. RESTORING THE SELINUX CONTEXT ON DIRECTORIES BY USING THE SELINUX RHEL SYSTEM R | OLE 245 |
| 24.2. MANAGING SELINUX NETWORK PORT LABELS BY USING THE SELINUX RHEL SYSTEM ROLE | 246 |
| 24.3. DEPLOYING AN SELINUX MODULE BY USING THE SELINUX RHEL SYSTEM ROLE | 247 |
| CHAPTER 25. CONFIGURING THE OPENSSH SERVER AND CLIENT BY USING RHEL SYSTEM ROLES | 250 |
| 25.1. HOW THE SSHD RHEL SYSTEM ROLE MAPS SETTINGS FROM A PLAYBOOK TO THE CONFIGURA | |
| FILE | 250 |
| 25.2. CONFIGURING OPENSSH SERVERS BY USING THE SSHD RHEL SYSTEM ROLE | 251 |
| 25.3. USING THE SSHD RHEL SYSTEM ROLE FOR NON-EXCLUSIVE CONFIGURATION | 253 |
| 25.4. OVERRIDING THE SYSTEM-WIDE CRYPTOGRAPHIC POLICY ON AN SSH SERVER BY USING THE | SSHD |
| RHEL SYSTEM ROLE | 255 |
| 25.5. HOW THE SSH RHEL SYSTEM ROLE MAPS SETTINGS FROM A PLAYBOOK TO THE CONFIGURAT | |
| FILE | 257 |
| 25.6. CONFIGURING OPENSSH CLIENTS BY USING THE SSH RHEL SYSTEM ROLE | 258 |
| CHAPTER 26. MANAGING LOCAL STORAGE BY USING RHEL SYSTEM ROLES | . 261 |
| 26.1. CREATING AN XFS FILE SYSTEM ON A BLOCK DEVICE BY USING THE STORAGE RHEL SYSTEM F | ROLE 261 |
| 26.2. PERSISTENTLY MOUNTING A FILE SYSTEM BY USING THE STORAGE RHEL SYSTEM ROLE | 262 |
| 26.3. CREATING OR RESIZING A LOGICAL VOLUME BY USING THE STORAGE RHEL SYSTEM ROLE | 263 |
| 26.4. ENABLING ONLINE BLOCK DISCARD BY USING THE STORAGE RHEL SYSTEM ROLE | 265 |
| 26.5. CREATING AND MOUNTING A FILE SYSTEM BY USING THE STORAGE RHEL SYSTEM ROLE | 266 |
| 26.6. CONFIGURING A RAID VOLUME BY USING THE STORAGE RHEL SYSTEM ROLE | 267 |
| 26.7. CONFIGURING AN LVM POOL WITH RAID BY USING THE STORAGE RHEL SYSTEM ROLE | 269 |
| 26.8. CONFIGURING A STRIPE SIZE FOR RAID LVM VOLUMES BY USING THE STORAGE RHEL SYSTEM ROLE | 1 270 |
| 26.9. CONFIGURING AN LVM-VDO VOLUME BY USING THE STORAGE RHEL SYSTEM ROLE | 271 |
| 26.10. CREATING A LUKS2 ENCRYPTED VOLUME BY USING THE STORAGE RHEL SYSTEM ROLE | 273 |
| 26.11. CREATING SHARED LVM DEVICES USING THE STORAGE RHEL SYSTEM ROLE | 275 |
| 26.12. RESIZING PHYSICAL VOLUMES BY USING THE STORAGE RHEL SYSTEM ROLE | 276 |
| 26.13. CREATING AN ENCRYPTED STRATIS POOL BY USING THE STORAGE RHEL SYSTEM ROLE | 277 |
| CHAPTER 27. USING THE SUDO SYSTEM ROLE | 280 |
| 27.1. APPLYING CUSTOM SUDOERS CONFIGURATION BY USING RHEL SYSTEM ROLES | 280 |
| | 200 |
| CHAPTER 28. MANAGING SYSTEMD UNITS BY USING RHEL SYSTEM ROLES | 282 |
| 28.1. MANAGING SERVICES BY USING THE SYSTEMD RHEL SYSTEM ROLE | 282 |

| 28.2. DEPLOYING SYSTEMD DROP-IN FILES BY USING THE SYSTEMD RHEL SYSTEM ROLE | 283 |
|----------------------------------------------------------------------------------------------------------------------------------------|-------------|
| 28.3. DEPLOYING SYSTEMD SYSTEM UNITS BY USING THE SYSTEMD RHEL SYSTEM ROLE | 285 |
| 28.4. DEPLOYING SYSTEMD USER UNITS BY USING THE SYSTEMD RHEL SYSTEM ROLE | 286 |
| CHAPTER 29. CONFIGURING TIME SYNCHRONIZATION BY USING RHEL SYSTEM ROLES | 289 |
| 29.1. CONFIGURING TIME SYNCHRONIZATION OVER NTP BY USING THE TIMESYNC RHEL SYSTEM ROL | E 289 |
| 29.2. CONFIGURING TIME SYNCHRONIZATION OVER NTP WITH NTS BY USING THE TIMESYNC RHEL SYSTEM ROLE | 291 |
| CHAPTER 30. CONFIGURING A SYSTEM FOR SESSION RECORDING BY USING RHEL SYSTEM ROLES | 294 |
| 30.1. CONFIGURING SESSION RECORDING FOR INDIVIDUAL USERS BY USING THE TLOG RHEL SYSTEM ROLE | 294 |
| 30.2. EXCLUDING CERTAIN USERS AND GROUPS FROM SESSION RECORDING BY USING THE TLOG RHEL SYSTEM ROLE | 296 |
| CHAPTER 31. CONFIGURING VPN CONNECTIONS BY USING RHEL SYSTEM ROLES | 298 |
| 31.1. CREATING A HOST-TO-HOST IPSEC VPN WITH PSK AUTHENTICATION BY USING THE VPN RHEL SYSTEM ROLE | 298 |
| 31.2. CREATING A HOST-TO-HOST IPSEC VPN WITH PSK AUTHENTICATION AND SEPARATE DATA AND CONTROL PLANES BY USING THE VPN RHEL SYSTEM ROLE | 300 |
| 31.3. CREATING AN IPSEC MESH VPN AMONG MULTIPLE HOSTS WITH CERTIFICATE-BASED AUTHENTICATION BY USING THE VPN RHEL SYSTEM ROLE | 302 |
| CHAPTER 32. CONFIGURING MICROSOFT SQL SERVER BY USING RHEL SYSTEM ROLES | 306 |
| 32.1. INSTALLING AND CONFIGURING SQL SERVER WITH AN EXISTING TLS CERTIFICATE BY USING THE | E 306 |
| 32.2. INSTALLING AND CONFIGURING SQL SERVER WITH A TLS CERTIFICATE ISSUED FROM IDM BY US THE MICROSOFT.SQL.SERVER ANSIBLE SYSTEM ROLE | SING 308 |
| 32.3. INSTALLING AND CONFIGURING SQL SERVER WITH CUSTOM STORAGE PATHS BY USING THE MICROSOFT.SQL.SERVER ANSIBLE SYSTEM ROLE | 311 |
| 32.4. INSTALLING AND CONFIGURING SQL SERVER WITH AD INTEGRATION BY USING THE MICROSOFT.SQL SERVER ANSIBLE SYSTEM ROLE | 313 |

PROVIDING FEEDBACK ON RED HAT DOCUMENTATION

We appreciate your feedback on our documentation. Let us know how we can improve it.

Submitting feedback through Jira (account required)

- 1. Log in to the Jira website.
- 2. Click **Create** in the top navigation bar
- 3. Enter a descriptive title in the **Summary** field.
- 4. Enter your suggestion for improvement in the **Description** field. Include links to the relevant parts of the documentation.
- 5. Click **Create** at the bottom of the dialogue.

CHAPTER 1. INTRODUCTION TO RHEL SYSTEM ROLES

By using RHEL system roles, you can remotely manage the system configurations of multiple RHEL systems across major versions of RHEL.

Important terms and concepts

The following describes important terms and concepts in an Ansible environment:

Control node

A control node is the system from which you run Ansible commands and playbooks. Your control node can be an Ansible Automation Platform, Red Hat Satellite, or a RHEL 9, 8, or 7 host. For more information, see Preparing a control node on RHEL 9.

Managed node

Managed nodes are the servers and network devices that you manage with Ansible. Managed nodes are also sometimes called hosts. Ansible does not have to be installed on managed nodes. For more information, see Preparing a managed node.

Ansible playbook

In a playbook, you define the configuration you want to achieve on your managed nodes or a set of steps for the system on the managed node to perform. Playbooks are Ansible's configuration, deployment, and orchestration language.

Inventory

In an inventory file, you list the managed nodes and specify information such as IP address for each managed node. In the inventory, you can also organize the managed nodes by creating and nesting groups for easier scaling. An inventory file is also sometimes called a hostfile.

Available roles and modules on a Red Hat Enterprise Linux 9 control node

Roles provided by the **rhel-system-roles** package:

- ad_integration: Active Directory integration
- aide: Advanced Intrusion Detection Environment
- bootloader: GRUB boot loader management
- **certificate**: Certificate issuance and renewal
- **cockpit**: Web console installation and configuration
- **crypto_policies**: System-wide cryptographic policies
- **fapolicy**: File access policy daemon configuration
- firewall: Firewalld management
- ha_cluster: HA Cluster management
- journald: Systemd journald management
- **kdump**: Kernel Dumps management
- **kernel settings**: Kernel settings management
- logging: Configuring logging

- **metrics**: Performance monitoring and metrics
- **nbde_client**: Network Bound Disk Encryption client
- nbde_server: Network Bound Disk Encryption server
- **network**: Networking configuration
- **podman**: Podman container management
- **postfix**: Postfix configuration
- **postgresql**: PostgreSQL configuration
- rhc: Subscribing RHEL and configuring Insights client
- **selinux**: SELinux management
- **ssh**: SSH client configuration
- **sshd**: SSH server configuration
- **storage**: Storage management
- **systemd**: Managing systemd units
- **timesync**: Time synchronization
- tlog: Terminal session recording
- vpn: Configuring IPsec VPNs

Roles provided by the **ansible-collection-microsoft-sql** package:

• microsoft.sql.server: Microsoft SQL Server

Modules provided by the **ansible-collection-redhat-rhel_mgmt** package:

- **rhel_mgmt.ipmi_boot**: Setting boot devices
- **rhel mgmt.ipmi power**: Setting the system power state
- **rhel_mgmt.redfish_command**: Managing out-of-band controllers (OOB)
- rhel_mgmt.redfish_command: Querying information from OOB controllers
- rhel_mgmt.redfish_command: Managing BIOS, UEFI, and OOB controllers

Additional resources

- Red Hat Enterprise Linux (RHEL) system roles
- /usr/share/ansible/roles/rhel-system-roles.
- /usr/share/doc/rhel-system-roles/<role_name>/ directory

CHAPTER 2. PREPARING A CONTROL NODE AND MANAGED NODES TO USE RHEL SYSTEM ROLES

Before you can use individual RHEL system roles to manage services and settings, you must prepare the control node and managed nodes.

2.1. PREPARING A CONTROL NODE ON RHEL 9

Before using RHEL system roles, you must configure a control node. This system then configures the managed hosts from the inventory according to the playbooks.

Prerequisites

- The system is registered to the Customer Portal.
- A **Red Hat Enterprise Linux Server** subscription is attached to the system.
- Optional: An **Ansible Automation Platform** subscription is attached to the system.

Procedure

- 1. Create a user named **ansible** to manage and run playbooks:
 - [root@control-node]# useradd ansible
- 2. Switch to the newly created **ansible** user:
 - [root@control-node]# su ansible

Perform the rest of the procedure as this user.

3. Create an SSH public and private key:

```
[ansible@control-node]$ ssh-keygen
Generating public/private rsa key pair.
Enter file in which to save the key (/home/ansible/.ssh/id_rsa):
Enter passphrase (empty for no passphrase): password>
Enter same passphrase again: cpassword>
...
```

Use the suggested default location for the key file.

- 4. Optional: To prevent Ansible from prompting you for the SSH key password each time you establish a connection, configure an SSH agent.
- 5. Create the ~/.ansible.cfg file with the following content:

```
[defaults]
inventory = /home/ansible/inventory
remote_user = ansible

[privilege_escalation]
become = True
```

become_method = sudo become_user = root become_ask_pass = True



NOTE

Settings in the ~/.ansible.cfg file have a higher priority and override settings from the global /etc/ansible/ansible.cfg file.

With these settings, Ansible performs the following actions:

- Manages hosts in the specified inventory file.
- Uses the account set in the remote_user parameter when it establishes SSH connections to managed nodes.
- Uses the sudo utility to execute tasks on managed nodes as the root user.
- Prompts for the root password of the remote user every time you apply a playbook. This is recommended for security reasons.
- 6. Create an ~/inventory file in INI or YAML format that lists the hostnames of managed hosts. You can also define groups of hosts in the inventory file. For example, the following is an inventory file in the INI format with three hosts and one host group named US:

managed-node-01.example.com

[US]

managed-node-02.example.com ansible_host=192.0.2.100 managed-node-03.example.com

Note that the control node must be able to resolve the hostnames. If the DNS server cannot resolve certain hostnames, add the **ansible_host** parameter next to the host entry to specify its IP address.

- 7. Install RHEL system roles:
 - On a RHEL host without Ansible Automation Platform, install the rhel-system-roles package:
 - [root@control-node]# dnf install rhel-system-roles

This command installs the collections in the /usr/share/ansible/collections/ansible_collections/redhat/rhel_system_roles/ directory, and the ansible-core package as a dependency.

- On Ansible Automation Platform, perform the following steps as the ansible user:
 - i. Define Red Hat automation hub as the primary source for content in the ~/.ansible.cfg file.
 - ii. Install the **redhat.rhel_system_roles** collection from Red Hat automation hub:

[ansible@control-node]\$ ansible-galaxy collection install redhat.rhel_system_roles

This command installs the collection in the

~/.ansible/collections/ansible_collections/redhat/rhel_system_roles/ directory.

Next step

• Prepare the managed nodes. For more information, see Preparing a managed node.

Additional resources

- Scope of support for the Ansible Core package included in the RHEL 9 and RHEL 8.6 and later AppStream repositories
- How to register and subscribe a system to the Red Hat Customer Portal using subscriptionmanager (Red Hat Knowledgebase)
- The **ssh-keygen(1)** manual page
- Connecting to remote machines with SSH keys using ssh-agent
- Ansible configuration settings
- How to build your inventory

2.2. PREPARING A MANAGED NODE

Managed nodes are the systems listed in the inventory and which will be configured by the control node according to the playbook. You do not have to install Ansible on managed hosts.

Prerequisites

- You prepared the control node. For more information, see Preparing a control node on RHEL 9.
- You have SSH access from the control node.



IMPORTANT

Direct SSH access as the **root** user is a security risk. To reduce this risk, you will create a local user on this node and configure a **sudo** policy when preparing a managed node. Ansible on the control node can then use the local user account to log in to the managed node and run playbooks as different users, such as **root**.

Procedure

1. Create a user named ansible:

[root@managed-node-01]# useradd ansible

The control node later uses this user to establish an SSH connection to this host.

2. Set a password for the **ansible** user:

[root@managed-node-01]# **passwd ansible** Changing password for user ansible. New password: **<password>** Retype new password: password
password
authentication tokens updated successfully.

You must enter this password when Ansible uses **sudo** to perform tasks as the **root** user.

- 3. Install the **ansible** user's SSH public key on the managed node:
 - a. Log in to the control node as the **ansible** user, and copy the SSH public key to the managed node:

[ansible@control-node]\$ ssh-copy-id managed-node-01.example.com

/usr/bin/ssh-copy-id: INFO: Source of key(s) to be installed:

"/home/ansible/.ssh/id_rsa.pub"

The authenticity of host 'managed-node-01.example.com (192.0.2.100)' can't be established.

ECDSA key fingerprint is

SHA256:9bZ33GJNODK3zbNhybokN/6Mq7hu3vpBXDrCxe7NAvo.

b. When prompted, connect by entering **yes**:

Are you sure you want to continue connecting (yes/no/[fingerprint])? yes

/usr/bin/ssh-copy-id: INFO: attempting to log in with the new key(s), to filter out any that are already installed

/usr/bin/ssh-copy-id: INFO: 1 key(s) remain to be installed -- if you are prompted now it is to install the new keys

c. When prompted, enter the password:

ansible@managed-node-01.example.com's password:

Number of key(s) added: 1

Now try logging into the machine, with: "ssh 'managed-node-01.example.com" and check to make sure that only the key(s) you wanted were added.

d. Verify the SSH connection by remotely executing a command on the control node:

[ansible@control-node]\$ **ssh managed-node-01.example.com whoami** ansible

- 4. Create a **sudo** configuration for the **ansible** user:
 - a. Create and edit the /etc/sudoers.d/ansible file by using the visudo command:

[root@managed-node-01]# visudo /etc/sudoers.d/ansible

The benefit of using **visudo** over a normal editor is that this utility provides basic checks, such as for parse errors, before installing the file.

- b. Configure a **sudoers** policy in the /**etc/sudoers.d/ansible** file that meets your requirements, for example:
 - To grant permissions to the **ansible** user to run all commands as any user and group on this host after entering the **ansible** user's password, use:

```
ansible ALL=(ALL) ALL
```

• To grant permissions to the **ansible** user to run all commands as any user and group on this host without entering the **ansible** user's password, use:

```
ansible ALL=(ALL) NOPASSWD: ALL
```

Alternatively, configure a more fine-granular policy that matches your security requirements. For further details on **sudoers** policies, see the **sudoers(5)** manual page.

Verification

1. Verify that you can execute commands from the control node on an all managed nodes:

The hard-coded all group dynamically contains all hosts listed in the inventory file.

2. Verify that privilege escalation works correctly by running the **whoami** utility on all managed nodes by using the Ansible **command** module:

```
[ansible@control-node]$ ansible all -m command -a whoami BECOME password: command -a whoami
BECOME password>
managed-node-01.example.com | CHANGED | rc=0 >>
root
...
```

If the command returns root, you configured **sudo** on the managed nodes correctly.

Additional resources

- Preparing a control node on RHEL 9
- sudoers(5) manual page

CHAPTER 3. ANSIBLE VAULT

Sometimes your playbook needs to use sensitive data such as passwords, API keys, and other secrets to configure managed hosts. Storing this information in plain text in variables or other Ansible-compatible files is a security risk because any user with access to those files can read the sensitive data.

With Ansible vault, you can encrypt, decrypt, view, and edit sensitive information. They could be included as:

- Inserted variable files in an Ansible Playbook
- Host and group variables
- Variable files passed as arguments when executing the playbook
- Variables defined in Ansible roles

You can use Ansible vault to securely manage individual variables, entire files, or even structured data like YAML files. This data can then be safely stored in a version control system or shared with team members without exposing sensitive information.



IMPORTANT

Files are protected with symmetric encryption of the Advanced Encryption Standard (AES256), where a single password or passphrase is used both to encrypt and decrypt the data. Note that the way this is done has not been formally audited by a third party.

To simplify management, it makes sense to set up your Ansible project so that sensitive variables and all other variables are kept in separate files, or directories. Then you can protect the files containing sensitive variables with the **ansible-vault** command.

Creating an encrypted file

The following command prompts you for a new vault password. Then it opens a file for storing sensitive variables using the default editor.

ansible-vault create vault.yml

New Vault password: <vault password>

Confirm New Vault password: <vault password>

Viewing an encrypted file

The following command prompts you for your existing vault password. Then it displays the sensitive contents of an already encrypted file.

ansible-vault view vault.yml

Vault password: <vault_password>

my_secret: "yJJvPqhsiusmmPPZdnjndkdnYNDjdj782meUZcw"

Editing an encrypted file

The following command prompts you for your existing vault password. Then it opens the already encrypted file for you to update the sensitive variables using the default editor.

ansible-vault edit vault.yml

Vault password: <vault_password>

Encrypting an existing file

The following command prompts you for a new vault password. Then it encrypts an existing unencrypted file.

ansible-vault encrypt vault.yml

New Vault password: <vault_password>

Confirm New Vault password: <vault_password>

Encryption successful

Decrypting an existing file

The following command prompts you for your existing vault password. Then it decrypts an existing encrypted file.

ansible-vault decrypt vault.yml

Vault password: <vault_password>

Decryption successful

Changing the password of an encrypted file

The following command prompts you for your original vault password, then for the new vault password.

ansible-vault rekey vault.yml

Vault password: <vault_password>
New Vault password: <vault_password>

Confirm New Vault password: <vault_password>

Rekey successful

Basic application of Ansible vault variables in a playbook

--- name: Create user accounts for all servers hosts: managed-node-01.example.com vars_files:
 - ~/vault.yml tasks:
 - name: Create user from vault.yml file user:
 name: "{{ username }}"
 password: "{{ pwhash }}"

You read-in the file with variables (**vault.yml**) in the **vars_files** section of your Ansible Playbook, and you use the curly brackets the same way you would do with your ordinary variables. Then you either run the playbook with the **ansible-playbook --ask-vault-pass** command and you enter the password manually. Or you save the password in a separate file and you run the playbook with the **ansible-playbook --vault-password-file** /path/to/my/vault-password-file command.

Additional resources

ansible-vault(1), ansible-playbook(1) man pages on your system

- Ansible vault
- Ansible vault Best Practices

CHAPTER 4. JOINING RHEL SYSTEMS TO AN ACTIVE DIRECTORY BY USING RHEL SYSTEM ROLES

If your organization uses Microsoft Active Directory (AD) to centrally manage users, groups, and other resources, you can join your Red Hat Enterprise Linux (RHEL) host to this AD. For example, AD users can then log into RHEL and you can make services on the RHEL host available for authenticated AD users. By using the **ad_integration** RHEL system role, you can automate the integration of Red Hat Enterprise Linux system into an Active Directory (AD) domain.



NOTE

The **ad_integration** role is for deployments using direct AD integration without an Identity Management (IdM) environment. For IdM environments, use the **ansible-freeipa** roles.

4.1. JOINING RHEL TO AN ACTIVE DIRECTORY DOMAIN BY USING THE AD_INTEGRATION RHEL SYSTEM ROLE

You can use the **ad_integration** RHEL system role to automate the process of joining RHEL to an Active Directory (AD) domain.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The managed node uses a DNS server that can resolve AD DNS entries.
- Credentials of an AD account which has permissions to join computers to the domain.
- Ensure that the required ports are open:
 - Ports required for direct integration of RHEL systems into AD using SSSD

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml

New Vault password: <vault_password>

Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

usr: administrator pwd: <password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
-name: Active Directory integration
hosts: managed-node-01.example.com
vars_files:
    - ~/vault.yml
tasks:
    - name: Join an Active Directory
    ansible.builtin.include_role:
    name: redhat.rhel_system_roles.ad_integration
vars:
    ad_integration_user: "{{ usr }}"
    ad_integration_password: "{{ pwd }}"
    ad_integration_realm: "ad.example.com"
    ad_integration_allow_rc4_crypto: false
    ad_integration_timesync_source: "time_server.ad.example.com"
```

The settings specified in the example playbook include the following:

ad_integration_allow_rc4_crypto: <true/false>

Configures whether the role activates the **AD-SUPPORT** crypto policy on the managed node. By default, RHEL does not support the weak RC4 encryption but, if Kerberos in your AD still requires RC4, you can enable this encryption type by setting **ad_integration_allow_rc4_crypto: true**.

Omit this the variable or set it to **false** if Kerberos uses AES encryption.

ad_integration_timesync_source: <time_server>

Specifies the NTP server to use for time synchronization. Kerberos requires a synchronized time among AD domain controllers and domain members to prevent replay attacks. If you omit this variable, the **ad_integration** role does not utilize the **timesync** RHEL system role to configure time synchronization on the managed node.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.ad_integration/README.md file on the control node.

3. Validate the playbook syntax:

 $\$\ ansible-playbook\ --ask-vault-pass\ --syntax-check\ \sim /playbook.yml$

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Verification

Check if AD users, such as administrator, are available locally on the managed node:

\$ ansible managed-node-01.example.com -m command -a 'getent passwd

administrator@ad.example.com'

 $administrator@ad.example.com: \verb§^*:1450400500:1450400513:Administrator:/home/administrator@ad.example.com: \verb§^*:1450400500:1450400513:Administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administrator:/home/administra$

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ad_integration/README.md file
- /usr/share/doc/rhel-system-roles/ad_integration/ directory
- Ansible vault

CHAPTER 5. CONFIGURING THE GRUB BOOT LOADER BY USING RHEL SYSTEM ROLES

By using the **bootloader** RHEL system role, you can automate the configuration and management tasks related to the GRUB boot loader.

This role currently supports configuring the GRUB boot loader, which runs on the following CPU architectures:

- AMD and Intel 64-bit architectures (x86-64)
- The 64-bit ARM architecture (ARMv8.0)
- IBM Power Systems, Little Endian (POWER9)

5.1. UPDATING THE EXISTING BOOT LOADER ENTRIES BY USING THE BOOTLOADER RHEL SYSTEM ROLE

You can use the **bootloader** RHEL system role to update the existing entries in the GRUB boot menu in an automated fashion. This way you can efficiently pass specific kernel command-line parameters that can optimize the performance or behavior of your systems.

For example, if you leverage systems, where detailed boot messages from the kernel and init system are not necessary, use **bootloader** to apply the **quiet** parameter to your existing boot loader entries on your managed nodes to achieve a cleaner, less cluttered, and more user-friendly booting experience.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You identified the kernel that corresponds to the boot loader entry you want to update.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

name: Configuration and management of GRUB boot loader hosts: managed-node-01.example.com tasks:
 name: Update existing boot loader entries ansible.builtin.include_role:

name: redhat.rhel_system_roles.bootloader
vars:

bootloader_settings:

- kernel:
 path: /boot/vmlinuz-5.14.0-362.24.1.el9_3.aarch64
 options:

name: quiet state: present

bootloader_reboot_ok: true

The settings specified in the example playbook include the following:

kernel

Specifies the kernel connected with the boot loader entry that you want to update.

options

Specifies the kernel command-line parameters to update for your chosen boot loader entry (kernel).

bootloader_reboot_ok: true

The role detects that a reboot is required for the changes to take effect and performs a restart of the managed node.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.bootloader/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Check that your specified boot loader entry has updated kernel command-line parameters:

```
# ansible managed-node-01.example.com -m ansible.builtin.command -a 'grubby -- info=ALL'
```

managed-node-01.example.com | CHANGED | rc=0 >>

ا ما

index=1

kernel="/boot/vmlinuz-5.14.0-362.24.1.el9_3.aarch64"

args="ro crashkernel=1G-4G:256M,4G-64G:320M,64G-:576M rd.lvm.lv=rhel/root

rd.lvm.lv=rhel/swap \$tuned_params quiet"

root="/dev/mapper/rhel-root"

initrd="/boot/initramfs-5.14.0-362.24.1.el9_3.aarch64.img \$tuned_initrd"

title="Red Hat Enterprise Linux (5.14.0-362.24.1.el9 3.aarch64) 9.4 (Plow)"

id="2c9ec787230141a9b087f774955795ab-5.14.0-362.24.1.el9_3.aarch64"

...

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.bootloader/README.md file
- /usr/share/doc/rhel-system-roles/bootloader/ directory

- Working With Playbooks
- Using Variables
- Roles
- Configuring kernel command-line parameters

5.2. SECURING THE BOOT MENU WITH PASSWORD BY USING THE BOOTLOADER RHEL SYSTEM ROLE

You can use the **bootloader** RHEL system role to set a password to the GRUB boot menu in an automated fashion. This way you can efficiently prevent unauthorized users from modifying boot parameters, and to have better control over the system boot.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

pwd: <password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

--- name: Configuration and management of GRUB boot loader hosts: managed-node-01.example.com vars_files:
- ~/vault.yml tasks:
- name: Set the bootloader password ansible.builtin.include_role:
 name: redhat.rhel_system_roles.bootloader vars:
 bootloader_password: "{{ pwd }}"
 bootloader reboot ok: true

The settings specified in the example playbook include the following:

bootloader password: "{{ pwd }}"

The variable ensures protection of boot parameters with a password.

bootloader_reboot_ok: true

The role detects that a reboot is required for the changes to take effect and performs a restart of the managed node.



IMPORTANT

Changing the boot loader password is not an idempotent transaction. This means that if you apply the same Ansible playbook again, the result will not be the same, and the state of the managed node will change.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.bootloader/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Verification

1. On your managed node during the GRUB boot menu screen, press the **e** key for edit.



2. You are prompted for a username and a password:

```
Enter username:
root
Enter password:
-
```

Enter username: root

The boot loader username is always **root** and you do not need to specify it in your Ansible playbook.

Enter password: <password>

The boot loader password corresponds to the **pwd** variable that you defined in the **vault.yml** file.

3. You can view or edit configuration of the particular boot loader entry:

```
GRUB version 2.06

load_video
set gfxpayload=keep
insmod gzio
linux ($root)/vmlinuz-5.14.0-362.24.1.e19_3.aarch64 root=/dev/mapper/rhel-r\
oot ro crashkernel=16-46:256M.46-646:320M.646-:576M rd.lum.lu=rhel/root rd.\
lum.lu=rhel/swap quiet
initrd ($root)/initramfs-5.14.0-362.24.1.e19_3.aarch64.img $tuned_initrd

Minimum Emacs-like screen editing is supported. TAB lists
completions. Press Ctrl-x or F10 to boot, Ctrl-c or F2 for a
command-line or ESC to discard edits and return to the GRUB menu.
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.bootloader/README.md file
- /usr/share/doc/rhel-system-roles/bootloader/ directory

5.3. SETTING A TIMEOUT FOR THE BOOT LOADER MENU BY USING THE BOOTLOADER RHEL SYSTEM ROLE

You can use the **bootloader** RHEL system role to configure a timeout for the GRUB boot loader menu in an automated way. You can update a period of time to intervene and select a non-default boot entry for various purposes.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: Configuration and management of the GRUB boot loader hosts: managed-node-01.example.com tasks:
- name: Update the boot loader timeout ansible.builtin.include_role:
    name: redhat.rhel_system_roles.bootloader vars:
    bootloader_timeout: 10
```

The settings specified in the example playbook include the following:

bootloader_timeout: 10

Input an integer to control for how long the GRUB boot loader menu is displayed before booting the default entry.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.bootloader/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. Remotely restart your managed node:

```
# ansible managed-node-01.example.com -m ansible.builtin.reboot
managed-node-01.example.com | CHANGED => {
    "changed": true,
    "elapsed": 21,
    "rebooted": true
}
```

2. On the managed node, observe the GRUB boot menu screen.

GRUB version 2.06 Red Hat Enterprise Linux (5.14.0-427.22.1.e19_4.aarch64) 9.4 (Plow) *Red Hat Enterprise Linux (5.14.0-362.24.1.e19_3.aarch64) 9.4 (Plow) Red Hat Enterprise Linux (0-rescue-2c9ec787230141a9b087f774955795ab) 9.4 (▶ UEFI Firmware Settings Use the ▲ and ▼ keys to select which entry is highlighted. Press enter to boot the selected 0S, `e' to edit the commands before booting or `c' for a command-line. ESC to return previous menu. The highlighted entry will be executed automatically in 10s.

The highlighted entry will be executed automatically in 10s

For how long this boot menu is displayed before GRUB automatically uses the default entry.

• Alternative: you can remotely query for the "timeout" settings in the /boot/grub2/grub.cfg file of your managed node:

```
# ansible managed-node-01.example.com -m ansible.builtin.command -a "grep
'timeout' /boot/grub2/grub.cfg"
managed-node-01.example.com | CHANGED | rc=0 >>
if [ x$feature_timeout_style = xy ] ; then
 set timeout style=menu
 set timeout=10
# Fallback normal timeout code in case the timeout style feature is
 set timeout=10
if [ x$feature_timeout_style = xy ] ; then
  set timeout style=menu
  set timeout=10
  set orig timeout style=${timeout style}
  set orig_timeout=${timeout}
   # timeout_style=menu + timeout=0 avoids the countdown code keypress check
   set timeout style=menu
   set timeout=10
   set timeout style=hidden
   set timeout=10
if [ x$feature_timeout_style = xy ]; then
 if [ "${menu show once timeout}" ]; then
  set timeout style=menu
  set timeout=10
  unset menu_show_once_timeout
  save env menu show once timeout
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.bootloader/README.md file
- /usr/share/doc/rhel-system-roles/bootloader/ directory

5.4. COLLECTING THE BOOT LOADER CONFIGURATION INFORMATION BY USING THE BOOTLOADER RHEL SYSTEM ROLE

You can use the **bootloader** RHEL system role to gather information about the GRUB boot loader entries in an automated fashion. You can use this information to verify the correct configuration of system boot parameters, such as kernel and initial RAM disk image paths.

As a result, you can for example:

- Prevent boot failures.
- Revert to a known good state when troubleshooting.
- Be sure that security-related kernel command-line parameters are correctly configured.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

 name: Configuration and management of GRUB boot loader hosts: managed-node-01.example.com tasks:

- name: Gather information about the boot loader configuration ansible.builtin.include_role:

name: redhat.rhel_system_roles.bootloader

vars:

bootloader_gather_facts: true

- name: Display the collected boot loader configuration information debug:

var: bootloader facts

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.bootloader/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

 After you run the preceding playbook on the control node, you will see a similar command-line output as in the following example:

The command-line output shows the following notable configuration information about the boot entry:

args

Command-line parameters passed to the kernel by the GRUB2 boot loader during the boot process. They configure various settings and behaviors of the kernel, initramfs, and other boot-time components.

id

Unique identifier assigned to each boot entry in a boot loader menu. It consists of machine ID and the kernel version.

root

The root filesystem for the kernel to mount and use as the primary filesystem during the boot.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.bootloader/README.md file
- /usr/share/doc/rhel-system-roles/bootloader/ directory
- Understanding boot entries

CHAPTER 6. REQUESTING CERTIFICATES FROM A CA AND CREATING SELF-SIGNED CERTIFICATES BY USING RHEL SYSTEM ROLES

Many services, such as web servers, use TLS to encrypt connections with clients. These services require a private key and a certificate, and a trusted certificate authority (CA) which signs the certificate.

By using the **certificate** RHEL system role, you can automate the generation of private keys on managed nodes. Additionally, the role configures the **certmonger** service to send the certificate signing request (CSR) to a CA, and the service automatically renews the certificate before it expires.

For testing purposes, you can use the **certificate** role to create self-signed certificates instead of requesting a signed certificate from a CA.

6.1. REQUESTING A NEW CERTIFICATE FROM AN IDM CA BY USING THE CERTIFICATE RHEL SYSTEM ROLE

If a Red Hat Enterprise Linux host is a member of a RHEL Identity Management (IdM) environment, you can request TLS certificates from the IdM certificate authority (CA) and use them in the services that run on this host. By using the **certificate** RHEL system role, you can automate the process of creating a private key and letting the **certmonger** service request a certificate from the CA. By default, **certmonger** will also renew the certificate before it expires.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The managed node is a member of an IdM domain and the domain uses the IdM-integrated CA.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Create certificates

hosts: managed-node-01.example.com

tasks:

- name: Create a self-signed certificate

ansible.builtin.include_role:

name: redhat.rhel_system_roles.certificate

vars:

certificate_requests:

- name: web-server

ca: ipa

dns: www.example.com

principal: HTTP/www.example.com@EXAMPLE.COM

run_before: systemctl stop httpd.service run_after: systemctl start httpd.service

The settings specified in the example playbook include the following:

name: <path_or_file_name>

Defines the name or path of the generated private key and certificate file:

- If you set the variable to **web-server**, the role stores the private key in the /etc/pki/tls/private/web-server.key and the certificate in the /etc/pki/tls/certs/web-server.crt files.
- If you set the variable to a path, such as /tmp/web-server, the role stores the private key in the /tmp/web-server.key and the certificate in the /tmp/web-server.crt files.
 Note that the directory you use must have the cert_t SELinux context set. You can use the selinux RHEL system role to manage SELinux contexts.

ca: ipa

Defines that the role requests the certificate from an IdM CA.

dns: <hostname_or_list_of_hostnames>

Sets the hostnames that the Subject Alternative Names (SAN) field in the issued certificate contains. You can use a wildcard (*) or specify multiple names in YAML list format.

principal: <kerberos_principal>

Optional: Sets the Kerberos principal that should be included in the certificate.

run before: <command>

Optional: Defines a command that **certmonger** should execute before requesting the certificate from the CA.

run after: <command>

Optional: Defines a command that **certmonger** should execute after it received the issued certificate from the CA.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.certificate/README.md file on the control node.

2. Validate the playbook syntax:

$\$\ ansible-playbook\ --syntax-check\ \sim\!/playbook.yml$

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• List the certificates that the **certmonger** service manages:

ansible managed-node-01.example.com -m command -a 'getcert list'

. . .

Number of certificates and requests being tracked: 1.

Request ID '20240918142211':

status: MONITORING

stuck: no

key pair storage: type=FILE,location='/etc/pki/tls/private/web-server.key'

certificate: type=FILE,location='/etc/pki/tls/certs/web-server.crt'

CA: IPA

issuer: CN=Certificate Authority,O=EXAMPLE.COM

subject: CN=www.example.com issued: 2024-09-18 16:22:11 CEST expires: 2025-09-18 16:22:10 CEST

dns: www.example.com

key usage: digitalSignature,keyEncipherment

eku: id-kp-serverAuth,id-kp-clientAuth

pre-save command: systemctl stop httpd.service post-save command: systemctl start httpd.service

track: yes auto-renew: yes

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.certificate/README.md file
- /usr/share/doc/rhel-system-roles/certificate/ directory

6.2. REQUESTING A NEW SELF-SIGNED CERTIFICATE BY USING THE CERTIFICATE RHEL SYSTEM ROLE

If you require a TLS certificate for a test environment, you can use a self-signed certificate. By using the **certificate** RHEL system role, you can automate the process of creating a private key and letting the **certmonger** service create a self-signed certificate. By default, **certmonger** will also renew the certificate before it expires.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Create certificates

hosts: managed-node-01.example.com

tasks:

- name: Create a self-signed certificate

ansible.builtin.include role:

name: redhat.rhel system roles.certificate

vars:

certificate_requests:

- name: web-server

ca: self-sign

dns: test.example.com

The settings specified in the example playbook include the following:

name: <path_or_file_name>

Defines the name or path of the generated private key and certificate file:

- If you set the variable to web-server, the role stores the private key in the /etc/pki/tls/private/web-server.key and the certificate in the /etc/pki/tls/certs/web-server.crt files.
- If you set the variable to a path, such as /tmp/web-server, the role stores the private key in the /tmp/web-server.key and the certificate in the /tmp/web-server.crt files.
 Note that the directory you use must have the cert_t SELinux context set. You can use the selinux RHEL system role to manage SELinux contexts.

ca: self-sign

Defines that the role created a self-signed certificate.

dns: <hostname_or_list_of_hostnames>

Sets the hostnames that the Subject Alternative Names (SAN) field in the issued certificate contains. You can use a wildcard (*) or specify multiple names in YAML list format.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.certificate/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

 $\$\ ansible-playbook\ {\sim}/playbook.yml$

Verification

• List the certificates that the **certmonger** service manages:

ansible managed-node-01.example.com -m command -a 'getcert list'

...

Number of certificates and requests being tracked: 1.

Request ID '20240918133610':

status: MONITORING

stuck: no

key pair storage: type=FILE,location='/etc/pki/tls/private/web-server.key'

certificate: type=FILE,location='/etc/pki/tls/certs/web-server.crt'

CA: local

issuer: CN=c32b16d7-5b1a4c5a-a953a711-c3ca58fb,CN=Local Signing Authority

subject: CN=test.example.com issued: 2024-09-18 15:36:10 CEST expires: 2025-09-18 15:36:09 CEST

dns: test.example.com

key usage: digitalSignature,keyEncipherment

eku: id-kp-serverAuth,id-kp-clientAuth

pre-save command: post-save command: track: yes auto-renew: yes

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.certificate/README.md file
- /usr/share/doc/rhel-system-roles/certificate/ directory

CHAPTER 7. INSTALLING AND CONFIGURING WEB CONSOLE BY USING RHEL SYSTEM ROLES

With the **cockpit** RHEL system role, you can automatically deploy and enable the web console on multiple RHEL systems.

7.1. INSTALLING THE WEB CONSOLE BY USING THECOCKPIT RHEL SYSTEM ROLE

You can use the **cockpit** system role to automate installing and enabling the RHEL web console on multiple systems.

In this example, you use the **cockpit** system role to:

- Install the RHEL web console.
- Allow the firewalld and selinux system roles to configure the system for opening new ports.
- Set the web console to use a certificate from the **ipa** trusted certificate authority instead of using a self-signed certificate.



NOTE

You do not have to call the **firewall** or **certificate** system roles in the playbook to manage the firewall or create the certificate. The **cockpit** system role calls them automatically as needed.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example, ~/playbook.yml, with the following content:

 name: Manage the RHEL web console hosts: managed-node-01.example.com tasks:

- name: Install RHEL web console ansible.builtin.include_role:

name: redhat.rhel_system_roles.cockpit

vars:

cockpit_packages: default cockpit_manage_selinux: true cockpit_manage_firewall: true cockpit_certificates:

 name: /etc/cockpit/ws-certs.d/01-certificate dns: ['localhost', 'www.example.com'] ca: ipa

The settings specified in the example playbook include the following:

cockpit_manage_selinux: true

Allow using the **selinux** system role to configure SELinux for setting up the correct port permissions on the **websm_port_t** SELinux type.

cockpit_manage_firewall: true

Allow the **cockpit** system role to use the **firewalld** system role for adding ports.

cockpit certificates: <YAML dictionary>

By default, the RHEL web console uses a self-signed certificate. Alternatively, you can add the **cockpit_certificates** variable to the playbook and configure the role to request certificates from an IdM certificate authority (CA) or to use an existing certificate and private key that is available on the managed node.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.cockpit/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.cockpit/README.md file
- /usr/share/doc/rhel-system-roles/cockpit directory
- Requesting certificates using RHEL system roles

CHAPTER 8. SETTING A CUSTOM CRYPTOGRAPHIC POLICY BY USING RHEL SYSTEM ROLES

Custom cryptographic policies are a set of rules and configurations that manage the use of cryptographic algorithms and protocols. These policies help you to maintain a protected, consistent, and manageable security environment across multiple systems and applications.

By using the **crypto_policies** RHEL system role, you can quickly and consistently configure custom cryptographic policies across many operating systems in an automated fashion.

8.1. ENHANCING SECURITY WITH THE FUTURE CRYPTOGRAPHIC POLICY USING THE CRYPTO_POLICIES RHEL SYSTEM ROLE

You can use the **crypto_policies** RHEL system role to configure the **FUTURE** policy on your managed nodes. This policy helps to achieve for example:

- Future-proofing against emerging threats: anticipates advancements in computational power.
- Enhanced security: stronger encryption standards require longer key lengths and more secure algorithms.
- Compliance with high-security standards: for example in healthcare, telco, and finance the data sensitivity is high, and availability of strong cryptography is critical.

Typically, **FUTURE** is suitable for environments handling highly sensitive data, preparing for future regulations, or adopting long-term security strategies.



WARNING

Legacy systems or software does not have to support the more modern and stricter algorithms and protocols enforced by the **FUTURE** policy. For example, older systems might not support TLS 1.3 or larger key sizes. This could lead to compatibility problems.

Also, using strong algorithms usually increases the computational workload, which could negatively affect your system performance.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

 name: Configure cryptographic policies hosts: managed-node-01.example.com

- name: Configure the FUTURE cryptographic security policy on the managed node ansible.builtin.include_role:

name: redhat.rhel_system_roles.crypto_policies

vars:

- crypto_policies_policy: FUTURE- crypto_policies_reboot_ok: true

The settings specified in the example playbook include the following:

crypto_policies_policy: FUTURE

Configures the required cryptographic policy (**FUTURE**) on the managed node. It can be either the base policy or a base policy with some sub-policies. The specified base policy and sub-policies have to be available on the managed node. The default value is **null**. It means that the configuration is not changed and the **crypto_policies** RHEL system role will only collect the Ansible facts.

crypto_policies_reboot_ok: true

Causes the system to reboot after the cryptographic policy change to make sure all of the services and applications will read the new configuration files. The default value is **false**.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.crypto_policies/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml



WARNING

Because the **FIPS:OSPP** system-wide subpolicy contains further restrictions for cryptographic algorithms required by the Common Criteria (CC) certification, the system is less interoperable after you set it. For example, you cannot use RSA and DH keys shorter than 3072 bits, additional SSH algorithms, and several TLS groups. Setting **FIPS:OSPP** also prevents connecting to Red Hat Content Delivery Network (CDN) structure. Furthermore, you cannot integrate Active Directory (AD) into the IdM deployments that use **FIPS:OSPP**, communication between RHEL hosts using **FIPS:OSPP** and AD domains might not work, or some AD accounts might not be able to authenticate.

Note that your **system is not CC-compliant** after you set the **FIPS:OSPP** cryptographic subpolicy. The only correct way to make your RHEL system compliant with the CC standard is by following the guidance provided in the **cc-config** package. See the Common Criteria section on the Product compliance Red Hat Customer Portal page for a list of certified RHEL versions, validation reports, and links to CC guides hosted at the National Information Assurance Partnership (NIAP) website.

Verification

1. On the control node, create another playbook named, for example, verify playbook.yml:

- name: Verification

hosts: managed-node-01.example.com

tasks:

- name: Verify active cryptographic policy

ansible.builtin.include role:

name: redhat.rhel_system_roles.crypto_policies

- name: Display the currently active cryptographic policy ansible.builtin.debug:

var: crypto_policies_active

The settings specified in the example playbook include the following:

crypto_policies_active

An exported Ansible fact that contains the currently active policy name in the format as accepted by the **crypto_policies_policy** variable.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/verify_playbook.yml

3. Run the playbook:

```
$ ansible-playbook ~/verify_playbook.yml
TASK [debug] *******************
ok: [host] => {
```

```
"crypto_policies_active": "FUTURE" }
```

The **crypto_policies_active** variable shows the active policy on the managed node.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.crypto_policies/README.md file
- /usr/share/doc/rhel-system-roles/crypto_policies/ directory
- update-crypto-policies(8) and crypto-policies(7) manual pages

CHAPTER 9. RESTRICTING THE EXECUTION OF APPLICATIONS BY USING THE FAPOLICYD RHEL SYSTEM ROLE

By using the **fapolicyd** software framework, you can restrict the execution of applications based on a user-defined policy and the framework verifies the integrity of applications before execution. This an efficient method to prevent running untrustworthy and possibly malicious applications. You can automate the installation and configuration of **fapolicyd** by using the **fapolicyd** RHEL system role.



IMPORTANT

The **fapolicyd** service prevents only the execution of unauthorized applications that run as regular users, and not as **root**.

9.1. PREVENTING USERS FROM EXECUTING UNTRUSTWORTHY CODE BY USING THE FAPOLICYD RHEL SYSTEM ROLE

You can automate the installation and configuration of the **fapolicyd** service by using the **fapolicyd** RHEL system role. With this role, you can remotely configure the service to allow users to execute only trusted applications, for example, the ones which are listed in the RPM database and in an allow list. Additionally, the service can perform integrity checks before it executes an allowed application.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

__.

- name: Configuring fapolicyd

hosts: managed-node-01.example.com

tasks:

 name: Allow only executables installed from RPM database and specific files ansible.builtin.include_role:

name: redhat.rhel_system_roles.fapolicyd

vars:

fapolicyd_setup_permissive: false fapolicyd_setup_integrity: sha256 fapolicyd_setup_trust: rpmdb,file fapolicyd_add_trusted_file:

- <path to allowed command>

- <path_to_allowed_service>

The settings specified in the example playbook include the following:

fapolicyd setup permissive: <true/false>

Enables or disables sending policy decisions to the kernel for enforcement. Set this variable for debugging and testing purposes to **false**.

fapolicyd_setup_integrity: <type_type>

Defines the integrity checking method. You can set one of the following values:

- **none** (default): Disables integrity checking.
- **size**: The service compares only the file sizes of allowed applications.
- **ima**: The service checks the SHA-256 hash that the kernel's Integrity Measurement Architecture (IMA) stored in a file's extended attribute. Additionally, the service performs a size check. Note that the role does not configure the IMA kernel subsystem. To use this option, you must manually configure the IMA subsystem.
- **sha256**: The service compares the SHA-256 hash of allowed applications.

fapolicyd_setup_trust: <trust_backends>

Defines the list of trust backends. If you include the **file** backend, specify the allowed executable files in the **fapolicyd add trusted file** list.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.fapolicyd.README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook ~/playbook.yml --syntax-check

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Execute a binary application that is not on the allow list as a user:

\$ ansible managed-node-01.example.com -m command -a 'su -c "/bin/not_authorized_application " <user_name>' bash: line 1: /bin/not_authorized_application: Operation not permitted non-zero return code

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.fapolicyd/README.md file
- /usr/share/doc/rhel-system-roles/fapolicyd/ directory

CHAPTER 10. CONFIGURING FIREWALLD BY USING RHEL SYSTEM ROLES

RHEL system roles is a set of contents for the Ansible automation utility. This content together with the Ansible automation utility provides a consistent configuration interface to remotely manage multiple systems at once.

The **rhel-system-roles** package contains the **rhel-system-roles.firewall** RHEL system role. This role was introduced for automated configurations of the **firewalld** service.

With the **firewall** RHEL system role you can configure many different **firewalld** parameters, for example:

- Zones
- The services for which packets should be allowed
- Granting, rejection, or dropping of traffic access to ports
- Forwarding of ports or port ranges for a zone

10.1. RESETTING THE FIREWALLD SETTINGS BY USING THE FIREWALL RHEL SYSTEM ROLE

Over time, updates to your firewall configuration can accumulate to the point, where they could lead to unintended security risks. With the **firewall** RHEL system role, you can reset the **firewalld** settings to their default state in an automated fashion. This way you can efficiently remove any unintentional or insecure firewall rules and simplify their management.

Prerequisites

- You have prepared the control node and the managed nodes.
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Reset firewalld example

hosts: managed-node-01.example.com

tasks:

 name: Reset firewalld ansible.builtin.include role:

name: redhat.rhel_system_roles.firewall

vars: firewall:

- previous: replaced

The settings specified in the example playbook include the following:

previous: replaced

Removes all existing user-defined settings and resets the **firewalld** settings to defaults. If you combine the **previous:replaced** parameter with other settings, the **firewall** role removes all existing settings before applying new ones.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.firewall/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

 Run this command on the control node to remotely check that all firewall configuration on your managed node was reset to its default values:

ansible managed-node-01.example.com -m ansible.builtin.command -a 'firewall-cmd --list-all-zones'

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.firewall/README.md file
- /usr/share/doc/rhel-system-roles/firewall/ directory

10.2. FORWARDING INCOMING TRAFFIC INFIREWALLD FROM ONE LOCAL PORT TO A DIFFERENT LOCAL PORT BY USING THE FIREWALL RHEL SYSTEM ROLE

You can use the **firewall** RHEL system role to remotely configure forwarding of incoming traffic from one local port to a different local port.

For example, if you have an environment where multiple services co-exist on the same machine and need the same default port, there are likely to become port conflicts. These conflicts can disrupt services and cause a downtime. With the **firewall** RHEL system role, you can efficiently forward traffic to alternative ports to ensure that your services can run simultaneously without modification to their configuration.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Configure firewalld

hosts: managed-node-01.example.com

tasks:

- name: Forward incoming traffic on port 8080 to 443

ansible.builtin.include role:

name: redhat.rhel_system_roles.firewall

vars: firewall:

forward_port: 8080/tcp;443;

state: enabled runtime: true permanent: true

The settings specified in the example playbook include the following:

forward port: 8080/tcp;443

Traffic coming to the local port 8080 using the TCP protocol is forwarded to the port 443.

runtime: true

Enables changes in the runtime configuration. The default is set to **true**.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.firewall/README.md file on the control node.

2. Validate the playbook syntax:

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

 On the control node, run the following command to remotely check the forwarded-ports on your managed node:

ansible managed-node-01.example.com -m ansible.builtin.command -a 'firewall-cmd --list-forward-ports'

managed-node-01.example.com | CHANGED | rc=0 >> port=8080:proto=tcp:toport=443:toaddr=

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.firewall/README.md file
- /usr/share/doc/rhel-system-roles/firewall/ directory

10.3. CONFIGURING A FIREWALLD DMZ ZONE BY USING THEFIREWALL RHEL SYSTEM ROLE

As a system administrator, you can use the **firewall** RHEL system role to configure a **dmz** zone on the **enp1s0** interface to permit **HTTPS** traffic to the zone. In this way, you enable external users to access your web servers.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Configure firewalld

hosts: managed-node-01.example.com

tasks:

- name: Creating a DMZ with access to HTTPS port and masquerading for hosts in DMZ ansible.builtin.include role:

name: redhat.rhel_system_roles.firewall

vars:

firewall:

- zone: dmz

interface: enp1s0 service: https state: enabled runtime: true permanent: true

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.firewall/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• On the control node, run the following command to remotely check the information about the **dmz** zone on your managed node:

ansible managed-node-01.example.com -m ansible.builtin.command -a 'firewall-cmd --zone=dmz --list-all'

 $managed\text{-}node\text{-}01.example.com \mid CHANGED \mid rc\text{=}0>>$

dmz (active) target: default

icmp-block-inversion: no interfaces: enp1s0

sources:

services: https ssh

ports:
protocols:
forward: no
masquerade: no
forward-ports:
source-ports:
icmp-blocks:

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.firewall/README.md file
- /usr/share/doc/rhel-system-roles/firewall/ directory

CHAPTER 11. CONFIGURING A HIGH-AVAILABILITY CLUSTER BY USING RHEL SYSTEM ROLES

With the **ha_cluster** system role, you can configure and manage a high-availability cluster that uses the Pacemaker high availability cluster resource manager.

11.1. VARIABLES OF THE HA_CLUSTER RHEL SYSTEM ROLE

In an **ha_cluster** RHEL system role playbook, you define the variables for a high availability cluster according to the requirements of your cluster deployment.

The variables you can set for an **ha cluster** RHEL system role are as follows:

ha_cluster_enable_repos

A boolean flag that enables the repositories containing the packages that are needed by the **ha_cluster** RHEL system role. When this variable is set to **true**, the default value, you must have active subscription coverage for RHEL and the RHEL High Availability Add-On on the systems that you will use as your cluster members or the system role will fail.

ha_cluster_enable_repos_resilient_storage

(RHEL 9.4 and later) A boolean flag that enables the repositories containing resilient storage packages, such as **dlm** or **gfs2**. For this option to take effect, **ha_cluster_enable_repos** must be set to **true**. The default value of this variable is **false**.

ha_cluster_manage_firewall

(RHEL 9.2 and later) A boolean flag that determines whether the **ha_cluster** RHEL system role manages the firewall. When **ha_cluster_manage_firewall** is set to **true**, the firewall high availability service and the **fence-virt** port are enabled. When **ha_cluster_manage_firewall** is set to **false**, the **ha_cluster** RHEL system role does not manage the firewall. If your system is running the **firewalld** service, you must set the parameter to **true** in your playbook.

You can use the **ha_cluster_manage_firewall** parameter to add ports, but you cannot use the parameter to remove ports. To remove ports, use the **firewall** system role directly.

In RHEL 9.2 and later, the firewall is no longer configured by default, because it is configured only when **ha_cluster_manage_firewall** is set to **true**.

ha cluster manage selinux

(RHEL 9.2 and later) A boolean flag that determines whether the **ha_cluster** RHEL system role manages the ports belonging to the firewall high availability service using the **selinux** RHEL system role. When **ha_cluster_manage_selinux** is set to **true**, the ports belonging to the firewall high availability service are associated with the SELinux port type **cluster_port_t**. When **ha_cluster_manage_selinux** is set to **false**, the **ha_cluster** RHEL system role does not manage SELinux.

If your system is running the **selinux** service, you must set this parameter to **true** in your playbook. Firewall configuration is a prerequisite for managing SELinux. If the firewall is not installed, the managing SELinux policy is skipped.

You can use the **ha_cluster_manage_selinux** parameter to add policy, but you cannot use the parameter to remove policy. To remove policy, use the **selinux** RHEL system role directly.

ha_cluster_cluster_present

A boolean flag which, if set to **true**, determines that HA cluster will be configured on the hosts according to the variables passed to the role. Any cluster configuration not specified in the playbook and not supported by the role will be lost.

If **ha_cluster_cluster_present** is set to **false**, all HA cluster configuration will be removed from the target hosts.

The default value of this variable is **true**.

The following example playbook removes all cluster configuration on **node1** and **node2**

- hosts: node1 node2

vars

ha_cluster_cluster_present: false

roles:

- rhel-system-roles.ha_cluster

ha_cluster_start_on_boot

A boolean flag that determines whether cluster services will be configured to start on boot. The default value of this variable is **true**.

ha_cluster_install_cloud_agents

(RHEL 9.5 and later) A boolean flag that determines whether resource and fence agents for cloud environments are installed. These agents are not installed by default. Alternately, you can specify the packages for cloud environments by using the **ha_cluster_fence_agent_packages** and **ha_cluster_extra_packages** variables. The default value of this variable is **false**.

ha_cluster_fence_agent_packages

List of fence agent packages to install. The default value of this variable is **fence-agents-all**, **fence-virt**.

ha cluster extra packages

List of additional packages to be installed. The default value of this variable is no packages. This variable can be used to install additional packages not installed automatically by the role, for example custom resource agents.

It is possible to specify fence agents as members of this list. However,

ha_cluster_fence_agent_packages is the recommended role variable to use for specifying fence agents, so that its default value is overridden.

ha_cluster_hacluster_password

A string value that specifies the password of the **hacluster** user. The **hacluster** user has full access to a cluster. To protect sensitive data, vault encrypt the password, as described in Encrypting content with Ansible Vault. There is no default password value, and this variable must be specified.

ha_cluster_hacluster_qdevice_password

(RHEL 9.3 and later) A string value that specifies the password of the **hacluster** user for a quorum device. This parameter is needed only if the **ha_cluster_quorum** parameter is configured to use a quorum device of type **net** and the password of the **hacluster** user on the quorum device is different from the password of the **hacluster** user specified with the **ha_cluster_hacluster_password** parameter. The **hacluster** user has full access to a cluster. To protect sensitive data, vault encrypt the password, as described in Encrypting content with Ansible Vault. There is no default value for this password.

ha_cluster_corosync_key_src

The path to Corosync **authkey** file, which is the authentication and encryption key for Corosync communication. It is highly recommended that you have a unique **authkey** value for each cluster. The key should be 256 bytes of random data.

If you specify a key for this variable, it is recommended that you vault encrypt the key, as described in Encrypting content with Ansible Vault.

If no key is specified, a key already present on the nodes will be used. If nodes do not have the same key, a key from one node will be distributed to other nodes so that all nodes have the same key. If no node has a key, a new key will be generated and distributed to the nodes.

If this variable is set, **ha cluster regenerate keys** is ignored for this key.

The default value of this variable is null.

ha cluster pacemaker key src

The path to the Pacemaker **authkey** file, which is the authentication and encryption key for Pacemaker communication. It is highly recommended that you have a unique **authkey** value for each cluster. The key should be 256 bytes of random data.

If you specify a key for this variable, it is recommended that you vault encrypt the key, as described in Encrypting content with Ansible Vault.

If no key is specified, a key already present on the nodes will be used. If nodes do not have the same key, a key from one node will be distributed to other nodes so that all nodes have the same key. If no node has a key, a new key will be generated and distributed to the nodes.

If this variable is set, **ha_cluster_regenerate_keys** is ignored for this key.

The default value of this variable is null.

ha cluster fence virt key src

The path to the **fence-virt** or **fence-xvm** pre-shared key file, which is the location of the authentication key for the **fence-virt** or **fence-xvm** fence agent.

If you specify a key for this variable, it is recommended that you vault encrypt the key, as described in Encrypting content with Ansible Vault.

If no key is specified, a key already present on the nodes will be used. If nodes do not have the same key, a key from one node will be distributed to other nodes so that all nodes have the same key. If no node has a key, a new key will be generated and distributed to the nodes. If the **ha_cluster** RHEL system role generates a new key in this fashion, you should copy the key to your nodes' hypervisor to ensure that fencing works.

If this variable is set, **ha_cluster_regenerate_keys** is ignored for this key.

The default value of this variable is null.

ha_cluster_pcsd_public_key_srcr, ha_cluster_pcsd_private_key_src

The path to the **pcsd** TLS certificate and private key. If this is not specified, a certificate-key pair already present on the nodes will be used. If a certificate-key pair is not present, a random new one will be generated.

If you specify a private key value for this variable, it is recommended that you vault encrypt the key, as described in Encrypting content with Ansible Vault.

If these variables are set, **ha_cluster_regenerate_keys** is ignored for this certificate-key pair.

The default value of these variables is null.

ha_cluster_pcsd_certificates

(RHEL 9.2 and later) Creates a **pcsd** private key and certificate using the **certificate** RHEL system role

If your system is not configured with a **pcsd** private key and certificate, you can create them in one of two ways:

- Set the ha_cluster_pcsd_certificates variable. When you set the
 ha_cluster_pcsd_certificates variable, the certificate RHEL system role is used internally
 and it creates the private key and certificate for pcsd as defined.
- Do not set the ha_cluster_pcsd_public_key_src, ha_cluster_pcsd_private_key_src, or
 the ha_cluster_pcsd_certificates variables. If you do not set any of these variables, the
 ha_cluster RHEL system role will create pcsd certificates by means of pcsd itself. The
 value of ha_cluster_pcsd_certificates is set to the value of the variable
 certificate_requests as specified in the certificate RHEL system role. For more information
 about the certificate RHEL system role, see Requesting certificates using RHEL system
 roles.

The following operational considerations apply to the use of the **ha_cluster_pcsd_certificate** variable:

- Unless you are using IPA and joining the systems to an IPA domain, the certificate RHEL system role creates self-signed certificates. In this case, you must explicitly configure trust settings outside of the context of RHEL system roles. System roles do not support configuring trust settings.
- When you set the ha_cluster_pcsd_certificates variable, do not set the ha_cluster_pcsd_public_key_src and ha_cluster_pcsd_private_key_src variables.
- When you set the **ha_cluster_pcsd_certificates** variable, **ha_cluster_regenerate_keys** is ignored for this certificate key pair.

The default value of this variable is [].

For an example **ha_cluster** RHEL system role playbook that creates TLS certificates and key files in a high availability cluster, see Creating pcsd TLS certificates and key files for a high availability cluster.

ha_cluster_regenerate_keys

A boolean flag which, when set to **true**, determines that pre-shared keys and TLS certificates will be regenerated. For more information about when keys and certificates will be regenerated, see the descriptions of the **ha_cluster_corosync_key_src**, **ha_cluster_pacemaker_key_src**, **ha_cluster_pcsd_public_key_src**, and **ha_cluster_pcsd_private_key_src** variables.

The default value of this variable is false.

ha_cluster_pcs_permission_list

Configures permissions to manage a cluster using **pcsd**. The items you configure with this variable are as follows:

- type user or group
- name user or group name
- **allow list** Allowed actions for the specified user or group:
 - read View cluster status and settings

- write Modify cluster settings except permissions and ACLs
- o grant Modify cluster permissions and ACLs
- **full** Unrestricted access to a cluster including adding and removing nodes and access to keys and certificates

The structure of the **ha_cluster_pcs_permission_list** variable and its default values are as follows:

ha_cluster_pcs_permission_list:

- type: group name: hacluster allow_list:
 - grant
 - read
 - write

ha_cluster_cluster_name

The name of the cluster. This is a string value with a default of **my-cluster**.

ha cluster transport

(RHEL 9.1 and later) Sets the cluster transport method. The items you configure with this variable are as follows:

- **type** (optional) Transport type: **knet**, **udp**, or **udpu**. The **udp** and **udpu** transport types support only one link. Encryption is always disabled for **udp** and **udpu**. Defaults to **knet** if not specified.
- **options** (optional) List of name-value dictionaries with transport options.
- **links** (optional) List of list of name-value dictionaries. Each list of name-value dictionaries holds options for one Corosync link. It is recommended that you set the **linknumber** value for each link. Otherwise, the first list of dictionaries is assigned by default to the first link, the second one to the second link, and so on.
- **compression** (optional) List of name-value dictionaries configuring transport compression. Supported only with the **knet** transport type.
- **crypto** (optional) List of name-value dictionaries configuring transport encryption. By default, encryption is enabled. Supported only with the **knet** transport type.

For a list of allowed options, see the **pcs -h cluster setup** help page or the **setup** description in the **cluster** section of the **pcs**(8) man page. For more detailed descriptions, see the **corosync.conf**(5) man page.

The structure of the **ha_cluster_transport** variable is as follows:

```
ha_cluster_transport:
type: knet
options:
- name: option1_name
    value: option1_value
- name: option2_name
    value: option2_value
links:
```

- name: option1_name value: option1_valuename: option2_name value: option2_value
- name: option1_name value: option1_valuename: option2_name value: option2_value
- compression:
- name: option1_name value: option1_value
 name: option2_name value: option2_value crypto:
 - name: option1_name value: option1_valuename: option2_name value: option2_value

For an example **ha_cluster** RHEL system role playbook that configures a transport method, see Configuring Corosync values in a high availability cluster .

ha_cluster_totem

(RHEL 9.1 and later) Configures Corosync totem. For a list of allowed options, see the **pcs -h cluster setup** help page or the **setup** description in the **cluster** section of the **pcs**(8) man page. For a more detailed description, see the **corosync.conf**(5) man page.

The structure of the **ha cluster totem** variable is as follows:

ha_cluster_totem:

options:

name: option1_name value: option1_valuename: option2_name value: option2_value

For an example **ha_cluster** RHEL system role playbook that configures a Corosync totem, see Configuring Corosync values in a high availability cluster .

ha_cluster_quorum

(RHEL 9.1 and later) Configures cluster quorum. You can configure the following items for cluster quorum:

- options (optional) List of name-value dictionaries configuring quorum. Allowed options are: auto_tie_breaker, last_man_standing, last_man_standing_window, and wait_for_all. For information about quorum options, see the votequorum(5) man page.
- **device** (optional) (RHEL 9.2 and later) Configures the cluster to use a quorum device. By default, no quorum device is used.
 - model (mandatory) Specifies a quorum device model. Only net is supported
 - **model_options** (optional) List of name-value dictionaries configuring the specified quorum device model. For model **net**, you must specify **host** and **algorithm** options.

Use the **pcs-address** option to set a custom **pcsd** address and port to connect to the **qnetd** host. If you do not specify this option, the role connects to the default **pcsd** port on the **host**.

- **generic_options** (optional) List of name-value dictionaries setting quorum device options that are not model specific.
- **heuristics_options** (optional) List of name-value dictionaries configuring quorum device heuristics.

For information about quorum device options, see the **corosync-qdevice**(8) man page. The generic options are **sync_timeout** and **timeout**. For model **net** options see the **quorum.device.net** section. For heuristics options, see the **quorum.device.heuristics** section.

To regenerate a quorum device TLS certificate, set the **ha_cluster_regenerate_keys** variable to **true**.

The structure of the **ha_cluster_quorum** variable is as follows:

ha_cluster_quorum:

options:

name: option1_name value: option1_valuename: option2_name

value: option2_value

device:

model: string model_options:

name: option1_name value: option1_valuename: option2_name value: option2_value

generic options:

name: option1_name value: option1_valuename: option2_name value: option2_value

heuristics_options:

name: option1_name value: option1_valuename: option2_name value: option2_value

For an example **ha_cluster** RHEL system role playbook that configures cluster quorum, see Configuring Corosync values in a high availability cluster . For an example **ha_cluster** RHEL system role playbook that configures a cluster using a quorum device, see Configuring a high availability cluster using a quorum device.

ha_cluster_sbd_enabled

(RHEL 9.1 and later) A boolean flag which determines whether the cluster can use the SBD node fencing mechanism. The default value of this variable is **false**. For example **ha_cluster** system role playbooks that enable SBD, see Configuring a high availability cluster with SBD node fencing by using the ha_cluster_node_options variable and Configuring a high availability cluster with SBD node fencing by using the ha_cluster variable.

ha cluster sbd options

(RHEL 9.1 and later) List of name-value dictionaries specifying SBD options. For information about these options, see the **Configuration via environment** section of the **sbd**(8) man page. Supported options are:

- delay-start defaults to false, documented as SBD_DELAY_START
- startmode defaults to always, documented as SBD_START_MODE
- timeout-action defaults to flush,reboot, documented as SBD_TIMEOUT_ACTION
- watchdog-timeout defaults to 5, documented as SBD WATCHDOG TIMEOUT

Watchdog and SBD devices can be configured on a node to node basis in one of two variables:

- ha_cluster_node_options, which you define in a playbook file (RHEL 9.5 and later). For an example ha_cluster RHEL system role playbook that uses the ha_cluster_node_options variable to configure node by node SBD options, see Configuring a high availability cluster with SBD node fencing by using the ha_cluster_node_options variable.
- **ha_cluster**, which you define in an inventory file. For an example procedure that configures node to node SBD options in an inventory file, see Configuring a high availability cluster with SBD node fencing by using the ha_cluster variable.

ha_cluster_cluster_properties

List of sets of cluster properties for Pacemaker cluster-wide configuration. Only one set of cluster properties is supported.

The structure of a set of cluster properties is as follows:

ha cluster cluster properties:

- attrs:

name: property1_name value: property1_valuename: property2_name value: property2_value

By default, no properties are set.

The following example playbook configures a cluster consisting of **node1** and **node2** and sets the **stonith-enabled** and **no-quorum-policy** cluster properties.

- hosts: node1 node2

vars:

ha_cluster_cluster_name: my-new-cluster ha_cluster_hacluster_password: password

ha_cluster_cluster_properties:

- attrs:

- name: stonith-enabled

value: 'true'

- name: no-quorum-policy

value: stop

roles:

- rhel-system-roles.ha_cluster

ha_cluster_node_options

(RHEL 9.4 and later) This variable defines settings which vary from one cluster node to another. It sets the options for the specified nodes, but does not specify which nodes form the cluster. You specify which nodes form the cluster with the **hosts** parameter in an inventory or a playbook. The items you configure with this variable are as follows:

- **node_name** (mandatory) Name of the node for which to define Pacemaker node attributes. It must match a name defined for a node.
- **pcs_address** (optional) (RHEL 9.5 and later) Address used by **pcs** to communicate with the node. You can specify a name, a FQDN or an IP address. You can specify a port as well.
- **corosync_addresses** (optional) (RHEL 9.5 and later) List of addresses used by Corosync. All nodes must have the same number of addresses. The order of the addresses must be the same for all nodes, so that the addresses belonging to a particular link are specified in the same position for all nodes.
- **sbd_watchdog_modules** (optional) (RHEL 9.5 and later) Watchdog kernel modules to be loaded, which create /dev/watchdog* devices. Defaults to an empty list if not set.
- **sbd_watchdog_modules_blocklist** (optional) (RHEL 9.5 and later) Watchdog kernel modules to be unloaded and blocked. Defaults to an empty list if not set.
- **sbd_watchdog** (optional) (RHEL 9.5 and later) Watchdog device to be used by SBD. Defaults to /dev/watchdog if not set.
- **sbd_devices** (optional) (RHEL 9.5 and later) Devices to use for exchanging SBD messages and for monitoring. Defaults to an empty list if not set. Always refer to the devices using the long, stable device name (/dev/disk/by-id/).
- **attributes** (optional) List of sets of Pacemaker node attributes for the node. Currently, only one set is supported. The first set is used and the rest are ignored.
- **utilization** (optional) (RHEL 9.5 and later) List of sets of the node's utilization. The field value must be an integer. Currently, only one set is supported. The first set is used and the rest are ignored.

The structure of the **ha_cluster_node_options** variable is as follows:

```
ha_cluster_node_options:
```

- node_name: node1

pcs_address: node1-address

corosync_addresses:

- 192.168.1.11
- 192.168.2.11

sbd watchdog modules:

- module1
- module2

sbd_watchdog_modules_blocklist:

- module3

sbd_watchdog: /dev/watchdog2

sbd devices:

- /dev/disk/by-id/00001
- /dev/disk/by-id/000002
- /dev/disk/by-id/000003

attributes:

- attrs:

name: attribute1value: value1_node1name: attribute2value: value2_node1

utilization:

name: utilization1value: value1_node1name: utilization2value: value2_node1

- node name: node2

pcs_address: node2-address:2224

corosync_addresses:

- 192.168.1.12

- 192.168.2.12

sbd_watchdog_modules:

- module1

sbd watchdog modules blocklist:

- module3

sbd watchdog: /dev/watchdog1

sbd devices:

- /dev/disk/by-id/00001
- /dev/disk/by-id/000002
- /dev/disk/by-id/000003

attributes:

- attrs:

name: attribute1value: value1_node2name: attribute2value: value2_node2

utilization:

- attrs:

name: utilization1value: value1_node2name: utilization2value: value2 node2

By default, no node options are defined.

For an example **ha_cluster** RHEL system role playbook that includes node options configuration, see Configuring a high availability cluster with node attributes .

ha_cluster_resource_primitives

This variable defines pacemaker resources configured by the RHEL system role, including fencing resources. You can configure the following items for each resource:

- id (mandatory) ID of a resource.
- agent (mandatory) Name of a resource or fencing agent, for example
 ocf:pacemaker:Dummy or stonith:fence_xvm. It is mandatory to specify stonith: for
 STONITH agents. For resource agents, it is possible to use a short name, such as Dummy,
 instead of ocf:pacemaker:Dummy. However, if several agents with the same short name
 are installed, the role will fail as it will be unable to decide which agent should be used.
 Therefore, it is recommended that you use full names when specifying a resource agent.

- **instance_attrs** (optional) List of sets of the resource's instance attributes. Currently, only one set is supported. The exact names and values of attributes, as well as whether they are mandatory or not, depend on the resource or fencing agent.
- **meta_attrs** (optional) List of sets of the resource's meta attributes. Currently, only one set is supported.
- copy_operations_from_agent (optional) (RHEL 9.3 and later) Resource agents usually define default settings for resource operations, such as interval and timeout, optimized for the specific agent. If this variable is set to true, then those settings are copied to the resource configuration. Otherwise, clusterwide defaults apply to the resource. If you also define resource operation defaults for the resource with the
 ha cluster resource operation defaults role variable, you can set this to false. The
 - ha_cluster_resource_operation_defaults role variable, you can set this to false. The default value of this variable is true.
- operations (optional) List of the resource's operations.
 - **action** (mandatory) Operation action as defined by pacemaker and the resource or fencing agent.
 - **attrs** (mandatory) Operation options, at least one option must be specified. (RHEL 9.5 and later)
- **utilization** (optional) List of sets of the resource's utilization. The **value** field must be an integer. Only one set is supported, so the first set is used and the rest are ignored.

The structure of the resource definition that you configure with the **ha_cluster** RHEL system role is as follows:

 id: resource-id agent: resource-agent instance attrs:

- attrs:

name: attribute1_name value: attribute1_valuename: attribute2_name value: attribute2_value

meta_attrs:

- attrs:

name: meta_attribute1_name
value: meta_attribute1_value
name: meta_attribute2_name
value: meta_attribute2_value

copy_operations_from_agent: bool operations:

action: operation1-action attrs:

 name: operation1_attribute1_name value: operation1_attribute1_value
 name: operation1_attribute2_name value: operation1_attribute2_value

- action: operation2-action

attrs:

- name: operation2_attribute1_name

value: operation2_attribute1_value - name: operation2_attribute2_name value: operation2_attribute2_value

By default, no resources are defined.

For an example **ha_cluster** RHEL system role playbook that includes resource configuration, see Configuring a high availability cluster with fencing and resources .

ha cluster resource groups

This variable defines pacemaker resource groups configured by the system role. You can configure the following items for each resource group:

- id (mandatory) ID of a group.
- **resources** (mandatory) List of the group's resources. Each resource is referenced by its ID and the resources must be defined in the **ha_cluster_resource_primitives** variable. At least one resource must be listed.
- **meta_attrs** (optional) List of sets of the group's meta attributes. Currently, only one set is supported.

The structure of the resource group definition that you configure with the **ha_cluster** RHEL system role is as follows:

ha_cluster_resource_groups:

- id: group-id

resource_ids:

- resource1-id
- resource2-id

meta_attrs:

- attrs:
 - name: group_meta_attribute1_name value: group_meta_attribute1_value
 name: group_meta_attribute2_name value: group_meta_attribute2_value

By default, no resource groups are defined.

For an example **ha_cluster** RHEL system role playbook that includes resource group configuration, see Configuring a high availability cluster with fencing and resources .

ha_cluster_resource_clones

This variable defines pacemaker resource clones configured by the system role. You can configure the following items for a resource clone:

- **resource_id** (mandatory) Resource to be cloned. The resource must be defined in the **ha cluster resource primitives** variable or the **ha cluster resource groups** variable.
- **promotable** (optional) Indicates whether the resource clone to be created is a promotable clone, indicated as **true** or **false**.
- **id** (optional) Custom ID of the clone. If no ID is specified, it will be generated. A warning will be displayed if this option is not supported by the cluster.

• **meta_attrs** (optional) - List of sets of the clone's meta attributes. Currently, only one set is supported.

The structure of the resource clone definition that you configure with the **ha_cluster** RHEL system role is as follows:

ha_cluster_resource_clones:
- resource_id: resource-to-be-cloned
promotable: true
id: custom-clone-id
meta_attrs:
- attrs:
- name: clone_meta_attribute1_name
 value: clone_meta_attribute1_value
- name: clone_meta_attribute2_name

value: clone_meta_attribute2_value

By default, no resource clones are defined.

For an example **ha_cluster** RHEL system role playbook that includes resource clone configuration, see Configuring a high availability cluster with fencing and resources .

ha cluster resource defaults

(RHEL 9.3 and later) This variable defines sets of resource defaults. You can define multiple sets of defaults and apply them to resources of specific agents using rules. The defaults you specify with the **ha_cluster_resource_defaults** variable do not apply to resources which override them with their own defined values.

Only meta attributes can be specified as defaults.

You can configure the following items for each defaults set:

- id (optional) ID of the defaults set. If not specified, it is autogenerated.
- **rule** (optional) Rule written using **pcs** syntax defining when and for which resources the set applies. For information on specifying a rule, see the **resource defaults set create** section of the **pcs**(8) man page.
- score (optional) Weight of the defaults set.
- attrs (optional) Meta attributes applied to resources as defaults.

The structure of the **ha_cluster_resource_defaults** variable is as follows:

meta_attrs:
- id: defaults-set-1-id
rule: rule-string
score: score-value
attrs:
- name: meta_attribute1_name
value: meta_attribute1_value
- name: meta_attribute2_name
value: meta_attribute2_value
- id: defaults-set-2-id

rule: rule-string

ha cluster resource defaults:

score: score-value attrs:

name: meta_attribute3_name
 value: meta_attribute3_value
 name: meta_attribute4_name
 value: meta_attribute4_value

For an example **ha_cluster** RHEL system role playbook that configures resource defaults, see Configuring a high availability cluster with resource and resource operation defaults.

ha_cluster_resource_operation_defaults

(RHEL 9.3 and later) This variable defines sets of resource operation defaults. You can define multiple sets of defaults and apply them to resources of specific agents and specific resource operations using rules. The defaults you specify with the **ha_cluster_resource_operation_defaults** variable do not apply to resource operations which override them with their own defined values. By default, the **ha_cluster** RHEL system role configures resources to define their own values for resource operations. For information about overriding these defaults with the **ha_cluster_resource_operations_defaults** variable, see the description of the **copy_operations_from_agent** item in **ha_cluster_resource_primitives**.

Only meta attributes can be specified as defaults.

The structure of the **ha_cluster_resource_operations_defaults** variable is the same as the structure for the **ha_cluster_resource_defaults** variable, with the exception of how you specify a rule. For information about specifying a rule to describe the resource operation to which a set applies, see the **resource op defaults set create** section of the **pcs**(8) man page.

ha_cluster_stonith_levels

(RHEL 9.4 and later) This variable defines STONITH levels, also known as fencing topology. Fencing levels configure a cluster to use multiple devices to fence nodes. You can define alternative devices in case one device fails and you can require multiple devices to all be executed successfully to consider a node successfully fenced. For more information on fencing levels, see Configuring fencing levels in Configuring and managing high availability clusters.

You can configure the following items when defining fencing levels:

- **level** (mandatory) Order in which to attempt the fencing level. Pacemaker attempts levels in ascending order until one succeeds.
- target (optional) Name of a node this level applies to.
- You must specify one of the following three selections:
 - **target_pattern** POSIX extended regular expression matching the names of the nodes this level applies to.
 - target attribute Name of a node attribute that is set for the node this level applies to.
 - **target_attribute** and **target_value** Name and value of a node attribute that is set for the node this level applies to.
- **resouce_ids** (mandatory) List of fencing resources that must all be tried for this level. By default, no fencing levels are defined.

The structure of the fencing levels definition that you configure with the **ha_cluster** RHEL system role is as follows:

```
ha cluster stonith levels:
 - level: 1..9
  target: node name
  target_pattern: node_name_regular_expression
  target attribute: node attribute name
  target_value: node_attribute_value
  resource_ids:
   - fence_device_1
   - fence device 2
 - level: 1..9
  target: node name
  target_pattern: node_name_regular_expression
  target attribute: node attribute name
  target value: node attribute value
  resource ids:
   - fence device 1
   - fence_device_2
```

For an example **ha_cluster** RHEL system role playbook that configures fencing defaults, see Configuring a high availability cluster with fencing levels .

ha_cluster_constraints_location

This variable defines resource location constraints. Resource location constraints indicate which nodes a resource can run on. You can specify a resources specified by a resource ID or by a pattern, which can match more than one resource. You can specify a node by a node name or by a rule. You can configure the following items for a resource location constraint:

- resource (mandatory) Specification of a resource the constraint applies to.
- **node** (mandatory) Name of a node the resource should prefer or avoid.
- id (optional) ID of the constraint. If not specified, it will be autogenerated.
- **options** (optional) List of name-value dictionaries.
 - **score** Sets the weight of the constraint.
 - A positive **score** value means the resource prefers running on the node.
 - A negative **score** value means the resource should avoid running on the node.
 - A **score** value of **-INFINITY** means the resource must avoid running on the node.
 - If **score** is not specified, the score value defaults to **INFINITY**.

By default no resource location constraints are defined.

The structure of a resource location constraint specifying a resource ID and node name is as follows:

ha_cluster_constraints_location:

resource:
 id: resource-id
 node: node-name
 id: constraint-id
 options:

- name: score

value: score-value - name: option-name value: option-value

The items that you configure for a resource location constraint that specifies a resource pattern are the same items that you configure for a resource location constraint that specifies a resource ID, with the exception of the resource specification itself. The item that you specify for the resource specification is as follows:

• **pattern** (mandatory) - POSIX extended regular expression resource IDs are matched against.

The structure of a resource location constraint specifying a resource pattern and node name is as follows:

ha_cluster_constraints_location:

- resource:

pattern: resource-pattern

node: node-name id: constraint-id

options:

name: score value: score-value

- name: resource-discovery value: resource-discovery-value

You can configure the following items for a resource location constraint that specifies a resource ID and a rule:

- resource (mandatory) Specification of a resource the constraint applies to.
 - id (mandatory) Resource ID.
 - **role** (optional) The resource role to which the constraint is limited: **Started**, **Unpromoted**, **Promoted**.
- **rule** (mandatory) Constraint rule written using **pcs** syntax. For further information, see the **constraint location** section of the **pcs**(8) man page.
- Other items to specify have the same meaning as for a resource constraint that does not specify a rule.

The structure of a resource location constraint that specifies a resource ID and a rule is as follows:

ha_cluster_constraints_location:

- resource:

id: resource-id role: resource-role rule: rule-string id: constraint-id options:

name: score value: score-value

- name: resource-discovery value: resource-discovery-value

The items that you configure for a resource location constraint that specifies a resource pattern and a rule are the same items that you configure for a resource location constraint that specifies a resource ID and a rule, with the exception of the resource specification itself. The item that you specify for the resource specification is as follows:

• **pattern** (mandatory) - POSIX extended regular expression resource IDs are matched against.

The structure of a resource location constraint that specifies a resource pattern and a rule is as follows:

ha_cluster_constraints_location:

- resource:

pattern: resource-pattern role: resource-role rule: rule-string id: constraint-id options:

name: score value: score-value

 name: resource-discovery value: resource-discovery-value

For an example **ha_cluster** RHEL system role playbook that creates a cluster with resource constraints, see Configuring a high availability cluster with resource constraints.

ha_cluster_constraints_colocation

This variable defines resource colocation constraints. Resource colocation constraints indicate that the location of one resource depends on the location of another one. There are two types of colocation constraints: a simple colocation constraint for two resources, and a set colocation constraint for multiple resources.

You can configure the following items for a simple resource colocation constraint:

- resource_follower (mandatory) A resource that should be located relative to resource_leader.
 - id (mandatory) Resource ID.
 - role (optional) The resource role to which the constraint is limited: Started, Unpromoted, Promoted.
- **resource_leader** (mandatory) The cluster will decide where to put this resource first and then decide where to put **resource follower**.
 - id (mandatory) Resource ID.
 - role (optional) The resource role to which the constraint is limited: Started, Unpromoted, Promoted.
- id (optional) ID of the constraint. If not specified, it will be autogenerated.
- options (optional) List of name-value dictionaries.
 - **score** Sets the weight of the constraint.
 - Positive score values indicate the resources should run on the same node.

- Negative score values indicate the resources should run on different nodes.
- A **score** value of **+INFINITY** indicates the resources must run on the same node.
- A **score** value of **-INFINITY** indicates the resources must run on different nodes.
- If **score** is not specified, the score value defaults to **INFINITY**.

By default no resource colocation constraints are defined.

The structure of a simple resource colocation constraint is as follows:

ha_cluster_constraints_colocation:

- resource_follower: id: resource-id1 role: resource-role1 resource_leader: id: resource-id2 role: resource-role2

id: constraint-id

options:

name: score value: score-valuename: option-name value: option-value

You can configure the following items for a resource set colocation constraint:

- resource_sets (mandatory) List of resource sets.
 - **resource_ids** (mandatory) List of resources in a set.
 - **options** (optional) List of name-value dictionaries fine-tuning how resources in the sets are treated by the constraint.
- **id** (optional) Same values as for a simple colocation constraint.
- **options** (optional) Same values as for a simple colocation constraint.

The structure of a resource set colocation constraint is as follows:

ha_cluster_constraints_colocation:

- resource_sets:
 - resource ids:
 - resource-id1
 - resource-id2

options:

name: option-name value: option-value

id: constraint-id

options:

name: score value: score-valuename: option-name value: option-value For an example **ha_cluster** RHEL system role playbook that creates a cluster with resource constraints, see Configuring a high availability cluster with resource constraints.

ha_cluster_constraints_order

This variable defines resource order constraints. Resource order constraints indicate the order in which certain resource actions should occur. There are two types of resource order constraints: a simple order constraint for two resources, and a set order constraint for multiple resources. You can configure the following items for a simple resource order constraint:

- resource_first (mandatory) Resource that the resource_then resource depends on.
 - id (mandatory) Resource ID.
 - action (optional) The action that must complete before an action can be initiated for the resource_then resource. Allowed values: start, stop, promote, demote.
- **resource_then** (mandatory) The dependent resource.
 - id (mandatory) Resource ID.
 - action (optional) The action that the resource can execute only after the action on the resource_first resource has completed. Allowed values: start, stop, promote, demote.
- id (optional) ID of the constraint. If not specified, it will be autogenerated.
- options (optional) List of name-value dictionaries.

By default no resource order constraints are defined.

The structure of a simple resource order constraint is as follows:

ha_cluster_constraints_order:

- resource first:

id: resource-id1

action: resource-action1

resource_then: id: resource-id2

action: resource-action2

id: constraint-id

options:

- name: score

value: score-value

- name: option-name

value: option-value

You can configure the following items for a resource set order constraint:

- resource_sets (mandatory) List of resource sets.
 - resource_ids (mandatory) List of resources in a set.
 - **options** (optional) List of name-value dictionaries fine-tuning how resources in the sets are treated by the constraint.
- id (optional) Same values as for a simple order constraint.
- options (optional) Same values as for a simple order constraint.

The structure of a resource set order constraint is as follows:

ha_cluster_constraints_order:

- resource sets:
 - resource ids:
 - resource-id1
 - resource-id2

options:

name: option-name value: option-value

id: constraint-id

options:

name: score value: score-valuename: option-name value: option-value

For an example **ha_cluster** RHEL system role playbook that creates a cluster with resource constraints, see Configuring a high availability cluster with resource constraints.

ha_cluster_constraints_ticket

This variable defines resource ticket constraints. Resource ticket constraints indicate the resources that depend on a certain ticket. There are two types of resource ticket constraints: a simple ticket constraint for one resource, and a ticket order constraint for multiple resources.

You can configure the following items for a simple resource ticket constraint:

- resource (mandatory) Specification of a resource the constraint applies to.
 - id (mandatory) Resource ID.
 - role (optional) The resource role to which the constraint is limited: Started,
 Unpromoted, Promoted.
- **ticket** (mandatory) Name of a ticket the resource depends on.
- id (optional) ID of the constraint. If not specified, it will be autogenerated.
- options (optional) List of name-value dictionaries.
 - **loss-policy** (optional) Action to perform on the resource if the ticket is revoked.

By default no resource ticket constraints are defined.

The structure of a simple resource ticket constraint is as follows:

ha_cluster_constraints_ticket:

- resource:

id: resource-id role: resource-role ticket: ticket-name id: constraint-id options:

name: loss-policy value: loss-policy-valuename: option-name value: option-value You can configure the following items for a resource set ticket constraint:

- resource_sets (mandatory) List of resource sets.
 - resource_ids (mandatory) List of resources in a set.
 - options (optional) List of name-value dictionaries fine-tuning how resources in the sets are treated by the constraint.
- ticket (mandatory) Same value as for a simple ticket constraint.
- **id** (optional) Same value as for a simple ticket constraint.
- **options** (optional) Same values as for a simple ticket constraint.

The structure of a resource set ticket constraint is as follows:

ha cluster constraints ticket:

- resource sets:
 - resource ids:
 - resource-id1
 - resource-id2

options:

- name: option-name value: option-value

ticket: ticket-name id: constraint-id options:

- name: option-name value: option-value

For an example ha_cluster RHEL system role playbook that creates a cluster with resource constraints, see Configuring a high availability cluster with resource constraints.

ha_cluster_acls

(RHEL 9.5 and later) This variable defines ACL roles, users and groups. You can configure the following items for **acl_roles**:

- id (mandatory) ID of an ACL role.
- **description** (optional) Description of the ACL role.
- **permissions** (optional) List of ACL role permissions.
 - kind (mandatory) The access being granted. Allowed values are read, write, and deny.
 - xpath (optional) An XPath specification selecting an XML element in the CIB to which the permission applies. It is mandatory to specify exactly one of the items: xpath or reference.
 - o reference (optional) The ID of an XML element in the CIB to which the permission applies. It is mandatory to specify exactly one of the items: xpath or reference. The ID must exist.

You can configure the following items for **acl_users**:

a id (manufatami) ID afam ACI was

- Ia (mandatory) ID of an ACL user.
- roles (optional) List of ACL Role IDs assigned to the user.

You can configure the following items for **acl_group**:

- id (mandatory) ID of an ACL group.
- roles (optional) List of ACL Role IDs assigned to the group.

The structure of an ACL definition is as follows:

```
ha_cluster_acls:
 acl roles:
  - id: role-id-1
   description: role description
    permissions:
    - kind: access-type
      xpath: XPath expression
     - kind: access-type
      reference: cib-element-id
  - id: role-id-2
    permissions:
     - kind: access-type
      xpath: XPath expression
 acl users:
  - id: user-name
   roles:
     - role-id-1
     - role-id-2
 acl_groups:
  - id: group-name
    roles:
     - role-id-2
```

To enable ACLS in the cluster, you must configure the **enable-acl** cluster property:

```
ha_cluster_cluster_properties:
    - attrs:
    - name: enable-acl
    value: 'true'
```

For an example **ha_cluster** RHEL system role playbook that creates a cluster with ACL roles, users, and groups, see Configuring a high availability cluster that implements access control lists (ACLS) by using the RHEL system role.

ha cluster alerts

(RHEL 9.5 and later) This variable defines Pacemaker alerts.



NOTE

The **ha_cluster** role configures the cluster to call external programs to handle alerts. You must provide the programs and distribute them to cluster nodes.

You can configure the following items for alerts:

- id (mandatory) ID of an alert
- **ipath** (mandatory) Path to the alert agent executable.
- **description** (optional) Description of the alert.
- **instance_attrs** (optional) List of sets of the alert's instance attributes. Only one set is supported. The first set is used and the rest are ignored.
- **meta_attrs** (optional) List of sets of the alert's meta attributes. Only one set is supported. The first set is used and the rest are ignored. ***recipients** (optional) List of alert's recipients.

You can configure the following items for **recipients**:

- **value** (mandatory) Value of a recipient.
- id (optional) ID of the recipient.
- **description** (optional) Description of the recipient.
- **instance_attrs** (optional) List of sets of the recipient's instance attributes. Only one set is supported. The first set is used and the rest are ignored.
- **meta_attrs** (optional) List of sets of the recipient's meta attributes. Only one set is supported. The first set is used and the rest are ignored.

The structure of an alert definition is as follows:

```
ha cluster alerts:
 - id: alert1
  path: /alert1/path
  description: Alert1 description
  instance attrs:
   - attrs:
     name: alert_attr1_name
      value: alert_attr1_value
  meta_attrs:
   - attrs:
     - name: alert meta attr1 name
      value: alert meta attr1 value
  recipients:
   - value: recipient value
     id: recipient1
     description: Recipient1 description
     instance_attrs:
      - attrs:
       name: recipient_attr1_name
        value: recipient attr1 value
     meta attrs:
      - attrs:
       - name: recipient_meta_attr1_name
        value: recipient meta attr1 value
```

For an example **ha_cluster** RHEL system role playbook that configures a cluster with alerts, see Configuring alerts for a high availability cluster by using the ha_cluster RHEL system role.

ha_cluster_qnetd

(RHEL 9.2 and later) This variable configures a **qnetd** host which can then serve as an external quorum device for clusters.

You can configure the following items for a **qnetd** host:

- present (optional) If true, configure a qnetd instance on the host. If false, remove qnetd configuration from the host. The default value is false. If you set this true, you must set ha_cluster_cluster_present to false.
- **start_on_boot** (optional) Configures whether the **qnetd** instance should start automatically on boot. The default value is **true**.
- **regenerate_keys** (optional) Set this variable to **true** to regenerate the **qnetd** TLS certificate. If you regenerate the certificate, you must either re-run the role for each cluster to connect it to the **qnetd** host again or run **pcs** manually.

You cannot run **qnetd** on a cluster node because fencing would disrupt **qnetd** operation. For an example **ha_cluster** RHEL system role playbook that configures a cluster using a quorum device, see Configuring a cluster using a quorum device.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory

11.2. SPECIFYING AN INVENTORY FOR THEHA_CLUSTER RHEL SYSTEM ROLE

When configuring an HA cluster using the **ha_cluster** RHEL system role playbook, you configure the names and addresses of the nodes for the cluster in an inventory.

For each node in an inventory, you can optionally specify the following items:

- **node_name** the name of a node in a cluster.
- **pcs_address** an address used by **pcs** to communicate with the node. It can be a name, FQDN or an IP address and it can include a port number.
- **corosync_addresses** list of addresses used by Corosync. All nodes which form a particular cluster must have the same number of addresses. The order of the addresses must be the same for all nodes, so that the addresses belonging to a particular link are specified in the same position for all nodes.

The following example shows an inventory with targets **node1** and **node2**. **node1** and **node2** must be either fully qualified domain names or must otherwise be able to connect to the nodes as when, for example, the names are resolvable through the /etc/hosts file.

all: hosts: node1:
ha_cluster:
node_name: node-A
pcs_address: node1-address
corosync_addresses:
- 192.168.1.11
- 192.168.2.11
node2:
ha_cluster:
node_name: node-B
pcs_address: node2-address:2224
corosync_addresses:
- 192.168.1.12
- 192.168.2.12

In RHEL 9.1 and later, you can optionally configure watchdog and SBD devices for each node in an inventory. All SBD devices must be shared to and accessible from all nodes. Watchdog devices can be different for each node as well. For an example procedure that configures SBD node fencing in an inventory file, see Configuring a high availability cluster with SBD node fencing by using the ha_cluster variable.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory

11.3. CREATING PCSD TLS CERTIFICATES AND KEY FILES FOR A HIGH AVAILABILITY CLUSTER

(RHEL 9.2 and later) The connection between cluster nodes is secured using Transport Layer Security (TLS) encryption. By default, the **pcsd** daemon generates self-signed certificates. For many deployments, however, you may want to replace the default certificates with certificates issued by a certificate authority of your company and apply your company certificate policies for **pcsd**.

You can use the **ha_cluster** RHEL system role to create TLS certificates and key files in a high availability cluster. When you run this playbook, the **ha_cluster** RHEL system role uses the **certificate** RHEL system role internally to manage TLS certificates.



WARNING

The **ha_cluster** RHEL system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.

- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster RHEL system role. For general information about creating an inventory file, see Preparing a control node on RHEL 9.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

```
$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>
```

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

```
cluster_password: <cluster_password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
-name: Create a high availability cluster
hosts: node1 node2
vars_files:
    - ~/vault.yml
tasks:
    - name: Create TLS certificates and key files in a high availability cluster
    ansible.builtin.include_role:
    name: redhat.rhel_system_roles.ha_cluster
    vars:
    ha_cluster_cluster_name: my-new-cluster
    ha_cluster_hacluster_password: "{{ cluster_password }}"
    ha_cluster_manage_firewall: true
    ha_cluster_manage_selinux: true
    ha_cluster_pcsd_certificates:
    - name: FILENAME
    common_name: "{{ ansible_hostname }}"
    ca: self-sign
```

The settings specified in the example playbook include the following:

```
ha_cluster_cluster_name: <cluster_name>
The name of the cluster you are creating.
```

ha_cluster_hacluster_password: <password>

The password of the **hacluster** user. The **hacluster** user has full access to a cluster.

ha_cluster_manage_firewall: true

A variable that determines whether the **ha_cluster** RHEL system role manages the firewall.

ha cluster manage selinux: true

A variable that determines whether the **ha_cluster** RHEL system role manages the ports of the firewall high availability service using the **selinux** RHEL system role.

ha_cluster_pcsd_certificates: <certificate_properties>

A variable that creates a self-signed **pcsd** certificate and private key files in /**var/lib/pcsd**. In this example, the **pcsd** certificate has the file name **FILENAME.crt** and the key file is named **FILENAME.key**.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory
- Requesting certificates using RHEL system roles

11.4. CONFIGURING A HIGH AVAILABILITY CLUSTER RUNNING NO RESOURCES

You can use the **ha_cluster** system role to configure a basic cluster in a simple, automatic way. Once you have created a basic cluster, you can use the **pcs** command-line interface to configure the other cluster components and behaviors on a resource-by-resource basis. The following example procedure configures a basic two-node cluster with no fencing configured using the minimum required parameters.



WARNING

The **ha_cluster** system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

• You have prepared the control node and the managed nodes .

- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster system role. For general information about creating an inventory file, see Preparing a control node on RHEL 9.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

```
$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault password>
```

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

```
cluster_password: <cluster_password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
-name: Create a high availability cluster hosts: node1 node2 vars_files:

~/vault.yml
tasks:
name: Create cluster with minimum required parameters and no fencing ansible.builtin.include_role:

name: redhat.rhel_system_roles.ha_cluster
vars:
ha_cluster_cluster_name: my-new-cluster
ha_cluster_hacluster_password: "{{ cluster_password }}"
ha_cluster_manage_firewall: true
ha_cluster_manage_selinux: true
```

The settings specified in the example playbook include the following:

```
ha_cluster_cluster_name: <cluster_name>
The name of the cluster you are creating.
```

ha_cluster_password: <password>

The password of the **hacluster** user. The **hacluster** user has full access to a cluster.

ha_cluster_manage_firewall: true

A variable that determines whether the **ha_cluster** RHEL system role manages the firewall.

ha_cluster_manage_selinux: true

A variable that determines whether the **ha_cluster** RHEL system role manages the ports of the firewall high availability service using the **selinux** RHEL system role.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory

11.5. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH FENCING AND RESOURCES

The specific components of a cluster configuration depend on your individual needs, which vary between sites. The following example procedure shows the formats for configuring different cluster components by using the **ha_cluster** RHEL system role. The configured cluster includes a fencing device, cluster resources, resource groups, and a cloned resource.



WARNING

The **ha_cluster** RHEL system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.

• The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster RHEL system role. For general information about creating an inventory file, see Preparing a control node on RHEL 9.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

cluster_password: <cluster_password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Create a high availability cluster
 hosts: node1 node2
 vars files:
  - ~/vault.yml
 tasks:
  - name: Create cluster with fencing and resources
   ansible.builtin.include_role:
    name: redhat.rhel_system_roles.ha_cluster
   vars:
    ha cluster cluster name: my-new-cluster
    ha_cluster_hacluster_password: "{{ cluster_password }}"
    ha_cluster_manage_firewall: true
    ha_cluster_manage_selinux: true
    ha cluster resource primitives:
      - id: xvm-fencing
       agent: 'stonith:fence_xvm'
       instance_attrs:
        - attrs:
           - name: pcmk host list
            value: node1 node2
      - id: simple-resource
       agent: 'ocf:pacemaker:Dummy'
      - id: resource-with-options
       agent: 'ocf:pacemaker:Dummy'
       instance attrs:
        - attrs:
           - name: fake
            value: fake-value
           - name: passwd
            value: passwd-value
       meta_attrs:
```

```
- attrs:
      - name: target-role
       value: Started
      - name: is-managed
       value: 'true'
  operations:
   - action: start
     attrs:
      - name: timeout
       value: '30s'
   - action: monitor
     attrs:
      - name: timeout
       value: '5'
      - name: interval
       value: '1min'
 - id: dummy-1
  agent: 'ocf:pacemaker:Dummy'
 - id: dummy-2
  agent: 'ocf:pacemaker:Dummy'
 - id: dummy-3
  agent: 'ocf:pacemaker:Dummy'
 - id: simple-clone
  agent: 'ocf:pacemaker:Dummy'
 - id: clone-with-options
  agent: 'ocf:pacemaker:Dummy'
ha_cluster_resource_groups:
 - id: simple-group
  resource ids:
   - dummy-1
   - dummy-2
  meta_attrs:
   - attrs:
      - name: target-role
       value: Started
      - name: is-managed
       value: 'true'
 - id: cloned-group
  resource_ids:
   - dummy-3
ha_cluster_resource_clones:
 - resource_id: simple-clone
 - resource_id: clone-with-options
  promotable: yes
  id: custom-clone-id
  meta attrs:
   - attrs:
      - name: clone-max
       value: '2'
      - name: clone-node-max
       value: '1'
 - resource_id: cloned-group
  promotable: yes
```

ha_cluster_name: <cluster_name>

The name of the cluster you are creating.

ha cluster hacluster password: <password>

The password of the **hacluster** user. The **hacluster** user has full access to a cluster.

ha_cluster_manage_firewall: true

A variable that determines whether the **ha cluster** RHEL system role manages the firewall.

ha_cluster_manage_selinux: true

A variable that determines whether the **ha_cluster** RHEL system role manages the ports of the firewall high availability service using the **selinux** RHEL system role.

ha_cluster_resource_primitives: <cluster_resources>

A list of resource definitions for the Pacemaker resources configured by the ha_cluster RHEL system role, including fencing

ha_cluster_resource_groups: <resource_groups>

A list of resource group definitions configured by the **ha cluster** RHEL system role.

ha_cluster_resource_clones: <resource_clones>

A list of resource clone definitions configured by the **ha_cluster** RHEL system role.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory
- Configuring fencing in a Red Hat High Availability cluster

11.6. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH RESOURCE AND RESOURCE OPERATION DEFAULTS

(RHEL 9.3 and later) In your cluster configuration, you can change the Pacemaker default values of a resource option for all resources. You can also change the default value for all resource operations in the cluster.

For information about changing the default value of a resource option, see Changing the default value of a resource option. For information about global resource operation defaults, see Configuring global resource operation defaults.

The following example procedure uses the **ha_cluster** RHEL system role to create a high availability cluster that defines resource and resource operation defaults.



WARNING

The **ha_cluster** RHEL system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster RHEL system role. For general information about creating an inventory file, see Preparing a control node on RHEL 9.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

cluster_password: <cluster_password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Create a high availability cluster

hosts: node1 node2

vars files:

- ~/vault.yml

tasks:

 name: Create cluster with fencing and resource operation defaults ansible.builtin.include_role:

```
name: redhat.rhel_system_roles.ha_cluster
vars:
 ha cluster cluster name: my-new-cluster
 ha_cluster_hacluster_password: "{{ cluster_password }}"
 ha cluster manage firewall: true
 ha cluster manage selinux: true
 # Set a different resource-stickiness value during
 # and outside work hours. This allows resources to
 # automatically move back to their most
 # preferred hosts, but at a time that
 # does not interfere with business activities.
 ha_cluster_resource_defaults:
  meta_attrs:
   - id: core-hours
    rule: date-spec hours=9-16 weekdays=1-5
    score: 2
    attrs:
     - name: resource-stickiness
       value: INFINITY
   - id: after-hours
    score: 1
    attrs:
      - name: resource-stickiness
       value: 0
 # Default the timeout on all 10-second-interval
 # monitor actions on IPaddr2 resources to 8 seconds.
 ha_cluster_resource_operation_defaults:
  meta_attrs:
   - rule: resource ::IPaddr2 and op monitor interval=10s
    score: INFINITY
    attrs:
      - name: timeout
       value: 8s
```

ha cluster cluster name: <cluster_name>

The name of the cluster you are creating.

ha_cluster_hacluster_password: <password>

The password of the **hacluster** user. The **hacluster** user has full access to a cluster.

ha_cluster_manage_firewall: true

A variable that determines whether the **ha_cluster** RHEL system role manages the firewall.

ha cluster manage selinux: true

A variable that determines whether the **ha_cluster** RHEL system role manages the ports of the firewall high availability service using the **selinux** RHEL system role.

ha_cluster_resource_defaults: < resource_defaults>

A variable that defines sets of resource defaults.

ha_cluster_resource_operation_defaults: <resource_operation_defaults>

A variable that defines sets of resource operation defaults.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha cluster/ directory

11.7. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH FENCING LEVELS

(RHEL 9.4 and later) When you configure multiple fencing devices for a node, you need to define fencing levels for those devices to determine the order that Pacemaker will use the devices to attempt to fence a node. For information about fencing levels, see Configuring fencing levels.

The following example procedure uses the **ha_cluster** RHEL system role to create a high availability cluster that defines fencing levels.



WARNING

The **ha_cluster** RHEL system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster RHEL system role. For general information about creating an inventory file, see Preparing a control node on RHEL 9.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml
New Vault password>

Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

cluster_password: <cluster_password>
fence1_password: <fence1_password>
fence2_password: <fence2_password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml. This example playbook file configures a cluster running the **firewalld** and **selinux** services.

```
- name: Create a high availability cluster
 hosts: node1 node2
 vars files:
  - ~/vault.yml
 tasks:
  - name: Configure a cluster that defines fencing levels
   ansible.builtin.include_role:
     name: redhat.rhel_system_roles.ha_cluster
   vars:
     ha_cluster_cluster_name: my-new-cluster
     ha_cluster_hacluster_password: "{{ cluster_password }}"
     ha cluster manage firewall: true
     ha cluster manage selinux: true
     ha_cluster_resource_primitives:
      - id: apc1
       agent: 'stonith:fence_apc_snmp'
       instance attrs:
        - attrs:
           - name: ip
            value: apc1.example.com
           - name: username
            value: user
           - name: password
            value: "{{ fence1_password }}"
           - name: pcmk host map
            value: node1:1;node2:2
      - id: apc2
       agent: 'stonith:fence_apc_snmp'
       instance_attrs:
        - attrs:
           - name: ip
            value: apc2.example.com
           - name: username
            value: user
```

```
- name: password
       value: "{{ fence2_password }}"
      - name: pcmk_host_map
       value: node1:1;node2:2
# Nodes have redundant power supplies, apc1 and apc2. Cluster must
# ensure that when attempting to reboot a node, both power
# supplies # are turned off before either power supply is turned
# back on.
ha cluster stonith levels:
 - level: 1
  target: node1
  resource_ids:
   - apc1
   - apc2
 - level: 1
  target: node2
  resource_ids:

    apc1

   - apc2
```

ha_cluster_name: <cluster_name>

The name of the cluster you are creating.

ha_cluster_password: <password>

The password of the **hacluster** user. The **hacluster** user has full access to a cluster.

ha_cluster_manage_firewall: true

A variable that determines whether the **ha cluster** RHEL system role manages the firewall.

ha_cluster_manage_selinux: true

A variable that determines whether the **ha_cluster** RHEL system role manages the ports of the firewall high availability service using the **selinux** RHEL system role.

ha_cluster_resource_primitives: <cluster_resources>

A list of resource definitions for the Pacemaker resources configured by the ha_cluster RHEL system role, including fencing

ha cluster stonith levels: <stonith_levels>

A variable that defines STONITH levels, also known as fencing topology, which configure a cluster to use multiple devices to fence nodes.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory

11.8. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH RESOURCE CONSTRAINTS

When configuring a cluster, you can specify the behavior of the cluster resources to be in line with your application requirements. You can control the behavior of cluster resources by configuring resource constraints.

You can define the following categories of resource constraints:

- Location constraints, which determine which nodes a resource can run on. For information about location constraints, see Determining which nodes a resource can run on .
- Ordering constraints, which determine the order in which the resources are run. For information about ordering constraints, see Determing the order in which cluster resources are run.
- Colocation constraints, which specify that the location of one resource depends on the location of another resource. For information about colocation constraints, see Colocating cluster resources.
- Ticket constraints, which indicate the resources that depend on a particular Booth ticket. For information about Booth ticket constraints, see Multi-site Pacemaker clusters.

The following example procedure uses the **ha_cluster** RHEL system role to create a high availability cluster that includes resource location constraints, resource colocation constraints, resource order constraints, and resource ticket constraints.



WARNING

The **ha_cluster** RHEL system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster RHEL system role. For general information about creating an inventory file, see Preparing a control node on RHEL 9.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

cluster_password: <cluster_password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Create a high availability cluster
hosts: node1 node2
vars files:
  - ~/vault.yml
tasks:
  - name: Create cluster with resource constraints
   ansible.builtin.include role:
    name: redhat.rhel_system_roles.ha_cluster
   vars:
    ha_cluster_cluster_name: my-new-cluster
    ha_cluster_hacluster_password: "{{ cluster_password }}"
    ha_cluster_manage_firewall: true
    ha_cluster_manage_selinux: true
    # In order to use constraints, we need resources
    # the constraints will apply to.
    ha_cluster_resource_primitives:
     - id: xvm-fencing
       agent: 'stonith:fence_xvm'
       instance attrs:
        - attrs:
          name: pcmk_host_list
            value: node1 node2
     - id: dummy-1
       agent: 'ocf:pacemaker:Dummy'
     - id: dummy-2
       agent: 'ocf:pacemaker:Dummy'
     - id: dummy-3
       agent: 'ocf:pacemaker:Dummy'
     - id: dummy-4
       agent: 'ocf:pacemaker:Dummy'
     - id: dummy-5
       agent: 'ocf:pacemaker:Dummy'
     - id: dummy-6
       agent: 'ocf:pacemaker:Dummy'
    # location constraints
```

ha_cluster_constraints_location:

```
# resource ID and node name
 - resource:
   id: dummy-1
  node: node1
  options:
   - name: score
    value: 20
 # resource pattern and node name
 - resource:
   pattern: dummy-\d+
  node: node1
  options:
   - name: score
    value: 10
 # resource ID and rule
 - resource:
   id: dummy-2
  rule: '#uname eq node2 and date in_range 2022-01-01 to 2022-02-28'
 # resource pattern and rule
 - resource:
   pattern: dummy-\d+
  rule: node-type eq weekend and date-spec weekdays=6-7
# colocation constraints
ha cluster constraints colocation:
 # simple constraint
 - resource_leader:
   id: dummy-3
  resource_follower:
   id: dummy-4
  options:
   - name: score
    value: -5
 # set constraint
 - resource sets:
   - resource_ids:
      - dummy-1
      - dummy-2
   - resource ids:
      - dummy-5
      - dummy-6
     options:
      - name: sequential
       value: "false"
  options:
   - name: score
     value: 20
# order constraints
ha_cluster_constraints_order:
 # simple constraint
 - resource first:
   id: dummy-1
  resource then:
   id: dummy-6
  options:
   - name: symmetrical
     value: "false"
```

```
# set constraint
 - resource_sets:
   - resource_ids:
      - dummy-1
      - dummy-2
     options:
      - name: require-all
       value: "false"
      - name: sequential
       value: "false"
   - resource ids:
      - dummy-3
   - resource_ids:
      - dummy-4
      - dummy-5
     options:
      - name: sequential
       value: "false"
# ticket constraints
ha cluster constraints ticket:
 # simple constraint
 - resource:
   id: dummy-1
  ticket: ticket1
  options:
   - name: loss-policy
     value: stop
 # set constraint
 - resource sets:
   - resource_ids:
      - dummy-3
      - dummy-4
      - dummy-5
  ticket: ticket2
  options:
   - name: loss-policy
     value: fence
```

ha cluster cluster name: <cluster_name>

The name of the cluster you are creating.

ha_cluster_password: <password>

The password of the **hacluster** user. The **hacluster** user has full access to a cluster.

ha_cluster_manage_firewall: true

A variable that determines whether the **ha_cluster** RHEL system role manages the firewall.

ha_cluster_manage_selinux: true

A variable that determines whether the **ha_cluster** RHEL system role manages the ports of the firewall high availability service using the **selinux** RHEL system role.

ha_cluster_resource_primitives: <cluster_resources>

A list of resource definitions for the Pacemaker resources configured by the ha_cluster RHEL system role, including fencing

ha_cluster_constraints_location: < location_constraints>

A variable that defines resource location constraints.

ha cluster constraints colocation: <colocation_constraints>

A variable that defines resource colocation constraints.

ha cluster constraints order: <order_constraints>

A variable that defines resource order constraints.

ha_cluster_constraints_ticket: <ticket_constraints>

A variable that defines Booth ticket constraints.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory

11.9. CONFIGURING COROSYNC VALUES IN A HIGH AVAILABILITY CLUSTER

(RHEL 9.1 and later) The **corosync.conf** file provides the cluster parameters used by Corosync, the cluster membership and messaging layer that Pacemaker is built on. For your system configuration, you can change some of the default parameters in the **corosync.conf** file. In general, you should not edit the **corosync.conf** file directly. You can, however, configure Corosync values by using the **ha_cluster** RHEL system role.

The following example procedure uses the **ha_cluster** RHEL system role to create a high availability cluster that configures Corosync values.



WARNING

The **ha_cluster** RHEL system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.

- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster RHEL system role. For general information about creating an inventory file, see Preparing a control node on RHEL 9.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

```
$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>
```

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

```
cluster_password: <cluster_password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Create a high availability cluster
hosts: node1 node2
 vars_files:
  - ~/vault.yml
 tasks:
  - name: Create cluster that configures Corosync values
   ansible.builtin.include_role:
    name: redhat.rhel system roles.ha cluster
   vars:
    ha cluster cluster name: my-new-cluster
    ha_cluster_hacluster_password: "{{ cluster_password }}"
    ha_cluster_manage_firewall: true
    ha cluster manage selinux: true
    ha_cluster_transport:
      type: knet
      options:
       - name: ip_version
        value: ipv4-6
       - name: link mode
        value: active
      links:
        - name: linknumber
         value: 1
        - name: link_priority
         value: 5
```

- name: linknumber value: 0 - name: link priority value: 10 compression: - name: level value: 5 - name: model value: zlib crypto: - name: cipher value: none - name: hash value: none ha_cluster_totem: options:

name: block_unlisted_ips

value: 'yes'

- name: send join

value: 0

ha_cluster_quorum:

options:

- name: auto tie breaker

value: 1

- name: wait_for_all

value: 1

The settings specified in the example playbook include the following:

ha_cluster_cluster_name: <cluster_name>

The name of the cluster you are creating.

ha cluster hacluster password: <password>

The password of the **hacluster** user. The **hacluster** user has full access to a cluster.

ha cluster manage firewall: true

A variable that determines whether the **ha cluster** RHEL system role manages the firewall.

ha_cluster_manage_selinux: true

A variable that determines whether the **ha_cluster** RHEL system role manages the ports of the firewall high availability service using the **selinux** RHEL system role.

ha cluster transport: <transport_method>

A variable that sets the cluster transport method.

ha_cluster_totem: <totem_options>

A variable that configures Corosync totem options.

ha_cluster_quorum: <quorum_options>

A variable that configures cluster quorum options.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel**system-roles.ha cluster/README.md** file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha cluster/ directory

11.10. EXPORTING A CLUSTER CONFIGURATION TO CREATE A RHEL SYSTEM ROLE PLAYBOOK

As of RHEL 9.6, you can use the **ha_cluster** RHEL system role to export the Corosync configuration of a cluster into **ha_cluster** variables that can be fed back to the role to recreate the same cluster. If you did not use **ha_cluster** to create your cluster, or if you do not have access to the original playbook for the cluster, you can use this feature to build a new playbook for creating the cluster.

When you export a cluster's configuration by using the **ha_cluster** RHEL system role, not all of the variables are exported. You must manually modify the configuration to account for these variables.

The following variables are present in the export:

- ha_cluster_cluster_present
- ha_cluster_start_on_boot
- ha_cluster_cluster_name
- ha_cluster_transport
- ha_cluster_totem
- ha cluster quorum
- ha_cluster_node_options Only the node_name, corosync_addresses and pcs_address
 options are present.

The following variables are not present in the export:

- **ha_cluster_hacluster_password** This is a mandatory variable for the role but it cannot be extracted from existing clusters.
- ha_cluster_corosync_key_src, ha_cluster_pacemaker_key_src and ha_cluster_fence_virt_key_src - These variables should contain paths to files with Corosync and Pacemaker keys. Since the keys themselves are not exported, these variables are not present in the export either. These keys should be unique for each cluster.
- ha_cluster_regenerate_keys You should decide whether to use existing keys or to generate new ones.

To export the current cluster configuration, run the **ha_cluster** RHEL system role and set **ha_cluster_export_configuration: true**. This triggers the export once the role finishes configuring a cluster or a **qnetd** host and stores it in the **ha_cluster_facts** variable.

By default, **ha_cluster_cluster_present** is set to **true** and **ha_cluster_qnetd.present** is set to **false**. These settings will reconfigure your cluster on the specified hosts, remove **qnetd** configuration from the specified hosts, and then export the configuration. To trigger the export without modifying an existing configuration, run the role with the following settings:

```
    hosts: node1
    vars:
    ha_cluster_cluster_present: null
    ha_cluster_qnetd: null
    ha_cluster_export_configuration: true

roles:
```

- linux-system-roles.ha_cluster

The following procedure:

- Exports the cluster configuration from cluster node **node1** into the **ha_cluster_facts** variable.
- Sets the **ha_cluster_present** and **ha_cluster_qnetd** variables to null to ensure that running this playbook does not modify the existing cluster configuration.
- Uses the Ansible debug module to display the content of **ha_cluster_facts**.
- Saves the contents of ha_cluster_facts to a file on the control node in a YAML format for you
 to write a playbook around it.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You have previously configured the high availability cluster with the configuration to export.
- You have created an inventory file on the control node, as described in Preparing a control node on RHEL 9.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
    name: Export high availability cluster configuration
hosts: node1
Tasks:

            name: Export configuration that does not modify existing cluster
                ansible.builtin.include_role:
                 name: redhat.rhel_system_roles.ha_cluster
                 vars:
                     ha_cluster_cluster_present: null
```

```
ha_cluster_qnetd: null
ha_cluster_export_configuration: true
- name: Print ha_cluster_info_result variable
ansible.builtin.debug:
var: ha_cluster_facts
- name: Save current cluster configuration to a file
delegate_to: localhost
ansible.builtin.copy:
content: "{{ ha_cluster_facts | to_nice_yaml(sort_keys=false) }}"
dest: /path/to/file
mode: "0640"
```

hosts: node1

A node containing the cluster information to export.

ha_cluster_cluster_present: null

Setting to indicate that the cluster configuration will not be changed on the specified host.

ha_cluster_qnetd: null

Setting to indicate that the quetd host configuration will not be changed on the specified host.

ha_cluster_export_configuration: true

A variable that determines whether to export the current cluster configuration and store it in the **ha_cluster_facts** variable, which is generated by the **ha_cluster_info** module.

ha_cluster_facts

A variable that contains the exported cluster configuration.

delegate to: localhost

Specifies the control node as the location for the exported configuration file.

content: "{{ ha_cluster_facts | to_nice_yaml(sort_keys=false) }"}, dest: /path/to/file, mode: "0640"

Copies the configuration file in a YAML format to /path/to/file, setting the file permissions to 0640.

2. Write a playbook for your system using the variables you exported to /path/to/file on the control node.

You must add the **ha_cluster_hacluster_password** variable, as it is a required variable but is not present in the export. Optionally, add the **ha_cluster_corosync_key_src**, **ha_cluster_pacemaker_key_src**, **ha_cluster_fence_virt_key_src**, and **ha_cluster_regenerate_keys** variables if your system requires them. These variables are never exported.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha cluster/ directory

11.11. CONFIGURING A HIGH AVAILABILITY CLUSTER THAT IMPLEMENTS ACCESS CONTROL LISTS (ACLS) BY USING THE HA CLUSTER RHEL SYSTEM ROLE

(RHEL 9.5 and later) The **pcs** administration account for a cluster is **hacluster**. Using access control lists (ACLs), you can grant permission for specific local users other than user **hacluster** to manage a Pacemaker cluster. A common use case for this feature is to restrict unauthorized users from accessing business-sensitive information.

By default, ACLs are not enabled. Consequently, any member of the group **haclient** on all nodes has full local read and write access to the cluster configuratioan. Users who are not members of **haclient** have no access. When ACLs are enabled, however, even users who are members of the **haclient** group have access only to what has been granted to that user by the ACLs. The **root** and **hacluster** user accounts always have full access to the cluster configuration, even when ACLs are enabled.

When you set permissions for local users with ACLs, you create a role which defines the permissions for that role. You then assign that role to a user. If you assign multiple roles to the same user, any deny permission takes precedence, then write, then read.

The following example procedure uses the **ha_cluster** RHEL system role to create in an automated fashion a high availability cluster that implements ACLs to control access to the cluster configuration.



WARNING

The **ha_cluster** RHEL system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster RHEL system role. For general information about creating an inventory file, see Preparing a control node on RHEL 9.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml
New Vault password>

Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

cluster_password: <cluster_password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Create a high availability cluster
hosts: node1 node2
 vars files:
  - ~/vault.yml
 tasks:
  - name: Configure a cluster with ACLs assigned
   ansible.builtin.include role:
    name: redhat.rhel_system_roles.ha_cluster
   vars:
      ha_cluster_cluster_name: my-new-cluster
      ha_cluster_password: "{{ cluster_password }}"
      ha_cluster_manage_firewall: true
      ha_cluster_manage_selinux: true
      # To use an ACL role permission reference, the reference must exist in CIB.
      ha cluster resource primitives:
       - id: not-for-operator
        agent: 'ocf:pacemaker:Dummy'
      # ACLs must be enabled (using the enable-acl cluster property) in order to be effective.
      ha_cluster_cluster_properties:
       - attrs:
         - name: enable-acl
           value: 'true'
      ha_cluster_acls:
       acl roles:
        - id: operator
         description: HA cluster operator
         permissions:
           - kind: write
            xpath: //crm config//nvpair[@name='maintenance-mode']
           - kind: deny
            reference: not-for-operator
        - id: administrator
         permissions:
           - kind: write
            xpath: /cib
       acl_users:
        - id: alice
```

roles:

- operator
- administrator
- id: bob roles:
 - administrator

acl_groups:

- id: admins
 - roles:
 - administrator

The settings specified in the example playbook include the following:

ha_cluster_name: <cluster_name>

The name of the cluster you are creating.

ha_cluster_password: <password>

The password of the **hacluster** user. The **hacluster** user has full access to a cluster.

ha_cluster_manage_firewall: true

A variable that determines whether the **ha_cluster** RHEL system role manages the firewall.

ha_cluster_manage_selinux: true

A variable that determines whether the **ha_cluster** RHEL system role manages the ports of the firewall high availability service using the **selinux** RHEL system role.

ha_cluster_resource_primitives: <cluster resources>

A list of resource definitions for the Pacemaker resources configured by the **ha_cluster** RHEL system role, including fencing resources.

ha_cluster_properties: <cluster properties>

A list of sets of cluster properties for Pacemaker cluster-wide configuration.

ha_cluster_acls: < dictionary>

A dictionary of ACL role, user, and group values.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha cluster/ directory
- Ansible vault

11.12. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH SBD NODE FENCING BY USING THE HA_CLUSTER_NODE_OPTIONS VARIABLE

You must configure a Red Hat high availability cluster with at least one fencing device to ensure the cluster-provided services remain available when a node in the cluster encounters a problem. If your environment does not allow for a remotely accessible power switch to fence a cluster node, you can configure fencing by using a STONITH Block Device (SBD). This device provides a node fencing mechanism for Pacemaker-based clusters through the exchange of messages by means of shared block storage. SBD integrates with Pacemaker, a watchdog device and, optionally, shared storage to arrange for nodes to reliably self-terminate when fencing is required.

You can use the **ha_cluster** RHEL system role to configure SBD fencing in an automated fashion. With **ha_cluster**, you can configure watchdog and SBD devices on a node-to-node basis by using one of two variables:

- ha_cluster_node_options: (RHEL 9.5 and later) This is a single variable you define in a playbook file. It is a list of dictionaries where each dictionary defines options for one node.
- **ha_cluster**: (RHEL 9.1 and later) A dictionary that defines options for one node only. You configure the **ha_cluster** variable in an inventory file. To set different values for each node, you define the variable separately for each node.

If both the **ha_cluster_node_options** and **ha_cluster** variables contain SBD options, those in **ha_cluster_node_options** have precedence.

This example procedure uses the **ha_cluster_node_options** variable in a playbook file to configure node addresses and SBD options on a per-node basis. For an example procedure that uses the **ha_cluster** variable in an inventory file, see Configuring a high availability cluster with SBD node fencing by using the ha_cluster variable.



WARNING

The **ha_cluster** RHEL system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster RHEL system role. For general information about creating an inventory file, see Preparing a control node on RHEL 9.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml

New Vault password: <vault_password>

Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

cluster_password: <cluster_password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Create a high availability cluster
hosts: node1 node2
 vars files:
  - ~/vault.yml
 tasks:
  - name: Configure a cluster with SBD fencing
   ansible.builtin.include role:
    name: redhat.rhel_system_roles.ha_cluster
   vars:
    my_sbd_devices:
     # This variable is indirectly used by various variables of the ha_cluster RHEL system
role.
     # Its purpose is to define SBD devices once so they do not need
     # to be repeated several times in the role variables.
     - /dev/disk/by-id/000001
     - /dev/disk/by-id/000002
     - /dev/disk/by-id/000003
    ha_cluster_cluster_name: my-new-cluster
    ha_cluster_password: "{{ cluster_password }}"
    ha cluster manage firewall: true
    ha_cluster_manage_selinux: true
    ha_cluster_sbd_enabled: true
    ha_cluster_sbd_options:
     - name: delay-start
       value: 'no'
     - name: startmode
       value: always
     - name: timeout-action
       value: 'flush,reboot'
     - name: watchdog-timeout
       value: 30
    ha_cluster_node_options:
     - node name: node1
       sbd_watchdog_modules:
        iTCO_wdt
       sbd_watchdog_modules_blocklist:
        - ipmi_watchdog
```

```
sbd_watchdog:/dev/watchdog1
  sbd_devices: "{{ my_sbd_devices }}"
 - node name: node2
  sbd_watchdog_modules:
   - iTCO wdt
  sbd_watchdog_modules_blocklist:
   - ipmi watchdog
  sbd_watchdog: /dev/watchdog1
  sbd_devices: "{{ my_sbd_devices }}"
# Best practice for setting SBD timeouts:
# watchdog-timeout * 2 = msgwait-timeout (set automatically)
# msgwait-timeout * 1.2 = stonith-timeout
ha_cluster_cluster_properties:
 - attrs:
   - name: stonith-timeout
    value: 72
ha_cluster_resource_primitives:
 - id: fence_sbd
  agent: 'stonith:fence_sbd'
  instance attrs:
   - attrs:
      - name: devices
       value: "{{ my_sbd_devices | join(',') }}"
      - name: pcmk delay base
       value: 30
```

ha_cluster_name: <cluster_name>

The name of the cluster you are creating.

ha_cluster_password: <password>

The password of the **hacluster** user. The **hacluster** user has full access to a cluster.

ha_cluster_manage_firewall: true

A variable that determines whether the **ha_cluster** RHEL system role manages the firewall.

ha_cluster_manage_selinux: true

A variable that determines whether the **ha_cluster** RHEL system role manages the ports of the firewall high availability service using the **selinux** RHEL system role.

ha_cluster_sbd_enabled: true

A variable that determines whether the cluster can use the SBD node fencing mechanism.

ha cluster sbd options: <sbd options>

A list of name-value dictionaries specifying SBD options. For information about these options, see the **Configuration via environment** section of the **sbd**(8) man page on your system.

ha_cluster_node_options: <node options>

A variable that defines settings which vary from one cluster node to another. You can configure the following SBD and watchdog items:

- sbd_watchdog_modules Modules to be loaded, which create /dev/watchdog* devices.
- **sbd_watchdog_modules_blocklist** Watchdog kernel modules to be unloaded and blocked.

- **sbd_watchdog** Watchdog device to be used by SBD.
- **sbd_devices** Devices to use for exchanging SBD messages and for monitoring. Always refer to the devices using the long, stable device name (/dev/disk/by-id/).

ha_cluster_properties: <cluster properties>

A list of sets of cluster properties for Pacemaker cluster-wide configuration.

ha_cluster_resource_primitives: <cluster resources>

A list of resource definitions for the Pacemaker resources configured by the **ha_cluster** RHEL system role, including fencing resources.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- Red Hat Knowledgebase article Exploring RHEL High Availability's Components sbd and fence_sbd
- Red Hat Knowledgebase article Design Guidance for RHEL High Availability Clusters sbd Considerations
- Red Hat Knowledgebase article Support Policies for RHEL High Availability Clusters sbd and fence_sbd
- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory
- Ansible vault

11.13. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH SBD NODE FENCING BY USING THE HA_CLUSTER VARIABLE

You must configure a Red Hat high availability cluster with at least one fencing device to ensure the cluster-provided services remain available when a node in the cluster encounters a problem. If your environment does not allow for a remotely accessible power switch to fence a cluster node, you can configure fencing by using a STONITH Block Device (SBD). This device provides a node fencing mechanism for Pacemaker-based clusters through the exchange of messages by means of shared block storage. SBD integrates with Pacemaker, a watchdog device and, optionally, shared storage to arrange for nodes to reliably self-terminate when fencing is required.

You can use the **ha_cluster** RHEL system role to configure SBD fencing in an automated fashion. With **ha_cluster**, you can configure watchdog and SBD devices on a node-to-node basis by using one of two variables:

- ha_cluster_node_options: (RHEL 9.5 and later) This is a single variable you define in a playbook file. It is a list of dictionaries where each dictionary defines options for one node.
- **ha_cluster**: (RHEL 9.1 and later) A dictionary that defines options for one node only. You configure the **ha_cluster** variable in an inventory file. To set different values for each node, you define the variable separately for each node.

If both the **ha_cluster_node_options** and **ha_cluster** variables contain SBD options, those in **ha_cluster_node_options** have precedence.

If both the **ha_cluster_node_options** and **ha_cluster** variables contain SBD options, those in **ha_cluster_node_options** have precedence.`

The following example procedure uses the **ha_cluster** system role to create a high availability cluster with SBD fencing. This example procedure uses the **ha_cluster** variable in an inventory file to configure node addresses and SBD options on a per-node basis. For an example procedure that uses the **ha_cluster_node_options** variable in a playbook file, see Configuring a high availability cluster with SBD node fencing by using the ha_cluster_nodes_options variable.



WARNING

The **ha_cluster** system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.

Procedure

1. Create an inventory file for your cluster that configures watchdog and SBD devices for each node by using the **ha_cluster** variable, as in the following exampla;e

```
all:
hosts:
node1:
ha_cluster:
sbd_watchdog_modules:
- iTCO_wdt
sbd_watchdog_modules_blocklist:
```

```
ipmi_watchdog
  sbd_watchdog: /dev/watchdog1
  sbd devices:
   - /dev/disk/by-id/000001
   - /dev/disk/by-id/00001
   - /dev/disk/by-id/000003
node2:
 ha cluster:
  sbd_watchdog_modules:
   - iTCO wdt
  sbd_watchdog_modules_blocklist:
   - ipmi_watchdog
  sbd_watchdog: /dev/watchdog1
  sbd_devices:
   - /dev/disk/by-id/000001
   - /dev/disk/by-id/000002
```

The SBD and watchdog settings specified in the example inventory include the following:

sbd_watchdog_modules

Watchdog kernel modules to be loaded, which create /dev/watchdog* devices.

sbd_watchdog_modules_blocklist

Watchdog kernel modules to be unloaded and blocked.

sbd_watchdog

Watchdog device to be used by SBD.

- /dev/disk/by-id/000003

sbd devices

Devices to use for exchanging SBD messages and for monitoring. Always refer to the devices using the long, stable device name (/dev/disk/by-id/).

For general information about creating an inventory file, see Preparing a control node on RHEL 9.

- 2. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

```
$ ansible-vault create ~/vault.yml
New Vault password: <vault password>
```

Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

```
cluster_password: <cluster_password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 3. Create a playbook file, for example ~/playbook.yml, as in the following example. Since you have specified the SBD and watchog variables in an inventory, you do not need to include them in the playbook.

```
- name: Create a high availability cluster
hosts: node1 node2
vars files:
  - ~/vault.yml
tasks:
  - name: Configure a cluster with sbd fencing devices configured in an inventory file
   ansible.builtin.include role:
    name: redhat.rhel_system_roles.ha_cluster
     ha cluster cluster name: my-new-cluster
     ha_cluster_password: "{{ cluster_password }}"
     ha_cluster_manage_firewall: true
     ha_cluster_manage_selinux: true
     ha_cluster_sbd_enabled: true
     ha_cluster_sbd_options:
       - name: delay-start
        value: 'no'
       - name: startmode
        value: always
       - name: timeout-action
        value: 'flush,reboot'
       - name: watchdog-timeout
        value: 30
     # Best practice for setting SBD timeouts:
     # watchdog-timeout * 2 = msgwait-timeout (set automatically)
     # msgwait-timeout * 1.2 = stonith-timeout
     ha_cluster_cluster_properties:
       - attrs:
         - name: stonith-timeout
           value: 72
     ha_cluster_resource_primitives:
       - id: fence_sbd
        agent: 'stonith:fence sbd'
        instance attrs:
         - attrs:
            # taken from host_vars
            # this only works if all nodes have the same sbd devices
            - name: devices
             value: "{{ ha_cluster.sbd_devices | join(',') }}"
            - name: pcmk_delay_base
             value: 30
```

ha_cluster_cluster_name: cluster_name

The name of the cluster you are creating.

ha_cluster_password: password

The password of the **hacluster** user. The **hacluster** user has full access to a cluster.

ha_cluster_manage_firewall: true

A variable that determines whether the **ha_cluster** RHEL system role manages the firewall.

ha_cluster_manage_selinux: true

A variable that determines whether the **ha_cluster** RHEL system role manages the ports of the firewall high availability service using the **selinux** RHEL system role.

ha cluster sbd enabled: true

A variable that determines whether the cluster can use the SBD node fencing mechanism.

ha cluster sbd options: sbd options

A list of name-value dictionaries specifying SBD options. For information about these options, see the **Configuration via environment** section of the **sbd**(8) man page on your system.

ha_cluster_properties: cluster properties

A list of sets of cluster properties for Pacemaker cluster-wide configuration.

ha_cluster_resource_primitives: cluster resources

A list of resource definitions for the Pacemaker resources configured by the **ha_cluster** RHEL system role, including fencing resources.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file on the control node.

4. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

5. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- Red Hat Knowledgebase article Exploring RHEL High Availability's Components sbd and fence sbd
- Red Hat Knowledgebase article Design Guidance for RHEL High Availability Clusters sbd Considerations
- Red Hat Knowledgebase article Support Policies for RHEL High Availability Clusters sbd and fence_sbd
- /usr/share/ansible/roles/rhel-system-roles.ha cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory
- Ansible vault

11.14. CONFIGURING A PLACEMENT STRATEGY FOR A HIGH AVAILABILITY CLUSTER BY USING THE RHEL HA_CLUSTER RHEL SYSTEM ROLE

(RHEL 9.5 and later) A Pacemaker cluster allocates resources according to a resource allocation score. By default, if the resource allocation scores on all the nodes are equal, Pacemaker allocates the resource to the node with the smallest number of allocated resources. If the resources in your cluster use significantly different proportions of a node's capacities, such as memory or I/O, the default

behavior may not be the best strategy for balancing your system's workload. In this case, you can customize an allocation strategy by configuring utilization attributes and placement strategies for nodes and resources.

For detailed information about configuring utilization attributes and placement strategies, see Configuring a node placement strategy.

This example procedure uses the **ha_cluster** RHEL system role to create a high availability cluster in an automated fashion that configures utilization attributes to define a placement strategy.



WARNING

The **ha_cluster** RHEL system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster RHEL system role. For general information about creating an inventory file, see Preparing a control node on RHEL 9.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml

New Vault password: <vault password>

Confirm New Vault password: <vault_password>

- b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:
 - cluster_password: <cluster_password>
- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Create a high availability cluster

```
hosts: node1 node2
vars_files:
 - ~/vault.yml
 - name: Configure a cluster with utilization attributes
  ansible.builtin.include_role:
   name: redhat.rhel system roles.ha cluster
  vars:
     ha cluster cluster name: my-new-cluster
     ha_cluster_password: "{{ cluster_password }}"
     ha cluster manage firewall: true
     ha_cluster_manage_selinux: true
     ha_cluster_cluster_properties:
      - attrs:
        - name: placement-strategy
          value: utilization
     ha_cluster_node_options:
      - node_name: node1
       utilization:
        - attrs:
           - name: utilization1
            value: 1
           - name: utilization2
            value: 2
      - node name: node2
       utilization:
        - attrs:
           - name: utilization1
            value: 3
           - name: utilization2
            value: 4
     ha_cluster_resource_primitives:
      - id: resource1
       agent: 'ocf:pacemaker:Dummy'
       utilization:
        - attrs:
           - name: utilization1
            value: 2
           - name: utilization2
            value: 3
```

The settings specified in the example playbook include the following:

ha_cluster_name: <cluster_name>

The name of the cluster you are creating.

ha cluster hacluster password: <password>

The password of the **hacluster** user. The **hacluster** user has full access to a cluster.

ha cluster manage firewall: true

A variable that determines whether the **ha cluster** RHEL system role manages the firewall.

ha_cluster_manage_selinux: true

A variable that determines whether the **ha_cluster** RHEL system role manages the ports of the firewall high availability service using the **selinux** RHEL system role.

ha cluster cluster properties: <cluster properties>

List of sets of cluster properties for Pacemaker cluster-wide configuration. For utilization to have an effect, the **placement-strategy** property must be set and its value must be different from the value **default**.

`ha_cluster_node_options: < node options>

A variable that defines various settings which vary from cluster node to cluster node.

ha_cluster_resource_primitives: <cluster resources>

A list of resource definitions for the Pacemaker resources configured by the **ha_cluster** RHEL system role, including fencing resources.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory
- Ansible vault

11.15. CONFIGURING ALERTS FOR A HIGH AVAILABILITY CLUSTER BY USING THE ha_cluster RHEL SYSTEM ROLE

(RHEL 9.5 and later) When a Pacemaker event occurs, such as a resource or a node failure or a configuration change, you may want to take some external action. For example, you may want to send an email message or log to a file or update a monitoring system.

You can configure your system to take an external action by using alert agents. These are external programs that the cluster calls in the same manner as the cluster calls resource agents to handle resource configuration and operation. The cluster passes information about the event to the agent through environment variables.



NOTE

The **ha_cluster** RHEL system role configures the cluster to call external programs to handle alerts. However, you must provide these programs and distribute them to cluster nodes.

For more detailed information about alert agents, see Triggering scripts for cluster events.

This example procedure uses the **ha_cluster** RHEL system role to create a high availability cluster in an automated fashion that configures a Pacemaker alert.



WARNING

The **ha_cluster** RHEL system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster RHEL system role. For general information about creating an inventory file, see Preparing a control node on RHEL 9.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

cluster_password: <cluster_password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Create a high availability cluster

hosts: node1 node2

vars_files:

- ~/vault.yml

tasks:

- name: Configure a cluster with alerts

ansible.builtin.include_role:

name: redhat.rhel_system_roles.ha_cluster

```
vars:
  ha_cluster_cluster_name: my-new-cluster
  ha_cluster_password: "{{ cluster_password }}"
  ha cluster manage firewall: true
  ha cluster manage selinux: true
  ha cluster alerts:
   - id: alert1
    path: /alert1/path
    description: Alert1 description
    instance attrs:
      - attrs:
        - name: alert_attr1_name
         value: alert_attr1_value
    meta attrs:
      - attrs:
        - name: alert_meta_attr1_name
         value: alert_meta_attr1_value
    recipients:
      - value: recipient value
       id: recipient1
       description: Recipient1 description
       instance_attrs:
        - attrs:
           - name: recipient attr1 name
            value: recipient_attr1_value
       meta_attrs:
        - attrs:
           - name: recipient_meta_attr1_name
            value: recipient meta attr1 value
```

The settings specified in the example playbook include the following:

ha_cluster_name: <cluster_name>

The name of the cluster you are creating.

ha_cluster_hacluster_password: <password>

The password of the **hacluster** user. The **hacluster** user has full access to a cluster.

ha_cluster_manage_firewall: true

A variable that determines whether the **ha cluster** RHEL system role manages the firewall.

ha_cluster_manage_selinux: true

A variable that determines whether the **ha_cluster** RHEL system role manages the ports of the firewall high availability service using the **selinux** RHEL system role.

ha_cluster_alerts: <alert definitions>

A variable that defines Pacemaker alerts.

- id ID of an alert.
- path Path to the alert agent executable.
- **description** Description of the alert.
- **instance_attrs** List of sets of the alert's instance attributes. Currently, only one set is supported, so the first set is used and the rest are ignored.

- **meta_attrs** List of sets of the alert's meta attributes. Currently, only one set is supported, so the first set is used and the rest are ignored.
- recipients List of alert's recipients.
- value- Value of a recipient.
- id ID of the recipient.
- **description** Description of the recipient.
- **instance_attrs** -List of sets of the recipient's instance attributes. Currently, only one set is supported, so the first set is used and the rest are ignored.
- **meta_attrs** List of sets of the recipient's meta attributes. Currently, only one set is supported, so the first set is used and the rest are ignored.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha cluster/ directory
- Ansible vault

11.16. CONFIGURING A HIGH AVAILABILITY CLUSTER USING A QUORUM DEVICE

(RHEL 9.2 and later) Your cluster can sustain more node failures than standard quorum rules permit when you configure a separate quorum device. The quorum device acts as a lightweight arbitration device for the cluster. A quorum device is recommended for clusters with an even number of nodes. With two-node clusters, the use of a quorum device can better determine which node survives in a splitbrain situation.

For information about quorum devices, see Configuring quorum devices.

To configure a high availability cluster with a separate quorum device by using the **ha_cluster** RHEL system role, first set up the quorum device. After setting up the quorum device, you can use the device in any number of clusters.

11.16.1. Configuring a quorum device

To configure a quorum device using the **ha_cluster** RHEL system role, follow the steps in this example procedure. Note that you cannot run a quorum device on a cluster node.



WARNING

The **ha_cluster** RHEL system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The system that you will use to run the quorum device has active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the quorum devices as described in Specifying an inventory for the ha_cluster RHEL system role. For general information about creating an inventory file, see Preparing a control node on RHEL 9.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

cluster_password: <cluster_password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook-qdevice.yml, with the following content:

--- name: Configure a host with a quorum device hosts: nodeQ
vars_files:
- ~/vault.yml
tasks:

```
    name: Create a quorum device for the cluster
ansible.builtin.include_role:
    name: redhat.rhel_system_roles.ha_cluster
vars:
    ha_cluster_cluster_present: false
    ha_cluster_hacluster_password: "{{ cluster_password }}"
    ha_cluster_manage_firewall: true
    ha_cluster_manage_selinux: true
    ha_cluster_qnetd:
    present: true
```

The settings specified in the example playbook include the following:

ha_cluster_cluster_present: false

A variable that, if set to **false**, determines that all cluster configuration will be removed from the target host.

ha_cluster_password: <password>

The password of the **hacluster** user. The **hacluster** user has full access to a cluster.

ha_cluster_manage_firewall: true

A variable that determines whether the **ha_cluster** RHEL system role manages the firewall.

ha_cluster_manage_selinux: true

A variable that determines whether the **ha_cluster** RHEL system role manages the ports of the firewall high availability service using the **selinux** RHEL system role.

ha_cluster_qnetd: <quorum_device_options>

A variable that configures a **qnetd** host.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook-qdevice.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook-qdevice.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory

11.16.2. Configuring a cluster to use a quorum device

To configure a cluster to use a quorum device, follow the steps in this example procedure.



WARNING

The **ha_cluster** RHEL system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster RHEL system role. For general information about creating an inventory file, see Preparing a control node on RHEL 9.
- You have configured a quorum device.

Procedure

 Create a playbook file, for example ~/playbook-cluster-qdevice.yml, with the following content:

```
- name: Configure a cluster to use a quorum device
hosts: node1 node2
vars files:
  - ~/vault.yml
tasks:
  - name: Create cluster that uses a quorum device
   ansible.builtin.include role:
    name: redhat.rhel_system_roles.ha_cluster
   vars:
    ha_cluster_cluster_name: my-new-cluster
    ha cluster hacluster password: "{{ cluster password }}"
    ha cluster manage firewall: true
    ha_cluster_manage_selinux: true
    ha_cluster_quorum:
     device:
       model: net
       model_options:
        - name: host
         value: nodeQ
        - name: algorithm
         value: Ims
```

The settings specified in the example playbook include the following:

ha_cluster_name: <cluster_name>

The name of the cluster you are creating.

ha cluster hacluster password: <password>

The password of the **hacluster** user. The **hacluster** user has full access to a cluster.

ha_cluster_manage_firewall: true

A variable that determines whether the **ha cluster** RHEL system role manages the firewall.

ha_cluster_manage_selinux: true

A variable that determines whether the **ha_cluster** RHEL system role manages the ports of the firewall high availability service using the **selinux** RHEL system role.

ha_cluster_quorum: <quorum_parameters>

A variable that configures cluster quorum which you can use to specify that the cluster uses a quorum device.

2. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook-cluster-qdevice.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook-cluster-qdevice.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha cluster/ directory

11.17. CONFIGURING A HIGH AVAILABILITY CLUSTER WITH NODE ATTRIBUTES

(RHEL 9.4 and later) You can use Pacemaker rules to make your configuration more dynamic. For example, you can use a node attribute to assign machines to different processing groups based on time and then use that attribute when creating location constraints.

Node attribute expressions are used to control a resource based on the attributes defined by a node or nodes. For information on node attributes, see Determining resource location with rules.

The following example procedure uses the **ha_cluster** RHEL system role to create a high availability cluster that configures node attributes.



WARNING

The **ha_cluster** RHEL system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster RHEL system role. For general information about creating an inventory file, see Preparing a control node on RHEL 9.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

```
$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>
```

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

```
cluster_password: <cluster_password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Create a high availability cluster
hosts: node1 node2
vars_files:
  - ~/vault.yml
tasks:
  - name: Create a cluster that defines node attributes
   ansible.builtin.include_role:
    name: redhat.rhel_system_roles.ha_cluster
   vars:
    ha cluster cluster name: my-new-cluster
    ha_cluster_password: "{{ cluster_password }}"
    ha_cluster_manage_firewall: true
    ha_cluster_manage_selinux: true
    ha cluster node options:
     - node name: node1
       attributes:
        - attrs:
          - name: attribute1
            value: value1A
          - name: attribute2
            value: value2A
```

node_name: node2 attributes:

- attrs:

name: attribute1 value: value1Bname: attribute2 value: value2B

ha_cluster_name: <cluster_name>

The name of the cluster you are creating.

ha_cluster_password: <password>

The password of the **hacluster** user. The **hacluster** user has full access to a cluster.

ha_cluster_manage_firewall: true

A variable that determines whether the **ha cluster** RHEL system role manages the firewall.

ha_cluster_manage_selinux: true

A variable that determines whether the **ha_cluster** RHEL system role manages the ports of the firewall high availability service using the **selinux** RHEL system role.

ha_cluster_node_options: <node_settings>

A variable that defines various settings that vary from one cluster node to another.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

Pacemaker rules

11.18. CONFIGURING AN APACHE HTTP SERVER IN A HIGH AVAILABILITY CLUSTER WITH THE HA_CLUSTER RHEL SYSTEM ROLE

High availability clusters provide highly available services by eliminating single points of failure and by failing over services from one cluster node to another in case a node becomes inoperative. Red Hat provides a variety of documentation for planning, configuring, and maintaining a Red Hat high availability cluster. For a listing of articles that provide indexes to the various areas of Red Hat cluster documentation, see the Red Hat High Availability Add-On Documentation Guide .

The following example use case configures an active/passive Apache HTTP server in a two-node Red Hat Enterprise Linux High Availability Add-On cluster by using the **ha_cluster** RHEL system role. In this use case, clients access the Apache HTTP server through a floating IP address. The web server runs on

one of two nodes in the cluster. If the node on which the web server is running becomes inoperative, the web server starts up again on the second node of the cluster with minimal service interruption.

This example uses an APC power switch with a host name of **zapc.example.com**. If the cluster does not use any other fence agents, you can optionally list only the fence agents your cluster requires when defining the **ha_cluster_fence_agent_packages** variable, as in this example.



WARNING

The **ha_cluster** RHEL system role replaces any existing cluster configuration on the specified nodes. Any settings not specified in the playbook will be lost.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The systems that you will use as your cluster members have active subscription coverage for RHEL and the RHEL High Availability Add-On.
- The inventory file specifies the cluster nodes as described in Specifying an inventory for the ha_cluster RHEL system role. For general information about creating an inventory file, see Preparing a control node on RHEL 9.
- You have configured an LVM logical volume with an XFS file system, as described in Configuring an LVM volume with an XFS file system in a Pacemaker cluster.
- You have configured an Apache HTTP server, as described in Configuring an Apache HTTP Server.
- Your system includes an APC power switch that will be used to fence the cluster nodes.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml New Vault password: <vault_password>

Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

cluster password: <cluster password>

c. Save the changes, and close the editor. Ansible encrypts the data in the vault.

2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Create a high availability cluster
hosts: z1.example.com z2.example.com
 vars files:
  - ~/vault.yml
 tasks:
  - name: Configure active/passive Apache server in a high availability cluster
   ansible.builtin.include role:
    name: redhat.rhel_system_roles.ha_cluster
   vars:
    ha_cluster_password: "{{ cluster_password }}"
    ha_cluster_cluster_name: my_cluster
    ha cluster manage firewall: true
    ha_cluster_manage_selinux: true
    ha_cluster_fence_agent_packages:
     - fence-agents-apc-snmp
    ha cluster resource primitives:
     - id: myapc
       agent: stonith:fence_apc_snmp
       instance_attrs:
        - attrs:
          - name: ipaddr
            value: zapc.example.com
          - name: pcmk_host_map
            value: z1.example.com:1;z2.example.com:2
          - name: login
            value: apc
          - name: passwd
            value: apc
     - id: my lvm
       agent: ocf:heartbeat:LVM-activate
       instance attrs:
        - attrs:
          - name: vgname
            value: my_vg
          - name: vg_access_mode
            value: system_id
      - id: my_fs
       agent: Filesystem
       instance attrs:
        - attrs:
          - name: device
            value: /dev/my vg/my lv
          - name: directory
            value: /var/www
          - name: fstype
            value: xfs
     - id: VirtualIP
       agent: IPaddr2
       instance_attrs:
        - attrs:
          - name: ip
            value: 198.51.100.3
          - name: cidr_netmask
```

value: 24
- id: Website
agent: apache
instance_attrs:
- attrs:

- name: configfile

value: /etc/httpd/conf/httpd.conf

- name: statusurl

value: http://127.0.0.1/server-status

ha_cluster_resource_groups:

- id: apachegroup resource_ids:
 - my_lvm
 - my_fs
 - VirtualIP
 - Website

The settings specified in the example playbook include the following:

ha_cluster_name: <cluster_name>

The name of the cluster you are creating.

ha_cluster_password: <password>

The password of the **hacluster** user. The **hacluster** user has full access to a cluster.

ha_cluster_manage_firewall: true

A variable that determines whether the **ha_cluster** RHEL system role manages the firewall.

ha_cluster_manage_selinux: true

A variable that determines whether the **ha_cluster** RHEL system role manages the ports of the firewall high availability service using the **selinux** RHEL system role.

ha_cluster_fence_agent_packages: <fence_agent_packages>

A list of fence agent packages to install.

ha_cluster_resource_primitives: <cluster_resources>

A list of resource definitions for the Pacemaker resources configured by the ha_cluster RHEL system role, including fencing

ha_cluster_resource_groups: <resource_groups>

A list of resource group definitions configured by the **ha_cluster** RHEL system role.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.ha_cluster/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

5. When you use the **apache** resource agent to manage Apache, it does not use **systemd**. Because of this, you must edit the **logrotate** script supplied with Apache so that it does not use **systemct!** to reload Apache.

Remove the following line in the /etc/logrotate.d/httpd file on each node in the cluster.

/bin/systemctl reload httpd.service > /dev/null 2>/dev/null || true

Replace the line you removed with the following three lines, specifying /var/run/httpd-website.pid as the PID file path where website is the name of the Apache resource. In this example, the Apache resource name is **Website**.

/usr/bin/test -f /var/run/httpd-Website.pid >/dev/null 2>/dev/null && /usr/bin/ps -q \$(/usr/bin/cat /var/run/httpd-Website.pid) >/dev/null 2>/dev/null && /usr/sbin/httpd -f /etc/httpd/conf/httpd.conf -c "PidFile /var/run/httpd-Website.pid" -k graceful > /dev/null 2>/dev/null || true

Verification

From one of the nodes in the cluster, check the status of the cluster. Note that all four resources are running on the same node, z1.example.com.
 If you find that the resources you configured are not running, you can run the pcs resource debug-start resource command to test the resource configuration.

[root@z1 ~]# pcs status Cluster name: my cluster

Last updated: Wed Jul 31 16:38:51 2013

Last change: Wed Jul 31 16:42:14 2013 via crm_attribute on z1.example.com

Stack: corosync

Current DC: z2.example.com (2) - partition with quorum

Version: 1.1.10-5.el7-9abe687

2 Nodes configured6 Resources configured

Online: [z1.example.com z2.example.com]

Full list of resources:

myapc (stonith:fence apc snmp): Started z1.example.com

Resource Group: apachegroup

my_lvm (ocf::heartbeat:LVM-activate): Started z1.example.com my_fs (ocf::heartbeat:Filesystem): Started z1.example.com VirtualIP (ocf::heartbeat:IPaddr2): Started z1.example.com Website (ocf::heartbeat:apache): Started z1.example.com

2. Once the cluster is up and running, you can point a browser to the IP address you defined as the **IPaddr2** resource to view the sample display, consisting of the simple word "Hello".

Hello

 To test whether the resource group running on z1.example.com fails over to node z2.example.com, put node z1.example.com in standby mode, after which the node will no longer be able to host resources.

[root@z1 ~]# pcs node standby z1.example.com

4. After putting node **z1** in **standby** mode, check the cluster status from one of the nodes in the cluster. Note that the resources should now all be running on **z2**.

[root@z1 ~]# pcs status Cluster name: my_cluster

Last updated: Wed Jul 31 17:16:17 2013

Last change: Wed Jul 31 17:18:34 2013 via crm attribute on z1.example.com

Stack: corosync

Current DC: z2.example.com (2) - partition with quorum

Version: 1.1.10-5.el7-9abe687

2 Nodes configured6 Resources configured

Node z1.example.com (1): standby

Online: [z2.example.com]

Full list of resources:

myapc (stonith:fence_apc_snmp): Started z1.example.com

Resource Group: apachegroup

my_lvm (ocf::heartbeat:LVM-activate): Started z2.example.com my_fs (ocf::heartbeat:Filesystem): Started z2.example.com VirtualIP (ocf::heartbeat:IPaddr2): Started z2.example.com Website (ocf::heartbeat:apache): Started z2.example.com

The web site at the defined IP address should still display, without interruption.

5. To remove **z1** from **standby** mode, enter the following command.

[root@z1 ~]# pcs node unstandby z1.example.com



NOTE

Removing a node from **standby** mode does not in itself cause the resources to fail back over to that node. This will depend on the **resource-stickiness** value for the resources. For information about the **resource-stickiness** meta attribute, see Configuring a resource to prefer its current node.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ha cluster/README.md file
- /usr/share/doc/rhel-system-roles/ha_cluster/ directory

CHAPTER 12. CONFIGURING THE SYSTEMD JOURNAL BY USING RHEL SYSTEM ROLES

With the journald RHEL system role you can automate the systemd journal, and configure persistent logging by using the Red Hat Ansible Automation Platform.

12.1. CONFIGURING PERSISTENT LOGGING BY USING THE JOURNALD RHEL SYSTEM ROLE

By default, the **systemd** journal stores logs only in a small ring buffer in /run/log/journal, which is not persistent. Rebooting the system also removes journal database logs. You can configure persistent logging consistently on multiple systems by using the journald RHEL system role.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Configure journald hosts: managed-node-01.example.com - name: Configure persistent logging ansible.builtin.include_role: name: redhat.rhel system roles.journald vars: journald_persistent: true journald_max_disk_size: <size> journald_per_user: true journald_sync_interval: <interval>

The settings specified in the example playbook include the following:

journald_persistent: true

Enables persistent logging.

journald_max_disk_size: <size>

Specifies the maximum size of disk space for journal files in MB, for example, 2048.

journald_per_user: true

Configures **journald** to keep log data separate for each user.

journald_sync_interval: <interval>

Sets the synchronization interval in minutes, for example, 1.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-

system-roles.journald/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.journald/README.md file
- /usr/share/doc/rhel-system-roles/journald/ directory

CHAPTER 13. CONFIGURING AUTOMATIC CRASH DUMPS BY USING RHEL SYSTEM ROLES

To manage kdump using Ansible, you can use the **kdump** role, which is one of the RHEL system roles available in RHEL 9.

Using the **kdump** role enables you to specify where to save the contents of the system's memory for later analysis.

13.1. CONFIGURING THE KERNEL CRASH DUMPING MECHANISM BY USING THE KDUMP RHEL SYSTEM ROLE

Kernel crash dumping is a crucial feature for diagnosing and troubleshooting system issues. When your system encounters a kernel panic or other critical failure, crash kernel dumping allows you to capture a memory dump (core dump) of the kernel's state at the time of the failure.

By using an Ansible playbook, you can set kernel crash dump parameters on multiple systems using the **kdump** RHEL system role. This ensures consistent settings across all managed nodes for the **kdump** service.



WARNING

The **kdump** system role replaces the content in the /**etc/kdump.conf** and /**etc/sysconfig/kdump** configuration files. Previous settings are changed to those specified in the role variables, and lost if they are not specified in the role variables.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

name: Configuring kernel crash dumping hosts: managed-node-01.example.com tasks:
name: Setting the kdump directory. ansible.builtin.include_role:
 name: redhat.rhel_system_roles.kdump vars:
 kdump_target:
 type: raw

location: /dev/sda1

kdump_path: /var/crash/vmcore kernel_settings_reboot_ok: true

The settings specified in the example playbook include the following:

kdump_target: <type_and_location>

Writes **vmcore** to a location other than the root file system. The **location** refers to a partition (by name, label, or UUID) when the **type** is raw or file system.

kernel_settings_reboot_ok: <true|false>

The default is **false**. If set to **true**, the system role will determine if a reboot of the managed host is necessary for the requested changes to take effect and reboot it. If set to **false**, the role will return the variable **kernel_settings_reboot_required** with a value of **true**, indicating that a reboot is required. In this case, a user must reboot the managed node manually.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.kdump/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Verify the kernel crash dump parameters:

\$ ansible managed-node-01.example.com -m command -a 'grep crashkernel /proc/cmdline'

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.kdump/README.md file
- /usr/share/doc/rhel-system-roles/kdump/ directory

CHAPTER 14. CONFIGURING KERNEL PARAMETERS PERMANENTLY BY USING RHEL SYSTEM ROLES

You can use the **kernel_settings** RHEL system role to configure kernel parameters on multiple clients simultaneously. Simultaneous configuration has the following advantages:

- Provides a friendly interface with efficient input setting.
- Keeps all intended kernel parameters in one place.

After you run the **kernel_settings** role from the control machine, the kernel parameters are applied to the managed systems immediately and persist across reboots.



IMPORTANT

Note that RHEL system role delivered over RHEL channels are available to RHEL customers as an RPM package in the default AppStream repository. RHEL system role are also available as a collection to customers with Ansible subscriptions over Ansible Automation Hub.

14.1. APPLYING SELECTED KERNEL PARAMETERS BY USING THE KERNEL_SETTINGS RHEL SYSTEM ROLE

You can use the **kernel_settings** RHEL system role to remotely configure various kernel parameters across multiple managed operating systems with persistent effects. For example, you can configure:

- Transparent hugepages to increase performance by reducing the overhead of managing smaller pages.
- The largest packet sizes to be transmitted over the network with the loopback interface.
- Limits on files to be opened simultaneously.

Prerequisites

- You have prepared the control node and the managed nodes.
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

 name: Configuring kernel settings hosts: managed-node-01.example.com tasks:

- name: Configure hugepages, packet size for loopback device, and limits on simultaneously open files.

ansible.builtin.include role:

name: redhat.rhel_system_roles.kernel_settings

vars:

kernel_settings_sysctl:

- name: fs.file-max

value: 400000

- name: kernel.threads-max

value: 65536

kernel_settings_sysfs:

- name: /sys/class/net/lo/mtu

value: 65000

kernel_settings_transparent_hugepages: madvise

kernel settings reboot ok: true

The settings specified in the example playbook include the following:

kernel_settings_sysfs: < list_of_sysctl_settings>

A YAML list of **sysctl** settings and the values you want to assign to these settings.

kernel_settings_transparent_hugepages: <value>

Controls the memory subsystem Transparent Huge Pages (THP) setting. You can disable THP support (**never**), enable it system wide (**always**) or inside **MAD_HUGEPAGE** regions (**madvise**).

kernel_settings_reboot_ok: <true|false>

The default is **false**. If set to **true**, the system role will determine if a reboot of the managed host is necessary for the requested changes to take effect and reboot it. If set to **false**, the role will return the variable **kernel_settings_reboot_required** with a value of **true**, indicating that a reboot is required. In this case, a user must reboot the managed node manually.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.kdump/README.md file on the control node.

1. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

2. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Verify the affected kernel parameters:

ansible managed-node-01.example.com -m command -a 'sysctl fs.file-max kernel.threads-max net.ipv6.conf.lo.mtu'
ansible managed-node-01.example.com -m command -a 'cat /sys/kernel/mm/transparent_hugepage/enabled'

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.kernel_settings/README.md file
- /usr/share/doc/rhel-system-roles/kernel_settings/ directory

CHAPTER 15. CONFIGURING LOGGING BY USING RHEL SYSTEM ROLES

You can use the **logging** RHEL system role to configure your local and remote hosts as logging servers in an automated fashion to collect logs from many client systems.

Logging solutions provide multiple ways of reading logs and multiple logging outputs.

For example, a logging system can receive the following inputs:

- Local files
- systemd/journal
- Another logging system over the network

In addition, a logging system can have the following outputs:

- Logs stored in the local files in the /var/log/ directory
- Logs sent to Elasticsearch engine
- Logs forwarded to another logging system

With the **logging** RHEL system role, you can combine the inputs and outputs to fit your scenario. For example, you can configure a logging solution that stores inputs from **journal** in a local file, whereas inputs read from files are both forwarded to another logging system and stored in the local log files.

15.1. FILTERING LOCAL LOG MESSAGES BY USING THELOGGING RHEL SYSTEM ROLE

You can use the property-based filter of the **logging** RHEL system role to filter your local log messages based on various conditions. As a result, you can achieve for example:

- Log clarity: In a high-traffic environment, logs can grow rapidly. The focus on specific messages, like errors, can help to identify problems faster.
- Optimized system performance: Excessive amount of logs is usually connected with system performance degradation. Selective logging for only the important events can prevent resource depletion, which enables your systems to run more efficiently.
- Enhanced security: Efficient filtering through security messages, like system errors and failed logins, helps to capture only the relevant logs. This is important for detecting breaches and meeting compliance standards.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Deploy the logging solution hosts: managed-node-01.example.com tasks: - name: Filter logs based on a specific value they contain ansible.builtin.include role: name: redhat.rhel_system_roles.logging logging_inputs: - name: files_input type: basics logging_outputs: - name: files output0 type: files property: msg property_op: contains property value: error path: /var/log/errors.log - name: files_output1 type: files property: msg property_op: "!contains" property_value: error path: /var/log/others.log logging_flows: - name: flow0 inputs: [files input] outputs: [files_output0, files_output1]

The settings specified in the example playbook include the following:

logging_inputs

Defines a list of logging input dictionaries. The **type: basics** option covers inputs from **systemd** journal or Unix socket.

logging_outputs

Defines a list of logging output dictionaries. The **type: files** option supports storing logs in the local files, usually in the /var/log/ directory. The **property: msg**; **property: contains**; and **property_value: error** options specify that all logs that contain the **error** string are stored in the /var/log/errors.log file. The **property: msg**; **property: !contains**; and **property_value: error** options specify that all other logs are put in the /var/log/others.log file. You can replace the **error** value with the string by which you want to filter.

logging_flows

Defines a list of logging flow dictionaries to specify relationships between **logging_inputs** and **logging_outputs**. The **inputs:** [files_input] option specifies a list of inputs, from which processing of logs starts. The **outputs:** [files_output0, files_output1] option specifies a list of outputs, to which the logs are sent.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.logging/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. On the managed node, test the syntax of the /etc/rsyslog.conf file:

rsyslogd -N 1

rsyslogd: version 8.1911.0-6.el8, config validation run...

rsyslogd: End of config validation run. Bye.

- 2. On the managed node, verify that the system sends messages that contain the **error** string to the log:
 - a. Send a test message:

logger error

b. View the /var/log/errors.log log, for example:

cat /var/log/errors.log

Aug 5 13:48:31 hostname root[6778]: error

Where *hostname* is the host name of the client system. Note that the log contains the user name of the user that entered the logger command, in this case **root**.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.logging/README.md file
- /usr/share/doc/rhel-system-roles/logging/ directory
- rsyslog.conf(5) and syslog(3) man pages on your system

15.2. APPLYING A REMOTE LOGGING SOLUTION BY USING THE LOGGING RHEL SYSTEM ROLE

You can use the **logging** RHEL system role to configure a remote logging solution, where one or more clients take logs from the **systemd-journal** service and forward them to a remote server. The server receives remote input from the **remote_rsyslog** and **remote_files** configurations, and outputs the logs to local files in directories named by remote host names.

As a result, you can cover use cases where you need for example:

Centralized log management: Collecting, accessing, and managing log messages of multiple
machines from a single storage point simplifies day-to-day monitoring and troubleshooting
tasks. Also, this use case reduces the need to log into individual machines to check the log

messages.

- Enhanced security: Storing log messages in one central place increases chances they are in a secure and tamper-proof environment. Such an environment makes it easier to detect and respond to security incidents more effectively and to meet audit requirements.
- Improved efficiency in log analysis: Correlating log messages from multiple systems is important for fast troubleshooting of complex problems that span multiple machines or services. That way you can quickly analyze and cross-reference events from different sources.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- Define the ports in the SELinux policy of the server or client system and open the firewall for those ports. The default SELinux policy includes ports 601, 514, 6514, 10514, and 20514. To use a different port, see modify the SELinux policy on the client and server systems.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Deploy the logging solution
 hosts: managed-node-01.example.com
  - name: Configure the server to receive remote input
   ansible.builtin.include role:
    name: redhat.rhel_system_roles.logging
   vars:
    logging_inputs:
      - name: remote udp input
       type: remote
       udp_ports: [ 601 ]
      - name: remote_tcp_input
       type: remote
       tcp_ports: [ 601 ]
    logging_outputs:
      - name: remote_files_output
       type: remote_files
    logging flows:
      - name: flow 0
       inputs: [remote_udp_input, remote_tcp_input]
       outputs: [remote_files_output]
- name: Deploy the logging solution
 hosts: managed-node-02.example.com
  - name: Configure the server to output the logs to local files in directories named by
remote host names
   ansible.builtin.include role:
    name: redhat.rhel_system_roles.logging
```

vars:

logging_inputs:

- name: basic_input

type: basics logging outputs:

- name: forward_output0

type: forwards severity: info

target: <host1.example.com>

udp port: 601

- name: forward_output1

type: forwards facility: mail

target: <host1.example.com>

tcp_port: 601 logging_flows: - name: flows0 inputs: [basic_input]

outputs: [forward_output0, forward_output1]

The settings specified in the first play of the example playbook include the following:

logging_inputs

Defines a list of logging input dictionaries. The **type: remote** option covers remote inputs from the other logging system over the network. The **udp_ports:** [**601**] option defines a list of UDP port numbers to monitor. The **tcp_ports:** [**601**] option defines a list of TCP port numbers to monitor. If both **udp_ports** and **tcp_ports** is set, **udp_ports** is used and **tcp_ports** is dropped.

logging_outputs

Defines a list of logging output dictionaries. The **type: remote_files** option makes output store logs to the local files per remote host and program name originated the logs.

logging_flows

Defines a list of logging flow dictionaries to specify relationships between **logging_inputs** and **logging_outputs**. The **inputs:** [remote_udp_input, remote_tcp_input] option specifies a list of inputs, from which processing of logs starts. The **outputs:** [remote_files_output] option specifies a list of outputs, to which the logs are sent.

The settings specified in the second play of the example playbook include the following:

logging_inputs

Defines a list of logging input dictionaries. The **type: basics** option covers inputs from **systemd** journal or Unix socket.

logging_outputs

Defines a list of logging output dictionaries. The **type: forwards** option supports sending logs to the remote logging server over the network. The **severity: info** option refers to log messages of the informative importance. The **facility: mail** option refers to the type of system program that is generating the log message. The **target:** <host1.example.com> option specifies the hostname of the remote logging server. The **udp_port:** 601/tcp_port: 601 options define the UDP/TCP ports on which the remote logging server listens.

logging_flows

Defines a list of logging flow dictionaries to specify relationships between **logging_inputs** and **logging_outputs**. The **inputs:** [basic_input] option specifies a list of inputs, from which processing of logs starts. The **outputs:** [forward_output0, forward_output1] option

specifies a list of outputs, to which the logs are sent.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.logging/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. On both the client and the server system, test the syntax of the /etc/rsyslog.conf file:

rsyslogd -N 1

rsyslogd: version 8.1911.0-6.el8, config validation run (level 1), master config

/etc/rsyslog.conf

rsyslogd: End of config validation run. Bye.

- 2. Verify that the client system sends messages to the server:
 - a. On the client system, send a test message:

logger test

b. On the server system, view the /var/log/<host2.example.com>/messages log, for example:

cat /var/log/<host2.example.com>/messages
Aug 5 13:48:31 <host2.example.com> root[6778]: test

Where **<host2.example.com>** is the host name of the client system. Note that the log contains the user name of the user that entered the logger command, in this case **root**.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.logging/README.md file
- /usr/share/doc/rhel-system-roles/logging/ directory
- rsyslog.conf(5) and syslog(3) manual pages

15.3. USING THE LOGGING RHEL SYSTEM ROLE WITH TLS

Transport Layer Security (TLS) is a cryptographic protocol designed to allow secure communication over the computer network.

You can use the **logging** RHEL system role to configure a secure transfer of log messages, where one or more clients take logs from the **systemd-journal** service and transfer them to a remote server while using TLS.

Typically, TLS for transferring logs in a remote logging solution is used when sending sensitive data over less trusted or public networks, such as the Internet. Also, by using certificates in TLS you can ensure that the client is forwarding logs to the correct and trusted server. This prevents attacks like "man-in-the-middle".

15.3.1. Configuring client logging with TLS

You can use the **logging** RHEL system role to configure logging on RHEL clients and transfer logs to a remote logging system using TLS encryption.

This procedure creates a private key and a certificate. Next, it configures TLS on all hosts in the clients group in the Ansible inventory. The TLS protocol encrypts the message transmission for secure transfer of logs over the network.



NOTE

You do not have to call the **certificate** RHEL system role in the playbook to create the certificate. The **logging** RHEL system role calls it automatically when the **logging_certificates** variable is set.

In order for the CA to be able to sign the created certificate, the managed nodes must be enrolled in an IdM domain.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has sudo permissions on them.
- The managed nodes are enrolled in an IdM domain.
- If the logging server you want to configure on the manage node runs RHEL 9.2 or later and the FIPS mode is enabled, clients must either support the Extended Master Secret (EMS) extension or use TLS 1.3. TLS 1.2 connections without EMS fail. For more information, see the Red Hat Knowledgebase solution TLS extension "Extended Master Secret" enforced.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

--

- name: Configure remote logging solution using TLS for secure transfer of logs hosts: managed-node-01.example.com tasks:
 - name: Deploying files input and forwards output with certs ansible.builtin.include_role:

name: redhat.rhel_system_roles.logging

vars:

logging_certificates:name: logging_cert

```
dns: ['www.example.com']
  ca: ipa
  principal: "logging/{{ inventory_hostname }}@IDM.EXAMPLE.COM"
logging_pki_files:
 - ca cert: /local/path/to/ca cert.pem
  cert: /local/path/to/logging_cert.pem
  private key: /local/path/to/logging cert.pem
logging inputs:
 - name: input_name
  type: files
  input_log_path: /var/log/containers/*.log
logging_outputs:
 - name: output_name
  type: forwards
  target: your_target_host
  tcp_port: 514
  tls: true
  pki authmode: x509/name
  permitted_server: 'server.example.com'
logging flows:
 - name: flow_name
  inputs: [input_name]
  outputs: [output_name]
```

The settings specified in the example playbook include the following:

logging_certificates

The value of this parameter is passed on to **certificate_requests** in the **certificate** RHEL system role and used to create a private key and certificate.

logging_pki_files

Using this parameter, you can configure the paths and other settings that logging uses to find the CA, certificate, and key files used for TLS, specified with one or more of the following sub-parameters: **ca_cert**, **ca_cert_src**, **cert**, **cert_src**, **private_key**, **private_key_src**, and **tls**.



NOTE

If you are using **logging_certificates** to create the files on the managed node, do not use **ca_cert_src**, **cert_src**, and **private_key_src**, which are used to copy files not created by **logging_certificates**.

ca_cert

Represents the path to the CA certificate file on the managed node. Default path is /etc/pki/tls/certs/ca.pem and the file name is set by the user.

cert

Represents the path to the certificate file on the managed node. Default path is /etc/pki/tls/certs/server-cert.pem and the file name is set by the user.

private key

Represents the path to the private key file on the managed node. Default path is /etc/pki/tls/private/server-key.pem and the file name is set by the user.

ca_cert_src

Represents the path to the CA certificate file on the control node which is copied to the target host to the location specified by **ca_cert**. Do not use this if using **logging_certificates**.

cert_src

Represents the path to a certificate file on the control node which is copied to the target host to the location specified by **cert**. Do not use this if using **logging_certificates**.

private_key_src

Represents the path to a private key file on the control node which is copied to the target host to the location specified by **private_key**. Do not use this if using **logging_certificates**.

tls

Setting this parameter to **true** ensures secure transfer of logs over the network. If you do not want a secure wrapper, you can set **tls: false**.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.logging/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.logging/README.md file
- /usr/share/doc/rhel-system-roles/logging/ directory
- /usr/share/ansible/roles/rhel-system-roles.certificate/README.md file
- /usr/share/doc/rhel-system-roles/certificate/ directory
- Requesting certificates using RHEL system roles.
- rsyslog.conf(5) and syslog(3) manual pages

15.3.2. Configuring server logging with TLS

You can use the **logging** RHEL system role to configure logging on RHEL servers and set them to receive logs from a remote logging system using TLS encryption.

This procedure creates a private key and a certificate. Next, it configures TLS on all hosts in the server group in the Ansible inventory.



NOTE

You do not have to call the **certificate** RHEL system role in the playbook to create the certificate. The **logging** RHEL system role calls it automatically.

In order for the CA to be able to sign the created certificate, the managed nodes must be enrolled in an IdM domain.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The managed nodes are enrolled in an IdM domain.
- If the logging server you want to configure on the manage node runs RHEL 9.2 or later and the FIPS mode is enabled, clients must either support the Extended Master Secret (EMS) extension or use TLS 1.3. TLS 1.2 connections without EMS fail. For more information, see the Red Hat Knowledgebase solution TLS extension "Extended Master Secret" enforced.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure remote logging solution using TLS for secure transfer of logs
 hosts: managed-node-01.example.com
 tasks:
  - name: Deploying remote input and remote_files output with certs
   ansible.builtin.include role:
    name: redhat.rhel_system_roles.logging
   vars:
    logging_certificates:
     - name: logging cert
       dns: ['www.example.com']
       principal: "logging/{{ inventory_hostname }}@IDM.EXAMPLE.COM"
    logging pki files:
     - ca cert: /local/path/to/ca cert.pem
       cert: /local/path/to/logging cert.pem
       private_key: /local/path/to/logging_cert.pem
    logging_inputs:
     - name: input name
       type: remote
       tcp_ports: [514]
       tls: true
       permitted_clients: ['clients.example.com']
    logging outputs:
     - name: output_name
       type: remote_files
       remote log path: /var/log/remote/%FROMHOST%/%PROGRAMNAME:::secpath-
replace%.log
       async writing: true
```

client_count: 20 io_buffer_size: 8192

inputs: [input_name]
outputs: [output_name]

The settings specified in the example playbook include the following:

logging_certificates

The value of this parameter is passed on to **certificate_requests** in the **certificate** RHEL system role and used to create a private key and certificate.

logging_pki_files

Using this parameter, you can configure the paths and other settings that logging uses to find the CA, certificate, and key files used for TLS, specified with one or more of the following sub-parameters: **ca_cert**, **ca_cert_src**, **cert**, **cert_src**, **private_key**, **private_key_src**, and **tls**.



NOTE

If you are using **logging_certificates** to create the files on the managed node, do not use **ca_cert_src**, **cert_src**, and **private_key_src**, which are used to copy files not created by **logging_certificates**.

ca cert

Represents the path to the CA certificate file on the managed node. Default path is /etc/pki/tls/certs/ca.pem and the file name is set by the user.

cert

Represents the path to the certificate file on the managed node. Default path is /etc/pki/tls/certs/server-cert.pem and the file name is set by the user.

private key

Represents the path to the private key file on the managed node. Default path is /etc/pki/tls/private/server-key.pem and the file name is set by the user.

ca_cert_src

Represents the path to the CA certificate file on the control node which is copied to the target host to the location specified by **ca_cert**. Do not use this if using **logging_certificates**.

cert src

Represents the path to a certificate file on the control node which is copied to the target host to the location specified by **cert**. Do not use this if using **logging_certificates**.

private_key_src

Represents the path to a private key file on the control node which is copied to the target host to the location specified by **private_key**. Do not use this if using **logging_certificates**.

tls

Setting this parameter to **true** ensures secure transfer of logs over the network. If you do not want a secure wrapper, you can set **tls: false**.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.logging/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.logging/README.md file
- /usr/share/doc/rhel-system-roles/logging/ directory
- Requesting certificates using RHEL system roles .
- rsyslog.conf(5) and syslog(3) manual pages

15.4. USING THE LOGGING RHEL SYSTEM ROLES WITH RELP

Reliable Event Logging Protocol (RELP) is a networking protocol for data and message logging over the TCP network. It ensures reliable delivery of event messages and you can use it in environments that do not tolerate any message loss.

The RELP sender transfers log entries in the form of commands and the receiver acknowledges them once they are processed. To ensure consistency, RELP stores the transaction number to each transferred command for any kind of message recovery.

You can consider a remote logging system in between the RELP Client and RELP Server. The RELP Client transfers the logs to the remote logging system and the RELP Server receives all the logs sent by the remote logging system. To achieve that use case, you can use the **logging** RHEL system role to configure the logging system to reliably send and receive log entries.

15.4.1. Configuring client logging with RELP

You can use the **logging** RHEL system role to configure a transfer of log messages stored locally to the remote logging system with RELP.

This procedure configures RELP on all hosts in the **clients** group in the Ansible inventory. The RELP configuration uses Transport Layer Security (TLS) to encrypt the message transmission for secure transfer of logs over the network.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure client-side of the remote logging solution using RELP
hosts: managed-node-01.example.com
tasks:
  - name: Deploy basic input and RELP output
   ansible.builtin.include role:
    name: redhat.rhel_system_roles.logging
    logging_inputs:
     - name: basic_input
       type: basics
    logging_outputs:
     - name: relp client
       type: relp
       target: logging.server.com
       port: 20514
       tls: true
       ca cert: /etc/pki/tls/certs/ca.pem
       cert: /etc/pki/tls/certs/client-cert.pem
       private_key: /etc/pki/tls/private/client-key.pem
       pki authmode: name
       permitted servers:
        - '*.server.example.com'
    logging_flows:
     - name: example_flow
       inputs: [basic input]
       outputs: [relp_client]
```

The settings specified in the example playbook include the following:

target

This is a required parameter that specifies the host name where the remote logging system is running.

port

Port number the remote logging system is listening.

tls

Ensures secure transfer of logs over the network. If you do not want a secure wrapper you can set the **tls** variable to **false**. By default **tls** parameter is set to true while working with RELP and requires key/certificates and triplets {**ca_cert**, **cert**, **private_key**} and/or {**ca_cert_src**, **cert_src**, **private_key_src**}.

- If the {ca_cert_src, cert_src, private_key_src} triplet is set, the default locations
 /etc/pki/tls/certs and /etc/pki/tls/private are used as the destination on the managed
 node to transfer files from control node. In this case, the file names are identical to the
 original ones in the triplet
- If the {ca_cert, cert, private_key} triplet is set, files are expected to be on the default path before the logging configuration.
- If both triplets are set, files are transferred from local path from control node to specific path of the managed node.

ca_cert

Represents the path to CA certificate. Default path is /etc/pki/tls/certs/ca.pem and the file name is set by the user.

cert

Represents the path to certificate. Default path is /etc/pki/tls/certs/server-cert.pem and the file name is set by the user.

private_key

Represents the path to private key. Default path is /etc/pki/tls/private/server-key.pem and the file name is set by the user.

ca_cert_src

Represents local CA certificate file path which is copied to the managed node. If **ca_cert** is specified, it is copied to the location.

cert src

Represents the local certificate file path which is copied to the managed node. If **cert** is specified, it is copied to the location.

private_key_src

Represents the local key file path which is copied to the managed node. If **private_key** is specified, it is copied to the location.

pki_authmode

Accepts the authentication mode as **name** or **fingerprint**.

permitted servers

List of servers that will be allowed by the logging client to connect and send logs over TLS.

inputs

List of logging input dictionary.

outputs

List of logging output dictionary.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.logging/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:



Additional resources

- /usr/share/ansible/roles/rhel-system-roles.logging/README.md file
- /usr/share/doc/rhel-system-roles/logging/ directory
- rsyslog.conf(5) and syslog(3) manual pages

15.4.2. Configuring server logging with RELP

You can use the **logging** RHEL system role to configure a server for receiving log messages from the remote logging system with RELP.

This procedure configures RELP on all hosts in the **server** group in the Ansible inventory. The RELP configuration uses TLS to encrypt the message transmission for secure transfer of logs over the network.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure server-side of the remote logging solution using RELP
hosts: managed-node-01.example.com
  - name: Deploying remote input and remote_files output
   ansible.builtin.include role:
    name: redhat.rhel system roles.logging
   vars:
    logging_inputs:
     - name: relp server
       type: relp
       port: 20514
       tls: true
       ca_cert: /etc/pki/tls/certs/ca.pem
       cert: /etc/pki/tls/certs/server-cert.pem
       private key: /etc/pki/tls/private/server-key.pem
       pki_authmode: name
       permitted_clients:
        - '*client.example.com'
    logging outputs:
     - name: remote files output
       type: remote_files
    logging_flows:
     - name: example_flow
       inputs: [relp_server]
       outputs: [remote_files_output]
```

The settings specified in the example playbook include the following:

port

Port number the remote logging system is listening.

tls

Ensures secure transfer of logs over the network. If you do not want a secure wrapper you can set the **tls** variable to **false**. By default **tls** parameter is set to true while working with

RELP and requires key/certificates and triplets {ca_cert, cert, private_key} and/or {ca_cert_src, cert_src, private_key_src}.

- If the {ca_cert_src, cert_src, private_key_src} triplet is set, the default locations
 /etc/pki/tls/certs and /etc/pki/tls/private are used as the destination on the managed
 node to transfer files from control node. In this case, the file names are identical to the
 original ones in the triplet
- If the {ca_cert, cert, private_key} triplet is set, files are expected to be on the default path before the logging configuration.
- If both triplets are set, files are transferred from local path from control node to specific path of the managed node.

ca_cert

Represents the path to CA certificate. Default path is /etc/pki/tls/certs/ca.pem and the file name is set by the user.

cert

Represents the path to the certificate. Default path is /etc/pki/tls/certs/server-cert.pem and the file name is set by the user.

private_key

Represents the path to private key. Default path is /etc/pki/tls/private/server-key.pem and the file name is set by the user.

ca_cert_src

Represents local CA certificate file path which is copied to the managed node. If **ca_cert** is specified, it is copied to the location.

cert src

Represents the local certificate file path which is copied to the managed node. If **cert** is specified, it is copied to the location.

private_key_src

Represents the local key file path which is copied to the managed node. If **private_key** is specified, it is copied to the location.

pki_authmode

Accepts the authentication mode as **name** or **fingerprint**.

permitted_clients

List of clients that will be allowed by the logging server to connect and send logs over TLS.

inputs

List of logging input dictionary.

outputs

List of logging output dictionary.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.logging/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.logging/README.md file
- /usr/share/doc/rhel-system-roles/logging/ directory
- rsyslog.conf(5) and syslog(3) manual pages

CHAPTER 16. CONFIGURING PERFORMANCE MONITORING WITH PCP BY USING RHEL SYSTEM ROLES

Performance Co-Pilot (PCP) is a system performance analysis toolkit. You can use it to record and analyze performance data from many components on a Red Hat Enterprise Linux system.

You can use the **metrics** RHEL system role to automate the installation and configuration of PCP, and the role can configure Grafana to visualize PCP metrics.

16.1. CONFIGURING PERFORMANCE CO-PILOT BY USING THEMETRICS RHEL SYSTEM ROLE

You can use Performance Co-Pilot (PCP) to monitor many metrics, such as CPU utilization and memory usage. For example, this can help to identify resource and performance bottlenecks. By using the **metrics** RHEL system role, you can remotely configure PCP on multiple hosts to record metrics.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

 name: Monitoring performance metrics hosts: managed-node-01.example.com tasks:

- name: Configure Performance Co-Pilot ansible.builtin.include role:

name: redhat.rhel_system_roles.metrics

vars:

metrics_retention_days: 14 metrics_manage_firewall: true metrics_manage_selinux: true

The settings specified in the example playbook include the following:

metrics retention days: < number>

Sets the number of days after which the **pmlogger_daily** systemd timer removes old PCP archives.

metrics_manage_firewall: <true/false>

Defines whether the role should open the required ports in the **firewalld** service. If you want to remotely access PCP on the managed nodes, set this variable to **true**.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.metrics/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

- Query a metric, for example:
 - # ansible managed-node-01.example.com -m command -a 'pminfo -f kernel.all.load'

Next step

• Optional: Configure Grafana to monitor PCP hosts and visualize metrics .

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.metrics/README.md file
- /usr/share/doc/rhel-system-roles/metrics/ directory

16.2. CONFIGURING PERFORMANCE CO-PILOT WITH AUTHENTICATION BY USING THE METRICS RHEL SYSTEM ROLE

You can enable authentication in Performance Co-Pilot (PCP) so that the **pmcd** service and Performance Metrics Domain Agents (PDMAs) can determine whether the user running the monitoring tools is allowed to perform an action. Authenticated users have access to metrics with sensitive information. Additionally, certain agents require authentication. For example, the **bpftrace** agent uses authentication to identify whether a user is allowed to load **bpftrace** scripts into the kernel to generate metrics.

By using the **metrics** RHEL system role, you can remotely configure PCP with authentication on multiple hosts.

Prerequisites

- You have prepared the control node and the managed nodes.
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml

New Vault password: <vault_password>

Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

```
metrics_usr: <username>
metrics_pwd: <password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: Monitoring performance metrics
hosts: managed-node-01.example.com
vars_files:
    - ~/vault.yml
tasks:
    - name: Configure Performance Co-Pilot
    ansible.builtin.include_role:
    name: redhat.rhel_system_roles.metrics
    vars:
    metrics_retention_days: 14
    metrics_manage_firewall: true
    metrics_manage_selinux: true
    metrics_username: "{{ metrics_usr}}"
    metrics_password: "{{ metrics_pwd}}"
```

The settings specified in the example playbook include the following:

metrics retention days: <number>

Sets the number of days after which the **pmlogger_daily** systemd timer removes old PCP archives.

metrics manage firewall: <true/false>

Defines whether the role should open the required ports in the **firewalld** service. If you want to remotely access PCP on the managed nodes, set this variable to **true**.

metrics username: <username>

The role creates this user locally on the managed node, adds the credentials to the /etc/pcp/passwd.db Simple Authentication and Security Layer (SASL) database, and configures authentication in PCP. Additionally, if you set metrics_from_bpftrace: true in the playbook, PCP uses this account to register bpftrace scripts.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.metrics/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Verification

- On a host with the **pcp** package installed, query a metric that requires authentication:
 - a. Query the metrics by using the credentials that you used in the playbook:

pminfo -fmdt -h pcp://managed-node-01.example.com?username=<user> proc.fd.count

Password: <password>

proc.fd.count

inst [844 or "000844 /var/lib/pcp/pmdas/proc/pmdaproc"] value 5

If the command succeeds, it returns the value of the **proc.fd.count** metric.

b. Run the command again, but omit the username to verify that the command fails for unauthenticated users:

pminfo -fmdt -h pcp://managed-node-01.example.com proc.fd.count

proc.fd.count

Error: No permission to perform requested operation

Next step

• Optional: Configure Grafana to monitor PCP hosts and visualize metrics .

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.metrics/README.md file
- /usr/share/doc/rhel-system-roles/metrics/ directory
- Ansible vault

16.3. SETTING UP GRAFANA BY USING THEMETRICS RHEL SYSTEM ROLE TO MONITOR MULTIPLE HOSTS WITH PERFORMANCE COPILOT

If you have already configured Performance Co-Pilot (PCP) on multiple hosts, you can use an instance of Grafana to visualize the metrics for these hosts. You can display the live data and, if the PCP data is stored in a Redis database, also past data.

By using the **metrics** RHEL system role, you can automate the process of setting up Grafana, the PCP plug-in, the optional Redis database, and the configuration of the data sources.



NOTE

If you use the **metrics** role to install Grafana on a host, the role also installs automatically PCP on this host.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- PCP is configured for remote access on the hosts you want to monitor .
- The host on which you want to install Grafana can access port 44321 on the PCP nodes you plan to monitor.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

```
grafana_admin_pwd: <password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Monitoring performance metrics
 hosts: managed-node-01.example.com
 vars_files:
  - ~/vault.yml
 tasks:
  - name: Set up Grafana to monitor multiple hosts
   ansible.builtin.include_role:
    name: redhat.rhel system roles.metrics
   vars:
    metrics_graph_service: true
    metrics_query_service: true
    metrics_monitored_hosts:
     - <pcp host 1.example.com>
     - <pcp host 2.example.com>
    metrics_manage_firewall: true
    metrics_manage_selinux: true
```

 name: Set Grafana admin password ansible.builtin.shell:

cmd: grafana-cli admin reset-admin-password "{{ grafana_admin_pwd }}"

The settings specified in the example playbook include the following:

metrics_graph_service: true

Installs Grafana and the PCP plug-in. Additionally, the role adds the **PCP Vector**, **PCP Redis**, and **PCP bpftrace** data sources to Grafana.

metrics_query_service: <true/false>

Defines whether the role should install and configure Redis for centralized metric recording. If enabled, data collected from PCP clients is stored in Redis and, as a result, you can also display historical data instead of only live data.

metrics_monitored_hosts: < list_of_hosts>

Defines the list of hosts to monitor. In Grafana, you can then display the data of these hosts and, additionally, the host that runs Grafana.

metrics manage firewall: <true/false>

Defines whether the role should open the required ports in the **firewalld** service. If you set this variable to **true**, you can, for example, access Grafana remotely.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.metrics/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Verification

- 1. Open http://*<grafana_server_IP_or_hostname>*:3000 in your browser, and log in as the admin user with the password you set in the procedure.
- 2. Display monitoring data:
 - To display live data:
 - i. Click Menu → Apps → Performance Co-Pilot → PCP Vector Checklist
 - ii. By default, the graphs display metrics from the host that runs Grafana. To switch to a different host, enter the hostname in the **hostspec** field and press **Enter**.
 - To display historical data stored in a Redis database: Create a panel with a PCP Redis data source. This requires that you set **metrics_query_service: true** in the playbook.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.metrics/README.md file
- /usr/share/doc/rhel-system-roles/metrics/ directory
- Ansible vault

16.4. CONFIGURING WEB HOOKS IN PERFORMANCE CO-PILOT BY USING THE METRICS RHEL SYSTEM ROLE

The Performance Co-Pilot (PCP) suite contains the performance metrics inference engine (PMIE) service. This service evaluates performance rules in real time. For example, you can use the default rules to detect excessive swap activities.

You can configure a host as a central PCP management site that collects the monitoring data from multiple PCP nodes. If a rule matches, this central host sends a notification to a web hook to notify other services. For example, the web hook can trigger Event-Driven Ansible to run on Ansible Automation Platform template or playbook on the host that had caused the event.

By using the **metrics** RHEL system role, you can automate the configuration of a central PCP management host that notifies a web hook.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- PCP is configured for remote access on the hosts you want to monitor .
- The host on which you want to configure PMIE can access port 44321 on the PCP nodes you plan to monitor.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: Monitoring performance metrics
hosts: managed-node-01.example.com
tasks:
- name: Configure PMIE web hooks
    ansible.builtin.include_role:
    name: redhat.rhel_system_roles.metrics
    vars:
    metrics_manage_firewall: true
    metrics_retention_days: 7
    metrics_monitored_hosts:
    - pcp-node-01.example.com
    - pcp-node-02.example.com
    metrics_webhook_endpoint: "https://<webserver>:<port>/<endpoint>"
```

The settings specified in the example playbook include the following:

metrics_retention_days: <number>

Sets the number of days after which the **pmlogger_daily** systemd timer removes old PCP archives.

metrics manage firewall: <true/false>

Defines whether the role should open the required ports in the **firewalld** service. If you want to remotely access PCP on the managed nodes, set this variable to **true**.

metrics_monitored_hosts: < list_of_hosts>

Specifies the hosts to observe.

metrics_webhook_endpoint: <URL>

Sets the web hook endpoint to which the performance metrics inference engine (PMIE) sends notifications about detected performance issues. By default, these issues are logged to the local system only.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.metrics/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. Check the configuration summary on **managed-node-node-01.example.com**:

```
# ansible managed-node-01.example.com -m command -a 'pcp summary'
```

Performance Co-Pilot configuration on managed-node-01.example.com:

platform: Linux managed-node-node-01.example.com 5.14.0-427.el9.x86_64 #1 SMP

PREEMPT DYNAMIC Fri Feb 23 01:51:18 EST 2024 x86 64

hardware: 8 cpus, 1 disk, 1 node, 1773MB RAM

timezone: CEST-2

services: pmcd pmproxy

pmcd: Version 6.2.0-1, 12 agents, 6 clients

pmda: root pmcd proc pmproxy xfs linux nfsclient mmv kvm jbd2

dm openmetrics

pmlogger: primary logger: /var/log/pcp/pmlogger/managed-node-node-

01.example.com/20240510.16.25

pcp-node-01.example.com: /var/log/pmlogger/pcp-node-

01.example.com/20240510.16.25

pcp-node-02.example.com: /var/log/pmlogger/pcp-node-

02.example.com/20240510.16.25

pmie: primary engine: /var/log/pcp/pmie/managed-node-01.example.com/pmie.log pcp-node-01.example.com: : /var/log/pcp/pmie/pcp-node-01.example.com/pmie.log

pcp-node-02.example.com: : /var/log/pcp/pmie/pcp-node-02.example.com/pmie.log

The last three lines confirm that PMIE is configured to monitor three systems.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.metrics/README.md file
- /usr/share/doc/rhel-system-roles/metrics/ directory
- Automate performance management with Performance Co-Pilot using Event-Driven Ansible blog post

CHAPTER 17. CONFIGURING NBDE BY USING RHEL SYSTEM ROLES

You can use the **nbde_client** and **nbde_server** RHEL system roles for automated deployments of Policy-Based Decryption (PBD) solutions using Clevis and Tang. The **rhel-system-roles** package contains these system roles, the related examples, and also the reference documentation.

17.1. USING THE NBDE_SERVER RHEL SYSTEM ROLE FOR SETTING UP MULTIPLE TANG SERVERS

By using the **nbde_server** system role, you can deploy and manage a Tang server as part of an automated disk encryption solution. This role supports the following features:

- Rotating Tang keys
- Deploying and backing up Tang keys

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
name: Deploy a Tang server
hosts: tang.server.example.com
tasks:

name: Install and configure periodic key rotation
ansible.builtin.include_role:
    name: redhat.rhel_system_roles.nbde_server
vars:
    nbde_server_rotate_keys: yes
    nbde_server_manage_firewall: true
    nbde_server_manage_selinux: true
```

This example playbook ensures deploying of your Tang server and a key rotation.

The settings specified in the example playbook include the following:

nbde_server_manage_firewall: true

Use the **firewall** system role to manage ports used by the **nbde_server** role.

nbde_server_manage_selinux: true

Use the **selinux** system role to manage ports used by the **nbde_server** role. For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.nbde_server/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• On your NBDE client, verify that your Tang server works correctly by using the following command. The command must return the identical message you pass for encryption and decryption:

ansible managed-node-01.example.com -m command -a 'echo test | clevis encrypt tang '{"url":"<tang.server.example.com>"}' -y | clevis decrypt' test

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.nbde server/README.md file
- /usr/share/doc/rhel-system-roles/nbde_server/ directory

17.2. SETTING UP CLEVIS CLIENTS WITH DHCP BY USING THE NBDE CLIENT RHEL SYSTEM ROLE

The **nbde_client** system role enables you to deploy multiple Clevis clients in an automated way.

This role supports binding a LUKS-encrypted volume to one or more Network-Bound (NBDE) servers - Tang servers. You can either preserve the existing volume encryption with a passphrase or remove it. After removing the passphrase, you can unlock the volume only using NBDE. This is useful when a volume is initially encrypted using a temporary key or password that you should remove after you provision the system.

If you provide both a passphrase and a key file, the role uses what you have provided first. If it does not find any of these valid, it attempts to retrieve a passphrase from an existing binding.

Policy-Based Decryption (PBD) defines a binding as a mapping of a device to a slot. This means that you can have multiple bindings for the same device. The default slot is slot 1.



NOTE

The **nbde_client** system role supports only Tang bindings. Therefore, you cannot use it for TPM2 bindings.

Prerequisites

• You have prepared the control node and the managed nodes .

- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- A volume that is already encrypted by using LUKS.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

 name: Configure clients for unlocking of encrypted volumes by Tang servers hosts: managed-node-01.example.com tasks:

- name: Create NBDE client bindings ansible.builtin.include_role:

name: redhat.rhel_system_roles.nbde_client

vars:

nbde_client_bindings:

device: /dev/rhel/root

encryption_key_src: /etc/luks/keyfile

nbde_client_early_boot: true

state: present servers:

- http://server1.example.com
- http://server2.example.com
- device: /dev/rhel/swap

encryption_key_src: /etc/luks/keyfile

servers:

- http://server1.example.com
- http://server2.example.com

This example playbook configures Clevis clients for automated unlocking of two LUKS-encrypted volumes when at least one of two Tang servers is available.

The settings specified in the example playbook include the following:

state: present

The values of **state** indicate the configuration after you run the playbook. Use the **present** value for either creating a new binding or updating an existing one. Contrary to a **clevis luks bind** command, you can use **state: present** also for overwriting an existing binding in its device slot. The **absent** value removes a specified binding.

nbde_client_early_boot: true

The **nbde_client** role ensures that networking for a Tang pin is available during early boot by default. If you scenario requires to disable this feature, add the **nbde_client_early_boot: false** variable to your playbook.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.nbde_client/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. On your NBDE client, check that the encrypted volume that should be automatically unlocked by your Tang servers contain the corresponding information in its LUKS pins:

```
# ansible managed-node-01.example.com -m command -a 'clevis luks list -d /dev/rhel/root' 1: tang '{"url":"<a href="http://server1.example.com/>"}' 2: tang '{"url":"<a href="http://server2.example.com/>"}'
```

2. If you do not use the **nbde_client_early_boot: false** variable, verify that the bindings are available for the early boot, for example:

```
# ansible managed-node-01.example.com -m command -a 'Isinitrd | grep clevis-luks' lrwxrwxrwx 1 root root 48 Jan 4 02:56 etc/systemd/system/cryptsetup.target.wants/clevis-luks-askpass.path -> /usr/lib/systemd/system/clevis-luks-askpass.path ...
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.nbde_client/README.md file
- /usr/share/doc/rhel-system-roles/nbde client/ directory

17.3. SETTING UP STATIC-IP CLEVIS CLIENTS BY USING THE NBDE_CLIENT RHEL SYSTEM ROLE

The **nbde_client** RHEL system role supports only scenarios with Dynamic Host Configuration Protocol (DHCP). On an NBDE client with static IP configuration, you must pass your network configuration as a kernel boot parameter.

Typically, administrators want to reuse a playbook and not maintain individual playbooks for each host to which Ansible assigns static IP addresses during early boot. In this case, you can use variables in the playbook and provide the settings in an external file. As a result, you need only one playbook and one file with the settings.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- A volume that is already encrypted by using LUKS.

Procedure

1. Create a file with the network settings of your hosts, for example, **static-ip-settings-clients.yml**, and add the values you want to dynamically assign to the hosts:

```
clients:
       managed-node-01.example.com:
        ip v4: 192.0.2.1
        gateway v4: 192.0.2.254
        netmask v4: 255.255.255.0
        interface: enp1s0
       managed-node-02.example.com:
        ip_v4: 192.0.2.2
        gateway_v4: 192.0.2.254
        netmask_v4: 255.255.255.0
        interface: enp1s0
2. Create a playbook file, for example, ~/playbook.yml, with the following content:
      - name: Configure clients for unlocking of encrypted volumes by Tang servers
       hosts: managed-node-01.example.com, managed-node-02.example.com
       vars files:
        - ~/static-ip-settings-clients.yml
        - name: Create NBDE client bindings
          ansible.builtin.include_role:
           name: redhat.rhel system roles.network
           nbde client bindings:
            - device: /dev/rhel/root
             encryption key src: /etc/luks/keyfile
             servers:
              - http://server1.example.com
              http://server2.example.com
            - device: /dev/rhel/swap
             encryption_key_src: /etc/luks/keyfile
             servers:
              http://server1.example.com
              - http://server2.example.com
        - name: Configure a Clevis client with static IP address during early boot
          ansible.builtin.include role:
           name: redhat.rhel_system_roles.bootloader
          vars:
           bootloader settings:
            - kernel: ALL
             options:
              - name: ip
                value: "{{ clients[inventory_hostname]['ip_v4'] }}::{{ clients[inventory_hostname]
      ['gateway_v4'] }}:{{ clients[inventory_hostname]['netmask_v4'] }}::{{
```

This playbook reads certain values dynamically for each host listed in the ~/static-ip-settings-clients.yml file.

clients[inventory_hostname]['interface'] }}:none"

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.nbde_client/README.md file
- /usr/share/doc/rhel-system-roles/nbde_client/ directory
- Looking forward to Linux network configuration in the initial ramdisk (initrd) (Red Hat Enable Sysadmin)

CHAPTER 18. CONFIGURING NETWORK SETTINGS BY USING RHEL SYSTEM ROLES

By using the **network** RHEL system role, you can automate network-related configuration and management tasks.

18.1. CONFIGURING AN ETHERNET CONNECTION WITH A STATIC IP ADDRESS BY USING THE NETWORK RHEL SYSTEM ROLE WITH AN INTERFACE NAME

To connect a Red Hat Enterprise Linux host to an Ethernet network, create a NetworkManager connection profile for the network device. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use the **network** RHEL system role to configure an Ethernet connection with static IP addresses, gateways, and DNS settings, and assign them to a specified interface name.

Typically, administrators want to reuse a playbook and not maintain individual playbooks for each host to which Ansible should assign static IP addresses. In this case, you can use variables in the playbook and maintain the settings in the inventory. As a result, you need only one playbook to dynamically assign individual settings to multiple hosts.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- A physical or virtual Ethernet device exists in the server configuration.
- The managed nodes use NetworkManager to configure the network.

Procedure

1. Edit the ~/inventory file, and append the host-specific settings to the host entries:

managed-node-01.example.com interface=enp1s0 ip_v4=192.0.2.1/24 ip_v6=2001:db8:1::1/64 gateway_v4=192.0.2.254 gateway_v6=2001:db8:1::fffe

managed-node-02.example.com interface=enp1s0 ip_v4=192.0.2.2/24 ip_v6=2001:db8:1::2/64 gateway_v4=192.0.2.254 gateway_v6=2001:db8:1::fffe

- 2. Create a playbook file, for example ~/playbook.yml, with the following content:
 - name: Configure the network hosts: managed-node-01.example.com,managed-node-02.example.com
 - name: Ethernet connection profile with static IP address settings ansible.builtin.include_role:

name: redhat.rhel system roles.network

```
vars:
 network_connections:
  - name: "{{ interface }}"
   interface_name: "{{ interface }}"
   type: ethernet
   autoconnect: yes
   ip:
     address:
      - "{{ ip v4 }}"
      - "{{ ip_v6 }}"
     gateway4: "{{ gateway_v4 }}"
     gateway6: "{{ gateway_v6 }}"
     dns:
      - 192.0.2.200
      - 2001:db8:1::ffbb
     dns_search:
      - example.com
   state: up
```

This playbook reads certain values dynamically for each host from the inventory file and uses static values in the playbook for settings which are the same for all hosts.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Query the Ansible facts of the managed node and verify the active network settings:

ansible managed-node-01.example.com -m ansible.builtin.setup

```
"ansible_default_ipv4": {
    "address": "192.0.2.1",
    "alias": "enp1s0",
    "broadcast": "192.0.2.255",
    "gateway": "192.0.2.254",
    "interface": "enp1s0",
    "macaddress": "52:54:00:17:b8:b6",
    "mtu": 1500,
    "netmask": "255.255.255.0",
    "network": "192.0.2.0",
    "prefix": "24",
    "type": "ether"
},
```

```
"ansible_default_ipv6": {
   "address": "2001:db8:1::1",
  "gateway": "2001:db8:1::fffe",
  "interface": "enp1s0",
  "macaddress": "52:54:00:17:b8:b6",
  "mtu": 1500,
  "prefix": "64",
  "scope": "global",
  "type": "ether"
},
"ansible_dns": {
  "nameservers": [
     "192.0.2.1",
     "2001:db8:1::ffbb"
   "search": [
     "example.com"
},
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

18.2. CONFIGURING AN ETHERNET CONNECTION WITH A STATIC IP ADDRESS BY USING THE NETWORK RHEL SYSTEM ROLE WITH A DEVICE PATH

To connect a Red Hat Enterprise Linux host to an Ethernet network, create a NetworkManager connection profile for the network device. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use the **network** RHEL system role to configure an Ethernet connection with static IP addresses, gateways, and DNS settings, and assign them to a device based on its path instead of its name.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- A physical or virtual Ethernet device exists in the server's configuration.
- The managed nodes use NetworkManager to configure the network.
- You know the path of the device. You can display the device path by using the udevadm info
 /sys/class/net/<device_name> | grep ID_PATH= command.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure the network
 hosts: managed-node-01.example.com
 tasks:
  - name: Ethernet connection profile with static IP address settings
   ansible.builtin.include role:
    name: redhat.rhel_system_roles.network
   vars:
    network_connections:
      - name: example
       match:
        path:
         - pci-0000:00:0[1-3].0
         - '&!pci-0000:00:02.0'
       type: ethernet
       autoconnect: yes
       ip:
        address:
         - 192.0.2.1/24
         - 2001:db8:1::1/64
        gateway4: 192.0.2.254
        gateway6: 2001:db8:1::fffe
        dns:
         - 192.0.2.200
         - 2001:db8:1::ffbb
        dns search:
         - example.com
       state: up
```

The settings specified in the example playbook include the following:

match

Defines that a condition must be met in order to apply the settings. You can only use this variable with the **path** option.

path

Defines the persistent path of a device. You can set it as a fixed path or an expression. Its value can contain modifiers and wildcards. The example applies the settings to devices that match PCI ID **0000:00:0[1-3].0**, but not **0000:00:02.0**.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

$\$\ ansible-playbook\ --syntax-check\ \sim\!/playbook.yml$

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Query the Ansible facts of the managed node and verify the active network settings:

```
# ansible managed-node-01.example.com -m ansible.builtin.setup
     "ansible_default_ipv4": {
       "address": "192.0.2.1",
       "alias": "enp1s0",
       "broadcast": "192.0.2.255",
       "gateway": "192.0.2.254",
       "interface": "enp1s0",
       "macaddress": "52:54:00:17:b8:b6",
       "mtu": 1500,
       "netmask": "255.255.255.0",
       "network": "192.0.2.0",
       "prefix": "24",
       "type": "ether"
     "ansible_default_ipv6": {
       "address": "2001:db8:1::1",
       "gateway": "2001:db8:1::fffe",
       "interface": "enp1s0",
       "macaddress": "52:54:00:17:b8:b6",
       "mtu": 1500,
       "prefix": "64",
       "scope": "global",
       "type": "ether"
    },
     "ansible_dns": {
       "nameservers": [
          "192.0.2.1",
          "2001:db8:1::ffbb"
       ],
       "search": [
          "example.com"
    },
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

18.3. CONFIGURING AN ETHERNET CONNECTION WITH A DYNAMIC IP ADDRESS BY USING THE NETWORK RHEL SYSTEM ROLE WITH AN INTERFACE NAME

To connect a Red Hat Enterprise Linux host to an Ethernet network, create a NetworkManager connection profile for the network device. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use the **network** RHEL system role to configure an Ethernet connection that retrieves its IP addresses, gateways, and DNS settings from a DHCP server and IPv6 stateless address autoconfiguration (SLAAC). With this role you can assign the connection profile to the specified interface name.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- A physical or virtual Ethernet device exists in the servers' configuration.
- A DHCP server and SLAAC are available in the network.
- The managed nodes use the NetworkManager service to configure the network.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
-name: Configure the network
hosts: managed-node-01.example.com
tasks:
    - name: Ethernet connection profile with dynamic IP address settings
    ansible.builtin.include_role:
    name: redhat.rhel_system_roles.network
    vars:
    network_connections:
    - name: enp1s0
    interface_name: enp1s0
    type: ethernet
    autoconnect: yes
    ip:
        dhcp4: yes
        auto6: yes
    state: up
```

The settings specified in the example playbook include the following:

dhcp4: yes

Enables automatic IPv4 address assignment from DHCP, PPP, or similar services.

auto6: yes

Enables IPv6 auto-configuration. By default, NetworkManager uses Router Advertisements. If the router announces the **managed** flag, NetworkManager requests an IPv6 address and prefix from a DHCPv6 server.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhelsystem-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Query the Ansible facts of the managed node and verify that the interface received IP addresses and DNS settings:

```
# ansible managed-node-01.example.com -m ansible.builtin.setup
     "ansible default ipv4": {
       "address": "192.0.2.1",
       "alias": "enp1s0",
       "broadcast": "192.0.2.255",
       "gateway": "192.0.2.254",
       "interface": "enp1s0",
       "macaddress": "52:54:00:17:b8:b6",
       "mtu": 1500,
       "netmask": "255.255.255.0",
       "network": "192.0.2.0",
       "prefix": "24",
       "type": "ether"
     "ansible_default_ipv6": {
       "address": "2001:db8:1::1",
       "gateway": "2001:db8:1::fffe",
       "interface": "enp1s0",
       "macaddress": "52:54:00:17:b8:b6",
       "mtu": 1500,
       "prefix": "64",
       "scope": "global",
       "type": "ether"
    },
     "ansible dns": {
       "nameservers": [
          "192.0.2.1",
          "2001:db8:1::ffbb"
       ],
       "search": [
          "example.com"
    },
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

18.4. CONFIGURING AN ETHERNET CONNECTION WITH A DYNAMIC IP ADDRESS BY USING THE NETWORK RHEL SYSTEM ROLE WITH A DEVICE PATH

To connect a Red Hat Enterprise Linux host to an Ethernet network, create a NetworkManager connection profile for the network device. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use the **network** RHEL system role to configure an Ethernet connection that retrieves its IP addresses, gateways, and DNS settings from a DHCP server and IPv6 stateless address autoconfiguration (SLAAC). The role can assign the connection profile to a device based on its path instead of an interface name.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- A physical or virtual Ethernet device exists in the server's configuration.
- A DHCP server and SLAAC are available in the network.
- The managed hosts use NetworkManager to configure the network.
- You know the path of the device. You can display the device path by using the udevadm info
 /sys/class/net/<device_name> | grep ID_PATH= command.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: Configure the network
hosts: managed-node-01.example.com
tasks:
- name: Ethernet connection profile with dynamic IP address settings
ansible.builtin.include_role:
    name: redhat.rhel_system_roles.network
vars:
    network_connections:
- name: example
    match:
    path:
    - pci-0000:00:0[1-3].0
    - '&!pci-0000:00:02.0'
type: ethernet
```

```
autoconnect: yes ip:
   dhcp4: yes
   auto6: yes
   state: up
```

The settings specified in the example playbook include the following:

match: path

Defines that a condition must be met in order to apply the settings. You can only use this variable with the **path** option.

path: <path_and_expressions>

Defines the persistent path of a device. You can set it as a fixed path or an expression. Its value can contain modifiers and wildcards. The example applies the settings to devices that match PCI ID **0000:00:0[1-3].0**, but not **0000:00:02.0**.

dhcp4: yes

Enables automatic IPv4 address assignment from DHCP, PPP, or similar services.

auto6: yes

Enables IPv6 auto-configuration. By default, NetworkManager uses Router Advertisements. If the router announces the **managed** flag, NetworkManager requests an IPv6 address and prefix from a DHCPv6 server.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

$\$\ ansible-playbook\ --syntax-check\ \sim\!/playbook.yml$

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

 Query the Ansible facts of the managed node and verify that the interface received IP addresses and DNS settings:

ansible managed-node-01.example.com -m ansible.builtin.setup ... "ansible_default_ipv4": { "address": "192.0.2.1", "alias": "enp1s0", "broadcast": "192.0.2.255", "gateway": "192.0.2.254", "interface": "enp1s0", "macaddress": "52:54:00:17:b8:b6", "mtu": 1500, "netmask": "255.255.255.0", "network": "192.0.2.0",

```
"prefix": "24",
   "type": "ether"
},
"ansible default ipv6": {
  "address": "2001:db8:1::1",
  "gateway": "2001:db8:1::fffe",
  "interface": "enp1s0",
  "macaddress": "52:54:00:17:b8:b6",
  "mtu": 1500,
   "prefix": "64",
  "scope": "global",
   "type": "ether"
},
"ansible_dns": {
  "nameservers": [
     "192.0.2.1",
     "2001:db8:1::ffbb"
   "search": [
     "example.com"
},
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

18.5. CONFIGURING A STATIC ETHERNET CONNECTION WITH 802.1X NETWORK AUTHENTICATION BY USING THE NETWORK RHEL SYSTEM ROLE

Network Access Control (NAC) protects a network from unauthorized clients. You can specify the details that are required for the authentication in NetworkManager connection profiles to enable clients to access the network. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use an Ansible playbook to copy a private key, a certificate, and the CA certificate to the client, and then use the **network** RHEL system role to configure a connection profile with 802.1X network authentication.

Prerequisites

- You have prepared the control node and the managed nodes.
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The network supports 802.1X network authentication.

- The managed nodes use NetworkManager.
- The following files required for the TLS authentication exist on the control node:
 - The client key is stored in the /srv/data/client.key file.
 - The client certificate is stored in the /srv/data/client.crt file.
 - The Certificate Authority (CA) certificate is stored in the /srv/data/ca.crt file.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>

Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

pwd: <password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Configure an Ethernet connection with 802.1X authentication hosts: managed-node-01.example.com

vars_files:

- ~/vault.yml

tasks:

- name: Copy client key for 802.1X authentication

ansible.builtin.copy:

src: "/srv/data/client.key"

dest: "/etc/pki/tls/private/client.key"

mode: 0600

 name: Copy client certificate for 802.1X authentication ansible.builtin.copy:

src: "/srv/data/client.crt"

dest: "/etc/pki/tls/certs/client.crt"

- name: Copy CA certificate for 802.1X authentication ansible.builtin.copy:

src: "/srv/data/ca.crt"

dest: "/etc/pki/ca-trust/source/anchors/ca.crt"

 name: Ethernet connection profile with static IP address settings and 802.1X ansible.builtin.include role:

name: redhat.rhel_system_roles.network

vars:

network connections:

```
- name: enp1s0
 type: ethernet
 autoconnect: yes
 ip:
  address:
   - 192.0.2.1/24
   - 2001:db8:1::1/64
  gateway4: 192.0.2.254
  gateway6: 2001:db8:1::fffe
  dns:
   - 192.0.2.200
   - 2001:db8:1::ffbb
  dns_search:
   - example.com
 ieee802_1x:
  identity: <user_name>
  eap: tls
  private_key: "/etc/pki/tls/private/client.key"
  private key password: "{{ pwd }}"
  client cert: "/etc/pki/tls/certs/client.crt"
  ca cert: "/etc/pki/ca-trust/source/anchors/ca.crt"
  domain_suffix_match: example.com
 state: up
```

The settings specified in the example playbook include the following:

ieee802 1x

This variable contains the 802.1X-related settings.

eap: tls

Configures the profile to use the certificate-based **TLS** authentication method for the Extensible Authentication Protocol (EAP).

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Verification

• Access resources on the network that require network authentication.

Additional resources

• /usr/share/ansible/roles/rhel-system-roles.network/README.md file

- /usr/share/doc/rhel-system-roles/network/ directory
- Ansible vault

18.6. CONFIGURING A WIFI CONNECTION WITH 802.1X NETWORK AUTHENTICATION BY USING THE NETWORK RHEL SYSTEM ROLE

Network Access Control (NAC) protects a network from unauthorized clients. You can specify the details that are required for the authentication in NetworkManager connection profiles to enable clients to access the network. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use an Ansible playbook to copy a private key, a certificate, and the CA certificate to the client, and then use the **network** RHEL system role to configure a connection profile with 802.1X network authentication.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The network supports 802.1X network authentication.
- You installed the **wpa_supplicant** package on the managed node.
- DHCP is available in the network of the managed node.
- The following files required for TLS authentication exist on the control node:
 - The client key is stored in the /srv/data/client.key file.
 - The client certificate is stored in the /srv/data/client.crt file.
 - The CA certificate is stored in the /srv/data/ca.crt file.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml

New Vault password: <vault_password>

Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

pwd: <password>

c. Save the changes, and close the editor. Ansible encrypts the data in the vault.

2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure a wifi connection with 802.1X authentication
hosts: managed-node-01.example.com
tasks:
  - name: Copy client key for 802.1X authentication
   ansible.builtin.copy:
    src: "/srv/data/client.key"
    dest: "/etc/pki/tls/private/client.key"
    mode: 0400
  - name: Copy client certificate for 802.1X authentication
   ansible.builtin.copy:
    src: "/srv/data/client.crt"
    dest: "/etc/pki/tls/certs/client.crt"
  - name: Copy CA certificate for 802.1X authentication
   ansible.builtin.copy:
    src: "/srv/data/ca.crt"
    dest: "/etc/pki/ca-trust/source/anchors/ca.crt"
  - name: Wifi connection profile with dynamic IP address settings and 802.1X
   ansible.builtin.import role:
    name: redhat.rhel_system_roles.network
   vars:
    network_connections:
      - name: Wifi connection profile with dynamic IP address settings and 802.1X
       interface name: wlp1s0
       state: up
       type: wireless
       autoconnect: yes
        dhcp4: true
        auto6: true
       wireless:
        ssid: "Example-wifi"
        key_mgmt: "wpa-eap"
       ieee802_1x:
        identity: <user_name>
        eap: tls
        private key: "/etc/pki/tls/client.key"
        private key password: "{{ pwd }}"
        private_key_password_flags: none
        client cert: "/etc/pki/tls/client.pem"
        ca cert: "/etc/pki/tls/cacert.pem"
        domain_suffix_match: "example.com"
```

The settings specified in the example playbook include the following:

ieee802_1x

This variable contains the 802.1X-related settings.

eap: tls

Configures the profile to use the certificate-based **TLS** authentication method for the Extensible Authentication Protocol (EAP).

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory
- Ansible vault
- Ansible vault

18.7. CONFIGURING A NETWORK BOND BY USING THENETWORK RHEL SYSTEM ROLE

You can combine network interfaces in a bond to provide a logical interface with higher throughput or redundancy. To configure a bond, create a NetworkManager connection profile. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use the **network** RHEL system role to configure a network bond and, if a connection profile for the bond's parent device does not exist, the role can create it as well.

Prerequisites

- You have prepared the control node and the managed nodes.
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- Two or more physical or virtual network devices are installed on the server.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

--

- name: Configure the network

hosts: managed-node-01.example.com

tasks:

- name: Bond connection profile with two Ethernet ports

```
ansible.builtin.include_role:
 name: redhat.rhel_system_roles.network
vars:
 network_connections:
  # Bond profile
  - name: bond0
   type: bond
   interface_name: bond0
    dhcp4: yes
    auto6: yes
   bond:
    mode: active-backup
   state: up
  # Port profile for the 1st Ethernet device
  - name: bond0-port1
   interface_name: enp7s0
   type: ethernet
   controller: bond0
   state: up
  # Port profile for the 2nd Ethernet device
  - name: bond0-port2
   interface_name: enp8s0
   type: ethernet
   controller: bond0
   state: up
```

The settings specified in the example playbook include the following:

type: type>

Sets the type of the profile to create. The example playbook creates three connection profiles: One for the bond and two for the Ethernet devices.

dhcp4: yes

Enables automatic IPv4 address assignment from DHCP, PPP, or similar services.

auto6: yes

Enables IPv6 auto-configuration. By default, NetworkManager uses Router Advertisements. If the router announces the **managed** flag, NetworkManager requests an IPv6 address and prefix from a DHCPv6 server.

mode: <bond_mode>

Sets the bonding mode. Possible values are:

- balance-rr (default)
- active-backup
- balance-xor
- broadcast
- 802.3ad
- balance-tlb

balance-alb.

Depending on the mode you set, you need to set additional variables in the playbook.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Temporarily remove the network cable from one of the network devices and check if the other device in the bond is handling the traffic.

Note that there is no method to properly test link failure events using software utilities. Tools that deactivate connections, such as **nmcli**, show only the bonding driver's ability to handle port configuration changes and not actual link failure events.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

18.8. CONFIGURING VLAN TAGGING BY USING THE NETWORK RHEL SYSTEM ROLE

If your network uses Virtual Local Area Networks (VLANs) to separate network traffic into logical networks, create a NetworkManager connection profile to configure VLAN tagging. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use the **network** RHEL system role to configure VLAN tagging and, if a connection profile for the VLAN's parent device does not exist, the role can create it as well.



NOTE

If the VLAN device requires an IP address, default gateway, and DNS settings, configure them on the VLAN device and not on the parent device.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.

• The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure the network
hosts: managed-node-01.example.com
  - name: VLAN connection profile with Ethernet port
   ansible.builtin.include_role:
    name: redhat.rhel_system_roles.network
   vars:
    network_connections:
     # Ethernet profile
     - name: enp1s0
       type: ethernet
       interface name: enp1s0
       autoconnect: yes
       state: up
       ip:
        dhcp4: no
        auto6: no
     # VLAN profile
     - name: enp1s0.10
       type: vlan
       vlan:
        id: 10
       ip:
        dhcp4: yes
        auto6: yes
       parent: enp1s0
       state: up
```

The settings specified in the example playbook include the following:

type: type>

Sets the type of the profile to create. The example playbook creates two connection profiles: One for the parent Ethernet device and one for the VLAN device.

dhcp4: <value>

If set to **yes**, automatic IPv4 address assignment from DHCP, PPP, or similar services is enabled. Disable the IP address configuration on the parent device.

auto6: <value>

If set to **yes**, IPv6 auto-configuration is enabled. In this case, by default, NetworkManager uses Router Advertisements and, if the router announces the **managed** flag, NetworkManager requests an IPv6 address and prefix from a DHCPv6 server. Disable the IP address configuration on the parent device.

parent: parent_device>

Sets the parent device of the VLAN connection profile. In the example, the parent is the Ethernet interface.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

Verify the VLAN settings:

ansible managed-node-01.example.com -m command -a 'ip -d addr show enp1s0.10' managed-node-01.example.com | CHANGED | rc=0 >> 4: vlan10@enp1s0.10: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc noqueue state UP group default qlen 1000 link/ether 52:54:00:72:2f:6e brd ff:ff:ff:ff:ff:ff promiscuity 0 vlan protocol 802.1Q id 10 <REORDER_HDR> numtxqueues 1 numrxqueues 1 gso_max_size 65536 gso_max_segs 65535 ...

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

18.9. CONFIGURING A NETWORK BRIDGE BY USING THENETWORK RHEL SYSTEM ROLE

You can connect multiple networks on layer 2 of the Open Systems Interconnection (OSI) model by creating a network bridge. To configure a bridge, create a connection profile in NetworkManager. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use the **network** RHEL system role to configure a bridge and, if a connection profile for the bridge's parent device does not exist, the role can create it as well.



NOTE

If you want to assign IP addresses, gateways, and DNS settings to a bridge, configure them on the bridge and not on its ports.

Prerequisites

• You have prepared the control node and the managed nodes .

- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- Two or more physical or virtual network devices are installed on the server.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure the network
hosts: managed-node-01.example.com
 tasks:
  - name: Bridge connection profile with two Ethernet ports
   ansible.builtin.include role:
    name: redhat.rhel_system_roles.network
   vars:
    network_connections:
      # Bridge profile
      - name: bridge0
       type: bridge
       interface name: bridge0
       ip:
        dhcp4: yes
        auto6: yes
       state: up
      # Port profile for the 1st Ethernet device
      - name: bridge0-port1
       interface_name: enp7s0
       type: ethernet
       controller: bridge0
       port_type: bridge
       state: up
      # Port profile for the 2nd Ethernet device
      - name: bridge0-port2
       interface_name: enp8s0
       type: ethernet
       controller: bridge0
       port_type: bridge
       state: up
```

The settings specified in the example playbook include the following:

type:

Sets the type of the profile to create. The example playbook creates three connection profiles: One for the bridge and two for the Ethernet devices.

dhcp4: yes

Enables automatic IPv4 address assignment from DHCP, PPP, or similar services.

auto6: yes

Enables IPv6 auto-configuration. By default, NetworkManager uses Router Advertisements. If the router announces the **managed** flag, NetworkManager requests an IPv6 address and prefix from a DHCPv6 server.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. Display the link status of Ethernet devices that are ports of a specific bridge:

ansible managed-node-01.example.com -m command -a 'ip link show master bridge0'

managed-node-01.example.com | CHANGED | rc=0 >>

3: enp7s0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel master bridge0 state UP mode DEFAULT group default qlen 1000

link/ether 52:54:00:62:61:0e brd ff:ff:ff:ff:ff

4: enp8s0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel master bridge0 state UP mode DEFAULT group default qlen 1000

link/ether 52:54:00:9e:f1:ce brd ff:ff:ff:ff:ff

2. Display the status of Ethernet devices that are ports of any bridge device:

ansible managed-node-01.example.com -m command -a 'bridge link show'

managed-node-01.example.com | CHANGED | rc=0 >>

3: enp7s0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 master bridge0 state forwarding priority 32 cost 100

4: enp8s0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 master bridge0 state listening priority 32 cost 100

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

18.10. SETTING THE DEFAULT GATEWAY ON AN EXISTING CONNECTION BY USING THE NETWORK RHEL SYSTEM ROLE

A host forwards a network packet to its default gateway if the packet's destination can neither be reached through the directly-connected networks nor through any of the routes configured on the host. To configure the default gateway of a host, set it in the NetworkManager connection profile of the

interface that is connected to the same network as the default gateway. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

In most situations, administrators set the default gateway when they create a connection. However, you can also set or update the default gateway setting on a previously-created connection.



WARNING

You cannot use the **network** RHEL system role to update only specific values in an existing connection profile. The role ensures that a connection profile exactly matches the settings in a playbook. If a connection profile with the same name already exists, the role applies the settings from the playbook and resets all other settings in the profile to their defaults. To prevent resetting values, always specify the whole configuration of the network connection profile in the playbook, including the settings that you do not want to change.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has sudo permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure the network
hosts: managed-node-01.example.com
  - name: Ethernet connection profile with static IP address settings
   ansible.builtin.include role:
    name: redhat.rhel_system_roles.network
   vars:
    network_connections:
     - name: enp1s0
       type: ethernet
       autoconnect: yes
       ip:
        address:
         - 198.51.100.20/24
         - 2001:db8:1::1/64
        gateway4: 198.51.100.254
        gateway6: 2001:db8:1::fffe
         - 198.51.100.200
```

- 2001:db8:1::ffbb

```
dns_search:
    - example.com
state: up
```

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

```
$ ansible-playbook --syntax-check ~/playbook.yml
```

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Query the Ansible facts of the managed node and verify the active network settings:

```
# ansible managed-node-01.example.com -m ansible.builtin.setup
...
    "ansible_default_ipv4": {
    ...
        "gateway": "198.51.100.254",
        "interface": "enp1s0",
    ...
     },
     "ansible_default_ipv6": {
    ...
        "gateway": "2001:db8:1::fffe",
        "interface": "enp1s0",
    ...
}
...
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

18.11. CONFIGURING A STATIC ROUTE BY USING THENETWORK RHEL SYSTEM ROLE

A static route ensures that you can send traffic to a destination that cannot be reached through the default gateway. You configure static routes in the NetworkManager connection profile of the interface that is connected to the same network as the next hop. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.



WARNING

You cannot use the **network** RHEL system role to update only specific values in an existing connection profile. The role ensures that a connection profile exactly matches the settings in a playbook. If a connection profile with the same name already exists, the role applies the settings from the playbook and resets all other settings in the profile to their defaults. To prevent resetting values, always specify the whole configuration of the network connection profile in the playbook, including the settings that you do not want to change.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure the network
 hosts: managed-node-01.example.com
 tasks:
  - name: Ethernet connection profile with static IP address settings
   ansible.builtin.include_role:
    name: redhat.rhel_system_roles.network
   vars:
    network_connections:
     - name: enp7s0
       type: ethernet
       autoconnect: yes
       ip:
        address:
         - 192.0.2.1/24
         - 2001:db8:1::1/64
        gateway4: 192.0.2.254
        gateway6: 2001:db8:1::fffe
        dns:
         - 192.0.2.200
         - 2001:db8:1::ffbb
        dns_search:
         - example.com
        route:
         - network: 198.51.100.0
           prefix: 24
           gateway: 192.0.2.10
         - network: '2001:db8:2::'
```

prefix: 64

gateway: 2001:db8:1::10

state: up

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. Display the IPv4 routes:

ansible managed-node-01.example.com -m command -a 'ip -4 route' managed-node-01.example.com | CHANGED | rc=0 >> ...
198.51.100.0/24 via 192.0.2.10 dev enp7s0

2. Display the IPv6 routes:

ansible managed-node-01.example.com -m command -a 'ip -6 route' managed-node-01.example.com | CHANGED | rc=0 >> ...
2001:db8:2::/64 via 2001:db8:1::10 dev enp7s0 metric 1024 pref medium

Additional resources


- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

18.12. ROUTING TRAFFIC FROM A SPECIFIC SUBNET TO A DIFFERENT DEFAULT GATEWAY BY USING THE NETWORK RHEL SYSTEM ROLE

You can use policy-based routing to configure a different default gateway for traffic from certain subnets. For example, you can configure RHEL as a router that, by default, routes all traffic to internet provider A using the default route. However, traffic received from the internal workstations subnet is routed to provider B. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use the **network** RHEL system role to configure the connection profiles, including routing tables and rules.

This procedure assumes the following network topology:



60 RHEL 0120

Prerequisites

- You have prepared the control node and the managed nodes.
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The managed nodes use NetworkManager and the firewalld service.
- The managed nodes you want to configure has four network interfaces:
 - The **enp7s0** interface is connected to the network of provider A. The gateway IP in the provider's network is **198.51.100.2**, and the network uses a /**30** network mask.
 - The **enp1s0** interface is connected to the network of provider B. The gateway IP in the provider's network is **192.0.2.2**, and the network uses a /**30** network mask.
 - The **enp8s0** interface is connected to the **10.0.0.0/24** subnet with internal workstations.
 - The **enp9s0** interface is connected to the **203.0.113.0/24** subnet with the company's servers.
- Hosts in the internal workstations subnet use 10.0.0.1 as the default gateway. In the procedure, you assign this IP address to the enp8s0 network interface of the router.
- Hosts in the server subnet use 203.0.113.1 as the default gateway. In the procedure, you assign
 this IP address to the enp9s0 network interface of the router.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- ---
- name: Configuring policy-based routing hosts: managed-node-01.example.com tasks:
 - name: Routing traffic from a specific subnet to a different default gateway

```
ansible.builtin.include_role:
 name: redhat.rhel_system_roles.network
vars:
 network connections:
  - name: Provider-A
   interface_name: enp7s0
   type: ethernet
   autoconnect: True
   ip:
    address:
      - 198.51.100.1/30
    gateway4: 198.51.100.2
    dns:
      - 198.51.100.200
   state: up
   zone: external
  - name: Provider-B
   interface name: enp1s0
   type: ethernet
   autoconnect: True
   ip:
    address:
      - 192.0.2.1/30
    route:
      - network: 0.0.0.0
       prefix: 0
       gateway: 192.0.2.2
       table: 5000
   state: up
   zone: external
  - name: Internal-Workstations
   interface name: enp8s0
   type: ethernet
   autoconnect: True
   ip:
    address:
      - 10.0.0.1/24
    route:
      - network: 10.0.0.0
       prefix: 24
       table: 5000
    routing_rule:
      - priority: 5
       from: 10.0.0.0/24
       table: 5000
   state: up
   zone: trusted
  - name: Servers
   interface_name: enp9s0
   type: ethernet
   autoconnect: True
    address:
```

- 203.0.113.1/24

state: up zone: trusted

The settings specified in the example playbook include the following:

table: <value>

Assigns the route from the same list entry as the table variable to the specified routing table.

routing rule: < list>

Defines the priority of the specified routing rule and from a connection profile to which routing table the rule is assigned.

zone: <zone_name>

Assigns the network interface from a connection profile to the specified **firewalld** zone.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

- 1. On a RHEL host in the internal workstation subnet:
 - a. Install the traceroute package:

dnf install traceroute

b. Use the **traceroute** utility to display the route to a host on the internet:

traceroute redhat.com

traceroute to redhat.com (209.132.183.105), 30 hops max, 60 byte packets 1 10.0.0.1 (10.0.0.1) 0.337 ms 0.260 ms 0.223 ms 2 192.0.2.2 (192.0.2.2) 0.884 ms 1.066 ms 1.248 ms ...

The output of the command displays that the router sends packets over **192.0.2.1**, which is the network of provider B.

- 2. On a RHEL host in the server subnet:
 - a. Install the traceroute package:

dnf install traceroute

b. Use the **traceroute** utility to display the route to a host on the internet:

```
# traceroute redhat.com
```

traceroute to redhat.com (209.132.183.105), 30 hops max, 60 byte packets 1 203.0.113.1 (203.0.113.1) 2.179 ms 2.073 ms 1.944 ms 2 198.51.100.2 (198.51.100.2) 1.868 ms 1.798 ms 1.549 ms ...

The output of the command displays that the router sends packets over **198.51.100.2**, which is the network of provider A.

- 3. On the RHEL router that you configured using the RHEL system role:
 - a. Display the rule list:

ip rule list

0: from all lookup local

5: from 10.0.0.0/24 lookup 5000

32766: from all lookup main 32767: from all lookup default

By default, RHEL contains rules for the tables local, main, and default.

b. Display the routes in table **5000**:

ip route list table 5000

0.0.0.0/0 via 192.0.2.2 dev enp1s0 proto static metric 100 10.0.0.0/24 dev enp8s0 proto static scope link src 192.0.2.1 metric 102

c. Display the interfaces and firewall zones:

firewall-cmd --get-active-zones

external

interfaces: enp1s0 enp7s0

trusted

interfaces: enp8s0 enp9s0

d. Verify that the **external** zone has masquerading enabled:

firewall-cmd --info-zone=external

external (active)

target: default

icmp-block-inversion: no interfaces: enp1s0 enp7s0

sources: services: ssh ports: protocols:

masquerade: yes

...

Additional resources

/usr/share/ansible/roles/rhel-system-roles.network/README.md file

/usr/share/doc/rhel-system-roles/network/ directory

18.13. CONFIGURING AN ETHTOOL OFFLOAD FEATURE BY USING THE NETWORK RHEL SYSTEM ROLE

Network interface controllers can use the TCP offload engine (TOE) to offload processing certain operations to the network controller. This improves the network throughput. You configure offload features in the connection profile of the network interface. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.



WARNING

You cannot use the **network** RHEL system role to update only specific values in an existing connection profile. The role ensures that a connection profile exactly matches the settings in a playbook. If a connection profile with the same name already exists, the role applies the settings from the playbook and resets all other settings in the profile to their defaults. To prevent resetting values, always specify the whole configuration of the network connection profile in the playbook, including the settings that you do not want to change.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
-name: Configure the network
hosts: managed-node-01.example.com
tasks:
-name: Ethernet connection profile with dynamic IP address settings and offload features
ansible.builtin.include_role:
name: redhat.rhel_system_roles.network
vars:
network_connections:
-name: enp1s0
type: ethernet
autoconnect: yes
ip:
dhcp4: yes
auto6: yes
ethtool:
```

features:

```
gro: no
gso: yes
tx_sctp_segmentation: no
state: up
```

The settings specified in the example playbook include the following:

gro: no

Disables Generic receive offload (GRO).

gso: yes

Enables Generic segmentation offload (GSO).

tx_sctp_segmentation: no

Disables TX stream control transmission protocol (SCTP) segmentation.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Query the Ansible facts of the managed node and verify the offload settings:

```
# ansible managed-node-01.example.com -m ansible.builtin.setup
...
    "ansible_enp1s0": {
        "active": true,
        "device": "enp1s0",
        "features": {
            ...
        "rx_gro_hw": "off,
            ...
        "tx_gso_list": "on,
            ...
        "tx_sctp_segmentation": "off",
            ...
        }
        ...
}
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

18.14. CONFIGURING AN ETHTOOL COALESCE SETTINGS BY USING THE NETWORK RHEL SYSTEM ROLE

By using interrupt coalescing, the system collects network packets and generates a single interrupt for multiple packets. This increases the amount of data sent to the kernel with one hardware interrupt, which reduces the interrupt load, and maximizes the throughput. You configure coalesce settings in the connection profile of the network interface. By using Ansible and the **network** RHEL role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.



WARNING

You cannot use the **network** RHEL system role to update only specific values in an existing connection profile. The role ensures that a connection profile exactly matches the settings in a playbook. If a connection profile with the same name already exists, the role applies the settings from the playbook and resets all other settings in the profile to their defaults. To prevent resetting values, always specify the whole configuration of the network connection profile in the playbook, including the settings that you do not want to change.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure the network
 hosts: managed-node-01.example.com
  - name: Ethernet connection profile with dynamic IP address settings and coalesce
settings
   ansible.builtin.include_role:
    name: redhat.rhel system roles.network
   vars:
    network_connections:
     - name: enp1s0
       type: ethernet
       autoconnect: yes
       ip:
        dhcp4: yes
        auto6: yes
       ethtool:
        coalesce:
```

rx_frames: 128 tx_frames: 128

state: up

The settings specified in the example playbook include the following:

rx frames: <value>

Sets the number of RX frames.

gso: <value>

Sets the number of TX frames.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Display the current offload features of the network device:

ansible managed-node-01.example.com -m command -a 'ethtool -c enp1s0'
managed-node-01.example.com | CHANGED | rc=0 >>
...
rx-frames: 128
...
tx-frames: 128
...

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

18.15. INCREASING THE RING BUFFER SIZE TO REDUCE A HIGH PACKET DROP RATE BY USING THE NETWORK RHEL SYSTEM ROLE

Increase the size of an Ethernet device's ring buffers if the packet drop rate causes applications to report a loss of data, timeouts, or other issues.

Ring buffers are circular buffers where an overflow overwrites existing data. The network card assigns a transmit (TX) and receive (RX) ring buffer. Receive ring buffers are shared between the device driver and the network interface controller (NIC). Data can move from NIC to the kernel through either hardware interrupts or software interrupts, also called SoftIRQs.

The kernel uses the RX ring buffer to store incoming packets until the device driver can process them. The device driver drains the RX ring, typically by using SoftlRQs, which puts the incoming packets into a kernel data structure called an **sk_buff** or **skb** to begin its journey through the kernel and up to the application that owns the relevant socket.

The kernel uses the TX ring buffer to hold outgoing packets which should be sent to the network. These ring buffers reside at the bottom of the stack and are a crucial point at which packet drop can occur, which in turn will adversely affect network performance.

You configure ring buffer settings in the NetworkManager connection profiles. By using Ansible and the **network** RHEL system role, you can automate this process and remotely configure connection profiles on the hosts defined in a playbook.



WARNING

You cannot use the **network** RHEL system role to update only specific values in an existing connection profile. The role ensures that a connection profile exactly matches the settings in a playbook. If a connection profile with the same name already exists, the role applies the settings from the playbook and resets all other settings in the profile to their defaults. To prevent resetting values, always specify the whole configuration of the network connection profile in the playbook, including the settings that you do not want to change.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You know the maximum ring buffer sizes that the device supports.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
name: Configure the network
hosts: managed-node-01.example.com
tasks:

name: Ethernet connection profile with dynamic IP address setting and increased ring

buffer sizes
ansible.builtin.include_role:
name: redhat.rhel_system_roles.network
vars:
network_connections:
- name: enp1s0
type: ethernet
autoconnect: yes
```

ip:

```
dhcp4: yes
auto6: yes
ethtool:
ring:
rx: 4096
tx: 4096
state: up
```

The settings specified in the example playbook include the following:

rx: <value>

Sets the maximum number of received ring buffer entries.

tx: <value>

Sets the maximum number of transmitted ring buffer entries.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Display the maximum ring buffer sizes:

```
# ansible managed-node-01.example.com -m command -a 'ethtool -g enp1s0'
managed-node-01.example.com | CHANGED | rc=0 >>
...
Current hardware settings:
RX: 4096
RX Mini: 0
RX Jumbo: 0
TX: 4096
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

18.16. CONFIGURING AN IPOIB CONNECTION BY USING THENETWORK RHEL SYSTEM ROLE

You can use IP over InfiniBand (IPoIB) to send IP packets over an InfiniBand interface. To configure IPoIB, create a NetworkManager connection profile. By using Ansible and the **network** system role, you

can automate this process and remotely configure connection profiles on the hosts defined in a playbook.

You can use the **network** RHEL system role to configure IPoIB and, if a connection profile for the InfiniBand's parent device does not exist, the role can create it as well.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- An InfiniBand device named **mlx4_ib0** is installed in the managed nodes.
- The managed nodes use NetworkManager to configure the network.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure the network
 hosts: managed-node-01.example.com
 tasks:
  - name: IPoIB connection profile with static IP address settings
   ansible.builtin.include_role:
    name: redhat.rhel_system_roles.network
    network_connections:
     # InfiniBand connection mlx4 ib0
     - name: mlx4 ib0
       interface_name: mlx4_ib0
       type: infiniband
     # IPoIB device mlx4 ib0.8002 on top of mlx4 ib0
     - name: mlx4_ib0.8002
       type: infiniband
       autoconnect: yes
       infiniband:
        p_key: 0x8002
        transport_mode: datagram
       parent: mlx4_ib0
        address:
         - 192.0.2.1/24
         - 2001:db8:1::1/64
       state: up
```

The settings specified in the example playbook include the following:

type: type>

Sets the type of the profile to create. The example playbook creates two connection profiles: One for the InfiniBand connection and one for the IPoIB device.

parent: parent device>

Sets the parent device of the IPoIB connection profile.

p_key: <value>

Sets the InfiniBand partition key. If you set this variable, do not set **interface_name** on the IPoIB device.

transport_mode: <mode>

Sets the IPoIB connection operation mode. You can set this variable to **datagram** (default) or **connected**.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.network/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. Display the IP settings of the **mlx4 ib0.8002** device:

```
# ansible managed-node-01.example.com -m command -a 'ip address show mlx4_ib0.8002'
managed-node-01.example.com | CHANGED | rc=0 >>
...
inet 192.0.2.1/24 brd 192.0.2.255 scope global noprefixroute ib0.8002
valid_lft forever preferred_lft forever
inet6 2001:db8:1::1/64 scope link tentative noprefixroute
valid_lft forever preferred_lft forever
```

2. Display the partition key (P_Key) of the **mlx4_ib0.8002** device:

```
# ansible managed-node-01.example.com -m command -a 'cat /sys/class/net/mlx4_ib0.8002/pkey' managed-node-01.example.com | CHANGED | rc=0 >> 0x8002
```

3. Display the mode of the **mlx4_ib0.8002** device:

```
# ansible managed-node-01.example.com -m command -a 'cat /sys/class/net/mlx4_ib0.8002/mode'
managed-node-01.example.com | CHANGED | rc=0 >> datagram
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

18.17. NETWORK STATES FOR THE NETWORK RHEL SYSTEM ROLE

The **network** RHEL system role supports state configurations in playbooks to configure the devices. For this, use the **network_state** variable followed by the state configurations.

Benefits of using the **network_state** variable in a playbook:

- Using the declarative method with the state configurations, you can configure interfaces, and the NetworkManager creates a profile for these interfaces in the background.
- With the network_state variable, you can specify the options that you require to change, and all
 the other options will remain the same as they are. However, with the network_connections
 variable, you must specify all settings to change the network connection profile.



IMPORTANT

You can set only Nmstate YAML instructions in **network_state**. These instructions differ from the variables you can set in **network_connections**.

For example, to create an Ethernet connection with dynamic IP address settings, use the following **vars** block in your playbook:

| Playbook with state configurations | Regular playbook |
|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------|
| vars: network_state: interfaces: - name: enp7s0 type: ethernet state: up ipv4: enabled: true auto-dns: true auto-gateway: true auto-routes: true dhcp: true ipv6: enabled: true auto-dns: true auto-dns: true auto-dns: true auto-dns: true auto-fateway: true auto-gateway: true auto-routes: true auto-routes: true auto-routes: true auto-routes: true | vars: network_connections: - name: enp7s0 interface_name: enp7s0 type: ethernet autoconnect: yes ip: dhcp4: yes auto6: yes state: up |

For example, to only change the connection status of dynamic IP address settings that you created as above, use the following **vars** block in your playbook:

| Playbook with state configurations | Regular playbook |
|----------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------|
| vars: network_state: interfaces: - name: enp7s0 type: ethernet state: down | vars: network_connections: - name: enp7s0 interface_name: enp7s0 type: ethernet autoconnect: yes ip: dhcp4: yes auto6: yes state: down |

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.network/README.md file
- /usr/share/doc/rhel-system-roles/network/ directory

CHAPTER 19. MANAGING CONTAINERS BY USING RHEL SYSTEM ROLES

With the **podman** RHEL system role, you can manage Podman configuration, containers, and **systemd** services that run Podman containers.

19.1. CREATING A ROOTLESS CONTAINER WITH BIND MOUNT BY USING THE PODMAN RHEL SYSTEM ROLE

You can use the **podman** RHEL system role to create rootless containers with bind mount by running an Ansible playbook and with that, manage your application configuration.

The example Ansible playbook starts two Kubernetes pods: one for a database and another for a web application. The database pod configuration is specified in the playbook, while the web application pod is defined in an external YAML file.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The user and group webapp exist, and must be listed in the /etc/subuid and /etc/subgid files on the host.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configure Podman
hosts: managed-node-01.example.com
tasks:
  - name: Create a web application and a database
   ansible.builtin.include role:
    name: redhat.rhel_system_roles.podman
    podman create host directories: true
    podman firewall:
     - port: 8080-8081/tcp
      state: enabled
     - port: 12340/tcp
      state: enabled
    podman_selinux_ports:
     - ports: 8080-8081
      setype: http port t
    podman kube specs:
     - state: started
      run as user: dbuser
      run as group: dbgroup
      kube file content:
        apiVersion: v1
        kind: Pod
```

```
metadata:
   name: db
  spec:
   containers:
    - name: db
      image: quay.io/linux-system-roles/mysql:5.6
      ports:
       - containerPort: 1234
        hostPort: 12340
      volumeMounts:
       - mountPath: /var/lib/db:Z
        name: db
   volumes:
    - name: db
      hostPath:
       path: /var/lib/db
- state: started
 run_as_user: webapp
 run_as_group: webapp
 kube file src:/path/to/webapp.yml
```

The settings specified in the example playbook include the following:

run_as_user and run_as_group

Specify that containers are rootless.

kube_file_content

Contains a Kubernetes YAML file defining the first container named **db**. You can generate the Kubernetes YAML file by using the **podman kube generate** command.

- The **db** container is based on the **quay.io/db/db:stable** container image.
- The **db** bind mount maps the /**var/lib/db** directory on the host to the /**var/lib/db** directory in the container. The **Z** flag labels the content with a private unshared label, therefore, only the **db** container can access the content.

kube file src: <path>

Defines the second container. The content of the /path/to/webapp.yml file on the controller node will be copied to the **kube** file field on the managed node.

volumes: < list>

A YAML list to define the source of the data to provide in one or more containers. For example, a local disk on the host (**hostPath**) or other disk device.

volumeMounts: < list>

A YAML list to define the destination where the individual container will mount a given volume.

podman_create_host_directories: true

Creates the directory on the host. This instructs the role to check the kube specification for **hostPath** volumes and create those directories on the host. If you need more control over the ownership and permissions, use **podman_host_directories**.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.podman/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.podman/README.md file
- /usr/share/doc/rhel-system-roles/podman/ directory

19.2. CREATING A ROOTFUL CONTAINER WITH PODMAN VOLUME BY USING THE PODMAN RHEL SYSTEM ROLE

You can use the **podman** RHEL system role to create a rootful container with a Podman volume by running an Ansible playbook and with that, manage your application configuration.

The example Ansible playbook deploys a Kubernetes pod named **ubi8-httpd** running an HTTP server container from the **registry.access.redhat.com/ubi8/httpd-24** image. The container's web content is mounted from a persistent volume named **ubi8-html-volume**. By default, the **podman** role creates rootful containers.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
name: Configure Podman
hosts: managed-node-01.example.com
tasks:

name: Start Apache server on port 8080
ansible.builtin.include_role:
name: redhat.rhel_system_roles.podman
vars:
podman_firewall:

port: 8080/tcp
state: enabled
podman_kube_specs:

state: started
kube_file_content:
apiVersion: v1
kind: Pod
metadata:
```

name: ubi8-httpd

spec:

containers:

- name: ubi8-httpd

image: registry.access.redhat.com/ubi8/httpd-24

ports:

- containerPort: 8080 hostPort: 8080 volumeMounts:

- mountPath: /var/www/html:Z

name: ubi8-html

volumes:

- name: ubi8-html

persistentVolumeClaim:

claimName: ubi8-html-volume

The settings specified in the example playbook include the following:

kube_file_content

Contains a Kubernetes YAML file defining the first container named **db**. You can generate the Kubernetes YAML file by using the **podman kube generate** command.

- The **ubi8-httpd** container is based on the **registry.access.redhat.com/ubi8/httpd-24** container image.
- The ubi8-html-volume maps the /var/www/html directory on the host to the container.
 The Z flag labels the content with a private unshared label, therefore, only the ubi8-httpd container can access the content.
- The pod mounts the existing persistent volume named **ubi8-html-volume** with the mount path /var/www/html.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.podman/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.podman/README.md file
- /usr/share/doc/rhel-system-roles/podman/ directory

19.3. CREATING A QUADLET APPLICATION WITH SECRETS BY USING THE PODMAN RHEL SYSTEM ROLE

You can use the **podman** RHEL system role to create a Quadlet application with secrets by running an Ansible playbook.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The certificate and the corresponding private key that the web server in the container should use are stored in the **~/certificate.pem** and **~/key.pem** files.

Procedure

1. Display the contents of the certificate and private key files:

```
$ cat ~/certificate.pem
----BEGIN CERTIFICATE----
...
----END CERTIFICATE----
$ cat ~/key.pem
----BEGIN PRIVATE KEY----
...
----END PRIVATE KEY----
```

You require this information in a later step.

- 2. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

```
$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>
```

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

```
root_password: <root_password>
certificate: |-
----BEGIN CERTIFICATE-----
...
----END CERTIFICATE-----
key: |-
----BEGIN PRIVATE KEY-----
...
-----END PRIVATE KEY-----
```

Ensure that all lines in the **certificate** and **key** variables start with two spaces.

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 3. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Deploy a wordpress CMS with MySQL database
hosts: managed-node-01.example.com
vars files:
  - ~/vault.yml
tasks:
 - name: Create and run the container
  ansible.builtin.include_role:
   name: redhat.rhel system roles.podman
  vars:
   podman_create_host_directories: true
   podman activate systemd unit: false
   podman_quadlet_specs:
    - name: quadlet-demo
     type: network
     file_content: |
       [Network]
       Subnet=192.168.30.0/24
       Gateway=192.168.30.1
       Label=app=wordpress
    - file_src: quadlet-demo-mysql.volume
    - template_src: quadlet-demo-mysql.container.j2
    - file_src: envoy-proxy-configmap.yml
    file_src: quadlet-demo.yml
    - file src: quadlet-demo.kube
     activate_systemd_unit: true
   podman_firewall:
    - port: 8000/tcp
     state: enabled
    - port: 9000/tcp
     state: enabled
   podman_secrets:
    - name: mysql-root-password-container
     state: present
     skip_existing: true
     data: "{{ root_password }}"
    - name: mysql-root-password-kube
     state: present
     skip existing: true
     data: |
       apiVersion: v1
        password: "{{ root_password | b64encode }}"
       kind: Secret
       metadata:
        name: mysql-root-password-kube
    - name: envoy-certificates
     state: present
     skip_existing: true
     data: |
       apiVersion: v1
       data:
        certificate.key: {{ key | b64encode }}
```

certificate.pem: {{ certificate | b64encode }}

kind: Secret metadata:

name: envoy-certificates

The procedure creates a WordPress content management system paired with a MySQL database. The **podman_quadlet_specs role** variable defines a set of configurations for the Quadlet, which refers to a group of containers or services that work together in a certain way. It includes the following specifications:

- The Wordpress network is defined by the **quadlet-demo** network unit.
- The volume configuration for MySQL container is defined by the file_src: quadlet-demo-mysql.volume field.
- The **template_src: quadlet-demo-mysql.container.j2** field is used to generate a configuration for the MySQL container.
- Two YAML files follow: **file_src: envoy-proxy-configmap.yml** and **file_src: quadlet-demo.yml**. Note that .yml is not a valid Quadlet unit type, therefore these files will just be copied and not processed as a Quadlet specification.
- The Wordpress and envoy proxy containers and configuration are defined by the **file_src: quadlet-demo.kube** field. The kube unit refers to the previous YAML files in the **[Kube]** section as **Yaml=quadlet-demo.yml** and **ConfigMap=envoy-proxy-configmap.yml**.
- 4. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

5. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.podman/README.md file
- /usr/share/doc/rhel-system-roles/podman/ directory

CHAPTER 20. CONFIGURING POSTFIX MTA BY USING RHEL SYSTEM ROLES

You can use the **postfix** RHEL system role to consistently manage configurations of the Postfix mail transfer agent (MTA) in an automated fashion. Deploying such configurations are helpful when you need for example:

- Stable mail server: enables system administrators to configure a fast and scalable server for sending and receiving emails.
- Secure communication: supports features such as TLS encryption, authentication, domain blacklisting, and more, to ensure safe email transmission.
- Improved email management and routing: implements filters and rules so that you have control over your email traffic.



IMPORTANT

The **postfix_conf** dictionary holds key-value pairs of the supported Postfix configuration parameters. Those keys that Postfix does not recognize as supported are ignored. The **postfix** RHEL system role directly passes the key-value pairs that you provide to the **postfix_conf** dictionary without verifying their syntax or limiting them. Therefore, the role is especially useful to those familiar with Postfix, and who know how to configure it.

20.1. CONFIGURING POSTFIX AS A NULL CLIENT FOR ONLY SENDING OUTGOING EMAILS

A null client is a special configuration, where the Postfix server is set up only to send outgoing emails, but not receive any incoming emails. Such a setup is widely used in scenarios where you need to send notifications, alerts, or logs; but receiving or managing emails is not needed. By using Ansible and the **postfix** RHEL system role, you can automate this process and remotely configure the Postfix server as a null client for only sending outgoing emails.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

--

- name: Manage Postfix

hosts: managed-node-01.example.com

tasks:

 name: Install postfix ansible.builtin.package:

name: postfix state: present

```
    name: Configure null client for only sending outgoing emails

    ansible.builtin.include_role:
     name: redhat.rhel_system_roles.postfix
     postfix conf:
      myhostname: server.example.com
      myorigin: "$mydomain"
      relayhost: smtp.example.com
      inet interfaces: loopback-only
      mydestination: ""
      relay_domains: "{{ lookup('ansible.builtin.pipe', 'postconf -h default_database type')
}}:/etc/postfix/relay_domains"
     postfix_files:
      name: relay_domains
       postmap: true
       content: |
        example.com OK
        example.net OK
```

The settings specified in the example playbook include the following:

myhostname: <server.example.com>

The internet hostname of this mail system. Defaults to the fully-qualified domain name (FQDN).

myorigin: \$mydomain

The domain name that locally-posted mail appears to come from and that locally posted mail is delivered to. Defaults to **\$myhostname**.

relayhost: <smtp.example.com>

The next-hop destination(s) for non-local mail, overrides non-local domains in recipient addresses. Defaults to an empty field.

inet interfaces: loopback-only

Defines which network interfaces the Postfix server listens on for incoming email connections. It controls whether and how the Postfix server accepts email from the network.

mydestination

Defines which domains and hostnames are considered local.

relay domains: "hash:/etc/postfix/relay domains"

Specifies the domains that Postfix can forward emails to when it is acting as a relay server (SMTP relay). In this case the domains will be generated by the **postfix_files** variable. On RHEL 10, you have to use **relay_domains: "Imdb:/etc/postfix/relay_domains"**.

postfix_files

Defines a list of files that will be placed in the /etc/postfix/ directory. Those files can be converted into Postfix Lookup Tables if needed. In this case postfix_files generates domain names for the SMTP relay.

For details about the role variables and the Postfix configuration parameters used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.postfix/README.md file and the postconf(5) manual page on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.postfix/README.md file
- /usr/share/doc/rhel-system-roles/postfix/ directory
- postconf(5) manual page on your system

CHAPTER 21. INSTALLING AND CONFIGURING A POSTGRESQL DATABASE SERVER BY USING RHEL SYSTEM ROLES

You can use the **postgresql** RHEL system role to automate the installation and management of the PostgreSQL database server. By default, this role also optimizes PostgreSQL by automatically configuring performance-related settings in the PostgreSQL service configuration files.

21.1. CONFIGURING POSTGRESQL WITH AN EXISTING TLS CERTIFICATE BY USING THE POSTGRESQL RHEL SYSTEM ROLE

If your application requires a PostgreSQL database server, you can configure this service with TLS encryption to enable secure communication between the application and the database. By using the **postgresql** RHEL system role, you can automate this process and remotely install and configure PostgreSQL with TLS encryption. In the playbook, you can use an existing private key and a TLS certificate that was issued by a certificate authority (CA).



NOTE

The **postgresql** role cannot open ports in the **firewalld** service. To allow remote access to the PostgreSQL server, add a task that uses the **firewall** RHEL system role to your playbook.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- Both the private key of the managed node and the certificate are stored on the control node in the following files:
 - Private key: ~/<FQDN_of_the_managed_node>.key
 - Certificate: ~/<FQDN of the managed node>.crt

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml

New Vault password: <vault_password>

Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

pwd: <password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Installing and configuring PostgreSQL
 hosts: managed-node-01.example.com
 vars files:
  - ~/vault.yml
 tasks:
  - name: Create directory for TLS certificate and key
    ansible.builtin.file:
     path: /etc/postgresql/
     state: directory
     mode: 755
  - name: Copy CA certificate
    ansible.builtin.copy:
     src: "~/{{ inventory_hostname }}.crt"
     dest: "/etc/postgresql/server.crt"
  - name: Copy private key
    ansible.builtin.copy:
     src: "~/{{ inventory_hostname }}.key"
     dest: "/etc/postgresql/server.key"
     mode: 0600
  - name: PostgreSQL with an existing private key and certificate
   ansible.builtin.include role:
     name: redhat.rhel_system_roles.postgresql
   vars:
     postgresql_version: "16"
     postgresql_password: "{{ pwd }}"
     postgresql_ssl_enable: true
     postgresql_cert_name: "/etc/postgresql/server"
     postgresql_server_conf:
      listen_addresses: ""*""
      password_encryption: scram-sha-256
     postgresql_pg_hba_conf:
      - type: local
       database: all
       user: all
       auth_method: scram-sha-256
      - type: hostssl
       database: all
       user: all
       address: '127.0.0.1/32'
       auth_method: scram-sha-256
      - type: hostssl
       database: all
       user: all
       address: '::1/128'
       auth_method: scram-sha-256
      - type: hostssl
       database: all
       user: all
```

address: '192.0.2.0/24'

auth_method: scram-sha-256

- name: Open the PostgresQL port in firewalld

ansible.builtin.include role:

name: redhat.rhel_system_roles.firewall

vars: firewall:

> service: postgresql state: enabled

The settings specified in the example playbook include the following:

postgresql version: <version>

Sets the version of PostgreSQL to install. The version you can set depends on the PostgreSQL versions that are available in Red Hat Enterprise Linux running on the managed node.

You cannot upgrade or downgrade PostgreSQL by changing the **postgresql_version** variable and running the playbook again.

postgresql password: <password>

Sets the password of the **postgres** database superuser.

You cannot change the password by changing the **postgresql_password** variable and running the playbook again.

postgresql_cert_name: <pri><private_key_and_certificate_file>

Defines the path and base name of both the certificate and private key on the managed node without **.crt** and **key** suffixes. During the PostgreSQL configuration, the role creates symbolic links in the **/var/lib/pgsql/data/** directory that refer to these files.

The certificate and private key must exist locally on the managed node. You can use tasks with the **ansible.builtin.copy** module to transfer the files from the control node to the managed node, as shown in the playbook.

postgresql_server_conf: < list_of_settings>

Defines **postgresql.conf** settings the role should set. The role adds these settings to the /etc/postgresql/system-roles.conf file and includes this file at the end of /var/lib/pgsql/data/postgresql.conf. Consequently, settings from the postgresql_server_conf variable override settings in /var/lib/pgsql/data/postgresql.conf. Re-running the playbook with different settings in postgresql_server_conf overwrites the /etc/postgresql/system-roles.conf file with the new settings.

postgresql_pg_hba_conf: < list_of_authentication_entries>

Configures client authentication entries in the /var/lib/pgsql/data/pg_hba.conf file. For details, see see the PostgreSQL documentation.

The example allows the following connections to PostgreSQL:

- Unencrypted connections by using local UNIX domain sockets.
- TLS-encrypted connections to the IPv4 and IPv6 localhost addresses.

• TLS-encrypted connections from the 192.0.2.0/24 subnet. Note that access from remote addresses is only possible if you also configure the **listen_addresses** setting in the **postgresql_server_conf** variable appropriately.

Re-running the playbook with different settings in **postgresql_pg_hba_conf** overwrites the **/var/lib/pgsql/data/pg_hba.conf** file with the new settings.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.postgresql/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Verification

• Use the **postgres** super user to connect to a PostgreSQL server and execute the \conninfo meta command:

psql "postgresql://postgres@managed-node-01.example.com:5432" -c '\conninfo' Password for user postgres:

You are connected to database "postgres" as user "postgres" on host "192.0.2.1" at port "5432".

SSL connection (protocol: TLSv1.3, cipher: TLS_AES_256_GCM_SHA384, compression: off)

If the output displays a TLS protocol version and cipher details, the connection works and TLS encryption is enabled.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.postgresql/README.md file
- /usr/share/doc/rhel-system-roles/postgresql/ directory
- Ansible vault

21.2. CONFIGURING POSTGRESQL WITH A TLS CERTIFICATE ISSUED FROM IDM BY USING THE POSTGRESQL RHEL SYSTEM ROLE

If your application requires a PostgreSQL database server, you can configure the PostgreSQL service with TLS encryption to enable secure communication between the application and the database. If the PostgreSQL host is a member of a Red Hat Enterprise Linux Identity Management (IdM) domain, the **certmonger** service can manage the certificate request and future renewals.

By using the **postgresql** RHEL system role, you can automate this process. You can remotely install and configure PostgreSQL with TLS encryption, and the **postgresql** role uses the **certificate** RHEL system role to configure **certmonger** and request a certificate from IdM.



NOTE

The **postgresql** role cannot open ports in the **firewalld** service. To allow remote access to the PostgreSQL server, add a task to your playbook that uses the **firewall** RHEL system role.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You enrolled the managed node in an IdM domain.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>

After the ansible-vault create command opens an editor, enter the sensitive data in the
 <key>: <value> format:

```
pwd: <password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
-name: Installing and configuring PostgreSQL
hosts: managed-node-01.example.com
vars_files:
    - ~/vault.yml
tasks:
    - name: PostgreSQL with certificates issued by IdM
    ansible.builtin.include_role:
    name: redhat.rhel_system_roles.postgresql
vars:
    postgresql_version: "16"
    postgresql_password: "{{ pwd }}"
    postgresql_ssl_enable: true
    postgresql_certificates:
    - name: postgresql_cert
    dns: "{{ inventory hostname }}"
```

```
ca: ipa
    principal: "postgresql/{{ inventory_hostname }}@EXAMPLE.COM"
  postgresql server conf:
   listen_addresses: ""*""
   password_encryption: scram-sha-256
  postgresql_pg_hba_conf:
   - type: local
    database: all
    user: all
    auth method: scram-sha-256
   - type: hostssl
    database: all
    user: all
    address: '127.0.0.1/32'
    auth_method: scram-sha-256
   - type: hostssl
    database: all
    user: all
    address: '::1/128'
    auth method: scram-sha-256
   - type: hostssl
    database: all
    user: all
    address: '192.0.2.0/24'
    auth_method: scram-sha-256
- name: Open the PostgresQL port in firewalld
 ansible.builtin.include role:
  name: redhat.rhel_system_roles.firewall
 vars:
  firewall:
```

The settings specified in the example playbook include the following:

postgresql_version: <version>

 service: postgresql state: enabled

Sets the version of PostgreSQL to install. The version you can set depends on the PostgreSQL versions that are available in Red Hat Enterprise Linux running on the managed node.

You cannot upgrade or downgrade PostgreSQL by changing the **postgresql_version** variable and running the playbook again.

postgresql_password: <password>

Sets the password of the **postgres** database superuser.

You cannot change the password by changing the **postgresql_password** variable and running the playbook again.

postgresql_certificates: <certificate_role_settings>

A list of YAML dictionaries with settings for the **certificate** role.

postgresql_server_conf: < list_of_settings>

Defines **postgresql.conf** settings you want the role to set. The role adds these settings to the /etc/postgresql/system-roles.conf file and includes this file at the end of

/var/lib/pgsql/data/postgresql.conf. Consequently, settings from the postgresql_server_conf variable override settings in /var/lib/pgsql/data/postgresql.conf. Re-running the playbook with different settings in postgresql_server_conf overwrites the /etc/postgresql/system-roles.conf file with the new settings.

postgresql_pg_hba_conf: conf: dist_of_authentication_entries>

Configures client authentication entries in the /var/lib/pgsql/data/pg_hba.conf file. For details, see see the PostgreSQL documentation.

The example allows the following connections to PostgreSQL:

- Unencrypted connections by using local UNIX domain sockets.
- TLS-encrypted connections to the IPv4 and IPv6 localhost addresses.
- TLS-encrypted connections from the 192.0.2.0/24 subnet. Note that access from remote addresses is only possible if you also configure the **listen_addresses** setting in the **postgresql server conf** variable appropriately.

Re-running the playbook with different settings in **postgresql_pg_hba_conf** overwrites the /var/lib/pgsql/data/pg_hba.conf file with the new settings.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.postgresql/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Verification

• Use the **postgres** super user to connect to a PostgreSQL server and execute the \conninfo meta command:

psql "postgresql://postgres@managed-node-01.example.com:5432" -c '\conninfo' Password for user postgres:

You are connected to database "postgres" as user "postgres" on host "192.0.2.1" at port "5432".

SSL connection (protocol: TLSv1.3, cipher: TLS_AES_256_GCM_SHA384, compression: off)

If the output displays a TLS protocol version and cipher details, the connection works and TLS encryption is enabled.

Additional resources

/usr/share/ansible/roles/rhel-system-roles.postgresgl/README.md file

- /usr/share/doc/rhel-system-roles/postgresql/ directory
- Ansible vault

CHAPTER 22. REGISTERING THE SYSTEM BY USING RHEL SYSTEM ROLES

The **rhc** RHEL system role enables administrators to automate the registration of multiple systems with Red Hat Subscription Management (RHSM) and Satellite servers. The role also supports Insights-related configuration and management tasks by using Ansible. By default, when you register a system by using **rhc**, the system is connected to Red Hat Insights. Additionally, with **rhc**, you can:

- Configure connections to Red Hat Insights
- Enable and disable repositories
- Configure the proxy to use for the connection
- Configure Insights remediations and, auto updates
- Set the release of the system
- Configure Insights tags

22.1. REGISTERING A SYSTEM BY USING THERHC RHEL SYSTEM ROLE

You can register multiple systems at scale with Red Hat subscription management (RHSM) by using the **rhc** RHEL system role. By default, **rhc** connects the system to Red Hat Insights when you register it. Registering your system enables features and capabilities that you can use to manage your system and report data.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml New Vault password:

Confirm New Vault password: <vault password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

activationKey: <activation_key>
organizationID: <organizationID>

username: <username>
password: <password>

c. Save the changes, and close the editor. Ansible encrypts the data in the vault.

- 2. Create a playbook file, for example ~/playbook.yml, with the following content:
 - To register by using an activation key and organization ID (recommended), use the following playbook:

```
---
- name: Managing systems with the rhc RHEL system role
hosts: managed-node-01.example.com
vars_files:
    - ~/vault.yml
tasks:
    - name: Registering system using activation key and organization ID
    ansible.builtin.include_role:
    name: redhat.rhel_system_roles.rhc
vars:
    rhc_auth:
    activation_keys:
    keys:
    - "{{ activationKey }}"
    rhc_organization: "{{ organizationID }}"
```

The settings specified in the example playbook include the following:

rhc_auth: activation_keys

The key **activation_keys** specifies that you want to register by using the activation keys.

• To register by using a username and password, use the following playbook:

```
---
- name: Managing systems with the rhc RHEL system role
hosts: managed-node-01.example.com
vars_files:
    - ~/vault.yml
tasks:
    - name: Registering system with username and password
    ansible.builtin.include_role:
        name: redhat.rhel_system_roles.rhc
    vars:
    rhc_auth:
    login:
        username: "{{ username }}"
        password: "{{ password }}"
```

The settings specified in the example playbook include the following:

rhc_auth: login

The key login specifies that you want to register by using the username and password.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.rhc/README.md file
- /usr/share/doc/rhel-system-roles/rhc/ directory
- Ansible Vault

22.2. REGISTERING A SYSTEM WITH SATELLITE BY USING THERHC RHEL SYSTEM ROLE

When organizations use Satellite to manage systems, it is necessary to register the system through Satellite. You can remotely register your system with Satellite by using the **rhc** RHEL system role.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

activationKey: <activation_key> organizationID: <organizationID>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Managing systems with the rhc RHEL system role hosts: managed-node-01.example.com vars files:

- ~/vault.yml

tasks:

- name: Register to the custom registration server and CDN

```
ansible.builtin.include_role:
    name: redhat.rhel_system_roles.rhc
vars:
    rhc_auth:
    activation_keys:
        keys:
        - "{{ activationKey }}"
    rhc_organization: "{{ organizationID }}"
    rhc_server:
    hostname: example.com
    port: 443
        prefix: /rhsm
    rhc_baseurl: http://example.com/pulp/content
```

The settings specified in the example playbook include the following:

hostname: example.com

A fully qualified domain name (FQDN) of the Satellite server for system registration and package management.

port: 443

Defines the network port used for communication with the Satellite server.

prefix: /rhsm

Specifies the URL path prefix for accessing resources on the Satellite server.

rhc_baseurl: http://example.com/pulp/content

Defines the prefix for content URLs. In a Satellite environment, the **baseurl** must be set to the same server where the system is registered. Refer to the **hostname** value to ensure the correct server is used.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.rhc/README.md file
- /usr/share/doc/rhel-system-roles/rhc/ directory
- Ansible Vault

22.3. DISABLING THE CONNECTION TO INSIGHTS AFTER THE REGISTRATION BY USING THE RHC RHEL SYSTEM ROLE

When you register a system by using the **rhc** RHEL system role, the role by default, enables the connection to Red Hat Insights. Red Hat Insights is a managed service in the Hybrid Cloud Console that

uses predictive analytics, remediation capabilities, and deep domain expertise to simplify complex operational tasks. You can disable it by using the **rhc** RHEL system role, if not required.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You have registered the system.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

name: Managing systems with the rhc RHEL system role hosts: managed-node-01.example.com tasks:
name: Disable Insights connection ansible.builtin.include_role:
 name: redhat.rhel_system_roles.rhc
 vars:
 rhc_insights:
 state: absent

The settings specified in the example playbook include the following:

rhc_insights absent/present

Enables or disables system registration with Red Hat Insights for proactive analytics and recommendations.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.rhc/README.md file
- /usr/share/doc/rhel-system-roles/rhc/ directory

22.4. MANAGING REPOSITORIES BY USING THE RHC RHEL SYSTEM ROLE

Enabling repositories on a RHEL system is essential for accessing, installing, and updating software packages from verified sources. You can remotely enable or disable repositories on managed nodes by using **rhc** RHEL system role to ensure the system security, stability, and compatibility.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You have details of the repositories which you want to enable or disable on the managed nodes.
- You have registered the system.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Managing systems with the rhc RHEL system role

hosts: managed-node-01.example.com

tasks:

name: Enable repository ansible.builtin.include_role:

name: redhat.rhel_system_roles.rhc

vars:

rhc_repositories:

- name: "RepositoryName"

state: enabled

The settings specified in the example playbook include the following:

name: RepositoryName

Name of the repository that should be enabled.

state: enabled/disabled

Optional, enables or disables the repository. Default is **enabled**.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

/usr/share/ansible/roles/rhel-system-roles.rhc/README.md file

• /usr/share/doc/rhel-system-roles/rhc/ directory

22.5. LOCKING THE SYSTEM TO A PARTICULAR RELEASE BY USING THE RHC RHEL SYSTEM ROLE

To ensure system stability and compatibility, it is sometimes necessary to limit the RHEL system to use only repositories from a specific minor version rather than automatically upgrading to the latest available release. Locking the system to a particular minor version helps maintain consistency in production environments, which prevents unintended updates that might introduce compatibility issues.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You know the RHEL version to which you want to lock the system. Note that you can only lock
 the system to the RHEL minor version that the managed node currently runs or a later minor
 version.
- You have registered the system.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Managing systems with the rhc RHEL system role

hosts: managed-node-01.example.com

tasks:

- name: Lock the system to a particular release

ansible.builtin.include role:

name: redhat.rhel_system_roles.rhc

vars:

rhc release: "8.6"

The settings specified in the example playbook include the following:

rhc_release: version

The version of RHEL to set for the system, so the available content will be limited to that version.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.rhc/README.md file
- /usr/share/doc/rhel-system-roles/rhc/ directory
- Red Hat Enterprise Linux (RHEL) Extended Update Support (EUS) Overview (Red Hat Knowledgebase).

22.6. USING A PROXY SERVER WHEN REGISTERING THE HOST BY USING THE RHC RHEL SYSTEM ROLE

If your security restrictions allow access to the Internet only through a proxy server, you can specify the proxy settings of the **rhc** role when you register the system using **rhc**.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

username: <username>
password: <password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

 name: Managing systems with the rhc RHEL system role hosts: managed-node-01.example.com

vars_files:

- ~/vault.yml

tasks:

 name: Register to the Red Hat Customer Portal by using proxy ansible.builtin.include_role:

name: redhat.rhel system roles.rhc

```
vars:
  rhc_auth:
  login:
    username: "{{ username }}"
    password: "{{ password }}"
  rhc_proxy:
  hostname: proxy.example.com
  port: 3128
  username: "{{ proxy_username }}"
  password: "{{ proxy_password }}"
```

The settings specified in the example playbook include the following:

hostname: proxy.example.com

A fully qualified domain name (FQDN) of the proxy server.

port: 3128

Defines the network port used for communication with the proxy server.

username: proxy_username

Specifies the username for authentication. This is required only if the proxy server requires authentication.

password: proxy_password

Specifies the password for authentication. This is required only if the proxy server requires authentication.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.rhc/README.md file
- /usr/share/doc/rhel-system-roles/rhc/ directory
- Ansible Vault

22.7. MANAGING AUTO UPDATES OF INSIGHTS RULES BY USING THE RHC RHEL SYSTEM ROLE

You can enable or disable the automatic collection rule updates for Red Hat Insights by using the **rhc** RHEL system role. By default, when you connect your system to Red Hat Insights, this option is enabled. You can disable it by using **rhc**.



WARNING

If you disable this feature, you risk using outdated rule definition files and not getting the most recent validation updates.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You have registered the system.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml
New Vault password: confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

username: <username>
password: <password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: Managing systems with the rhc RHEL system role hosts: managed-node-01.example.com vars_files:
    - ~/vault.yml tasks:
    - name: Enable Red Hat Insights autoupdates ansible.builtin.include_role:
        name: redhat.rhel_system_roles.rhc vars:
        rhc_auth:
        login:
            username: "{{ username }}"
            password: "{{ password }}"
```

rhc_insights: autoupdate: true state: present

The settings specified in the example playbook include the following:

autoupdate: true/false

Enables or disables the automatic collection rule updates for Red Hat Insights.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.rhc/README.md file
- /usr/share/doc/rhel-system-roles/rhc/ directory
- Ansible Vault

22.8. CONFIGURING INSIGHTS REMEDIATIONS BY USING THERHORIEST SYSTEM ROLF

You can configure your systems to automatically update the dynamic configuration by using the **rhc** RHEL system role. When you connect your system to Red Hat Insights, it is enabled by default. You can disable it, if not required. You can use **rhc** to ensure your system is ready for remediation when connected directly to Red Hat. For more information about Red Hat Insights remediations, see Red Hat Insights Remediations Guide.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You have Insights remediations enabled.
- You have registered the system.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

 name: Managing systems with the rhc RHEL system role hosts: managed-node-01.example.com

tasks:

- name: Disable remediation ansible.builtin.include_role:

name: redhat.rhel_system_roles.rhc

vars:

rhc_insights:

remediation: absent state: present

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.rhc/README.md file
- /usr/share/doc/rhel-system-roles/rhc/ directory

22.9. CONFIGURING INSIGHTS TAGS BY USING THE RHC RHEL SYSTEM ROLF

You can use the **rhc** RHEL system role to configure Red Hat Insights tags for system filtering and grouping. You can also customize tags based on the requirements. Filtering and grouping systems by using Red Hat Insights tags help administrators efficiently manage, monitor, and apply policies to specific sets of systems based on attributes like environment, location, or function. This improves visibility, simplifies automation, and enhances security compliance across large infrastructures.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml New Vault password:

Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

```
username: <username>
password: <password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Managing systems with the rhc RHEL system role
hosts: managed-node-01.example.com
vars_files:
  - ~/vault.yml
tasks:
  - name: Creating tags
   ansible.builtin.include_role:
    name: redhat.rhel_system_roles.rhc
   vars:
    rhc auth:
     login:
       username: "{{ username }}"
       password: "{{ password }}"
    rhc insights:
     tags:
       group: group-name-value
       location: location-name-value
       description:
        - RHEL8
        - SAP
       sample_key: value
     state: present
```

The settings specified in the example playbook include the following:

group: group-name-value

Specifies the system group for organizing and managing registered hosts.

location: location-name-value

Defines the location associated with the registered system.

description

Provides a brief summary or identifier for the registered system.

state: present/absent

Indicates the current status of the registered system.



NOTE

The content inside the **tags** is a YAML structure representing the tags desired by the administrator for the configured systems. The example provided here is for illustrative purposes only and is not exhaustive. Administrators can customize the YAML structure to include any additional keys and values as needed.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check --ask-vault-pass ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.rhc/README.md file
- /usr/share/doc/rhel-system-roles/rhc/ directory
- Ansible Vault
- Custom system tagging

22.10. UNREGISTERING A SYSTEM BY USING THERHC RHEL SYSTEM ROLE

You can use the **rhc** RHEL system role to unregister the system from the Red Hat subscription service if you no longer want to receive content from the registration server on a specific system, for example, system decommissioning, VM deletion, or when switching to a local content mirror.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The system is already registered.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Managing systems with the rhc RHEL system role

hosts: managed-node-01.example.com

tasks:

- name: Unregister the system ansible.builtin.include_role:

name: redhat.rhel_system_roles.rhc

vars:

rhc_state: absent

The settings specified in the example playbook include the following:

rhc_state: absent

Specifies the system should be unregistered from the registration server, RHSM, or Satellite.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.rhc/README.md file
- /usr/share/doc/rhel-system-roles/rhc/ directory

CHAPTER 23. REMOTE MANAGEMENT WITH IPMI AND REDFISH BY USING THE RHEL_MGMT COLLECTION

With the Intelligent Platform Management Interface (IPMI) and the Redfish API, administrators can remotely manage hosts even if the operating system is not running. The **rhel_mgmt** Ansible collection provides modules that use IPMI and Redfish to perform certain remote operations, such as setting the boot device.

23.1. SETTING THE BOOT DEVICE BY USING THERHEL_MGMT.IPMI_BOOT MODULE

You can set the boot device of a host by using the **ipmi_boot** module of the **redhat.rhel_mgmt** collection. This module uses the Intelligent Platform Management Interface (IPMI) to perform this operation.



IMPORTANT

When you use this Ansible module, three hosts are involved: the control node, the managed node, and the host with the baseboard management controller (BMC) on which the actual IPMI operation is applied. The control node executes the playbook on the managed node. The managed host connects to the remote BMC to execute the IPMI operation. For example, if you set **hosts: managed-node-01.example.com** and **name: server.example.com** in the playbook, then **managed-node-01.example.com** changes the setting by using IPMI on **server.example.com**.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The **ansible-collection-redhat-rhel_mgmt** package is installed on the control node.
- You have credentials to access the BMC, and these credentials have permissions to change settings.
- The managed node can access the remote BMC over the network.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml

New Vault password: <vault_password>

Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

ipmi_usr: <username>
ipmi_pwd: <password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

--- name: Set the boot device by using IPMI hosts: managed-node-01.example.com vars_files:
- ~/vault.yml

tasks:

- name: Install python3-pyghmi prerequisite

ansible.builtin.dnf: name: python3-pyghmi state: latest

- name: Set the boot device to hd
redhat.rhel_mgmt.ipmi_boot:
 name: <bmc_hostname_or_ip_address>
 port: <bmc_port_number>
 user: "{{ ipmi_usr }}"
 password: "{{ ipmi_pwd }}"

bootdev: hd persistent: true

The settings specified in the example playbook include the following:

name: <bmc_hostname_or_ip_address>

Defines the hostname or IP address of the BMC. This is the BMC of the host on which the managed node performs the action.

port:
 cport_number>

Sets the Remote Management Control Protocol (RMCP) port number. The default is 623.

bootdev: <value>

Sets the boot device. You can select one of the following values:

- hd: Boots from the hard disk.
- **network**: Boots from network.
- **optical**: Boots from an optical drive, such as a DVD-ROM.
- **floppy**: Boots from a floppy disk.
- **safe**: Boots from hard drive in safe mode.
- **setup**: Boots into the BIOS or UEFI.
- **default**: Removes any IPMI-directed boot device request.

persistent: <true/false>

Configures whether the remote host uses the defined setting for all future boots or only for the next one. By default, this variable is set to **false**. Note that not all BMCs support setting the boot device persistently.

For details about all variables used in the playbook, use the **ansible-doc redhat.rhel_mgmt.ipmi_boot** command on the control node to display the documentation of the module.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

Additional resources

- The ansible-doc redhat.rhel_mgmt.ipmi_boot command on the control node
- Ansible vault

23.2. SETTING THE SYSTEM POWER STATE BY USING THE RHEL_MGMT.IPMI_POWER MODULE

You can set the hardware state by using the <code>ipmi_power</code> module of the <code>redhat.rhel_mgmt</code> collection. For example, you can ensure that a host is powered on or hard-reset it without involvement of the operating system. The <code>ipmi_power</code> module uses the Intelligent Platform Management Interface (IPMI) to perform operations.



IMPORTANT

When you use this Ansible module, three hosts are involved: the control node, the managed node, and the host with the baseboard management controller (BMC) on which the actual IPMI operation is applied. The control node executes the playbook on the managed node. The managed host connects to the remote BMC to execute the IPMI operation. For example, if you set **hosts: managed-node-01.example.com** and **name: server.example.com** in the playbook, then **managed-node-01.example.com** changes the setting by using IPMI on **server.example.com**.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The **ansible-collection-redhat-rhel_mgmt** package is installed on the control node.

- You have credentials to access the BMC, and these credentials have permissions to change settings.
- The managed node can access the remote BMC over the network.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Configure the system state by using IPMI hosts: managed-node-01.example.com vars files: - ~/vault.yml tasks: - name: Install python3-pyghmi prerequisite ansible.builtin.dnf: name: python3-pyghmi state: latest - name: Ensure a machine is powered on redhat.rhel mgmt.ipmi power: name: <bmc_hostname_or_ip_address> port:

port_number> user: "{{ ipmi_usr }}" password: "{{ ipmi_pwd }}" state: on

The settings specified in the example playbook include the following:

name: <bmc_hostname_or_ip_address>

Defines the hostname or IP address of the BMC. This is the BMC of the host on which the managed node performs the action.

port:
 cport_number>

Sets the Remote Management Control Protocol (RMCP) port number. The default is 623.

state: <value>

Sets the state which the device should be in. You can select one of the following values:

- **on**: Powers on the system.
- **off**: Powers off the system without notifying the operating system.
- **shutdown**: Requests a shutdown from the operating system.
- reset: Performs a hard reset.
- **boot**: Powers on the system if it was switched off, or resets the system if it was switched off.

For details about all variables used in the playbook, use the **ansible-doc redhat.rhel_mgmt.ipmi_power** command on the control node to display the documentation of the module.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- The ansible-doc redhat.rhel_mgmt.ipmi_power command on the control node
- Ansible vault

23.3. MANAGING OUT-OF-BAND CONTROLLERS BY USING THE RHEL MGMT.REDFISH COMMAND MODULE

You can send commands to the Redfish API to remotely manage out-of-band (OOB) controllers by using the **redfish_command** module of the **redhat.rhel_mgmt** collection. With this module, you can perform a large number of management operations, for example:

- Performing power management actions
- Managing virtual media
- Managing users of the OOB controller
- Updating the firmware



IMPORTANT

When you use this Ansible module, three hosts are involved: the control node, the managed node, and the host with the OOB controller on which the actual operation is performed. The control node executes the playbook on the managed node, and the managed host connects to the remote OOB controller by using the Redfish API to execute the operation. For example, if you set hosts: managed-node-01.example.com and baseuri: server.example.com in the playbook, then managed-node-01.example.com executes the operation on server.example.com.

Prerequisites

- You have prepared the control node and the managed nodes.
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has sudo permissions on them.
- The **ansible-collection-redhat-rhel_mgmt** package is installed on the control node.
- You have credentials to access the OOB controller, and these credentials have permissions to change settings.
- The managed node can access the remote OOB controller over the network.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

```
redfish_usr: <username> redfish_pwd: redfish_pwd:
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

--- name: Send commands to OOB controller by using the Redfish API hosts: managed-node-01.example.com
vars_files:
- ~/vault.yml
tasks:

- name: Power on the system
redhat.rhel_mgmt.redfish_command:
 baseuri: <uri>
 username: "{{ redfish_usr }}"

password: "{{ redfish_pwd }}"

category: Systems command: PowerOn

The settings specified in the example playbook include the following:

baseuri: <uri>

Defines the URI of the OOB controller. This is the OOB controller of the host on which the managed node performs the action.

category: <value>

Sets the category of the command to execute. The following categories are available:

- **Accounts**: Manages user accounts of the OOB controller.
- Chassis: Manages chassis-related settings.
- **Manager**: Provides access to Redfish services.
- **Session**: Manages Redfish login sessions.
- **Systems** (default): Manages machine-related settings.
- **Update**: Manages firmware update-related actions.

command: <command>

Sets the command to execute. Depending on the command, it can be necessary to set additional variables.

For details about all variables used in the playbook, use the **ansible-doc redhat.rhel_mgmt.redfish_command** command on the control node to display the documentation of the module.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

Additional resources

- The ansible-doc redhat.rhel mgmt.ipmi command command on the control node
- Ansible vault

23.4. QUERYING INFORMATION FROM OUT-OF-BAND CONTROLLERS BY USING THE RHEL_MGMT.REDFISH_INFO MODULE

You can remotely query information from of out-of-band (OOB) controllers through the Redfish API by using the **redfish_info** module of the **redhat.rhel_mgmt** collection. To display the returned value, register a variable with the fetched information, and display the content of this variable.



IMPORTANT

When you use this Ansible module, three hosts are involved: the control node, the managed node, and the host with the OOB controller on which the actual operation is performed. The control node executes the playbook on the managed node, and the managed host connects to the remote OOB controller by using the Redfish API to execute the operation. For example, if you set hosts: managed-node-01.example.com and baseuri: server.example.com in the playbook, then managed-node-01.example.com executes the operation on server.example.com.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The **ansible-collection-redhat-rhel_mgmt** package is installed on the control node.
- You have credentials to access the OOB controller, and these credentials have permissions to query settings.
- The managed node can access the remote OOB controller over the network.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

redfish_usr: <username>
redfish_pwd: <password>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

--- name: Query information by using the Redfish API hosts: managed-node-01.example.com vars_files:
- ~/vault.yml tasks:

- name: Get CPU inventory
redhat.rhel_mgmt.redfish_info:
 baseuri: <uri>
 username: "{{ redfish_usr }}"
 password: "{{ redfish_pwd }}"

category: Systems command: GetCpuInventory

register: result

- name: Display the fetched information
ansible.builtin.debug:
 msg: "{{ result.redfish_facts.cpu.entries | to_nice_json }}"

The settings specified in the example playbook include the following:

baseuri: <uri>

Defines the URI of the OOB controller. This is the OOB controller of the host on which the managed node performs the action.

category: <value>

Sets the category of the information to query. The following categories are available:

- Accounts: User accounts of the OOB controller
- Chassis: Chassis-related settings
- Manager: Redfish services
- **Session**: Redfish login sessions
- **Systems** (default): Machine-related settings
- **Update**: Firmware-related settings
- All: Information from all categories.

You can also set multiple categories if you use a list, for example ["Systems", "Accounts"].

command: <command>

Sets the guery command to execute.

For details about all variables used in the playbook, use the **ansible-doc redhat.rhel_mgmt.redfish_info** command on the control node to display the documentation of the module.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- The ansible-doc redhat.rhel_mgmt.redfish_info command on the control node
- Ansible vault

23.5. MANAGING BIOS, UEFI, AND OUT-OF-BAND CONTROLLERS BY USING THE RHEL_MGMT.REDFISH_CONFIG MODULE

You can configure BIOS, UEFI, and out-of-band (OOB) controllers settings through the Redfish API by using the **redfish_config** module of the **redhat.rhel_mgmt** collection. This enables you to modify the settings remotely with Ansible.



IMPORTANT

When you use this Ansible module, three hosts are involved: the control node, the managed node, and the host with the OOB controller on which the actual operation is performed. The control node executes the playbook on the managed node, and the managed host connects to the remote OOB controller by using the Redfish API to execute the operation. For example, if you set hosts: managed-node-01.example.com and baseuri: server.example.com in the playbook, then managed-node-01.example.com executes the operation on server.example.com.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has sudo permissions on them.
- The ansible-collection-redhat-rhel mgmt package is installed on the control node.
- You have credentials to access the OOB controller, and these credentials have permissions to change settings.
- The managed node can access the remote OOB controller over the network.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml

New Vault password: <vault_password>

Confirm New Vault password: <vault_password>

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

redfish_usr: <username>
redfish_pwd: cpassword>

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

--- name: Configure BIOS/UEFI settings by using the Redfish API hosts: managed-node-01.example.com vars_files:
 - ~/vault.yml tasks:
 - name: Change the boot mode to UEFI redhat.rhel_mgmt.redfish_config:
 baseuri: <uri>
 username: "{{ redfish_usr }}"
 password: "{{ redfish_pwd }}"
 category: Systems
 command: SetBiosAttributes
 bios_attributes:
 BootMode: "Uefi"

The settings specified in the example playbook include the following:

baseuri: <uri>

Defines the URI of the OOB controller. This is the OOB controller of the host on which the managed node performs the action.

category: <value>

Sets the category of the command to execute. The following categories are available:

- Accounts: Manages user accounts of the OOB controller.
- Chassis: Manages chassis-related settings.
- Manager: Provides access to Redfish services.
- **Session**: Manages Redfish login sessions.
- Systems (default): Manages machine-related settings.
- **Update**: Manages firmware update-related actions.

command: <command>

Sets the command to execute. Depending on the command, it can be necessary to set additional variables.

For details about all variables used in the playbook, use the **ansible-doc redhat.rhel_mgmt.redfish_config** command on the control node to display the documentation of the module.

3. Validate the playbook syntax:

$\$\ ansible-playbook\ \hbox{--ask-vault-pass}\ \hbox{--syntax-check}\ \hbox{\sim/playbook.yml}$

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Additional resources

- The ansible-doc redhat.rhel_mgmt.redfish_config command on the control node
- Ansible vault

CHAPTER 24. CONFIGURING SELINUX BY USING RHEL SYSTEM ROLES

You can remotely configure and manage SELinux permissions by using the **selinux** RHEL system role, for example:

- Cleaning local policy modifications related to SELinux booleans, file contexts, ports, and logins.
- Setting SELinux policy booleans, file contexts, ports, and logins.
- Restoring file contexts on specified files or directories.
- Managing SELinux modules.

24.1. RESTORING THE SELINUX CONTEXT ON DIRECTORIES BY USING THE SELINUX RHEL SYSTEM ROLE

There can be multiple cases when files have an incorrect SELinux context than. For example, if files are copied or moved to a directory, their SELinux context might not match the new location's expected context. With an incorrect SELinux context, applications might fail to access the files. To remotely reset the SELinux context on directories on a large number of hosts, you can use the **selinux** RHEL system role.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: Managing SELinux
hosts: managed-node-01.example.com
tasks:
- name: Restore SELinux context
ansible.builtin.include_role:
    name: redhat.rhel_system_roles.selinux
vars:
    selinux_restore_dirs:
    -/var/www/
- /etc/
```

The settings specified in the example playbook include the following:

selinux_restore_dirs: < list>

Defines the list of directories on which the role should reset the SELinux context.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.selinux/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Display the SELinux context for files or directories for which you have reset the context. For example, to display the context on the /var/www/ directory, enter:

ansible rhel9.example.com -m command -a 'ls -ldZ /var/www/' drwxr-xr-x. 4 root root system_u:object_r:httpd_sys_content_t:s0 33 Feb 28 13:20 /var/www/

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.selinux/README.md file
- /usr/share/doc/rhel-system-roles/selinux/ directory

24.2. MANAGING SELINUX NETWORK PORT LABELS BY USING THE SELINUX RHEL SYSTEM ROLE

If you want to run a service on a non-standard port, you must set the corresponding SELinux type label on this port. This prevents that SELinux denies permission to the service when the service wants to listen on the non-standard port. By using the **selinux** RHEL system role, you can automate this task and remotely assign a type label on ports.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Managing SELinux

hosts: managed-node-01.example.com

tasks:

- name: Set http_port_t label on network port

ansible.builtin.include_role:

name: redhat.rhel_system_roles.selinux

vars:

selinux_ports:

- ports: <port_number>

proto: tcp

setype: http_port_t
state: present

The settings specified in the example playbook include the following:

Defines the port numbers to which you want to assign the SELinux label. Separate multiple values by comma.

setype: <type_label>

Defines the SELinux type label.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.selinux/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Display the port numbers that have the http port t label assigned:

```
# ansible managed-node-01.example.com -m shell -a 'semanage port --list | grep http_port_t'
http_port_t tcp 80, 81, 443, <port_number>, 488, 8008, 8009, 8443, 9000
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.selinux/README.md file
- /usr/share/doc/rhel-system-roles/selinux/ directory

24.3. DEPLOYING AN SELINUX MODULE BY USING THE SELINUX RHEL SYSTEM ROLE

If the default SELinux policies do not meet your requirements, you can create custom modules to allow your application to access the required resources. By using the **selinux** RHEL system role, you can automate this process and remotely deploy SELinux modules.

Prerequisites

• You have prepared the control node and the managed nodes .

- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The SELinux module you want to deploy is stored in the same directory as the playbook.
- The SELinux module is available in the Common Intermediate Language (CIL) or policy package (PP) format.

If you are using a PP module, ensure that **policydb** version on the managed nodes is the same or later than the version used to build the PP module.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: Managing SELinux
hosts: managed-node-01.example.com
tasks:
- name: Deploying a SELinux module
ansible.builtin.include_role:
    name: redhat.rhel_system_roles.selinux
vars:
    selinux_modules:
    - path: <module_file>
priority: <value>
    state: enabled
```

The settings specified in the example playbook include the following:

path: <module file>

Sets the path to the module file on the control node.

priority: <value>

Sets the SELinux module priority. 400 is the default.

state: <value>

Defines the state of the module:

- **enabled**: Install or enable the module.
- disabled: Disable a module.
- **absent**: Remove a module.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.selinux/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

- Remotely display the list of SELinux modules and filter for the one you used in the playbook:
 - # ansible managed-node-01.example.com -m shell -a 'semodule -l | grep <module>'

If the module is listed, it is installed and enabled.

- /usr/share/ansible/roles/rhel-system-roles.selinux/README.md file
- /usr/share/doc/rhel-system-roles/selinux/ directory

CHAPTER 25. CONFIGURING THE OPENSSH SERVER AND CLIENT BY USING RHEL SYSTEM ROLES

You can use the **sshd** RHEL system role to configure OpenSSH servers and the **ssh** RHEL system role to configure OpenSSH clients consistently, in an automated fashion, and on any number of RHEL systems at the same time. Such configurations are necessary for any system where secure remote interaction is needed, for example:

- Remote system administration: securely connecting to your machine from another computer using an SSH client.
- Secure file transfers: the Secure File Transfer Protocol (SFTP) provided by OpenSSH enable you to securely transfer files between your local machine and a remote system.
- Automated DevOps pipelines: automating software deployments that require secure connection to remote servers (CI/CD pipelines).
- Tunneling and port forwarding: forwarding a local port to access a web service on a remote server behind a firewall. For example a remote database or a development server.
- Key-based authentication: more secure alternative to password-based logins.
- Certificate-based authentication: centralized trust management and better scalability.
- Enhanced security: disabling root logins, restricting user access, enforcing strong encryption and other such forms of hardening ensures stronger system security.

25.1. HOW THE SSHD RHEL SYSTEM ROLE MAPS SETTINGS FROM A PLAYBOOK TO THE CONFIGURATION FILE

In the ${\bf sshd}$ RHEL system role playbook, you can define the parameters for the server SSH configuration file.

If you do not specify these settings, the role produces the **sshd_config** file that matches the RHEL defaults.

In all cases, booleans correctly render as **yes** and **no** in the final configuration on your managed nodes. You can use lists to define multi-line configuration items. For example:

sshd_ListenAddress:
- 0.0.0.0
- '::'

renders as:

ListenAddress 0.0.0.0 ListenAddress ::

- /usr/share/ansible/roles/rhel-system-roles.sshd/README.md file
- /usr/share/doc/rhel-system-roles/sshd/ directory

25.2. CONFIGURING OPENSSH SERVERS BY USING THESSHD RHEL SYSTEM ROLE

You can use the **sshd** RHEL system role to configure multiple OpenSSH servers. These ensure secure communication environment for remote users by providing namely:

- Management of incoming SSH connections from remote clients
- Credentials verification
- Secure data transfer and command execution



NOTE

You can use the **sshd** RHEL system role alongside with other RHEL system roles that change SSHD configuration, for example the Identity Management RHEL system roles. To prevent the configuration from being overwritten, ensure the **sshd** RHEL system role uses namespaces (RHEL 8 and earlier versions) or a drop-in directory (RHEL 9).

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: SSH server configuration

hosts: managed-node-01.example.com

tasks:

- name: Configure sshd to prevent root and password login except from particular subnet ansible.builtin.include role:

name: redhat.rhel_system_roles.sshd

vars:

sshd_config:

PermitRootLogin: no

PasswordAuthentication: no

Match:

- Condition: "Address 192.0.2.0/24"

PermitRootLogin: yes

PasswordAuthentication: yes

The settings specified in the example playbook include the following:

PasswordAuthentication: yes|no

Controls whether the OpenSSH server (**sshd**) accepts authentication from clients that use the username and password combination.

Match:

The match block allows the **root** user login using password only from the subnet 192.0.2.0/24.

For details about the role variables and the OpenSSH configuration options used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.sshd/README.md file and the sshd_config(5) manual page on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. Log in to the SSH server:

\$ ssh <username>@<ssh_server>

2. Verify the contents of the **sshd_config** file on the SSH server:

\$ cat /etc/ssh/sshd_config.d/00-ansible_system_role.conf
#
Ansible managed
#

PasswordAuthentication no PermitRootLogin no Match Address 192.0.2.0/24

PasswordAuthentication yes

PermitRootLogin yes

- 3. Check that you can connect to the server as root from the **192.0.2.0/24** subnet:
 - a. Determine your IP address:

\$ hostname -I 192.0.2.1

If the IP address is within the 192.0.2.1 - 192.0.2.254 range, you can connect to the server.

b. Connect to the server as root:

\$ ssh root@<ssh_server>

- /usr/share/ansible/roles/rhel-system-roles.sshd/README.md file
- /usr/share/doc/rhel-system-roles/sshd/ directory

25.3. USING THE SSHD RHEL SYSTEM ROLE FOR NON-EXCLUSIVE CONFIGURATION

By default, applying the **sshd** RHEL system role overwrites the entire configuration. This may be problematic if you have previously adjusted the configuration, for example, with a different RHEL system role or a playbook. To apply the **sshd** RHEL system role for only selected configuration options while keeping other options in place, you can use the non-exclusive configuration.

You can apply a non-exclusive configuration:

- In RHEL 8 and earlier by using a configuration snippet.
- In RHEL 9 and later by using files in a drop-in directory. The default configuration file is already placed in the drop-in directory as /etc/ssh/sshd_config.d/00-ansible_system_role.conf.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has sudo permissions on them.

Procedure

- 1. Create a playbook file, for example ~/playbook.yml, with the following content:
 - For managed nodes that run RHEL 8 or earlier:

```
---
- name: Non-exclusive sshd configuration
hosts: managed-node-01.example.com
tasks:
- name: Configure SSHD to accept environment variables
ansible.builtin.include_role:
    name: redhat.rhel_system_roles.sshd
vars:
    sshd_config_namespace: <my-application>
    sshd_config:
    # Environment variables to accept
    AcceptEnv:
    LANG
    LS_COLORS
EDITOR
```

For managed nodes that run RHEL 9 or later:

```
name: Non-exclusive sshd configuration
hosts: managed-node-01.example.com
tasks:

name: Configure sshd to accept environment variables
ansible.builtin.include_role:
name: redhat.rhel_system_roles.sshd
vars:
sshd config file: /etc/ssh/sshd config.d/ <42-my-application>.conf
```

```
sshd_config:
# Environment variables to accept
AcceptEnv:
LANG
LS_COLORS
EDITOR
```

The settings specified in the example playbooks include the following:

sshd_config_namespace: <my-application>

The role places the configuration that you specify in the playbook to configuration snippets in the existing configuration file under the given namespace. You need to select a different namespace when running the role from different context.

sshd_config_file: /etc/ssh/sshd_config.d/<42-my-application>.conf

In the **sshd_config_file** variable, define the **.conf** file into which the **sshd** system role writes the configuration options. Use a two-digit prefix, for example **42-** to specify the order in which the configuration files will be applied.

AcceptEnv:

Controls which environment variables the OpenSSH server (**sshd**) will accept from a client:

- LANG: defines the language and locale settings.
- **LS_COLORS**: defines the displaying color scheme for the **Is** command in the terminal.
- **EDITOR**: specifies the default text editor for the command-line programs that need to open an editor.

For details about the role variables and the OpenSSH configuration options used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.sshd/README.md file and the sshd_config(5) manual page on the control node.

2. Validate the playbook syntax:

$\$\ ansible-playbook\ --syntax-check\ \sim\!/playbook.yml$

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

- Verify the configuration on the SSH server:
 - For managed nodes that run RHEL 8 or earlier:

```
# cat /etc/ssh/sshd_config
...
# BEGIN sshd system role managed block: namespace <my-application>
```

Match all
AcceptEnv LANG LS_COLORS EDITOR
END sshd system role managed block: namespace <my-application>

• For managed nodes that run RHEL 9 or later:

cat /etc/ssh/sshd_config.d/42-my-application.conf # Ansible managed # AcceptEnv LANG LS_COLORS EDITOR

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.sshd/README.md file
- /usr/share/doc/rhel-system-roles/sshd/ directory
- sshd_config(5) man page on your system

25.4. OVERRIDING THE SYSTEM-WIDE CRYPTOGRAPHIC POLICY ON AN SSH SERVER BY USING THE SSHD RHEL SYSTEM ROLE

When the default cryptographic settings do not meet certain security or compatibility needs, you may want to override the system-wide cryptographic policy on the OpenSSH server using the **sshd** RHEL system role. Especially, in the following notable situations:

- Compatibility with older clients: necessity to use weaker-than-default encryption algorithms, key exchange protocols, or ciphers.
- Enforcing stronger security policies: simultaneously, you can disable weaker algorithms. Such a measure could exceed the default system cryptographic policies, especially in the highly secure and regulated environments.
- Performance considerations: the system defaults could enforce stronger algorithms that can be computationally intensive for some systems.
- Customizing for specific security needs: adapting for unique requirements that are not covered by the default cryptographic policies.



WARNING

It is not possible to override all aspects of the cryptographic policies from the **sshd** RHEL system role. For example, SHA1 signatures might be forbidden on a different layer so for a more generic solution, see Setting a custom cryptographic policy by using RHEL system roles.

Prerequisites

• You have prepared the control node and the managed nodes .

- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
name: Deploy SSH configuration for OpenSSH server hosts: managed-node-01.example.com tasks:
name: Overriding the system-wide cryptographic policy ansible.builtin.include_role:
    name: redhat.rhel_system_roles.sshd vars:
    sshd_sysconfig: true
    sshd_sysconfig_override_crypto_policy: true
    sshd_KexAlgorithms: ecdh-sha2-nistp521
    sshd_Ciphers: aes256-ctr
    sshd_MACs: hmac-sha2-512-etm@openssh.com
    sshd_HostKeyAlgorithms: rsa-sha2-512,rsa-sha2-256
```

The settings specified in the example playbook include the following:

sshd_KexAlgorithms

You can choose key exchange algorithms, for example, **ecdh-sha2-nistp256**, **ecdh-sha2-nistp384**, **ecdh-sha2-nistp521**,**diffie-hellman-group14-sha1**, or **diffie-hellman-group-exchange-sha256**.

sshd Ciphers

You can choose ciphers, for example, aes128-ctr, aes192-ctr, or aes256-ctr.

sshd_MACs

You can choose MACs, for example, hmac-sha2-256, hmac-sha2-512, or hmac-sha1.

sshd HostKeyAlgorithms

You can choose a public key algorithm, for example, **ecdsa-sha2-nistp256**, **ecdsa-sha2-nistp384**, **ecdsa-sha2-nistp521**, or **ssh-rsa**.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.sshd/README.md file on the control node.

On RHEL 9 managed nodes, the system role writes the configuration into the /etc/ssh/sshd_config.d/00-ansible_system_role.conf file, where cryptographic options are applied automatically. You can change the file by using the sshd_config_file variable. However, to ensure the configuration is effective, use a file name that lexicographically precedes the /etc/ssh/sshd_config.d/50-redhat.conf file, which includes the configured crypto policies.

On RHEL 8 managed nodes, you must enable override by setting the **sshd_sysconfig_override_crypto_policy** and **sshd_sysconfig** variables to **true**.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• You can verify the success of the procedure by using the verbose SSH connection and check the defined variables in the following output:

\$ ssh -vvv <ssh_server>

...

debug2: peer server KEXINIT proposal

debug2: KEX algorithms: ecdh-sha2-nistp521

debug2: host key algorithms: rsa-sha2-512,rsa-sha2-256

debug2: ciphers ctos: aes256-ctr debug2: ciphers stoc: aes256-ctr

debug2: MACs ctos: hmac-sha2-512-etm@openssh.com debug2: MACs stoc: hmac-sha2-512-etm@openssh.com

• • •

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.sshd/README.md file
- /usr/share/doc/rhel-system-roles/sshd/ directory

25.5. HOW THE SSH RHEL SYSTEM ROLE MAPS SETTINGS FROM A PLAYBOOK TO THE CONFIGURATION FILE

In the **ssh** RHEL system role playbook, you can define the parameters for the client SSH configuration file.

If you do not specify these settings, the role produces a global **ssh_config** file that matches the RHEL defaults.

In all the cases, booleans correctly render as **yes** or **no** in the final configuration on your managed nodes. You can use lists to define multi-line configuration items. For example:

LocalForward:

- 22 localhost:2222
- 403 localhost:4003

renders as:

LocalForward 22 localhost:2222 LocalForward 403 localhost:4003



NOTE

The configuration options are case sensitive.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.ssh/README.md file
- /usr/share/doc/rhel-system-roles/ssh/ directory

25.6. CONFIGURING OPENSSH CLIENTS BY USING THE SSH RHEL SYSTEM ROLE

You can use the **ssh** RHEL system role to configure multiple OpenSSH clients. These enable the local user to establish a secure connection with the remote OpenSSH server by ensuring namely:

- Secure connection initiation
- Credentials provision
- Negotiation with the OpenSSH server on the encryption method used for the secure communication channel
- Ability to send files securely to and from the OpenSSH server



NOTE

You can use the **ssh** RHEL system role alongside with other system roles that change SSH configuration, for example the Identity Management RHEL system roles. To prevent the configuration from being overwritten, make sure that the **ssh** RHEL system role uses a drop-in directory (default in RHEL 8 and later).

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

--

- name: SSH client configuration

hosts: managed-node-01.example.com

tasks:

 name: Configure ssh clients ansible.builtin.include_role:

name: redhat.rhel_system_roles.ssh

vars:

ssh_user: root

ssh:

Compression: true

GSSAPIAuthentication: no

ControlMaster: auto

ControlPath: ~/.ssh/.cm%C

Host:

- Condition: example

Hostname: server.example.com

User: user1 ssh_ForwardX11: no

The settings specified in the example playbook include the following:

ssh_user: root

Configures the **root** user's SSH client preferences on the managed nodes with certain configuration specifics.

Compression: true

Compression is enabled.

ControlMaster: auto

ControlMaster multiplexing is set to auto.

Host

Creates alias **example** for connecting to the **server.example.com** host as a user called **user1**.

ssh ForwardX11: no

X11 forwarding is disabled.

For details about the role variables and the OpenSSH configuration options used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.ssh/README.md file and the ssh_config(5) manual page on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

 Verify that the managed node has the correct configuration by displaying the SSH configuration file:

cat ~/root/.ssh/config

Ansible managed
Compression yes
ControlMaster auto
ControlPath ~/.ssh/.cm%C
ForwardX11 no
GSSAPIAuthentication no
Host example
Hostname example.com
User user1

- /usr/share/ansible/roles/rhel-system-roles.ssh/README.md file
- /usr/share/doc/rhel-system-roles/ssh/ directory
- ssh_config(5) manual page

CHAPTER 26. MANAGING LOCAL STORAGE BY USING RHEL SYSTEM ROLES

To manage LVM and local file systems (FS) by using Ansible, you can use the **storage** role, which is one of the RHEL system roles available in RHEL 9.

Using the **storage** role enables you to automate administration of file systems on disks and logical volumes on multiple machines and across all versions of RHEL starting with RHEL 7.7.

26.1. CREATING AN XFS FILE SYSTEM ON A BLOCK DEVICE BY USING THE STORAGE RHEL SYSTEM ROLE

The example Ansible playbook uses the storage role to create an XFS file system on a block device using the default parameters. If the file system on the /dev/sdb device or the mount point directory does not exist, the playbook creates them.



NOTE

The **storage** role can create a file system only on an unpartitioned, whole disk or a logical volume (LV). It cannot create the file system on a partition.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

--- name: Manage local storage
hosts: managed-node-01.example.com
tasks:
- name: Create an XFS file system on a block device
ansible.builtin.include_role:
 name: redhat.rhel_system_roles.storage
 vars:
 storage_volumes:
 - name: barefs
 type: disk
 disks:
 - sdb
 fs_type: xfs

The setting specified in the example playbook include the following:

name: barefs

The volume name (*barefs* in the example) is currently arbitrary. The **storage** role identifies the volume by the disk device listed under the **disks** attribute.

fs_type: <file_system>

You can omit the **fs_type** parameter if you want to use the default file system XFS.

disks: <list_of_disks_and_volumes>

A YAML list of disk and LV names. To create the file system on an LV, provide the LVM setup under the **disks** attribute, including the enclosing volume group. For details, see Creating or resizing a logical volume by using the storage RHEL system role.

Do not provide the path to the LV device.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.storage/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

26.2. PERSISTENTLY MOUNTING A FILE SYSTEM BY USING THE STORAGE RHEL SYSTEM ROLE

The example Ansible playbook uses the storage role to persistently mount an existing file system. It ensures that the file system is immediately available and persistently mounted by adding the appropriate entry to the /etc/fstab file. This allows the file system to remain mounted across reboots. If the file system on the /dev/sdb device or the mount point directory does not exist, the playbook creates them.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

--

- name: Manage local storage

hosts: managed-node-01.example.com

tasks:

name: Persistently mount a file system ansible.builtin.include_role:
 name: redhat.rhel_system_roles.storage vars:
 storage_volumes:
 - name: barefs
 type: disk
 disks:
 - sdb
 fs_type: xfs
 mount_point: /mnt/data
 mount_user: somebody
 mount_group: somegroup
 mount_mode: 0755

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.storage/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

26.3. CREATING OR RESIZING A LOGICAL VOLUME BY USING THE STORAGE RHEL SYSTEM ROLE

Use the **storage** role to perform the following tasks:

- To create an LVM logical volume in a volume group consisting of many disks
- To resize an existing file system on LVM
- To express an LVM volume size in percentage of the pool's total size

If the volume group does not exist, the role creates it. If a logical volume exists in the volume group, it is resized if the size does not match what is specified in the playbook.

If you are reducing a logical volume, to prevent data loss you must ensure that the file system on that logical volume is not using the space in the logical volume that is being reduced.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Manage local storage
 hosts: managed-node-01.example.com
 tasks:
  - name: Create logical volume
   ansible.builtin.include role:
    name: redhat.rhel_system_roles.storage
   vars:
    storage_pools:
      - name: myvg
       disks:
        - sda
        - sdb
        - sdc
       volumes:
        - name: mylv
         size: 2G
         fs_type: ext4
         mount_point: /mnt/data
```

The settings specified in the example playbook include the following:

size: <size>

You must specify the size by using units (for example, GiB) or percentage (for example, 60%).

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.storage/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

Verify that specified volume has been created or resized to the requested size:

ansible managed-node-01.example.com -m command -a 'lvs myvg'

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

26.4. ENABLING ONLINE BLOCK DISCARD BY USING THESTORAGE RHEL SYSTEM ROLE

You can mount an XFS file system with the online block discard option to automatically discard unused blocks.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: Manage local storage
hosts: managed-node-01.example.com
tasks:
- name: Enable online block discard
ansible.builtin.include_role:
    name: redhat.rhel_system_roles.storage
vars:
    storage_volumes:
    - name: barefs
    type: disk
    disks:
    - sdb
    fs_type: xfs
    mount_point: /mnt/data
    mount_options: discard
```

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.storage/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Verify that online block discard option is enabled:

ansible managed-node-01.example.com -m command -a 'findmnt /mnt/data'

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

26.5. CREATING AND MOUNTING A FILE SYSTEM BY USING THE STORAGE RHEL SYSTEM ROLE

The example Ansible playbook uses the storage role to create and mount a file system. It ensures that the file system is immediately available and persistently mounted by adding the appropriate entry to the /etc/fstab file. This allows the file system to remain mounted across reboots. If the file system on the /dev/sdb device or the mount point directory does not exist, the playbook creates them.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: Manage local storage
hosts: managed-node-01.example.com
tasks:
-name: Create and mount a file system
ansible.builtin.include_role:
    name: redhat.rhel_system_roles.storage
vars:
    storage_volumes:
    - name: barefs
    type: disk
    disks:
    - sdb
    fs_type: ext4
    fs_label: label-name
    mount_point: /mnt/data
```

The setting specified in the example playbook include the following:

disks: < list of devices>

A YAML list of device names that the role uses when it creates the volume.

fs type: <file system>

Specifies the file system the role should set on the volume. You can select **xfs**, **ext3**, **ext4**, **swap**, or **unformatted**.

label-name: <file_system_label>

Optional: sets the label of the file system.

mount point: <directory>

Optional: if the volume should be automatically mounted, set the **mount_point** variable to the directory to which the volume should be mounted.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.storage/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

26.6. CONFIGURING A RAID VOLUME BY USING THESTORAGE RHEL SYSTEM ROLE

With the **storage** system role, you can configure a RAID volume on RHEL by using Red Hat Ansible Automation Platform and Ansible-Core. Create an Ansible playbook with the parameters to configure a RAID volume to suit your requirements.



WARNING

Device names might change in certain circumstances, for example, when you add a new disk to a system. Therefore, to prevent data loss, use persistent naming attributes in the playbook. For more information about persistent naming attributes, see Persistent naming attributes.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Manage local storage
hosts: managed-node-01.example.com
 tasks:
  - name: Create a RAID on sdd, sde, sdf, and sdg
   ansible.builtin.include role:
    name: redhat.rhel_system_roles.storage
   vars:
    storage_safe_mode: false
    storage volumes:
     - name: data
       type: raid
       disks: [sdd, sde, sdf, sdg]
       raid level: raid0
       raid chunk size: 32 KiB
       mount_point: /mnt/data
       state: present
```

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.storage/README.md file on the control node.

2. Validate the playbook syntax:

 $\$\ ansible-playbook\ --syntax-check\ \sim\!/playbook.yml$

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

Verify that the array was correctly created:

ansible managed-node-01.example.com -m command -a 'mdadm --detail /dev/md/data'

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

26.7. CONFIGURING AN LVM POOL WITH RAID BY USING THESTORAGE RHEL SYSTEM ROLE

With the **storage** system role, you can configure an LVM pool with RAID on RHEL by using Red Hat Ansible Automation Platform. You can set up an Ansible playbook with the available parameters to configure an LVM pool with RAID.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has sudo permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Manage local storage
hosts: managed-node-01.example.com
tasks:
  - name: Configure LVM pool with RAID
   ansible.builtin.include_role:
    name: redhat.rhel_system_roles.storage
   vars:
    storage_safe_mode: false
    storage_pools:
     - name: my_pool
       type: lvm
       disks: [sdh, sdi]
       raid_level: raid1
       volumes:
        - name: my_volume
         size: "1 GiB"
         mount_point: "/mnt/app/shared"
         fs_type: xfs
         state: present
```

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.storage/README.md file on the control node.

2. Validate the playbook syntax:

 $\$\ ansible-playbook\ --syntax-check\ \sim\!/playbook.yml$

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Verify that your pool is on RAID:

ansible managed-node-01.example.com -m command -a 'Isblk'

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory
- Managing RAID

26.8. CONFIGURING A STRIPE SIZE FOR RAID LVM VOLUMES BY USING THE STORAGE RHEL SYSTEM ROLE

With the **storage** system role, you can configure a stripe size for RAID LVM volumes on RHEL by using Red Hat Ansible Automation Platform. You can set up an Ansible playbook with the available parameters to configure an LVM pool with RAID.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Manage local storage
 hosts: managed-node-01.example.com
 tasks:
  - name: Configure stripe size for RAID LVM volumes
   ansible.builtin.include role:
    name: redhat.rhel system roles.storage
   vars:
    storage_safe_mode: false
    storage_pools:
      - name: my_pool
       type: lvm
       disks: [sdh, sdi]
       volumes:
        - name: my_volume
         size: "1 GiB"
         mount_point: "/mnt/app/shared"
         fs_type: xfs
         raid level: raid0
         raid stripe size: "256 KiB"
         state: present
```

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.storage/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Verify that stripe size is set to the required size:

ansible managed-node-01.example.com -m command -a 'lvs -o+stripesize /dev/my_pool/my_volume'

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory
- Managing RAID

26.9. CONFIGURING AN LVM-VDO VOLUME BY USING THESTORAGE RHEL SYSTEM ROLE

You can use the **storage** RHEL system role to create a VDO volume on LVM (LVM-VDO) with enabled compression and deduplication.



NOTE

Because of the **storage** system role use of LVM-VDO, only one volume can be created per pool.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Manage local storage
hosts: managed-node-01.example.com
tasks:
  - name: Create LVM-VDO volume under volume group 'myvg'
   ansible.builtin.include role:
    name: redhat.rhel_system_roles.storage
   vars:
    storage_pools:
     - name: myvg
      disks:
        - /dev/sdb
      volumes:
        - name: mylv1
         compression: true
         deduplication: true
         vdo pool size: 10 GiB
         size: 30 GiB
         mount_point: /mnt/app/shared
```

The settings specified in the example playbook include the following:

vdo pool size: <size>

The actual size that the volume takes on the device. You can specify the size in human-readable format, such as 10 GiB. If you do not specify a unit, it defaults to bytes.

size: <size>

The virtual size of VDO volume.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.storage/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• View the current status of compression and deduplication:

```
$ ansible managed-node-01.example.com -m command -a 'lvs -
o+vdo_compression,vdo_compression_state,vdo_deduplication,vdo_index_state'
LV VG Attr LSize Pool Origin Data% Meta% Move Log Cpy%Sync Convert
VDOCompression VDOCompressionState VDODeduplication VDOIndexState
mylv1 myvg vwi-a-v--- 3.00t vpool0 enabled
online enabled online
```

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

26.10. CREATING A LUKS2 ENCRYPTED VOLUME BY USING THE STORAGE RHEL SYSTEM ROLE

You can use the **storage** role to create and configure a volume encrypted with LUKS by running an Ansible playbook.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

```
$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>
```

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

```
luks_password: <password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Manage local storage
 hosts: managed-node-01.example.com
 vars_files:
  - ~/vault.yml
 tasks:
  - name: Create and configure a volume encrypted with LUKS
   ansible.builtin.include_role:
    name: redhat.rhel_system_roles.storage
   vars:
    storage volumes:
      - name: barefs
       type: disk
       disks:
        - sdb
       fs type: xfs
       fs_label: <label>
```

mount_point: /mnt/data

encryption: true

encryption_password: "{{ luks_password }}"

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.storage/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Verification

1. Find the **luksUUID** value of the LUKS encrypted volume:

ansible managed-node-01.example.com -m command -a 'cryptsetup luksUUID /dev/sdb'

4e4e7970-1822-470e-b55a-e91efe5d0f5c

2. View the encryption status of the volume:

ansible managed-node-01.example.com -m command -a 'cryptsetup status luks-4e4e7970-1822-470e-b55a-e91efe5d0f5c'

/dev/mapper/luks-4e4e7970-1822-470e-b55a-e91efe5d0f5c is active and is in use.

type: LUKS2

cipher: aes-xts-plain64

keysize: 512 bits key location: keyring device: /dev/sdb

.

3. Verify the created LUKS encrypted volume:

ansible managed-node-01.example.com -m command -a 'cryptsetup luksDump /dev/sdb'

LUKS header information

Version: 2 Epoch: 3

Metadata area: 16384 [bytes] Keyslots area: 16744448 [bytes]

UUID: 4e4e7970-1822-470e-b55a-e91efe5d0f5c

Label: (no label)

Subsystem: (no subsystem)

Flags: (no flags)

```
Data segments:
0: crypt
offset: 16777216 [bytes]
length: (whole device)
cipher: aes-xts-plain64
sector: 512 [bytes]
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory
- Encrypting block devices by using LUKS
- Ansible vault

26.11. CREATING SHARED LVM DEVICES USING THESTORAGE RHEL SYSTEM ROLE

You can use the **storage** RHEL system role to create shared LVM devices if you want your multiple systems to access the same storage at the same time.

This can bring the following notable benefits:

- Resource sharing
- Flexibility in managing storage resources
- Simplification of storage management tasks

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- **Ivmlockd** is configured on the managed node. For more information, see Configuring LVM to share SAN disks among multiple machines.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Manage local storage

hosts: managed-node-01.example.com

become: true

tasks:

 name: Create shared LVM device ansible.builtin.include_role:

```
name: redhat.rhel_system_roles.storage
vars:
storage_pools:
- name: vg1
disks: /dev/vdb
type: lvm
shared: true
state: present
volumes:
- name: /v1
size: 4g
mount_point: /opt/test1
storage_safe_mode: false
storage_use_partitions: true
```

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.storage/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

26.12. RESIZING PHYSICAL VOLUMES BY USING THESTORAGE RHEL SYSTEM ROLE

With the **storage** system role, you can resize LVM physical volumes after resizing the underlying storage or disks from outside of the host. For example, you increased the size of a virtual disk and want to use the extra space in an existing LVM.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The size of the underlying block storage has been changed.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Manage local storage

hosts: managed-node-01.example.com

tasks:

- name: Resize LVM PV size ansible.builtin.include role:

name: redhat.rhel_system_roles.storage

vars:

storage_pools:
- name: myvg
disks: ["sdf"]
type: lvm

grow_to_fill: true

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.storage/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

Display the new physical volume size:

\$ ansible managed-node-01.example.com -m command -a 'pvs'
PV VG Fmt Attr PSize PFree
/dev/sdf1 myvg lvm2 a-- 1,99g 1,99g

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory

26.13. CREATING AN ENCRYPTED STRATIS POOL BY USING THE STORAGE RHEL SYSTEM ROLE

To secure your data, you can create an encrypted Stratis pool with the **storage** RHEL system role. In addition to a passphrase, you can use Clevis and Tang or TPM protection as an encryption method.



IMPORTANT

You can configure Stratis encryption only on the entire pool.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You can connect to the Tang server. For more information, see Deploying a Tang server with SELinux in enforcing mode.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

```
$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>
```

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:

```
luks_password: <password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Manage local storage
hosts: managed-node-01.example.com
vars files:
  - ~/vault.yml
tasks:
  - name: Create a new encrypted Stratis pool with Clevis and Tang
   ansible.builtin.include_role:
    name: redhat.rhel system roles.storage
   vars:
    storage_pools:
      - name: mypool
       disks:
         - sdd
         - sde
       type: stratis
       encryption: true
       encryption_password: "{{ luks_password }}"
       encryption_clevis_pin: tang
       encryption_tang_url: tang-server.example.com:7500
```

The settings specified in the example playbook include the following:

encryption_password

Password or passphrase used to unlock the LUKS volumes.

encryption_clevis_pin

Clevis method that you can use to encrypt the created pool. You can use tang and tpm2.

encryption_tang_url

URL of the Tang server.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.storage/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Verification

• Verify that the pool was created with Clevis and Tang configured:

```
$ ansible managed-node-01.example.com -m command -a 'sudo stratis report' ...

"clevis_config": {
    "thp": "j-G4ddvdbVfxpnUbgxlpbe3KutSKmcHttlLAtAkMTNA",
    "url": "tang-server.example.com:7500"
    },
    "clevis_pin": "tang",
    "in_use": true,
    "key_description": "blivet-mypool",
```

- /usr/share/ansible/roles/rhel-system-roles.storage/README.md file
- /usr/share/doc/rhel-system-roles/storage/ directory
- Ansible vault

CHAPTER 27. USING THE SUDO SYSTEM ROLE

As an administrator, you can consistently configure the /etc/sudoers files on multiple systems by using the sudo RHEL system role.

27.1. APPLYING CUSTOM SUDOERS CONFIGURATION BY USING RHEL SYSTEM ROLES

You can use the **sudo** RHEL system role to apply custom **sudoers** configuration on your managed nodes. That way, you can define which users can run which commands on which hosts, with better configuration efficiency and more granular control.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: "Configure sudo"
hosts: managed-node-01.example.com
tasks:
    - name: "Apply custom /etc/sudoers configuration"
    ansible.builtin.include_role:
    name: redhat.rhel_system_roles.sudo
    vars:
    sudo_sudoers_files:
    - path: "/etc/sudoers"
    user_specifications:
    - users:
    - <user_name>
    hosts:
    - <host_name>
    commands:
    - <path to command binary>
```

The settings specified in the playbook include the following:

users

The list of users that the rule applies to.

hosts

The list of hosts that the rule applies to. You can use **ALL** for all hosts.

commands

The list of commands that the rule applies to. You can use **ALL** for all commands. For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhelsystem-roles.sudo/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. On the managed node, verify that the playbook applied the new rules.

```
# cat /etc/sudoers | tail -n1
<user_name> <host_name>= <path_to_command_binary>
```

- /usr/share/ansible/roles/rhel-system-roles.sudo/README.md file
- /usr/share/doc/rhel-system-roles.sudo/sudo/ directory

CHAPTER 28. MANAGING SYSTEMD UNITS BY USING RHEL SYSTEM ROLES

By using the **systemd** RHEL system role, you can automate certain systemd-related tasks and perform them remotely. You can use the role for the following actions:

- Manage services
- Deploy units
- Deploy drop-in files

28.1. MANAGING SERVICES BY USING THE SYSTEMD RHEL SYSTEM ROLE

You can automate and remotely manage systemd units, such as starting or enabling services, by using the **systemd** RHEL system role.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

 Create a playbook file, for example ~/playbook.yml, with the following content. Use only the variables depending on what actions you want to perform.

 name: Managing systemd services hosts: managed-node-01.example.com tasks:

 name: Perform action on systemd units ansible.builtin.include_role: name: redhat.rhel_system_roles.systemd vars:

systemd started units:

- <systemd_unit_1>.service
systemd stopped units:

- <systemd_unit_2>.service
systemd_restarted_units:

- <systemd_unit_3>.service
systemd_reloaded_units:

- <systemd_unit_4>.service
systemd_enabled_units:

- <systemd_unit_5>.service
systemd_disabled_units:

- <systemd_unit_6>.service
systemd_masked_units:

- <systemd_unit_7>.service
systemd_unmasked_units:
- <systemd_unit_8>.service

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.systemd/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.systemd/README.md file
- /usr/share/doc/rhel-system-roles/systemd/ directory

28.2. DEPLOYING SYSTEMD DROP-IN FILES BY USING THE SYSTEMD RHEL SYSTEM ROLE

Systemd applies drop-in files on top of setting it reads for a unit from other locations. Therefore, you can modify unit settings with drop-in files without changing the original unit file. By using the **systemd** RHEL system role, you can automate the process of deploying drop-in files.



IMPORTANT

The role uses the hard-coded file name **99-override.conf** to store drop-in files in /etc/systemd/system/<name>._<unit_type>/. Note that it overrides existing files with this name in the destination directory.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a Jinja2 template with the systemd drop-in file contents. For example, create the ~/sshd.service.conf.j2 file with the following content:

{{ ansible_managed | comment }}
[Unit]
After=
After=network.target sshd-keygen.target network-online.target

This drop-in file specifies the same units in the **After** setting as the original /usr/lib/systemd/system/sshd.service file and, additionally, network-online.target. With this extra target, sshd starts after the network interfaces are actived and have IP addresses assigned. This ensures that sshd can bind to all IP addresses.

Use the **<name>.<unit_type>.conf.j2** convention for the file name. For example, to add a drop-in for the **sshd.service** unit, you must name the file **sshd.service.conf.j2**. Place the file in the same directory as the playbook.

2. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Managing systemd services hosts: managed-node-01.example.com

- name: Deploy an sshd.service systemd drop-in file

ansible.builtin.include_role:

name: redhat.rhel_system_roles.systemd

vars:

systemd dropins:

- sshd.service.conf.j2

The settings specified in the example playbook include the following:

systemd_dropins: < list_of_files>

Specifies the names of the drop-in files to deploy in YAML list format.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.systemd/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Verify that the role placed the drop-in file in the correct location:

ansible managed-node-01.example.com -m command -a 'ls /etc/systemd/system/sshd.service.d/'
99-override.conf

Additional resources

• /usr/share/ansible/roles/rhel-system-roles.systemd/README.md file

/usr/share/doc/rhel-system-roles/systemd/ directory

28.3. DEPLOYING SYSTEMD SYSTEM UNITS BY USING THE SYSTEMD RHEL SYSTEM ROLE

You can create unit files for custom applications, and systemd reads them from the /etc/systemd/system/ directory. By using the systemd RHEL system role, you can automate the deployment of custom unit files.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a Jinja2 template with the custom systemd unit file contents. For example, create the ~/example.service.j2 file with the contents for your service:

```
{{ ansible_managed | comment }}
[Unit]
Description=Example systemd service unit file
[Service]
ExecStart=/bin/true
```

Use the **<name>.<unit_type>.j2** convention for the file name. For example, to create the **example.service** unit, you must name the file **example.service.j2**. Place the file in the same directory as the playbook.

2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
---
- name: Managing systemd services
hosts: managed-node-01.example.com
tasks:
- name: Deploy, enable, and start a custom systemd service
ansible.builtin.include_role:
    name: redhat.rhel_system_roles.systemd
vars:
    systemd_unit_file_templates:
    - example.service.j2
    systemd_enabled_units:
    - example.service
    systemd_started_units:
    - example.service
```

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.systemd/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Verify that the service is enabled and started:

ansible managed-node-01.example.com -m command -a 'systemctl status example.service'

...

example.service - A service for demonstrating purposes
 Loaded: loaded (/etc/systemd/system/example.service; enabled; vendor preset: disabled)
 Active: active (running) since Thu 2024-07-04 15:59:18 CEST; 10min ago

...

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.systemd/README.md file
- /usr/share/doc/rhel-system-roles/systemd/ directory

28.4. DEPLOYING SYSTEMD USER UNITS BY USING THE SYSTEMD RHEL SYSTEM ROLE

You can create per-user unit files for custom applications, and systemd reads them from the /home/<username>/.config/systemd/user/ directory. By using the systemd RHEL system role, you can automate the deployment of custom unit files for individual users.

Prerequisites

- You have prepared the control node and the managed nodes.
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The user you specify in the playbook for the systemd unit exists.

Procedure

1. Create a Jinja2 template with the custom systemd unit file contents. For example, create the ~/example.service.j2 file with the contents for your service:

```
{{ ansible_managed | comment }}
[Unit]
Description=Example systemd service unit file
```

[Service] ExecStart=/bin/true RemainAfterExit=yes

[Install]

WantedBy=multi-user.target

Use the **<name>.<unit_type>.j2** convention for the file name. For example, to create the **example.service** unit, you must name the file **example.service.j2**. Place the file in the same directory as the playbook.

2. Create a playbook file, for example ~/playbook.yml, with the following content:

 name: Managing systemd services hosts: managed-node-01.example.com tasks:

- name: Deploy, enable, and start a custom systemd service for a user

ansible.builtin.include_role:

name: rhel-system-roles.systemd

vars:

systemd_unit_file_templates:

- item: example.service.j2

user: <username>

systemd_enabled_units:

- item: example.service

user: <username>

systemd started units:

item: example.service user: <username>



IMPORTANT

The **systemd** RHEL system role does not create new users, and it returns an error if you specify a non-existent user in the playbook.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.systemd/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Verify that the service is enabled and started:

ansible managed-node-01.example.com -m command -a 'systemctl --user -M <username>@ status example.service'

...

• example.service - Example systemd service unit file

Loaded: loaded (/home/<username>/.config/systemd/user/example.service; enabled;

preset: disabled)

Active: active (exited) since Wed 2025-03-05 13:33:36 CET; 45s ago

••

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.systemd/README.md file
- /usr/share/doc/rhel-system-roles/systemd/ directory

CHAPTER 29. CONFIGURING TIME SYNCHRONIZATION BY USING RHEL SYSTEM ROLES

The Network Time Protocol (NTP) and Precision Time Protocol (PTP) are standards to synchronize the clock of computers over a network. An accurate time synchronization in networks is important because certain services rely on it. For example, Kerberos tolerates only a small time difference between the server and client to prevent replay attacks.

You can set the time service to configure in the **timesync_ntp_provider** variable of a playbook. If you do not set this variable, the role determines the time service based on the following factors:

- On RHEL 8 and later: chronyd
- On RHEL 6 and 7: **chronyd** (default) or, if already installed **ntpd**.

29.1. CONFIGURING TIME SYNCHRONIZATION OVER NTP BY USING THE TIMESYNC RHEL SYSTEM ROLE

The Network Time Protocol (NTP) synchronizes the time of a host with an NTP server over a network. In IT networks, services rely on a correct system time, for example, for security and logging purposes. By using the **timesync** RHEL system role, you can automate the configuration of Red Hat Enterprise Linux NTP clients in your network and keep the time synchronized.



WARNING

The **timesync** RHEL system role replaces the configuration of the specified given or detected provider service on the managed host. Consequently, all settings are lost if they are not specified in the playbook.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

--

 name: Managing time synchronization hosts: managed-node-01.example.com

- name: Configuring NTP with an internal server (preferred) and a public server pool as fallback

ansible.builtin.include_role:
name: redhat.rhel system roles.timesync

vars:

timesync_ntp_servers:

- hostname: time.example.com

trusted: yes prefer: yes iburst: yes

- hostname: 0.rhel.pool.ntp.org

pool: yes iburst: yes

The settings specified in the example playbook include the following:

pool: <yes/no>

Flags a source as an NTP pool rather than an individual host. In this case, the service expects that the name resolves to multiple IP addresses which can change over time.

iburst: yes

Enables fast initial synchronization.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.timesync/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

- Display the details about the time sources:
 - If the managed node runs the **chronyd** service, enter:

• If the managed node runs the **ntpd** service, enter:

```
# ansible managed-node-01.example.com -m command -a 'ntpq -p'
remote refid st t when poll reach delay offset jitter

=======
*time.example.com .PTB. 1 u 2 64 77 23.585 967.902 0.684
```

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.time_sync/README.md file
- /usr/share/doc/rhel-system-roles/time_sync/ directory
- Are the rhel.pool.ntp.org NTP servers supported by Red Hat? (Red Hat Knowledgebase)

29.2. CONFIGURING TIME SYNCHRONIZATION OVER NTP WITH NTS BY USING THE TIMESYNC RHEL SYSTEM ROLE

The Network Time Protocol (NTP) synchronizes the time of a host with an NTP server over a network. By using the Network Time Security (NTS) mechanism, clients establish a TLS-encrypted connection to the server and authenticate NTP packets. In IT networks, services rely on a correct system time, for example, for security and logging purposes. By using the **timesync** RHEL system role, you can automate the configuration of Red Hat Enterprise Linux NTP clients in your network and keep the time synchronized over NTS.

Note that you cannot mix NTS servers with non-NTS servers. In mixed configurations, NTS servers are trusted and clients do not fall back to unauthenticated NTP sources because they can be exploited in man-in-the-middle (MITM) attacks. For further details, see the **authselectmode** parameter description in the **chrony.conf(5)** man page on your system.



WARNING

The **timesync** RHEL system role replaces the configuration of the specified given or detected provider service on the managed host. Consequently, all settings are lost if they are not specified in the playbook.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- The managed nodes use **chronyd**.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Managing time synchronization hosts: managed-node-01.example.com

tasks:

- name: Configuring NTP with NTS-enabled servers

ansible.builtin.include role:

name: redhat.rhel_system_roles.timesync

vars:

timesync_ntp_servers:

- hostname: ptbtime1.ptb.de

nts: yes iburst: yes

The settings specified in the example playbook include the following:

iburst: yes

Enables fast initial synchronization.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.timesync/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

- If the managed node runs the **chronyd** service:
 - 1. Display the details about the time sources:

2. For sources with NTS enabled, display information that is specific to authentication of NTP sources:

Verify that the reported cookies in the **Cook** column is larger than 0.

If the managed node runs the **ntpd** service, enter:

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.time_sync/README.md file
- /usr/share/doc/rhel-system-roles/time_sync/ directory
- Are the rhel.pool.ntp.org NTP servers supported by Red Hat? (Red Hat Knowledgebase)

CHAPTER 30. CONFIGURING A SYSTEM FOR SESSION RECORDING BY USING RHEL SYSTEM ROLES

Use the **tlog** RHEL system role to record and monitor terminal session activities on your managed nodes in an automatic fashion. You can configure the recording to take place per user or user group by means of the **SSSD** service.

The session recording solution in the tlog RHEL system role consists of the following components:

- The tlog utility
- System Security Services Daemon (SSSD)
- Optional: The web console interface

30.1. CONFIGURING SESSION RECORDING FOR INDIVIDUAL USERS BY USING THE TLOG RHEL SYSTEM ROLE

Prepare and apply an Ansible playbook to configure a RHEL system to log session recording data to the **systemd** journal.

With that, you can enable recording the terminal output and input of a specific user during their sessions, when the user logs in on the console, or by SSH.

The playbook installs **tlog-rec-session**, a terminal session I/O logging program, that acts as the login shell for a user. The role creates an SSSD configuration drop file, and this file defines for which users and groups the login shell should be used. Additionally, if the **cockpit** package is installed on the system, the playbook also installs the **cockpit-session-recording** package, which is a **Cockpit** module that allows you to view and play recordings in the web console interface.

Prerequisites

- You have prepared the control node and the managed nodes.
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

--- name: Deploy session recording
hosts: managed-node-01.example.com
tasks:
- name: Enable session recording for specific users
ansible.builtin.include role:

name: redhat.rhel system roles.tlog

vars:

tlog_scope_sssd: some
tlog_users_sssd:
 - <recorded_user>

tlog_scope_sssd: <value>

The **some** value specifies you want to record only certain users and groups, not **all** or **none**.

tlog users sssd: < list_of_users>

A YAML list of users you want to record a session from. Note that the role does not add users if they do not exist.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. Check the SSSD drop-in file's content:

cd /etc/sssd/conf.d/sssd-session-recording.conf

You can see that the file contains the parameters you set in the playbook.

- 2. Log in as a user whose session will be recorded, perform some actions, and log out.
- 3. As the **root** user:
 - a. Display the list of recorded sessions:

```
# journalctl _COMM=tlog-rec-sessio
Nov 12 09:17:30 managed-node-01.example.com -tlog-rec-session[1546]:
{"ver":"2.3","host":"managed-node-
01.example.com","rec":"07418f2b0f334c1696c10cbe6f6f31a6-60a-e4a2","user":"demo-user",...
```

You require the value of the **rec** (recording ID) field in the next step.

Note that the value of the **_COMM** field is shortened due to a 15 character limit.

b. Play back a session:

tlog-play -r journal -M TLOG_REC=<recording_id>

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.tlog/README.md file
- /usr/share/doc/rhel-system-roles/tlog/ directory

30.2. EXCLUDING CERTAIN USERS AND GROUPS FROM SESSION RECORDING BY USING THE TLOG RHEL SYSTEM ROLE

You can use the **tlog_exclude_users_sssd** and **tlog_exclude_groups_sssd** role variables from the **tlog** RHEL system role to exclude users or groups from having their sessions recorded and logged in the **systemd** journal.

The playbook installs **tlog-rec-session**, a terminal session I/O logging program, that acts as the login shell for a user. The role creates an SSSD configuration drop file, and this file defines for which users and groups the login shell should be used. Additionally, if the **cockpit** package is installed on the system, the playbook also installs the **cockpit-session-recording** package, which is a **Cockpit** module that allows you to view and play recordings in the web console interface.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has sudo permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
-name: Deploy session recording excluding users and groups hosts: managed-node-01.example.com tasks:
-name: Exclude users and groups ansible.builtin.include_role:
name: redhat.rhel_system_roles.tlog vars:
tlog_scope_sssd: all tlog_exclude_users_sssd:
- jeff
- james tlog_exclude_groups_sssd:
- admins
```

tlog_scope_sssd: <value>

The value **all** specifies that you want to record all users and groups.

```
tlog_exclude_users_sssd: <user_list>
```

A YAML list of users user names you want to exclude from the session recording.

```
tlog_exclude_groups_sssd: <group_list>
```

A YAML list of groups you want to exclude from the session recording.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

1. Check the SSSD drop-in file's content:

cat /etc/sssd/conf.d/sssd-session-recording.conf

You can see that the file contains the parameters you set in the playbook.

- 2. Log in as a user whose session will be recorded, perform some actions, and log out.
- 3. As the **root** user:
 - a. Display the list of recorded sessions:

```
# journalctl _COMM=tlog-rec-sessio
Nov 12 09:17:30 managed-node-01.example.com -tlog-rec-session[1546]:
{"ver":"2.3","host":"managed-node-
01.example.com","rec":"07418f2b0f334c1696c10cbe6f6f31a6-60a-e4a2","user":"demo-user",...
...
```

You require the value of the **rec** (recording ID) field in the next step.

Note that the value of the **COMM** field is shortened due to a 15 character limit.

b. Play back a session:

tlog-play -r journal -M TLOG_REC=<recording_id>

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.tlog/README.md file
- /usr/share/doc/rhel-system-roles/tlog/ directory

CHAPTER 31. CONFIGURING VPN CONNECTIONS BY USING RHEL SYSTEM ROLES

A VPN is an encrypted connection to securely transmit traffic over untrusted networks. By using the **vpn** RHEL system role, you can automate the process of creating VPN configurations.



NOTE

The **vpn** RHEL system role supports only Libreswan, which is an IPsec implementation, as the VPN provider.

31.1. CREATING A HOST-TO-HOST IPSEC VPN WITH PSK AUTHENTICATION BY USING THE VPN RHEL SYSTEM ROLE

You can use IPsec to directly connect hosts to each other through a VPN. The hosts can use a preshared key (PSK) to authenticate to each other. By using the **vpn** RHEL system role, you can automate the process of creating IPsec host-to-host connections with PSK authentication.

By default, the role creates a tunnel-based VPN.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
-name: Configuring VPN
hosts: managed-node-01.example.com, managed-node-02.example.com
tasks:
    - name: IPsec VPN with PSK authentication
    ansible.builtin.include_role:
        name: redhat.rhel_system_roles.vpn
    vars:
    vpn_connections:
    - hosts:
        managed-node-01.example.com:
        managed-node-02.example.com:
        auth_method: psk
        auto: start
    vpn_manage_firewall: true
    vpn_manage_selinux: true
```

The settings specified in the example playbook include the following:

hosts: <list>

Defines a YAML dictionary with the hosts between which you want to configure a VPN. If an entry is not an Ansible managed node, you must specify its fully-qualified domain name (FQDN) or IP address in the **hostname** parameter, for example:

...
- hosts:
...
external-host.example.com:
hostname: 192.0.2.1

The role configures the VPN connection on each managed node. The connections are named <host_A>-to-<host_B>, for example, managed-node-01.example.com-to-managed-node02.example.com. Note that the role can not configure Libreswan on external (unmanaged)
nodes. You must manually create the configuration on these hosts.

auth method: psk

Enables PSK authentication between the hosts. The role uses **openssI** on the control node to create the PSK.

auto: <start-up_method>

Specifies the start-up method of the connection. Valid values are **add**, **ondemand**, **start**, and **ignore**. For details, see the **ipsec.conf(5)** man page on a system with Libreswan installed. The default value of this variable is null, which means no automatic startup operation.

vpn manage firewall: true

Defines that the role opens the required ports in the **firewalld** service on the managed nodes.

vpn_manage_selinux: true

Defines that the role sets the required SELinux port type on the IPsec ports.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.vpn/README.md file on the control node.

2. Validate the playbook syntax:

\$ ansible-playbook --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Confirm that the connections are successfully started, for example:

ansible managed-node-01.example.com -m shell -a 'ipsec trafficstatus | grep 'managed-node-01.example.com-to-managed-node-02.example.com''

006 #3: "managed-node-01.example.com-to-managed-node-02.example.com", type=ESP, add_time=1741857153, inBytes=38622, outBytes=324626, maxBytes=2^63B, id='@managed-node-02.example.com'

Note that this command only succeeds if the VPN connection is active. If you set the **auto** variable in the playbook to a value other than **start**, you might need to manually activate the connection on the managed nodes first.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.vpn/README.md file
- /usr/share/doc/rhel-system-roles/vpn/ directory

31.2. CREATING A HOST-TO-HOST IPSEC VPN WITH PSK AUTHENTICATION AND SEPARATE DATA AND CONTROL PLANES BY USING THE VPN RHEL SYSTEM ROLE

You can use IPsec to directly connect hosts to each other through a VPN. For example, to enhance the security by minimizing the risk of control messages being intercepted or disrupted, you can configure separate connections for both the data traffic and the control traffic. By using the **vpn** RHEL system role, you can automate the process of creating IPsec host-to-host connections with a separate data and control plane and PSK authentication.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.

Procedure

1. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configuring VPN
 hosts: managed-node-01.example.com, managed-node-02.example.com
 tasks:
  - name: IPsec VPN with PSK authentication
   ansible.builtin.include role:
    name: redhat.rhel system roles.vpn
   vars:
    vpn_connections:
     name: control_plane_vpn
      hosts:
        managed-node-01.example.com:
         hostname: 203.0.113.1 # IP address for the control plane
        managed-node-02.example.com:
         hostname: 198.51.100.2 # IP address for the control plane
      auth method: psk
      auto: start
     name: data_plane_vpn
      hosts:
        managed-node-01.example.com:
         hostname: 10.0.0.1 # IP address for the data plane
        managed-node-02.example.com:
```

hostname: 172.16.0.2 # IP address for the data plane

auth_method: psk

auto: start

vpn_manage_firewall: true vpn manage selinux: true

The settings specified in the example playbook include the following:

hosts: < list>

Defines a YAML dictionary with the hosts between which you want to configure a VPN. The connections are named *<name>-<IP_address_A>-to-<IP_address_B>*, for example **control_plane_vpn-203.0.113.1-to-198.51.100.2**.

The role configures the VPN connection on each managed node. Note that the role can not configure Libreswan on external (unmanaged) nodes. You must manually create the configuration on these hosts.

auth_method: psk

Enables PSK authentication between the hosts. The role uses **openssI** on the control node to create the pre-shared key.

auto: <start-up_method>

Specifies the start-up method of the connection. Valid values are **add**, **ondemand**, **start**, and **ignore**. For details, see the **ipsec.conf(5)** man page on a system with Libreswan installed. The default value of this variable is null, which means no automatic startup operation.

vpn_manage_firewall: true

Defines that the role opens the required ports in the **firewalld** service on the managed nodes.

vpn_manage_selinux: true

Defines that the role sets the required SELinux port type on the IPsec ports.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.vpn/README.md file on the control node.

2. Validate the playbook syntax:

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

3. Run the playbook:

\$ ansible-playbook ~/playbook.yml

Verification

• Confirm that the connections are successfully started, for example:

ansible managed-node-01.example.com -m shell -a 'ipsec trafficstatus | grep "control_plane_vpn-203.0.113.1-to-198.51.100.2"

. . .

006 #3: "control_plane_vpn-203.0.113.1-to-198.51.100.2", type=ESP, add_time=1741860073, inBytes=0, outBytes=0, maxBytes=2^63B, id='198.51.100.2'

Note that this command only succeeds if the VPN connection is active. If you set the **auto** variable in the playbook to a value other than **start**, you might need to manually activate the connection on the managed nodes first.

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.vpn/README.md file
- /usr/share/doc/rhel-system-roles/vpn/ directory

31.3. CREATING AN IPSEC MESH VPN AMONG MULTIPLE HOSTS WITH CERTIFICATE-BASED AUTHENTICATION BY USING THE VPN RHEL SYSTEM ROLE

Libreswan supports creating an opportunistic mesh to establish IPsec connections among a large number of hosts with a single configuration on each host. Adding hosts to the mesh does not require updating the configuration on existing hosts. For enhanced security, use certificate-based authentication in Libreswan.

By using the **vpn** RHEL system role, you can automate configuring a VPN mesh with certificate-based authentication among managed nodes.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You prepared a PKCS #12 file for each managed node:
 - Fach file contains:
 - The certificate authority (CA) certificate
 - The node's private key
 - The node's client certificate
 - The files are named <managed_node_name_as_in_the_inventory>.p12.
 - The files are stored in the same directory as the playbook.

Procedure

Edit the ~/inventory file, and append the cert_name variable:

managed-node-01.example.com cert_name=managed-node-01.example.com managed-node-02.example.com cert_name=managed-node-02.example.com managed-node-03.example.com cert_name=managed-node-03.example.com

Set the **cert_name** variable to the value of the common name (CN) field used in the certificate for each host. Typically, the CN field is set to the fully-qualified domain name (FQDN).

- 2. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

```
$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>
```

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

```
pkcs12_pwd: <password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 3. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Configuring VPN
hosts: managed-node-01.example.com, managed-node-02.example.com, managed-node-
03.example.com
vars files:
  - ~/vault.yml
 tasks:
  - name: Install LibreSwan
   ansible.builtin.package:
    name: libreswan
     state: present
  - name: Identify the path to IPsec NSS database
   ansible.builtin.set_fact:
     nss_db_dir: "{{ '/etc/ipsec.d/' if
      ansible_distribution in ['CentOS', 'RedHat']
      and ansible distribution major version is version('8', '=')
      else '/var/lib/ipsec/nss/' }}"
  - name: Locate IPsec NSS database files
   ansible.builtin.find:
    paths: "{{ nss_db_dir }}"
    patterns: "*.db"
   register: db_files
  - name: Remove IPsec NSS database files
   ansible.builtin.file:
    path: "{{ item.path }}"
    state: absent
   loop: "{{ db_files.files }}"
   when: db files.matched > 0
  - name: Initialize IPsec NSS database
   ansible.builtin.command:
    cmd: ipsec initnss
  - name: Copy PKCS #12 file to the managed node
   ansible.builtin.copy:
     src: "~/{{ inventory_hostname }}.p12"
```

```
dest: "/etc/ipsec.d/{{ inventory_hostname }}.p12"
     mode: 0600
  - name: Import PKCS #12 file in IPsec NSS database
   ansible.builtin.shell:
     cmd: 'pk12util -d {{ nss_db_dir }} -i /etc/ipsec.d/{{ inventory_hostname }}.p12 -W "{{
pkcs12 pwd }}""
  - name: Remove PKCS #12 file
    ansible.builtin.file:
     path: "/etc/ipsec.d/{{ inventory hostname }}.p12"
     state: absent

    name: Opportunistic mesh IPsec VPN with certificate-based authentication

    ansible.builtin.include_role:
     name: redhat.rhel_system_roles.vpn
   vars:
     vpn connections:
      - opportunistic: true
       auth method: cert
       policies:
         - policy: private
          cidr: default
         - policy: private
          cidr: 192.0.2.0/24
         - policy: clear
          cidr: 192.0.2.1/32
     vpn_manage_firewall: true
     vpn_manage_selinux: true
```

The settings specified in the example playbook include the following:

opportunistic: true

Enables an opportunistic mesh among multiple hosts. The **policies** variable defines for which subnets and hosts traffic must or or can be encrypted and which of them should continue using clear text connections.

auth_method: cert

Enables certificate-based authentication. This requires that you specified the nickname of each managed node's certificate in the inventory.

policies: < list_of_policies>

Defines the Libreswan policies in YAML list format.

The default policy is **private-or-clear**. To change it to **private**, the above playbook contains an according policy for the default **cidr** entry.

To prevent a loss of the SSH connection during the execution of the playbook if the Ansible control node is in the same IP subnet as the managed nodes, add a **clear** policy for the control node's IP address. For example, if the mesh should be configured for the **192.0.2.0/24** subnet and the control node uses the IP address **192.0.2.1**, you require a **clear** policy for **192.0.2.1/32** as shown in the playbook.

For details about policies, see the **ipsec.conf(5)** man page on a system with Libreswan installed.

vpn_manage_firewall: true

Defines that the role opens the required ports in the **firewalld** service on the managed nodes.

vpn_manage_selinux: true

Defines that the role sets the required SELinux port type on the IPsec ports.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/rhel-system-roles.vpn/README.md file on the control node.

4. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

5. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Verification

- 1. On a node in the mesh, ping another node to activate the connection:
 - [root@managed-node-01]# ping managed-node-02.example.com
- 2. Confirm that the connections is active:

[root@managed-node-01]# **ipsec trafficstatus** 006 #2: "private#192.0.2.0/24"[1] ...192.0.2.2, type=ESP, add_time=1741938929, inBytes=372408, outBytes=545728, maxBytes=2^63B, id='CN=managed-node-02.example.com'

Additional resources

- /usr/share/ansible/roles/rhel-system-roles.vpn/README.md file
- /usr/share/doc/rhel-system-roles/vpn/ directory

CHAPTER 32. CONFIGURING MICROSOFT SQL SERVER BY USING RHEL SYSTEM ROLES

You can use the **microsoft.sql.server** Ansible system role to automate the installation and management of Microsoft SQL Server. This role also optimizes Red Hat Enterprise Linux (RHEL) to improve the performance and throughput of SQL Server by applying the **mssql** TuneD profile.



NOTE

During the installation, the role adds repositories for SQL Server and related packages to the managed hosts. Packages in these repositories are provided, maintained, and hosted by Microsoft.

32.1. INSTALLING AND CONFIGURING SQL SERVER WITH AN EXISTING TLS CERTIFICATE BY USING THE MICROSOFT.SQL.SERVER ANSIBLE SYSTEM ROLE

If your application requires a Microsoft SQL Server database, you can configure SQL Server with TLS encryption to enable secure communication between the application and the database. By using the **microsoft.sql.server** Ansible system role, you can automate this process and remotely install and configure SQL Server with TLS encryption. In the playbook, you can use an existing private key and a TLS certificate that was issued by a certificate authority (CA).

Depending on the RHEL version on the managed host, the version of SQL Server that you can install differs:

- RHEL 7.9: SQL Server 2017 and 2019
- RHEL 8: SQL Server 2017, 2019, and 2022
- RHEL 9.4 and later: SQL Server 2022

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You installed the **ansible-collection-microsoft-sql** package or the **microsoft.sql** collection on the control node.
- The managed node has 2 GB or more RAM installed.
- The managed node uses one of the following versions: RHEL 7.9, RHEL 8, RHEL 9.4 or later.
- You stored the certificate in the **sql_crt.pem** file in the same directory as the playbook.
- You stored the private key in the **sql_cert.key** file in the same directory as the playbook.
- SQL clients trust the CA that issued the certificate.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

```
$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>
```

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

```
sa_pwd: <sa_password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

```
- name: Installing and configuring Microsoft SQL Server
hosts: managed-node-01.example.com
 vars files:
  - ~/vault.yml
 tasks:
  - name: SQL Server with an existing private key and certificate
   ansible.builtin.include role:
    name: microsoft.sql.server
   vars:
    mssql_accept_microsoft_odbc_driver_for_sql_server_eula: true
    mssql_accept_microsoft_cli_utilities_for_sql_server_eula: true
    mssql_accept_microsoft_sql_server_standard_eula: true
    mssql_version: 2022
    mssql password: "{{ sa pwd }}"
    mssql edition: Developer
    mssql_tcp_port: 1433
    mssql_manage_firewall: true
    mssql tls enable: true
    mssql_tls_self_sign: false
    mssql_tls_cert: sql_crt.pem
    mssql_tls_private_key: sql_cert.key
    mssql tls version: 1.2
    mssql_tls_force: true
```

The settings specified in the example playbook include the following:

mssql_tls_enable: true

Enables TLS encryption. If you enable this setting, you must also define **mssql_tls_cert** and **mssql_tls_private_key**.

```
mssql_tls_self_sign: false
```

Indicates whether the certificates that you use are self-signed or not. Based on this setting, the role decides whether to run the **sqlcmd** command with the **-C** argument to trust certificates.

```
mssql_tls_cert: <path>
```

Sets the path to the TLS certificate stored on the control node. The role copies this file to the /etc/pki/tls/certs/ directory on the managed node.

mssql_tls_private_key: <path>

Sets the path to the TLS private key on the control node. The role copies this file to the /etc/pki/tls/private/ directory on the managed node.

mssql_tls_force: true

Replaces the TLS certificate and private key in their destination directories if they exist.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/microsoft.sql-server/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Verification

• On the SQL Server host, use the **sqlcmd** utility with the **-N** parameter to establish an encrypted connection to SQL server and run a query, for example:

\$ /opt/mssql-tools/bin/sqlcmd -N -S server.example.com -U "sa" -P <sa_password> -Q
'SELECT SYSTEM_USER'

If the command succeeds, the connection to the server was TLS encrypted.

Additional resources

- /usr/share/ansible/roles/microsoft.sql-server/README.md file
- Ansible vault

32.2. INSTALLING AND CONFIGURING SQL SERVER WITH A TLS CERTIFICATE ISSUED FROM IDM BY USING THE MICROSOFT.SQL.SERVER ANSIBLE SYSTEM ROLE

If your application requires a Microsoft SQL Server database, you can configure SQL Server with TLS encryption to enable secure communication between the application and the database. If the SQL Server host is a member in a Red Hat Enterprise Linux Identity Management (IdM) domain, the **certmonger** service can manage the certificate request and future renewals.

By using the **microsoft.sql.server** Ansible system role, you can automate this process. You can remotely install and configure SQL Server with TLS encryption, and the **microsoft.sql.server** role uses the **certificate** Ansible system role to configure **certmonger** and request a certificate from IdM.

Depending on the RHEL version on the managed host, the version of SQL Server that you can install differs:

- RHEL 7.9: SQL Server 2017 and 2019
- RHEL 8: SQL Server 2017, 2019, and 2022
- RHEL 9.4 and later: SQL Server 2022

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You installed the **ansible-collection-microsoft-sql** package or the **microsoft.sql** collection on the control node.
- The managed node has 2 GB or more RAM installed.
- The managed node uses one of the following versions: RHEL 7.9, RHEL 8, RHEL 9.4 or later.
- You enrolled the managed node in a Red Hat Enterprise Linux Identity Management (IdM) domain.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>

- b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<**key>: **<**value> format:
 - sa_pwd: <sa_password>
- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

 name: Installing and configuring Microsoft SQL Server hosts: managed-node-01.example.com vars_files:

- ~/vault.yml

tasks:

 name: SQL Server with certificates issued by Red Hat IdM ansible.builtin.include_role: name: microsoft.sql.server

vars:

```
mssql_accept_microsoft_odbc_driver_for_sql_server_eula: true
mssql_accept_microsoft_cli_utilities_for_sql_server_eula: true
mssql_accept_microsoft_sql_server_standard_eula: true

mssql_version: 2022
mssql_password: "{{ sa_pwd }}"
mssql_edition: Developer
mssql_tcp_port: 1433
mssql_manage_firewall: true

mssql_tls_enable: true
mssql_tls_certificates:
    - name: sql_cert
    dns: server.example.com
    ca: ipa
```

The settings specified in the example playbook include the following:

mssql_tls_enable: true

Enables TLS encryption. If you enable this setting, you must also define **mssql_tls_certificates**.

mssql_tls_certificates

A list of YAML dictionaries with settings for the **certificate** role.

name: <file name>

Defines the base name of the certificate and private key. The **certificate** role stores the certificate in the /etc/pki/tls/certs/<file_name>.crt and the private key in the /etc/pki/tls/private/<file_name>.key file.

dns: <hostname_or_list_of_hostnames>

Sets the hostnames that the Subject Alternative Names (SAN) field in the issued certificate contains. You can use a wildcard (*) or specify multiple names in YAML list format.

ca: <ca_type>

Defines how the **certificate** role requests the certificate. Set the variable to **ipa** if the host is enrolled in an IdM domain or **self-sign** to request a self-signed certificate.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/microsoft.sql-server/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Verification

• On the SQL Server host, use the **sqlcmd** utility with the **-N** parameter to establish an encrypted connection to SQL server and run a query, for example:

\$ /opt/mssql-tools/bin/sqlcmd -N -S server.example.com -U "sa" -P <sa_password> -Q 'SELECT SYSTEM USER'

If the command succeeds, the connection to the server was TLS encrypted.

Additional resources

- /usr/share/ansible/roles/microsoft.sql-server/README.md file
- Requesting certificates by using RHEL system roles
- Ansible vault

32.3. INSTALLING AND CONFIGURING SQL SERVER WITH CUSTOM STORAGE PATHS BY USING THE MICROSOFT.SQL.SERVER ANSIBLE SYSTEM ROLE

When you use the **microsoft.sql.server** Ansible system role to install and configure a new SQL Server, you can customize the paths and modes of the data and log directories. For example, configure custom paths if you want to store databases and log files in a different directory with more storage.



IMPORTANT

If you change the data or log path and re-run the playbook, the previously-used directories and all their content remains at the original path. Only new databases and logs are stored in the new location.

Table 32.1. SQL Server default settings for data and log directories

| Туре | Directory | Mode | Owner | Group |
|------|----------------------|------|-------|-------|
| Data | /var/opt/mssql/data/ | [a] | mssql | mssql |
| Logs | /var/opt/mssql/los/ | [a] | mssql | mssql |

[a] If the directory exists, the role preserves the mode. If the directory does not exist, the role applies the default **umask** on the managed node when it creates the directory.

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.
- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You installed the **ansible-collection-microsoft-sql** package or the **microsoft.sql** collection on the control node.
- The managed node has 2 GB or more RAM installed.

• The managed node uses one of the following versions: RHEL 7.9, RHEL 8, RHEL 9.4 or later.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

```
$ ansible-vault create ~/vault.yml
New Vault password: <vault_password>
Confirm New Vault password: <vault_password>
```

b. After the **ansible-vault create** command opens an editor, enter the sensitive data in the **<key>: <value>** format:

```
sa_pwd: <sa_password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Edit an existing playbook file, for example ~/playbook.yml, and add the storage and log-related variables:

```
- name: Installing and configuring Microsoft SQL Server
hosts: managed-node-01.example.com
vars_files:
  - ~/vault.yml
tasks:
  - name: SQL Server with custom storage paths
   ansible.builtin.include_role:
    name: microsoft.sql.server
   vars:
    mssql accept microsoft odbc driver for sql server eula: true
    mssql_accept_microsoft_cli_utilities_for_sql_server_eula: true
    mssql_accept_microsoft_sql_server_standard_eula: true
    mssql version: 2022
    mssql_password: "{{ sa_pwd }}"
    mssql_edition: Developer
    mssql_tcp_port: 1433
    mssql_manage_firewall: true
    mssql_datadir: /var/lib/mssql/
    mssql_datadir_mode: '0700'
    mssql logdir: /var/log/mssql/
    mssql_logdir_mode: '0700'
```

The settings specified in the example playbook include the following:

mssql_datadir_mode and mssql_logdir_mode

Set the permission modes. Specify the value in single quotes to ensure that the role parses the value as a string and not as an octal number.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/microsoft.sql-server/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

Verification

1. Display the mode of the data directory:

\$ ansible managed-node-01.example.com -m command -a 'ls -ld /var/lib/mssql/' drwx-----. 12 mssql mssql 4096 Jul 3 13:53 /var/lib/mssql/

2. Display the mode of the log directory:

\$ ansible managed-node-01.example.com -m command -a 'ls -ld /var/log/mssql/' drwx-----. 12 mssql mssql 4096 Jul 3 13:53 /var/log/mssql/

Additional resources

- /usr/share/ansible/roles/microsoft.sql-server/README.md file
- Ansible vault

32.4. INSTALLING AND CONFIGURING SQL SERVER WITH AD INTEGRATION BY USING THE MICROSOFT.SQL.SERVER ANSIBLE SYSTEM ROLF

You can integrate Microsoft SQL Server into an Active Directory (AD) to enable AD users to authenticate to SQL Server. By using the **microsoft.sql.server** Ansible system role, you can automate this process and remotely install and configure SQL Server accordingly. Note that you must still perform manual steps in AD and SQL Server after you run the playbook.

Depending on the RHEL version on the managed host, the version of SQL Server that you can install differs:

- RHFI 7.9: SQL Server 2017 and 2019
- RHEL 8: SQL Server 2017, 2019, and 2022
- RHEL 9.4 and later: SQL Server 2022

Prerequisites

- You have prepared the control node and the managed nodes .
- You are logged in to the control node as a user who can run playbooks on the managed nodes.

- The account you use to connect to the managed nodes has **sudo** permissions on them.
- You installed the **ansible-collection-microsoft-sql** package or the **microsoft.sql** collection on the control node.
- The managed node has 2 GB or more RAM installed.
- The managed node uses one of the following versions: RHEL 7.9, RHEL 8, RHEL 9.4 or later.
- An AD domain is available in the network.
- A reverse DNS (RDNS) zone exists in AD, and it contains Pointer (PTR) resource records for each AD domain controller (DC).
- The managed host's network settings use an AD DNS server.
- The managed host can resolve the following DNS entries:
 - Both the hostnames and the fully-qualified domain names (FQDNs) of the AD DCs resolve to their IP addresses.
 - The IP addresses of the AD DCs resolve to their FQDNs.

Procedure

- 1. Store your sensitive variables in an encrypted file:
 - a. Create the vault:

\$ ansible-vault create ~/vault.yml

New Vault password: <vault_password>

Confirm New Vault password: <vault_password>

b. After the ansible-vault create command opens an editor, enter the sensitive data in the <key>: <value> format:

```
sa_pwd: <sa_password>
sql_pwd: <SQL_AD_password>
ad admin pwd: <AD admin password>
```

- c. Save the changes, and close the editor. Ansible encrypts the data in the vault.
- 2. Create a playbook file, for example ~/playbook.yml, with the following content:

- name: Installing and configuring Microsoft SQL Server hosts: managed-node-01.example.com vars files: - ~/vault.yml

tasks:

- name: SQL Server with AD authentication ansible.builtin.include_role: name: microsoft.sql.server vars: mssql_accept_microsoft_odbc_driver_for_sql_server_eula: true

mssql_accept_microsoft_cli_utilities_for_sql_server_eula: true

```
mssql_accept_microsoft_sql_server_standard_eula: true

mssql_version: 2022
mssql_password: "{{ sa_pwd }}"
mssql_edition: Developer
mssql_tcp_port: 1433
mssql_manage_firewall: true

mssql_ad_configure: true
mssql_ad_join: true
mssql_ad_join: true
mssql_ad_sql_user: sqluser
mssql_ad_sql_user: sqluser
mssql_ad_sql_password: "{{ sql_pwd }}"
ad_integration_realm: ad.example.com
ad_integration_user: Administrator
ad_integration_password: "{{ ad_admin_pwd }}"
```

The settings specified in the example playbook include the following:

mssql_ad_configure: true

Enables authentication against AD.

mssql ad join: true

Uses the **ad_integration** RHEL system role to join the managed node to AD. The role uses the settings from the **ad_integration_realm**, **ad_integration_user**, and **ad_integration_password** variables to join the domain.

mssql_ad_sql_user: <username>

Sets the name of an AD account that the role should create in AD and SQL Server for administration purposes.

ad_integration_user: <AD_user>

Sets the name of an AD user with privileges to join machines to the domain and to create the AD user specified in **mssql_ad_sql_user**.

For details about all variables used in the playbook, see the /usr/share/ansible/roles/microsoft.sql-server/README.md file on the control node.

3. Validate the playbook syntax:

\$ ansible-playbook --ask-vault-pass --syntax-check ~/playbook.yml

Note that this command only validates the syntax and does not protect against a wrong but valid configuration.

4. Run the playbook:

\$ ansible-playbook --ask-vault-pass ~/playbook.yml

- 5. Authorize AD users that should be able to authenticate to SQL Server. On the SQL Server, perform the following steps:
 - a. Obtain a Kerberos ticket for the **Administrator** user:

$\$\ kinit\ Administrator@ad.example.com$

b. Authorize an AD user:

$\$ /opt/mssql-tools/bin/sqlcmd -S. -Q 'CREATE LOGIN [AD\<AD_user>] FROM WINDOWS:'

Repeat this step for every AD user who should be able to access SQL Server.

Verification

- On the managed node that runs SQL Server:
 - a. Obtain a Kerberos ticket for an AD user:
 - \$ kinit *<AD_user>*@ad.example.com
 - b. Use the **sqlcmd** utility to log in to SQL Server and run a query, for example:
 - \$ /opt/mssql-tools/bin/sqlcmd -S. -Q 'SELECT SYSTEM_USER'

Additional resources

- /usr/share/ansible/roles/microsoft.sql-server/README.md file
- Ansible vault