

- 1. Download the package from https://github.com/igolinin/DMXtools/blob/main/DMXtools/DMXtools.unitypackage
- 2. Open Unity HDRP project (or create a new one).
- Select Menu/Assets/Import Package/Custom Package and browse to DMXtools.unitypackage. Click "Import".
- 4. Navigate to Menu/Edit/Project Settings/Player and set
 - a. Api Compatibility Level: .Net 4.x,
- 5. Navigate to Menu/Edit/Project Settings/Editor and set
 - a. Enter Play Mode Settings: true
 - b. Reload Domain: falsec. Reload Scene: false



6. Navigate to Menu/Window/ArtNet/Console this will open console window



- 7. User can select one of 8 built-in art-net universes or choose all(heads only)
- 8. Selected universe can be marked as DMX out universe to send data of this universe to the real DMX fixtures connected via DMX usb dongle(only Enntec usb pro MKii tested, but should also work with open DMX dongle as well).
 - a. When universe is enabled as "DMX out universe", option "serial DMX" becomes visible.
 - b. USB DMX device must be connected to the PC before "serial DMX" is enabled.
 - c. Only one physical DMX universe is supported.

- 9. To get familiar with systems features please open demo scene "Playground"
- 10. Number of virtual DMX fixtures are already placed in the scene. By selecting the universe and choosing the heads view user can
 - a. "Find heads", which detects all the universe's DMX fixtures that are present in the scene. The same button can be used in case of the error which might occur when exiting play mode.
 - b. "Connect heads" makes sure that all the heads are connected to DMX data object.
 - c. "Reset selection" resets the selection of the heads.
 - d. "Blackout" clears all the output.
- 11. When one or more heads are selected, the side panel displays sliders for the fixture's common attributes.
- 12. Each universe including DMX out universe can be set to "receive ArtNet" in this case art-net data is received from the external art-net controller. This feature only works real time in the play mode, but pressing "Update art-net data" can update virtual fixtures output after the latest received art-net data while in edit mode.
- 13. Cue the snapshot of all the DMX data values for all universes can be saved with basic cue editor.
- 14. Navigate to Menu/Window/ArtNet/Cue Editor.
- 15. To save the cue simply enter the cue name and click "Record Cue" button.
- 16. To remove the cue click "Remove Selected"
- 17. To save the entire cue stack click "Save Stack". The stack is saved on a per scene basis.
- 18. To play back the cues enable the "Playback" option. It is recommended to reset selection and black out on the console before beginning the playback.
- 19. To add more fixtures to the scene drag and drop prefabs from Assets/Prefabs/Lights/HDRP.
 - a. Set universe and address numbers in the inspector.
 - b. Set address number in console.
 - c. Press "Find heads" if any errors.