DD2D - Matryushka approach 0

Generated by Doxygen 1.8.3.1

Tue May 28 2013 10:41:49

Contents

1	Mair	n Page			1
2	Hier	archica	Index		3
	2.1	Class I	Hierarchy		3
3	Data	Struct	ure Index		5
	3.1	Data S	tructures		5
4	File	Index			7
	4.1	File Lis	st		7
5	Data	Struct	ure Docun	nentation	9
	5.1	Defect	Class Ref	erence	9
		5.1.1	Detailed	Description	10
		5.1.2	Construc	tor & Destructor Documentation	11
			5.1.2.1	Defect	11
			5.1.2.2	Defect	11
			5.1.2.3	Defect	11
		5.1.3	Member	Function Documentation	11
			5.1.3.1	getPosition	11
			5.1.3.2	getPosition	12
			5.1.3.3	getX	12
			5.1.3.4	getY	12
			5.1.3.5	getZ	13
			5.1.3.6	setPosition	13
			5.1.3.7	setPosition	13
			5.1.3.8	setPosition	13
			5.1.3.9	setX	14
			5.1.3.10	setY	14
			5.1.3.11	setZ	14
			5.1.3.12	stressField	14
		5.1.4	Field Doo	cumentation	15
			E 1 / 1	200	15

ii CONTENTS

5.2	Disloca	ation Class Reference
	5.2.1	Detailed Description
	5.2.2	Constructor & Destructor Documentation
		5.2.2.1 Dislocation
		5.2.2.2 Dislocation
	5.2.3	Member Function Documentation
		5.2.3.1 calculateRotationMatrix
		5.2.3.2 getBurgers
		5.2.3.3 getLineVector
		5.2.3.4 getPosition
		5.2.3.5 getPosition
		5.2.3.6 getX
		5.2.3.7 getY
		5.2.3.8 getZ
		5.2.3.9 setBurgers
		5.2.3.10 setLineVector
		5.2.3.11 setMobile
		5.2.3.12 setPinned
		5.2.3.13 setPosition
		5.2.3.14 setPosition
		5.2.3.15 setPosition
		5.2.3.16 setX
		5.2.3.17 setY
		5.2.3.18 setZ
		5.2.3.19 stressField
		5.2.3.20 stressFieldLocal
	5.2.4	Field Documentation
		5.2.4.1 bmag
		5.2.4.2 bvec
		5.2.4.3 lvec
		5.2.4.4 mobile
		5.2.4.5 pos
		5.2.4.6 rotationMatrix
5.3	Disloca	ationSource Class Reference
	5.3.1	Detailed Description
	5.3.2	Constructor & Destructor Documentation
		5.3.2.1 DislocationSource
		5.3.2.2 DislocationSource
	5.3.3	Member Function Documentation
		5.3.3.1 dipoleNucleationLength

CONTENTS

		5.3.3.2	getBurgers	29
		5.3.3.3	getBurgersMag	30
		5.3.3.4	getIterationCount	30
		5.3.3.5	getLineVector	30
		5.3.3.6	getNumIterations	30
		5.3.3.7	getPosition	31
		5.3.3.8	getPosition	31
		5.3.3.9	getTauCritical	31
		5.3.3.10	getX	31
		5.3.3.11	getY	32
		5.3.3.12	getZ	32
		5.3.3.13	ifEmitDipole	32
		5.3.3.14	incrementIterationCount	32
		5.3.3.15	resetIterationCounter	33
		5.3.3.16	setBurgers	33
		5.3.3.17	setBurgersMagnitude	33
		5.3.3.18	setLineVector	33
		5.3.3.19	setNumIterations	33
		5.3.3.20	setPosition	34
		5.3.3.21	setPosition	34
		5.3.3.22	setPosition	34
		5.3.3.23	setTauCritical	35
		5.3.3.24	setX	35
		5.3.3.25	setY	35
		5.3.3.26	setZ	35
		5.3.3.27	stressField	36
	5.3.4	Field Doo	sumentation	36
		5.3.4.1	bmag	36
		5.3.4.2	bvec	36
		5.3.4.3	countIterations	36
		5.3.4.4	lvec	37
		5.3.4.5	mobile	37
		5.3.4.6	nlterations	37
		5.3.4.7	pos	37
		5.3.4.8	rotationMatrix	37
		5.3.4.9	tauCritical	37
5.4	Matrix3	3 Class R	eference	37
	5.4.1	Detailed I	Description	39
	5.4.2	Construc	tor & Destructor Documentation	39
		5.4.2.1	Matrix33	39

iv CONTENTS

		5.4.2.2 Matrix33			 	 39
		5.4.2.3 Matrix33			 	 40
		5.4.2.4 Matrix33			 	 40
	5.4.3	Member Function D	ocumentation		 	 40
		5.4.3.1 adjugate			 	 40
		5.4.3.2 getValue			 	 41
		5.4.3.3 operator!			 	 41
		5.4.3.4 operator	·		 	 42
		5.4.3.5 operator			 	 42
		5.4.3.6 operator			 	 43
		5.4.3.7 operator	=		 	 43
		5.4.3.8 operator	=		 	 43
		5.4.3.9 operator-			 	 44
		5.4.3.10 operator-	=		 	 44
		5.4.3.11 operator-			 	 44
		5.4.3.12 operator-	=		 	 45
		5.4.3.13 operator/	·		 	 45
		5.4.3.14 operator	٠		 	 46
		5.4.3.15 setValue			 	 46
	5.4.4	Field Documentatio	n		 	 46
		5.4.4.1 x			 	 46
5.5	Rotatio	nMatrix Class Refere	ence		 	 47
	5.5.1	Detailed Description	1		 	 48
	5.5.2	Constructor & Destr	ructor Documentation	n	 	 48
		5.5.2.1 Rotation	Matrix		 	 48
		5.5.2.2 Rotation	Matrix		 	 49
	5.5.3	Member Function D	ocumentation		 	 49
		5.5.3.1 adjugate			 	 49
		5.5.3.2 getValue			 	 49
		5.5.3.3 operator!			 	 50
		5.5.3.4 operator	•		 	 50
		5.5.3.5 operator	•		 	 51
		5.5.3.6 operator			 	 51
		5.5.3.7 operator	=		 	 52
		5.5.3.8 operator	=		 	 52
		5.5.3.9 operator-	•		 	 52
		5.5.3.10 operator-	=		 	 53
		5.5.3.11 operator-			 	 53
		5.5.3.12 operator-	=		 	 53
		5.5.3.13 operator/	`		 	 54

CONTENTS

		5.5.3.14 operator~
		5.5.3.15 setValue
	5.5.4	Field Documentation
		5.5.4.1 x
5.6	Strain	Class Reference
	5.6.1	Detailed Description
	5.6.2	Constructor & Destructor Documentation
		5.6.2.1 Strain
		5.6.2.2 Strain
	5.6.3	Member Function Documentation
		5.6.3.1 adjugate
		5.6.3.2 getPrincipalStrains
		5.6.3.3 getShearStrains
		5.6.3.4 getValue
		5.6.3.5 operator!
		5.6.3.6 operator*
		5.6.3.7 operator*
		5.6.3.8 operator*
		5.6.3.9 operator*=
		5.6.3.10 operator*=
		5.6.3.11 operator+
		5.6.3.12 operator+=
		5.6.3.13 operator
		5.6.3.14 operator-=
		5.6.3.15 operator [^]
		5.6.3.16 operator \sim
		5.6.3.17 populateMatrix
		5.6.3.18 rotate
		5.6.3.19 setValue
	5.6.4	Field Documentation
		5.6.4.1 principalStrains
		5.6.4.2 shearStrains
		5.6.4.3 x
5.7	Stress	Class Reference
	5.7.1	Detailed Description
	5.7.2	Constructor & Destructor Documentation
		5.7.2.1 Stress
		5.7.2.2 Stress
	5.7.3	Member Function Documentation
		5.7.3.1 adjugate

<u>vi</u> CONTENTS

		5.7.3.2	getPrincipalStresses	69
		5.7.3.3	getShearStresses	69
		5.7.3.4	getValue	69
		5.7.3.5	operator!	70
		5.7.3.6	operator*	70
		5.7.3.7	operator*	71
		5.7.3.8	operator*	71
		5.7.3.9	operator*=	72
		5.7.3.10	operator*=	72
		5.7.3.11	operator+	72
		5.7.3.12	operator+=	73
		5.7.3.13	operator	73
		5.7.3.14	operator-=	73
		5.7.3.15	$operator^\wedge \ldots \ldots \ldots \ldots$	74
		5.7.3.16	operator~	74
		5.7.3.17	populateMatrix	74
		5.7.3.18	rotate	75
		5.7.3.19	setValue	75
	5.7.4	Field Doo	cumentation	75
		5.7.4.1	principalStresses	75
		5.7.4.2	shearStresses	75
		5.7.4.3	$x \ \dots $	76
5.8	Vector	3d Class F	Reference	76
	5.8.1	Detailed	Description	77
	5.8.2	Construc	tor & Destructor Documentation	77
		5.8.2.1	Vector3d	77
		5.8.2.2	Vector3d	77
		5.8.2.3	Vector3d	78
	5.8.3	Member	Function Documentation	78
		5.8.3.1	getValue	78
		5.8.3.2	getVector	78
		5.8.3.3	magnitude	79
		5.8.3.4	normalize	79
		5.8.3.5	operator*	79
		5.8.3.6	operator*	80
		5.8.3.7	operator*=	80
		5.8.3.8	operator+	80
		5.8.3.9	operator+=	81
		5.8.3.10	operator	81
		5.8.3.11	operator-=	81

CONTENTS vii

			5.8.3.12	$operator^\wedge \ldots \ldots \ldots \ldots$	82
			5.8.3.13	$operator^{\wedge} = \dots $	82
			5.8.3.14	setValue	82
			5.8.3.15	setVector	83
			5.8.3.16	sum	83
		5.8.4	Field Doo	cumentation	83
			5.8.4.1	x	83
6	File	Docume	entation		85
	6.1			Reference	85
		6.1.1		Description	86
		6.1.2		efinition Documentation	86
		•	6.1.2.1	PI	86
			6.1.2.2	SQRT2	86
			6.1.2.3	SQRT3	86
			6.1.2.4	SQRT5	86
	6.2	defect		eference	86
	0.2	6.2.1		Description	87
	6.3	_		erence	88
	0.0	6.3.1		Description	89
	6.4			ile Reference	89
		6.4.1		Description	90
	6.5	disloca		Reference	91
		6.5.1		Description	92
	6.6	disloca		ts.h File Reference	92
				Description	93
		6.6.2		efinition Documentation	94
			6.6.2.1	DEFAULT BURGERS 0	94
			6.6.2.2	DEFAULT_BURGERS_1	94
			6.6.2.3	DEFAULT_BURGERS_2	94
			6.6.2.4	DEFAULT BURGERS MAGNITUDE	94
			6.6.2.5	DEFAULT_LINEVECTOR_0	94
			6.6.2.6	DEFAULT_LINEVECTOR_1	94
			6.6.2.7	DEFAULT_LINEVECTOR_2	95
			6.6.2.8	DEFAULT_POSITION_0	95
			6.6.2.9	DEFAULT_POSITION_1	95
			6.6.2.10	DEFAULT_POSITION_2	95
	6.7	disloca	ntionSource	e.cpp File Reference	95
		6.7.1	Detailed I	Description	96
	6.8	disloca	itionSource	e.h File Reference	97

viii CONTENTS

	6.8.1	Detailed Description	. 98
6.9	disloca	onSourceDefaults.h File Reference	. 98
	6.9.1	Detailed Description	. 99
	6.9.2	Macro Definition Documentation	. 99
		6.9.2.1 DEFAULT_NITERATIONS	. 99
		6.9.2.2 DEFAULT_TAU_CRITICAL	. 100
6.10	mainpa	e.dox File Reference	. 100
6.11	matrix3	cpp File Reference	. 100
	6.11.1	Detailed Description	. 100
6.12	matrix3	S.h File Reference	. 101
	6.12.1	Detailed Description	. 102
6.13	rotation	Matrix.cpp File Reference	. 103
	6.13.1	Detailed Description	. 103
6.14	rotation	Matrix.h File Reference	. 103
	6.14.1	Detailed Description	. 104
6.15	strain.c	p File Reference	. 105
	6.15.1	Detailed Description	. 105
6.16	strain.h	File Reference	. 106
	6.16.1	Detailed Description	. 107
6.17	stress.	pp File Reference	. 107
	6.17.1	Detailed Description	. 108
6.18	stress.l	File Reference	. 109
	6.18.1	Detailed Description	. 110
6.19	vector3	l.cpp File Reference	. 111
	6.19.1	Detailed Description	. 111
6.20	vector3	l.h File Reference	. 111
	6.20.1	Detailed Description	. 113

Chapter 1

Main Page

The files in this program provide a heirarchical data structure system for carrying out dislocation dynamics simulations in two dimensions. The base class is Defect, which represents a generic defect in a metallic crystal. All other defects, such as dislocations, dislocation sources, precipitates, etc., are represented by their own classes which inherit certain functions from the Defect class.

The goal of carrying out these simulations in two dimensions is to be able to simulate plastic deformation of up to a few percent. Current three dimensional dislocation dynamics simulations are computationally expensive. This approach hopes to sacrifice some of the precision in order to gain in speed and flexibility.

The program is under development now, with the data structures being defined. When it will be complete, it is intended to have data structures nested within each other, hence the name Matryushka. For example, a polycrystal is a collection of grains; a grain is a collection of slip systems; a slip system is a collection of slip planes; a slip plane is a collection of dislocations, dislocation sources and other defects. This program will also take advantage of the functionality provided by the C++ STL to manage lists of various objects in the simulation. Once the base simulations execute successfully, other defects will be introduced.

To view the hierarchical structure, go to the section labeled Data Structures > Class Heirarchy. A good place to start would be the Defect class, which is the generic base class for most of the entities present in the simulation.

2 Main Page

Chapter 2

Hierarchical Index

2.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

Defect	 	 													9
Dislocation	 	 											 		. 15
DislocationSource	 	 											 		. 25
Matrix33	 	 													37
RotationMatrix	 	 											 		. 47
Strain	 	 											 		. 55
Stress	 	 											 		. 65
Vector3d	 	 													76

Hierarchical Index

Chapter 3

Data Structure Index

3.1 Data Structures

Here are the data structures with brief descriptions:

Defect		
	Class Defect representing a generic defect in a material	9
Dislocati	on	
	Dislocation class representing a dislocation in the simulation	15
Dislocati	onSource	
	DislocationSource class representing a source of dislocations in the simulation	25
Matrix33		
	Matrix33 class representing a 3x3 square matrix	37
Rotation	Matrix	
	RotationMatrix class to represent a rotation matrix	47
Strain		
	Strain class to represent the strain tensor	55
Stress		
	Stress class to represent the stress tensor	65
Vector3d		
	Vector3d class representing a single 3-dimensional vector in the simulation	76

6 **Data Structure Index**

Chapter 4

File Index

4.1 File List

Here is a list of all files with brief descriptions:

constants.h	
Definition of constants used in the program	85
defect.cpp	
Definition of member functions of the Defect class	86
defect.h	
Definition of the Defect class	88
dislocation.cpp	
Definition of constructors and member functions of the Dislocation class	89
dislocation.h	
Definition of the Dislocation class	91
dislocationDefaults.h	
Definition of certain default values for members of the Dislocation class	92
dislocationSource.cpp	
Definition of the member functions of the DislocationSource class	95
dislocationSource.h	
Definition of the DislocationSource class	97
dislocationSourceDefaults.h	
Definition of certain default values for members of the DislocationSource class	98
matrix33.cpp	
	100
matrix33.h	
	10
rotationMatrix.cpp	
	100
rotationMatrix.h	400
	10
Strain.cpp Definition of the member functions if the Strain class	101
	10
Strain.h Definition of the Strain class	106
	100
Stress.cpp Definition of the member functions if the Stress class	107
stress.h	10
	109
vector3d.cpp	10.
	11:
vector3d.h	
	11:

8 File Index

Chapter 5


Data Structure Documentation

5.1 Defect Class Reference


Class Defect representing a generic defect in a material.

#include <defect.h>

Inheritance diagram for Defect:



Collaboration diagram for Defect:



Public Member Functions

• Defect ()

Default constructor.

• Defect (double x, double y, double z)

Constructor specifying the position.

• Defect (double *p)

Constructor specifying the position.

void setPosition (double *a)

Sets the position of the defect.

void setPosition (double x, double y, double z)

Sets the position of the defect.

void setPosition (Vector3d a)

Sets the position of the defect.

void setX (double x)

Sets the X-coordinate of the defect.

void setY (double y)

Sets the Y-coordinate of the defect.

void setZ (double z)

Sets the Z-coordinate of the defect.

double * getPosition ()

Returns in an array the position.

void getPosition (double *a)

Returns the array position in a pre-allocated array.

• double getX ()

Returns the X-coordinate of the defect.

· double getY ()

Returns the Y-coordinate of the defect.

• double getZ ()

Returns the Z-coordinate of the defect.

virtual Stress stressField (Vector3d p, double mu, double nu)

Virtual function for calculating the stress field.

Protected Attributes

Vector3d pos

Position vector of the defect in 2D space.

5.1.1 Detailed Description

Class Defect representing a generic defect in a material.

Defines the Defect class representing an defect in the simulation. This is simply a generic description class with virtual functions. Later classes like dislocations, precipitates, boundaries etc will inherit from this class.

Definition at line 20 of file defect.h.

5.1.2 Constructor & Destructor Documentation

5.1.2.1 Defect::Defect ()

Default constructor.

Creates the object with position (0.0, 0.0, 0.0).

Definition at line 17 of file defect.cpp.

```
18 {
19    for (int i=0; i<3; i++)
20     {
21        this->pos.setValue(i, 0.0);
22    }
23 }
```

5.1.2.2 Defect::Defect (double x, double y, double z)

Constructor specifying the position.

The object is initialized with the position specified by the arguments (x, y, z).

Parameters

X	X-coordinate of the defect.
У	Y-coordinate of the defect
Z	Z-coordinate of the defect.

Definition at line 32 of file defect.cpp.

```
33 {
34     this->pos.setValue (0, x);
35     this->pos.setValue (1, y);
36     this->pos.setValue (2, z);
37 }
```

5.1.2.3 Defect::Defect (double * p)

Constructor specifying the position.

The object is initialized with the position specified in the array pointed to by the argument.

Parameters

```
p Pointer to the array containing the coordinates of the defect.
```

Definition at line 44 of file defect.cpp.

```
45 {
46 this->pos.setValue (p);
47 }
```

5.1.3 Member Function Documentation

5.1.3.1 double * Defect::getPosition()

Returns in an array the position.

The position of the defect is saved in an array and a pointer to its first term is returned.

Returns

Pointer to the first term of the array containing the position of the defect.

Definition at line 119 of file defect.cpp.

```
120 {
121    return (this->pos.getVector ());
122 }
```

5.1.3.2 void Defect::getPosition (double * a)

Returns the array position in a pre-allocated array.

Returns in the array provided in the argument the position of the defect. The array must be pre-allocated.

Parameters

a Pointer to the location where the defect coordinates are to be populated.

Definition at line 129 of file defect.cpp.

```
130 {
131    a = this->pos.getVector ();
132 }
```

5.1.3.3 double Defect::getX ()

Returns the X-coordinate of the defect.

Returns

X-coordinate of the defect.

Definition at line 138 of file defect.cpp.

```
139 {
140    return (this->getValue (0));
141 }
```

5.1.3.4 double Defect::getY()

Returns the Y-coordinate of the defect.

Returns

Y-coordinate of the defect.

Definition at line 147 of file defect.cpp.

```
148 {
149     return (this->pos.getValue (1));
150 }
```

5.1 Defect Class Reference 13

5.1.3.5 double Defect::getZ()

Returns the Z-coordinate of the defect.

Returns

Z-coordinate of the defect.

Definition at line 156 of file defect.cpp.

```
157 {
158    return (this->pos.getValue (2));
159 }
```

5.1.3.6 void Defect::setPosition (double * a)

Sets the position of the defect.

The position of the defect is set to the co-ordinates present in the array pointed to by the argument. Sets the position of the defect as the values in the array pointed to by the argument.

Parameters

а	Pointer to the array containing the coordinates of the defect.
---	--

Definition at line 56 of file defect.cpp.

```
57 {
58  this->pos.setVector (a);
59 }
```

5.1.3.7 void Defect::setPosition (double x, double y, double z)

Sets the position of the defect.

The position of the defect is set to the co-ordinates specified by the arguments (x, y, z). Sets the position of the defect as the coordinates provided as arguments.

Parameters

X	X-coordinate of the defect.
У	Y-coordinate of the defect.
Z	Z-coordinate of the defect.

Definition at line 69 of file defect.cpp.

```
70 {
71 this->pos.setValue (0, x);
72 this->pos.setValue (1, y);
73 this->pos.setValue (2, z);
74 }
```

5.1.3.8 void Defect::setPosition (Vector3d a)

Sets the position of the defect.

The position of the defect is set to the position vector fiven by the argument a.

Parameters

a Position vector of the defect.

Definition at line 81 of file defect.cpp.

```
82 {
83    this->position = a;
84 }
```

5.1.3.9 void Defect::setX (double x)

Sets the X-coordinate of the defect.

Parameters

```
x X-coordinate of the defect.
```

Definition at line 90 of file defect.cpp.

```
91 {
92   this->pos.setValue (0, x);
93 }
```

5.1.3.10 void Defect::setY (double y)

Sets the Y-coordinate of the defect.

Parameters

```
y Y-coordinate of the defect.
```

Definition at line 99 of file defect.cpp.

```
100 {
101   this->pos.setValue (1, y);
102 }
```

5.1.3.11 void Defect::setZ (double z)

Sets the Z-coordinate of the defect.

Parameters

```
z Z-coordinate of the defect.
```

Definition at line 108 of file defect.cpp.

```
109 {
110    this->pos.setValue (2, z);
111 }
```

5.1.3.12 virtual Stress Defect::stressField (Vector3d p, double mu, double nu) [inline], [virtual]

Virtual function for calculating the stress field.

Returns the value of the stress field of the given defect at the position given by the argument. This is a virtual function and always returns a zero matrix. Classes which inherit this function should have their own implementations of this function to override its behaviour.

Parameters

р	Position vector of the the point where the stress field is to be calculated.
mu	Shear modulus in Pascals.
nu	Poisson's ratio.

Returns

Stress field value at the position p.

Reimplemented in Dislocation.

Definition at line 136 of file defect.h.

5.1.4 Field Documentation

5.1.4.1 Vector3d Defect::pos [protected]

Position vector of the defect in 2D space.

Definition at line 26 of file defect.h.

The documentation for this class was generated from the following files:


- defect.h
- · defect.cpp

5.2 Dislocation Class Reference


Dislocation class representing a dislocation in the simulation.

```
#include <dislocation.h>
```

Inheritance diagram for Dislocation:



Collaboration diagram for Dislocation:



Public Member Functions

• Dislocation ()

Default constructor.

• Dislocation (Vector3d burgers, Vector3d line, Vector3d position, double bm, bool m)

Constructor that explicitly specifies all parameters.

• void setBurgers (Vector3d burgers)

Sets the Burgers vector of the dislocation.

void setLineVector (Vector3d line)

Sets the line vector of the dislocation.

· void setMobile ()

Sets the dislocation as mobile.

• void setPinned ()

Sets the dislocation as pinned.

Vector3d getBurgers ()

Gets the Burgers vector of the dislocation.

Vector3d getLineVector ()

Gets the line vector of the dislocation.

void calculateRotationMatrix ()

Calculate the roation matrix.

• Stress stressField (Vector3d p, double mu, double nu)

Calculates the stress field due to this dislocation at the position given as argument.

• Stress stressFieldLocal (Vector3d p, double mu, double nu)

Calculates the stress field due to the dislocation in the local co-ordinate system.

• void setPosition (double *a)

Sets the position of the defect.

• void setPosition (double x, double y, double z)

Sets the position of the defect.

void setPosition (Vector3d a)

Sets the position of the defect.

void setX (double x)

Sets the X-coordinate of the defect.

void setY (double y)

Sets the Y-coordinate of the defect.

void setZ (double z)

Sets the Z-coordinate of the defect.

double * getPosition ()

Returns in an array the position.

void getPosition (double *a)

Returns the array position in a pre-allocated array.

• double getX ()

Returns the X-coordinate of the defect.

double getY ()

Returns the Y-coordinate of the defect.

• double getZ ()

Returns the Z-coordinate of the defect.

Protected Attributes

· Vector3d byec

Burgers vector of the dislocation.

· Vector3d Ivec

Line vector if the dislocation.

• bool mobile

Boolean term indicating mobility.

· double bmag

Magnitude of the Burgers vector in metres.

· RotationMatrix rotationMatrix

The rotation matrix for rotating from the global to the local co-ordinate system and vice-versa.

· Vector3d pos

Position vector of the defect in 2D space.

5.2.1 Detailed Description

Dislocation class representing a dislocation in the simulation.

The Dislocation class represents a dislocation in the simulation. The class inherits from the Defect class. A dislocation has several properties like a Burgers vector, line vector, etc. which will all be declared here.

Definition at line 21 of file dislocation.h.

5.2.2 Constructor & Destructor Documentation

5.2.2.1 Dislocation::Dislocation ()

Default constructor.

Initializes the dislocation with the following default parameters: Position: (0.0, 0.0, 0.0) Burgers vector: Default value set in defaults file. Line vector: Default value set in defaults file. Burgers vector magnitude: Default value set in the defaults file. Mobile: true.

Initializes the dislocation with the following default parameters: Position: (0.0, 0.0, 0.0) Burgers vector: Default value set in defaults file. Line vector: Default value set in defaults file. Burgers vector magnitude: Default value set in teh defaults file. Mobile: true.

Definition at line 21 of file dislocation.cpp.

5.2.2.2 Dislocation::Dislocation (Vector3d burgers, Vector3d line, Vector3d position, double bm, bool m)

Constructor that explicitly specifies all parameters.

All parameters: Burgers vector, line vector, position, are specified.

Parameters

burgers	Burgers vector.
line	Line vector.
position	Position of the dislocation.
bm	Magnitude of the Burgers vector in metres.
m	Mobility (true/false).

Definition at line 40 of file dislocation.cpp.

```
41 {
42    this->bvec = burgers;
43    this->lvec = line;
44    this->pos = position;
45    this->mobile = m;
46    this->bmag = bm;
47    this->calculateRotationMatrix ();
48 }
```

5.2.3 Member Function Documentation

5.2.3.1 void Dislocation::calculateRotationMatrix ()

Calculate the roation matrix.

This function calculates the rotation matrix for this dislocation using the global and local co-ordinate systems. The matrix rotationMatrix is for rotation from the old (unprimed, global) to the new (primed, dislocation) system.

Definition at line 109 of file dislocation.cpp.

```
110 {
       Vector3d globalSystem[3];
                                                // Global co-ordinate systems
111
       Vector3d localSystem[3];
                                                // Dislocation co-ordinate system
113
       \ensuremath{//} 
 Vectors of the global co-ordinate system
114
       globalSystem[0] = Vector3d (1.0, 0.0, 0.0);
globalSystem[1] = Vector3d (0.0, 1.0, 0.0);
115
116
       globalSystem[2] = Vector3d (0.0, 0.0, 1.0);
117
118
119
        // Vectors of the dislocation co-ordinate system
       localSystem[0] = bvec.normalize ();
localSystem[2] = lvec.normalize ();
localSystem[1] = (lvec ^ bvec).normalize ();
120
121
122
123
124
       // Calculate rotation matrix
```

```
this->rotationMatrix = RotationMatrix (globalSystem, localSystem);
126 }
```

5.2.3.2 Vector3d Dislocation::getBurgers ()

Gets the Burgers vector of the dislocation.

Returns

Burgers vector in a variable of type Vector3d.

Definition at line 90 of file dislocation.cpp.

```
91 {
92    return ( this->bvec );
93 }
```

5.2.3.3 Vector3d Dislocation::getLineVector()

Gets the line vector of the dislocation.

Returns

Line vector in a variable of type Vector3d.

Definition at line 99 of file dislocation.cpp.

```
100 {
101    return ( this->lvec );
102 }
```

5.2.3.4 double * Defect::getPosition() [inherited]

Returns in an array the position.

The position of the defect is saved in an array and a pointer to its first term is returned.

Returns

Pointer to the first term of the array containing the position of the defect.

Definition at line 119 of file defect.cpp.

```
120 {
121   return (this->pos.getVector ());
122 }
```

5.2.3.5 void Defect::getPosition (double * a) [inherited]

Returns the array position in a pre-allocated array.

Returns in the array provided in the argument the position of the defect. The array must be pre-allocated.

Parameters

a Pointer to the location where the defect coordinates are to be populated.

Definition at line 129 of file defect.cpp.

```
130 {
131    a = this->pos.getVector ();
132 }
```

5.2.3.6 double Defect::getX() [inherited]

Returns the X-coordinate of the defect.

Returns

X-coordinate of the defect.

Definition at line 138 of file defect.cpp.

```
139 {
140    return (this->getValue (0));
141 }
```

5.2.3.7 double Defect::getY() [inherited]

Returns the Y-coordinate of the defect.

Returns

Y-coordinate of the defect.

Definition at line 147 of file defect.cpp.

```
148 {
149     return (this->pos.getValue (1));
150 }
```

5.2.3.8 double Defect::getZ() [inherited]

Returns the Z-coordinate of the defect.

Returns

Z-coordinate of the defect.

Definition at line 156 of file defect.cpp.

```
157 {
158    return (this->pos.getValue (2));
159 }
```

5.2.3.9 void Dislocation::setBurgers (Vector3d burgers)

Sets the Burgers vector of the dislocation.

Parameters

burgers | Bergers vector of the dislocation.

Definition at line 54 of file dislocation.cpp.

```
55 {
56   this->bvec = burgers;
57 }
```

5.2.3.10 void Dislocation::setLineVector (Vector3d line)

Sets the line vector of the dislocation.

Parameters

```
line Line vector of the dislocation.
```

Definition at line 62 of file dislocation.cpp.

```
63 {
64 this->lvec = line;
65 }
```

5.2.3.11 void Dislocation::setMobile ()

Sets the dislocation as mobile.

Sets the flag mobile to true.

Definition at line 71 of file dislocation.cpp.

```
72 {
73   this->mobile = true;
74 }
```

5.2.3.12 void Dislocation::setPinned ()

Sets the dislocation as pinned.

Sets the flag mobile to false.

Definition at line 80 of file dislocation.cpp.

```
81 {
82   this->mobile = false;
83 }
```

5.2.3.13 void Defect::setPosition (double * a) [inherited]

Sets the position of the defect.

The position of the defect is set to the co-ordinates present in the array pointed to by the argument. Sets the position of the defect as the values in the array pointed to by the argument.

Parameters

```
a Pointer to the array containing the coordinates of the defect.
```

Definition at line 56 of file defect.cpp.

```
57 {
```

```
58 this->pos.setVector (a);
59 }
```

5.2.3.14 void Defect::setPosition (double *x***, double** *y***, double** *z* **)** [inherited]

Sets the position of the defect.

The position of the defect is set to the co-ordinates specified by the arguments (x, y, z). Sets the position of the defect as the coordinates provided as arguments.

Parameters

X	X-coordinate of the defect.
У	Y-coordinate of the defect.
Z	Z-coordinate of the defect.

Definition at line 69 of file defect.cpp.

```
70 {
71    this->pos.setValue (0, x);
72    this->pos.setValue (1, y);
73    this->pos.setValue (2, z);
74 }
```

5.2.3.15 void Defect::setPosition (Vector3d *a* **)** [inherited]

Sets the position of the defect.

The position of the defect is set to the position vector fiven by the argument a.

Parameters

```
a Position vector of the defect.
```

Definition at line 81 of file defect.cpp.

```
82 {
83 this->position = a;
84 }
```

5.2.3.16 void Defect::setX (double x) [inherited]

Sets the X-coordinate of the defect.

Parameters

```
x X-coordinate of the defect.
```

Definition at line 90 of file defect.cpp.

```
91 {
92   this->pos.setValue (0, x);
93 }
```

5.2.3.17 void Defect::setY (double y) [inherited]

Sets the Y-coordinate of the defect.

Parameters

У	Y-coordinate of the defect.

Definition at line 99 of file defect.cpp.

```
100 {
101   this->pos.setValue (1, y);
102 }
```

5.2.3.18 void Defect::setZ (double z) [inherited]

Sets the Z-coordinate of the defect.

Parameters

```
z Z-coordinate of the defect.
```

Definition at line 108 of file defect.cpp.

```
109 {
110   this->pos.setValue (2, z);
111 }
```

5.2.3.19 Stress Dislocation::stressField (Vector3d p, double mu, double nu) [virtual]

Calculates the stress field due to this dislocation at the position given as argument.

The stress field of the dislocation is calculated at the position indicated by the argument.

Parameters

р	Position vector of the point where the stress field is to be calculated.
mu	Shear modulus in Pascals.
nu	Poisson's ratio.

Returns

Stress tensor, expressed in the global co-ordinate system, giving the value of the stress field at position p.

Reimplemented from Defect.

Definition at line 137 of file dislocation.cpp.

```
138 {
139
     double principalStresses[3];
140
     double shearStresses[3];
     141
142
     r = p - this->pos; // Still in global coordinate system
143
     Vector3d rLocal = this->rotationMatrix * r;
                                              // Rotated to local co-ordinate
144
      system
145
146
147
     // Calculate the stress field in the local co-ordinate \ensuremath{\mathsf{system}}
     Stress sLocal = this->stressFieldLocal (rLocal, mu, nu);
148
149
     // Calculate the stress field in the global co-ordinate system
150
     Stress sGlobal = (this->rotationMatrix) * sLocal * (^(this->
     rotationMatrix));
151
152
     return (sGlobal);
153 }
```

5.2.3.20 Stress Dislocation::stressFieldLocal (Vector3d p, double mu, double nu)

Calculates the stress field due to the dislocation in the local co-ordinate system.

The stress field due to the dislocation is calculated at the position indicated by the argument. The stress tensor is expressed in the dislocation's local co-ordinate system.

Parameters

р	Position vector of the point where the stress field is to be calculated. This position vector is
	calculated in the local co-ordinate system, taking the dislocation as the origin.
mu	Shear modulus in Pascals.
nu	Poisson's ratio.

Returns

Stress tensor, expressed in the dislocation's local co-ordinate system.

Definition at line 163 of file dislocation.cpp.

```
164 {
165
     double D = ( mu * this - > bm ) / ( 2.0 * PI * ( 1.0 - nu ) ); // Constant for all components of the
     stress tensor
166
167
                               // Terms that appear repeatedly in the stress tensor
     double x, y, denominator;
168
     x = p.getValue (0);
170
     y = p.getValue (1);
171
     denominator = pow ( ((x*x) + (y*y)), 2);
172
    173
175
176
     shearStresses[0] = D * x * ( (x*x) - (y*y) ) / denominator;
shearStresses[1] = 0.0;
177
178
179
     shearStresses[2] = 0.0;
180
     return (Stress(principalStresses, shearStresses));
182 }
```

5.2.4 Field Documentation

5.2.4.1 double Dislocation::bmag [protected]

Magnitude of the Burgers vector in metres.

The magnitude of the Burgers vector is useful for several calculations such as stress field around the dislocation.

Definition at line 44 of file dislocation.h.

5.2.4.2 Vector3d Dislocation::bvec [protected]

Burgers vector of the dislocation.

Definition at line 27 of file dislocation.h.

5.2.4.3 Vector3d Dislocation::lvec [protected]

Line vector if the dislocation.

Definition at line 32 of file dislocation.h.

5.2.4.4 bool Dislocation::mobile [protected]

Boolean term indicating mobility.

For mobile dislocations this term is true and for pinned dislocations it is false.

Definition at line 38 of file dislocation.h.

5.2.4.5 Vector3d Defect::pos [protected], [inherited]

Position vector of the defect in 2D space.

Definition at line 26 of file defect.h.

5.2.4.6 RotationMatrix Dislocation::rotationMatrix [protected]

The rotation matrix for rotating from the global to the local co-ordinate system and vice-versa.

This is the rotation matrix that represents the relationship between the global and local co-ordinate systems. It is used to convert tensors and vectors between the two systems. The rotation matrix needs to be calculated once and may be refreshed periodically if lattice rotation is implemented. In the absence of lattice rotation, the matrix will remain invariant.

Definition at line 50 of file dislocation.h.

The documentation for this class was generated from the following files:


- · dislocation.h
- · dislocation.cpp

5.3 DislocationSource Class Reference


DislocationSource class representing a source of dislocations in the simulation.

#include <dislocationSource.h>

Inheritance diagram for DislocationSource:



Collaboration diagram for DislocationSource:



Public Member Functions

• DislocationSource ()

Default constructor.

- DislocationSource (Vector3d burgers, Vector3d line, Vector3d position, double bm, double tau, int nlter) Constructor that explicitly specifies all parameters.
- void setBurgers (Vector3d burgers)

Sets the Burgers vector of the dislocation.

void setLineVector (Vector3d line)

Sets the line vector of the dislocation.

• void setBurgersMagnitude (double bm)

Set the magnitude of the Burgers vector.

void setTauCritical (double tauC)

Set the critical shear stres for dipole emission.

• void setNumIterations (int nIter)

Set the number of iterations before a dipole is emitted.

void resetIterationCounter ()

Sets the iteration counter to zero.

• Vector3d getBurgers ()

Returns the Burgers vector of the dislocations in the dipole.

Vector3d getLineVector ()

Returns the line vector of the dislocations in the dipole.

double getBurgersMag ()

Returns the magnitude of the Burgers vector.

• double getTauCritical ()

Returns the critical shear stress value for dipole emission.

• int getNumIterations ()

Returns the number if iterations that the dislocation source must spend experiencing a shear stress greater than the critical value before it can emit a dislocation dipole.

• int getIterationCount ()

Get the count of the iterations spent at higher than critical shear stress.

• double dipoleNucleationLength (double tau, double mu, double nu)

The nucleation length of the dipole.

void incrementIterationCount ()

Increments the variable countIterations by 1.

bool ifEmitDipole ()

Checks if the dislocation source has experienced higher than critical shear stress for long enough to emit a dipole.

• void setPosition (double *a)

Sets the position of the defect.

void setPosition (double x, double y, double z)

Sets the position of the defect.

void setPosition (Vector3d a)

Sets the position of the defect.

void setX (double x)

Sets the X-coordinate of the defect.

void setY (double y)

Sets the Y-coordinate of the defect.

void setZ (double z)

Sets the Z-coordinate of the defect.

double * getPosition ()

Returns in an array the position.

void getPosition (double *a)

Returns the array position in a pre-allocated array.

double getX ()

Returns the X-coordinate of the defect.

double getY ()

Returns the Y-coordinate of the defect.

• double getZ ()

Returns the Z-coordinate of the defect.

virtual Stress stressField (Vector3d p, double mu, double nu)

Virtual function for calculating the stress field.

Protected Attributes

· Vector3d bvec

Burgers vector of the dislocation.

· Vector3d Ivec

Line vector if the dislocation.

· bool mobile

Boolean term indicating mobility.

· double bmag

Magnitude of the Burgers vector in metres.

· RotationMatrix rotationMatrix

The rotation matrix for rotating from the global to the local co-ordinate system and vice-versa.

double tauCritical

Critical stress for the emission of a dislocation dipole.

int nlterations

Number of iterations before a dipole is emitted.

· int countIterations

Counter variable for the number of consecutive iterations the dislocation source has experienced a shear stress greater than its critical value.

Vector3d pos

Position vector of the defect in 2D space.

5.3.1 Detailed Description

DislocationSource class representing a source of dislocations in the simulation.

This class inherits from the Defect class. This object is basically the representation of a Frank-Read source emitting dislocation dipoles. When the dislocation source experiences a shear stress greater than a critical value for a certain amount of time (or number of iterations), it emits a dislocation dipole with a length that is a function of the applied stress. The properties of this class and the member functions will be declared here.

Definition at line 22 of file dislocationSource.h.

5.3.2 Constructor & Destructor Documentation

5.3.2.1 DislocationSource::DislocationSource ()

Default constructor.

Initializes the dislocation with the default parameters provided in the files dislocationDefaults.h and dislocationSourceDefaults.h.

Definition at line 17 of file dislocationSource.cpp.

5.3.2.2 DislocationSource::DislocationSource (Vector3d burgers, Vector3d line, Vector3d position, double bm, double tau, int nlter)

Constructor that explicitly specifies all parameters.

All parameters: Burgers vector, line vector, position, are specified.

Parameters

burgers	Burgers vector.
line	Line vector.
position	Position of the dislocation source.
bm	Magnitude of the Burgers vector in metres.
tau	Critical shear stress value.
nlter	Number of iterations of experiencing critical stress before a dipole is emitted.

All parameters: Burgers vector, line vector, position, are specified.

Parameters

burgers	Burgers vector.
line	Line vector.
position	Position of the dislocation.
bm	Magnitude of the Burgers vector in metres.
tau	Critical shear stress value.
nlter	Number of iterations of experiencing critical stress before a dipole is emitted.

Definition at line 38 of file dislocationSource.cpp.

```
39 {
    this->bvec
40
                   = burgers;
                   = line;
     this->lvec
41
    this->pos
                   = position;
     this->bmag
                   = bm;
    this->tauCritical = tau;
this->nIterations = nIter;
45
46
    this->countIterations = 0;
47 }
```

5.3.3 Member Function Documentation

5.3.3.1 double DislocationSource::dipoleNucleationLength (double tau, double mu, double nu)

The nucleation length of the dipole.

When a dislocation source has experienced a shear stress greater than the critical value for a certain amount of time, it emits a dislocation dipole. In three dimensions, this is equivalent to a dislocation loop emitted by a Frank-Read source. The length of the dipole (or diameter of the loop in 3D) is such that the interaction force between the two dislocations (or line tension in 3D) balances out the applied shear stress.

Parameters

tau	The shear stress experienced by the dislocation source.
mu	Shear modulus of the material, in Pa.
nu	Poisson's ratio.

Returns

The length of the dislocation dipole.

Definition at line 167 of file dislocationSource.cpp.

5.3.3.2 Vector3d DislocationSource::getBurgers ()

Returns the Burgers vector of the dislocations in the dipole.

Returns

The Burgers vector of the dislocations in the dipole.

Definition at line 108 of file dislocationSource.cpp.

```
109 {
110    return (this->bvec);
111 }
```

5.3.3.3 double DislocationSource::getBurgersMag ()

Returns the magnitude of the Burgers vector.

Returns

The magnitude of the Burgers vector.

Definition at line 126 of file dislocationSource.cpp.

```
127 {
128    return (this->bmag);
129 }
```

5.3.3.4 int DislocationSource::getIterationCount ()

Get the count of the iterations spent at higher than critical shear stress.

Returns

Number of iterations spent at higher than critical shear stress.

Definition at line 153 of file dislocationSource.cpp.

```
154 {
155   return (this->countIterations);
156 }
```

5.3.3.5 Vector3d DislocationSource::getLineVector ()

Returns the line vector of the dislocations in the dipole.

Returns

The line vector of the dislocations in the dipole.

Definition at line 117 of file dislocationSource.cpp.

```
118 {
119    return (this->lvec);
120 }
```

5.3.3.6 int DislocationSource::getNumIterations ()

Returns the number if iterations that the dislocation source must spend experiencing a shear stress greater than the critical value before it can emit a dislocation dipole.

Returns

The number if iterations that the dislocation source must spend experiencing a shear stress greater than the critical value before it can emit a dislocation dipole.

Definition at line 144 of file dislocationSource.cpp.

```
145 {
146    return (this->nIterations);
147 }
```

```
5.3.3.7 double * Defect::getPosition() [inherited]
```

Returns in an array the position.

The position of the defect is saved in an array and a pointer to its first term is returned.

Returns

Pointer to the first term of the array containing the position of the defect.

Definition at line 119 of file defect.cpp.

```
120 {
121    return (this->pos.getVector ());
122 }
```

```
5.3.3.8 void Defect::getPosition ( double * a ) [inherited]
```

Returns the array position in a pre-allocated array.

Returns in the array provided in the argument the position of the defect. The array must be pre-allocated.

Parameters

a Pointer to the location where the defect coordinates are to be populated.

Definition at line 129 of file defect.cpp.

```
130 {
131    a = this->pos.getVector ();
132 }
```

5.3.3.9 double DislocationSource::getTauCritical ()

Returns the critical shear stress value for dipole emission.

Returns

The critical shear stress value for dipole emission.

Definition at line 135 of file dislocationSource.cpp.

```
136 {
137    return (this->tauCritical);
138 }
```

5.3.3.10 double Defect::getX() [inherited]

Returns the X-coordinate of the defect.

Returns

X-coordinate of the defect.

Definition at line 138 of file defect.cpp.

```
139 {
140    return (this->getValue (0));
141 }
```

```
5.3.3.11 double Defect::getY() [inherited]
```

Returns the Y-coordinate of the defect.

Returns

Y-coordinate of the defect.

Definition at line 147 of file defect.cpp.

```
148 {
149     return (this->pos.getValue (1));
150 }
```

```
5.3.3.12 double Defect::getZ( ) [inherited]
```

Returns the Z-coordinate of the defect.

Returns

Z-coordinate of the defect.

Definition at line 156 of file defect.cpp.

```
157 {
158    return (this->pos.getValue (2));
159 }
```

5.3.3.13 bool DislocationSource::ifEmitDipole ()

Checks if the dislocation source has experienced higher than critical shear stress for long enough to emit a dipole.

The number of iterations for which the dislocation source must experience a shear stress higher than the critical value is given in the member nlterations. When the counter variable countlterations reaches this value, the source is ready to emit a dipole, so a true value is returned. In other cases, false is returned.

Returns

The boolean result of whether the count of iterations is greater than the limiting number of iterations provided at input.

Definition at line 192 of file dislocationSource.cpp.

```
193 {
194    return ( this->countIterations >= this->nIterations );
195 }
```

5.3.3.14 void DislocationSource::incrementIterationCount ()

Increments the variable countIterations by 1.

Definition at line 182 of file dislocationSource.cpp.

```
183 {
184    this->countIterations++;
185 }
```

5.3.3.15 void DislocationSource::resetIterationCounter()

Sets the iteration counter to zero.

Definition at line 98 of file dislocationSource.cpp.

```
99 {
100    this->countIterations = 0;
101 }
```

5.3.3.16 void DislocationSource::setBurgers (Vector3d burgers)

Sets the Burgers vector of the dislocation.

Parameters

burgers | Burgers vector of the dislocation.

Definition at line 54 of file dislocationSource.cpp.

```
55 {
56    this->bvec = burgers;
57 }
```

5.3.3.17 void DislocationSource::setBurgersMagnitude (double bm)

Set the magnitude of the Burgers vector.

Parameters

bm | Magnitude of the Burgers vector.

Definition at line 72 of file dislocationSource.cpp.

```
73 {
74 this->bmag = bm;
75 }
```

5.3.3.18 void DislocationSource::setLineVector (Vector3d line)

Sets the line vector of the dislocation.

Parameters

line Line vector of the dislocation.

Definition at line 63 of file dislocationSource.cpp.

```
64 {
65 this->lvec = line;
66 }
```

5.3.3.19 void DislocationSource::setNumIterations (int nlter)

Set the number of iterations before a dipole is emitted.

Parameters

nlter Number of iterations spent at a high shear stress value before a dislocation dipole is emitted.

Definition at line 90 of file dislocationSource.cpp.

```
91 {
92   this->nIterations = nIter;
93 }
```

5.3.3.20 void Defect::setPosition (double * a) [inherited]

Sets the position of the defect.

The position of the defect is set to the co-ordinates present in the array pointed to by the argument. Sets the position of the defect as the values in the array pointed to by the argument.

Parameters

a Pointer to the array containing the coordinates of the defect.

Definition at line 56 of file defect.cpp.

```
57 {
58  this->pos.setVector (a);
59 }
```

5.3.3.21 void Defect::setPosition (double *x***, double** *y***, double** *z* **)** [inherited]

Sets the position of the defect.

The position of the defect is set to the co-ordinates specified by the arguments (x, y, z). Sets the position of the defect as the coordinates provided as arguments.

Parameters

X	X-coordinate of the defect.
У	Y-coordinate of the defect.
Z	Z-coordinate of the defect.

Definition at line 69 of file defect.cpp.

```
70 {
71     this->pos.setValue (0, x);
72     this->pos.setValue (1, y);
73     this->pos.setValue (2, z);
74 }
```

5.3.3.22 void Defect::setPosition (Vector3d *a* **)** [inherited]

Sets the position of the defect.

The position of the defect is set to the position vector fiven by the argument a.

Parameters

а	Position vector of the defect.

Definition at line 81 of file defect.cpp.

```
82 {
83   this->position = a;
84 }
```

5.3.3.23 void DislocationSource::setTauCritical (double tauC)

Set the critical shear stres for dipole emission.

Parameters

```
tauC | Critical shear stress for dipole emission.
```

Definition at line 81 of file dislocationSource.cpp.

```
82 {
83  this->tauCritical = tauC;
84 }
```

5.3.3.24 void Defect::setX (double x) [inherited]

Sets the X-coordinate of the defect.

Parameters

```
x X-coordinate of the defect.
```

Definition at line 90 of file defect.cpp.

```
91 {
92    this->pos.setValue (0, x);
93 }
```

5.3.3.25 void Defect::setY (double y) [inherited]

Sets the Y-coordinate of the defect.

Parameters

```
y Y-coordinate of the defect.
```

Definition at line 99 of file defect.cpp.

```
100 {
101   this->pos.setValue (1, y);
102 }
```

5.3.3.26 void Defect::setZ (double z) [inherited]

Sets the Z-coordinate of the defect.

Parameters

```
z Z-coordinate of the defect.
```

Definition at line 108 of file defect.cpp.

```
109 {
110   this->pos.setValue (2, z);
111 }
```

5.3.3.27 virtual Stress Defect::stressField (Vector3d p, double mu, double nu) [inline], [virtual], [inherited]

Virtual function for calculating the stress field.

Returns the value of the stress field of the given defect at the position given by the argument. This is a virtual function and always returns a zero matrix. Classes which inherit this function should have their own implementations of this function to override its behaviour.

Parameters

р	Position vector of the the point where the stress field is to be calculated.
mu	Shear modulus in Pascals.
nu	Poisson's ratio.

Returns

Stress field value at the position p.

Reimplemented in Dislocation.

Definition at line 136 of file defect.h.

5.3.4 Field Documentation

5.3.4.1 double DislocationSource::bmag [protected]

Magnitude of the Burgers vector in metres.

The magnitude of the Burgers vector is useful for several calculations such as stress field around the dislocation.

Definition at line 45 of file dislocationSource.h.

5.3.4.2 Vector3d DislocationSource::bvec [protected]

Burgers vector of the dislocation.

Definition at line 28 of file dislocationSource.h.

```
5.3.4.3 int DislocationSource::countIterations [protected]
```

Counter variable for the number of consecutive iterations the dislocation source has experienced a shear stress greater than its critical value.

A dislocation source needs to experience a shear stress higher than a critical value, given by tauCritical, for a certain amount of time before it is triggered and it emits a dislocation dipole. This limiting number of iterations is given by the variable nlterations, and this variable countlterations is a counter variable. Once this limit is reached, a dipole is emitted and this counter variable is set to zero.

Definition at line 69 of file dislocationSource.h.

5.3.4.4 Vector3d DislocationSource::lvec [protected]

Line vector if the dislocation.

Definition at line 33 of file dislocationSource.h.

5.3.4.5 bool DislocationSource::mobile [protected]

Boolean term indicating mobility.

For mobile dislocations this term is true and for pinned dislocations it is false.

Definition at line 39 of file dislocationSource.h.

```
5.3.4.6 int DislocationSource::nlterations [protected]
```

Number of iterations before a dipole is emitted.

A dislocation dipole source needs to experience a certain critical level of shear stress for a certain amount of time before it can emit a dipole. The amount of time is represented instead by a number of iterations nlterations.

Definition at line 63 of file dislocationSource.h.

```
5.3.4.7 Vector3d Defect::pos [protected], [inherited]
```

Position vector of the defect in 2D space.

Definition at line 26 of file defect.h.

5.3.4.8 RotationMatrix DislocationSource::rotationMatrix [protected]

The rotation matrix for rotating from the global to the local co-ordinate system and vice-versa.

This is the rotation matrix that represents the relationship between the global and local co-ordinate systems. It is used to convert tensors and vectors between the two systems. The rotation matrix needs to be calculated once and may be refreshed periodically if lattice rotation is implemented. In the absence of lattice rotation, the matrix will remain invariant.

Definition at line 51 of file dislocationSource.h.

```
5.3.4.9 double DislocationSource::tauCritical [protected]
```

Critical stress for the emission of a dislocation dipole.

A dislocation dipole source needs to experience a certain critical level of shear stress for a certain amount of time before it can emit a dipole. This critical stress is given by tauCritical.

Definition at line 57 of file dislocationSource.h.

The documentation for this class was generated from the following files:


- · dislocationSource.h
- · dislocationSource.cpp

5.4 Matrix33 Class Reference

Matrix33 class representing a 3x3 square matrix.

```
#include <matrix33.h>
```

Inheritance diagram for Matrix33:



Public Member Functions

• Matrix33 ()

Default constructor.

Matrix33 (double **a)

Constructor with the values provided in a 3x3 matrix.

Matrix33 (Vector3d a)

Constructor to create the matrix from the dyadic product of a vector with itself.

• Matrix33 (Vector3d a, Vector3d b)

Constructor with the vectors, the product of which will result in the matrix.

void setValue (int row, int column, double value)

Function to set the value of an element indicated by its position.

• double getValue (int row, int column)

Returns the value of the element located by the row and column indices provided.

• Matrix33 adjugate ()

Returns the adjugate matrix of the present matrix.

• Matrix33 operator+ (const Matrix33 &) const

Operator for addition of two matrices.

void operator+= (const Matrix33 &)

Operator for reflexive addition of two matrices.

Matrix33 operator- (const Matrix33 &) const

Operator for the subtraction of two matrices.

• void operator-= (const Matrix33 &)

Operator for reflexive subtraction of two matrices.

Matrix33 operator* (const double &) const

Operator for scaling the matrix by a scalar.

• void operator*= (const double &)

Operator for reflexive scaling of the matrix by a scalar.

• Matrix33 operator* (const Matrix33 &) const

Operator for the multiplication of two matrices.

• void operator*= (const Matrix33 &)

Operator for reflexive multiplication of two matrices.

Vector3d operator* (const Vector3d &) const

Operator for the multiplication of a matrix with a vector.

Matrix33 operator[^] () const

Transpose.

• double operator \sim () const

Determinant.

· Matrix33 operator! () const

Inverse.

Protected Attributes

• double x [3][3]

Array containing the elements of the matrix.

5.4.1 Detailed Description

Matrix33 class representing a 3x3 square matrix.

This class represents a 3x3 square matrix. The member functions and operators define various operations that may be carried out on the matrix.

Definition at line 20 of file matrix33.h.

5.4.2 Constructor & Destructor Documentation

```
5.4.2.1 Matrix33::Matrix33 ( )
```

Default constructor.

Initializes the matrix with all elements equal to 0.0.

Definition at line 17 of file matrix33.cpp.

```
18 {
19    int i, j;
20
21    for (i=0; i<3; i++)
22    {
23        for (j=0; j<3; j++)
24        {
25             this->x[i][j] = 0.0;
26        }
27    }
28 }
```

5.4.2.2 Matrix33::Matrix33 (double ** a)

Constructor with the values provided in a 3x3 matrix.

Populated the mstrix with data present in corresponding elements of the provided 3x3 array.

Parameters

```
a | Pointer to the two-dimensional 3x3 array.
```

Definition at line 35 of file matrix33.cpp.

```
44
45 }
46 }
```

5.4.2.3 Matrix33::Matrix33 (Vector3d a)

Constructor to create the matrix from the dyadic product of a vector with itself.

The matrix is created by performing the dyadic product of the provided vector with itself.

Parameters

a The vector whose dyadic product results in the matrix.

Definition at line 53 of file matrix33.cpp.

```
54 {
55   int i, j;
56
57   for (i=0; i<3; i++)
58   {
59      for (j=0; j<3; j++)
60      {
61          this->x[i][j] = a.x[i] * a.x[j];
62      }
63   }
64 }
```

5.4.2.4 Matrix33::Matrix33 (Vector3d a, Vector3d b)

Constructor with the vectors, the product of which will result in the matrix.

The matrix is created from the product the first vector with the second.

Parameters

а	First vector.
b	Second vector.

Definition at line 72 of file matrix33.cpp.

```
73 {
74   int i, j;
75
76   for (i=0; i<3; i++)
77   {
78      for (j=0; j<3; j++)
79      {
80           this->x[i][j] = a.x[i] * b.x[j];
81      }
82   }
83 }
```

5.4.3 Member Function Documentation

5.4.3.1 Matrix33 Matrix33::adjugate ()

Returns the adjugate matrix of the present matrix.

The adjugate matrix of the present matrix is returned. The adjugate matrix is calculated by evaluating the determinant of the cofactor matrix of each element, and then replacing the corresponding element position by the value of the determinant. This operation is useful in calculating the inverse of a matrix.

Returns

The adjugate matrix of the present matrix.

Definition at line 129 of file matrix33.cpp.

```
130 {
              Matrix33 adj;
131
132
              adj.x[0][0] = (this->x[1][1]*this->x[2][2]) - (this->x[1][2]*this->x[2][1]);
adj.x[0][1] = (this->x[1][2]*this->x[2][0]) - (this->x[1][0]*this->x[2][2]);
adj.x[0][2] = (this->x[1][0]*this->x[2][1]) - (this->x[1][1]*this->x[2][0]);
133
134
135
136
              adj.x[1][0] = (this->x[2][1]*this->x[0][2]) - (this->x[0][1]*this->x[2][2]);
adj.x[1][1] = (this->x[2][2]*this->x[0][0]) - (this->x[2][0]*this->x[0][2]);
adj.x[1][2] = (this->x[2][0]*this->x[0][1]) - (this->x[2][1]*this->x[0][0]);
137
138
139
140
             adj.x[2][0] = (this->x[0][1]*this->x[1][2]) - (this->x[0][2]*this->x[1][1]);
adj.x[2][1] = (this->x[0][2]*this->x[1][0]) - (this->x[0][0]*this->x[1][2]);
adj.x[2][2] = (this->x[0][0]*this->x[1][1]) - (this->x[1][0]*this->x[0][1]);
141
142
143
144
145
             return (adj);
```

5.4.3.2 double Matrix33::getValue (int row, int column)

Returns the value of the element located by the row and column indices provided.

The value of the element indicated by the arguments row and column is returned. The values of row and column must correspond to array indices, and thus can be one of 0, 1 and 2. In any other case 0.0 is returned.

Parameters

row	Row index of the element.
column	Column index of the element.

Returns

Value of the element located at the given position.

Definition at line 111 of file matrix33.cpp.

```
112 {
113     if (row>=0 && row<3)
114     {
115         if (column>=0 && column<3)
116         {
117              return (this->x[row][column]);
118         }
119     }
120
121     return (0.0);
122 }
```

5.4.3.3 Matrix33 Matrix33::operator! () const

Inverse.

Returns in a new matrix the inverse of the current matrix. If the current matrix is non-invertible, a zero matrix is returned.

Returns

Matrix with the inverse of the current matrix. If the current matrix is non-invertible, a zero matrix is returned.

Definition at line 370 of file matrix33.cpp.

```
372
     Matrix33 r; // Result matrix
373
374
     double determinant = ~(*this);
375
376
     if (determinant == 0.0)
377
378
         // The matrix is non-invertible
379
         return (r); // Zero matrix
380
381
     // If we are still here, the matrix is invertible
382
383
     // Transpose
384
385
     Matrix33 tr = ^(*this);
386
     // Find Adjugate matrix
387
388
     Matrix33 adj = tr.adjugate();
389
390
     // Calculate the inverse by dividing the adjugate matrix by the determinant
391
     r = adj * (1.0/determinant);
392
393
    return (r);
394 }
```

5.4.3.4 Matrix33 Matrix33::operator* (const double & p) const

Operator for scaling the matrix by a scalar.

Scales the current matrix by the scalar provided and returns the result in a third matrix.

Returns

Matrix containing the result of scaling the current matrix by the scalar provided as argument.

Definition at line 233 of file matrix33.cpp.

```
235
      int i, j;
      Matrix33 r;
236
237
238
      for (i=0; i<3; i++)
239
          for (j=0; j<3; j++)</pre>
240
241
              r.x[i][j] = this->x[i][j] * p;
2.42
243
244
245
246 return (r);
247 }
```

5.4.3.5 Matrix33 Matrix33::operator* (const Matrix33 & p) const

Operator for the multiplication of two matrices.

Multiplies the current matrix with another 3x3 matrix and returns the result in a new matrix.

Returns

The result of the multiplication of the current matrix with the one provided as argument.

Definition at line 271 of file matrix33.cpp.

```
272 {
273    int i, j, k;
274    Matrix33 r;
275
276    for (i=0; i<3; i++)
277    {
278         for (j=0; j<3; j++)
```

5.4.3.6 Vector3d Matrix33::operator* (const Vector3d & v) const

Operator for the multiplication of a matrix with a vector.

Returns in a vector the result of the multiplication of the current matrix with the provided vector.

Returns

The vector resulting from the multiplication of the current matrix with a vector.

Definition at line 311 of file matrix33.cpp.

```
312 {
      Vector3d r(0.0, 0.0, 0.0);
313
314
     int i, j;
316
     for (i=0; i<3; i++)</pre>
317
        for (j=0; j<3; j++)
318
319
             r[i] += this -> x[i][j] * v.x[j];
320
321
      }
323
324
     return (r);
325 }
```

5.4.3.7 void Matrix33::operator*= (const double & p)

Operator for reflexive scaling of the matrix by a scalar.

Scales the current matrix by the scalar provided and populates the current matrix elements with the result.

Definition at line 253 of file matrix33.cpp.

```
254 {
255   int i, j;
256
257   for (i=0; i<3; i++)
258   {
259     for (j=0; j<3; j++)
260     {
261         this->x[i][j] *= p;
262     }
263   }
264 }
```

5.4.3.8 void Matrix33::operator*= (const Matrix33 & p)

Operator for reflexive multiplication of two matrices.

Multiplies the current matrix with another 3x3 matrix and populates the elements of the current matrix with the result. Definition at line 295 of file matrix33.cpp.

```
296 {
297     Matrix33* r = new Matrix33;
298
299     *r = (*this) * p;
300     *this = *r;
301
302     delete(r);
303     r = NULL;
304 }
```

5.4.3.9 Matrix33 Matrix33::operator+ (const Matrix33 & p) const

Operator for addition of two matrices.

Adds the current matrix to the provided matrix and returns a third matrix with the result.

Returns

Matrix containing the sum of the present matrix and the one provided.

Definition at line 155 of file matrix33.cpp.

```
156 {
      int i, j;
Matrix33 r;
157
159
160
      for (i=0; i<3; i++)</pre>
161
          for (j=0; j<3; j++)
162
163
              r.x[i][j] = this->x[i][j] + p.x[i][j];
164
166
      }
167
168
     return (r);
169 }
```

5.4.3.10 void Matrix33::operator+= (const Matrix33 & p)

Operator for reflexive addition of two matrices.

Adds the current matrix to the provided matrix and populates the current matrix elements with the result.

Definition at line 175 of file matrix33.cpp.

5.4.3.11 Matrix33 Matrix33::operator-(const Matrix33 & p) const

Operator for the subtraction of two matrices.

Subtracts the given matrix from the current matrix and returns the result in a new matrix.

Returns

Matrix containing the result of subtracting the provided matrix from the current matrix.

Definition at line 194 of file matrix33.cpp.

```
195 {
     int i, j;
Matrix33 r;
196
197
198
      for (i=0; i<3; i++)
200
          for (j=0; j<3; j++)
201
202
              r.x[i][j] = this->x[i][j] - p.x[i][j];
203
204
205
206
207
     return (r);
208 }
```

5.4.3.12 void Matrix33::operator-= (const Matrix33 & p)

Operator for reflexive subtraction of two matrices.

Subtracts the given matrix from the current matrix and populates the current matrix with the result.

Definition at line 214 of file matrix33.cpp.

5.4.3.13 Matrix33 Matrix33::operator () const

Transpose.

Performs the transpose of the current matrix.

Returns

A new matrix with the transpose of the current matrix.

Definition at line 333 of file matrix33.cpp.

```
334 {
      Matrix33 r;
335
336
      int i, j;
337
      for (i=0; i<3; i++)</pre>
338
339
340
          for (j=0; j<3; j++)</pre>
341
               r.x[i][j] = this->x[j][i];
342
343
344
345
346
      return (r);
347 }
```

5.4.3.14 double Matrix33::operator \sim () const

Determinant.

Calculates the determinant of the current matrix.

Returns

Returns the determinant of the current matrix.

Definition at line 354 of file matrix33.cpp.

```
356
                                        double d = 0.0;
357
                                        358
                                         x[1][2]));
                                       d += this.x[0][1] * ( (this->x[1][2]*this->x[2][0]) - (this->x[1][0]*this->
359
                                        x[2][2]));
360
                                                                          this.x[0][2] * ( (this->x[1][0]*this->x[2][1]) - (this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--
                                        x[1][1]));
361
362
                                       return (d);
363 }
```

5.4.3.15 void Matrix33::setValue (int row, int column, double value)

Function to set the value of an element indicated by its position.

The element indicated by the arguments row and column is set to the value provided. The values of row and column must correspond to array indices, and thus can be one of 0, 1 and 2. In any other case 0.0 is returned.

Parameters

row	Row index of the element.
column	Column index of the element.
value	Value that the element is to be set to.

Definition at line 93 of file matrix33.cpp.

5.4.4 Field Documentation

```
5.4.4.1 double Matrix33::x[3][3] [protected]
```

Array containing the elements of the matrix.

Definition at line 26 of file matrix33.h.

The documentation for this class was generated from the following files:


- matrix33.h
- · matrix33.cpp

5.5 RotationMatrix Class Reference


RotationMatrix class to represent a rotation matrix.

#include <rotationMatrix.h>

Inheritance diagram for RotationMatrix:



Collaboration diagram for RotationMatrix:



Public Member Functions

• RotationMatrix ()

Default constructor.

RotationMatrix (Vector3d *unPrimed, Vector3d *primed)

Defines the rotation matrix based on two co-ordinate systems.

• void setValue (int row, int column, double value)

Function to set the value of an element indicated by its position.

double getValue (int row, int column)

Returns the value of the element located by the row and column indices provided.

• Matrix33 adjugate ()

Returns the adjugate matrix of the present matrix.

• Matrix33 operator+ (const Matrix33 &) const

Operator for addition of two matrices.

void operator+= (const Matrix33 &)

Operator for reflexive addition of two matrices.

• Matrix33 operator- (const Matrix33 &) const

Operator for the subtraction of two matrices.

void operator-= (const Matrix33 &)

Operator for reflexive subtraction of two matrices.

• Matrix33 operator* (const double &) const

Operator for scaling the matrix by a scalar.

• Matrix33 operator* (const Matrix33 &) const

Operator for the multiplication of two matrices.

Vector3d operator* (const Vector3d &) const

Operator for the multiplication of a matrix with a vector.

void operator*= (const double &)

Operator for reflexive scaling of the matrix by a scalar.

void operator*= (const Matrix33 &)

Operator for reflexive multiplication of two matrices.

Matrix33 operator[∧] () const

Transpose.

double operator
 ~ () const

Determinant.

· Matrix33 operator! () const

Inverse.

Protected Attributes

double x [3][3]

Array containing the elements of the matrix.

5.5.1 Detailed Description

RotationMatrix class to represent a rotation matrix.

The member functions of this class create a rotation matrix for carrying out rotations in 3D and transformation of axes.

Definition at line 19 of file rotationMatrix.h.

5.5.2 Constructor & Destructor Documentation

5.5.2.1 RotationMatrix::RotationMatrix ()

Default constructor.

Initializes the rotation matrix with a unit matrix.

Definition at line 14 of file rotationMatrix.cpp.

```
15 {
16
     int i, j;
17
     18
19
                this->setValue ( i, j, 1.0 );
23
            else {
                this->setValue ( i, j, 0.0 );
24
25
26
     }
28 }
```

5.5.2.2 RotationMatrix::RotationMatrix (Vector3d * unPrimed, Vector3d * primed)

Defines the rotation matrix based on two co-ordinate systems.

The rotation matrix is created using the axes of the two co-ordinate systems provided as arguments. The vectors must be normalized to be unit vectors.

Parameters

unPrimed	Pointer to the array containing the three axes vectors of the unprimed (old) system.
primed	Pointer to the array containing the three axes vectors of the primed (new) system.

Definition at line 36 of file rotationMatrix.cpp.

```
37 {
38     int i, j;
39
40     for ( i=0; i<3; i++ ) {
41          for ( j=0; j<3; j++ ) {
42                this->setValue ( i, j, primed[i]*unPrimed[j] );
43          }
44     }
45 }
```

5.5.3 Member Function Documentation

5.5.3.1 Matrix33 Matrix33::adjugate() [inherited]

Returns the adjugate matrix of the present matrix.

The adjugate matrix of the present matrix is returned. The adjugate matrix is calculated by evaluating the determinant of the cofactor matrix of each element, and then replacing the corresponding element position by the value of the determinant. This operation is useful in calculating the inverse of a matrix.

Returns

The adjugate matrix of the present matrix.

Definition at line 129 of file matrix33.cpp.

```
130 {
131
       Matrix33 adi:
       133
134
       adj.x[0][2] = (this->x[1][0]*this->x[2][1]) - (this->x[1][1]*this->x[2][0]);
135
136
       adj.x[1][0] = (this->x[2][1]*this->x[0][2]) - (this->x[0][1]*this->x[2][2]);
adj.x[1][1] = (this->x[2][2]*this->x[0][0]) - (this->x[2][0]*this->x[0][2]);
adj.x[1][2] = (this->x[2][0]*this->x[0][1]) - (this->x[2][1]*this->x[0][0]);
137
138
139
140
141
       adj.x[2][0] = (this->x[0][1]*this->x[1][2]) - (this->x[0][2]*this->x[1][1]);
       adj.x[2][1] = (this->x[0][2]*this->x[1][0]) - (this->x[0][0]*this->x[1][2]);
adj.x[2][2] = (this->x[0][0]*this->x[1][1]) - (this->x[1][0]*this->x[0][1]);
142
143
144
145
       return (adj);
146 }
```

5.5.3.2 double Matrix33::getValue (int row, int column) [inherited]

Returns the value of the element located by the row and column indices provided.

The value of the element indicated by the arguments row and column is returned. The values of row and column must correspond to array indices, and thus can be one of 0, 1 and 2. In any other case 0.0 is returned.

Parameters

row	Row index of the element.
column	Column index of the element.

Returns

Value of the element located at the given position.

Definition at line 111 of file matrix33.cpp.

5.5.3.3 Matrix33 Matrix33::operator! () const [inherited]

Inverse.

Returns in a new matrix the inverse of the current matrix. If the current matrix is non-invertible, a zero matrix is returned

Returns

Matrix with the inverse of the current matrix. If the current matrix is non-invertible, a zero matrix is returned.

Definition at line 370 of file matrix33.cpp.

```
372
                                                           Matrix33 r; // Result matrix
373
374
                                                           double determinant = \sim(*this);
375
376
                                                           if (determinant == 0.0)
377
378
                                                                                                     // The matrix is non-invertible % \left( 1\right) =\left( 1\right) \left( 1\right) 
379
                                                                                                   return (r);
                                                                                                                                                                                                                                                                        // Zero matrix
380
381
                                                        // If we are still here, the matrix is invertible
382
383
                                                          // Transpose
384
385
                                                          Matrix33 tr = ^(*this);
386
                                                          // Find Adjugate matrix
387
388
                                                      Matrix33 adj = tr.adjugate();
389
                                                           // Calculate the inverse by dividing the adjugate matrix by the determinant
391
                                                        r = adj * (1.0/determinant);
392
393
                                                        return (r);
394 }
```

5.5.3.4 Matrix33 Matrix33::operator* (const double & p) const [inherited]

Operator for scaling the matrix by a scalar.

Scales the current matrix by the scalar provided and returns the result in a third matrix.

Returns

Matrix containing the result of scaling the current matrix by the scalar provided as argument.

Definition at line 233 of file matrix33.cpp.

```
234 {
      int i, j;
Matrix33 r;
235
236
237
      for (i=0; i<3; i++)</pre>
2.38
239
240
          for (j=0; j<3; j++)
242
               r.x[i][j] = this->x[i][j] * p;
             }
243
244
       }
245
246
      return (r);
247 }
```

5.5.3.5 Matrix33 Matrix33::operator* (const Matrix33 & p) const [inherited]

Operator for the multiplication of two matrices.

Multiplies the current matrix with another 3x3 matrix and returns the result in a new matrix.

Returns

The result of the multiplication of the current matrix with the one provided as argument.

Definition at line 271 of file matrix33.cpp.

```
int i, j, k;
Matrix33 r;
274
275
276
      for (i=0; i<3; i++)</pre>
277
278
           for (j=0; j<3; j++)</pre>
279
280
               r.x[i][j] = 0.0;
281
              for (k=0; k<3; k++)
282
                    r.x[i][j] += this->x[i][k] * p.x[k][j];
283
284
285
             }
       }
287
288
     return (r);
289 }
```

5.5.3.6 Vector3d Matrix33::operator*(const Vector3d & v) const [inherited]

Operator for the multiplication of a matrix with a vector.

Returns in a vector the result of the multiplication of the current matrix with the provided vector.

Returns

The vector resulting from the multiplication of the current matrix with a vector.

Definition at line 311 of file matrix33.cpp.

5.5.3.7 void Matrix33::operator*=(const double & p) [inherited]

Operator for reflexive scaling of the matrix by a scalar.

Scales the current matrix by the scalar provided and populates the current matrix elements with the result.

Definition at line 253 of file matrix33.cpp.

```
254 {
255   int i, j;
256
257   for (i=0; i<3; i++)
258   {
259     for (j=0; j<3; j++)
260     {
261         this->x[i][j] *= p;
262   }
263   }
264 }
```

5.5.3.8 void Matrix33::operator*=(const Matrix33 & p) [inherited]

Operator for reflexive multiplication of two matrices.

Multiplies the current matrix with another 3x3 matrix and populates the elements of the current matrix with the result. Definition at line 295 of file matrix33.cpp.

```
296 {
297    Matrix33* r = new Matrix33;
298
299    *r = (*this) * p;
300    *this = *r;
301
302    delete(r);
303    r = NULL;
304 }
```

5.5.3.9 Matrix33 Matrix33::operator+(const Matrix33 & p) const [inherited]

Operator for addition of two matrices.

Adds the current matrix to the provided matrix and returns a third matrix with the result.

Returns

Matrix containing the sum of the present matrix and the one provided.

Definition at line 155 of file matrix33.cpp.

```
156 {
157    int i, j;
158    Matrix33 r;
159
160    for (i=0; i<3; i++)
161    {
162         for (j=0; j<3; j++)
163         {
```

5.5.3.10 void Matrix33::operator+= (const Matrix33 & p) [inherited]

Operator for reflexive addition of two matrices.

Adds the current matrix to the provided matrix and populates the current matrix elements with the result.

Definition at line 175 of file matrix33.cpp.

5.5.3.11 Matrix33 Matrix33::operator-(const Matrix33 & p) const [inherited]

Operator for the subtraction of two matrices.

Subtracts the given matrix from the current matrix and returns the result in a new matrix.

Returns

Matrix containing the result of subtracting the provided matrix from the current matrix.

Definition at line 194 of file matrix33.cpp.

```
195 {
196
      int i, j;
      Matrix33 r;
198
199
      for (i=0; i<3; i++)</pre>
200
          for (j=0; j<3; j++)</pre>
201
202
              r.x[i][j] = this->x[i][j] - p.x[i][j];
204
205
      }
206
207
     return (r);
208 }
```

5.5.3.12 void Matrix33::operator-= (const Matrix33 & p) [inherited]

Operator for reflexive subtraction of two matrices.

Subtracts the given matrix from the current matrix and populates the current matrix with the result.

Definition at line 214 of file matrix33.cpp.

```
215 {
216    int i, j;
217
218    for (i=0; i<3; i++)
219    {
220         for (j=0; j<3; j++)
```

5.5.3.13 Matrix33 Matrix33::operator^() const [inherited]

Transpose.

Performs the transpose of the current matrix.

Returns

A new matrix with the transpose of the current matrix.

Definition at line 333 of file matrix33.cpp.

```
334 {
335
      Matrix33 r;
336
      int i, j;
337
      for (i=0; i<3; i++)</pre>
338
339
340
           for (j=0; j<3; j++)</pre>
341
342
               r.x[i][j] = this->x[j][i];
343
344
        }
345
346
      return (r);
347 }
```

5.5.3.14 double Matrix33::operator ∼ () const [inherited]

Determinant.

Calculates the determinant of the current matrix.

Returns

Returns the determinant of the current matrix.

Definition at line 354 of file matrix33.cpp.

5.5.3.15 void Matrix33::setValue (int row, int column, double value) [inherited]

Function to set the value of an element indicated by its position.

The element indicated by the arguments row and column is set to the value provided. The values of row and column must correspond to array indices, and thus can be one of 0, 1 and 2. In any other case 0.0 is returned.

Parameters

row	Row index of the element.
column	Column index of the element.
value	Value that the element is to be set to.

Definition at line 93 of file matrix33.cpp.

5.5.4 Field Documentation

```
5.5.4.1 double Matrix33::x[3][3] [protected], [inherited]
```

Array containing the elements of the matrix.

Definition at line 26 of file matrix33.h.

The documentation for this class was generated from the following files:


- rotationMatrix.h
- rotationMatrix.cpp

5.6 Strain Class Reference


Strain class to represent the strain tensor.

```
#include <strain.h>
```

Inheritance diagram for Strain:



Collaboration diagram for Strain:



Public Member Functions

• Strain ()

Default constructor.

• Strain (double *principal, double *shear)

Constructor specifying the principal and shear strains.

void populateMatrix ()

Construct the strain tensor from the principal and shear strains.

double * getPrincipalStrains ()

Get the principal strains.

double * getShearStrains ()

Get the shear strains.

• Strain rotate (RotationMatrix alpha)

Rotate the strain tensor from one coordinate system to another.

• void setValue (int row, int column, double value)

Function to set the value of an element indicated by its position.

• double getValue (int row, int column)

Returns the value of the element located by the row and column indices provided.

• Matrix33 adjugate ()

Returns the adjugate matrix of the present matrix.

• Matrix33 operator+ (const Matrix33 &) const

Operator for addition of two matrices.

void operator+= (const Matrix33 &)

Operator for reflexive addition of two matrices.

Matrix33 operator- (const Matrix33 &) const

Operator for the subtraction of two matrices.

void operator-= (const Matrix33 &)

Operator for reflexive subtraction of two matrices.

• Matrix33 operator* (const double &) const

Operator for scaling the matrix by a scalar.

Matrix33 operator* (const Matrix33 &) const

Operator for the multiplication of two matrices.

Vector3d operator* (const Vector3d &) const

Operator for the multiplication of a matrix with a vector.

void operator*= (const double &)

5.6 Strain Class Reference 57

Operator for reflexive scaling of the matrix by a scalar.

void operator*= (const Matrix33 &)

Operator for reflexive multiplication of two matrices.

Matrix33 operator[∧] () const

Transpose.

- double operator \sim () const

Determinant.

• Matrix33 operator! () const

Inverse.

Protected Attributes

- double principalStrains [3]
- double shearStrains [3]
- double x [3][3]

Array containing the elements of the matrix.

5.6.1 Detailed Description

Strain class to represent the strain tensor.

The member functions of this class construct the symmetric strain tensor and operate on it.

Definition at line 21 of file strain.h.

5.6.2 Constructor & Destructor Documentation

```
5.6.2.1 Strain::Strain ( )
```

Default constructor.

Initializes the strain tensor with zeros.

Definition at line 16 of file strain.cpp.

```
17 {
18   int i, j;
19
20   for (i=0; i<3; i++)
21   {
22     principalStrains [i] = 0.0;
23     shearStrains [i] = 0.0;
24   }
25
   this->populateMatrix ();
27 }
```

5.6.2.2 Strain::Strain (double * principal, double * shear)

Constructor specifying the principal and shear strains.

The principal and shear strains are provided in the arguments and the symmetrical strain tensor is contstructed using them.

Parameters

principal	Pointer to the array containing principal strains.
shear	Pointer to the array containing shear strains.

Definition at line 35 of file strain.cpp.

```
36 {
37    int i;
38
39    for (i=0; i<3; i++)
40    {
41         this->principalStrains [i] = principal [i];
42         this->shearStrains [i] = shear [i];
43    }
44    this->populateMatrix ();
46 }
```

5.6.3 Member Function Documentation

5.6.3.1 Matrix33 Matrix33::adjugate() [inherited]

Returns the adjugate matrix of the present matrix.

The adjugate matrix of the present matrix is returned. The adjugate matrix is calculated by evaluating the determinant of the cofactor matrix of each element, and then replacing the corresponding element position by the value of the determinant. This operation is useful in calculating the inverse of a matrix.

Returns

The adjugate matrix of the present matrix.

Definition at line 129 of file matrix33.cpp.

```
130 {
     Matrix33 adj;
131
132
133
      adj.x[0][0] = (this->x[1][1]*this->x[2][2]) - (this->x[1][2]*this->x[2][1]);
      134
      adj.x[0][2] = (this->x[1][0]*this->x[2][1]) - (this->x[1][1]*this->x[2][0]);
135
136
     137
138
     adj.x[1][2] = (this->x[2][0]*this->x[0][1]) - (this->x[2][1]*this->x[0][0]);
140
     adj.x[2][0] = (this->x[0][1]*this->x[1][2]) - (this->x[0][2]*this->x[1][1]);
adj.x[2][1] = (this->x[0][2]*this->x[1][0]) - (this->x[0][0]*this->x[1][2]);
adj.x[2][2] = (this->x[0][0]*this->x[1][1]) - (this->x[1][0]*this->x[0][1]);
141
142
143
144
145
     return (adj);
146 }
```

$5.6.3.2 \quad double*Strain::getPrincipalStrains(\quad)$

Get the principal strains.

Returns a 3-member array with the principal strains: s11 s22 s33.

Returns

3-member array with the principal strains.

Definition at line 68 of file strain.cpp.

```
69 {
70     double p[3];
71     int i;
72
73     for (i=0; i<3; i++)
74         {
75          p[i] = this->principalStrains[i];
76     }
77
78     return (p);
79 }
```

5.6 Strain Class Reference 59

```
5.6.3.3 double * Strain::getShearStrains ( )
```

Get the shear strains.

Returns a 3-member array with the shear strains: s12 s13 s23.

Returns

3-member array with the shear strains.

Definition at line 86 of file strain.cpp.

```
87 {
88    double s[3];
89    int i;
90
91    for (i=0; i<3; i++)
92    {
93        s[i] = this->shearStrains[i];
94    }
95
96    return (s);
97 }
```

5.6.3.4 double Matrix33::getValue (int row, int column) [inherited]

Returns the value of the element located by the row and column indices provided.

The value of the element indicated by the arguments row and column is returned. The values of row and column must correspond to array indices, and thus can be one of 0, 1 and 2. In any other case 0.0 is returned.

Parameters

row	Row index of the element.
column	Column index of the element.

Returns

Value of the element located at the given position.

Definition at line 111 of file matrix33.cpp.

```
112 {
113     if (row>=0 && row<3)
114     {
115         if (column>=0 && column<3)
116         {
117             return (this->x[row][column]);
118         }
119     }
120     return (0.0);
121     return (0.0);
```

5.6.3.5 Matrix33 Matrix33::operator! () const [inherited]

Inverse.

Returns in a new matrix the inverse of the current matrix. If the current matrix is non-invertible, a zero matrix is returned.

Returns

Matrix with the inverse of the current matrix. If the current matrix is non-invertible, a zero matrix is returned.

Definition at line 370 of file matrix33.cpp.

```
371 {
372
     Matrix33 r; // Result matrix
373
374
     double determinant = ~(*this);
375
376
     if (determinant == 0.0)
377
         // The matrix is non-invertible
378
379
         return (r);
                         // Zero matrix
380
381
382
     // If we are still here, the matrix is invertible
383
     // Transpose
384
     Matrix33 tr = ^(*this);
385
386
387
      // Find Adjugate matrix
388
     Matrix33 adj = tr.adjugate();
389
     // Calculate the inverse by dividing the adjugate matrix by the determinant
390
     r = adj * (1.0/determinant);
391
392
393
     return (r);
394 }
```

5.6.3.6 Matrix33 Matrix33::operator* (const double & p) const [inherited]

Operator for scaling the matrix by a scalar.

Scales the current matrix by the scalar provided and returns the result in a third matrix.

Returns

Matrix containing the result of scaling the current matrix by the scalar provided as argument.

Definition at line 233 of file matrix33.cpp.

```
234 {
235
      int i, j;
      Matrix33 r;
236
237
238
      for (i=0; i<3; i++)</pre>
239
          for (j=0; j<3; j++)</pre>
240
241
               r.x[i][j] = this->x[i][j] * p;
243
244
       }
245
246
      return (r);
247 }
```

5.6.3.7 Matrix33 Matrix33::operator* (const Matrix33 & p) const [inherited]

Operator for the multiplication of two matrices.

Multiplies the current matrix with another 3x3 matrix and returns the result in a new matrix.

Returns

The result of the multiplication of the current matrix with the one provided as argument.

Definition at line 271 of file matrix33.cpp.

5.6 Strain Class Reference 61

```
int i, j, k;
Matrix33 r;
274
275
      for (i=0; i<3; i++)</pre>
276
          for (j=0; j<3; j++)</pre>
279
280
              r.x[i][j] = 0.0;
281
               for (k=0; k<3; k++)
282
283
                   r.x[i][j] += this->x[i][k] * p.x[k][j];
284
285
       }
286
287
288
      return (r);
289 }
```

5.6.3.8 Vector3d Matrix33::operator*(const Vector3d & v) const [inherited]

Operator for the multiplication of a matrix with a vector.

Returns in a vector the result of the multiplication of the current matrix with the provided vector.

Returns

The vector resulting from the multiplication of the current matrix with a vector.

Definition at line 311 of file matrix33.cpp.

```
313
      Vector3d r(0.0, 0.0, 0.0);
314
     int i, j;
315
316
      for (i=0; i<3; i++)</pre>
317
         for (j=0; j<3; j++)
318
319
320
              r[i] += this -> x[i][j] * v.x[j];
321
322
       }
323
324
     return (r);
325 }
```

5.6.3.9 void Matrix33::operator*=(const double & p) [inherited]

Operator for reflexive scaling of the matrix by a scalar.

Scales the current matrix by the scalar provided and populates the current matrix elements with the result.

Definition at line 253 of file matrix33.cpp.

```
254 {
255   int i, j;
256
257   for (i=0; i<3; i++)
258   {
259     for (j=0; j<3; j++)
260     {
261         this->x[i][j] *= p;
262     }
263   }
264 }
```

5.6.3.10 void Matrix33::operator*=(const Matrix33 & p) [inherited]

Operator for reflexive multiplication of two matrices.

Multiplies the current matrix with another 3x3 matrix and populates the elements of the current matrix with the result. Definition at line 295 of file matrix33.cpp.

```
296 {
297    Matrix33* r = new Matrix33;
298
299    *r = (*this) * p;
300    *this = *r;
301
302    delete(r);
303    r = NULL;
304 }
```

5.6.3.11 Matrix33 Matrix33::operator+(const Matrix33 & p) const [inherited]

Operator for addition of two matrices.

Adds the current matrix to the provided matrix and returns a third matrix with the result.

Returns

Matrix containing the sum of the present matrix and the one provided.

Definition at line 155 of file matrix33.cpp.

```
156 {
      int i, j;
158
     Matrix33 r;
159
160
      for (i=0; i<3; i++)</pre>
161
        for (j=0; j<3; j++)
162
163
164
              r.x[i][j] = this->x[i][j] + p.x[i][j];
165
      }
166
167
     return (r);
168
```

5.6.3.12 void Matrix33::operator+= (const Matrix33 & p) [inherited]

Operator for reflexive addition of two matrices.

Adds the current matrix to the provided matrix and populates the current matrix elements with the result.

Definition at line 175 of file matrix33.cpp.

```
176 {
177   int i, j;
178   for (i=0; i<3; i++)
180   {
181      for (j=0; j<3; j++)
182      {
183           this->x[i][j] += p.x[i][j];
184      }
185   }
186 }
```

5.6.3.13 Matrix33 Matrix33::operator-(const Matrix33 & p) const [inherited]

Operator for the subtraction of two matrices.

Subtracts the given matrix from the current matrix and returns the result in a new matrix.

5.6 Strain Class Reference 63

Returns

Matrix containing the result of subtracting the provided matrix from the current matrix.

Definition at line 194 of file matrix33.cpp.

```
195 {
     int i, j;
Matrix33 r;
196
197
198
199
      for (i=0; i<3; i++)
200
          for (j=0; j<3; j++)
201
202
              r.x[i][j] = this->x[i][j] - p.x[i][j];
203
204
205
206
207
     return (r);
208 }
```

5.6.3.14 void Matrix33::operator=(const Matrix33 & p) [inherited]

Operator for reflexive subtraction of two matrices.

Subtracts the given matrix from the current matrix and populates the current matrix with the result.

Definition at line 214 of file matrix33.cpp.

5.6.3.15 Matrix33 Matrix33::operator () const [inherited]

Transpose.

Performs the transpose of the current matrix.

Returns

A new matrix with the transpose of the current matrix.

Definition at line 333 of file matrix33.cpp.

```
334 {
      Matrix33 r;
335
336
      int i, j;
337
      for (i=0; i<3; i++)</pre>
338
339
340
          for (j=0; j<3; j++)</pre>
341
               r.x[i][j] = this->x[j][i];
342
343
344
345
346
      return (r);
347 }
```

```
5.6.3.16 double Matrix33::operator~( ) const [inherited]
```

Determinant.

Calculates the determinant of the current matrix.

Returns

Returns the determinant of the current matrix.

Definition at line 354 of file matrix33.cpp.

```
355 {
356
                                                                            double d = 0.0;
357
                                                                            358
                                                                              x[1][2]));
                                                                       d += this.x[0][1] * ( (this->x[1][2]*this->x[2][0]) - (this->x[1][0]*this-> (this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x[1][0]*this->x
359
                                                                            x[2][2]));
                                                                                                                                            this.x[0][2] * ( (this->x[1][0]*this->x[2][1]) - (this->x[2][0]*this->x[2][0] + (this->x[2][0]) + (this-x[2][0]) + (this-x[2]
                                                                            x[1][1]));
361
362
                                                                         return (d);
363 }
```

5.6.3.17 void Strain::populateMatrix ()

Construct the strain tensor from the principal and shear strains.

Takes the values in principalStrains and shearStrains and constructs the symmetrical strain matrix.

Definition at line 52 of file strain.cpp.

```
53 {
54    this->x[0][0] = this->principalStrains [0];
55    this->x[1][1] = this->principalStrains [1];
56    this->x[2][2] = this->principalStrains [2];
57
58    this->x[0][1] = this->x[1][0] = this->shearStrains [0];
59    this->x[0][2] = this->x[2][0] = this->shearStrains [1];
60    this->x[1][2] = this->x[2][1] = this->shearStrains [2];
61 }
```

5.6.3.18 Strain Strain::rotate (RotationMatrix alpha)

Rotate the strain tensor from one coordinate system to another.

Rotates the present strain matrix from one coordinate system to another using the rotation matrix supplied. The result is returned in a new Strain matrix.

Parameters

```
alpha Rotation matrix.
```

Returns

Rotated strain tensor.

Definition at line 105 of file strain.cpp.

```
106 {
107     Matrix33 alphaT = ^alpha; // Transpose
108     Strain sNew;
109
110     sNew = alpha * (*this) * alphaT; // Rotate the strain matrix
111
```

```
112 return (sNew);
113 }
```

5.6.3.19 void Matrix33::setValue (int row, int column, double value) [inherited]

Function to set the value of an element indicated by its position.

The element indicated by the arguments row and column is set to the value provided. The values of row and column must correspond to array indices, and thus can be one of 0, 1 and 2. In any other case 0.0 is returned.

Parameters

row	Row index of the element.	
column	Column index of the element.	
value	Value that the element is to be set to.	

Definition at line 93 of file matrix33.cpp.

```
94 {
95     if (row>=0 && row<3)
96     {
97         if (column>=0 && column<3)
98         {
99             this->x[row][column] = value;
100         }
101     }
102 }
```

5.6.4 Field Documentation

5.6.4.1 double Strain::principalStrains[3] [protected]

The three principal strains: s11, s22, s33.

Definition at line 27 of file strain.h.

5.6.4.2 double Strain::shearStrains[3] [protected]

The three shear strains: s12, s13, s23,

Definition at line 31 of file strain.h.

5.6.4.3 double Matrix33::x[3][3] [protected], [inherited]

Array containing the elements of the matrix.

Definition at line 26 of file matrix33.h.

The documentation for this class was generated from the following files:


- strain.h
- strain.cpp

5.7 Stress Class Reference


Stress class to represent the stress tensor.

```
#include <stress.h>
```

Inheritance diagram for Stress:



Collaboration diagram for Stress:



Public Member Functions

• Stress ()

Default constructor.

• Stress (double *principal, double *shear)

Constructor specifying the principal and shear stresses.

• void populateMatrix ()

Construct the stress tensor from the principal and shear stresses.

• double * getPrincipalStresses ()

Get the principal stresses.

• double * getShearStresses ()

Get the shear stresses.

Stress rotate (RotationMatrix alpha)

Rotate the stress tensor from one coordinate system to another.

• void setValue (int row, int column, double value)

Function to set the value of an element indicated by its position.

• double getValue (int row, int column)

Returns the value of the element located by the row and column indices provided.

• Matrix33 adjugate ()

Returns the adjugate matrix of the present matrix.

Matrix33 operator+ (const Matrix33 &) const

Operator for addition of two matrices.

void operator+= (const Matrix33 &)

Operator for reflexive addition of two matrices.

• Matrix33 operator- (const Matrix33 &) const

Operator for the subtraction of two matrices.

• void operator-= (const Matrix33 &)

Operator for reflexive subtraction of two matrices.

Matrix33 operator* (const double &) const

Operator for scaling the matrix by a scalar.

• Matrix33 operator* (const Matrix33 &) const

Operator for the multiplication of two matrices.

Vector3d operator* (const Vector3d &) const

Operator for the multiplication of a matrix with a vector.

void operator*= (const double &)

Operator for reflexive scaling of the matrix by a scalar.

void operator*= (const Matrix33 &)

Operator for reflexive multiplication of two matrices.

Matrix33 operator[∧] () const

Transpose.

• double operator \sim () const

Determinant.

• Matrix33 operator! () const

Inverse.

Protected Attributes

- double principalStresses [3]
- double shearStresses [3]
- double x [3][3]

Array containing the elements of the matrix.

5.7.1 Detailed Description

Stress class to represent the stress tensor.

The member functions of this class construct the symmetric stress tensor and operate on it.

Definition at line 21 of file stress.h.

5.7.2 Constructor & Destructor Documentation

5.7.2.1 Stress::Stress()

Default constructor.

Initializes the stress tensor with zeros.

Definition at line 16 of file stress.cpp.

```
17 {
18    int i, j;
19
20    for (i=0; i<3; i++)
21    {
22        principalStresses [i] = 0.0;
23        shearStresses [i] = 0.0;
24    }
25
26    this->populateMatrix ();
27 }
```

5.7.2.2 Stress::Stress (double * principal, double * shear)

Constructor specifying the principal and shear stresses.

The principal and shear stresses are provided in the arguments and the symmetrical stress tensor is contstructed using them.

Parameters

principal	Pointer to the array containing principal stresses.
shear	Pointer to the array containing shear stresses.

Definition at line 35 of file stress.cpp.

```
36 {
37    int i;
38
39    for (i=0; i<3; i++)
40    {
41        this->principalStresses [i] = principal [i];
42        this->shearStresses [i] = shear [i];
43    }
44
5    this->populateMatrix ();
46 }
```

5.7.3 Member Function Documentation

5.7.3.1 Matrix33 Matrix33::adjugate() [inherited]

Returns the adjugate matrix of the present matrix.

The adjugate matrix of the present matrix is returned. The adjugate matrix is calculated by evaluating the determinant of the cofactor matrix of each element, and then replacing the corresponding element position by the value of the determinant. This operation is useful in calculating the inverse of a matrix.

Returns

The adjugate matrix of the present matrix.

Definition at line 129 of file matrix33.cpp.

```
130 {
        Matrix33 adi:
131
132
        133
134
135
136
        adj.x[1][0] = (this->x[2][1]*this->x[0][2]) - (this->x[0][1]*this->x[2][2]);
adj.x[1][1] = (this->x[2][2]*this->x[0][0]) - (this->x[2][0]*this->x[0][2]);
137
138
        adj.x[1][2] = (this->x[2][0]*this->x[0][1]) - (this->x[2][1]*this->x[0][0]);
139
140
        adj.x[2][0] = (this->x[0][1]*this->x[1][2]) - (this->x[0][2]*this->x[1][1]);
adj.x[2][1] = (this->x[0][2]*this->x[1][0]) - (this->x[0][0]*this->x[1][2]);
adj.x[2][2] = (this->x[0][0]*this->x[1][1]) - (this->x[1][0]*this->x[0][1]);
141
142
143
144
145
        return (adj);
146 }
```

5.7 Stress Class Reference 69

```
5.7.3.2 double * Stress::getPrincipalStresses ( )
```

Get the principal stresses.

Returns a 3-member array with the principal stresses: s11 s22 s33.

Returns

3-member array with the principal stresses.

Definition at line 68 of file stress.cpp.

```
69 {
70     double p[3];
71     int i;
72
73     for (i=0; i<3; i++)
74      {
75         p[i] = this->principalStresses[i];
76     }
77
78     return (p);
79 }
```

5.7.3.3 double * Stress::getShearStresses ()

Get the shear stresses.

Returns a 3-member array with the shear stresses: s12 s13 s23.

Returns

3-member array with the shear stresses.

Definition at line 86 of file stress.cpp.

```
87 {
88     double s[3];
89     int i;
90
91     for (i=0; i<3; i++)
92     {
93         s[i] = this->shearStresses[i];
94     }
95
96     return (s);
97 }
```

5.7.3.4 double Matrix33::getValue (int row, int column) [inherited]

Returns the value of the element located by the row and column indices provided.

The value of the element indicated by the arguments row and column is returned. The values of row and column must correspond to array indices, and thus can be one of 0, 1 and 2. In any other case 0.0 is returned.

Parameters

row	Row index of the element.
column	Column index of the element.

Returns

Value of the element located at the given position.

Definition at line 111 of file matrix33.cpp.

```
112 {
113     if (row>=0 && row<3)
114     {
115         if (column>=0 && column<3)
116         {
117             return (this->x[row][column]);
118         }
119     }
120     return (0.0);
121     return (0.0);
```

5.7.3.5 Matrix33 Matrix33::operator! () const [inherited]

Inverse.

Returns in a new matrix the inverse of the current matrix. If the current matrix is non-invertible, a zero matrix is returned.

Returns

Matrix with the inverse of the current matrix. If the current matrix is non-invertible, a zero matrix is returned.

Definition at line 370 of file matrix33.cpp.

```
371 {
     Matrix33 r; // Result matrix
372
373
374
     double determinant = ~(*this);
375
376
     if (determinant == 0.0)
377
378
       // The matrix is non-invertible
379
         return (r);  // Zero matrix
380
381
382
     // If we are still here, the matrix is invertible
383
     // Transpose
384
385
     Matrix33 tr = ^(*this);
386
387
     // Find Adjugate matrix
388 Matrix33 adj = tr.adjugate();
389
390
     // Calculate the inverse by dividing the adjugate matrix by the determinant
391
     r = adj * (1.0/determinant);
392
393
     return (r);
394 }
```

5.7.3.6 Matrix33 Matrix33::operator* (const double & p) const [inherited]

Operator for scaling the matrix by a scalar.

Scales the current matrix by the scalar provided and returns the result in a third matrix.

Returns

Matrix containing the result of scaling the current matrix by the scalar provided as argument.

Definition at line 233 of file matrix33.cpp.

```
234 {
      int i, j;
Matrix33 r;
235
236
237
      for (i=0; i<3; i++)</pre>
238
239
         for (j=0; j<3; j++)
241
242
              r.x[i][j] = this->x[i][j] * p;
243
       }
244
245
246
      return (r);
```

5.7.3.7 Matrix33 Matrix33::operator* (const Matrix33 & p) const [inherited]

Operator for the multiplication of two matrices.

Multiplies the current matrix with another 3x3 matrix and returns the result in a new matrix.

Returns

The result of the multiplication of the current matrix with the one provided as argument.

Definition at line 271 of file matrix33.cpp.

```
272 {
      int i, j, k;
Matrix33 r;
273
274
275
276
      for (i=0; i<3; i++)</pre>
277
           for (j=0; j<3; j++)</pre>
278
279
               r.x[i][j] = 0.0;
281
               for (k=0; k<3; k++)
282
283
                    r.x[i][j] += this -> x[i][k] * p.x[k][j];
284
285
             }
286
       }
288
      return (r);
289 }
```

5.7.3.8 **Vector3d Matrix33::operator* (const Vector3d & v) const** [inherited]

Operator for the multiplication of a matrix with a vector.

Returns in a vector the result of the multiplication of the current matrix with the provided vector.

Returns

The vector resulting from the multiplication of the current matrix with a vector.

Definition at line 311 of file matrix33.cpp.

```
312 {
313
      Vector3d r(0.0, 0.0, 0.0);
314
     int i, j;
315
316
      for (i=0; i<3; i++)</pre>
317
318
        for (j=0; j<3; j++)
320
              r[i] += this -> x[i][j] * v.x[j];
321
322
      }
323
324
     return (r);
325 }
```

```
5.7.3.9 void Matrix33::operator*=(const double & p) [inherited]
```

Operator for reflexive scaling of the matrix by a scalar.

Scales the current matrix by the scalar provided and populates the current matrix elements with the result.

Definition at line 253 of file matrix33.cpp.

```
254 {
255   int i, j;
256
257   for (i=0; i<3; i++)
258   {
259     for (j=0; j<3; j++)
260     {
261         this->x[i][j] *= p;
262     }
263   }
264 }
```

5.7.3.10 void Matrix33::operator*=(const Matrix33 & p) [inherited]

Operator for reflexive multiplication of two matrices.

Multiplies the current matrix with another 3x3 matrix and populates the elements of the current matrix with the result. Definition at line 295 of file matrix33.cpp.

```
296 {
297    Matrix33* r = new Matrix33;
298
299    *r = (*this) * p;
300    *this = *r;
301
302    delete(r);
303    r = NULL;
304 }
```

5.7.3.11 Matrix33 Matrix33::operator+(const Matrix33 & p) const [inherited]

Operator for addition of two matrices.

Adds the current matrix to the provided matrix and returns a third matrix with the result.

Returns

Matrix containing the sum of the present matrix and the one provided.

Definition at line 155 of file matrix33.cpp.

```
156 {
157
      int i, j;
      Matrix33 r;
158
159
      for (i=0; i<3; i++)</pre>
160
161
162
          for (j=0; j<3; j++)
163
               r.x[i][j] = this->x[i][j] + p.x[i][j];
164
165
        1
166
167
      return (r);
```

5.7 Stress Class Reference 73

```
5.7.3.12 void Matrix33::operator+=(const Matrix33 & p) [inherited]
```

Operator for reflexive addition of two matrices.

Adds the current matrix to the provided matrix and populates the current matrix elements with the result.

Definition at line 175 of file matrix33.cpp.

5.7.3.13 Matrix33 Matrix33::operator-(const Matrix33 & p) const [inherited]

Operator for the subtraction of two matrices.

Subtracts the given matrix from the current matrix and returns the result in a new matrix.

Returns

Matrix containing the result of subtracting the provided matrix from the current matrix.

Definition at line 194 of file matrix33.cpp.

```
int i, j;
Matrix33 r;
196
197
198
      for (i=0; i<3; i++)</pre>
199
200
          for (j=0; j<3; j++)</pre>
201
202
203
               r.x[i][j] = this->x[i][j] - p.x[i][j];
204
205
        }
206
207
      return (r);
208 }
```

5.7.3.14 void Matrix33::operator=(const Matrix33 & p) [inherited]

Operator for reflexive subtraction of two matrices.

Subtracts the given matrix from the current matrix and populates the current matrix with the result.

Definition at line 214 of file matrix33.cpp.

```
215 {
216    int i, j;
217
218    for (i=0; i<3; i++)
219    {
220         for (j=0; j<3; j++)
221         {
222             this->x[i][j] -= p.x[i][j];
223         }
224    }
225 }
```

```
5.7.3.15 Matrix33 Matrix33::operator ( ) const [inherited]
```

Transpose.

Performs the transpose of the current matrix.

Returns

A new matrix with the transpose of the current matrix.

Definition at line 333 of file matrix33.cpp.

```
334 {
335
      Matrix33 r;
336
      int i, j;
337
      for (i=0; i<3; i++)</pre>
338
339
340
          for (j=0; j<3; j++)</pre>
341
342
               r.x[i][j] = this->x[j][i];
343
       }
344
345
346
      return (r);
347 }
```

```
5.7.3.16 double Matrix33::operator\sim ( ) const [inherited]
```

Determinant.

Calculates the determinant of the current matrix.

Returns

Returns the determinant of the current matrix.

Definition at line 354 of file matrix33.cpp.

```
355 {
356
                                          double d = 0.0;
357
                                         358
                                          x[1][2]);
                                       d += this.x[0][1] * ((this->x[1][2]*this->x[2][0]) - (this->x[1][0]*this->
359
360
                                      d \mathrel{+=} this.x[0][2] \mathrel{*} ( (this->x[1][0]*this->x[2][1]) - (this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this->x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2][0]*this--x[2
                                          x[1][1]));
361
                                         return (d);
362
363 }
```

5.7.3.17 void Stress::populateMatrix ()

Construct the stress tensor from the principal and shear stresses.

Takes the values in principalStresses and shearStresses and constructs the symmetrical stress matrix.

Definition at line 52 of file stress.cpp.

```
53 {
54     this->x[0][0] = this->principalStresses [0];
55     this->x[1][1] = this->principalStresses [1];
56     this->x[2][2] = this->principalStresses [2];
57
58     this->x[0][1] = this->x[1][0] = this->shearStresses [0];
59     this->x[0][2] = this->x[2][0] = this->shearStresses [1];
60     this->x[1][2] = this->x[2][1] = this->shearStresses [2];
61 }
```

5.7 Stress Class Reference 75

5.7.3.18 Stress Stress::rotate (RotationMatrix alpha)

Rotate the stress tensor from one coordinate system to another.

Rotates the present stress matrix from one coordinate system to another using the rotation matrix supplied. The result is returned in a new Stress matrix.

Parameters

```
alpha Rotation matrix.
```

Returns

Rotated stress tensor.

Definition at line 105 of file stress.cpp.

5.7.3.19 void Matrix33::setValue (int row, int column, double value) [inherited]

Function to set the value of an element indicated by its position.

The element indicated by the arguments row and column is set to the value provided. The values of row and column must correspond to array indices, and thus can be one of 0, 1 and 2. In any other case 0.0 is returned.

Parameters

row	Row index of the element.	
column	Column index of the element.	
value	Value that the element is to be set to.	

Definition at line 93 of file matrix33.cpp.

5.7.4 Field Documentation

5.7.4.1 double Stress::principalStresses[3] [protected]

The three principal stresses: s11, s22, s33.

Definition at line 27 of file stress.h.

5.7.4.2 double Stress::shearStresses[3] [protected]

The three shear stresses: s12, s13, s23,

Definition at line 31 of file stress.h.

```
5.7.4.3 double Matrix33::x[3][3] [protected], [inherited]
```

Array containing the elements of the matrix.

Definition at line 26 of file matrix33.h.

The documentation for this class was generated from the following files:

- · stress.h
- · stress.cpp

5.8 Vector3d Class Reference

Vector3d class representing a single 3-dimensional vector in the simulation.

```
#include <vector3d.h>
```

Public Member Functions

· Vector3d ()

Default constructor.

Vector3d (double *a)

Constructor with values provided in an array.

• Vector3d (double a1, double a2, double a3)

Constructor with values provided explicitly.

void setValue (int index, double value)

Function to set the value of an element of the vector.

void setVector (double *a)

Function to set the value of the entire vector using an array.

double getValue (int index)

Function to get the value of an element of the vector.

double * getVector ()

Function to get the values of the elements of the vector in an array.

• double sum ()

Computes the sum of the elements of the vector.

• double magnitude ()

Computes the magnitude of the vector.

Vector3d normalize ()

Returns the vector normalized to be a unit vector.

• Vector3d operator+ (const Vector3d &) const

Operator for addition of two vectors.

void operator+= (const Vector3d &)

Operator for reflexive addition of two vectors.

Vector3d operator- (const Vector3d &) const

Operator for the subtraction of two vectors.

void operator-= (const Vector3d &)

Operator for reflexive subtraction of two vectors.

Vector3d operator* (const double &) const

Operator for scaling the vector by a scalar.

• void operator*= (const double &)

Operator for reflexive scaling of the vector by a scalar.

double operator* (const Vector3d &) const

Operator for the scalar product of two vectors.

Vector3d operator[∧] (const Vector3d &) const

Operator for the vector product of two vectors.

void operator[^]= (const Vector3d &)

Operator for reflexive vector product of two vectors.

Protected Attributes

• double x [3]

The elements of the vector.

5.8.1 Detailed Description

Vector3d class representing a single 3-dimensional vector in the simulation.

This class represents a vector in 3D space. The member functions and operators define various operations on the vector and its interactions with other data types.

Definition at line 20 of file vector3d.h.

5.8.2 Constructor & Destructor Documentation

```
5.8.2.1 Vector3d::Vector3d()
```

Default constructor.

Initializes the vector with all elements equal to 0.0.

Definition at line 16 of file vector3d.cpp.

```
17 {
18    this->x[0] = 0.0;
19    this->x[1] = 0.0;
20    this->x[2] = 0.0;
21 }
```

5.8.2.2 Vector3d::Vector3d (double * a)

Constructor with values provided in an array.

Initializes the vector with the values provided in the array.

Parameters

```
a Pointer to the array containing the elements of the vector
```

Definition at line 28 of file vector3d.cpp.

```
29 {
30    this->x[0] = a[0];
31    this->x[1] = a[1];
32    this->x[2] = a[2];
33    }
```

5.8.2.3 Vector3d::Vector3d (double a1, double a2, double a3)

Constructor with values provided explicitly.

Initializes the vector with the three values provided as arguments.

Parameters

a1	Value of the first element of the vector.
a2	Value of the second element of the vector.
аЗ	Value of the third element of the vector.

Definition at line 42 of file vector3d.cpp.

```
43 {
44    this->x[0] = a1;
45    this->x[1] = a2;
46    this->x[2] = a3;
```

5.8.3 Member Function Documentation

5.8.3.1 double Vector3d::getValue (int index)

Function to get the value of an element of the vector.

Returns the value of the element at the position indicated by the argument index.

Parameters

index	Index of the element whose value is to be got.

Returns

The value of the element of the vector at the position

Definition at line 83 of file vector3d.cpp.

```
84 {
85     if (index>=0 && index<3)
86     {
87         return (this->x[index]);
88     }
89     else
90     {
91         return (0);
92     }
93 }
```

5.8.3.2 double * Vector3d::getVector()

Function to get the values of the elements of the vector in an array.

The vector is returned in an array.

Returns

Pointer to the first term of an array containing the elements of the vector.

Definition at line 100 of file vector3d.cpp.

```
101 {
```

5.8.3.3 double Vector3d::magnitude ()

Computes the magnitude of the vector.

Computes the magnitude of the vector. Basically the square root of the sum of the squares of the vector elements.

Returns

The magnitude of the vector.

Definition at line 134 of file vector3d.cpp.

5.8.3.4 Vector3d Vector3d::normalize ()

Returns the vector normalized to be a unit vector.

This function normalizes a vector by dividing its elements by the magnitude. In case the magnitude is zero, a zero vector is returned.

Returns

Normalized vector.

Definition at line 152 of file vector3d.cpp.

```
153 {
     double m = this->magnitude ();
154
156
     if (m==0.0)
     return (Vector3d ());
}
157
158
159
160
     else
161
    {
162
       return ((*this) * (1.0/m));
163
     }
164 }
```

5.8.3.5 Vector3d Vector3d::operator* (const double & p) const

Operator for scaling the vector by a scalar.

Scales the current vector by the scalar provided and returns the result in a third vector.

Returns

Vector containing the result of scaling the current vector by the scala provided as argument.

Definition at line 239 of file vector3d.cpp.

5.8.3.6 double Vector3d::operator* (const Vector3d & p) const

Operator for the scalar product of two vectors.

Performs the scalar product or dot product of the current vector with the one provided as argument and returns the result.

Returns

Scalar value of the scalar product of dot product of the current vector with the one provided as argument.

Definition at line 271 of file vector3d.cpp.

5.8.3.7 void Vector3d::operator*= (const double & p)

Operator for reflexive scaling of the vector by a scalar.

Scales the current vector by the scalar provided and populates the current vector elements with the result.

Definition at line 256 of file vector3d.cpp.

```
257 {
258    int i;
259
260    for (i=0; i<3; i++)
261    {
262        this->x[i] *= p;
263    }
264 }
```

5.8.3.8 Vector3d Vector3d::operator+ (const Vector3d & p) const

Operator for addition of two vectors.

Adds the current vector to the provided vector and returns a third vector with the result.

Returns

Vector containing the sum of the current vector with the one provided as argument.

Definition at line 173 of file vector3d.cpp.

5.8.3.9 void Vector3d::operator+= (const Vector3d & p)

Operator for reflexive addition of two vectors.

Adds the current vector to the provided vector and populates the current vector elements with the result.

Definition at line 190 of file vector3d.cpp.

```
191 {
192    int i;
193
194    for (i=0; i<3; i++)
195     {
196         this->x[i] += p.x[i];
197    }
198 }
```

5.8.3.10 Vector3d Vector3d::operator-(const Vector3d & p) const

Operator for the subtraction of two vectors.

Subtracts the given vector from the current vector and returns the result in a new vector.

Returns

Vector containing the result of subtracting the vector provided as argument from the current vector.

Definition at line 206 of file vector3d.cpp.

5.8.3.11 void Vector3d::operator-= (const Vector3d & p)

Operator for reflexive subtraction of two vectors.

Subtracts the given vector from the current vector and populates the current vector with the result.

Definition at line 223 of file vector3d.cpp.

```
224 {
225   int i;
226
227   for (i=0; i<3; i++)
228   {
229     this->x[i] -= p.x[i];
230   }
231 }
```

5.8.3.12 Vector3d Vector3d::operator (const Vector3d & p) const

Operator for the vector product of two vectors.

Evaluates the vector product of the current vector with the provided vector and returns the result in a third vector.

Returns

Vector containing the result of the vector product of the current vector with the one provided as argument.

Definition at line 289 of file vector3d.cpp.

```
290 {
291    Vector3d r(0.0, 0.0, 0.0);
292
293    r.x[0] = (this->x[1] * p.x[2]) - (this->x[2] * p.x[1]);
294    r.x[1] = (this->x[2] * p.x[0]) - (this->x[0] * p.x[2]);
295    r.x[2] = (this->x[0] * p.x[1]) - (this->x[1] * p.x[0]);
296
297    return (r);
298 }
```

5.8.3.13 void Vector3d::operator $^{\wedge}$ = (const Vector3d & p)

Operator for reflexive vector product of two vectors.

Evaluates the vector product of the current vector and the one provided, and populates the result in the current vector.

Definition at line 304 of file vector3d.cpp.

```
305 {
306
    Vector3d* r = Vector3d(0.0, 0.0, 0.0);
307
   308
309
311
312
    *this = *r;
313
314
   delete (r);
315
   r = NULL;
316 }
```

5.8.3.14 void Vector3d::setValue (int index, double value)

Function to set the value of an element of the vector.

Sets the value of the element indicated by the index argument.

Parameters

index	Index of the element whose value is to be set.
value	Value that is to be given to the element.

Definition at line 56 of file vector3d.cpp.

```
57 {
58    if (index>=0 && index <3)
59    {
60       this->x[index] = value;
61    }
62 }
```

5.8.3.15 void Vector3d::setVector (double * a)

Function to set the value of the entire vector using an array.

Sets the values of the elements if the vector to values in the array pointed to by the argument a.

Parameters

a Pointer of the array containing the values of the elements of the vector.

Definition at line 69 of file vector3d.cpp.

```
70 {
71     this->x[0] = a[0];
72     this->x[1] = a[1];
73     this->x[2] = a[2];
74 }
```

5.8.3.16 double Vector3d::sum ()

Computes the sum of the elements of the vector.

Sums the elements of the vector and returns the result.

Returns

The sum of the elements of the vector.

Definition at line 116 of file vector3d.cpp.

5.8.4 Field Documentation

5.8.4.1 double Vector3d::x[3] [protected]

The elements of the vector.

Definition at line 26 of file vector3d.h.

The documentation for this class was generated from the following files:

- · vector3d.h
- · vector3d.cpp




Chapter 6

File Documentation

6.1 constants.h File Reference

Definition of constants used in the program.

This graph shows which files directly or indirectly include this file:



Macros

• #define PI 3.141592654

The irrational number pi.

• #define SQRT2 1.414213562

The square root of 2.

• #define SQRT3 1.732050808

The square root of 3.

• #define SQRT5 2.236067978

The square root of 5.

6.1.1 Detailed Description

Definition of constants used in the program.

Author

Adhish Majumdar

Version

0.0

Date

26/04/2013

This file defines the values of various constants used in the program.

Definition in file constants.h.

6.1.2 Macro Definition Documentation

6.1.2.1 #define PI 3.141592654

The irrational number pi.

Definition at line 16 of file constants.h.

6.1.2.2 #define SQRT2 1.414213562

The square root of 2.

Definition at line 21 of file constants.h.

6.1.2.3 #define SQRT3 1.732050808

The square root of 3.

Definition at line 26 of file constants.h.

6.1.2.4 #define SQRT5 2.236067978


The square root of 5.

Definition at line 31 of file constants.h.

6.2 defect.cpp File Reference

Definition of member functions of the Defect class.

#include "defect.h"
Include dependency graph for defect.cpp:



6.2.1 Detailed Description

Definition of member functions of the Defect class.

Author

Adhish Majumdar

Version

0.0

Date

22/04/2013


This file defines the member functions of the Defect class representing a single defect in the simulation. Definition in file defect.cpp.

6.3 defect.h File Reference


Definition of the **Defect** class.

#include "stress.h"

Include dependency graph for defect.h:



This graph shows which files directly or indirectly include this file:



Data Structures

class Defect

Class Defect representing a generic defect in a material.

6.3.1 Detailed Description

Definition of the **Defect** class.

Author

Adhish Majumdar

Version

0.0

Date

27/05/2013


This file defines the Defect class representing an defect in the simulation. This is simply a generic description class with virtual functions. Later classes like dislocations, precipitates, boundaries etc will inherit from this class.

Definition in file defect.h.

6.4 dislocation.cpp File Reference

Definition of constructors and member functions of the Dislocation class.

#include "dislocation.h"
Include dependency graph for dislocation.cpp:



6.4.1 Detailed Description

Definition of constructors and member functions of the Dislocation class.

Author

Adhish Majumdar

Version

0.0

Date

29/04/2013


This file defines the constructors and member functions of the Dislocation class. This class inherits from the Defect class.

Definition in file dislocation.cpp.


6.5 dislocation.h File Reference

Definition of the Dislocation class.

```
#include "defect.h"
#include "dislocationDefaults.h"
#include "constants.h"
Include dependency graph for dislocation.h:
```



This graph shows which files directly or indirectly include this file:



Data Structures

· class Dislocation

Dislocation class representing a dislocation in the simulation.

6.5.1 Detailed Description

Definition of the Dislocation class.

Author

Adhish Majumdar

Version

0.0

Date

29/04/2013


This file defines the Dislocation class representing a dislocation in the simulation. This class inherits from the Defect class.

Definition in file dislocation.h.

6.6 dislocationDefaults.h File Reference

Definition of certain default values for members of the Dislocation class.

This graph shows which files directly or indirectly include this file:



Macros

• #define DEFAULT_POSITION_0 0.0

Default value of the position vector x-coordinate.

• #define DEFAULT_POSITION_1 0.0

Default value of the position vector y-coordinate.

• #define DEFAULT_POSITION_2 0.0

Default value of the position vector z-coordinate.

• #define DEFAULT BURGERS MAGNITUDE 5.0e-09

Default value of the magnitude of the Burgers vector.

• #define DEFAULT_BURGERS_0 1.0

Default value of the Burgers vector x-coordinate.

• #define DEFAULT BURGERS 1 1.0

Default value of the Burgers vector y-coordinate.

#define DEFAULT_BURGERS_2 0.0

Default value of the Burgers vector z-coordinate.

#define DEFAULT_LINEVECTOR_0 1.0

Default value of the line vector x-coordinate.

• #define DEFAULT_LINEVECTOR_1 -1.0

Default value of the line vector y-coordinate.

#define DEFAULT_LINEVECTOR_2 -2.0

Default value of the line vector z-coordinate.

6.6.1 Detailed Description

Definition of certain default values for members of the Dislocation class.

Author

Adhish Majumdar

Version

0.0

Date

26/04/2013

This file defines some default values for members of the Dislocation class representing a dislocation in the simulation.

Definition in file dislocationDefaults.h.

6.6.2 Macro Definition Documentation

6.6.2.1 #define DEFAULT_BURGERS_0 1.0

Default value of the Burgers vector x-coordinate.

Definition at line 34 of file dislocationDefaults.h.

6.6.2.2 #define DEFAULT_BURGERS_1 1.0

Default value of the Burgers vector y-coordinate.

Definition at line 38 of file dislocationDefaults.h.

6.6.2.3 #define DEFAULT_BURGERS_2 0.0

Default value of the Burgers vector z-coordinate.

Definition at line 42 of file dislocationDefaults.h.

6.6.2.4 #define DEFAULT_BURGERS_MAGNITUDE 5.0e-09

Default value of the magnitude of the Burgers vector.

Definition at line 29 of file dislocationDefaults.h.

6.6.2.5 #define DEFAULT_LINEVECTOR_0 1.0

Default value of the line vector x-coordinate.

Definition at line 47 of file dislocationDefaults.h.

6.6.2.6 #define DEFAULT_LINEVECTOR_1 -1.0

Default value of the line vector y-coordinate.

Definition at line 51 of file dislocationDefaults.h.

6627	#define	DEEALILT	LINEVECTOR	2 -2 0
0.0.2./	#OBINE	DEFAULT	LINEVECTOR	/ -/ ·U

Default value of the line vector z-coordinate.

Definition at line 55 of file dislocationDefaults.h.

6.6.2.8 #define DEFAULT_POSITION_0 0.0

Default value of the position vector x-coordinate.

Definition at line 16 of file dislocationDefaults.h.

6.6.2.9 #define DEFAULT_POSITION_1 0.0

Default value of the position vector y-coordinate.

Definition at line 20 of file dislocationDefaults.h.

6.6.2.10 #define DEFAULT_POSITION_2 0.0

Default value of the position vector z-coordinate.


Definition at line 24 of file dislocationDefaults.h.

6.7 dislocationSource.cpp File Reference

Definition of the member functions of the DislocationSource class.

#include "dislocationSource.h"

Include dependency graph for dislocationSource.cpp:



6.7.1 Detailed Description

Definition of the member functions of the DislocationSource class.

Author

Adhish Majumdar

Version

0.0

Date

27/05/2013


This file defines the member functions of the DislocationSource class representing a source of dislocations in the simulation. This class inherits from the Defect class. This object is basically the representation of a Frank-Read source emitting dislocation dipoles. When the dislocation source experiences a shear stress greater than a critical value for a certain amount of time (or number of iterations), it emits a dislocation dipole with a length that is a function of the applied stress.

Definition in file dislocationSource.cpp.


6.8 dislocationSource.h File Reference

Definition of the DislocationSource class.

```
#include "dislocation.h"
#include "constants.h"
#include "dislocationDefaults.h"
#include "dislocationSourceDefaults.h"
Include dependency graph for dislocationSource.h:
```



This graph shows which files directly or indirectly include this file:



Data Structures

· class DislocationSource

DislocationSource class representing a source of dislocations in the simulation.

6.8.1 Detailed Description

Definition of the DislocationSource class.

Author

Adhish Majumdar

Version

0.0

Date

27/05/2013


This file defines the DislocationSource class representing a source of dislocations in the simulation. This class inherits from the Defect class. This object is basically the representation of a Frank-Read source emitting dislocation dipoles. When the dislocation source experiences a shear stress greater than a critical value for a certain amount of time (or number of iterations), it emits a dislocation dipole with a length that is a function of the applied stress.

Definition in file dislocationSource.h.

6.9 dislocationSourceDefaults.h File Reference

Definition of certain default values for members of the DislocationSource class.

This graph shows which files directly or indirectly include this file:



Macros

- #define DEFAULT_TAU_CRITICAL 1.0e09
 - Default value of the critical shear stress for a dislocation source to emit a dipole.
- #define DEFAULT_NITERATIONS 10

Default value of the number of iterations required for a dislocation source to emit a dipole.

6.9.1 Detailed Description

Definition of certain default values for members of the DislocationSource class.

Author

Adhish Majumdar

Version

0.0

Date

02/05/2013

This file defines some default values for members of the DislocationSource class representing a dislocation dipole source in the simulation.

Definition in file dislocationSourceDefaults.h.

6.9.2 Macro Definition Documentation

6.9.2.1 #define DEFAULT_NITERATIONS 10

Default value of the number of iterations required for a dislocation source to emit a dipole.

The dislocation source must experience a shear stress greater than the critical value in order to emit a dipole. This time is expressed in terms of the number of iterations here.

Definition at line 23 of file dislocationSourceDefaults.h.

6.9.2.2 #define DEFAULT_TAU_CRITICAL 1.0e09

Default value of the critical shear stress for a dislocation source to emit a dipole.

Default value of the critical shear stress for a dislocation source to emit a dipole. The number is expressed in Pa.

Definition at line 17 of file dislocationSourceDefaults.h.


6.10 mainpage.dox File Reference

6.11 matrix33.cpp File Reference

Definition of the member functions and operators of the Matrix33 class.

```
#include "matrix33.h"
```

Include dependency graph for matrix33.cpp:



6.11.1 Detailed Description

Definition of the member functions and operators of the Matrix33 class.

Author

Adhish Majumdar

Version

0.0

Date

22/04/2013


This file defines the member functions and operators of the Matrix33 class representing a 3x3 matrix in the simulation.

Definition in file matrix33.cpp.


6.12 matrix33.h File Reference

Definition of the Matrix33 class.

#include "vector3d.h"
Include dependency graph for matrix33.h:



This graph shows which files directly or indirectly include this file:



Data Structures

• class Matrix33

Matrix33 class representing a 3x3 square matrix.

6.12.1 Detailed Description

Definition of the Matrix33 class.

Author

Adhish Majumdar

Version

0.0

Date

22/04/2013

This file defines the Matrix33 class representing a 3x3 matrix in the simulation.

Definition in file matrix33.h.

6.13 rotationMatrix.cpp File Reference

Definition of the RotationMatrix class member functions.

6.13.1 Detailed Description

Definition of the RotationMatrix class member functions.

Author

Adhish Majumdar

Version

0.0

Date


25/04/2013

This file defines member functions of the RotationMatrix class for carrying out 3D rotations and axes transformations. Definition in file rotationMatrix.cpp.


6.14 rotationMatrix.h File Reference

Definition of the RotationMatrix class.

```
#include "matrix33.h"
Include dependency graph for rotationMatrix.h:
```



This graph shows which files directly or indirectly include this file:



Data Structures

· class RotationMatrix

RotationMatrix class to represent a rotation matrix.

6.14.1 Detailed Description

Definition of the RotationMatrix class.

Author

Adhish Majumdar

Version

0.0

Date

25/04/2013

This file defines the RotationMatrix class for carrying out 3D rotations and axes transformations.


Definition in file rotationMatrix.h.

6.15 strain.cpp File Reference

Definition of the member functions if the Strain class.

#include "strain.h"

Include dependency graph for strain.cpp:



6.15.1 Detailed Description

Definition of the member functions if the Strain class.

Author

Adhish Majumdar

Version

0.0

Date

22/04/2013


This file defines the member functions of the Strain class for the strain tensor.

Definition in file strain.cpp.


6.16 strain.h File Reference

Definition of the Strain class.

```
#include "matrix33.h"
#include "rotationMatrix.h"
Include dependency graph for strain.h:
```



This graph shows which files directly or indirectly include this file:



Data Structures

• class Strain

Strain class to represent the strain tensor.

6.16.1 Detailed Description

Definition of the Strain class.

Author

Adhish Majumdar

Version

0.0

Date

25/04/2013


This file defines the Strain class for the strain tensor.

Definition in file strain.h.

6.17 stress.cpp File Reference

Definition of the member functions if the Stress class.

#include "stress.h"
Include dependency graph for stress.cpp:



6.17.1 Detailed Description

Definition of the member functions if the Stress class.

Author

Adhish Majumdar

Version

0.0

Date

22/04/2013


This file defines the member functions of the Stress class for the stress tensor.

Definition in file stress.cpp.


6.18 stress.h File Reference

Definition of the Stress class.

```
#include "matrix33.h"
#include "rotationMatrix.h"
Include dependency graph for stress.h:
```



This graph shows which files directly or indirectly include this file:



Data Structures

class Stress

Stress class to represent the stress tensor.

6.18.1 Detailed Description

Definition of the Stress class.

Author

Adhish Majumdar

Version

0.0

Date

22/04/2013

This file defines the Stress class for the stress tensor.


Definition in file stress.h.

6.19 vector3d.cpp File Reference

Definition of member functions and operators of the Vector3d class.

#include "vector3d.h"

Include dependency graph for vector3d.cpp:



6.19.1 Detailed Description

Definition of member functions and operators of the Vector3d class.

Author

Adhish Majumdar

Version

0.0

Date

29/04/2013

This file defines the member functions and operators of the Vector3d class representing a single 3-dimensional vector in the simulation.


Definition in file vector3d.cpp.

6.20 vector3d.h File Reference


Definition of the Vector3d class.

#include <math.h>

Include dependency graph for vector3d.h:



This graph shows which files directly or indirectly include this file:



Data Structures

class Vector3d

Vector3d class representing a single 3-dimensional vector in the simulation.

6.20.1 Detailed Description

Definition of the Vector3d class.

Author

Adhish Majumdar

Version

0.0

Date

29/04/2013

This file defines the Vector3d class representing a single 3-dimensional vector in the simulation.

Definition in file vector3d.h.

Index

adjugate	defect.h, 88
Matrix33, 40	dipoleNucleationLength
RotationMatrix, 49	DislocationSource, 29
Strain, 58	Dislocation, 15
Stress, 68	bmag, 24
	bvec, 24
bmag	calculateRotationMatrix, 18
Dislocation, 24	Dislocation, 17, 18
DislocationSource, 36	getBurgers, 19
bvec	getLineVector, 19
Dislocation, 24	getPosition, 19
DislocationSource, 36	getX, 20
	getY, 20
calculateRotationMatrix	getZ, 20
Dislocation, 18	lvec, 24
constants.h, 85	mobile, 24
PI, 86	pos, 25
SQRT2, 86	rotationMatrix, 25
SQRT3, 86	setBurgers, 20
SQRT5, 86	setLineVector, 21
countIterations	setMobile, 21
DislocationSource, 36	setPinned, 21
DEEALU T DUDOEDO A	setPosition, 21, 22
DEFAULT_BURGERS_0	setX, 22
dislocationDefaults.h, 94	setY, 22
DEFAULT_BURGERS_1	setZ, 23
dislocationDefaults.h, 94	stressField, 23
DEFAULT_BURGERS_2	stressFieldLocal, 23
dislocationDefaults.h, 94	dislocation.cpp, 89
DEFAULT_NITERATIONS	dislocation.h, 91
dislocationSourceDefaults.h, 99	dislocationDefaults.h, 92
DEFAULT_POSITION_0	DEFAULT BURGERS 0, 94
dislocationDefaults.h, 95	DEFAULT BURGERS 1, 94
DEFAULT_POSITION_1	DEFAULT BURGERS 2, 94
dislocationDefaults.h, 95	DEFAULT POSITION 0, 95
DEFAULT_POSITION_2	DEFAULT POSITION 1, 95
dislocationDefaults.h, 95	DEFAULT_POSITION_2, 95
Defect, 9	DislocationSource, 25
Defect, 11	bmag, 36
getPosition, 11, 12	bridg, 36
getX, 12	countIterations, 36
getY, 12	dipoleNucleationLength, 29
getZ, 12	DislocationSource, 28
pos, 15	DislocationSource, 28
setPosition, 13	
setX, 14	getBurgers, 29
setY, 14	getBurgersMag, 29
setZ, 14	getlterationCount, 30 getLineVector, 30
stressField, 14	getNumIterations, 30
defect.cpp, 86	genvarinterations, so

INDEX 115

getPosition, 30, 31	Vector3d, 78
getTauCritical, 31	getVector
getX, 31	Vector3d, 78
getY, 31	getX
getZ, 32	Defect, 12
ifEmitDipole, 32	Dislocation, 20
incrementIterationCount, 32	DislocationSource, 31
lvec, 36	getY
mobile, 37	Defect, 12
nlterations, 37	Dislocation, 20
pos, 37	DislocationSource, 31
resetIterationCounter, 32	getZ
rotationMatrix, 37	Defect, 12
setBurgers, 33	Dislocation, 20
setBurgersMagnitude, 33	DislocationSource, 32
setLineVector, 33	ME and AD in a la
setNumIterations, 33	ifEmitDipole
setPosition, 34	DislocationSource, 32
setTauCritical, 35	incrementIterationCount
setX, 35	DislocationSource, 32
setY, 35	luca
setZ, 35	lvec
stressField, 36	Dislocation, 24
tauCritical, 37	DislocationSource, 36
dislocationSource.cpp, 95	magnitude
dislocationSource.h, 97	Vector3d, 79
dislocationSourceDefaults.h, 98	mainpage.dox, 100
getBurgers	Matrix33, 37
Dislocation, 19	adjugate, 40
DislocationSource, 29	getValue, 41
getBurgersMag	Matrix33, 39, 40
DislocationSource, 29	operator*, 42, 43
getIterationCount	operator*=, 43
DislocationSource, 30	operator \sim , 45
getLineVector	operator $^{\wedge}$, 45
Dislocation, 19	operator+, 44
DislocationSource, 30	operator+=, 44
getNumIterations	operator-, 44
DislocationSource, 30	operator-=, 45
getPosition	setValue, 46
Defect, 11, 12	x, 46
Dislocation, 19	matrix33.cpp, 100
DislocationSource, 30, 31	matrix33.h, 101
getPrincipalStrains	mobile
Strain, 58	Dislocation, 24
getPrincipalStresses	DislocationSource, 37
Stress, 69	Disiocation Source, 37
getShearStrains	nIterations
Strain, 58	DislocationSource, 37
getShearStresses	normalize
Stress, 69	Vector3d, 79
getTauCritical	vectorod, 75
DislocationSource, 31	operator*
getValue	Matrix33, 42, 43
Matrix33, 41	RotationMatrix, 50, 51
RotationMatrix, 49	Strain, 60, 61
Strain, 59	Stress, 70, 71
Stress, 69	Vector3d, 79, 80
Guess, 00	vectorou, 10, 00

116 INDEX

operator*=	DislocationSource, 32
Matrix33, 43	rotate
RotationMatrix, 52	Strain, 64
Strain, 61	Stress, 74
Stress, 71, 72	RotationMatrix, 47
Vector3d, 80	adjugate, 49
operator \sim	getValue, 49
Matrix33, 45	operator*, 50, 51
RotationMatrix, 54	operator*=, 52
Strain, 63	operator \sim , 54
Stress, 74	operator [∧] , 54
operator^	operator+, 52
Matrix33, 45	operator+=, 53
RotationMatrix, 54 Strain, 63	operator-, 53 operator-=, 53
Stress, 73	RotationMatrix, 48
Vector3d, 82	RotationMatrix, 48
operator^=	setValue, 54
Vector3d, 82	x, 55
operator+	rotationMatrix
Matrix33, 44	Dislocation, 25
RotationMatrix, 52	DislocationSource, 37
Strain, 62	rotationMatrix.cpp, 103
Stress, 72	rotationMatrix.h, 103
Vector3d, 80	,
operator+=	SQRT2
Matrix33, 44	constants.h, 86
RotationMatrix, 53	SQRT3
Strain, 62	constants.h, 86
Stress, 72	SQRT5
Vector3d, 81	constants.h, 86
operator-	setBurgers
Matrix33, 44	Dislocation, 20
RotationMatrix, 53	DislocationSource, 33
Strain, 62	setBurgersMagnitude
Stress, 73	DislocationSource, 33
Vector3d, 81	setLineVector Dislocation, 21
operator-=	DislocationSource, 33
Matrix33, 45	setMobile
RotationMatrix, 53	Dislocation, 21
Strain, 63	setNumIterations
Stress, 73	DislocationSource, 33
Vector3d, 81	setPinned
PI	Dislocation, 21
constants.h, 86	setPosition
populateMatrix	Defect, 13
Strain, 64	Dislocation, 21, 22
Stress, 74	DislocationSource, 34
pos	setTauCritical
Defect, 15	DislocationSource, 35
Dislocation, 25	setValue
DislocationSource, 37	Matrix33, 46
principalStrains	RotationMatrix, 54
Strain, 65	Strain, 65
principalStresses	Stress, 75
Stress, 75	Vector3d, 82
	setVector
resetIterationCounter	Vector3d, 83

INDEX 117

setX	stress.cpp, 107
Defect, 14	stress.h, 109
Dislocation, 22	stressField
DislocationSource, 35	Defect, 14
setY	Dislocation, 23
Defect, 14	DislocationSource, 36
Dislocation, 22	stressFieldLocal
DislocationSource, 35	Dislocation, 23
setZ	sum
Defect, 14	Vector3d, 83
Dislocation, 23	An a Cuitinal
DislocationSource, 35	tauCritical
shearStrains	DislocationSource, 37
Strain, 65	Vector3d, 76
shearStresses	getValue, 78
Stress, 75	getVector, 78
Strain, 55	magnitude, 79
adjugate, 58	normalize, 79
getPrincipalStrains, 58	operator*, 79, 80
getShearStrains, 58	operator*=, 80
getValue, 59	operator [∧] , 82
operator*, 60, 61	operator $^{\wedge}$ =, 82
operator*=, 61	operator+, 80
operator∼, 63	operator+=, 81
operator^, 63	operator-, 81
operator+, 62	operator-=, 81
operator+=, 62	setValue, 82
operator-, 62	
operator-=, 63	setVector, 83
populateMatrix, 64	sum, 83
principalStrains, 65	Vector3d, 77
rotate, 64	x, 83
setValue, 65	vector3d.cpp, 111
shearStrains, 65	vector3d.h, 111
Strain, 57	X
x, 65	^ Matrix33, 46
strain.cpp, 105	RotationMatrix, 55
strain.h, 106	Strain, 65
Stress, 65	Stress, 76
adjugate, 68	Vector3d, 83
getPrincipalStresses, 69	vectorou, oo
getShearStresses, 69	
getValue, 69	
operator*, 70, 71	
operator*=, 71, 72	
operator \sim , 74	
operator [^] , 73	
•	
operator+, 72	
operator+=, 72	
operator-, 73	
operator-=, 73	
populateMatrix, 74	
principalStresses, 75	
rotate, 74	
setValue, 75	
shearStresses, 75	
Stress, 67, 68	
x, 76	