RTI Connext DDS

Core Libraries

XML-Based Application Creation

Getting Started Guide

Version 6.0.1



© 2020 Real-Time Innovations, Inc.
All rights reserved.
Printed in U.S.A. First printing.
March 2020.

Trademarks

RTI, Real-Time Innovations, Connext, NDDS, the RTI logo, 1RTI and the phrase, "Your Systems. Working as one," are registered trademarks, trademarks or service marks of Real-Time Innovations, Inc. All other trademarks belong to their respective owners.

Copy and Use Restrictions

No part of this publication may be reproduced, stored in a retrieval system, or transmitted in any form (including electronic, mechanical, photocopy, and facsimile) without the prior written permission of Real-Time Innovations, Inc. The software described in this document is furnished under and subject to the RTI software license agreement. The software may be used or copied only under the terms of the license agreement.

This is an independent publication and is neither affiliated with, nor authorized, sponsored, or approved by, Microsoft Corporation.

The security features of this product include software developed by the OpenSSL Project for use in the OpenSSL Toolkit (http://www.openssl.org/).

Technical Support

Real-Time Innovations, Inc. 232 E. Java Drive Sunnyvale, CA 94089

Phone: (408) 990-7444 Email: support@rti.com

Website: https://support.rti.com/

Contents

Chapter 1 Introduction	1
Chapter 2 Paths Mentioned in Documentation	
Chapter 3 A 'Hello, World' Example	
3.1 Hello World using XML and Dynamic Data	5
3.1.1 Build the Application	6
3.1.2 Run the Application	7
3.1.3 Examine the XML Configuration Files Definition	8
3.1.3.1 QoS Definition	9
3.1.3.2 Type Definition	10
3.1.3.3 Domain Definition	10
3.1.3.4 Participant Definition	11
3.1.4 Publisher Application	12
3.1.5 Subscriber Application	14
3.1.6 Subscribing with a Content Filter	15
3.2 Hello World using XML and Compiled Types	16
3.2.1 Define the Data Types using IDL or XML	16
3.2.2 Generate Type-Support Code from the Type Definition	17
3.2.3 Build the Application	18
3.2.4 Run the Application	18
3.2.5 Examine the XML Configuration Files Definition	20
3.2.6 Examine the Publisher Application	21
3.2.7 Examine the Subscriber Application	23
Chapter 4 Using Prototyper	26
Chapter 5 Understanding XML-Based Application Creation	
5.1 Important Points	29
5.2 Loading XML Configuration Files	29

5.3 XML Syntax and Validation	30
5.3.1 Validation at Run Time	30
5.3.2 Validation during Editing	30
5.4 Accessing Entities Defined in XML Configuration from an Application	31
5.5 XML Tags for Configuring Entities	31
5.5.1 Domain Library	33
5.5.2 Participant Library	37
5.6 Names Assigned to Entities	43
5.6.1 Referring to Entities and Other Elements within XML Files	45
5.7 Creating and Retrieving Entities Configured in an XML File	46
5.7.1 Creating and Retrieving a DomainParticipant Configured in an XML File	46
5.7.2 Creating and Retrieving Publishers and Subscribers	47
5.7.3 Creating and Retrieving DataWriters and DataReaders	48
5.7.4 Creating Content Filters	49
5.7.5 Using User-Generated Types	49
Chapter 6 Connext DDS Micro Application Generation	
6.1 Paths Mentioned in Documentation	52
6.2 Command-Line Options	54
6.3 Generated Files	55
6.3.1 Integrating Generated Files into Your Application's Build	56
6.4 A "Hello, World" Example	56
6.4.1 Generate Type-Support Code from the Type Definition	56
6.4.2 Generate DDS Entities from the System Definition	58
6.4.3 Examine the XML Configuration Files and the Generated Code	59
6.4.3.1 Type Definition	60
6.4.3.2 Domain Definition	60
6.4.3.3 DomainParticipant Definition	62
6.4.4 QoS Definition	66
6.4.4.1 DomainParticipant Factory QoS	70
6.4.4.2 DomainParticipant QoS	70
6.4.4.3 Publisher QoS	73
6.4.4.4 DataWriter QoS	73
6.4.4.5 Subscriber QoS	76
6.4.4.6 DataReader QoS	76
6.4.5 Transport and Discovery Configuration	78
6.4.6 Flow Controllers	80

6.4.7 Static Discovery	. 82
6.5 Errors Caused by Invalid Configurations	. 87

Chapter 1 Introduction

This document assumes you have a basic understanding of RTI® Connext® DDS application development and concepts such as Domains, DomainParticipants, Topics, DataWriters and DataReaders. For an overview of these concepts, please see the RTI Connext DDS Core Libraries Getting Started Guide, which is part of your distribution, or you can find it online at https://community.rti.com/documentation.

XML-Based Application Creation is a mechanism to simplify the development and programming of *Connext DDS* applications. *Connext DDS* supports the use of XML for the complete system definition. This includes not only the definition of the data types and Quality of Service settings, but also the definition of the *Topics*, *DomainParticipants*, and all the *Entities* they contain (*Publishers*, *Subscribers*, *DataWriters* and *DataReaders*).

With the traditional approach, an application developer must program explicitly into the code the actions needed to join a domain, register the data types it will use, create the *Topics* and all the *Entities* (*Publishers*, *Subscribers*, *DataReaders* and *DataWriters*) that the application uses. Even for simple applications this "system creation" code can result in hundreds of lines of boiler-plate code. Besides being error prone, the traditional approach results in larger code-bases that are harder to understand and maintain. Using XML-Based Application Creation can significantly simplify this process.

XML-Based Application Creation is a simple layer that builds on top of the standard APIs. Everything that you do with the XML configuration can also be done with the underlying APIs. In this manner, an application can be initially developed using XML-Based Application Creation and transitioned to the traditional API at a later time. This would be useful in case the application has to be deployed on a platform without a file system or needs to be ported to a DDS-compliant library that does not support XML-based configuration.

Using XML-Based Application Creation is easy: simply edit **USER_QOS_PROFILE.xml** to define:

- The data types that will be used to communicate information in the system
- The Topics that will be used in the domain, associating each Topic with a data type
- The DomainParticipants that can potentially be used, giving each a participant name
- The DataWriters and DataReaders present within each DomainParticipant, each associated with its corresponding Topic.

The application code simply indicates the **participant configuration name** of the *DomainParticipant* that the application wants to create. The XML-Based Application Creation infrastructure takes care of the rest: creating the *DomainParticipant*, registering the types and *Topics*, and populating all the configured *Entities*.

When the application needs to read or write data, register listeners, or perform any other action, it simply looks up the appropriate *Entity* by name and uses it.

XML-Based Application Creation enables several powerful work flows:

- Developers can describe all the Entities that a Connext DDS application will need in an XML file
 and then create that application with a single function call, saving many hundreds of lines of setup
 code.
- Application descriptions written in XML are usable from all programming languages.
- The complete domain (including the data types and *Topics* that can be in the domain) can be defined in an XML file and shared among all the developers and applications.
- The Quality of Service (QoS) that should be used for each *DomainParticipant*, *Topic*, *DataReader*, and *DataWriter* can be fully specified in the XML and shared among a group of developers and applications.
- The XML description of the application can be used in combination with *RTI Prototyper* to design and prototype application deployment scenarios, allowing quick testing and validation without the need for programming.

To use the companion RTI Prototyper, see Using Prototyper (Chapter 4 on page 26).

Chapter 2 Paths Mentioned in Documentation

The documentation refers to:

<NDDSHOME>

This refers to the installation directory for RTI® Connext® DDS. The default installation paths are:

- macOS® systems:
 - /Applications/rti connext dds-6.0.1
- Linux systems, non-root user:
 - /home/<your user name>/rti connext dds-6.0.1
- Linux systems, *root* user:
 - /opt/rti connext dds-6.0.1
- Windows® systems, user without Administrator privileges:
 - <your home directory>\rti_connext_dds-6.0.1
- Windows systems, user with Administrator privileges:
 - C:\Program Files\rti connext dds-6.0.1

You may also see **\$NDDSHOME** or **%NDDSHOME**%, which refers to an environment variable set to the installation path.

Wherever you see **NDDSHOME**> used in a path, replace it with your installation path.

Note for Windows Users: When using a command prompt to enter a command that includes the path C:\Program Files (or any directory name that has a space), enclose the path in quotation marks. For example:

"C:\Program Files\rti_connext_dds-6.0.1\bin\rtiddsgen"

Or if you have defined the **NDDSHOME** environment variable:

"%NDDSHOME%\bin\rtiddsgen"

<path to examples>

By default, examples are copied into your home directory the first time you run *RTI Launcher* or any script in **NDDSHOME**>/bin. This document refers to the location of the copied examples as **path to examples>**.

Wherever you see *<path to examples>*, replace it with the appropriate path.

Default path to the examples:

- macOS systems: /Users/<your user name>/rti_workspace/6.0.1/examples
- Linux systems: /home/<your user name>/rti_workspace/6.0.1/examples
- Windows systems: <your Windows documents folder>\rti workspace\6.0.1\examples

Where 'your Windows documents folder' depends on your version of Windows. For example, on Windows 10, the folder is **C:\Users\<your user name>\Documents**.

Note: You can specify a different location for **rti_workspace**. You can also specify that you do not want the examples copied to the workspace. For details, see *Controlling Location for RTI Workspace and Copying of Examples* in the *RTI Connext DDS Installation Guide*.

Chapter 3 A 'Hello, World' Example

This chapter assumes that you have installed *Connext DDS* and configured your environment correctly. If you have not done so, please follow the steps in the please follow the steps in the RTI Connext DDS Installation Guide, and Step 1, Set up the Environment, in the RTI Connext DDS Core Libraries Getting Started Guide. These guides are part of your distribution; you can also find them online at https://community.rti.com/documentation. The *Getting Started Guide* will help you set both your environment variable NDDSHOME and, depending on your architecture, the environment variable PATH (on Windows® systems), LD_LIBRARY_PATH (on Linux® systems), or DYLD_LIBRARY_PATH (on macOS® systems).


3.1 Hello World using XML and Dynamic Data

The files for this example are in the directory <path to examples 1 > /connext_dds/c++/hello_world xml dynamic.

This simple scenario consists of two applications, illustrated in the figure below: **HelloWorld_publisher.exe**, which writes the *Topic*, **HelloWorldTopic**, and **HelloWorld_subscriber.exe**, which subscribes to that *Topic*.

¹See Chapter 2 Paths Mentioned in Documentation on page 3.

Figure 3.1: Hello World Domain



First we will build and run the application, then we will examine the configuration file and source code.

3.1.1 Build the Application

The example code is provided in C++, C#, and Java. The following instructions describe how to build it on Windows and UNIX-based systems. If you will be using an embedded platform, see the <u>RTI Connext DDS Core Libraries Getting Started Guide Addendum for Embedded Systems</u> for instructions specific to these platforms.

To build the example C++ applications on a Windows system:

1. In Windows Explorer, go to <path to examples>\connext_dds\c++\hello_world_xml_dynam-ic\win32 and open the Microsoft® Visual Studio® solution file for your architecture. For example, the file for Visual Studio 2012 32-bit platforms is Hello-i86Win32VS2012.sln.

Note: If your Windows SDK Version is not 10.0.15063.0, you may be prompted to retarget the file. If this happens, in the Retarget Projects window that appears, select an installed version of Windows SDK and click OK.

2. The Solution Configuration combo box in the toolbar indicates whether you are building debug or release executables; select **Release**. Then select **Build Solution** from the Build menu.

To build the example C++ applications on a UNIX-based system:

- From your command shell, change directory to path to examples>/connext_dds/c++/ hello_
 world_xml_dynamic.
- 2. Type:

```
gmake -f make/Makefile. <architecture>
```

where <architecture> is one of the supported architectures (e.g., Makefile.i86Linux2.6gcc4.4.5); see the contents of the make directory for a list of available architectures. This command will build a release executable. To build a debug version instead, type:

```
gmake -f make/Makefile.<architecture> DEBUG=1
```

3.1.2 Run the Application

The previous step should have built one executable: **Hello.exe**. This application should be in the proper architecture subdirectory under the **objs** directory (for example, **objs\i86Win32VS2012** in the Windows example cited below and **objs/i86Linux2.6gcc4.4.5** in the Linux example).

To start the publishing application on a Windows system:

From your command shell, go to **<path to examples>\connext_dds\c++\ hello_world_xml_dynamic** and type:

```
objs\<architecture>\Hello pub
```

where <architecture> is the architecture you just built; look in the **objs** directory to see the name of the architecture you built. For example, the Windows architecture name corresponding to 32-bit Visual Studio 2012 is i86Win32VS2012.

To start the publishing application on a UNIX-based system:

From your command shell, change directory to **<path to examples>/connext_dds/c++/ hello_world_xml_dynamic** and type:

```
objs/<architecture>/Hello pub
```

where <architecture> is the architecture you just built; look in the **objs** directory to see the name of the architecture you built. For example, **i86Linux2.6gcc4.4.5**.

To start the subscribing application on a Windows system:

From a different command shell, go to **<path to examples>\connext_dds\c++\ hello_world_xml_dynamic** and type:

```
objs\<architecture>\Hello sub
```

where <architecture> is the architecture you just built; look in the **objs** directory to see the name of the architecture you built. For example, the Windows architecture name corresponding to 32-bit Visual

Studio 2012 is i86Win32VS2012.

To start the subscribing application on a UNIX-based system:

From a different command shell, change directory to path to examples>/connext_dds/c++/ hello_
world_xml_dynamic and type:

```
objs/<architecture>/Hello sub
```

where <architecture> is the architecture you just built; look in the **objs** directory to see the name of the architecture you built. For example, **i86Linux2.6gcc4.4.5**.

You should immediately see some messages from the publishing application showing that it is writing data and messages from the subscribing application showing the data it receives. Do not worry about the contents of the messages. They are generated automatically for this example. The important thing is to understand how the application is defined, which will be explained in the following sections.

3.1.3 Examine the XML Configuration Files Definition

A *Connext DDS* application is defined in the file **USER_QOS_PROFILES.xml** found in the directory **<path to examples>/connext_dds/c++/ hello_world_xml_dynamic**. Let's review its content to see how this scenario was constructed. The main sections in the file are:

- 3.1.3.1 QoS Definition on the next page
- 3.1.3.2 Type Definition on page 10
- 3.1.3.3 Domain Definition on page 10
- 3.1.3.4 Participant Definition on page 11

The entire file is shown below. We will examine the file section-by-section.

```
<?xml version="1.0"?>
-<dds version="6.0.1"
xsi:noNamespaceSchemaLocation=
"http://community.rti.com/schema/5.2.0/rti dds profiles.xsd"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
    <!-- Qos Library -->
    <qos library name="qosLibrary">
       <qos profile name="DefaultProfile">
       </qos profile>
    </qos library>
    <!-- types -->
    <types>
       <const name="MAX NAME LEN" value="64" type="long"/>
       <const name="MAX MSG LEN" value="128" type="long"/>
       <struct name="HelloWorld">
               <member name="sender" type="string"</pre>
```

```
stringMaxLength="MAX NAME LEN" key="true"/>
                <member name="message" type="string"</pre>
                 stringMaxLength="MAX MSG LEN"/>
                <member name="count" type="long"/>
       </struct>
    </types>
    <!-- Domain Library -->
    <domain library name="MyDomainLibrary">
       <domain name="HelloWorldDomain" domain id="0">
               <register type name="HelloWorldType"
                  type ref="HelloWorld"/>
               <topic name="HelloWorldTopic"</pre>
                  register type ref="HelloWorldType">
                        <topic gos name="HelloWorld gos"
                         base name="qosLibrary::DefaultProfile"/>
                </topic>
       </domain>
    </domain library>
    <!-- Participant library -->
    <domain participant library name="MyParticipantLibrary">
       <domain participant name="PublicationParticipant"</pre>
       domain ref="MyDomainLibrary::HelloWorldDomain">
               <publisher name="MyPublisher">
                        <data writer name="HelloWorldWriter"</pre>
                         topic ref="HelloWorldTopic"/>
               </publisher>
       </domain participant>
       <domain participant name="SubscriptionParticipant"</pre>
       domain ref="MyDomainLibrary::HelloWorldDomain">
                <subscriber name="MySubscriber">
                        <data reader name="HelloWorldReader"</pre>
                         topic ref="HelloWorldTopic">
                                <datareader qos name="HelloWorld reader qos"</pre>
                                 base name="qosLibrary::DefaultProfile"/>
                        </data reader>
               </subscriber>
       </domain participant>
    </domain participant library>
</dds>
```

3.1.3.1 QoS Definition

The defined DDS *Entities* have an associated QoS. The QoS section of the XML file provides a way to define QoS libraries and profiles, which can then be used to configure the QoS of the defined *Entities*.

The syntax of the QoS libraries and profiles section is described in Configuring QoS with XML, in the RTI Connext DDS Core Libraries User's Manual and may also contain *Entity* configurations.

In this example, the QoS library and profile are empty, just to provide a placeholder where the QoS can be specified. Using this empty profile results in the default DDS QoS being used:

```
<!-- QoS Library -->
<qos_library name="qosLibrary">
```

3.1.3.2 Type Definition

The data associated with the HelloWorld *Topic* consists of two strings and a numeric counter:

- 1. The first string contains the name of the sender of the message. This field is marked as "key" as signals the identity of the data-object.
- 2. The second string contains a message.
- 3. The third field is a simple counter which the application increments with each message.

This example uses the Dynamic Data API, so the data type must be defined in the XML configuration. You can do this by adding the type definition within the <types> tag:

The <types> tag may be used to define a library containing the types that the different applications will need. However, for this simple example just one data-type, the HelloWorld type seen above, is included.

3.1.3.3 Domain Definition

The domain section is used to define the system's *Topics* and the corresponding data types associated with each *Topic*. To define a *Topic*, the associated data type must be registered with the domain, giving it a registered type name. The registered type name is used to refer to that data type within the domain at the time the *Topic* is defined.

In this example, the configuration file registers the previously defined HelloWorld type under the name HelloWorldType. Then it defines a *Topic* named HelloWorldTopic, which is associated with the registered type, referring to it by its registered name, HelloWorldType:

```
</domain>
</domain_library>
```

Notes:

- The attribute **type_ref** in the <register_type> element refers to the same HelloWorld type defined in the <types> section.
- A domain definition may register as many data types and define as many *Topics* as it needs. In this example, a single data type and *Topic* will suffice.
- The **domain_library** can be used to define multiple domains. However, this example only uses one domain.

3.1.3.4 Participant Definition

The participant section is used to define the *DomainParticipants* in the system and the *DataWriters* and *DataReaders* that each participant has. *DomainParticipants* are defined within the <domain_participant_library> tag.

Each DomainParticipant:

- Has a unique name (within the library) which will be used later by the application that creates it.
- Is associated with a domain, which defines the domain_id, Topics, and data types the DomainParticipant will use.
- Defines the *Publishers* and *Subscribers* within the *DomainParticipant*. *Publishers* contain *DataWriters*, *Subscribers* contain *DataReaders*.
- Defines the set of *DataReaders* it will use to write data. Each *DataReader* has a QoS and a unique name which can be used from application code to retrieve it.
- Defines the set of *DataWriters* it will use to write data. Each *DataWriter* has a QoS and a unique name which can be used from application code to retrieve it.
- Optionally the *Participants*, *Publishers*, *Subscribers*, *DataWriters*, and *DataReaders* can specify a QoS profile that will be used to configure them.

The example below defines two *DomainParticipants*, called PublicationParticipant and SubscriptionParticipant:

Examining the XML, we see that:

- PublicationParticipant is bound to the domain, MyDomainLibrary::HelloWorldDomain.
- The participant contains a single *Publisher* named MyPublisher, which itself contains a single *DataWriter* named HelloWorldWriter.
- The *DataWriter* writes the *Topic* HelloWorldTopic, which is defined in the domain MyDomainLibrary::HelloWorldDomain.

Similarly:

- SubscriptionParticipant is also bound to the domain MyDomainLibrary::HelloWorldDomain.
- The participant contains a single *Subscriber* named MySubscriber, which itself contains a single *DataReader* named HelloWorldReader.
- The DataReader reads the Topic HelloWorldTopic, which is defined in the domain MyDomainLibrary::HelloWorldDomain.

Since both participants are in the same domain and the HelloWorldWriter *DataWriter* writes the same *Topic* that the HelloWorldReader *DataReader* reads, the two participants will communicate as depicted in Figure 3.1: Hello World Domain on page 6.

3.1.4 Publisher Application

Open the file connext_dds/c++/hello_world_xml_dynamic/src/HelloWorld_publisher.cxx and look at the source code.

The logic of this simple application is contained in the **publisher_main()** function. The logic is composed of two parts:

• Entity Creation

The application first creates a *DomainParticipant* using the function **create_participant_from_config()**. This function takes the configuration name of the participant, MyParticipantLibrary::PublicationParticipant, which is the same name that was specified in the XML file.

Note that the name in the XML file, PublicationParticipant, has been qualified with the name of the library it belongs to: MyParticipantLibrary.

This single function call registers all the necessary data types and creates and the *Topics* and *Entities* that were specified in the XML file. In this simple case, the participant only contains a *Publisher*, MyPublisher, with a single *DataWriter*, HelloDataWriter. However, in more realistic scenarios, this single call can create hundreds of entities (both readers and writers).

• Use of the Entities

The remaining part of the function uses the created *Entities* to perform the logic of the program.

This example writes data using the single *DataWriter*. So the application looks up the HelloWorldWriter *DataWriter* using the fully qualified name MyPublisher::HelloWorldWriter and narrows it to be a DynamicDataWriter:

Once the *DataWriter* is available, some data objects need to be created and used to send the data. As this example uses dynamic data, and the type code is internally created, you can use the operations **create_data()** and **delete_data()** in a *DataWriter* to create and delete a data object. This is achieved with the calls seen below:

```
/* Create data */
DDS DynamicData *dynamicData =
       dynamicWriter->create_data(DDS_DYNAMIC_DATA_PROPERTY_DEFAULT);
/* Main loop to repeatedly send data */
for (count=0; count < 100; ++count) {
        /* Set the data fields */
        retcode = dynamicData->set_string(
               "sender", DDS DYNAMIC DATA MEMBER ID UNSPECIFIED,
               "John Smith");
        retcode = dynamicData->set string(
               "message", DDS DYNAMIC DATA MEMBER ID UNSPECIFIED,
               "Hello World!");
        retcode = dynamicData->set long(
               "count", DDS DYNAMIC DATA MEMBER ID UNSPECIFIED,
               count);
        /* Write the data */
        retcode = dynamicWriter->write(*dynamicData, DDS HANDLE NIL);
/* Delete data sample */
dynamicWriter->delete data(dynamicData
```

Note that operations such as **set_long()** are used to set the different attributes of the Dynamic Data object. These operations refer to the attribute names (e.g., "count") that were defined as part of the data type.

3.1.5 Subscriber Application

Open the file <path to examples>/connext_dds/c++/hello_world_xml_dynamic/src/HelloWorld_sub-scriber.cxx and look at the source code.

The logic of this simple application is contained in the **subscriber_main()** function. Similar to the publisher application, the logic is composed of two parts:

Entity Creation

The application first creates a *DomainParticipant* using the function **create_participant_from_config()**. This function takes the configuration name of the participant **MyParticipantLibrary::SubscriptionParticipant**, which is the same name that was specified in the XML file. Notice that the name in the XML file, **SubscriptionParticipant**, has been qualified with the name of the library it belongs to: **MyParticipantLibrary**.

This single function call registers all the necessary data types and creates and the *Topics* and *Entities* that were specified in the XML file. In this simple case, the participant only contains a *Subscriber*, **MySubscriber**, with a single *DataReader*, **HelloDataReader**. However in more realistic scenarios, this single call can create hundreds of *Entities* (both *DataReaders* and *DataWriters*).

• Use of the Entities

The remaining part of the function uses the entities that were created to perform the logic of the program.

This example only needs to read data using the single *DataReader*. So the application looks up the HelloWorldReader *DataReader* using the fully qualified name MySubscriber::HelloWorldReader and narrows it to be a DynamicDataReader:

To process the data, the application installs a *Listener* on the *DataReader*. The HelloWorldListener, defined on the same file implements the DataReaderListener interface, which the *DataReader* uses to notify the application of relevant events, such as the reception of data.

```
/* Create a DataReaderListener */
HelloWorldListener * reader_listener = new HelloWorldListener();

/* set listener */
retcode = dynamicReader->set_listener(reader_listener, DDS_DATA_AVAILABLE_STATUS);
```

The last part is the implementation of the listener functions. In this case, we only implement the **on_data available()** operation which is the one called when data is received.

The on_data_available() function receives all the data into a sequence and then uses the DDS_DynamicData::print() function to print each data item received.

```
void HelloWorldListener::on data available(DDSDataReader* reader)
        DDSDynamicDataReader * ddDataReader = NULL;
        DDS DynamicDataSeq dataSeq;
        DDS SampleInfoSeq infoSeq;
        DDS_ReturnCode_t retcode = DDS_RETCODE_ERROR;
        DDS Long i = 0;
        ddDataReader = DDSDynamicDataReader::narrow(reader);
        retcode = ddDataReader->take(dataSeq, infoSeq,
               DDS LENGTH UNLIMITED, DDS ANY SAMPLE STATE,
               DDS ANY VIEW STATE, DDS ANY INSTANCE STATE);
        printf("on data available:%s\n",
               ddDataReader->get topicdescription()->get name());
        for (i = 0; i < dataSeq.length(); ++i) {
               if (infoSeq[i].valid data) {
                       retcode = dataSeq[i].print(stdout, 0);
        retcode = ddDataReader->return loan(dataSeq, infoSeq);
```

3.1.6 Subscribing with a Content Filter

To use a content filter, modify the SubscriptionParticipant configuration to look like this:

```
</domain_participant>
</domain_participant_library>
```

The extra XML within the <filter> tag adds a SQL content filter which only accepts samples with the field count greater than two.

Now run HelloWorld_subscriber without recompiling and confirm that you see the expected behavior.

3.2 Hello World using XML and Compiled Types

The files for this example are in the directory **<path to examples>/connext_dds/c++/hello_world_xml_compiled**. This simple scenario consists of two applications identical in purpose to the one illustrated in Figure 3.1: Hello World Domain on page 6: HelloWorld_publisher.exe, which writes to the *Topic* "HelloWorldTopic," and HelloWorld subscriber.exe, which subscribes to that same Topic.

In contrast with 3.1 Hello World using XML and Dynamic Data on page 5, which uses the Dynamic Data API, this example uses compiled types.

Compiled types are syntactically nicer to use from application code and provide better performance. The drawback is that there is an extra step of code-generation involved to create that supporting infrastructure to marshal and unmarshal the types into a format suitable for network communications.

3.2.1 Define the Data Types using IDL or XML

The first step is to describe the data type in a programming language-neutral manner. Two languages are supported by the *Connext DDS* tools: XML and IDL. These languages (XML and IDL) provide equivalent type-definition capabilities, so you can choose either one depending on your personal preference. You can even transform between one and the other with the RTI tools. That said, as the rest of the configuration files use XML, it is often more convenient to also use XML to describe the data types, so they can be shared or moved to other XML configuration files.

The directory **<path to examples>/connext_dds/c++/hello_world_xml_compiled** contains the XML description of the data type in the file **HelloWorld.xml**; it also contains the equivalent IDL description in **HelloWorld.idl**.

Let's examine the contents of the XML file:

The file defines a structure type called "HelloWorld" consisting of a string (the sender), a string (the message), and an integer count. Note that the type-declaration syntax is identical the one used within the USER_QOS_PROFILES.xml file that we used for the dynamic example (3.1.3.2 Type Definition on page 10).

3.2.2 Generate Type-Support Code from the Type Definition

This step produces code to support the direct use of the structure 'HelloWorld' from application code. The code is generated using the provided tool named *rtiddsgen*.

The Code Generator supports many programming languages. XML-Based Application Creation currently supports C, C++, Java, and C#. We will use C++ in this example.

To generate code, follow these steps (replacing <architecture> as needed for your system; e.g., i86Win32VS2012 or i86Linux2.6gcc4.4.5):

On a Windows system:

From your command shell, change directory to **<path to examples>\connext_dds\c++\hello_world_ xml compiled** and type:

```
<NDDSHOME>\bin\rtiddsgen -language C++ -example <architecture> HelloWorld.xml
```

On a UNIX-based system:

From your command shell, change directory to path to examples>/connext_dds/c++/hello_world_
xml compiled and type:

```
<NDDSHOME>/bin/rtiddsgen -language C++ -example <architecture> HelloWorld.xml
```

As a result of this step you will see the following files appear in the directory **HelloWorld_xml_dynamic**: **HelloWorld.h**, **HelloWorld.cxx**, **HelloWorldPlugin.h**, **HelloWorldPlugin.cxx**, **HelloWorldSupport.h**, and **HelloWorldSupport.cxx**.

The most notable thing at this point is that the **HelloWorld.h** file contains the declaration of the C++ structure, built according to the specification in the XML file:

```
static const DDS_Long MAX_NAME_LEN = 64;
static const DDS_Long MAX_MSG_LEN = 128;

typedef struct HelloWorld
{
        char* sender; /* maximum length = ((MAX_NAME_LEN)) */
        char* message; /* maximum length = ((MAX_MSG_LEN)) */
        DDS_Long count;
} HelloWorld;
```

3.2.3 Build the Application

The example code is provided in C++, C#, and Java. The following instructions describe how to build it on Windows and UNIX-based systems. If you will be using an embedded platform, see the <u>RTI Connext DDS Core Libraries Getting Started Guide Addendum for Embedded Systems</u> for instructions specific to these platforms.

C++ on Windows Systems:

In the Windows Explorer, go to **<path to examples>\connext_dds\c++\hello_world_xml_compiled** and open the Microsoft Visual Studio solution file for your architecture. For example, the file for Visual Studio 2012 for 32-bit platforms is **HelloWorld-vs2012.sln**.

The Solution Configuration combo box in the toolbar indicates whether you are building debug or release executables; select **Release**. Select **Build Solution** from the Build menu.

C++ on UNIX-based Systems:

From your command shell, change directory to path to examples>/connext_dds/c++/hello_world_
xml compiled.

Type:

```
gmake -f Makefile.<architecture>
```

where <architecture> is one of the supported architectures (e.g., Makefile.i86Linux2.6gcc4.4.5). This command will build a *release* executable. To build a *debug* version instead, type:

```
gmake -f Makefile.<architecture> DEBUG=1
```

3.2.4 Run the Application

The previous step built two executables: **HelloWorld_subscriber** and **HelloWorld_publisher**. These applications should be in proper architecture subdirectory under the **objs** directory (for example, **objs\i86Win32VS2012** in the Windows example cited below and **objs/i86Linux2.6gcc4.4.5** in the Linux example).

1. Start the subscribing application:

On a Windows system:

From your command shell, go to **<path to examples>\connext_dds\c++\hello_world_xml_com-piled** and type:

```
objs\<architecture>\HelloWorld subscriber.exe
```

where <architecture> is the architecture you just built; see the contents of the **objs** directory to see the name of the architecture you built. For example, the Windows architecture name corresponding to 32-bit Visual Studio 2012 is i86Win32VS2012.

On a UNIX-based system:

From your command shell, change directory to **<path to examples>/connext_dds/c++/hello_world xml compiled** and type:

```
objs/<architecture>/HelloWorld subscriber
```

where <architecture> is the architecture you just built of the supported architectures; examine the contents of the **objs** directory to see the name of the architecture you built.

2. Start the publishing application:

On a Windows system:

From your command shell, go to **<path to examples>\connext_dds\c++\hello_world_xml_com-piled** and type:

```
objs\<architecture>\HelloWorld_publisher.exe
```

where <architecture> is the architecture you just built; see the contents of the **objs** directory to see the name of the architecture you built.

On a UNIX-based system:

From your command shell, change directory to path to examples>/connext_dds/c++/hello_
world xml compiled and type:

```
objs/<architecture>/HelloWorld publisher
```

You should immediately see some messages on the publishing application showing that it is writing data and messages in the subscribing application indicating the data it receives. Do not worry about the contents of the messages. They are generated automatically for this example. The important thing is to understand how the application is defined, which will be explained in the following subsections.

3.2.5 Examine the XML Configuration Files Definition

This system is defined in the file USER_QOS_PROFILES.xml in the directory <path to examples>/-connext_dds/c++/hello_world_xml_compiled. Let's look at its content and what are the elements defined to construct this scenario.

```
<?xml version="1.0"?>
<dds version="5.2.0"
xsi:noNamespaceSchemaLocation=
"http://community.rti.com/schema/5.2.0/rti dds profiles.xsd"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
<!-- Qos Library -->
<qos library name="qosLibrary">
    <qos profile name="DefaultProfile"> </qos profile>
</qos library>
<!-- Domain Library -->
<domain library name="MyDomainLibrary">
    <domain name="HelloWorldDomain" domain id="0">
       <register type name="HelloWorldType"/>
       <topic name="HelloWorldTopic" register type ref="HelloWorldType">
           <topic qos name="HelloWorld qos"
            base name="qosLibrary::DefaultProfile"/>
       </topic>
    </domain>
</domain library>
<!-- Participant library -->
<domain_participant_library name="MyParticipantLibrary">
       <domain participant name="PublicationParticipant"</pre>
        domain ref="MyDomainLibrary::HelloWorldDomain">
               <publisher name="MyPublisher">
                        <data writer name="HelloWorldWriter"</pre>
                         topic ref="HelloWorldTopic"/>
               </publisher>
       </domain participant>
       <domain participant name="SubscriptionParticipant"</pre>
        domain ref="MyDomainLibrary::HelloWorldDomain">
               <subscriber name="MySubscriber">
                        <data_reader name="HelloWorldReader"</pre>
                         topic ref="HelloWorldTopic">
                                <datareader gos
                                 name="HelloWorld reader_qos"
                                 base name="qosLibrary::DefaultProfile"/>
                        </data reader>
               </subscriber>
       </domain participant>
</domain_participant_library>
</dds>
```

Notice that this file contains virtually the same information found in the **hello_world_xml_dynamic** example. This is no surprise, since we are essentially trying to define the same system. Please see 3.1.3

Examine the XML Configuration Files Definition on page 8 for a description of what each section in the XML does.

There are only two differences in the configuration file for the **hello_world_xml_compiled** compared to **hello world xml dynamic**:

The type definition "<types>" section does not appear in the configuration of the HelloWorld_xml_compiled example.

The type-definition section that appears between the tags "<types>" and "</types>" is not there because in this case the data types are compiled in. So the type-definition has been moved to an external file to facilitate the code generation described in 3.2.2 Generate Type-Support Code from the Type Definition on page 17.

• The registration of the data-type inside the domain uses the syntax:

```
<register_type name="HelloWorldType" />
```

This contrasts with what was used in the HelloWorld_xml_dynamic example:

```
<register type name="HelloWorldType" type ref="HelloWorld" />.
```

The difference between the two is easily observable from the type registration mechanism in XML-Application Creation, which is a follows:

- 1. If a <register_type> tag is not present, the value of the attribute register_type_ref of a {{<topic>}}] is used as registered type name of a type support that must have been already registered by the application.
- 2. If a <register_type> tag is specified but its attribute type_ref is not present, this is equivalent to 1, but the registered type name is the one specified by the <register type> tag.
- 3. If a <register_type> tag is specified and the **type_ref** is present, XML-Application Creation will first search for a type support already registered. If no type support is found, it will automatically register the type using DynamiData and with the TypeCode defined by the XML type referenced by type_ref.

This behavior enables the possibility of defining configurations that are independent of how the types are registered, leaving that decision up to the end application. That is, the same configuration can be used for applications that generate a type or that rely on DynamicData.

3.2.6 Examine the Publisher Application

Open the file connext_dds/c++/hello_world_xml_compiled/HelloWorld_publisher.cxx and look at the source code.

The logic of this simple application is contained in the **publisher_main()** function. The logic can be seen as composed of three parts:

• Type registration (this step is new compared to HelloWorld xml dynamic)

The first thing the application does is register the data-types that were defined in the code-generation step. This is accomplished by calling the **register_type_support()** function on the DomainParticipantFactory.

The function **register_type_support()** must be called for each code-generated data type that will be associated with the *Topics* published and subscribed to by the application. In this example, there is only one *Topic* and one data type, so only one call to this function is required.

The function **register_type_support()** takes as a parameter the TypeSupport function that defines the data type in the compiled code. In this case, it is **HelloWorldTypeSupport::register_type()**, which is declared in **HelloWorldSupport.h**. However, you cannot see it directly because it is defined using macros. Instead you will find the line:

```
DDS_TYPESUPPORT_CPP(HelloWorldTypeSupport, HelloWorld);
```

This line defines the HelloWorldTypeSupport::register type() function.

In general, if you include multiple data-type definitions in a single XML (or IDL) file called **MyFile.xml** (or **MyFile.idl**), you will have multiple TypeSupport types defined within the generated file **MyFileTypeSupport.h**. You can identify them searching for the **DDS_ TYPESUPPORT_CPP()** macro and you should register each of them (the ones the application uses) using the operation **register_type_support()** as was shown above.

Entity creation

The steps to create the entities are the same as for the HelloWorld_xml_dynamic example. The application first creates a *DomainParticipant* using the function **create_participant_from_config()**, which takes the configuration name of the participant "MyParticipantLibrary::PublicationParticipant" (which is the same name that was specified in the XML file). Note that the name in the XML file "PublicationParticipant" has been qualified with the name of the library it belongs to: "MyParticipantLibrary".

This single function call registers all the necessary data types and creates the *Topics* and *Entities* that were specified in the XML file. In this simple case, the participant only contains a *Publisher* "MyPublisher" with a single *DataWriter* "HelloDataWriter". However in more realistic scenarios, this single call can create hundreds of entities (both readers and writers).

• Use of the Entities

The remaining part of the function uses the entities that were created to perform the logic of the program.

This example only needs to write data using the single *DataWriter*. So the application looks-up the "HelloWorldWriter" *DataWriter* using the fully qualified name "MyPublisher::HelloWorldWriter" and narrows it to be a HelloWorldDataWriter. Note the difference with the HelloWorld_xml_dynamic example. Rather than the generic "DynamicDataWriter" used in that example, here we use a *DataWriter* specific to the HelloWorld data type.

```
HelloWorldDataWriter * helloWorldWriter = HelloWorldDataWriter::narrow(
       participant->lookup datawriter by name(
               "MyPublisher::HelloWorldWriter"));
/* Create data */
HelloWorld * helloWorldData = HelloWorldTypeSupport::create data();
/* Main loop */
for (count=0; (sample count == 0) || (count < sample count); ++count)</pre>
       printf("Writing HelloWorld, count: %d\n", count);
       /* Set the data fields */
       helloWorldData->sender = "John Smith";
       helloWorldData->message = "Hello World!";
       helloWorldData->count = count;
       retcode = helloWorldWriter->write(*helloWorldData,
                                          DDS HANDLE NIL);
       if (retcode != DDS RETCODE OK) {
               printf("write error %d\n", retcode);
               publisher shutdown(participant);
               return -1;
       NDDSUtility::sleep(send_period);
```

Note that the data-object helloWorldData can be manipulated directly as a plain-language object. Then to set a field in the object, the application can refer to it directly. For example:

```
helloWorldData->count = count;
```

This "plain language object" API is both higher performance and friendlier to the programmer than the DynamicData API.

3.2.7 Examine the Subscriber Application

Open the file connext_dds/c++/hello_world_xml_compiled/HelloWorld_sub-scriber.cxx and look at the source code.

The logic of this simple application is in the **subscriber_main()** function. Similar to the publisher application the logic can be seen as composed of three parts:

1. Type registration (this step is new compared to HelloWorld xml dynamic)

This step is identical to the one for the publisher application. The first thing the application does is register the data types that were defined in the code-generation step. This is accomplished calling the register_type_support() function on the DomainParticipantFactory.

Please refer to the explanation of the publishing application for more details on this step, regardless of whether the application uses a type to publish or subscribe.

2. Entity creation

The steps for creating the entities are the same as for the HelloWorld_xml_dynamic example. The application first creates a *DomainParticipant* using the function **create_participant_from_config()** this function takes the configuration name of the participant "MyParticipantLibrary::SubscriptionParticipant" which is the same name that was specified in the XML file. Note that the name in the XML file "SubscriptionParticipant" has been qualified with the name of the library it belongs to: "MyParticipantLibrary".

This single function call registers all the necessary data types, and creates the *Topics* and *Entities* that were specified in the XML file. In this simple case, the participant only contains a *Subscriber* "MySubscriber" with a single *DataReader* "HelloDataReader". However in more realistic scenarios, this single call can create hundreds of entities (both *DataReaders* and *DataWriters*).

3. Use of the Entities

The remaining part of the function uses the created entities to perform the logic of the program.

This example only needs to read data using the single *DataReader* So the application looks-up the "HelloWorldReader" *DataReader* using the fully qualified name "MyPublisher::HelloWorldReader" and narrows it to be a HelloWorldDataReader:

To process the data, the application installs a Listener on the *DataReader*. The HelloWorldListener defined in the same file implements the DataReaderListener interface. The *DataReader* uses that interface to notify the application of relevant events, such as the reception of data.

The last part is the implementation of the listener functions. In this case, we only implement the **on_data_available()** operation, which is called when data is received.

The on_data_available() function receives all the data into a sequence, then uses the HelloWorldTypeSupport::print() function to print each data item received.

Note that the sequence received is of type HelloWorldSeq which contains the native plain language objects of type HelloWorld. This can be manipulated directly by the application. For example the fields can be dereferenced as shown in the code snippet below:

```
HelloWorld *helloWorldData = &dataSeq[i];
printf("count= %s\n", helloWorldData->count);
```

Chapter 4 Using Prototyper

RTI Prototyper is a companion tool for use with the XML-Based Application Creation feature. This tool allows application developers to quickly try out scenarios directly from their XML descriptions, without writing any code.

On a Windows system:

From your command shell, go to <path to examples>\connext_dds\c++\hello_world_xml_dynamic. Open two console windows.

In one window, type (all on one line):

```
$NDDSHOME\bin\rtiddsprototyper -cfgName PublicationParticipant
"MyParticipantLibrary::PublicationParticipant"
```

In the other window, type (all on one line):

```
$NDDSHOME\bin\rtiddsprototyper -cfgName SubscriptionParticipant
"MyParticipantLibrary::SubscriptionParticipant"
```

On a UNIX-based system:

From your command shell, go to <path to examples>/connext_dds/c++/hello_world_xml_dynamic. Open two console windows.

In one window, type (all on one line):

```
${NDDSHOME}/bin/rtiddsprototyper -cfgName PublicationParticipant
"MyParticipantLibrary::PublicationParticipant"
```

In the other window, type (all on one line):

```
${NDDSHOME}/bin/rtiddsprototyper -cfgName SubscriptionParticipant
"MyParticipantLibrary::SubscriptionParticipant"
```

You can run both of these on the same computer or on separate computers within the same (multicast enabled) network. You should immediately see the subscribing application receive and print the information from the publishing side.


For more information, please read the <u>RTI Connext DDS Core Libraries Protoyper with Lua Getting Started Guide</u>.

Chapter 5 Understanding XML-Based Application Creation

Figure 5.1: Using Both Connext API and XML Configuration File to Develop an Application below depicts a *Connext DDS* application built with the aid of both the *Connext DDS* API and an XML configuration file. Using the XML configuration file in combination with the XML-Based Application Creation feature simplifies and accelerates application development.

The Entities defined in the XML configuration file can be created by a single call to the API. Once created, all Entities can be retrieved from application code using standard "lookup" operations so they can be used to read and write data.

Figure 5.1: Using Both Connext API and XML Configuration File to Develop an Application



5.1 Important Points

- Applications can instantiate a *DomainParticipant* from a participant configuration described in the XML configuration file. All the *Entities* defined by such a participant configuration are created automatically as part of *DomainParticipant* creation. In addition, multiple participant configurations may be defined within a single XML configuration file.
- All the *Entities* created from a participant configuration are automatically assigned an entity name. *Entities* can be retrieved via "lookup" operations by specifying their name. Each *Entity* stores its own name in the QoS policies of the *Entity* so that it can be retrieved locally (via a lookup) and communicated via discovery. This is described in 5.7 Creating and Retrieving Entities Configured in an XML File on page 46.
- An XML configuration file is not tied to the application that uses it. Different applications may run using the same configuration file. A single file may define multiple participant configurations. A single application can instantiate as many *DomainParticipants* as desired.
- Changes in the XML configuration file do not require recompilation, even if *Entities* are added or removed, unless the logic that uses the *Entities* also needs to change.

5.2 Loading XML Configuration Files

Connext DDS loads its XML configuration from multiple locations. This section presents the various approaches, listed in load order.

The following locations contain QoS Profiles (see Configuring QoS with XML, in the RTI Connext DDS Core Libraries User's Manual) and may also contain *Entity* configurations.

• \$NDDSHOME/resource/xml/NDDS_QOS_PROFILES.xml

This file contains the *Connext DDS* default QoS values; it is loaded automatically if it exists. When present this is the first file loaded. (Where *x.y* represent version numbers.)

This file is loaded automatically if it exists (not the default case) and ignore_resource_profile in the PROFILE QosPolicy is FALSE (the default). **NDDS_QOS_PROFILES.xml does not exist by default.** However, NDDS_QOS_PROFILES.example.xml is shipped with the host bundle of the product; you can copy it to NDDS_QOS_PROFILES.xml and modify it for your own use. The file contains the default QoS values that will be used for all entity kinds. (First to be loaded)

• File specified in NDDS_QOS_PROFILES Environment Variable

The files (or XML strings) separated by semicolons referenced in this environment variable, if any, are loaded automatically. These files are loaded after the **NDDS_QOS_PROFILES.xml** and they are loaded in the order they appear listed in the environment variable.

<working directory>/USER QOS PROFILES.xml

This file is loaded automatically if it exists in the 'working directory' of the application, that is, the directory from which the application is run. (Last to be loaded)

5.3 XML Syntax and Validation

The configuration files use XML format. Please see 3.1.3 Examine the XML Configuration Files Definition on page 8 for an example XML file and a description of its contents.

5.3.1 Validation at Run Time

Connext DDS validates the input XML files using a built-in Document Type Definition (DTD). You can find a copy of the built-in DTD in **\$NDDSHOME/resource/schema/rti_dds_profiles.dtd**.

This is only a copy of the DTD that *Connext DDS* uses. Changing this file has no effect unless you specify its path with the DOCTYPE tag, described below.

You can overwrite the built-in DTD by using the XML tag, <!DOCTYPE>. For example, the following indicates that *Connext DDS* must use a different DTD file to perform validation:

```
<!DOCTYPE dds SYSTEM
"/local/usr/rti/dds/modified_rti_dds_profiles.dtd">
```

If you do not specify the DOCTYPE tag in the XML file, the built-in DTD is used. The DTD path can be absolute or relative to the application's current working directory.

5.3.2 Validation during Editing

Connext DDS provides DTD and XSD files that describe the format of the XML content. We highly recommend including a reference to the XSD in the XML file. This provides helpful features in code editors such as Visual Studio, Eclipse, or Netbeans, including validation and auto-completion while you are editing the XML file.

To include a reference to the XSD file, use the **noNamespaceSchemaLocation** attribute inside the opening <dds> tag, as illustrated below (replace '6.x.y' with the current version number and replace <NDDSHOME> as described in Chapter 2 Paths Mentioned in Documentation on page 3):

```
<?xml version="1.0" encoding="UTF-8"?>
<dds xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
    xsi:noNamespaceSchemaLocation=
    "<NDDSHOME>/resource/schema/rti_dds_profiles.xsd"
    version="6.x.y">
```

You may use relative or absolute paths to the schema files. These files are provided as part of your distribution in the following location (replace <NDDSHOME> as described in Chapter 2 Paths Mentioned in Documentation on page 3):

- <NDDSHOME>/resource/schema/rti dds profiles.xsd
- <NDDSHOME>/resource/schema/rti_dds_profiles.dtd

If you want to use the DTD for syntax validation instead of the XSD, use the <!DOCTYPE> tag. Note, however, that this validation is less strict and will offer far less help in terms of auto-completion. The use of <!DOCTYPE> is shown below. Simply replace \$NDDSHOME with your *Connext DDS* installation directory:

5.4 Accessing Entities Defined in XML Configuration from an Application

You can use the operations listed in Table 5.1 Operations Intended for Use with XML-Based Configuration to retrieve and then use the *Entities* defined in your XML configuration files.

Table 5.1 Operations Intended for Use with XML-Based Configuration

Working with	Configuration-Related Operations	Reference
DomainParticipantFactory	create_participant_from_config create_participant_from_config_w_ params lookup_participant_by_name	5.7.1 Creating and Retrieving a DomainParticipant Configured in an XML File on page 46
	register_type_support	5.7.5 Using User-Generated Types on page 49
DomainParticipant	lookup_publisher_by_name lookup_subscriber_by_name lookup_datawriter_by_name lookup_datareader_by_name	5.7.2 Creating and Retrieving Publishers and Subscribers on page 47
Publisher Subscriber	lookup_datawriter_by_name	5.7.3 Creating and Retrieving DataWriters and DataReaders on page 48

5.5 XML Tags for Configuring Entities

There are two top-level tags to configure Entities in the XML configuration files:

- <domain_library>: Defines a collection of domains. A domain defines a global data-space where applications can publish and subscribe to data by referring to the same *Topic* name. Each domain within the domain library defines the *Topics* and associated data-types that can be used within that domain. Note that this list is not necessarily exhaustive. The participants defined within the <domain_participant_library> might add *Topics* beyond the ones listed in the domain library.
- <domain_participant_library>: Defines a collection of *DomainParticipants*. A *DomainParticipant* provides the means for an application to join a domain. The *DomainParticipant* contains all the Entities needed to publish and subscribe data in the domain (*Publishers*, *Subscribers*, *DataWriters*, *DataReaders*, etc.).

Figure 5.2: Top-Level Tags in Configuration File below and Table 5.2 Top-Level Tags in Configuration File describe the top-level tags that are allowed within the root <dds> tag.

Figure 5.2: Top-Level Tags in Configuration File




Table 5.2 Top-Level Tags in Configuration File

Tags within <dds></dds>	Description		Number of Tags Allowed
<domain_lib- rary></domain_lib- 	Specifies a domain library. Set of <domain> definitions. Attributes:</domain>		0 or more
laly-	name	Domain library name	
<domain_par-< td=""><td colspan="2">Specifies a participant library. Set of <domain_participant> definitions.</domain_participant></td><td></td></domain_par-<>	Specifies a participant library. Set of <domain_participant> definitions.</domain_participant>		
ticipant_lib- rary>	name	Participant library name	0 or more

Table 5.2 Top-Level Tags in Configuration File

Tags within <dds></dds>	Description	Number of Tags Allowed
<qos_library></qos_library>	Specifies a QoS library and profiles. The contents of this tag are specified in the same manner as for a <i>Connext DDS</i> QoS profile file—see <u>Configuring QoS with XML, in the RTI Connext DDS Core Libraries User's Manual</u> .	0 or more
<types></types>	Defines types that can be used for dynamic data registered types. See Creating User Data Types with Extensible Markup Language (XML), in the RTI Connext DDS Core Libraries User's Manual.	0 or 1

5.5.1 Domain Library

A domain library provides a way to organize a set of domains that belong to the same system. A domain represents a data space where data can be shared by means of reading and writing the same *Topics*, each *Topic* having an associated data-type. Therefore, in a <domain> tag you can specify *Topics* and their data types.

Figure 5.3: Domain Library Tag




Figure 5.3: Domain Library Tag above, Table 5.3 Domain Library Tags, and Table 5.4 Domain Tags describe what tags can be in a <domain_library>.

- The <register_type> tag specifies a type definition that will be registered in the *DomainParticipants* whenever they specify a *Topic* associated with that data type.
- The <topic> tag specifies a *Topic* by associating it with a <register_type> that contains the type information.

In a domain, you can also specify the domain ID to which the *DomainParticipant* associated with this domain will be bound.

Table 5.3 Domain Library Tags

Tags within <domain_ library></domain_ 	Description		Number of Tags allowed	
	Specifies a domain. Attributes:			
	name	Domain name		
<domain></domain>	domain_id (<i>optional</i>)	Domain ID (default id=0)	1 or more	
	base_name	Base domain name. Specifies another domain from which properties will be inherited.		

Table 5.4 Domain Tags

Tags within <domain></domain>	Description		Number of Tags allowed
<register_ type></register_ 	builtin.string (see String builtin.keyedString (see builtin.octets (see Octet builtin.keyedOctets (see dynamicData Data type	ta type to be registered. These are as follows: Builtin Type, in the RTI Connext DDS Core Libraries User's Manual) Keyed String Builtin Type, in the RTI Connext DDS Core Libraries User's Manual) Builtin Type, in the RTI Connext DDS Core Libraries User's Manual) Keyed Octets Builtin Type, in the RTI Connext DDS Core Libraries User's Manual) Keyed Octets Builtin Type, in the RTI Connext DDS Core Libraries User's Manual) is defined within the <types> tag. defined by the type support code created by the code generator, rtiddsgen.</types>	1 or more
	name type_ref(optional)	Name used to refer to this registered type within the XML file. This is also the name under which the type is registered with the <i>DomainParticipants</i> unless overridden by the <registered_name> tag. Reference (fully qualified name) to a defined type within <types>. Indicates to use DynamicData if a type is not registered at participant creation time.</types></registered_name>	

Table 5.4 Domain Tags

Tags within <domain></domain>	Description		
	Specifies a topic associa	ating its data-type and optionally QoS.	
	name	Name of the topic if no <registered_name> is specified.</registered_name>	
<topic></topic>	register_type_ref	Name of a registered type support or reference (name) to a register_type within this domain with which this topic is associated. A built-in registered type can be specified by using one of these special values: • DDS::String	1 or more
		DDS::KeyedString	
		• DDS::Octets	
		DDS::KeyedOctets	

Note that a domain may inherit from another "base domain" definition by using the **base_name** attribute. A domain that declares a "base domain" might still override some of the properties in the base domain. Overriding is done simply by including elements in the derived domain with the same name as in the base domain.

The <register_type> tag, described in Figure 5.4: Register Type Tag below and Table 5.5 Register Type Tag, determines how a type is registered by specifying the type definition and the name with which it is registered.

Figure 5.4: Register Type Tag




Table 5.5 Register Type Tag

Tags within <register_type></register_type>	Description	Number of tags allowed
<registered_name></registered_name>	Name with which the type is registered.	0 or 1

The <topic> tag, described in Figure 5.5: Topic Tag below and Table 5.6 Topic Tag, describes a *Topic* by specifying the name and type of the *Topic*. It may also contain the QoS configuration for that *Topic*.

Figure 5.5: Topic Tag




Table 5.6 Topic Tag

Tags within <topic></topic>	Description	Number of tags allowed
<registered_name></registered_name>	Name of the <i>Topic</i> .	0 or 1
<topic_qos></topic_qos>	Topic QoS configuration.	0 or 1

Some elements may refer to already specified types and QoS tags. The definitions of these referenced tags may appear either in the same configuration file or in a different one—as long as it is one of the ones loaded by *Connext DDS* as described in 5.2 Loading XML Configuration Files on page 29.

If a QoS is not specified for an Entity, then the QoS will be set to a default value that is either the default configured in the XML files, or if such default does not exist, then the *Connext DDS* QoS defaults. Please see Configuring QoS with XML, in the RTI Connext DDS Core Libraries User's Manual for more details.

For example:

```
</domain>
</domain library>
```

The above configuration defines a domain with name "MyDomain" and domain_id "10" containing a *Topic* called "MyTopic" with type "MyType" registered with the name "MyRegisteredType":

- <register_type> defines the registration of a dynamic data type with name "MyRegisteredType" and definition "MyType"—defined in the same file.
- <topic> with name "MyTopic" and whose corresponding type is the one defined above with the name "MyRegisteredType" found within the same configuration. The *Topic* QoS configuration is the one defined by the profile "qosLibrary::DefaultProfile", which is defined in a different file.

Note that the *DomainParticipant* created from a configuration profile bound to this domain will be created with **domain_id=10**, unless the **domain_id** is overridden in the participant configuration.

5.5.2 Participant Library

A participant library provides a way to organize a set of participants belonging to the same system. A participant configuration specifies all the entities that a *DomainParticipant* created from this configuration will contain.

Figure 5.6: Participant Library Tag




Figure 5.6: Participant Library Tag on the previous page, Table 5.7 Participant Library Tag, and Table 5.8 Domain Participant Tag show the description of a <domain_participant_library> and the tags it contains.

A <domain_participant> can be associated with a domain where topics and their associated types are already defined. The elements <register_type> and <topic> may also be defined in a <domain_participant>—the same way it is done in a <domain>. This makes it possible to add *Topics*, data-types, etc. beyond the ones defined in the domain, or alternatively redefine the elements that are already in the <domain>.

A <domain_participant> is defined by specifying the set of *Entities* it contains. This is done using tags such as <publisher>, <subscriber>, <data_writer> and <data_reader>, which specify an *Entity* of their corresponding type. These *Entities* are created within the *DomainParticipant* instantiated from the configuration profile that contains the definitions.

Table 5.7 Participant Library Tag

Tags within <domain_ participant_library></domain_ 		Number of Tags Allowed		
	Specifies a parti Attributes:	cipant configuration.		
	name	Participant configuration name.		
<domain_participant></domain_participant>	base_name (optional)	Base participant name. It specifies another participant from which to inherit the configuration.	1 or more	
	domain_ref (optional)	Reference (fully qualified name) to a defined <domain> in the domain library.</domain>		
	domain_id (<i>op-tional</i>)	Domain ID. If specified, overrides the id in the domain it refers to. If no domain_id is specified directly or in the referenced domain then the default domain_id is 0.		

A <domain_participant> may inherit its configuration from another "base participant" specified using the **base_name** attribute. In this case, overriding applies to the base <domain_participant> as well as to the referred <domain>.

Note that in *DataWriters* always belong to a *Publisher* and *DataReaders* to a *Subscriber*. For this reason the <data_writer> and <data_reader> typically appear nested inside the corresponding <publisher> and <subscriber> tags. However, for convenience, it is possible to define <data_writer> and <data_reader> tags directly under the <domain_participant> tag. In this case, the *DataWriters* and *DataReaders* are created inside the implicit *Publisher* and *Subscriber*, respectively.

Table 5.8 Domain Participant Tag


Tags within <domain_ participant=""></domain_>	Description		
<memory_ management></memory_ 	Configures certain aspects of how Connext DDS allocates internal memory. The configuration is per DomainParticipant and therefore affects all the contained DataReaders and DataWriters. For example: <pre></pre>		0 or more
<register_ type></register_ 	Specifies how a type is registered. Same as within the <domain> tag</domain>		
<topic></topic>	Specifies a topic. Same as within the <domain> tag</domain>		
	Specifies a configuration. Attributes:		
<publisher></publisher>	name	Publisher configuration name.	0 or more
	multiplicity (optional)	Number of <i>Publishers</i> that are created with this configuration. Default is 1.	
	Specifies a <i>Subscriber</i> configuration. Attributes:		
<subscriber></subscriber>	name	Subscriber configuration name.	0 or more
	multiplicity (<i>optional</i>)	Number of <i>Subscribers</i> that are created with this configuration. Default is 1.	


Table 5.8 Domain Participant Tag

Tags within <domain_ participant=""></domain_>	Description		Number of Tags Allowed
	Specifies a <i>DataWriter</i> configuration. The <i>DataWriter</i> will be created inside the implicit <i>Publisher</i> . Attributes:		
	name	DataWriter configuration name.	
<data_writer></data_writer>	topic_ref	Reference (name) a <topic> within the <domain> referenced by its <participant> parent.</participant></domain></topic>	0 or more
	multiplicity (optional)	Number of <i>DataWriters</i> that are created with this configuration. Default is 1.	
	Specifies a data reader configuration. The <i>DataReader</i> will be created inside the implicit subscriber. Attributes:		
	name	Data reader configuration name.	
<data_ reader></data_ 	topic_ref	Reference (name) a <topic> within the <domain> referenced by its <participant> parent.</participant></domain></topic>	0 or more
	multiplicity (optional)	Number of <i>DataReaders</i> that are created with this configuration. Default is 1.	
<pre><participant_ qos=""></participant_></pre>	DomainParticipant QoS configuration.		0 or 1

The <publisher>, <subscriber>, <data_writer>, and <data_reader> tags are described in Figure 5.7: Publisher and Subscriber Tags on the next page, Table 5.9 Publisher Tag, Table 5.10 Subscriber Tag, Table 5.11 DataWriter Tag and Table 5.12 DataReader Tags.

Figure 5.7: Publisher and Subscriber Tags





The <publisher> tag defines by default a *Publisher*. It may contain a QoS configuration and several *DataWriters*. Likewise, the <subscriber> tag defines by default a *Subscriber*. It may contain a QoS configuration and several *DataReaders*.

Table 5.9 Publisher Tag

Tags within <publisher></publisher>	Description	Number of Tags Allowed
<data_writer></data_writer>	Specifies a <i>DataWriter</i> configuration. Same as within the <participant> tag.</participant>	0 or more
<publisher_qos></publisher_qos>	Publisher QoS configuration.	0 or 1

Table 5.10 Subscriber Tag

Tags within <subscriber></subscriber>	Description	Number of Tags Allowed
<data_reader></data_reader>	Specifies a DataReader configuration. Same as within the <participant> tag.</participant>	0 or more
<subscriber_qos></subscriber_qos>	Subscriber QoS configuration.	0 or 1

Table 5.11 DataWriter Tag

Tags within <data_writer></data_writer>	Description	Number of Tags Allowed
<datawriter_qos></datawriter_qos>	DataWriter QoS configuration	0 or 1

Table 5.12 DataReader Tags

Tags within <data_reader></data_reader>	Description		Number of Tags Allowed
<datareader_ qos></datareader_ 	DataReader QoS configuration.		0 or more
	Enables the creation of <i>I</i> Attributes:	DataReader with this configuration from a ContentFilteredTopic.	
<filter></filter>	name	Name of the ContentFilteredTopic. The ContentFilteredTopic will be associated with the same <i>Topic</i> referenced by the containing <data_reader></data_reader>	0 or 1
	filter_kind	Specifies which ContentFilter to use. It defaults to the builtin.sql filter.	

The <filter> tag within a <data_reader> enables content filtering. It causes the corresponding *DataReader* to be created from a ContentFilteredTopic with the specified filter characteristics.

The ContentFilteredTopic name is generated as follows: xml filter name::xml topic name.

Where **xml_filter_name** is the value of the attribute name of the <filter> tag, and **xml_topic_name** is the value of the attribute name of the referred <topic> tag.

Table 5.13 Filter Tag

Tags within <filter></filter>	Description	Number of Tags Allowed
<expression></expression>	Filter expression	0 or 1
<pre><parameter_list></parameter_list></pre>	List of parameters. Parameters are specified using <param/> tags. The maximum number of parameters is 100. <parameter_list></parameter_list>	0 or 1

For example:

The above configuration defines a <domain participant> that is bound to the <domain> "MyDomain".

A *DomainParticipant* created from this configuration will contain:

- A *Publisher* which has a *DataWriter* created from the *Topic* "MyTopic".
- A *Subscriber* which has *DataReader* created from a ContentFilteredTopic whose related *Topic*, "MyTopic", uses a SQL filter. The ContentFilteredTopic has the name "MyTopic::MyFilter".

5.6 Names Assigned to Entities

Each Entity configured in an XML file is given a unique name. This name is used to refer to it from other parts of the XML configuration and also to retrieve it at run-time using the *Connext DDS* API.

In the context of XML-based configuration, we distinguish between two kinds of names:

- Configuration name: The name of a specific Entity's configuration. It is given by the name attribute of the corresponding XML element.
- **Entity name:** The actual name of the Entity within the run-time system. The name assignment follows these rules of precedence:
 - 1. An explicit name provided as a parameter in DomainParticipantConfigParams_t (applies only to a *DomainParticipant*).
 - 2. An explicit name, obtained from the specified EntityNameQosPolicy settings.
 - 3. A default entity name, obtained from the name attribute of the corresponding configuration.

For example:

```
</domain_participant>
</domain_participant_library>
```

For the above XML configuration, the name assignments are:

Entity	Configuration Name	Entity Name
DomainParticipant	"MyParticipant"	"MyParticipant"
Publisher	"MyPublisher"	"MyPublisher"
DataWriter	"MyWriter"	"MyWriter"
DataWriter	"MyWriter2"	"WriterNameFromQos"

For all the cases, the entity name is stored by *Connext DDS* using the EntityNameQosPolicy QoS policy for *DomainParticipants*, *Publishers*, *Subscribers*, *DataWriters* and *DataReaders*. The policy is represented by the following C structure:

```
Struct DDS_EntityNameQosPolicy {
    char * name;
    char * role_name;
}
```

The mapping is:

Field	Value
name	Entity name
role_name	Configuration name

For the above XML example, assuming the entities are created with create_participant_from_config(configuration):

Entity	EntityNameQosPolicy
DomainParticipant	name = "MyParticipant" role_name = "MyParticipant"
Publisher	name = "MyPublisher" role_name = "MyPublisher"
DataWriter	name = "MyWriter" role_name = "MyWriter"
DataWriter	name = "WriterNameFromQos" role_name = "MyWriter2"

5.6.1 Referring to Entities and Other Elements within XML Files

Entities and other elements within the XML file are addressed using a hierarchical name that matches their declaration hierarchy. This is summarized in the table below.

Entity or Element	Hierarchical Name	Example Use
type	[type_name]	type_ref="MyType"
qos	[qos_library_name]::[qos_profile_name]	base_name="qosLibrary::DefaultProfile"
domain	[domain_libary_name]::[domain_name]	domain_ref= "MyDomainLibrary::MyDomain"
participant	[domain_participant_library_name]:: [participant_name]	base_name= "MyParticipantLibrary::PublicationParticipant"
topic	[topic_name] Must be defined within the scope of the Domain or the Participant that refers to it	topic_ref="MyTopic"
publisher	[publisher_name] Must be defined within the scope of the Participant that refers to it	base_name="MyPublisher"
subscriber	[subscriber_name] Must be defined within the scope of the Participant that refers to it	base_name="MySubscriber"
data_writer	[publisher_name]::[datawriter_name] If addressing from within the same Publisher, the "publisher_name::" prefix may be omitted	base_name="MyPublisher::MyWriter" base_name="MyWriter"
data_reader	[subscriber_name]::[datareader_name] If addressing from within the same Subscriber, the "subscriber_name::" prefix may be omitted	base_name="MySubscriber::MyReader" base_name="MyReader"

The example above corresponds to a configuration such as the one following:

```
</domain>
       </domain library>
       <domain participant library name="MyParticipantLibrary">
                <domain participant name="MyParticipant"</pre>
                domain ref="MyDomainLibrary::MyDomain">
                         <publisher name="MyPublisher">
                                 <data writer name="MyWriter"</pre>
                                  topic ref="MyTopic"/>
                         </publisher>
                        <subscriber name="MySubscriber">
                                  <data reader name="MyReader"</pre>
                                  topic ref="MyTopic"/>
                         </subscriber>
                 </domain participant>
        </domain_participant_library>
</dds>
```

5.7 Creating and Retrieving Entities Configured in an XML File

There are two kinds of operations that affect *Entities* configured in an XML file:

- Create the defined entities. Only the operation **create_participant_from_config()** in the DomainParticipantFactory triggers the creation of a *DomainParticipant* and all its contained Entities given a configuration name.
- Retrieve the defined entities: After creation, you can retrieve the defined Entities by using the
 lookup_by_name() operations available in the DomainParticipantFactory, DomainParticipant, Publisher and Subscriber.

5.7.1 Creating and Retrieving a DomainParticipant Configured in an XML File

To create a *DomainParticipant* from a configuration profile in XML, use the function **create_participant_from_config()**, which receives the configuration name and creates all the entities defined by that configuration.

For example:

Given the above configuration, a *DomainParticipant* is created as follows:

```
//handle error
}
```

The *DomainParticipant* is bound to the domain_id specified in either the <domain_participant> tag—this has precedence—or the <domain> tag. In this example the **domain id** is set to one.

When the *DomainParticipant* is created by means of **create_participant_from_config()**, a name will be generated automatically based on the configuration name and the number of existing participants created from the same configuration. The generation follows the same strategy explained in 5.6 Names Assigned to Entities on page 43 for the domain entities where the multiplicity is replaced by the number of existing participants. If this is number is identified by "N", the participant name for a new participant will be assigned as follows:

Participant Name	N
"configuration_name"	0
"configuration_name#N"	[1,N-1]

For example, if we create three participants from the configuration "lib::participant", the names assigned as the participants are created will be:

- -participant
- -participant#1
- -participant#2

Once a participant is created, it can be retrieved by its name at any other place in your program as follows, based on the previous example and assuming that only one participant was created:

To provide more flexibility, **create_participant_from_config_w_params()** allows you to specify the participant name. You can also override the specification in the configuration for the domain ID and QoS profile for the participant and entites in the domain.

5.7.2 Creating and Retrieving Publishers and Subscribers

Publishers and Subscribers configured in XML are created automatically when a DomainParticipant is created from the <domain participant> that contains the <publisher> and <subscriber> configurations.

Given the following example:

Once a *DomainParticipant* is created as explained in 5.7.1 Creating and Retrieving a DomainParticipant Configured in an XML File on page 46, *Publishers* and *Subscribers* can be retrieved from the created *DomainParticipant* using their name as follows:

5.7.3 Creating and Retrieving DataWriters and DataReaders

DataWriters and DataReaders configured in XML are created automatically when a DomainParticipant is created from the <domain_participant> that contains the <data_writer> and <data_reader> configurations.

Given the following example:

Once a *DomainParticipant* is created as explained in 5.7.1 Creating and Retrieving a DomainParticipant Configured in an XML File on page 46, *DataWriters* and *DataReaders* can be retrieved from the created *DomainParticipant* using their fully qualified name seen below:

```
DDSDataWriter * dataWriter =
    participant->lookup_dataWriter_by_name(
    "MyPublisher::MyWriter");
if (dataWriter == NULL) {
    //handle error
}
DDSDataReader * dataReader =
    participant->lookup_datareader_by_name(
"MySubscriber::MyReader");
if (dataReader == NULL) {
    //handle error
}
```

Or from the created *Publisher* and *Subscriber*, using their 'unqualified' name seen below:

```
DDSDataWriter * dataWriter =
    publisher->lookup_dataWriter_by_name("MyWriter");
if (dataWriter == NULL) {
    //handle error
}
DDSDataReader * dataReader =
    subscriber->lookup datareader by name("MyReader");
```

5.7.4 Creating Content Filters

To use a content filter, modify the "SubscriptionParticipant" configuration to look like this:

It adds a SQL content filter, which only accepts samples with the field count greater than two.

Now run the HelloWorld_subscriber application without recompiling and check that it only receives data when counter less than 20 as expected.

5.7.5 Using User-Generated Types

If a user-generated type by means of *rtiddsgen* is desired rather than dynamic data, the corresponding type support must be registered with the DomainParticipantFactory before creating a *DomainParticipant*. To register the type support, use the function **register_type_support()** in the DomainParticipantFactory,

which takes (a) a pointer to a function that registers a type and (b) the type name it is registered with. Then the specified function will be called automatically by the middleware whenever the type registration is needed.

The definition of this function is given by:

This "register type function" should be generated using the *rtiddsgen* command-line tool from the IDL or XML definition of the data type. See 3.2 Hello World using XML and Compiled Types on page 16 for a simple example of how to follow this process.

For example, the following XML snippet defines a data type registered under the name **MyType** with a TypeSupport that is user-generated. To use this data type, the application must also generate the TypeSupport code for the appropriate language binding using *rtiddsgen* and associate the generated TypeSupport with the name **MyType**. This association is made by calling the operation **register_type_support()** on the DomainParticipantFactory:


Continuing the example above, assume that the structure of "MyType" is described in the IDL file MyType.idl. Also assume that you are using the C++ language API and you have already run rtiddsgen and generated the type-support files: MyTypeSupport.h and MyTypeSupport.exx. These files will contain the declaration and implementation of the function MyTypeSupport::register_type(). In this situation, you must associate the MyTypeSupport::register_type() operation with the type name MyType by calling DDSTheParticipantFactory->register_type_support() from your application code prior to creating the *DomainParticipant* as shown in the C++ snippet below:

You can find an example of using a user-generated type in **<path to examples>/connext_dds/c++/hello_world_xml_compiled**. Also refer to the description of this example in 3.2 Hello World using XML and Compiled Types on page 16.

Chapter 6 Connext DDS Micro Application Generation

XML-Based Application Creation can also be used to configure Connext DDS Micro applications, through a utility called RTI Micro Application Generator (MAG).

MAG generates code from an XML configuration file; it creates DDS entities and registers all the components needed for a *Connext DDS Micro*-based application.



Extending XML-Based Application Creation to Connext DDS Micro enables two important use cases:

- Users who may eventually develop with *Connext DDS Micro*, but who haven't determined their final platform, can prototype applications on a generic platform and validate that the QoS and DDS Entity configuration is within scope of what *Connext DDS Micro* supports. The same concept applies to those who eventually want to use *Connext DDS* in a safety-critical platform, such as those required by DO-178C for avionics or ISO 26262 for automotive applications.
- Users who want to develop directly with *Connext DDS Micro* can simplify their development efforts through shared XML files that can be configuration managed. This reduces the burden on system integrators who want to configure *Connext DDS Micro* systems without having to manually code in static configurations.

Some of the main features of MAG are:

- Generates code for the languages supported by *Connext DDS Micro*: C and C++.
- Automatically configures the remote entities that are needed to communicate with applications that
 use static discovery.
- Automatically tries to use the default values used by *Connext DDS Micro*, to reduce the size of the generated code.
- Optimizes the components used by your application. By default, MAG generates code that will unregister transports that your application is not using.

Notes:

- MAG has been tested with Oracle JRE 8, which is included in the installation package. No other versions of Java are supported.
- Customization is not currently supported for MAG.

6.1 Paths Mentioned in Documentation

This chapter may refer to:

• <RTIMEHOME>

This refers to the installation directory for *Connext DDS Micro*. The default installation paths are:

- Mac OS X systems: /Applications/rti_connext_dds-6.0.1/rti_connext_dds_micro-3.0.1
- UNIX-based systems, non-root user: /home/<your user name>/rti connext dds-6.0.1/rti connext dds micro-3.0.1

- UNIX-based systems, root user: /opt/rti connext dds-6.0.1/rti connext dds micro-3.0.1
- Windows systems, user without Administrator privileges:
 <your home directory>\rti_connext_dds-6.0.1\rti_connext_dds_micro-3.0.1
- Windows systems, user with Administrator privileges:
 - 64-bit machines:

C:\Program Files\rti_connext_dds-6.0.1\rti_connext_dds_micro-3.0.1

• 32-bit machines:

C:\Program Files (x86)\rti connext dds-6.0.1\rti connext dds micro-3.0.1

You may also see \$RTIMEHOME or %RTIMEHOME%, which refers to an environment variable set to the installation path.

Wherever you see <RTIMEHOME> used in a path, replace it with your installation path.

Note for Windows Users: When using a command prompt to enter a command that includes the path C:\Program Files (or any directory name that has a space), enclose the path in quotation marks. For example:

```
"C:\Program Files\rti_connext_dds-6.0.1\rti_connext_dds_micro-3.0.1\rtiddsmag\scripts\rtiddsmag.bat"
```

Or if you have defined the RTIMEHOME environment variable:

"%RTIMEHOME%\rtiddsmag\scripts\rtiddsmag.bat"

<path to Micro examples>

Connext DDS Micro examples are in **<RTIMEHOME>/example** after you've installed Connext DDS Micro. This document refers to the location of these examples as **<path to Micro examples>**.

Wherever you see <path to Micro examples>, replace it with the appropriate path.

Default path to the *Connext DDS Micro* examples:

- UNIX-based systems: <RTIMEHOME>/example/unix
- Windows systems: <RTIMEHOME>\example\windows

Note: The script to run MAG can be in two different folders:

- <NDDSHOME>/bin/rtiddsmag
- <RTIMEHOME>/rtiddsmag/scripts/rtiddsmag

The first script is included in the *Connext DDS Professional* bundle and the second in the *Connext DDS Micro* RTI package.

6.2 Command-Line Options

The following table shows the options available when using *rtiddsmag* to generate code for *Connext DDS Micro* applications.

Table 6.1 Command-Line Options for rtiddsmag

Option	Description
-d <outdir></outdir>	Generates the output in the specified directory. By default, MAG will generate files in the directory where the XML file is located.
-dontAddLocations	Use this flag to avoid adding the input file location of fields into the generated files. By default (when this flag is not used), MAG will add the location where an entity was defined in the XML file. The location will be placed above the definition of that entity in the generated code.
-dontOptimizeSE	Use this flag to avoid static endpoint discovery optimization. Then MAG will include all DataWriters and DataReaders when calculating the remote entities. By default (when this option is not used) MAG will optimize the number of remote entities by only including Data Writers and DataReaders that use the same Topic in the remote model.
-dontUpdateResourceLimits	Use this flag to avoid automatically updating the resource limit settings for DomainParticipants, DataReaders and DataWriters. By default (when this flag is not used), MAG will update the resource limits so it will at least be able to support the entities defined in the XML file. If your applications communicate with more remote entities that the ones specified in the XML file, you might need to manually update them.
-dontUseDefaultValues	Use this flag to avoid automatically generating code using default QoS policy values when possible. By default (when this flag is not used), MAG will check whether the values that are set in every element of the QoS policies for each entity are the same as the defaults used by <i>Connext DDS Micro</i> . If that's the case, the generated code will contain the default values for those policies, instead of the values set by the user.
-dpdeName <name></name>	Specifies the name used by MAG when registering a DPDE discovery plugin. By default, this name is dpde .
-dpseName <name></name>	Specifies the name used by MAG when registering a DPSE discovery plugin. By default, this name is dpse .
-help	Prints out the command-line options for MAG.
-idlFile <file></file>	Specifies the IDL file name used by rtiddsgen to generate the code. This value is used by MAG to specify the Plugin header generated by rtiddsgen. By default, MAG uses the name of the XML file.
-language <c c++></c c++>	Specifies the language to use for the generated files. The default language is C
-onlyValidate	Causes MAG to just validate the input file. It will not generate any code.
-outputFinalQoS <qoslibrary::qosprofile></qoslibrary::qosprofile>	Use this flag to display the final values of the specified QoS profile after applying inheritance. Although MAG currently doesn't generate code to set the QoS for <i>Connext DDS Micro</i> , using this flag will determine the final values in the profile after applying inheritance. For complex XML files, with multiple levels of inheritance, it might be a challenge to determine the final QoS values. Using this flag simplifies the process. Note: This option does not check whether or not the final values are supported by <i>Connext DDS Micro</i> .

Option	Description	
-referencedFile <file></file>	Specifies a file which is referenced from the one being used to generate code. In general, it is recommended to split the application definition from the QoS definition. This way, the QoS can be shared among various applications. Note: Can be repeated: -referencedFile <file1> -referencedFile <file2></file2></file1>	
-replace	Use this flag to overwrite existing generated files.	
-shmemName <name></name>	Specifies the name used by MAG when registering a shared emmory (SHMEM) transport plugin. By default, this name is shmem .	
-udpName <name></name>	Specifies the name used by MAG when registering a UDP transport plugin. By default, this name is udp .	
-verbosity [1-4]	Sets the MAG verbosity: 1: Exceptions. 2: Exceptions and warnings. 3: Exceptions, warnings, and information. (Default) 4: Exceptions, warnings, information, and debug.	
-version	Displays the version of MAG being used, such as 1.x.y.	

6.3 Generated Files

The following table shows the files that MAG creates for an example XML file, **HelloWorld.xml** (which contains the application definition) and a referenced file, **HelloWorldQos.xml** (which contains the QoS definition). This second file is optional; you can define the QoS in the application file.

Table 6.2 C and C++ Files Created for Example HelloWorld.xml

Generated Files	Description
HelloWorldAppgen.h (C and C++)	Generated code for each DDS <i>Entity</i> and its run-time components.
HelloWorldAppgen.c (C and C++)	Generated code for each Entity Model; also contains the values of each array used in the header file.
HelloWorldAppgen_plugin.h (C++ only)	Header file that contains the declarations of all the wrappers.
HelloWorldAppgen_plugin.cxx (C++ only)	A wrapperforthe _get() call (get_plugin_type): struct DDS_TypePluginI *HelloWorldPlugin_get_cpp(void) { return HelloWorldPlugin_get(); }

6.3.1 Integrating Generated Files into Your Application's Build

Integrating the generated files into your application is as easy as including the generated files **Hel-loWorldAppgen.c** in your application. If your application uses C++, you will also need to include **HelloWorldAppgen plugin.h** and **HelloWorldAppgen plugin.cxx**.

Then you can create entities using the standard **DDS_DomainParticipantFactory_create_participant_from_config()** operation and retrieve all the entities from your application code using the standard **lookup_<entity>_by_name()** operations, such as **lookup_datawriter_by_name()**. For details on these operations, see the DomainParticipantFactory module in the *Connext DDS Micro* API reference HTML documentation, available at https://community.rti.com/documentation/.

6.4 A "Hello, World" Example

This simple scenario consists of two applications: **HelloWorld_publisher**, which writes the *Topic*, HelloWorldTopic, and **HelloWorld_subscriber**, which subscribes to that *Topic*.

The files for this example are provided when you install *Connext DDS Micro*. You will find them in the directory **<path to Micro examples>/C/HelloWorld_appgen**. (See 6.1 Paths Mentioned in Documentation on page 52.)

6.4.1 Generate Type-Support Code from the Type Definition

The first step is to describe the data type in a programming language-neutral manner. Three languages are supported by *RTI Code Generator*: XML, IDL, and XSD. These three languages provide equivalent type-definition capabilities, so you can choose whichever one you prefer. You can even transform between one of these three languages and another with *RTI Code Generator*. That said, since the rest of the configuration files use XML, it is often more convenient to also use XML to describe the data types, so they can be shared or moved to other XML configuration files.

The file **HelloWorld.xml** contains the XML description of the data type. You can find this file in **<path to Micro examples>/C/HelloWorld appgen**.

Let's examine the type used in this example:

The data associated with the HelloWorld *Topic* consists of two strings and a numeric counter:

- 1. The first string contains the name of the sender of the message. This field is marked as the "key" since it signals the identity of the data-object.
- 2. The second string contains a message.
- 3. The third field is a simple counter, which the application increments with each message.

Once the type has been defined, we use *rtiddsgen* to generate the code for the HelloWorld data type.

We will use the C language in this example.

To generate code with rtiddsgen:

• On a Windows system:

From your command shell, change directory to **<path to Micro examples>\C\HelloWorld_app-gen** and type:

```
<RTIMEHOME>\rtiddsgen\scripts\rtiddsgen.bat -language C -micro HelloWorld.xml
```

Note: The Visual Studio solution in the example folder automatically calls *rtiddsgen*.

• On a UNIX-based system:

From your command shell, change directory to **<path to Micro examples>/C/HelloWorld_app-gen** and type:

```
<RTIMEHOME>/rtiddsgen/scripts/rtiddsgen -language C -micro HelloWorld.xml
```

After running *rtiddsgen*, you will see the following files in the **HelloWorld appgen** directory:

- HelloWorld.h
- HelloWorld.c
- HelloWorldPlugin.h
- HelloWorldPlugin.c
- HelloWorldSupport.h
- HelloWorldSupport.c

The most notable files are **HelloWorld.h** and **HelloWorldPlugin.h**:

• **HelloWorld.h** contains the declaration of the C structure, built according to the specification in the XML file:

```
typedef struct HelloWorld
{
    CDR_String sender;
    CDR_String message;
    CDR_Long count;
} HelloWorld;
```

• **HelloWorldPlugin.h** contains the **get_plugin_type()** function that MAG will use when generating the code to create all the DDS entities:

```
NDDSUSERD11Export extern struct NDDS_Type_Plugin*
HelloWorldTypePlugin_get(void);
```

6.4.2 Generate DDS Entities from the System Definition

This step uses *rtiddsmag* to generate code to support the creation of DDS entities using *XML-Based Application Creation*.

rtiddsmag supports C and C++. We will use C in this example.

Note: You can do this step before or after generating Type-Support from the Type definition since the type code doesn't need to exist when running *rtiddsmag*.

To generate code with rtiddsmag:

• On a Windows system:

From your command shell, change directory to **<path to Micro examples>\C\HelloWorld_app-gen** and type:

```
<NDDSHOME>\bin\rtiddsmag.bat -language C -referencedFile HelloWorldQos.xml HelloWorld.xml

or

<RTIMEHOME>\rtiddsmag\scripts\rtiddsmag.bat -language C -referencedFile HelloWorldQos.xml
HelloWorld.xml
```

Note: The Visual Studio solution in the example folder automatically calls *rtiddsmag*.

• On a UNIX-based system:

From your command shell, change directory to **<path to Micro examples>/C/HelloWorld_app-gen** and type:

```
<NDDSHOME>/bin/rtiddsmag -language C -referencedFile HelloWorldQos.xml HelloWorld.xml

or

<RTIMEHOME>/rtiddsmag/scripts/rtiddsmag -language C -referencedFile HelloWorldQos.xml
HelloWorld.xml
```

We will examine the content of the generated files in the next section.

6.4.3 Examine the XML Configuration Files and the Generated Code

The entire **HelloWorld.xml** file is shown below. Let's review its content to see how this scenario was constructed. The main sections in the file are:

- 6.4.3.1 Type Definition on the next page
- 6.4.3.2 Domain Definition on the next page
- 6.4.3.3 DomainParticipant Definition on page 62

```
<?xml version="1.0"?>
<dds xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
xsi:noNamespaceSchemaLocation="http://community.rti.com/schema/6.0.0/rti dds profiles.xsd">
   <!-- Type Definition -->
   <types>
        <const name="MAX NAME LEN" type="long" value="64"/>
       <const name="MAX MSG LEN" type="long" value="128"/>
        <struct name="HelloWorld">
            <member name="sender" type="string" stringMaxLength="MAX_NAME_LEN" key="true"/>
            <member name="message" type="string" stringMaxLength="MAX MSG LEN"/>
            <member name="count" type="long"/>
        </struct>
   </types>
    <!-- Domain Library -->
    <domain library name="HelloWorldLibrary">
        <domain name="HelloWorldDomain" domain id="0">
            <register type name="HelloWorldType" type ref="HelloWorld">
            </register type>
            <topic name="HelloWorldTopic" register type ref="HelloWorldType">
                <registered_name>HelloWorldTopic</registered_name>
            </topic>
        </domain>
    </domain library>
    <!-- Participant Library -->
    <domain participant library name="HelloWorldAppLibrary">
        <domain_participant name="HelloWorldDPDEPubDP"</pre>
        domain ref="HelloWorldLibrary::HelloWorldDomain">
            <publisher name="HelloWorldDPDEPub">
                <data writer topic ref="HelloWorldTopic" name="HelloWorldDPDEDW">
                    <datawriter qos base name="QosLibrary::DPDEProfile"/>
                </data_writer>
            </publisher>
            <participant qos base name="QosLibrary::DPDEProfile"/>
        </domain participant>
        <domain participant name="HelloWorldDPDESubDP"</pre>
         domain ref="HelloWorldLibrary::HelloWorldDomain">
            <subscriber name="HelloWorldDPDESub">
                <data reader topic ref="HelloWorldTopic" name="HelloWorldDPDEDR">
                    <datareader qos base name="QosLibrary::DPDEProfile"/>
```

```
</data reader>
            </subscriber>
            <participant qos base name="QosLibrary::DPDEProfile"/>
        </domain participant>
        <domain participant name="HelloWorldDPSEPubDP"</pre>
         domain ref="HelloWorldLibrary::HelloWorldDomain">
            <publisher name="HelloWorldDPSEPub">
                <data_writer topic_ref="HelloWorldTopic" name="HelloWorldDPSEDW">
                <datawriter qos base name="QosLibrary::DPSEProfile"/>
                </data writer>
            </publisher>
            <participant qos base name="QosLibrary::DPSEProfile"/>
        </domain participant>
        <domain participant name="HelloWorldDPSESubDP"</pre>
         domain ref="HelloWorldLibrary::HelloWorldDomain">
            <subscriber name="HelloWorldDPSESub">
                <data reader topic ref="HelloWorldTopic" name="HelloWorldDPSEDR">
                    <datareader qos base name="QosLibrary::DPSEProfile"/>
                </data reader>
            </subscriber>
            <participant qos base name="QosLibrary::DPSEProfile"/>
        </domain participant>
    </domain_participant_library>
</dds>
```

6.4.3.1 Type Definition

rtiddsmag doesn't use the types section of the XML file to generate any code. This section is used by rtiddsgen to generate the code to support the direct use of the structure 'HelloWorld' from application code (see 6.4.1 Generate Type-Support Code from the Type Definition on page 56).

6.4.3.2 Domain Definition

The domain section defines the system's *Topics* and their corresponding data types. To define a *Topic*, the associated data type must be registered with the domain, giving it a registered type name. The registered type name is used to refer to that data type within the domain when the *Topic* is defined.

In this example, the configuration file registers the previously defined HelloWorld type under the name HelloWorldType. Then it defines a *Topic* named HelloWorldTopic, which is associated with the registered type, referring to its registered name, HelloWorldType. The value used in **get_plugin_type** depends on how the registration of the data-type is configured inside the domain:

- 1. If a <register_type> tag is specified *without* a type_ref attribute, the value of **get_type_plugin** is generated from the <register_type> tag plus the string "Plugin_get".
- 2. If a <register_type> tag is specified with a type_ref attribute, the value of get_type_plugin is generated from that attribute plus the string "TypePlugin_get". Our example has type_ref = "HelloWorld", so the value of get_type_plugin will be HelloWorldTypePlugin_get.

rtiddsmag generates the following code for each entity that uses this Topic:

HelloWorldAppgen.c

These two structures are used in the DomainParticipant definition, where they will be registered by *Connext DDS Micro* when calling the Micro Application Generation API.

• HelloWorldAppgen.h

```
extern const struct APPGEN_TypeRegistrationModel

HelloWorldAppLibrary_HelloWorldDPDEPubDP_type_registrations[1];

extern const struct APPGEN_TopicModel

HelloWorldAppLibrary_HelloWorldDPDEPubDP_topics[1];
```

```
#define RTI_APP_GEN__DP_HelloWorldAppLibrary_HelloWorldDPDEPubDP \
{ \
    ...
    1UL, /* type_registration_count */ \
    HelloWorldAppLibrary_HelloWorldDPDEPubDP_type_registrations, /* type_registrations*/ \
    1UL, /* topic_count */ \
    HelloWorldAppLibrary_HelloWorldDPDEPubDP_topics, /* topics */ \
    ...
}
```

Note: *Connext DDS Micro* automatically registers the types that *rtiddsmag* generates. This means the content inside the Domain definition must match the types generated by *rtiddsgen*.

6.4.3.3 DomainParticipant Definition

The DomainParticipant section defines the *DomainParticipants* in the system and the *DataWriters* and *DataReaders* that each *DomainParticipant* has. *DomainParticipants* are defined within the <domain_participant_library> tag.

Each DomainParticipant:

- Has a unique name (within the library) which will be used later by the application that creates it.
- Is associated with a domain, which defines the **domain_id**, *Topics*, and the data types the *DomainParticipant* will use.
- Defines the *Publishers* and *Subscribers* within the *DomainParticipant*. *Publishers* contain *DataWriters*, *Subscribers* contain *DataReaders*.
- Defines the set of *DataReaders* it will use to read data. Each *DataReader* has a QoS and a unique name which can be used from application code to retrieve it.
- Defines the set of *DataWriters* it will use to write data. Each *DataWriter* has a QoS and a unique name which can be used from application code to retrieve it.
- Optionally, the *DomainParticipants*, *Publishers*, *Subscribers*, *DataWriters*, and *DataReaders* can specify a QoS profile that will be used to configure them.

The example below defines four *DomainParticipants*, two of them (HelloWorldDPDEPubDP and HelloWorldDPDESubDP) use Dynamic Participant/Dynamic Endpoint (DPDE) and the other two (HelloWorldDPSEPubDP and HelloWorldDPSESubDP) use Dynamic Participant/Static Endpoint (DPSE) discovery:

```
<datawriter_qos base_name="QosLibrary::DPDEProfile"/>
            </data writer>
        </publisher>
        <participant qos base name="QosLibrary::DPDEProfile"/>
    </domain participant>
    <domain participant name="HelloWorldDPDESubDP"</pre>
    domain ref="HelloWorldLibrary::HelloWorldDomain">
        <subscriber name="HelloWorldDPDESub">
            <data reader topic ref="HelloWorldTopic" name="HelloWorldDPDEDR">
                <datareader qos base name="QosLibrary::DPDEProfile"/>
            </data reader>
        </subscriber>
        <participant qos base name="QosLibrary::DPDEProfile"/>
    </domain participant>
    <domain participant name="HelloWorldDPSEPubDP"</pre>
     domain ref="HelloWorldLibrary::HelloWorldDomain">
        <publisher name="HelloWorldDPSEPub">
            <data writer topic ref="HelloWorldTopic" name="HelloWorldDPSEDW">
                <datawriter qos base name="QosLibrary::DPSEProfile"/>
            </data writer>
        </publisher>
        <participant qos base name="QosLibrary::DPSEProfile"/>
    </domain participant>
    <domain participant name="HelloWorldDPSESubDP"</pre>
    domain ref="HelloWorldLibrary::HelloWorldDomain">
        <subscriber name="HelloWorldDPSESub">
            <data reader topic ref="HelloWorldTopic" name="HelloWorldDPSEDR">
                <datareader qos base name="QosLibrary::DPSEProfile"/>
            </data reader>
        </subscriber>
        <participant_qos base_name="QosLibrary::DPSEProfile"/>
    </domain participant>
</domain participant library>
```

Examining the XML, we see that:

- Each *DomainParticipant* is bound to the Domain, HelloWorldLibrary::HelloWorldDomain.
- The two *DomainParticipants* that use DPDE as their discovery mechanism inherit from the profile QosLibrary::DPDELibrary, while the other two that use DPSE as their discovery mechanism inherit from QosLibrary::DPSELibrary.
- Each *DomainParticipant* contains a single *Publisher* or *Subscriber*, which it turn contains a single *DataWriter* or *DataReader* that inherits from QosLibrary::DPDELibrary or QosLibrary::DPSELibrary, depending on the discovery mechanism used by its *DomainParticipant*.
- Each *DataWriter* writes the *Topic* HelloWorldTopic, which is defined in the domain HelloWorldLibrary::HelloWorldDomain. Each *DataReader* reads the same *Topic*.

Since both Dynamic *DomainParticipants* (those which are using DPDE as their discovery mechanism) are in the same the domain and the *DataWriter* writes the same *Topic* that the *DataReader* reads, the two *DomainParticipants* will communicate. This also apply to both static participants (those which are using DPSE as their discovery mechanism); the only difference is that *rtiddsmag* will generate extra code to configure the remote entities (for details, see 6.4.7 Static Discovery on page 82).

Let's look at the content of a DomainParticipant definition to explain the code generated by *rtiddsmag*.

rtiddsmag generates the code needed to register each component used by this *DomainParticipant* and unregister those components that are not being used. In our example, for each *DomainParticipant*, rtiddsmag registers the discovery transport, **dpde** or **dpse**; registers the UDP transport used by each *DomainParticipant* (since they use the same configuration, only one UDP transport configuration is generated); and unregisters the default UDP and INTRA transports, since they are not being used (these two are the only ones that can be unregistered by rtiddsmag).

It also creates the code for each entity. In this case, it generates the code needed to create:

- A Publisher named HelloWorldDPDEPub
- A DataWriter named HelloWorldDPDEDW
- A DomainParticipant named HelloWorldDPDEPubDP
- The QoS used by this *DomainParticipant* (see 6.4.4 QoS Definition on page 66)

HelloWorldAppgen.c

```
const struct ComponentFactoryUnregisterModel
HelloWorldAppLibrary_HelloWorldDPDEPubDP_unregister_components[2] =
{
        "_udp", /* NETIO_DEFAULT_UDP_NAME */
        NULL, /* udp struct RT_ComponentFactoryProperty** */
        NULL /* udp struct RT_ComponentFactoryListener** */
    },
        {
        "_intra", /* NETIO_DEFAULT_INTRA_NAME */
        NULL, /* _intra struct RT_ComponentFactoryProperty** */
        NULL /* _intra struct RT_ComponentFactoryListener** */
    }
};
```

```
struct DPDE DiscoveryPluginProperty
HelloWorldAppLibrary HelloWorldDPDEPubDP dpde[1] =
   RTI APP GEN dpde HelloWorldAppLibrary HelloWorldDPDEPubDP dpde1
};
struct UDP InterfaceFactoryProperty
HelloWorldAppLibrary HelloWorldDPDEPubDP udpv4[1] =
   RTI APP GEN udpv4 HelloWorldAppLibrary HelloWorldDPDEPubDP udp1
};
const struct ComponentFactoryRegisterModel
HelloWorldAppLibrary HelloWorldDPDEPubDP register components[2] =
       "dpde1", /* register name */
       DPDE_DiscoveryFactory_get_interface, /* register_intf */
       &HelloWorldAppLibrary HelloWorldDPDEPubDP dpde[0]. parent, /* register property */
       NULL /* register listener */
   },
       "udp1", /* register name */
       UDP_InterfaceFactory_get_interface, /* register_intf */
       &HelloWorldAppLibrary HelloWorldDPDEPubDP udpv4[0]. parent. parent, /* register
property */
       NULL /* register listener */
};
. . .
const struct APPGEN DataWriterModel
HelloWorldAppLibrary HelloWorldDPDEPubDP publisher HelloWorldDPDEPub data writers[1] =
       "HelloWorldDPDEDW", /* name */
       1UL, /* multiplicity */
       "HelloWorldTopic", /* topic name */
       RTI APP GEN DW QOS HelloWorldAppLibrary HelloWorldDPDEPubDP HelloWorldDPDEPub
HelloWorldDPDEDW /* writer qos */
const struct APPGEN PublisherModel
HelloWorldAppLibrary HelloWorldDPDEPubDP publishers[1] =
   {
       "HelloWorldDPDEPub", /* name */
       1UL, /* multiplicity */
       DDS_PublisherQos_INITIALIZER, /* publisher_qos */
       1UL, /* writer count */
       HelloWorldDPDEPubDP publisher HelloWorldDPDEPub data writers /*
data writers */
  }
};
```

HelloWorldAppgen.h

```
extern struct DPDE DiscoveryPluginProperty HelloWorldAppLibrary HelloWorldDPDEPubDP dpde[1];
extern struct UDP InterfaceFactoryProperty HelloWorldAppLibrary HelloWorldDPDEPubDP udpv4[1];
extern const struct ComponentFactoryUnregisterModel
 HelloWorldAppLibrary HelloWorldDPDEPubDP unregister components[2];
extern const struct ComponentFactoryRegisterModel
 HelloWorldAppLibrary HelloWorldDPDEPubDP register components[2];
#define RTI APP GEN DPF HelloWorldAppLibrary HelloWorldDPDEPubDP \
    2UL, /* unregister count */ \
    HelloWorldAppLibrary HelloWorldDPDEPubDP unregister components, /* unregister components */
    2UL, /* register count */ \
    HelloWorldAppLibrary HelloWorldDPDEPubDP register components, /* register components */ \
    RTI_APP_GEN___DPF_QOS_QosLibrary_DefaultProfile /* factory_qos */ \
extern const struct APPGEN TypeRegistrationModel
 HelloWorldAppLibrary HelloWorldDPDEPubDP type registrations[1];
extern const struct APPGEN_TopicModel HelloWorldAppLibrary_HelloWorldDPDEPubDP_topics[1];
extern const struct APPGEN PublisherModel
 HelloWorldAppLibrary HelloWorldDPDEPubDP publishers[1];
#define RTI APP GEN DP HelloWorldAppLibrary HelloWorldDPDEPubDP \
    "HelloWorldDPDEPubDP", /* name */ \
    RTI APP GEN DPF HelloWorldAppLibrary HelloWorldDPDEPubDP, /* domain participant factory */
   RTI APP GEN DP QOS HelloWorldAppLibrary HelloWorldDPDEPubDP, /* participant qos */ \
    OL, /* domain id */ \
    1UL, /* type registration count */ \
    HelloWorldAppLibrary_HelloWorldDPDEPubDP_type_registrations, /* type_registrations */ \
    1UL, /* topic count */ \
    HelloWorldAppLibrary HelloWorldDPDEPubDP topics, /* topics */ \
   1UL, /* publisher count */ \
    HelloWorldAppLibrary HelloWorldDPDEPubDP publishers, /* publishers */ \
    OUL, /* subscriber count */ \
   NULL, /* subscribers */ \
    OUL, /* remote_participant_count */ \
    NULL, /* remote participants */ \
    OUL, /* flow controller count */ \
    NULL, /* flow controllers */ \
```

6.4.4 QoS Definition

The defined DDS Entities have an associated QoS, which can be defined in a separate file such as **HelloWorldQos.xml** or within the System XML file.

See the entire file below. Then we will examine the file section by section, showing the code generated by *rtiddsmag*.

```
<?xml version="1.0"?>
<dds xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
 xsi:noNamespaceSchemaLocation="http://community.rti.com/schema/6.0.0/rti dds profiles.xsd">
    <qos_library name="QosLibrary">
        <qos profile name="DefaultProfile" is default participant factory profile="true">
            <!-- Participant Factory Qos -->
            <participant factory qos>
                <entity_factory>
                    <autoenable_created_entities>false</autoenable_created_entities>
                </entity factory>
            </participant factory qos>
            <!-- Participant Qos -->
            <participant_qos>
                <discovery>
                    <accept unknown peers>false</accept unknown peers>
                    <initial peers>
                        <element>127.0.0.1</element>
                        <element>239.255.0.1</element>
                    </initial_peers>
                    <enabled transports>
                        <element>udpv4</element>
                    </enabled transports>
                    <multicast receive addresses>
                        <element>udpv4://127.0.0.1</element>
                        <element>udpv4://239.255.0.1</element>
                    </multicast_receive_addresses>
                </discovery>
                <default unicast>
                    <value>
                        <element>
                            <transports>
                                <element>udpv4</element>
                            </transports>
                        </element>
                    </value>
                </default unicast>
                <transport builtin>
                    <mask>UDPv4</mask>
                </transport builtin>
                <resource limits>
                    <local_writer_allocation>
                        <max count>1</max count>
                    </local writer allocation>
                    <local_reader_allocation>
                         <max count>1</max count>
                    </local_reader_allocation>
```

```
<local_publisher_allocation>
            <max count>1</max count>
        </local publisher allocation>
        <local subscriber allocation>
            <max count>1</max count>
        </local_subscriber_allocation>
        <local topic allocation>
            <max count>1</max count>
        </local topic allocation>
        <local_type_allocation>
            <max count>1</max count>
        </local_type_allocation>
        <remote participant allocation>
            <max count>8</max count>
        </remote participant allocation>
        <remote writer allocation>
            <max count>8</max count>
        </remote writer allocation>
        <remote reader allocation>
            <max count>8</max count>
        </remote_reader_allocation>
        <max receive ports>32</max receive ports>
        <max_destination_ports>32</max_destination_ports>
    </resource limits>
</participant qos>
<!-- DataWriter Qos -->
<datawriter qos>
    <history>
        <depth>32</depth>
    </history>
    <resource limits>
        <max instances>2</max instances>
        <max samples>64</max samples>
        <max samples per instance>32</max samples per instance>
    </resource limits>
    <reliability>
        <kind>RELIABLE RELIABILITY QOS</kind>
    </reliability>
    col>
        <rtps reliable writer>
            <heartbeat period>
                <nanosec>250000000</nanosec>
                <sec>0</sec>
            </heartbeat period>
        </rtps_reliable_writer>
    </protocol>
    <!-- transports -->
    <unicast>
        <value>
            <element>
                <transports>
                    <element>udpv4</element>
                </transports>
```

```
</element>
            </value>
        </unicast>
    </datawriter qos>
    <!-- DataReader Qos -->
    <datareader qos>
        <history>
            <depth>32</depth>
        </history>
        <resource limits>
            <max instances>2</max instances>
            <max_samples>64</max_samples>
            <max samples per instance>32</max samples per instance>
        </resource limits>
        <reliability>
            <kind>RELIABLE_RELIABILITY_QOS</kind>
        </reliability>
        <reader resource limits>
            <max_remote_writers>10</max_remote_writers>
            <max remote writers per instance>10</max remote writers per instance>
        </reader_resource_limits>
        <!-- transports -->
        <unicast>
            <value>
                <element>
                    <transports>
                        <element>udpv4</element>
                    </transports>
                </element>
            </value>
        </unicast>
        <multicast>
            <value>
                <element>
                    <receive address>127.0.0.1</receive address>
                    <transports>
                        <element>udpv4</element>
                    </transports>
                </element>
            </value>
        </multicast>
    </datareader qos>
</qos_profile>
<qos_profile name="DPDEProfile" base_name="DefaultProfile">
    <participant qos>
        <discovery config>
            <builtin_discovery_plugins>SDP</builtin_discovery_plugins>
        </discovery_config>
    </participant_qos>
</qos profile>
```

Note: *rtiddsmag* only generates code for the QoSs used by at least one entity, unless the profile has either of the default flags is default participant factory profile or is default qos set to true.

6.4.4.1 DomainParticipant Factory QoS

rtiddsmag only generates code for the <participant_factory_qos> in the <qos_profile> that has the flag is_default participant factory profile set to true. For example:

rtiddsmag generates the following code:

HelloWorldAppgen.h

6.4.4.2 DomainParticipant QoS

The example defines a base profile named DefaultProfile, which contains the base QoSs used by each *DomainParticipant*. You can see the content of the *DomainParticipant* QoS below.

```
<multicast_receive_addresses>
            <element>udpv4://127.0.0.1</element>
            <element>udpv4://239.255.0.1</element>
        </multicast receive addresses>
    </discovery>
    <default_unicast>
        <value>
            <element>
                <transports>
                    <element>udpv4</element>
                </transports>
            </element>
        </value>
    </default unicast>
    <transport builtin>
        <mask>UDPv4</mask>
    </transport builtin>
    <resource limits>
        <local writer allocation>
            <max count>1</max count>
        </local_writer_allocation>
        <local reader allocation>
            <max_count>1</max_count>
        </local reader allocation>
        <local publisher allocation>
            <max count>1</max count>
        </local_publisher_allocation>
        <local_subscriber_allocation>
            <max count>1</max count>
        </local subscriber allocation>
        <local topic allocation>
            <max_count>1</max_count>
        </local topic allocation>
        <local_type_allocation>
            <max count>1</max count>
        </local_type_allocation>
        <remote participant allocation>
            <max_count>8</max_count>
        </remote_participant_allocation>
        <remote writer allocation>
            <max count>8</max count>
        </remote writer allocation>
        <remote_reader_allocation>
            <max count>8</max count>
        </remote_reader_allocation>
        <max receive ports>32</max receive ports>
        <max_destination_ports>32</max_destination_ports>
    </resource limits>
</participant_qos>
```

This *DomainParticipant* is then inherited by two different profiles, which set up the discovery mechanism:

rtiddsmag generates the following code for each *DomainParticipant* whose QoS inherits from any of the previous ones, adding those values that are specified in the XML configuration file (which is not the case in our example).

HelloWorldAppgen.c

```
const char *const HelloWorldAppLibrary_HelloWorldDPDEPubDP_initial_peers[2] =
{
    "127.0.0.1",
    "239.255.0.1"
};
const char *const HelloWorldAppLibrary_HelloWorldDPDEPubDP_discovery_enabled_transports[3] =
{
    "udp1://",
    "udp1://239.255.0.1"
};
const char *const HelloWorldAppLibrary_HelloWorldDPDEPubDP_transport_enabled_transports[1] =
{
    "udp1"
};
const char *const HelloWorldAppLibrary_HelloWorldDPDEPubDP_user_traffic_enabled_transports[1] =
{
    "udp1"
};
const char *const HelloWorldAppLibrary_HelloWorldDPDEPubDP_user_traffic_enabled_transports[1] =
{
    "udp1://"
};
```

```
}, \
       /* discovery */ \
       REDA StringSeq INITIALIZER W LOAN(HelloWorldAppLibrary HelloWorldDPDEPubDP initial
peers, 2, 2), /* initial peers */ \
       REDA StringSeq INITIALIZER W LOAN(HelloWorldAppLibrary HelloWorldDPDEPubDP discovery
enabled_transports, 3, 3), /* enabled_transports */ \
            { \{ "dpde1" \} }, /* RT ComponentFactoryId INITIALIZER */ \setminus
                NDDS Discovery Property INITIALIZER \
        }, /* discovery component */ \
       DDS BOOLEAN FALSE /* accept unknown peers */ \
       /* resource limits */ \
       1L, /* local writer allocation */ \
       1L, /* local reader allocation */ \
       1L, /* local publisher allocation */ \
       1L, /* local subscriber allocation */ \
       1L, /* local_topic_allocation */ \
       1L, /* local_type_allocation */ \
        8L, /* remote participant allocation */ \
        8L, /* remote writer allocation */ \
        8L, /* remote reader allocation */ \
        32L, /* matching writer reader pair allocation */ \
        32L, /* matching_reader_writer_pair_allocation */ \
        32L, /* max_receive_ports */ \
        32L, /* max destination ports */ \
        65536, /* unbound data buffer size */ \
       500UL /* shmem_ref_transfer_mode_max_segments */ \
    }, \
    DDS_ENTITY_NAME QOS POLICY DEFAULT, \
    DDS WIRE PROTOCOL QOS POLICY DEFAULT, \
       /* transports */ \
        REDA_StringSeq_INITIALIZER_W_LOAN(HelloWorldAppLibrary_HelloWorldDPDEPubDP_transport_
enabled transports, 1, 1) /* enabled transports */ \
    }, \
       /* user traffic */ \
       REDA StringSeq INITIALIZER W LOAN(HelloWorldAppLibrary HelloWorldDPDEPubDP user
traffic enabled transports, 1, 1) /* enabled transports */
    }, \
    DDS TRUST QOS POLICY DEFAULT, \
    DDS_PROPERTY_QOS_POLICY_DEFAULT \
```

6.4.4.3 Publisher QoS

Our example doesn't specify any value for *Publisher* QoS, however *rtiddsmag* would generate code if it was specified.

6.4.4.4 DataWriter QoS

The example defines a base profile named DefaultProfile, which contains the base QoSs used by each *DomainParticipant*. You can see the content of the *DataWriter* QoS below.

```
<!-- DataWriter Qos -->
<datawriter qos>
   <history>
      <depth>32</depth>
   </history>
   <resource limits>
      <max instances>2</max instances>
      <max samples>64</max samples>
      <max_samples_per_instance>32</max_samples_per_instance>
    </resource limits>
    <reliability>
       <kind>RELIABLE RELIABILITY QOS</kind>
    </reliability>
    otocol>
        <rtps reliable writer>
           <heartbeat period>
              <nanosec>250000000</nanosec>
              <sec>0</sec>
            </heartbeat period>
        </rtps_reliable_writer>
    </protocol>
    <!-- transports -->
    <unicast>
        <value>
            <element>
                <transports>
                    <element>udpv4</element>
                </transports>
            </element>
        </value>
    </unicast>
</datawriter qos>
```

rtiddsmag generates the following code:

HelloWorldAppgen.c

```
const char *const
HelloWorldAppLibrary_HelloWorldDPDEPubDP_HelloWorldDPDEPub_HelloWorldDPDEDW_transport_enabled_
transports[1] =
{
    "udp1://"
};
```

```
DDS_LIVELINESS_QOS_POLICY_DEFAULT, \
    {    /* history */ \
       DDS KEEP LAST HISTORY QOS, /* kind */ \
       32L /* depth */ \
    { /* resource limits */ \
       64L, /* max samples */ \setminus
       2L, /* max instances */ \
       32L /* max samples per instance */ \
    DDS OWNERSHIP QOS POLICY DEFAULT, \
    DDS_OWNERSHIP_STRENGTH_QOS_POLICY_DEFAULT, \
    DDS LATENCY BUDGET QOS POLICY DEFAULT, \
    { /* reliability */ \
        DDS RELIABLE RELIABILITY QOS, /* kind */ \
        { /* max_blocking_time */ \
           0L, /* sec */ \
           100000000L /* nanosec */ \
       } \
    }, \
    DDS DURABILITY QOS POLICY DEFAULT, \
    DDS DESTINATION ORDER QOS POLICY DEFAULT, \
    DDS_TRANSPORT_ENCAPSULATION_QOS_POLICY_DEFAULT, \
    DDS DATA REPRESENTATION QOS POLICY DEFAULT, \
    DDS RTPS AUTO ID, /* rtps object id */ \
        { /* rtps_reliable_writer */ \
        { /* heartbeat period */ \
           0L, /* sec */ \
           250000000L /* nanosec */ \
       1L, /* heartbeats_per_max_samples */ \
        DDS LENGTH UNLIMITED, /* max send window */ \
        DDS_LENGTH_UNLIMITED, /* max_heartbeat_retries */ \
        {    /* first write sequence number */ \
           0, /* high */ \
           1 /* low */ \
    }, \
    DDS BOOLEAN TRUE /* serialize on write */ \
    DDS TYPESUPPORT QOS POLICY DEFAULT, \
    { /* transports */ \
       REDA StringSeq INITIALIZER W LOAN(HelloWorldAppLibrary HelloWorldDPDEPubDP
HelloWorldDPDEPub_HelloWorldDPDEDW_transport_enabled_transports, 1, 1) /* enabled transports */
    RTI MANAGEMENT QOS POLICY DEFAULT, \
    DDS DATAWRITERRESOURCE LIMITS QOS POLICY DEFAULT, \
    DDS PUBLISH MODE QOS POLICY DEFAULT, \
    DDS_DATAWRITERQOS_TRUST_INITIALIZER \
    DDS_DATAWRITERQOS_APPGEN_INITIALIZER \
   NULL, \
    DDS DataWriterTransferModeQosPolicy INITIALIZER \
```

}

6.4.4.5 Subscriber QoS

Our example doesn't specify any value for Subscriber QoS, however *rtiddsmag* would generate code if it was specified.

6.4.4.6 DataReader QoS

The example defines a base profile named DefaultProfile, which contains the base QoSs used by each *DomainParticipant*. You can see the content of the *DataReader* QoS below.

```
<!-- DataReader QoS -->
<datareader_qos>
    <history>
        <depth>32</depth>
    </history>
    <resource limits>
        <max instances>2</max instances>
        <max samples>64</max samples>
        <max samples per instance>32</max samples per instance>
    </resource limits>
    <reliability>
        <kind>RELIABLE RELIABILITY QOS</kind>
    </reliability>
    <reader resource limits>
        <max remote writers>10</max remote writers>
        <max_remote_writers_per_instance>10</max_remote_writers_per_instance>
    </reader resource limits>
    <!-- transports -->
    <unicast>
        <value>
            <element>
                <transports>
                   <element>udpv4</element>
                </transports>
            </element>
        </value>
    </unicast>
    <multicast>
        <value>
                <receive address>127.0.0.1</receive address>
                <transports>
                    <element>udpv4</element>
                </transports>
            </element>
        </value>
    </multicast>
</datareader qos>
```

rtiddsmag generates the following code:

HelloWorldAppgen.c

```
const char *const
HelloWorldAppLibrary_HelloWorldDPDESubDP_HelloWorldDPDESub_HelloWorldDPDEDR_transport_enabled_
transports[2] =
{
    "udp1://",
    "udp1://127.0.0.1"
};
```

```
extern const char *const
HelloWorldAppLibrary HelloWorldDPDESubDP HelloWorldDPDESub HelloWorldDPDEDR transport enabled
transports[2];
#define RTI APP GEN DR QOS HelloWorldAppLibrary HelloWorldDPDESubDP HelloWorldDPDESub
HelloWorldDPDEDR \
{ \
    DDS DEADLINE QOS POLICY DEFAULT, \
    DDS LIVELINESS QOS POLICY DEFAULT, \
    {    /* history */ \
       DDS KEEP LAST HISTORY QOS, /* kind */ \
       32L /* depth */ \
    {    /* resource limits */ \
       64L, /* max samples */ \setminus
       2L, /* max instances */ \
       32L /* max samples per instance */ \
    DDS OWNERSHIP QOS POLICY DEFAULT, \
    DDS LATENCY BUDGET QOS POLICY DEFAULT, \
    { /* reliability */ \
        DDS RELIABLE RELIABILITY QOS, /* kind */ \
        { /* max blocking time */ \
           0L, /* sec */ \
            OL /* nanosec */ \
        } \
    DDS DURABILITY QOS POLICY DEFAULT, \
    DDS_DESTINATION_ORDER_QOS_POLICY_DEFAULT, \
    DDS TRANSPORT ENCAPSULATION QOS POLICY DEFAULT, \
    DDS DATA REPRESENTATION QOS POLICY DEFAULT, \
    DDS TYPESUPPORT QOS POLICY DEFAULT, \
    DDS DATA READER PROTOCOL QOS POLICY DEFAULT, \
    { /* transports */ \
        REDA StringSeq INITIALIZER W LOAN(HelloWorldAppLibrary HelloWorldDPDESubDP
HelloWorldDPDESub HelloWorldDPDEDR transport enabled transports, 2, 2) /* enabled transports */
    { /* reader resource limits */ \
       10L, /* max remote writers */ \
       10L, /* max_remote_writers_per_instance */ \
       1L, /* max samples per remote writer */ \
       1L, /* max outstanding reads */ \
```

```
DDS_NO_INSTANCE_REPLACEMENT_QOS, /* instance_replacement */ \
4L, /* max_routes_per_writer */ \
DDS_MAX_AUTO, /* max_fragmented_samples */ \
DDS_MAX_AUTO, /* max_fragmented_samples_per_remote_writer */ \
DDS_SIZE_AUTO /* shmem_ref_transfer_mode_attached_segment_allocation */ \
}, \
RTI_MANAGEMENT_QOS_POLICY_DEFAULT, \
DDS_DATAREADERQOS_TRUST_INITIALIZER \
DDS_DATAREADERQOS_APPGEN_INITIALIZER \
NULL \
}
```

6.4.5 Transport and Discovery Configuration

rtiddsmag creates the code necessary to configure each one of the available transports used by Connext DDS Micro (UDP and SHMEM) and the discovery mechanism (Dynamic and Static discovery). It also generates the name automatically for each component regardless of if it is a transport or discovery; for this rtiddsmag will add a DomainParticipant number at the end of its name, only if that configuration is not used by any other DomainParticipant:

- UDP Transport: **udp** + participant_number.
- SHMEM Transport: **shmem** + participant number.
- DPDE: **dpde** + participant_number.
- DPSE: **dpse** + participant number.

These names can be changed by using the ...Names options described in 6.2 Command-Line Options on page 54.

Notes:

- *rtiddsmag* will only create the transport configuration based on the strongly typed XML elements in the schema. *rtiddsmag* will **not** use the values in the property tag to configure the transport.
- If the length of one of these names exceeds the maximum length, *rtiddsmag* will throw an error.

The following configuration specifies dynamic discovery:

```
#define RTI_APP_GEN___dpde__HelloWorldAppLibrary_HelloWorldDPDEPubDP_dpde1 \
{ \
    RT_ComponentFactoryProperty_INITIALIZER, /* _parent */ \
```

```
/*participant_liveliness_assert_period */ \
        30L, /* sec */ \
        OL /* nanosec */ \setminus
       /*participant liveliness lease duration */ \
       100L, /* sec */ \
       OL /* nanosec */ \
    }, \
    5, /* initial participant announcements */ \
       /*initial participant announcement period */ \
       1L, /* sec */ \
       0L /* nanosec */ \
    }, \
    DDS BOOLEAN FALSE, /* cache serialized samples */ \
    DDS LENGTH AUTO, /* max participant locators */ \
    4, /* max locators per discovered participant */ \
    8, /* max_samples_per_builtin_endpoint_reader */ \
    DDS LENGTH UNLIMITED, /* builtin writer max heartbeat retries */ \
      /*builtin writer heartbeat period */ \
       0L, /* sec */ \
       100000000L /* nanosec */ \
    1L /* builtin_writer_heartbeats_per_max_samples */ \
    DDS PARTICIPANT MESSAGE READER RELIABILITY KIND INITIALIZER \
#define RTI APP GEN __DP_QOS_HelloWorldAppLibrary_HelloWorldDPDEPubDP \
{ \
    REDA StringSeq INITIALIZER W LOAN(HelloWorldAppLibrary HelloWorldDPDEPubDP initial
peers, 2, 2), /* initial peers */ \
       REDA_StringSeq_INITIALIZER_W_LOAN(HelloWorldAppLibrary_HelloWorldDPDEPubDP_discovery_
enabled_transports, 3, 3), /* enabled_transports */ \
        { \
            { "dpde1" } }, /* RT ComponentFactoryId INITIALIZER */ \
               NDDS Discovery Property INITIALIZER \
        }, /* discovery component */ \
        DDS_BOOLEAN_FALSE /* accept_unknown_peers */ \
    }, \
    . . .
```

Notes:

- rtiddsmag will throw an error if the list of available transports for the *DomainParticipant*, DataWriter, and DataReader contains a transport alias that is not part of the **transport_builtin** mask.
- rtiddsmag will not generate code for the SHMEM or UDPv4 transport if it is not specified in the

transport builtin mask.

• UDP transformation is not supported in XML.

When using the transport alias to specify the **enabled_transports** for the discovery *DomainParticipant*, *DataWriter* or *DataReader*, you could use the transport names for the built-in transport plugins: **shmem** and **udpv4**. *rtiddsmag* will automatically modify this alias to match the new one with the *DomainParticipant* number at the end of the name.

6.4.6 Flow Controllers

rtiddsmag creates code which it will be used by *Connext DDS Micro* to create a flow controller. The flow controller is configured through properties in the XML file. Let's see an example of how to configure a flow controller named **custom_flowcontroller** and the code that *rtiddsmag* generates:

```
<participant qos>
    property>
        <value>
            <element>
                    dds.flow controller.token bucket.custom flowcontroller.token bucket.max
tokens
                </name>
                <value>2</value>
            </element>
            <element>
                    dds.flow controller.token bucket.custom flowcontroller.token bucket.tokens
added_per_period
                </name>
                <value>2</value>
            </element>
            <element>
                    dds.flow controller.token bucket.custom flowcontroller.token bucket.tokens
leaked_per_period
                <!-- The value -1 means LENGTH UNLIMITED -->
                <value>-1</value>
            </element>
            <element>
                <name>
                    dds.flow_controller.token_bucket.custom_flowcontroller.token_
bucket.period.sec
                </name>
                <value>0</value>
            </element>
```

```
<element>
                    dds.flow controller.token bucket.custom flowcontroller.token
bucket.period.nanosec
                </name>
                <value>100000000
            </element>
            <element>
                <name>
                    dds.flow controller.token bucket.custom flowcontroller.token bucket.bytes
per_token
                </name>
                <value>1024</value>
            </element>
        </value>
    </property>
</participant_qos>
<datawriter qos>
    <publish mode>
        <flow controller name>
            dds.flow_controller.token_bucket.custom_flowcontroller
        </flow controller name>
        <kind>ASYNCHRONOUS_PUBLISH_MODE_QOS</kind>
        <priority>12</priority>
    </publish mode>
</datawriter qos>
```

HelloWorldAppgen.c

```
1024L /* bytes_per_token */ \
    }, \
    DDS BOOLEAN FALSE /* is vendor specific */ \
#define
RTI APP GEN DW QOS HelloWorldAppLibrary HelloWorldDPDEPubDP HelloWorldDPDEPub
HelloWorldDPDEDW \
{ \
    { /* publish mode */ \
        DDS ASYNCHRONOUS PUBLISH MODE QOS, /* max_remote_readers */ \
        "custom flowcontroller", /* flow controller name */ \
        12L /* priority */ \
    }, \
    . . .
extern const struct APPGEN FlowControllerModel
HelloWorldAppLibrary HelloWorldDPDEPubDP flow controllers[1];
#define RTI APP GEN DP HelloWorldAppLibrary HelloWorldDPDEPubDP \
{ \
    1UL, /* flow_controller count */ \
    HelloWorldAppLibrary HelloWorldDPDEPubDP flow controllers /* flow controllers */ \
```

6.4.7 Static Discovery

rtiddsmag iterates through each *DomainParticipant* definition in the XML configuration file, creating the remote entities that are needed to communicate with applications that use static discovery, and updating the **object_id** of each *DataWriter* or *DataReader* involved if they don't have a valid value or they are using the default value.

Let's see an example of two applications that use static discovery and how *rtiddsmag* generates the necessary code that will be asserted by *Connext DDS Micro* to communicate with both applications:

For these two *DomainParticipants*, *rtiddsmag* will update the **rtps_object_id** for the *DataWriter* and *DataReader*, since they didn't have any values set in the XML file. You can see this in the following snippet from **HelloWorldAppgen.h**:

```
#define
RTI APP GEN DW QOS HelloWorldAppLibrary HelloWorldDPSEPubDP HelloWorldDPSEPub
HelloWorldDPSEDW \
{ \
    1UL, /* rtps_object_id */ \
       { /* rtps reliable writer */ \
           { /* heartbeat period */ \
              0L, /* sec */ \
               250000000UL /* nanosec */ \
           1L, /* heartbeats_per_max_samples */ \
           DDS LENGTH UNLIMITED, /* max send window */ \
           DDS LENGTH UNLIMITED, /* max heartbeat retries */ \
           { /* first write sequence number */ \
               0, /* high */ \
               1 /* low */ \
           } \
       }, \
       DDS BOOLEAN TRUE /* serialize on write */ \
   }, \
    . . .
#define
RTI APP GEN DR QOS HelloWorldAppLibrary HelloWorldDPSESubDP HelloWorldDPSESub
HelloWorldDPSEDR \
{ \
    2UL /* rtps object id */ \
   }, \
    . . .
```

rtiddsmag will also generate the remote *DomainParticipants*, *DataWriters*, and *DataReaders* that need to be asserted in order for endpoints to match:

```
const struct APPGEN_RemoteSubscriptionModel
HelloWorldAppLibrary_HelloWorldDPSEPubDP_remote_subscribers[1] =
{
```

```
RTI_APP_GEN_ RSD_HelloWorldAppLibrary_HelloWorldDPSEPubDP_HelloWorldAppLibrary
HelloWorldDPSESubDP HelloWorldDPSESub HelloWorldDPSEDR
};
const struct APPGEN RemoteParticipantModel
HelloWorldAppLibrary HelloWorldDPSEPubDP remote participants[1] =
        "HelloWorldDPSESubDP", /* name */
        OUL, /* remote publisher count */
       NULL, /* remote publishers */
       1UL, /* remote subscriber count */
        HelloWorldAppLibrary HelloWorldDPSEPubDP remote subscribers /* remote subscribers */
};
const struct APPGEN RemotePublicationModel
HelloWorldAppLibrary HelloWorldDPSESubDP remote publishers[1] =
    RTI APP GEN RPD HelloWorldAppLibrary HelloWorldDPSESubDP HelloWorldAppLibrary
HelloWorldDPSEPubDP HelloWorldDPSEPub HelloWorldDPSEDW
const struct APPGEN RemoteParticipantModel
HelloWorldAppLibrary HelloWorldDPSESubDP remote participants[1] =
        "HelloWorldDPSEPubDP", /* name */
       1UL, /* remote publisher count */
        HelloWorldAppLibrary HelloWorldDPSESubDP remote publishers, /* remote publishers */
        OUL, /* remote subscriber count */
       NULL /* remote subscribers */
```

```
{ /* max blocking_time */ \
                OL, /* sec */ \
                0L /* nanosec */ \
            } \
        DDS_LIVELINESS_QOS_POLICY_DEFAULT, \
        DDS DURABILITY QOS POLICY DEFAULT, \
        DDS DESTINATION ORDER QOS POLICY_DEFAULT, \
        DDS SEQUENCE INITIALIZER, \
        DDS SEQUENCE INITIALIZER, \
        DDS DATA REPRESENTATION QOS POLICY DEFAULT \
        DDS TRUST SUBSCRIPTION DATA INITIALIZER \
    HelloWorldTypePlugin get /* get type plugin */ \
extern const struct APPGEN RemoteSubscriptionModel HelloWorldAppLibrary HelloWorldDPSEPubDP
remote subscribers[1];
extern const struct APPGEN RemoteParticipantModel HelloWorldAppLibrary HelloWorldDPSEPubDP
remote_participants[1];
#define RTI APP GEN DP HelloWorldAppLibrary HelloWorldDPSEPubDP \
    "HelloWorldDPSEPubDP", /* name */ \
    RTI_APP_GEN__DPF_HelloWorldAppLibrary_HelloWorldDPSEPubDP, /* domain_participant_factory */
   RTI APP GEN DP QOS HelloWorldAppLibrary HelloWorldDPSEPubDP, /* participant gos */ \
    OL, /* domain id */ \
   1UL, /* type registration count */ \
    HelloWorldAppLibrary HelloWorldDPSEPubDP type registrations, /* type registrations */ \
   1UL, /* topic count */ \
    HelloWorldAppLibrary HelloWorldDPSEPubDP topics, /* topics */ \
   1UL, /* publisher count */ \
    HelloWorldAppLibrary HelloWorldDPSEPubDP publishers, /* publishers */ \
    OUL, /* subscriber count */ \
   NULL, /* subscribers */ \
    1UL, /* remote_participant_count */ \
    HelloWorldAppLibrary HelloWorldDPSEPubDP remote participants /* remote_participants */ \
    OUL, /* flow controller count */ \
    NULL, /* flow controllers */ \
#define RTI APP GEN RPD HelloWorldAppLibrary HelloWorldDPSESubDP HelloWorldAppLibrary
HelloWorldDPSEPubDP HelloWorldDPSEPub HelloWorldDPSEDW \
{ \
    { /* publication data */ \
           { 0, 0, 0, 1 } /* key */ \
        }, \
            { 0, 0, 0, 0 } /* participant key */ \
        "HelloWorldTopic", /* topic name */ \
       "HelloWorldType", /* type name */ \
        DDS DEADLINE QOS POLICY DEFAULT, \
```

```
DDS OWNERSHIP QOS POLICY DEFAULT, \
        DDS OWNERSHIP_STRENGTH_QOS_POLICY_DEFAULT, \
        DDS LATENCY BUDGET QOS POLICY DEFAULT, \
          /* reliability */ \
           DDS RELIABLE RELIABILITY QOS, /* kind */ \
            { /* max_blocking_time */ \
               0L, /* sec */ \
                100000000L /* nanosec */ \
            } \
        }, \
        DDS LIVELINESS QOS POLICY DEFAULT, \
        DDS_DURABILITY_QOS_POLICY_DEFAULT, \
        DDS DESTINATION ORDER QOS POLICY DEFAULT, \
        DDS SEQUENCE INITIALIZER, \
        DDS DATA REPRESENTATION QOS POLICY DEFAULT \
        DDS TRUST PUBLICATION DATA INITIALIZER \
    HelloWorldTypePlugin get /* get type plugin */ \
extern const struct APPGEN RemotePublicationModel HelloWorldAppLibrary HelloWorldDPSESubDP
remote publishers[1];
extern const struct APPGEN RemoteParticipantModel HelloWorldAppLibrary HelloWorldDPSESubDP
remote participants[1];
#define RTI APP GEN DP HelloWorldAppLibrary HelloWorldDPSESubDP \
    "HelloWorldDPSESubDP", /* name */ \
    RTI APP GEN DPF HelloWorldAppLibrary HelloWorldDPSESubDP, /* domain participant factory */
   RTI APP GEN DP QOS HelloWorldAppLibrary HelloWorldDPSESubDP, /* participant qos */ \
    OL, /* domain id */ \
    1UL, /* type registration count */ \
    HelloWorldAppLibrary HelloWorldDPSESubDP type registrations, /* type registrations */ \
    1UL, /* topic count */ \
    HelloWorldAppLibrary HelloWorldDPSESubDP topics, /* topics */ \
    OUL, /* publisher count */ \
    NULL, /* publishers */ \
    1UL, /* subscriber_count */ \
    HelloWorldAppLibrary HelloWorldDPSESubDP subscribers, /* subscribers */ \
    1UL, /* remote_participant_count */ \
    HelloWorldAppLibrary HelloWorldDPSESubDP remote participants /* remote participants */ \
    OUL, /* flow controller count */ \
    NULL /* flow controllers */ \
```

6.5 Errors Caused by Invalid Configurations

This section explains the different results thrown by MAG if it receives invalid configuration files.

• Invalid XML content

MAG will fail to validate the configuration file if it contains invalid content, such as elements/attributes that don't exist in the schema or values that aren't supported by any of the existing types. For example:

```
07:41:48.334 [main] INFO com.rti.micro.appgen.MicroAppGen - Processing file : /home/test/Error.xml
07:41:49.827 [main] ERROR com.rti.micro.appgen.MicroAppGen - Failed to parse inp ut file : /home/test/Error.xml
07:41:49.837 [main] ERROR com.rti.micro.appgen.MicroAppGen - cvc-complex-type.2.
4.a: Invalid content was found starting with element 'invalid_tag'. One of '{dat a_writer, publisher_qos}' is expected.
07:41:49.837 [main] INFO com.rti.micro.appgen.MicroAppGen - Exiting.
```

• Unsupported elements

MAG will throw a warning for any elements that are not supported by *Connext DDS Micro*. Unsupported elements will be ignored, such as the user_data in the following:

```
07:39:52.643 [main] INFO com.rti.micro.appgen.MicroAppGen - Processing file : /
home/test/Warning.xml
07:39:53.439 [main] WARN com.rti.micro.appgen.utils.ConverterUtils - userData i
s not supported by Micro, the tool will ignore its value.
file=/home/test/Warning.xml, lineNumber=90, columnNumber=38
```

• Unsupported values

MAG will throw an error if it finds a value that is not supported by Connext DDS Micro.

```
<dds>
    <!-- Participant Library -->
    <domain participant library name="FeatureTestLibrary">
        <domain participant name="01 EmptyDomainParticipant"</pre>
         domain ref="HelloWorldLibrary::HelloWorldDomain">
            <publisher name ="test">
                <data writer topic ref="HelloWorldTopic1" name="testW">
                    <datawriter gos>
                        <durability>
                             <!-- transient is not supported by Micro -->
                             <kind>TRANSIENT DURABILITY QOS</kind>
                        </durability>
                    </datawriter qos>
                </data writer>
            </publisher>
        </domain participant>
    </domain participant library>
</dds>
```

```
07:39:01.248 [main] INFO com.rti.micro.appgen.MicroAppGen - Processing file : /home/test/Error.xml
07:39:02.069 [main] ERROR com.rti.micro.appgen.utils.ConverterUtils - TRANSIENT_
DURABILITY_QOS is not supported by Micro, only VOLATILE and TRANSIENT_LOCAL are valid values for the durability kind field.
file=/home/test/Error.xml, lineNumber=35, columnNumber=37
07:39:02.072 [main] ERROR com.rti.micro.appgen.MicroAppGen - Failed to add input file information into the model.
07:39:02.074 [main] INFO com.rti_micro.appgen.MicroAppGen - Exiting.
```

MAG will also throw an error if the QoS values are not consistent with values supported in *Connext DDS Micro*. For example, the following XML contains a deadline period that is too large.

```
domain ref="HelloWorldLibrary::HelloWorldDomain">
            <publisher name ="test">
                <data writer topic ref="HelloWorldTopic1" name="testW">
                    <datawriter qos>
                        <deadline>
                            <!-- this deadline exceeds the maximum -->
                            <period>
                                 <sec>123213123</sec>
                                <nanosec>12</nanosec>
                            </period>
                        </deadline>
                    </datawriter qos>
                </data writer>
            </publisher>
        </domain_participant>
    </domain_participant_library>
</dds>
```

```
07:43:26.805 [main] INFO com.rti.micro.appgen.MicroAppGen - Processing file : / home/test/Error.xml
07:43:27.619 [main] ERROR com.rti.micro.appgen.utils.ConverterUtils - The durati on of deadline.period=3.90706250000000038052 y exceeded the maximum range [1 ns, 1 year]
file=/home/test/Error.xml, lineNumber=35, columnNumber=11
07:43:27.620 [main] ERROR com.rti.micro.appgen.MicroAppGen - Failed to add input file information into the model.
07:43:27.620 [main] INFO com.rti.micro.appgen.MicroAppGen - Exiting.
```