# Chapter 3 Transport Layer


#### A note on the use of these ppt slides:

We're making these slides freely available to all (faculty, students, readers). They're in PowerPoint form so you see the animations; and can add, modify, and delete slides (including this one) and slide content to suit your needs. They obviously represent a *lot* of work on our part. In return for use, we only ask the following:

- If you use these slides (e.g., in a class) that you mention their source (after all, we'd like people to use our book!)
- \* If you post any slides on a www site, that you note that they are adapted from (or perhaps identical to) our slides, and note our copyright of this material.

Thanks and enjoy! JFK/KWR

© All material copyright 1996-2013 J.F Kurose and K.W. Ross, All Rights Reserved



KUROSE ROSS

Networking: A
Top Down
Approach
6<sup>th</sup> edition
Jim Kurose, Keith
Ross
Addison-Wesley
March 2012

### Chapter 3: Transport Layer

#### our goals:

- understand principles behind transport layer services:
  - multiplexing, demultiplexing
  - reliable data transfer
  - flow control
  - congestion control

- learn about Internet transport layer protocols:
  - UDP: connectionless transport
  - TCP: connectionoriented reliable transport
  - TCP congestion control


### Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

## Transport services and protocols

- provide logical communication between app processes running on different hosts
- transport protocols run in end systems
  - send side: breaks app messages into segments, passes to network layer
  - rcv side: reassembles segments into messages, passes to app layer
- more than one transport protocol available to apps
  - Internet: TCP and UDP



#### Transport vs. network

### layer

- \* network layer: logical communication between hosts
- \* transport layer: logical communication between processes
  - relies on, enhances, network layer services


#### household analogy:

- 12 kids in Ann's house sending letters to 12 kids in Bill's house:
- hosts = houses
- processes = kids
- app messages = letters in envelopes
- transport protocol = Ann and Bill who demux to in-house siblings
- network-layer protocol = postal service

## Internet transport-layer

### protocols

- reliable, in-order delivery (TCP)
  - congestion control
  - flow control
  - connection setup
- unreliable, unordered delivery: UDP
  - no-frills extension of "best-effort" IP
- services not available:
  - delay guarantees
  - bandwidth guarantees




### Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer


- 3.5 connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

### Multiplexing/ demultiplexing



#### How demultiplexing works

- host receives IP datagrams
  - each datagram has source IP address, destination IP address
  - each datagram carries one transport-layer segment
  - each segment has source, destination port number
- host uses IP addresses & port numbers to direct segment to appropriate socket



TCP/UDP segment format

## Connectionless demultiplexing


- \* recall: when creating datagram to send into UDP socket, must specify
  - destination IP address
  - destination port #

IP datagrams with same dest. port #, but different source IP addresses and/or source port numbers will be directed to same socket at dest

- when host receives UDP segment:
  - checks destination port # in segment
  - directs UDP segment to socket with that port #



## Connectionless demux: example




## Connection-oriented demux

- \* TCP socket identified by 4tuple:
  - source IP address
  - source port number
  - dest IP address
  - dest port number
- demux: receiver uses all four values to direct segment to appropriate socket

- server host may support many simultaneous TCP sockets:
  - each socket identified by its own 4-tuple
- web servers have different sockets for each connecting client
  - non-persistent HTTP will have different socket for each request


## Connection-oriented demux: example



three segments, all destined to IP address: B, dest port: 80 are demultiplexed to *different* sockets

### Connection-oriented demux:

example



### Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

## UDP: User Datagram Protocol [RFC 768]

- "no frills," "bare bones" Internet transport protocol
- \* "best effort" service, UDP segments may be:
  - lost
  - delivered out-of-order to app
- \* connectionless:
  - no handshaking between UDP sender, receiver
  - each UDP segment handled independently of others

- UDP use:
  - streaming multimedia apps (loss tolerant, rate sensitive)
  - DNS
  - SNMP
- reliable transfer over UDP:
  - add reliability at application layer
  - application-specific error recovery!

#### **UDP:** segment header

32 bits dest port # source port # checksum length application data (payload)

**UDP** segment format

length, in bytes of UDP segment, including header

#### why is there a UDP?

- no connection establishment (which can add delay)
- \* simple: no connection state at sender, receiver
- small header size
- no congestion control: UDP can blast away as fast as desired

#### **UDP** checksum

### Goal: detect "errors" (e.g., flipped bits) in transmitted segment

#### sender:

- treat segment contents, including header fields, as sequence of 16-bit integers
- checksum: addition (one's complement sum) of segment contents
- sender puts checksum value into UDP checksum field


#### receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
  - NO error detected
  - YES no error detected. But maybe errors nonetheless? More later

. . . .

## Internet checksum: example

example: add two 16-bit integers



Note: when adding numbers, a carryout from the most significant bit needs to be added to the result

### Chapter 3 outline


- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

### Principles of reliable data

transfer

- important in application, transport, link layers
  - top-10 list of important networking topics!




- (a) provided service
- characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

### Principles of reliable data

transfer

- \* important in application, transport, link layers
  - top-10 list of important networking topics!




 characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

### Principles of reliable data


transfer

- \* important in application, transport, link layers
  - top-10 list of important networking topics!



 characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

## Reliable data transfer: getting started



## Reliable data transfer: getting started

#### we'll:

- incrementally develop sender, receiver sides of reliable data transfer protocol (rdt)
- consider only unidirectional data transfer
  - but control info will flow on both directions!
- \* use finite state machines (FSM) to specify sender, receiversing state transition actions taken on state transition

state: when in this "state" next state uniquely determined by next event




## rdt1.0: reliable transfer over a reliable channel

- underlying channel perfectly reliable
  - no bit errors
  - no loss of packets

sender

- separate FSMs for sender, receiver:
  - sender sends data into underlying channel
  - receiver reads data from underlying channel



receiver

#### rdt2.0: channel with bit

#### errors

- underlying channel may flip bits in packet
  - checksum to detect bit errors
- \* the question: how to recover from errors:


How do humans recover from "errors" during conversation?

#### rdt2.0: channel with bit


#### errors

- underlying channel may flip bits in packet
  - checksum to detect bit errors
- \* the question: how to recover from errors:
  - acknowledgements (ACKs): receiver explicitly tells sender that pkt received OK
  - negative acknowledgements (NAKs): receiver explicitly tells sender that pkt had errors
  - sender retransmits pkt on receipt of NAK
- \* new mechanisms in rat2.0 (beyond rat1.0):
  - error detection
  - feedback: control msgs (ACK,NAK) from receiver to sender

#### rdt2.0: FSM specification



#### receiver




#### rdt2.0: operation with no

#### errors

```
rdt send(data)
  snkpkt = make_pkt(data, checksum)
  udt send(sndpkt)
                              rdt rcv(rcvpkt) &&
                                isNAK(rcvpkt)
Wait for
                  Wait for
                                                                rdt_rcv(rcvpkt) &&
                  ACK or
call from
                               udt_send(sndpkt)
                                                                 corrupt(rcvpkt)
above
                   NAK
                                                                udt send(NAK)
   rdt rcv(rcvpkt) && isACK(rcvpkt)
                                                                   Wait for
       Λ
                                                                  call from
                                                                    below
                                                            rdt rcv(rcvpkt) &&
                                                               notcorrupt(rcvpkt)
                                                             extract(rcvpkt,data)
                                                             deliver_data(data)
                                                             udt_send(ACK)
```

#### rdt2.0: error scenario



### rdt2.0 has a fatal flaw!

## what happens if ACK/NAK corrupted?


- sender doesn't know what happened at receiver!
- can't just retransmit: possible duplicate

#### handling duplicates:

- sender retransmits current pkt if ACK/NAK corrupted
- \* sender adds sequence number to each pkt
- receiver discards (doesn't deliver up) duplicate pkt

stop and wait
sender sends one
packet,
then waits for
receiver
response

## rdt2.1: sender, handles garbled ACK/NAKs



## rdt2.1: receiver, handles garbled ACK/NAKs

rdt rcv(rcvpkt) && notcorrupt(rcvpkt) && has seq0(rcvpkt) extract(rcvpkt,data) deliver data(data) sndpkt = make pkt(ACK, chksum) udt send(sndpkt) rdt rcv(rcvpkt) && (<del>corrupt(rcvpkt)</del> sndpkt = make\_pkt(NAK, chksum) udt send(sndpkt) Wait for Wait for 0 from 1 from rdt rcv(rcvpkt) && below, not corrupt(rcvpkt) && below has seq1(rcvpkt) sndpkt = make pkt(ACK, chksum) udt send(sndpkt) rdt rcv(rcvpkt) && notcorrupt(rcvpkt) && has seq1(rcvpkt) extract(rcvpkt,data)

deliver data(data)

udt send(sndpkt)

sndpkt = make pkt(ACK, chksum)

rdt\_rcv(rcvpkt) &&

(corrupt(rcvpkt)
sndpkt = make\_pkt(NAK, chksum)
udt send(sndpkt)

rdt\_rcv(rcvpkt) && not corrupt(rcvpkt) && has seq0(rcvpkt)

sndpkt = make\_pkt(ACK, chksum)
udt\_send(sndpkt)

#### rdt2.1: discussion

#### sender:

- seq # added to pkt
- two seq. #'s (0,1) will suffice. Why?
- must check if received ACK/NAK corrupted
- twice as many states
  - state must "remember" whether "expected" pkt should have seq # of 0 or 1


#### receiver:

- must check if received packet is duplicate
  - state indicates whether 0 or 1 is expected pkt seq #
- note: receiver can not know if its last ACK/NAK received OK at sender

#### rdt2.2: a NAK-free protocol

- same functionality as rdt2.1, using ACKs only
- instead of NAK, receiver sends ACK for last pkt received OK
  - receiver must explicitly include seq # of pkt being ACKed
- duplicate ACK at sender results in same action as NAK: retransmit current pkt

# rdt2.2: sender, receiver fragments




# rdt3.0: channels with errors and

### new assumption: underlying channel can also lose packets (data, ACKs)


 checksum, seq. #, ACKs, retransmissions will be of help ... but not enough

- approach: sender waits
   "reasonable" amount
   of time for ACK
- retransmits if no ACK received in this time
- if pkt (or ACK) just delayed (not lost):
  - retransmission will be duplicate, but seq. #'s already handles this
  - receiver must specify seq # of pkt being ACKed
- requires countdown timer


## rdt3.0 sender



# rdt3.0 in action



### rdt3.0 in



## Performance of rdt3.0

- rdt3.0 is correct, but performance stinks
- \* e.g.: 1 Gbps link, 15 ms prop. delay, 8000 bit packet:


$$D_{trans} = \frac{L}{R} = \frac{8000 \text{ bits}}{10^9 \text{ bits/sec}} = 8 \text{ microsecs}$$

U sender: utilization – fraction of time sender busy

sending 
$$U_{sender} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$


- if RTT=30 msec, 1KB pkt every 30 msec: 33kB/sec thruput over 1 Gbps link
- network protocol limits use of physical resources!

# rdt3.0: stop-and-wait operation



## Pipelined protocols

- pipelining: sender allows multiple, "inflight", yet-to-be-acknowledged pkts
  - range of sequence numbers must be increased




(a) a stop-and-wait protocol in operation

(b) a pipelined protocol in operation

two generic forms of pipelined protocols: go-Back-N, selective repeat

# Pipelining: increased utilization



# Pipelined protocols:

### overview

### Go-back-N:

- sender can have up to N unacked packets in pipeline
- \* receiver only sends cumulative ack
  - doesn't ack packet if there's a gap
- sender has timer for oldest unacked packet
  - when timer expires, retransmit all unacked packets


### Selective Repeat:

- \* sender can have up to N unack'ed packets in pipeline
- rcvr sends individual ack for each packet

- sender maintains timer for each unacked packet
  - when timer expires, retransmit only that unacked packet

## Go-Back-N: sender

- k-bit seq # in pkt header
- "window" of up to N, consecutive unack'ed pkts




- ACK(n): ACKs all pkts up to, including seq # n -"cumulative ACK"
  - may receive duplicate ACKs (see receiver)
- timer for oldest in-flight pkt
- timeout(n): retransmit packet n and all higher seq # pkts in window

### GBN: sender extended FSM

```
rdt send(data)
                        if (nextseqnum < base+N) {
                          sndpkt[nextseqnum] = make_pkt(nextseqnum,data,chksum)
                          udt send(sndpkt[nextseqnum])
                          if (base == nextsegnum)
                            start timer
                          nextseqnum++
                        else
   Λ
                         refuse data(data)
  base=1
  nextseqnum=1
                                           timeout
                                           start timer
                             Wait
                                           udt send(sndpkt[base])
                                           udt send(sndpkt[base+1])
rdt rcv(rcvpkt)
 && corrupt(rcvpkt)
                                           udt send(sndpkt[nextsegnum-
                         rdt_rcv(rcvpkt) &&<sup>1])</sup>
                            notcorrupt(rcvpkt)
                          base = getacknum(rcvpkt)+1
                          If (base == nextseqnum)
                            stop timer
                           else
                            start timer
```


# GBN: receiver extended



### ACK-only: always send ACK for correctlyreceived pkt with highest *in-order* seq #

- may generate duplicate ACKs
- need only remember expectedseqnum
- out-of-order pkt:
  - discard (don't buffer): no receiver buffering!
  - re-ACK pkt with highest in-order seq #


## **GBN** in action



## Selective repeat

- receiver individually acknowledges all correctly received pkts
  - buffers pkts, as needed, for eventual inorder delivery to upper layer
- sender only resends pkts for which ACK not received
  - sender timer for each unACKed pkt
- sender window
  - N consecutive seq #'s
  - limits seq #s of sent, unACKed pkts

# Selective repeat: sender, receiver windows



(b) receiver view of sequence numbers

# Selective repeat

#### sender

### data from above:

if next available seq # in window, send pkt

### timeout(n):

resend pkt n, restart timer

## ACK(n) in [sendbase,sendbase+N]:

- mark pkt n as received
- if n smallest unACKed pkt, advance window base to next unACKed seq #

#### receiver

- pkt n in [rcvbase, rcvbase+N-1]
- send ACK(n)
- out-of-order: buffer
- in-order: deliver (also deliver buffered, in-order pkts), advance window to next notyet-received pkt


#### pkt n in [rcvbase-N,rcvbase-1]

ACK(n)

#### otherwise:

ignore

## Selective repeat in action



Selective repeat (after receipt)


dilemma

example:


- \* seq #'s: 0, 1, 2, 3
- window size=3
- receiver sees no difference in two scenarios!
- duplicate data accepted as new in (b)

Q: what relationship between seq # size and window size to avoid problem in (b)?

receiver window (after receipt)



receiver can't see sender side. receiver behavior identical in both cases! something's (very) wrong!



## Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

## TCP: Overview RFCs: 793,1122,1323,

<del>2018, 2581</del>

- point-to-point:
  - one sender, one receiver
- reliable, in-order byte steam:
  - no "message boundaries"
- \* pipelined:
  - TCP congestion and flow control set window size

- full duplex data:
  - bi-directional data flow in same connection
  - MSS: maximum segment size
- connection-oriented:
  - handshaking (exchange of control msgs) inits sender, receiver state before data exchange
- flow controlled:
  - sender will not overwhelm receiver

## TCP segment structure


URG: urgent data (generally not used)

ACK: ACK # valid

PSH: push data now (generally not used)

RST, SYN, FIN: connection estab (setup, teardown commands)

> Internet checksum' (as in UDP)



counting by bytes of data (not segments!)

> # bytes rcvr willing to accept


## TCP seq. numbers, ACKs

#### <u>sequence numbers:</u>


byte stream "number" of first byte in segment's data

#### acknowledgements:

- seq # of next byte expected from other side
- cumulative ACK
- Q: how receiver handles out-of-order segments
  - A: TCP spec doesn't say, - up to implementor



# TCP seq. numbers, ACKs



simple telnet scenario

# TCP round trip time, timeout

- Q: how to set TCP timeout value?
- longer than RTTbut RTT varies
- too short:
   premature timeout,
   unnecessary
   retransmissions
- \* too long: slow reaction to segment loss


- Q: how to estimate RTT?
- \* SampleRTT: measured time from segment transmission until ACK receipt
  - ignore retransmissions
- \* SampleRTT will vary, want estimated RTT "smoother"
  - average several recent measurements, not just current SampleRTT

# TCP round trip time, timeout

EstimatedRTT =  $(1-\alpha)$ \*EstimatedRTT +  $\alpha$ \*SampleRTT

- exponential weighted moving average
- influence of past sample decreases exponentially fast

\* typical value:  $\alpha = 0.125$ 



(seconds)

# TCP round trip time, timeout

- \* timeout interval: EstimatedRTT plus "safety margin"
  - large variation in EstimatedRTT -> larger safety margin
- estimate SampleRTT deviation from EstimatedRTT:

```
DevRTT = (1-\beta)*DevRTT + \beta*|SampleRTT-EstimatedRTT| (typically, \beta = 0.25)
```

## Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

## TCP reliable data transfer

- TCP creates rdt service on top of IP 's unreliable service
  - pipelined segments
  - cumulative acks
  - single retransmission timer
- retransmissions triggered by:
  - timeout events
  - duplicate acks

let's initially consider simplified TCP sender:

- ignore duplicate acks
- ignore flow control, congestion control

## TCP sender events:

### data rcvd from app:

- create segment with seq #
- seq # is byte-stream number of first data byte in segment
- start timer if not already running
  - think of timer as for oldest unacked segment
  - expiration interval: TimeOutInterval


#### timeout:

- retransmit segment that caused timeout
- restart timer

#### ack rcvd:


- if ack acknowledges previously unacked segments
  - update what is known to be ACKed
  - start timer if there are still unacked segments

## TCP sender (simplified)



### TCP: retransmission


### scenarios



lost ACK scenario

premature timeout

# TCP: retransmission scenarios



cumulative ACK

## TCP ACK generation [RFC 1122, RFC

2<del>501]</del>

event at receiver	TCP receiver action
arrival of in-order segment with expected seq #. All data up to expected seq # already ACKed	delayed ACK. Wait up to 500ms for next segment. If no next segment, send ACK
arrival of in-order segment with expected seq #. One other segment has ACK pending	immediately send single cumulative ACK, ACKing both in-order segments
arrival of out-of-order segment higher-than-expect seq. # . Gap detected	immediately send duplicate ACK, indicating seq. # of next expected byte
arrival of segment that partially or completely fills gap	immediate send ACK, provided that segment starts at lower end of gap

# TCP fast retransmit


- time-out period often relatively long:
  - long delay before resending lost packet
- detect lost segments via duplicate ACKs.
  - sender often sends many segments back-to-back
  - if segment is lost, there will likely be many duplicate ACKs.

#### TCP fast retransmit

if sender receives 3 ACKs for same ("triple duplicate ACKs"), auplicate ACKs"), resend unacked segment with smallest seq #

likely that unacked segment lost, so don't wait for timeout

# TCP fast retransm



fast retransmit after sender receipt of triple duplicate ACK

## Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

## TCP flow control

application may remove data from TCP socket buffers ....

... slower than TCP receiver is delivering (sender is sending)

### application process application OS TCP socket receiver buffers TCP code IΡ code from sender


#### flow controt

receiver controls sender, so sender won't overflow receiver's buffer by transmitting too much, too fast

receiver protocol stack

## TCP flow control

- receiver "advertises" free buffer space by including rwnd value in TCP header of receiverto-sender segments
  - RcvBuffer size set via socket options (typical default is 4096 bytes)
  - many operating systems autoadjust RcvBuffer
- \* sender limits amount of unacked ("in-flight") data to receiver's rwnd value
- guarantees receive buffer will not overflow



receiver-side buffering

## Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

## Connection Management

before exchanging data, sender/receiver "handshake":

- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters

```
connection state:
ESTAB
connection variables:
seq # client-to-
server
server-to-client
rcvBuffer size
netw@flserver,client
```


```
connection state:
ESTAB
connection Variables:
seq # client-to-
server
server-to-
client
networkiffer size
```


```
Socket clientSocket =
  newSocket("hostname","port
  number");
```

```
Socket connectionSocket =
  welcomeSocket.accept();
```

# Agreeing to establish a connection

#### 2-way handshake:







# Q: will 2-way handshake always work in network?

- variable delays
- retransmitted messages (e.g. req\_conn(x)) due to message loss
- message reordering
- can't "see" other side


# Agreeing to establish a connection

2-way handshake failure scenarios:






## TCP 3-way handshake




# TCP 3-way handshake: FSM



## TCP: closing a connection

- client, server each close their side of connection
  - send TCP segment with FIN bit = 1
- respond to received FIN with ACK
  - on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled

## TCP: closing a connection



## Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

# Principles of congestion control

### congestion:

- informally: "too many sources sending too much data too fast for network to handle"
- different from flow control!
- manifestations:
  - lost packets (buffer overflow at routers)
  - long delays (queueing in router buffers)
- \* a top-10 problem!


#### scenario 1


two senders, two receivers

 one router, infinite buffers


output link capacity: R

no retransmission






 maximum perconnection throughput: R/2



large delays as arrival rate, λ<sub>in</sub>, approaches capacity

#### scenario 2


- \* one router, finite buffers
- \* sender retransmission of timed-out packet
  - $^{\bullet}$  application-layer input = application-layer output:  $\lambda_{\text{in}}$  =  $\lambda_{\text{out}}$
  - transport-layer input includes  $retransmissions_i$ :  $\lambda_{in} \quad \lambda_{in}$




### scenario 2

## idealization: perfect knowledge

 sender sends only when router buffers available






### scenario 2

Idealization: known
loss packets can be lost,
dropped at router due

to full buffers


sender only resends if packet known to be lost





### scenario 2

Idealization: known
loss packets can be lost,
dropped at router due
to full buffers

sender only resends if packet known to be lost








#### scenario 2 Realistic: duplicates

- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered



#### "costs" of congestion:

- more work (retrans) for given "goodput"
- unneeded retransmissions: link carries multiple copies of pkt
  - decreasing goodput


#### scenario 3

- four senders
- multihop paths
- timeout/retransmit


Q: what happens as  $\lambda_{in}$  and  $\lambda_{in}$  increase?


and  $\lambda_{in}$  increase?

A: as red  $\lambda_{in}$  increases, all arriving blue pkts at upper queue are dropped, blue



#### scenario 3





#### another "cost" of congestion:

when packet dropped, any "upstream transmission capacity used for that packet was wasted!

# Approaches towards congestion control

two broad approaches towards congestion control:

#### end-end congestion control:

- no explicit feedback from network
- congestion inferred from end-system observed loss, delay
- approach taken by TCP

# network-assisted congestion control:

- routers provide feedback to end systems
  - single bit indicating congestion (SNA, DECbit, TCP/IP ECN, ATM)
  - explicit rate for sender to send at

# Case study: ATM ABR congestion


# ABR: available bit rate:

- "elastic service"
- if sender's path "underloaded":
  - sender should use available bandwidth
- if sender's path congested:
  - sender throttled to minimum guaranteed rate

# RM (resource management) cells:

- sent by sender, interspersed with data cells
- bits in RM cell set by switches ("network-assisted")
  - NI bit: no increase in rate (mild congestion)
  - CI bit: congestion indication
- \* RM cells returned to sender by receiver, with bits intact

# Case study: ATM ABR congestion control



- \* two-byte ER (explicit rate) field in RM cell
  - congested switch may lower ER value in cell
  - senders' send rate thus max supportable rate on path
- EFCI bit in data cells: set to 1 in congested switch
  - if data cell preceding RM cell has EFCI set, receiver sets CI bit in returned RM cell

## Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

# TCP congestion control: additive increase multiplicative decrease

 approach: sender increases transmission rate (window size), probing for usable bandwidth, until loss occurs


additive increase: increase cwnd by 1 MSS every RTT until loss detected

multiplicative decrease: cut cwnd in half

after loss

cwnd: TCP sender congestion window size

AIMD saw tooth behavior: probing for bandwidth



# TCP Congestion Control: details

last byte Sent, not-yet ACKed ("in-flight"

\* sender l'imits transmission:

LastByteSent
LastByteAcked

cwnd is dynamic, function of perceived network congestion


#### TCP sending rate:

roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes

rate 
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec

## TCP Slow Start

- \* when connection begins, increase rate exponentially until first loss event:
  - initially cwnd = 1 MSS
  - double cwnd every RTT
  - done by incrementing cwnd for every ACK received
- summary: initial rate is slow but ramps up exponentially fast



# TCP: detecting, reacting to loss


- loss indicated by timeout:
  - cwnd set to 1 MSS;
  - window then grows exponentially (as in slow start) to threshold, then grows linearly
- \* loss indicated by 3 duplicate ACKs: TCP RENO
  - dup ACKs indicate network capable of delivering some segments
  - cwnd is cut in half window then grows linearly
- \* TCP Tahoe always sets cwnd to 1 (timeout or 3 duplicate acks)

## TCP: switching from slow start

### to CA

Q: when should the exponential increase switch to linear?


A: when cwnd gets to 1/2 of its value before timeout.



#### **Implementation:**


- variable ssthresh
- on loss event, ssthresh is set to 1/2 of cwnd just before loss event

# Summary: TCP Congestion Control



# TCP throughput

- avg. TCP thruput as function of window size, RTT?
  - ignore slow start, assume always data to send
- W: window size (measured in bytes) where loss occurs
  - avg. window size (# inaflight bytes) is ¾ W
     avg TCP thruput = A Phytes/sec
     avg. thruput is 3/4W perRIT



# TCP Futures: TCP over "long, fat pipes"


- example: 1500 byte segments, 100ms
   RTT, want 10 Gbps throughput
- requires W = 83,333 in-flight segments
- throughput in terms of segment loss probability, L [Mathis 1997]:

TCP throughput = 
$$\frac{1.22 \cdot MSS}{RTT \sqrt{L}}$$

- → to achieve 10 Gbps throughput, need a loss rate of  $L = 2 \cdot 10^{-10}$  a very small loss rate!
- new versions of TCP for high-speed

## TCP Fairness

fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K




## Why is TCP fair?

#### two competing sessions:

additive increase gives slope of 1, as throughout increases

\* multiplicative decrease decreases throughput proportionally equal bandwidth share



# Fairness (more)

#### Fairness and UDP

- multimedia apps often do not use TCP
  - do not want rate throttled by congestion control
- instead use UDP:
  - send audio/video at constant rate, tolerate packet loss

# Fairness, parallel TCP connections

- application can open multiple parallel connections between two hosts
- \* web browsers do this
- e.g., link of rate R with 9 existing connections:
  - new app asks for 1 TCP, gets rate R/10
  - new app asks for 11 TCPs, gets R/2

## Chapter 3: summary

- principles behind transport layer services:
  - multiplexing, demultiplexing
  - reliable data transfer
  - flow control
  - congestion control
- instantiation, implementation in the Internet
  - UDP
  - TCP

#### next:

- leaving the network "edge" (application, transport layers)
- into the network "core"