Chapter 9: Virtual Memory







Objectives

- To describe the benefits of a virtual memory system
- To explain the concepts of demand paging, page-replacement algorithms, and allocation of page frames
- To discuss the principle of the working-set model






Background

- Virtual memory separation of user logical memory from physical memory.
 - Only part of the program needs to be in memory for execution
 - Logical address space can therefore be much larger than physical address space
 - Allows address spaces to be shared by several processes
 - Allows for more efficient process creation
- Virtual memory can be implemented via:
 - Demand paging
 - Demand segmentation






Virtual Memory That is Larger Than Physical Memory








Virtual-address Space







Shared Library Using Virtual Memory








Demand Paging

- Bring a page into memory only when it is needed
 - Less I/O needed
 - Less memory needed
 - Faster response
 - More users
- Page is needed ⇒ reference to it
 - invalid reference ⇒ abort
 - not-in-memory ⇒ bring to memory
- Lazy swapper never swaps a page into memory unless page will be needed
 - Swapper that deals with pages is a pager





Transfer of a Paged Memory to Contiguous Disk Space








Valid-Invalid Bit

- With each page table entry a valid-invalid bit is associated (v ⇒ in-memory, i ⇒ not-in-memory)
- Initially valid-invalid bit is set to i on all entries
- Example of a page table snapshot:




During address tra

is I ⇒ page fault

page table



Page Table When Some Pages Are Not in Main Memory







Page Fault

If there is a reference to a page, first reference to that page will trap to operating system:

page fault


- 3. Operating system looks at another table to decide:
 - Invalid reference ⇒ abort
 - Just not in memory
- Get empty frame
- Swap page into frame
- Reset tables
- Set validation bit = v
- Restart the instruction that caused the page fault





Page Fault (Cont.)

- Restart instruction
 - block move




auto increment/decrement location





Steps in Handling a Page Fault







Performance of Demand Paging

- Page Fault Rate $0 \le p \le 1.0$
 - if p = 0 no page faults
 - if p = 1, every reference is a fault
- Effective Access Time (EAT)

```
EAT = (1 - p) x memory access
+ p (page fault overhead
+ swap page out
+ swap page in
+ restart overhead
)
```





Demand Paging Example

- Memory access time = 200 nanoseconds
- Average page-fault service time = 8 milliseconds

EAT =
$$(1 - p) \times 200 + p$$
 (8 milliseconds)
= $(1 - p \times 200 + p \times 8,000,000$
= $200 + p \times 7,999,800$

If one access out of 1,000 causes a page fault, then EAT = 8.2 microseconds.

This is a slowdown by a factor of 40!!





Page Replacement


- Prevent over-allocation of memory by modifying page-fault service routine to include page replacement
- Use modify (dirty) bit to reduce overhead of page transfers only modified pages are written to disk
- Page replacement completes separation between logical memory and physical memory – large virtual memory can be provided on a smaller physical memory



9.22



Need For Page Replacement





9.23




Basic Page Replacement

- Find the location of the desired page on disk
- Find a free frame:
 - If there is a free frame, use it
 - If there is no free frame, use a page replacement algorithm to select a victim frame
- Bring the desired page into the (newly) free frame; update the page and frame tables
- Restart the process





Page Replacement








Page Replacement Algorithms

- Want lowest page-fault rate
- Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
- In all our examples, the reference string is





Graph of Page Faults Versus The Number of Frames







First-In-First-Out (FIFO) Algorithm


- Reference string: 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5
- 3 frames (3 pages can be in memory at a time per process)

Belady's Anomaly: more mes ⇒ more page faults 3






FIFO Page Replacement





FIFO Illustrating Belady's Anomaly








Optimal Algorithm


- Replace page that will not be used for longest period of time
- 4 frames example



- How do you know this 4 5
- Used for measuring how well your algorithm performs



Optimal Page Replacement





Least Recently Used (LRU) Algorithm

Reference string: 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5


3	1	1	1	1	5
	2	2	2	2	2
0	3	5	5	4	4
	4	4	3	3	3

- Counter implementation
 - Every page entry has a counter; every time page is referenced through this entry, copy the clock into the counter
 - When a page needs to be changed, look at the counters to determine which are to change





LRU Page Replacement






Thrashing

- If a process does not have "enough" pages, the page-fault rate is very high. This leads to:
 - low CPU utilization
 - operating system thinks that it needs to increase the degree of multiprogramming
 - another process added to the system
- Thrashing ≡ a process is busy swapping pages in and out





Thrashing (Cont.)







Demand Paging and Thrashing

- Why does demand paging work? Locality model
 - Process migrates from one locality to another
 - Localities may overlap
- Why does thrashing occur?
 Σ size of locality > total memory size






Buddy System

- Allocates memory from fixed-size segment consisting of physicallycontiguous pages
- Memory allocated using power-of-2 allocator
 - Satisfies requests in units sized as power of 2
 - Request rounded up to next highest power of 2
 - When smaller allocation needed than is available, current chunk split into two buddies of next-lower power of 2
 - Continue until appropriate sized chunk available





Buddy System Allocator





End of Chapter 9

