

Open CASCADE Technology 7.4.0.beta

Upgrade from older OCCT versions

September 26, 2019

Contents

1	Intro	duction	5
	1.1	Precautions	5
	1.2	Disclaimer	5
2	Upgı	rade to OCCT 6.5.0	6
3	Upgı	rade to OCCT 6.5.1	7
4	Upgı	rade to OCCT 6.5.2	8
5	Upgı	rade to OCCT 6.5.3	9
6	Upgı	rade to OCCT 6.5.4	10
7	Upgı	rade to OCCT 6.6.0	11
8	Upgı	rade to OCCT 6.7.0	13
	8.1	Object-level clipping and capping algorithm.	13
	8.2	Redesign of markers presentation	13
	8.3	Default views are not created automatically	13
	8.4	Improved dimensions implementation	13
	8.5	NCollection_Set replaced by List collection	14
9	Upgı	rade to OCCT 6.8.0	15
	9.1	Changes in NCollection classes	15
	9.2	3D View Camera	15
	9.3	Redesign of Connected Interactive Objects	15
	9.4	Support of UNICODE Characters	16
	9.5	Elimination of Projection Shift Concept	16
10	Upgı	rade to OCCT 6.9.0	17
	10.1	3D Viewer initialization	17
	10.2	Changes in Selection	17
	10.3	Changes in Adaptor3d_Curve class	18
	10.4	Changes in V3d_View class	18
11	Upgı	rade to OCCT 7.0.0	19
	11.1	Removal of legacy persistence	19
	11.2	Removal of CDL and WOK	20
		11.2.1 Automatic upgrade	20
		11.2.2 Possible compiler errors	22
		11.2.3 Possible runtime problems	24

11.2.4 Option to avoid cast of handle to reference to base type	24
11.2.5 Preserving compatibility with OCCT 6.x	25
11.2.6 Applications based on CDL and WOK	25
11.3 Separation of BSpline cache	26
11.4 Structural result of Boolean operations	26
11.5 BRepExtrema_ExtCC finds one solution only	26
11.6 Removal of SortTools package	26
11.7 On-screen objects and ColorScale	27
11.8 UserDraw and Visual3d	27
11.9 Deprecation of Local Context	29
11.10Separation of visualization part from TKCAF	29
11.11 Correction of interpretation of Euler angles in gp_Quaternion	29
11.12Zoom Persistent Selection	30
11.13Texture mapping of objects	30
11.14Shape presentation builders	30
Upgrada to OCCT 7.1.0	31
	31
	31 31
	32
	32
_	32
	32
	33
12.9 Other changes	33
Upgrade to OCCT 7.2.0	35
13.1 Removed features	35
13.2 Corrections in BRepOffset API	35
13.3 Corrections in BRepOffset API	36
13.4 Highlight style	36
13.5 Elimination of implicit 3D Viewer updates	37
13.6 Elimination of Quantity_NameOfColor from TKV3d interface classes	37
13.7 Result of Boolean operations on containers	38
13.8 Other changes	38
13.9 BOP - Pairs of interfering indices	38
13.10Removal of the Draw commands based on old Boolean operations	39
13.11 Change of Face/Face intersection in Boolean operations	39
13.12Restore OCCT 6.9.1 persistence	39
13.13Change in BRepLib_MakeFace algorithm	40
	11.2.5 Preserving compatibility with OCCT 6.x 11.2.6 Applications based on CDL and WOK 11.3 Separation of BSpline cache 11.4 Structural result of Boolean operations 11.5 BRepExtrema_ExtCC finds one solution only 11.6 Removal of SortTools package 11.7 On-screen objects and ColorScale 11.8 UserDraw and Visual3d 11.9 Deprecation of Local Context 11.10 Separation of visualization part from TKCAF 11.11 Correction of interpretation of Euler angles in gp_Ouaternion 11.12 Zoom Persistent Selection 11.13 Texture mapping of objects 11.14 Shape presentation builders Upgrade to OCCT 7.1.0 12.1 Presentation attributes 12.2 Typedefs 12.3 Programmable Pipeline 12.4 Transformation persistence 12.5 Dynamic highlight and selection properties 12.6 Correction in Tobj_Model class 12.7 Redundant environment variables 12.8 Removed features 12.9 Other changes 12.9 Other changes 12.0 Corrections in BRepOffset API 13.1 Removed features 13.2 Corrections in BRepOffset API 13.3 Corrections in BRepOffset API 13.4 Highlight style 13.5 Elimination of Quantity_NameOfColor from TKV3d interface classes 13.7 Result of Boolean operations on containers 13.8 Other changes 13.9 BOP - Pairs of interfering indices 13.10Removal of the Draw commands based on old Boolean operations 13.11Change of Face/Face intersection in Boolean operations

	13.14Change in BRepFill_OffsetWire algorithm	40
	13.15Change in Geom(2d)Adaptor_Curve::IsPeriodic	41
	13.16Change in algorithm ShapeUpgrade_UnifySameDomain	41
	13.17Changes in STL Reader / Writer	41
	13.18Refactoring of the Error/Warning reporting system in Boolean Component	41
14	Upgrade to OCCT 7.2.1	42
	14.1 Changes in ShapeUpgrade_UnifySameDomain	42
	14.2 Moving BuildPCurveForEdgeOnPlane from BOPTools_AlgoTools2D to BRepLib	42
	14.3 Removed features	42
15	Upgrade to OCCT 7.3.0	44
	15.1 Light sources	44
	15.2 Shading Models	44
	15.3 Custom low-level OpenGL elements	44
	15.4 Changes in BOPAlgo_Section	44
	15.5 Changes in BRepAdaptor_CompCurve	44
	15.6 Removed features	45
	15.7 Boolean Operations - Solid Builder algorithm	45
	15.8 Boolean Operation classes in BRepAlgo are deprecated	45
	15.9 Unification of the Error/Warning reporting system of Application Framework	45
16	Upgrade to OCCT 7.4.0	46
	16.1 Changes in BRepPrimAPI_MakeRevol algorithm	46
	16.2 Removed features	46
	16.3 Local Context removal	46
	16.4 Changes in behavior of Convert algorithms	46
	16.5 Changes in selection API and picked point calculation algorithm.	47
	16.6 Document format version management improvement	47
	16.7 BRepMesh - revision of the data model	47
	16.8 Changes in API of Chamfer algorithms	48
	16.9 Aspects unification	48
	16.10 Material definition	48
	16.11 Changes in Graphic3d_Text and OpenGI_Text API	49
	16.12Presentation invalidation	49
	16.13Interior styles	50
	16.14PrsMgr and SelectMgr hierarchy clean up	50
	16.15Polygon offset defaults	50
	16.16Adding ZLayers in given position	50
	16.17Modified enumerations	50
	16.18 Custom defines within env.bat	51

6.19 Switching Boolean Operations algorithm to use BVH tree instead of UB tree	51
6.20 Standard Stream.hxx no more has "using std::" statements	51

1 Introduction 5

1 Introduction

This document provides technical details on changes made in particular versions of OCCT. It can help to upgrade user applications based on previous versions of OCCT to newer ones.

1.1 Precautions

Back-up your code before the upgrade. We strongly recommend using version control system during the upgrade process and saving one or several commits at each step of upgrade, until the overall result is verified. This will facilitate identification and correction of possible problems that can occur at the intermediate steps of upgrade. It is advisable to document each step carefully to be able to repeat it if necessary.

1.2 Disclaimer

This document describes known issues that have been encountered during porting of OCCT and some applications and approaches that have helped to resolve these issues in known cases. It does not pretend to cover all possible migration issues that can appear in your application. Take this document with discretion; apply your expertise and knowledge of your application to ensure the correct result.

The automatic upgrade tool is provided as is, without warranty of any kind, and we explicitly disclaim any liability for possible errors that may appear due to use of this tool. It is your responsibility to ensure that the changes you made in your code are correct. When you upgrade the code by an automatic script, make sure to carefully review the introduced changes at each step before committing them.

Porting of user applications from an earlier OCCT version to version 6.5 requires taking into account the following major changes:

- If you are not comfortable with dependence on Intel TBB, FreeImage, or GI2Ps libraries, you will need to (re)build OCCT with these dependencies disabled.
- The low-level format version of OCAF binary and XML persistence has been incremented. Hence, the files saved by OCCT 6.5 to OCAF binary or XML format will not be readable by previous versions of OCCT.
- The *BRepMesh* triangulation algorithm has been seriously revised and now tries hard to fulfill the requested deflection and angular tolerance parameters. If you experience any problems with performance or triangulation quality (in particular, display of shapes in shading mode), consider revising the values of these parameters used in your application.
- If you were using method *ToPixMap()* of class *V3d_View* to get a buffer for passing to Windows API functions (e.g. *BitBlt*), this will not work anymore. You will need to use method *Image_PixMap::AccessBuffer()* to get the raw buffer data that can be further passed to WinAPI functions.
- As the processing of message gravity parameter in Message package has been improved, some application
 messages (especially the ones generated by IGES or STEP translators) can be suppressed or new messages
 appear in the application. Use relevant message level parameter to tune this behavior.

Porting of user applications from an earlier OCCT version to version 6.5.1 requires taking into account the following major changes:

• Method *Graphic3d_Structure::Groups()* now returns *Graphic3d_SequenceOfGroup*. If this method has been used, the application code should be updated to iterate another collection type or, if *Graphic3d_HSetOfGroup* is required, to fill its own collection:

```
const Graphic3d_SequenceOfGroup& aGroupsSeq = theStructure.Groups();
Handle(Graphic3d_HSetOfGroup) aGroupSet = new Graphic3d_HSetOfGroup();
Standard_Integer aLen = aGroupsSeq.Length();
for (Standard_Integer aGr = 1; aGr <= aLen; ++aGr)
{
    aGroupSet->Add (aGroupsSeq.Value (aGr));
}
```

- All occurrences of Select3D_Projector in the application code (if any) should be replaced with Handle(← Select3D_Projector).
- The code of inheritors of *Select3D_SensitiveEntity* should be updated if they override *Matches()* (this is probable, if clipping planes are used).
- Constructor for V3d_Plane has been changed, so the extra argument should be removed if used in the application. It is necessary to add a new plane using method V3d_Viewer::AddPlane() if V3d_Viewer has been used to manage clipping planes list (this does not affect clipping planes representation). Have a look at the source code for new DRAWEXE vclipplane command in ViewerTest_ObjectsCommands.cxx, VClipPlane to see how clipping planes can be managed in the application.

Porting of user applications from an earlier OCCT version to version 6.5.2 requires taking into account the following major changes:

- Any code that has been generated by WOK from CDL generic classes Tcollection_DataMap and Tcollection
 _IndexedDataMap needs to be regenerated by WOK to take into account the change in the interface of these classes.
- The enumerations CDF_StoreStatus and CDF_RetrievableStatus have been replaced by the enumerations PCDM_StoreStatus and PCDM_ReaderStatus. Correspondingly, the methods Open, Save and SaveAs of the class TDocStd_Application have changed their return value. Any code, which uses these enumerations, needs to be updated.
- BRepLib_MakeFace has been modified to receive tolerance value for resolution of degenerated edges. This tolerance parameter has no default value to ensure that the client code takes care of passing a meaningful value, not just Precision::Confusion, so some porting overheads are expected.
- If the callback mechanism in call_togl_redraw function was used in the application code, it is necessary to revise it to take into account the new callback execution and provide a check of reason value of Aspect_
 GraphicCallbackStruct in callback methods to confirm that the callback code is executed at the right moment. Now the callbacks are executed before redrawing the underlayer, before redrawing the overlayer and at the end of redrawing. The information about the moment when the callback is invoked is provided with the reason value in form of an additional bit flag (OCC_PRE_REDRAW, OCC_PRE_OVERLAY). The state of OpenGl changed in callback methods will not be restored automatically, which might lead to unwanted behavior in redrawing procedure.
- The print method used in the application code might need to be revised to take into account the ability to choose between print algorithms: tile and stretch. The stretch algorithm will be selected by default during porting.
- It is recommended to <code>BRepMesh_DiscretFactory</code> users, to check <code>BRepMesh_DiscretFactory::SetDefault()</code> return value to determine plugin availability / validity. <code>BRepMesh_DiscretFactory::Discret()</code> method now returns handle instead of pointer. The code should be updated in the following manner:

- The default state of BRepMesh parallelization has been turned off. The user should switch this flag explicitly:
 - by using methods BRepMesh_IncrementalMesh::SetParallel(Standard_True) for each BRepMesh_←
 IncrementalMesh instance before Perform();
 - by calling BRepMesh_IncrementalMesh::SetParallelDefault(Standard_True) when BRepMesh_←
 DiscretFactory is used to retrieve the meshing tool (this also affects auto-triangulation in AIS).

Porting of user applications from an earlier OCCT version to version 6.5.3 requires taking into account the following major changes:

- As a result of code clean-up and redesign of TKOpenGl driver, some obsolete functions and rendering primitives (TriangleMesh, TriangleSet, Bezier, Polyline, Polygon, PolygonHoles, QuadrangleMesh and QuadrangleSet) have been removed. Instead, the application developers should use primitive arrays that provide the same functionality but are hardware-accelerated. The details can be found in OCCT Visualization User's Guide, "Primitive Arrays" chapter.
- The applications that might have used internal functions provided by *TKOpenGI* or removed primitives will need to be updated.
- In connection with the implementation of Z-layers it might be necessary to revise the application code or revise the custom direct descendant classes of *Graphic3d_GraphicDriver* and *Graphic3d_StructureManager* to use the Z-layer feature.
- Global variables Standard PI and PI have been eliminated (use macro M PI instead).
- Method *HashCode()* has been removed from class *Standard_Transient*. It is advisable to use global function *HashCode()* for Handle objects instead.
- · Declaration of operators new/delete for classes has become consistent and is encapsulated in macros.
- Memory management has been changed to use standard heap (MMGT_OPT=0) and reentrant mode (MM
 GT_REENTRANT=1) by default.
- Map classes in NCollection package now receive one more argument defining a hash tool.

Porting of user applications from an earlier OCCT version to version 6.5.4 requires taking into account the following major changes:

• The code using obsolete classes Aspect_PixMap, Xw_PixMap and WNT_PixMap should be rewritten implementing class Image_PixMap, which is now retrieved by ToPixMap methods as argument. A sample code using ToPixMap is given below:

```
#include <Image_AlienPixMap.hxx>
void dump (Handle(V3d_View)& theView3D)
{
   Standard_Integer aWndSizeX = 0;
   Standard_Integer aWndSizeY = 0;
   theView3D->Window()->Size (aWndSizeX, aWndSizeY);
   Image_AlienPixMap aPixMap;
   theView3D->ToPixMap (aPixMap, aWndSizeX, aWndSizeY);
   apixMap.Save ("c:\\image.png");
}
```

- Now OpenGL resources related to Interactive Objects are automatically freed when the last view (window) is removed from graphical driver. To avoid presentation data loss, the application should replace an old view with a new one in the proper order: first the new view is created and activated and only then the old one is detached and removed.
- It is recommended to use *NCollection* containers with hasher parameter (introduced in 6.5.3) instead of global definition *IsEqual()/HashCode()* as well as to use explicit namespaces to avoid name collision.

Porting of user applications from an earlier OCCT version to version 6.6.0 requires taking into account the following major changes:

- Due to the changes in the implementation of Boolean Operations, the order of sub-shapes resulting from the same operation performed with OCCT 6.5.x and OCCT 6.6.0 can be different. It is necessary to introduce the corresponding changes in the applications for which the order of sub-shapes resulting from a Boolean operation is important. It is strongly recommended to use identification methods not relying on the order of sub-shapes (e.g. OCAF naming).
- If you need to use OCCT on Mac OS X with X11 (without Cocoa), build OCCT with defined pre-processor macro CSF_MAC_USE_GLX11. XLib front-end (previously the only way for unofficial OCCT builds on Mac OS X) is now disabled by default on this platform. If your application has no support for Cocoa framework you may build OCCT with XLib front-end adding MACOSX_USE_GLX macro to compiler options (you may check the appropriate option in WOK configuration GUI and in CMake configuration). Notice that XQuartz (XLib implementation for Mac OS X) now is an optional component and does not provide a sufficient level of integrity with native (Cocoa-based) applications in the system. It is not possible to build OCCT with both XLib and Cocoa at the same time due to symbols conflict in OpenGL functions.
- Animation mode and degeneration presentation mode (simplified presentation for animation) and associated methods have been removed from 3D viewer functionality. Correspondingly, the code using methods SetAnimationModeOn(), SetAnimationModeOff(), AnimationModelsOn(), AnimationMode(), Tumble(), SetDegenerateModeOn(), SetDegenerateModeOff() and DegenerateModelsOn() of classes V3d_View and Visual3d_View will need to be removed or redesigned. Hidden Line Removal presentation was not affected; however, the old code that used methods V3d_View::SetDegenerateModeOn or V3d_View::SetDegenerate—ModeOff to control HLR presentation should be updated to use V3d_View::SetComputedMode method instead.
- Calls of *Graphic3d_Group::BeginPrimitives()* and *Graphic3d_Group::EndPrimitives()* should be removed from the application code.
- Application functionality for drawing 2D graphics that was formerly based on TKV2d API should be migrated to TKV3d API. The following changes are recommended for this migration:
 - A 2D view can be implemented as a V3d_View instance belonging to V3d_Viewer managed by AIS
 _InteractiveContext instance. To turn V3d_View into a 2D view, the necessary view orientation should be set up at the view initialization stage using V3d_View::SetProj() method, and view rotation methods simply should not be called.
 - Any 2D graphic entity (formerly represented with AIS2D_InteractiveObject) should become a class derived from AIS_InteractiveObject base. These entities should be manipulated in a view using AIS_
 — InteractiveContext class API.
 - All drawing code should be put into Compute() virtual method of a custom interactive object class and
 use API of Graphic3d package. In particular, all geometry should be drawn using class hierarchy derived
 from Graphic3d_ArrayOfPrimitives. Normally, the Z coordinate for 2D geometry should be constant,
 unless the application implements some advanced 2D drawing techniques like e.g. multiple "Z layers"
 of drawings.
 - Interactive selection of 2D presentations should be set up inside ComputeSelection() virtual method of
 a custom interactive object class, using standard sensitive entities from Select3D package and standard
 or custom entity owners derived from SelectMgr_EntityOwner base. Refer to the Visualization User's
 Guide for further details concerning OCCT 3D visualization and selection classes. See also Viewer2D
 OCCT sample application, which shows how 2D drawing can be implemented using TKV3d API.
- Run-time graphic driver library loading mechanism based on *CSF_GraphicShr* environment variable usage has been replaced by explicit linking against *TKOpenGI* library. The code sample below shows how the graphic driver should be created and initialized in the application code:

```
// initialize a new viewer with OpenGl graphic driver
Handle(Graphic3d_GraphicDriver) aGraphicDriver =
new OpenGl_GraphicDriver ("TKOpenGl");
```

```
aGraphicDriver->Begin (new Aspect_DisplayConnection());
  TCollection_ExtendedString aNameOfViewer ("Visu3D");
  Handle (V3d_Viewer) aViewer
= new V3d_Viewer (aGraphicDriver, aNameOfViewer.ToExtString());
  aViewer->Init():
// create a new window or a wrapper over the existing window,
// provided by a 3rd-party framework (Qt, MFC, C# or Cocoa)
#if defined(_WIN32) || defined(__WIN32__)
  Aspect_Handle aWindowHandle = (Aspect_Handle )winId();
Handle (WNT_Window) aWindow = new WNT_Window (winId());
#elif defined(_APPLE_) && !defined(MACOSX_USE_GLX)
NSView* aViewHandle = (NSView* )winId();
  Handle(Cocoa_Window) aWindow = new Cocoa_Window (aViewHandle);
#else
 Aspect_Handle aWindowHandle = (Aspect_Handle )winId();
  Handle (Xw_Window) aWindow =
new Xw_Window (aGraphicDriver->GetDisplayConnection(), aWindowHandle);
#endif // WNT
// setup the window for a new view
  Handle(V3d_View) aView = aViewer->CreateView();
  aView->SetWindow (aWindow);
```

- The following changes should be made in the application-specific implementations of texture aspect:
 - Graphic3d_TextureRoot inheritors now should return texture image by overloading of Graphic3d_←
 TextureRoot::GetImage() method instead of the old logic.
 - Now you can decide if the application should store the image copy as a field of property or reload it dynamically each time (to optimize the memory usage). The default implementation (which loads the image content from the provided file path) does not hold an extra copy since it will be uploaded to the graphic memory when first used.
 - Notice that the image itself should be created within Image_PixMap class from AlienImage package, while Image_Image class is no more supported and will be removed in the next OCCT release.

Porting of user applications from an earlier OCCT version to version 6.7.0 requires taking into account the following major changes.

8.1 Object-level clipping and capping algorithm.

- It might be necessary to revise and port code related to management of view-level clipping to use *Graphic3d* __*ClipPlane* instead of *V3d_Plane* instances. Note that *V3d_Plane* class has been preserved as previously, it can be used as plane representation. Another approach to represent *Graphic3d_ClipPlane* in a view is to use custom presentable object.
- The list of arguments of Select3D_SensitiveEntity::Matches() method for picking detection has changed. Since now, for correct selection clipping, the implementations should perform a depth clipping check and return (as output argument) minimum depth value found at the detected part of sensitive. Refer to CDL / Doxygen documentation to find descriptive hints and snippets.
- Select3D_SensitiveEntity::ComputeDepth() abstract method has been removed. Custom implementations should provide depth checks by method Matches() instead all data required for it is available within a scope of single method.
- It might be necessary to revise the code of custom sensitive entities and port Matches() and ComputeDepth()
 methods to ensure proper selection clipping. Note that obsolete signature of Matches is not used anymore
 by the selector. If your class inheriting Select3D_SensitiveEntity redefines the method with old signature the
 code should not compile as the return type has been changed. This is done to prevent override of removed
 methods.

8.2 Redesign of markers presentation

- Due to the redesign of *Graphic3d_AspectMarker3d* class the code of custom markers initialization should be updated. Notice that you can reuse old markers definition code as *TColStd_HArray1OfByte*; however, *Image_PixMap* is now the preferred way (and supports full-color images on modern hardware).
- Logics and arguments of methods AIS_InteractiveContext::Erase() and AIS_InteractiveContext::EraseAll()
 have been changed. Now these methods do not remove resources from Graphic3d_Structure; they simply
 change the visibility flag in it. Therefore, the code that deletes and reomputes resources should be revised.
- *Graphic3d_Group::MarkerSet()* has been removed. *Graphic3d_Group::AddPrimitiveArray()* should be used instead to specify marker(s) array.

8.3 Default views are not created automatically

As the obsolete methods Init(), DefaultOrthographicView() and DefaultPerspectiveView() have been removed from $V3d_Viewer$ class, the two default views are no longer created automatically. It is obligatory to create $V3d_Viewer$ instances explicitly, either directly by operator new or by calling $V3d_Viewer::CreateView()$.

The call *V3d_Viewer::SetDefaultLights()* should also be done explicitly at the application level, if the application prefers to use the default light source configuration. Otherwise, the application itself should set up the light sources to obtain a correct 3D scene.

8.4 Improved dimensions implementation

It might be necessary to revise and port code related to management of AIS_LengthDimension, AIS_←
 AngleDimension and AIS_DiameterDimension presentations. There is no more need to compute value of
 dimension and pass it as string to constructor argument. The value is computed internally. The custom value
 can be set with SetCustomValue() method.

- The definition of units and general aspect properties is now provided by Prs3d_DimensionUnits and Prs3d←
 _DimensionApsect classes.
- It might be also necessary to revise code of your application related to usage of AIS_DimensionDisplayMode enumeration. If it used for specifying the selection mode, then it should be replaced by a more appropriate enumeration AIS_DimensionSelectionMode.

8.5 NCollection_Set replaced by List collection

It might be necessary to revise your application code, which uses non-ordered *Graphic3d_SetOfHClipPlane* collection type and replace its occurrences by ordered *Graphic3d_SequenceOfHClipPlane* collection type.

Porting of user applications from an earlier OCCT version to version 6.8.0 requires taking into account the following major changes.

9.1 Changes in NCollection classes

Method *Assign()* in *NCollection* classes does not allow any more copying between different collection types. Such copying should be done manually.

List and map classes in *NCollection* package now require that their items be copy-constructible, but do not require items to have default constructor. Thus the code using *NCollection* classes for non-copy-constructible objects needs be updated. One option is to provide copy constructor; another possibility is to use Handle or other smart pointer.

9.2 3D View Camera

If *ViewMapping* and *ViewOrientation* were used directly, this functionality has to be ported to the new camera model. The following methods should be considered as an alternative to the obsolete *Visual3d* services (all points and directions are supposed to be in world coordinates):

- Graphic3d_Camera::ViewDimensions() or V3d_View::Size()/ZSize() returns view width, height and depth
 (or "Z size"). Since the view is symmetric now, you can easily compute top, bottom, left and right limits.
 Graphic3d_Camera::ZNear()/ZFar() can be used to obtain the near and far clipping distances with respect to
 the eye.
- Graphic3d Camera::Up() or V3d View::Up() returns Y direction of the view.
- Graphic3d_Camera::Direction() returns the reverse view normal directed from the eye, V3d_View::Proj() returns the old-style view normal.
- *Graphic3d_Camera::Eye()* or *V3d_View::Eye()* returns the camera position (same as projection reference point in old implementation).
- *Graphic3d_Camera::Center()* or *V3d_View::At()* returns the point the camera looks at (or view reference point according to old terminology).

The current perspective model is not fully backward compatible, so the old perspective-related functionality needs to be reviewed.

Revise application-specific custom presentations to provide a proper bounding box, otherwise the object might become erroneously clipped by automatic *ZFit* or frustum culling algorithms enabled by default.

9.3 Redesign of Connected Interactive Objects

The new implementation of connected Interactive Objects makes it necessary to take the following steps if you use connected Interactive Objects in your application.

- Use new PrsMgr_PresentableObject transformation API.
- Call RemoveChild() from the original object after connect if you need the original object and AIS_Connected
 —
 Interactive to move independently.
- Access instances of objects connected to AIS MultiplyConnectedInteractive with Children() method.
- For *PrsMgr_PresentableObject* transformation:
 - SetLocation (TopLoc Location) -> SetLocalTransformation (gp Trsf)
 - Location -> LocalTransformation
 - HasLocation -> HasTransformation
 - ResetLocation -> ResetTransformation

9.4 Support of UNICODE Characters

Support of UNICODE characters introduced in OCCT breaks backward compatibility with applications, which currently use filenames in extended ASCII encoding bound to the current locale. Such applications should be updated to convert such strings to UTF-8 format.

The conversion from UTF-8 to wchar_t is made using little-endian approach. Thus, this code will not work correctly on big-endian platforms. It is needed to complete this in the way similar as it is done for binary persistence (see the macro *DO_INVERSE* in *FSD_FileHeader.hxx*).

9.5 Elimination of Projection Shift Concept

It might be necessary to revise the application code, which deals with Center() method of V3d View.

This method was used to pan a *V3d* view by virtually moving the screen center with respect to the projection ray passed through Eye and At points. There is no more need to derive the panning from the Center parameter to get a camera-like eye position and look at the coordinates. *Eye()* and *At()* now return these coordinates directly. When porting code dealing with *Center()*, the parameters *Eye()* and *At()* can be adjusted instead. Also *V3d_View::Set← Center(Xpix, Ypix)* method can be used instead of *V3d_View::Center(X, Y)* to center the view at the given point. However, if the center coordinates X and Y come from older OCCT releases, calling *V3d_View::Panning(-X, -Y)* can be recommended to compensate missing projection shift effect.

There are several changes introduced to $Graphic3d_Camera$. The internal data structure of the camera is based on $Standard_Real$ data types to avoid redundant application-level conversions and precision errors. The transformation matrices now can be evaluated both for $Standard_Real$ and $Standard_ShortReal$ value types. ZNear and $Z \leftarrow Far$ planes can be either negative or positive for orthographic camera projection, providing a trade-off between the camera distance and the range of ZNear or ZFar to reduce difference of exponents of values composing the orientation matrix - to avoid calculation errors. The negative values can be specified to avoid Z-clipping if the reference system of camera goes inside of the model when decreasing camera distance.

The auto z fit mode, since now, has a parameter defining Z-range margin (the one which is usually passed as argument to ZFitAll() method). The methods SetAutoZFitMode(), AutoZFitScaleFactor() and ZFitAll() from class $V3d_View$ deal with the new parameter.

The class *Select3D_Projector* now supports both orientation and projection transformation matrices, which can be naturally set for the projector. The definition of projector was revised in *StdSelect_ViewerSelector3d*: perspective and orthographic projection parameters are handled properly. Orthographic projector is based only on direction of projection - no more *Center* property. This makes it possible to avoid unnecessary re-projection of sensitive while panning, zooming or moving along the projection ray of the view. These operations do not affect the orthographic projection.

Porting of user applications from an earlier OCCT version to version 6.9.0 requires taking into account the following major changes.

10.1 3D Viewer initialization

3D Viewer now uses GLSL programs for managing frame buffer and stereoscopic output. For proper initialization, application should configure **CSF_ShadersDirectory** environment variable pointing to a folder with GLSL resources - files from folder **CASROOT**/src/Shaders. *Note that CSF_ShadersDirectory become optional since OCCT 7.1.0 release.*

10.2 Changes in Selection

Selection mechanism of 3D Viewer has been redesigned to use 3-level BVH tree traverse directly in 3D space instead of projection onto 2D screen space (updated on each rotation). This architectural redesign may require appropriate changes at application level in case if custom Interactive Objects are used.

Standard selection

Usage of standard OCCT selection entities would require only minor updates.

Custom Interactive Objects should implement new virtual method SelectMgr_SelectableObject::BoundingBox().

Now the method <code>SelectMgr_Selection::Sensitive()</code> does not return <code>SelectBasics_SensitiveEntity</code>. It returns an instance of <code>SelectMgr_SensitiveEntity</code>, which belongs to a different class hierarchy (thus <code>DownCast()</code> will fail). To access base sensitive it is necessary to use method <code>SelectMgr_SensitiveEntity::BaseSensitive()</code>. For example:

```
Handle(SelectMgr_Selection) aSelection = anInteractiveObject->Selection (aMode);
for (aSelection->Init(); aSelection->More(); aSelection->Next())
{
    Handle(SelectBasics_SensitiveEntity) anEntity = aSelection->Sensitive()->BaseSensitive();
}
```

Custom sensitive entities

Custom sensitive entities require more complex changes, since the selection algorithm has been redesigned and requires different output from the entities.

The method SelectBasics_SensitiveEntity::Matches() of the base class should be overridden following the new signature:

Standard_Boolean Matches (SelectBasics_SelectingVolumeManager& theMgr, SelectBasics_PickResult& the
PickResult), where theMgr contains information about the currently selected frustum or set of frustums (see Select
Mgr_RectangularFrustum, SelectMgr_TrangularFrustum, SelectMgr_TriangularFrustumSet) and SelectBasics_
PickResult is an output parameter, containing information about the depth of the detected entity and distance to its center of geometry.

In the overridden method it is necessary to implement an algorithm of overlap and inclusion detection (the active mode is returned by *theMgr.IsOverlapAllowed()*) with triangular and rectangular frustums.

The depth and distance to the center of geometry must be calculated for the 3D projection of user-picked screen point in the world space. You may use already implemented overlap and inclusion detection methods for different primitives from *SelectMgr_RectangularFrustum* and *SelectMgr_TriangularFrustum*, including triangle, point, axisaligned box, line segment and planar polygon.

Here is an example of overlap/inclusion test for a box:

```
if (!theMgr.IsOverlapAllowed()) // check for inclusion
{
   Standard_Boolean isInside = Standard_True;
   return theMgr.Overlaps (myBox.CornerMin(), myBox.CornerMax(), &isInside) && isInside;
}
```

```
Standard_Real aDepth;
if (!theMgr.Overlaps (myBox, aDepth)) // check for overlap
{
   return Standard_False;
}
thePickResult =
SelectBasics_PickResult (aDepth, theMgr.DistToGeometryCenter (myCenter3d));
```

The interface of *SelectBasics_SensitiveEntity* now contains four new pure virtual functions that should be implemented by each custom sensitive:

- BoundingBox() returns a bounding box of the entity;
- Clear() clears up all the resources and memory allocated for complex sensitive entities;
- BVH() builds a BVH tree for complex sensitive entities, if it is needed;
- *NbSubElements()* returns atomic sub-entities of a complex sensitive entity, which will be used as primitives for BVH building. If the entity is simple and no BVH is required, this method returns 1.

Each sensitive entity now has its own tolerance, which can be overridden by method *SelectBasics_SensitiveEntity*—::SetSensitivityFactor() called from constructor.

10.3 Changes in Adaptor3d_Curve class

All classes inheriting *Adaptor3d_Curve* (directly or indirectly) must be updated in application code to use new signature of methods *Intervals()* and *NbIntervals()*. Note that no compiler warning will be generated if this is not done.

10.4 Changes in V3d_View class

The methods V3d_View::Convert and V3d_View::ConvertWithProj() have ceased to return point on the active grid. It might be necessary to revise the code of your application so that V3d_View::ConvertToGrid() was called explicitly for the values returned by V3d_View::Convert to get analogous coordinates on the grid. The methods V3d_\(circ\) View::Convert and V3d_View::ConvertWithProj convert point into reference plane of the view corresponding to the intersection with the projection plane of the eye/view point vector.

11 Upgrade to OCCT 7.0.0

Porting of user applications from an earlier OCCT version to version 7.0.0 requires taking into account the following major changes.

Building OCCT now requires compiler supporting some C++11 features. The supported compilers are:

- · MSVC: version 10 (Visual Studio 2010) or later
- · GCC: version 4.3 or later
- · CLang: version 3.6 or later
- ICC: version XE 2013 SP 1 or later

When compiling code that uses OCCT with GCC and CLang compilers, it is necessary to use compiler option -std=c++0x (or its siblings) to enable C++11 features.

11.1 Removal of legacy persistence

Legacy persistence for shapes and OCAF data based on *Storage_Schema* (toolkits *TKPShape*, *TKPLCAF*, *TKP*← *CAF*, *TKShapeShcema*, *TLStdLSchema*, *TKStdSchema*, and *TKXCAFSchema*) has been removed in OCCT 7.0.0. The applications that used these data persistence tools need to be updated to use other persistence mechanisms.

Note

For compatibility with previous versions, the possibility to read standard OCAF data (*TKLCAF* and *TKCAF*) from files stored in the old format is preserved (toolkits *TKStdL* and *TKStd*).

The existing data files in standard formats can be converted using OCCT 6.9.1 or a previous version, as follows.

Note

Reading / writing custom files capability from OCCT 6.9.1 is restored in OCCT 7.2.0. See details in Restore OCCT 6.9.1 persistence section.

CSFDB files

Files in *CSFDB* format (usually with extension .csfdb) contain OCCT shape data that can be converted to BRep format. The easiest way to do that is to use ImportExport sample provided with OCCT 6.9.0 (or earlier):

- · Start ImportExport sample;
- · Select File / New;
- · Select File / Import / CSFDB... and specify the file to be converted;
- Drag the mouse with the right button pressed across the view to select all shapes by the rectangle;
- · Select File / Export / BREP... and specify the location and name for the resulting file

OCAF and XCAF documents

Files containing OCAF data saved in the old format usually have extensions .std, .sgd or .dxc (XDE documents). These files can be converted to XML or binary OCAF formats using DRAW Test Harness commands. Note that if the file contains only attributes defined in *TKLCAF* and *TKCAF*, this action can be performed in OCCT 7.0; otherwise OCCT 6.9.1 or earlier should be used.

For that, start *DRAWEXE* and perform the following commands:

To convert *.std and *.sgd file formats to binary format *.cbf (The created document should be in BinOcaf format instead of MDTV-Standard):

```
Draw[]> pload ALL
Draw[]> Open [path to *.std or *.sgd file] Doc
Draw[]> Format Doc BinOcaf
Draw[]> SaveAs Doc [path to the new file]
```

• To convert *.dxc file format to binary format *.xbf (The created document should be in BinXCAF format instead of MDTV-XCAF):

```
Draw[]> pload ALL
Draw[]> XOpen [path to *.dxc file] Doc
Draw[]> Format Doc BinXCAF
Draw[]> XSave Doc [path to the new file]
```

On Windows, it is necessary to replace back slashes in the file path by direct slashes or pairs of back slashes.

Use XmlOcaf or XmlXCAF instead of BinOcaf and BinXCAF, respectively, to save in XML format instead of binary one.

11.2 Removal of CDL and WOK

OCCT code has been completely refactored in version 7.0 to get rid of obsolete technologies used since its inception: CDL (Cas.Cade Definition Language) and WOK (Workshop Organization Kit).

C++ code previously generated by WOK from CDL declarations is now included directly in OCCT sources.

This modification did not change names, API, and behavior of existing OCCT classes, thus in general the code based on OCCT 6.x should compile and work fine with OCCT 7.0. However, due to redesign of basic mechanisms (CDL generic classes, Handles and RTTI) using C++ templates, some changes may be necessary in the code when porting to OCCT 7.0, as described below.

WOK is not necessary anymore for building OCCT from sources, though it still can be used in a traditional way – auxiliary files required for that are preserved. The recommended method for building OCCT 7.x is CMake, see occt_dev_guides__building_cmake. The alternative solution is to use project files generated by OCCT legacy tool genproj, see occt_dev_guides__building_msvc, occt_dev_guides__building_code_blocks, and occt_dev_guides__building_xcode.

11.2.1 Automatic upgrade

Most of typical changes required for upgrading code for OCCT 7.0 can be done automatically using the *upgrade* tool included in OCCT 7.0. This tool is a Tcl script, thus Tcl should be available on your workstation to run it.

Example:

```
$ tclsh
% source <path_to_occt>/adm/upgrade.tcl
% upgrade -recurse -all -src=<path_to_your_sources>
```

On Windows, the helper batch script *upgrade.bat* can be used, provided that Tcl is either available in *PATH*, or configured via *custom.bat* script (for instance, if you use OCCT installed from Windows installer package). Start it from the command prompt:

```
\verb|cmd> <path_to_occt> \upgrade.bat -recurse -all -inc=<path_to_occt> \undersection of the control of the cont
```

Run the upgrade tool without arguments to see the list of available options.

The upgrade tool performs the following changes in the code.

1. Replaces macro *DEFINE_STANDARD_RTTI* by *DEFINE_STANDARD_RTTIEXT*, with second argument indicating base class for the main argument class (if inheritance is recognized by the script):

```
DEFINE_STANDARD_RTTI(Class) -> DEFINE_STANDARD_RTTIEXT(Class, Base)
```

Note

If macro <code>DEFINE_STANDARD_RTTI</code> with two arguments (used in intermediate development versions of OCCT 7.0) is found, the script will convert it to either <code>DEFINE_STANDARD_RTTIEXT</code> or <code>DEFINE</code>—<code>STANDARD_RTTI_INLINE</code>. The former case is used if current file is header and source file with the same name is found in the same folder. In this case, macro <code>IMPLEMENT_STANDARD_RTTI</code> is injected in the corresponding source file. The latter variant defines all methods for RTTI as inline, and does not require <code>IMPLEMENT_STANDARD_RTTIEXT</code> macro.

2. Replaces forward declarations of collection classes previously generated from CDL generics (defined in *T*← *Collection* package) by inclusion of the corresponding header:

```
class TColStd ArraylOfReal: -> #include <TColStd ArraylOfReal.hxx>
```

3. Replaces underscored names of Handle classes by usage of a macro:

```
Handle_Class -> Handle(Class)
```

This change is not applied if the source or header file is recognized as containing the definition of Qt class with signals or slots, to avoid possible compilation errors of MOC files caused by inability of MOC to recognize macros (see https://doc.qt.io/qt-4.8/signalsandslots.html). The file is considered as defining a Qt object if it contains strings Q_OBJECT and either slots: or signals:.

4. Removes forward declarations of classes with names Handle(C) or $Handle_C$, replacing them either by forward declaration of its argument class, or (for files defining Qt objects) #include statement for a header with the name of the argument class and extension .hxx:

```
class Handle(TColStd_HArray1OfReal); -> #include <TColStd_HArray1OfReal.hxx>
```

5. Removes #includes of files Handle_...hxx that have disappeared in OCCT 7.0:

```
#include <Handle_Geom_Curve.hxx> ->
```

6. Removes *typedef* statements that use *Handle* macro to generate the name:

```
typedef NCollection_Handle<Message_Msg> Handle(Message_Msg); ->
```

7. Converts C-style casts applied to Handles into calls to DownCast() method:

8. Moves *Handle()* macro out of namespace scope:

```
Namespace::Handle(Class) -> Handle(Namespace::Class)
```

9. Converts local variables of reference type, which are initialized by a temporary object returned by call to *DownCast()*, to the variables of non-reference type (to avoid using references to destroyed memory):

```
\verb|const Handle(A)\& a = \verb|Handle(B)::DownCast (b); -> \verb|Handle(A)| a (|Handle(B)::DownCast (b)); \\
```

- Adds #include for all classes used as argument to macro STANDARD_TYPE(), except for already included ones;
- 11. Removes uses of obsolete macros *IMPLEMENT_DOWNCAST* and *IMPLEMENT_STANDARD_...*, except *IMPLEMENT_STANDARD_RTTIEXT*.

Note

If you plan to keep compatibility of your code with older versions of OCCT, add option *-compat* to avoid this change. See also Preserving compatibility with OCCT 6.x.

As long as the upgrade routine runs, some information messages are sent to the standard output. In some cases the warnings or errors like the following may appear:

Be sure to check carefully all reported errors and warnings, as the corresponding code will likely require manual corrections. In some cases these messages may help you to detect errors in your code, for instance, cases where *DEFINE STANDARD RTTI* macro is used with incorrect class name as an argument.

11.2.2 Possible compiler errors

Some situations requiring upgrade cannot be detected and / or handled by the automatic procedure. If you get compiler errors or warnings when trying to build the upgraded code, you will need to fix them manually. The following paragraphs list known situations of this kind.

Missing header files

The use of handle objects (construction, comparison using operators == or !=, use of function *STANDRAD_TYPE()* and method *DownCast()*) now requires the type of the object pointed by Handle to be completely known at compile time. Thus it may be necessary to include header of the corresponding class to make the code compilable.

For example, the following lines will fail to compile if *Geom_Line.hxx* is not included:

```
Handle(Geom_Line) aLine = 0;
if (aLine != aCurve) {...}
if (aCurve->IsKind(STANDARD_TYPE(Geom_Line)) {...}
aLine = Handle(Geom_Line)::DownCast (aCurve);
```

Note that it is not necessary to include header of the class to declare Handle to it. However, if you define a class *B* that uses Handle(*A*) in its fields, or contains a method returning Handle(*A*), it is advisable to have header defining *A* included in the header of *B*. This will eliminate the need to include the header *A* in each source file where class *B* is used.

Ambiguity of calls to overloaded functions

This issue appears in the compilers that do not support default arguments in template functions (known cases are Visual C++10 and 11): the compiler reports an ambiguity error if a handle is used in the argument of a call to the function that has two or more overloaded versions, receiving handles to different types. The problem is that operator const handle < T2>& is defined for any type T2, thus the compiler cannot make the right choice.

Example:

```
void func (const Handle(Geom_Curve)&);
void func (const Handle(Geom_Surface)&);
Handle(Geom_TrimmedCurve) aCurve = new Geom_TrimmedCurve (...);
func (aCurve); // ambiguity error in VC++ 10
```

Note that this problem can be avoided in many cases if macro OCCT HANDLE NOCAST is used, see below.

To resolve this ambiguity, change your code so that argument type should correspond exactly to the function signature. In some cases this can be done by using the relevant type for the corresponding variable, like in the example above:

```
Handle(Geom_Curve) aCurve = new Geom_TrimmedCurve (...);
```

Other variants consist in assigning the argument to a local variable of the correct type and using the direct cast or constructor:

```
const Handle(Geom_Curve)& aGCurve (aTrimmedCurve);
func (aGCurve); // OK - argument has exact type
func (static_cast(aCurve)); // OK - direct cast
func (Handle(Geom_Curve) (aCurve)); // OK - temporary handle is constructed
```

Another possibility consists in defining additional template variant of the overloaded function causing ambiguity, and using *SFINAE* to resolve the ambiguity. This technique can be illustrated by the definition of the template variant of method *IGESData IGESWriter::Send()*.

Lack of implicit cast to base type

As the cast of a handle to the reference to another handle to the base type has become a user-defined operation, the conversions that require this cast together with another user-defined cast will not be resolved automatically by the compiler.

For example:

```
Handle(Geom_Geometry) aC = GC_MakeLine (p, v); // compiler error
```

The problem is that the class *GC_MakeLine* has a user-defined conversion to *const Handle(Geom_Trimmed← Curve)&*, which is not the same as the type of the local variable *aC*.

To resolve this, use method Value():

```
Handle(Geom_Geometry) aC = GC_MakeLine (p, v).Value(); // ok
```

or use variable of the appropriate type:

```
Handle(Geom_TrimmedCurve) aC = GC_MakeLine (p, v); // ok
```

A similar problem appears with GCC compiler, when *const* handle to derived type is used to construct handle to base type via assignment (and in some cases in return statement), for instance:

```
const Handle(Geom_Line) aLine;
Handle(Geom_Curve) c1 = aLine; // GCC error
Handle(Geom_Curve) c2 (aLine); // ok
```

This problem is specific to GCC and it does not appear if macro OCCT_HANDLE_NOCAST is used, see below.

Incorrect use of STANDARD_TYPE and Handle macros

You might need to clean your code from incorrect use of macros STANDARD TYPE() and Handle().

1. Explicit definitions of static functions with names generated by macro *STANDARD_TYPE()*, which are artifacts of old implementation of RTTI, should be removed.

Example:

```
const Handle(Standard_Type) & STANDARD_TYPE(math_GlobOptMin)
{
  static Handle(Standard_Type) _atype = new Standard_Type ("math_GlobOptMin", sizeof (math_GlobOptMin));
  return _atype;
}
```

2. Incorrect location of closing parenthesis of *Handle()* macro that was not detectable in OCCT 6.x will cause a compiler error and must be corrected.

Example (note misplaced closing parenthesis):

```
aBSpline = Handle( Geom2d_BSplineCurve::DownCast(BS->Copy()) );
```

Use of class Standard_AncestorIterator

Class Standard_AncestorIterator has been removed; use method Parent() of Standard_Type class to parse the inheritance chain.

Absence of cast to Standard_Transient*

Handles in OCCT 7.0 do not have the operator of conversion to *Standard_Transient**, which was present in earlier versions. This is done to prevent possible unintended errors like this:

```
Handle(Geom_Line) aLine = ...;
Handle(Geom_Surface) aSurf = ...;
...
if (aLine == aSurf) {...} // will cause a compiler error in OCCT 7.0, but not OCCT 6.x
```

The places where this implicit cast has been used should be corrected manually. The typical situation is when Handle is passed to stream:

```
Handle(Geom_Line) aLine = ...;
os << aLine; // in OCCT 6.9.0, resolves to operator << (void*)</pre>
```

Call method *get()* explicitly to output the address of the Handle.

Method DownCast for non-base types

Method *DownCast()* in OCCT 7.0 is made templated; if its argument is not a base class, "deprecated" compiler warning is generated. This is done to prevent possible unintended errors like this:

```
Handle(Geom_Surface) aSurf = ;
Handle(Geom_Line) aLine =
   Handle(Geom_Line)::DownCast (aSurf); // will cause a compiler warning in OCCT 7.0, but not OCCT 6.x
```

The places where this cast has been used should be corrected manually.

If down casting is used in a template context where the argument can have the same or unrelated type so that <code>DownCast()</code> may be not available in all cases, use C++ <code>dynamic_cast<></code> instead, e.g.:

```
template <class T>
bool CheckLine (const Handle(T) theArg)
{
   Handle(Geom_Line) aLine = dynamic_cast<Geom_Line> (theArg.get());
   ...
}
```

11.2.3 Possible runtime problems

Here is the list of known possible problems at run time after the upgrade to OCCT 7.0.

References to temporary objects

In previous versions, the compiler was able to detect the situation when a local variable of a "reference to a Handle" type is initialized by temporary object, and ensured that lifetime of that object is longer than that of the variable. In OCCT 7.0 with default options, it will not work if types of the temporary object and variable are different (due to involvement of user-defined type cast), thus such temporary object will be destroyed immediately.

This problem does not appear if macro OCCT HANDLE NOCAST is used during compilation, see below.

Example:

```
// note that DownCast() returns new temporary object!
const Handle(Geom_BoundedCurve)& aBC =
Handle(Geom_TrimmedCurve)::DownCast(aCurve);
aBC->Transform (T); // access violation in OCCT 7.0
```

11.2.4 Option to avoid cast of handle to reference to base type

In OCCT 6.x and earlier versions the handle classes formed a hierarchy echoing the hierarchy of the corresponding object classes. This automatically enabled the possibility to use the handle to a derived class in all contexts where the handle to a base class was needed, e.g. to pass it in a function by reference without copying:

```
Standard_Boolean GetCurve (Handle(Geom_Curve)& theCurve);
....
Handle(Geom_Line) aLine;
if (GetCurve (aLine)) {
    // use aLine, unsafe
}
```

This feature was used in multiple places in OCCT and dependent projects. However it is potentially unsafe: in the above example no checks are done at compile time or at run time to ensure that the type assigned to the argument handle is compatible with the type of the handle passed as argument. If an object of incompatible type (e.g. Geom_Circle) is assigned to *theCurve*, the behavior will be unpredictable.

For compatibility with the existing code, OCCT 7.0 keeps this possibility by default, providing operators of type cast to the handle to a base type. However, this feature is unsafe and in specific situations it may cause compile-time or run-time errors as described above.

To provide a safer behavior, this feature can be disabled by a compile-time macro *OCCT_HANDLE_NOCAST*. When it is used, constructors and assignment operators are defined (instead of type cast operators) to convert handles to a derived type into handles to a base type. This implies creation of temporary objects and hence may be more expensive at run time in some circumstances, however this way is more standard, safer, and in general recommended.

The code that relies on the possibility of casting to base should be amended to always use the handle of argument type in function call and to use *DownCast()* to safely convert the result to the desired type. For instance, the code from the example below can be changed as follows:

```
Handle(Geom_Line) aLine;
Handle(Geom_Curve) aCurve;
if (GetCurve (aCure) && !(aLine = Handle(Geom_Line)::DownCast (aCurve)).IsNull()) {
    // use aLine safely
}
```

11.2.5 Preserving compatibility with OCCT 6.x

If you like to preserve the compatibility of your application code with OCCT versions 6.x even after the upgrade to 7.0, consider the following suggestions:

- 1. If your code used sequences of macros *IMPLEMENT_STANDARD_...* generated by WOK, replace them by single macro *IMPLEMENT_STANDARD_RTTIEXT*
- 2. When running automatic upgrade tool, add option -compat.
- 3. Define macros *DEFINE_STANDARD_RTTIEXT* and *DEFINE_STANDARD_RTTI_INLINE* when building with previous versions of OCCT, resolving to *DEFINE_STANDARD_RTTI* with single argument

Example:

```
#if OCC_VERSION_HEX < 0x070000
  #define DEFINE_STANDARD_RTTIEXT(C1,C2) DEFINE_STANDARD_RTTI(C1)
  #define DEFINE_STANDARD_RTTI_INLINE(C1,C2) DEFINE_STANDARD_RTTI(C1)
#endif</pre>
```

11.2.6 Applications based on CDL and WOK

If your application is essentially based on CDL, and you need to upgrade it to OCCT 7.0, you will very likely need to convert your application code to non-CDL form. This is a non-trivial effort; the required actions would depend strongly on the structure of the code and used CDL features.

The upgrade script and sources of a specialized WOK version used for OCCT code upgrade can be found in WOK Git repository in branch CR0_700_2.

Contact us if you need more help.

11.3 Separation of BSpline cache

Implementation of NURBS curves and surfaces has been revised: the cache of polynomial coefficients, which is used to accelerate the calculation of values of a B-spline, has been separated from data objects $Geom2d_B \leftarrow SplineCurve$, $Geom_BSplineCurve$ and $Geom_BSplineSurface$ into the dedicated classes $BSplCLib_Cache$ and $BSplSLib_Cache$.

The benefits of this change are:

- Reduced memory footprint of OCCT shapes (up to 20% on some cases)
- · Possibility to evaluate the same B-Spline concurrently in parallel threads without data races and mutex locks

The drawback is that direct evaluation of B-Splines using methods of curves and surfaces becomes slower due to the absence of cache. The slow-down can be avoided by using adaptor classes *Geom2dAdaptor_Curve*, *Geom—Adaptor_Curve* and *GeomAdaptor_Surface*, which now use cache when the curve or surface is a B-spline.

OCCT algorithms have been changed to use adaptors for B-spline calculations instead of direct methods for curves and surfaces. The same changes (use of adaptors instead of direct call to curve and surface methods) should be implemented in relevant places in the applications based on OCCT to get the maximum performance.

11.4 Structural result of Boolean operations

The result of Boolean operations became structured according to the structure of the input shapes. Therefore it may impact old applications that always iterate on direct children of the result compound assuming to obtain solids as iteration items, regardless of the structure of the input shapes. In order to get always solids as iteration items it is recommended to use TopExp_Explorer instead of TopoDS_Iterator.

11.5 BRepExtrema ExtCC finds one solution only

Extrema computation between non-analytical curves in shape-shape distance calculation algorithm has been changed in order to return only one solution. So, if e.g. two edges are created on parallel b-spline curves the algorithm BRepExtrema_DistShapeShape will return only one solution instead of enormous number of solutions. There is no way to get algorithm working in old manner.

11.6 Removal of SortTools package

Package *SortTools* has been removed. The code that used the tools provided by that package should be corrected manually. The recommended approach is to use sorting algorithms provided by STL.

For instance:

```
#include <SortTools_StraightInsertionSortOfReal.hxx>
#include <SortTools_ShellSortOfReal.hxx>
#include <TCollection_CompareOfReal.hxx>
...
TCollection_Array1OfReal aValues = ...;
...
TCollection_CompareOfReal aCompReal;
SortTools_StraightInsertionSortOfReal::Sort(aValues, aCompReal);
```

can be replaced by:

```
#include <algorithm>
...
TCollection_Array1OfReal aValues = ...;
...
std::stable_sort (aValues.begin(), aValues.end());
```

11.7 On-screen objects and ColorScale

The old mechanism for rendering Underlay and Overlay on-screen 2D objects based on *Visual3d_Layer* and immediate drawing model (uncached and thus slow) has been removed. Classes *Aspect_Clayer2d*, *OpenGl_ GraphicDriver_Layer*, *Visual3d_Layer, Visual3d_LayerItem*, *V3d_LayerMgr* and *V3d_LayerMgrPointer* have been deleted. The following auxiliary definition have been removed as well: Aspect_TypeOfPrimitive, Aspect_TypeOfLayer, Aspect_TypeOfDrawMode, Aspect_TypeOfConstraint, Aspect_DriverDefinitionError, Aspect_BadAccess.

General AIS interactive objects with transformation persistence flag *Graphic3d_TMF_2d* can be used as a replacement of *Visual3d_LayerItem*. The anchor point specified for transformation persistence defines the window corner of (or center in case of (0, 0) point). To keep on-screen 2D objects on top of the main screen, they can be assigned to the appropriate Z-layer. Predefined Z-layers *Graphic3d_ZLayerId_TopOSD* and *Graphic3d_ZLayerId_BotOSD* are intended to replace Underlay and Overlay layers within the old API.

ColorScale object previously implemented using Visual3d_LayerItem has been moved to a new class AIS_Color← Scale, with width and height specified explicitly. The property of V3d_View storing the global ColorScale object has been removed with associated methods V3d_View::ColorScaleDisplay(), V3d_View::ColorScaleErase(), V3d← _View::ColorScaleIsDisplayed() and V3d_View::ColorScale() as well as the classes V3d_ColorScale, V3d_Color← ScaleLayerItem and Aspect_ColorScale. Here is an example of creating ColorScale using the updated API:

```
Handle(AIS_ColorScale) aCS = new AIS_ColorScale();
// configuring
Standard_Integer aWidth, aHeight;
aView->Window()->Size (aWidth, aHeight);
aCS->SetSize (aWidth, aHeight);
aCS->SetRange (0.0, 10.0);
aCS->SetNumberOfIntervals (10);
// displaying
aCS->SetZLayer (Graphic3d_ZLayerId_TopOSD);
aCS->SetTransformPersistence (Graphic3d_TMF_2d, gp_Pnt (-1,-1,0));
aCS->SetTOUpdate();
theContextAIS->Display (aCS);
```

To see how 2d objects are implemented in OCCT you can call Draw commands *vcolorscale*, *vlayerline* or *vdrawtext* (with *-2d* option). Draw command *vcolorscale* now requires the name of *ColorScale* object as argument. To display this object use command *vdisplay*. For example:

```
pload VISUALIZATION
vinit
vcolorscale cs -demo
pload MODELING
box b 100 100 100
vdisplay b
vsetdispmode 1
vfit
vlayerline 0 300 300 300 10
vdrawtext t "2D-TEXT" -2d -pos 0 150 0 -color red
```

Here is a small example in C++ illustrating how to display a custom AIS object in 2d:

11.8 UserDraw and Visual3d

Visual3d package

Package *Visual3d* implementing the intermediate layer between high-level *V3d* classes and low-level OpenGl classes for views and graphic structures management has been dropped.

The *OpenGI_View* inherits from the new class *Graphic3d_CView*. *Graphic3d_CView* is an interface class that declares abstract methods for managing displayed structures, display properties and a base layer code that implements computation and management of HLR (or more broadly speaking view-depended) structures.

In the new implementation it takes place of the eliminated *Visual3d_View*. As before the instance of *Graphic3d_C View* is still completely managed by *V3d_View* classes. It can be accessed through *V3d_View* interface but normally it should not be required as all its methods are completely wrapped.

In more details, a concrete specialization of *Graphic3d_CView* is created and returned by the graphical driver on request. Right after the creation the views are directly used for setting rendering properties and adding graphical structures to be displayed.

The rendering of graphics is possible after mapping a window and activating the view. The direct setting of properties obsoletes the use of intermediate structures with display parameter like *Visual3d_ContextView*, etc. This means that the whole package *Visual3d* becomes redundant.

The functionality previously provided by Visual3d package has been redesigned in the following way:

- The management of display of structures has been moved from Visual3d_ViewManager into Graphic3d_←
 StructureManager.
- The class *Visual3d_View* has been removed. The management of computed structures has been moved into the base layer of *Graphi3d CView*.
- All intermediate structures for storing view parameters, e.g. *Visual3d_ContextView*, have been removed. The settings are now kept by instances of *Graphic3d_CView*.
- The intermediate class *Visual3d_Light* has been removed. All light properties are stored in *Graphic3d_CLight* structure, which is directly accessed by instances of *V3d_Light* classes.
- All necessary enumerations have been moved into *Graphic3d* package.

Custom OpenGL rendering and UserDraw

Old APIs based on global callback functions for creating *UserDraw* objects and for performing custom OpenGL rendering within the view have been dropped. *UserDraw* callbacks are no more required since *OpenGI_Group* now inherits *Graphic3d Group* and thus can be accessed directly from *AIS InteractiveObject*:

To perform a custom OpenGL code within the view, it is necessary to inherit from class *OpenGL_View*. See the following code sample:

```
return;
    // perform custom drawing
    const Handle(OpenGl_Context)& aCtx = myWorkspace->GetGlContext();
GLfloat aVerts[3] = { 0.0f, 0,0f, 0,0f };
aCtx->core20->glEnableClientState(GL_VERTEX_ARRAY);
    aCtx->core20->glVertexPointer(3, GL_FLOAT, 0, aVerts);
    aCtx->core20->glDrawArrays(GL_POINTS, 0, 1);
    aCtx->core20->glDisableClientState(GL_VERTEX_ARRAY);
};
//! Custom driver for creating UserView.
class UserDriver : public OpenGl_GraphicDriver
public:
  //! Create instance of own view.
  virtual Handle(Graphic3d_CView) CreateView (const Handle(Graphic3d_StructureManager)& theMgr)
       Standard OVERRIDE
    Handle(UserView) aView = new UserView (theMgr, this, myCaps, myDeviceLostFlag, &myStateCounter);
    myMapOfView.Add (aView);
    for (TColStd_SequenceOfInteger::Iterator aLayerIt (myLayerSeq); aLayerIt.More(); aLayerIt.Next())
                                          aLayerID = aLayerIt.Value();
       const Graphic3d_ZLayerId
      \verb|const Graphic3d_ZLayerSettings@ aSettings = myMapOfZLayerSettings.Find (aLayerID); \\
      aView->AddZLayer
                                  (aLayerID);
      aView->SetZLayerSettings (aLayerID, aSettings);
    return aView;
```

11.9 Deprecation of Local Context

The conception of Local Context has been deprecated. The related classes, e.g. *AIS_LocalContext*, and methods (*AIS_InteractiveContext::OpenLocalContext()* and others) will be removed in a future OCCT release.

The main functionality provided by Local Context - selection of object subparts - can be now used within Neutral Point without opening any Local Context.

The property *SelectionMode()* has been removed from the class *AIS_InteractiveObject*. This property contradicts to selection logic, since it is allowed to activate several Selection modes at once. Therefore keeping one selection mode as object field makes no sense. Applications that used this method should implement selection mode caching at application level, if it is necessary for some reason.

11.10 Separation of visualization part from TKCAF

Visualization CAF attributes have been moved into a new toolkit *TKVCAF*. If your application uses the classes from *TPrsStd* package then add link to *TKVCAF* library.

Version numbers of *BinOCAF* and *XmIOCAF* formats are incremented; new files cannot be read by earlier versions of OCCT.

Before loading the OCAF files saved by previous versions and containing *TPrsStd_AlSPresentation* attribute it is necessary to define the environment variable *CSF_MIGRATION_TYPES*, pointing to file *src/StdResources/* \leftarrow *MigrationSheet.txt*. When using documents loaded from a file, make sure to call method *TPrsStd_AlSViewer::New()* prior to accessing *TPrsStd_AlSPresentation* attributes in this document as that method creates them.

11.11 Correction of interpretation of Euler angles in gp Quaternion

Conversion of gp_Quaternion to and from intrinsic Tait-Bryan angles (including gp_YawPitchRoll) is fixed.

Before that fix the sequence of rotation axes was opposite to the intended; e.g. $gp_YawPitchRoll$ (equivalent to $gp_Intrinsic_ZYX$) actually defined intrinsic rotations around X, then Y, then Z. Now the rotations are made in the correct order.

The applications that use *gp_Quaternion* to convert Yaw-Pitch-Roll angles (or other intrinsic Tait-Bryan sequences) may need to be updated to take this change into account.

11.12 Zoom Persistent Selection

Zoom persistent selection introduces a new structure *Graphic3d_TransformPers* to transform persistence methods and parameters and a new class *Graphic3d_WorldViewProjState* to refer to the camera transformation state. You might need to update your code to deal with the new classes if you were using the related features. Keep in mind the following:

- Graphic3d_Camera::ModelViewState has been renamed to Graphic3d_Camera::WorldViewState.
- Transformation matrix utilities from *OpenGI_Utils* namespace have been moved to *Graphic3d_TransformUtils* and *Graphic3d_TransformUtils.hxx* header respectively.
- Matrix stack utilities from *OpenGI_Utils* namespace have been moved to *OpenGI_MatrixStack* class and *OpenGI_MatrixStack.hxx* header respectively.
- OpenGl_View methods Begin/EndTransformPersistence have been removed. Use Graphic3d_Transform
 — Pers::Apply() instead to apply persistence to perspective and world-view projection matrices.

11.13 Texture mapping of objects

Textured objects now have the priority over the environment mapping.

Redundant enumerations V3d_TypeOfSurface and Graphic3d_TypeOfSurface, class OpenGl_SurfaceDetailState, the corresponding methods from Graphic3d_CView, OpenGl_ShaderManager, OpenGl_View, V3d_View and V3d~Viewer have been deleted. Draw command VSetTextureMode has been deleted.

11.14 Shape presentation builders

Presentation tools for building Wireframe presentation have been refactored to eliminate duplicated code and interfaces. Therefore, the following classes have been modified:

- StdPrs_WFDeflectionShape and Prs3d_WFShape have been removed. StdPrs_WFShape should be used instead.
- StdPrs ToolShadedShape has been renamed to StdPrs ToolTriangulatedShape.

12 Upgrade to OCCT 7.1.0

12.1 Presentation attributes

This section should be considered if application defines custom presentations, i.e. inherited from *AIS_Interactive Object*. The previous versions of OCCT have three levels for defining presentation properties (e.g. colors, materials, etc.):

- 1. For the entire structure *Graphic3d_Structure | Prs3d_Presentation*.
- 2. For a specific group of primitives *Graphic3d_Group::SetGroupPrimitivesAspect()* overriding structure aspects.
- 3. For a specific primitive array within the graphic group Graphic3d Group::SetPrimitivesAspect().

The structure level has de facto not been used for a long time since OCCT presentations always define aspects at the graphic group level (overriding any structure aspects). Within this OCCT release, structure level of aspects has been completely removed. In most cases the application code should just remove missing methods. In those rare cases, when this functionality was intentionally used, the application should explicitly define aspects to the appropriate graphic groups.

Note that defining several different aspects within the same graphic group should also be avoided in the application code since it is a deprecated functionality which can be removed in further releases. *Graphic3d_Group::SetGroup*—*PrimitivesAspect()* should be the main method defining presentation attributes.

The implementation of *Graphic3d_Group::SetGroupPrimitivesAspect()* has been changed from copying aspect values to keeping the passed object. Although it was not documented, previously it was possible to modify a single aspect instance, like *Graphic3d_AspectFillArea3d* and set it to multiple groups. Now such code would produce an unexpected result and therefore should be updated to create the dedicated aspect instance.

12.2 Typedefs

The following type definitions in OCCT has been modified to use C++11 types:

- Standard_Boolean is now bool (previously unsigned int).
- Standard ExtCharacter is now char16 t (previously short).
- Standard_ExtString; is now const char16_t (previously const short).
- Standard_Utf16Char is now char16_t (previously uint16_t for compatibility with old compilers).
- Standard_Utf32Char is now char32_t (previously uint32_t for compatibility with old compilers).

For most applications this change should be transparent on the level of source code. Binary compatibility is not maintained, as *bool* has a different size in comparison with *unsigned int*.

12.3 Programmable Pipeline

Fixed-function pipeline has been already deprecated since OCCT 7.0.0. Release 7.1.0 disables this functionality by default in favor of Programmable Pipeline (based on GLSL programs).

Method V3d_View::Export(), based on gl2ps library, requires fixed pipeline and will return error if used with default settings. Applications should explicitly enable fixed pipeline by setting OpenGl_Caps::ffpEnable flag to TRUE within OpenGl_GraphicDriver::ChangeOptions() before creating the viewer to use V3d_View::Export(). This method is declared as deprecated and will be removed in one of the the next OCCT releases. The recommended way to generate a vector image of a 3D model or scene is to use an application-level solution independent from OpenGL.

12.4 Transformation persistence

The behavior of transformation persistence flags *Graphic3d_TMF_ZoomPers* and *Graphic3d_TMF_TriedronPers* has been changed for consistency with a textured fixed-size 2D text. An object with these flags is considered as defined in pixel units, and the presentation is no more scaled depending on the view height. The applications that need to scale such objects depending on viewport size should update them manually.

Flags *Graphic3d_TMF_PanPers* and *Graphic3d_TMF_FullPers* have been removed. *Graphic3d_TMF_TriedronPers* or *Graphic3d_TMF_2d* can be used instead depending on the context.

Graphic3d_TransModeFlags is not an integer bitmask anymore - enumeration values should be specified instead. Several transformation persistence methods in PrsMgr_PresentableObject have been marked deprecated. Transformation persistence should be defined using Graphic3d_TransformPers constructor directly and passed by a handle, not value.

12.5 Dynamic highlight and selection properties

Release 7.1.0 introduces *Graphic3d_HighlightStyle* - an entity that allows flexible customization of highlighting parameters (such as highlighting method, color, and transparency). Therefore, the signatures of the following methods related to highlighting:

- AIS_InteractiveContext::Hilight();
- AIS InteractiveContext::HilightWithColor();
- PrsMgr PresentationManager::Color();
- SelectMgr_EntityOwner::HilightWithColor(); have been changed to receive Graphic3d_HighlightStyle instead of Quantity_Color.

Method AIS Interactive Context::Hilight is now deprecated and highlights the interactive object with selection style.

A group of methods AIS_InteractiveContext::IsHilighted has changed its behavior - now they only check highlight flags of the object or the owner in the global status. If the highlight color is required on the application level, it is necessary to use overloaded methods AIS_InteractiveContext::HighlightStyle for the owner and the object.

The following methods have been replaced in AIS_InteractiveContext class:

- HilightColor and SetHilightColor by HighlightStyle and SetHighlightStyle;
- SelectionColor setter and getter by SelectionStyle and SetSelectionStyle.

The API of *Prs3d_Drawer* has been extended to allow setting up styles for both dynamic selection and highlighting. Therefore, it is possible to change the highlight style of a particular object on the application level via *SelectMgr_ SelectableObject::HilightAttributes()* and process it in the entity owner.

12.6 Correction in TObj_Model class

Methods *TObj_Model::SaveAs* and *TObj_Model::Load* now receive *TCollection_ExtendedString* filename arguments instead of char*. UTF-16 encoding can be used to pass file names containing Unicode symbols.

12.7 Redundant environment variables

The following environment variables have become redundant:

• CSF_UnitsLexicon and CSF_UnitsDefinition are no more used. Units definition (UnitsAPI/Lexi_Expr.dat and UnitsAPI/Units.dat) is now embedded into source code.

12.8 Removed features 33

• CSF_XSMessage and CSF_XHMessage are now optional. English messages (XSMessage/*XSTEP.us* and SHMessage/*SHAPE.us*) are now embedded into source code and automatically loaded when environment variables are not set.

- CSF_ShadersDirectory is not required any more, though it still can be used to load custom shaders. Mandatory GLSL resources are now embedded into source code.
- CSF_PluginDefaults and other variables pointing to OCAF plugin resources (CSF_StandardDefaults, CS← F_XCAFDefaults, CSF_StandardLiteDefaults and CSF_XmlOcafResource) are not necessary if method T← DocStd_Application::DefineFormat() is used to enable persistence of OCAF documents.

Other environment variables still can be used to customize behavior of relevant algorithms but are not necessary any more (all required resources are embedded).

12.8 Removed features

The following obsolete features have been removed:

- Anti-aliasing API V3d_View::SetAntialiasingOn(). This method was intended to activate deprecated Open
 GL functionality GL_POLYGON_SMOOTH, GL_LINE_SMOOTH and GL_POINT_SMOOTH. Instead of the
 old API, the application should request MSAA buffers for anti-aliasing by assigning Graphic3d_Rendering
 Params::NbMsaaSamples property of the structure returned by V3d_View::ChangeRenderingParams().
- Prs3d_Drawer::ShadingAspectGlobal() flag has been removed as not used. The corresponding calls can be removed safely from the application code.
- The methods managing ZClipping planes and ZCueing: V3d_View::SetZClippingType(), V3d_View::SetZClippingType(), V3d_View::SetZClippingDype(), V3d_View::Set
- The 3D viewer printing API V3d_View::Print() has been removed. This functionality was available on Windows platforms only. The applications should use the general image dump API V3d_View::ToPixMap() and manage printing using a platform-specific API at the application level. Text resolution can be managed by rendering parameter Graphic3d_RenderingParams::Resolution, returned by V3d_View::ChangeRenderingParams().
- Methods PrsMgr_PresentationManager::BoundBox, PrsMgr_PresentationManager::Hilight and SelectMgr_
 EntityOwner::Hilight have been removed as not used. The corresponding method in custom implementations
 of SelectMgr_EntityOwner can be removed safely. PrsMgr_PresentationManager::Color with the corresponding style must be used instead.
- Class NCollection_QuickSort has been removed. The code that used the tools provided by that class should be corrected manually. The recommended approach is to use sorting algorithms provided by STL (std::sort). See also Removal of SortTools package above.
- Package *Dico*. The code that used the tools provided by that package should be corrected manually. The recommended approach is to use *NCollection_DataMap* and *NCollection_IndexedDataMap* classes.

12.9 Other changes

The following classes have been changed:

- BVH_Sorter class has become abstract. The list of arguments of both Perform methods has been changed and the methods became pure virtual.
- Extrema_FuncExtPS has been renamed to Extrema_FuncPSNorm.
- The default constructor and the constructor taking a point and a surface have been removed from class *Extrema_GenLocateExtPS*. Now the only constructor takes the surface and optional tolerances in U and V directions. The new method *Perform* takes the point with the start solution and processes it. The class has become not assignable and not copy-constructable.

12.9 Other changes 34

Constructors with arguments *(const gp_Ax22d& D, const gp_Pnt2d& F)* have been removed from GCE2d←
 _MakeParabola, gce_MakeParab2d and gp_Parab2d. The objects created with some constructors of class
 gp_Parab2d may differ from the previous version (see the comments in gp_Parab2d.hxx). The result returned
 by gp_Parab2d::Directrix() method has an opposite direction in comparison with the previous OCCT versions.

- BRepTools_Modifier class now has two modes of work. They are defined by the boolean parameter Mutable
 Input, which is turned off by default. This means that the algorithm always makes a copy of a sub-shape (e.g. vertex) if its tolerance is to be increased in the output shape. The old mode corresponds to MutableInput turned on. This change may impact an application if it implements a class derived from BRepTools_Modifier.
- The second parameter theIsOuterWire of method ShapeAnalysis_Wire::CheckSmallArea has been removed.
- In class *GeomPlate_CurveConstraint*, two constructors taking boundary curves of different types have been replaced with one constructor taking the curve of an abstract type.
- The last optional argument RemoveInvalidFaces has been removed from the constructor of class BRep
 — Offset MakeOffset and method Initialize.
- The public method BOPDS_DS::VerticesOnIn has been renamed into SubShapesOnIn and the new output parameter theCommonPB has been added.

13 Upgrade to OCCT 7.2.0

13.1 Removed features

The following obsolete features have been removed:

- AIS_InteractiveContext::PreSelectionColor(), DefaultColor(), WasCurrentTouched(), ZDetection(). These properties were unused, and therefore application should remove occurrences of these methods.
- AIS_InteractiveObject::SelectionPriority(). These property was not implemented.
- The class LocOpe HBuilder has been removed as obsolete.
- The package TestTopOpe has been removed;
- The package TestTopOpeDraw has been removed;
- The package TestTopOpeTools has been removed.
- The packages *QANewModTopOpe*, *QANewBRepNaming* and *QANewDBRepNaming* have been removed as containing obsolete features.
- The following methods of the IntPolyh_Triangle class have been removed as unused:
 - CheckCommonEdge
 - SetEdgeandOrientation
 - MultipleMiddleRefinement2.
- The following methods of the IntPolyh MaillageAffinage class have been removed as unused:
 - LinkEdges2Triangles;
 - TriangleEdgeContact2;
 - StartingPointsResearch2;
 - NextStartingPointsResearch2;
 - TriangleComparePSP;
 - StartPointsCalcul.
- The method PerformAdvanced of the ShapeConstruct_ProjectCurveOnSurface class has been removed as unused.
- The method Perform of the ShapeConstruct ProjectCurveOnSurface class is modified:
 - input arguments continuity, maxdeg, nbinterval have been removed as unused;
 - input arguments TolFirst, TolLast have been added at the end of arguments' list.
- Typedefs Quantity_Factor, Quantity_Parameter, Quantity_Ratio, Quantity_Coefficient, Quantity_PlaneAngle, Quantity_Length, V3d_Parameter and V3d_Coordinate have been removed; Standard_Real should be used instead.

13.2 Corrections in BRepOffset API

In classes *BRepTools_ReShape* and *ShapeBuild_ReShape*, the possibility to process shapes different only by orientation in different ways has been removed. Thus methods *Remove()* and *Replace()* do not have any more the last argument 'oriented'; they work always as if *Standard_False* was passed before (default behavior). Methods *ModeConsiderLo()* and *Apply()* with three arguments have been removed.

13.3 Corrections in BRepOffset API

Class BRepOffsetAPI MakeOffsetShape:

- BRepOffsetAPI_MakeOffsetShape::BRepOffsetAPI_MakeOffsetShape() constructor with parameters has been deleted.
- BRepOffsetAPI_MakeOffsetShape::PerformByJoin() method has been added. This method is old algorithm behaviour.

The code below shows new calling procedure:

```
BRepOffsetAPI_MakeOffsetShape OffsetMaker;
OffsetMaker.PerformByJoin(Shape, OffsetValue, Tolerance);
NewShape = OffsetMaker.Shape();
```

Class BRepOffsetAPI_MakeThickSolid:

- BRepOffsetAPI_MakeThickSolid::BRepOffsetAPI_MakeThickSolid() constructor with parameters has been deleted.
- BRepOffsetAPI_MakeThickSolid::MakeThickSolidByJoin() method has been added. This method is old algorithm behaviour.

The code below shows new calling procedure:

```
BRepOffsetAPI_MakeThickSolid BodyMaker;
BodyMaker.MakeThickSolidByJoin(myBody, facesToRemove, -myThickness / 50, 1.e-3);
myBody = BodyMaker.Shape();
```

13.4 Highlight style

Management of highlight attributes has been revised and might require modifications from application side:

- New class *Graphic3d_PresentationAttributes* defining basic presentation attributes has been introduced. It's definition includes properties previously defined by class Graphic3d_HighlightStyle (*Color*, *Transparency*), and new properties (*Display mode*, *ZLayer*, optional *FillArea aspect*).
- Class *Prs3d_Drawer* now inherits class *Graphic3d_PresentationAttributes*. So that overall presentation attributes are now split into two parts Basic attributes and Detailed attributes.
- Class Graphic3d_HighlightStyle has been dropped. It is now defined as a typedef to Prs3d_Drawer. Therefore, highlight style now also includes not only Basic presentation attributes, but also Detailed attributes which can be used by custom presentation builders.
- Highlighting style defined by class *Graphic3d_PresentationAttributes* now provides more options:
 - Graphic3d_PresentationAttributes::BasicFillAreaAspect() property providing complete Material definition. This option, when defined, can be used instead of the pair Object Material + Highlight Color.
 - Graphic3d_PresentationAttributes::ZLayer() property specifying the Layer where highlighted presentation should be shown. This property can be set to Graphic3d_ZLayerId_UNKNOWN, which means that ZLayer of main presentation should be used instead.
 - Graphic3d_PresentationAttributes::DisplayMode() property specifying Display Mode for highlight presentation.
- Since Highlight and Selection styles within AIS_InteractiveContext are now defined by Prs3d_Drawer inheriting from Graphic3d_PresentationAttributes, it is now possible to customize default highlight attributes like Display Mode and ZLayer, which previously could be defined only on Object level.

- Properties Prs3d_Drawer::HighlightStyle() and Prs3d_Drawer::SelectionStyle() have been removed. Instead, AIS_InteractiveObject now defines DynamicHilightAttributes() for dynamic highlighting in addition to Hilight
 Attributes() used for highlighting in selected state. Note that AIS_InteractiveObject::HilightAttributes() and AIS_InteractiveObject::DynamicHilightAttributes() override highlighting properties for both entire object and for part coming from decomposition. This includes Z-layer settings, which will be the same when overriding properties through AIS_InteractiveObject, while AIS_InteractiveContext::HighlightStyle() allows customizing properties for local and global selection independently (with Graphic3d_ZLayerId_Top used for dynamic highlighting of object part by default).
- The following protected fields have been removed from class AIS InteractiveObject:
 - myOwnColor, replaced by myDrawer->Color()
 - myTransparency, replaced by myDrawer->Transparency()
 - myZLayer, replaced by myDrawer->ZLayer()
- The method *PrsMgr_PresentationManager::Unhighlight()* taking Display Mode as an argument has been marked deprecated. Implementation now performs unhighlighting of all highlighted presentation mode.
- The methods taking/returning Quantity_NameOfColor (predefined list of colors) and duplicating methods operating with Quantity_Color (definition of arbitrary RGB color) in AIS have been removed. Quantity_Color should be now used instead.

13.5 Elimination of implicit 3D Viewer updates

Most AIS_InteractiveContext methods are defined with a flag to update viewer immediatly or not. Within previous version of OCCT, this argument had default value TRUE. While immediate viewer updates are useful for beginners (the result is displayed as soon as possible), this approach is inefficent for batch viewer updates, and having default value as TRUE leaded to non-intended accidential updates which are difficult to find.

To avoid such issues, the interface has been modified and default value has been removed. Therefore, old application code should be updated to set the flag the ToUpdateViewer explicitly to desired value (TRUE to preserve old previous behavior), if it was not already set.

The following AlS_InteractiveContext methods have been changed: Display, Erase, EraseAll, DisplayAll, EraseSelected, DisplaySelected, ClearPrs, Remove, RemoveAll, Hilight, HilightWithColor, Unhilight, Redisplay, RecomputePrsOnly, Update, SetDisplayMode, UnsetDisplayMode, SetColor, UnsetColor, SetWidth, UnsetWidth, SetMaterial, UnsetMaterial, SetTransparency, UnsetTransparency, SetLocalAttributes, UnsetLocalAttributes, SetPolygonOffsets, SetTrihedronSize, SetPlaneSize, SetPlaneSize, SetDeviationCoefficient, SetDeviationAngle, SetAngleAndDeviation, SetHLRDeviationCoefficient, SetHLRDeviationAngle, SetHLRAngleAndDeviation, SetWidth, SelectedAspect, MoveTo, Select, ShiftSelect, SetSelected, UpdateSelected, AddOrRemoveSelected, HilightWithColor, UnhilightSelected, ClearSelected, ResetOriginalState, SubIntensityOn, SubIntensityOff, FitSelected, EraseGlobal, ClearGlobalPrs.

In addition, the API for immediate viewer update has been removed from V3d_View and Graphic3d_Structure Manager classes (enumerations *Aspect_TypeOfUpdate* and *V3d_TypeOfUpdate*): V3d::SetUpdateMode(), V3d:: UpdateMode(), Graphic3d_StructureManager::UpdateMode().

The argument the Update Mode has been removed from methods Graphic 3d_CView::Display(), Erase(), Update(). Method Graphic 3d_CView::Update() does not redraw the view and does not re-compute structures anymore.

The following Grid management methods within class V3d_Viewer do not implicitly redraw the viewer: ActivateGrid, DeactivateGrid, SetRectangularGridValues, SetCircularGridValues, RectangularGridGraphicValues, CircularGrid← GraphicValues, SetPrivilegedPlane, DisplayPrivilegedPlane.

13.6 Elimination of Quantity_NameOfColor from TKV3d interface classes

The duplicating interface methods accepting *Quantity_NameOfColor* (in addition to methods accepting *Quantity_ Color*) of TKV3d toolkit have been removed. In most cases this change should be transparent, however applications implementing such interface methods should also remove them (compiler will automatically highlight this issue for methods marked with Standard_OVERRIDE keyword).

13.7 Result of Boolean operations on containers

 The result of Boolean operations on arguments of collection types (WIRE/SHELL/COMPSOLID) is now filtered from duplicating containers.

13.8 Other changes

- MMgt_TShared class definition has been removed Standard_Transient should be used instead (MMgt_T←
 Shared is marked as deprecated typedef of Standard_Transient for smooth migration).
- Class GeomPlate_BuildPlateSurface accepts base class Adaptor3d_HCurve (instead of inherited Adaptor3d HCurveOnSurface accepted earlier).
- Types GeomPlate_Array1OfHCurveOnSurface and GeomPlate_HArray1OfHCurveOnSurface have been replaced with GeomPlate_Array1OfHCurve and GeomPlate_HArray1OfHCurve correspondingly (accept base class Adaptor3d HCurve instead of Adaptor3d HCurveOnSurface).
- Enumeration Image_PixMap::ImgFormat, previously declared as nested enumeration within class Image_←
 PixMap, has been moved to global namespace as Image_Format following OCCT coding rules. The enumeration values have suffix Image_Format_ and preserve previous name scheme for easy renaming of old values e.g. Image_PixMap::ImgGray become Image_Format_Gray. Old definitions are preserved as depreacated aliases to the new ones;
- Methods Image_PixMap::PixelColor() and Image_PixMap::SetPixelColor() now take/return Quantity_Color
 — RGBA instead of Quantity_Color/NCollection_Vec4.
- The method BOPAlgo_Builder::Origins() returns BOPCol_DataMapOfShapeListOfShape instead of BOP
 — Col DataMapOfShapeShape.
- The methods BOPDS_DS::IsToSort(const Handle(BOPDS_CommonBlock)&, Standard_Integer&) and BO← PDS_DS::SortPaveBlocks(const Handle(BOPDS_CommonBlock)&) have been removed. The sorting is now performed during the addition of the Pave Blocks into Common Block.
- The methods BOPAlgo_Tools::MakeBlocks() and BOPAlgo_Tools::MakeBlocksCnx() have been replaced with the single template method BOPAlgo_Tools::MakeBlocks(). The chains of connected elements are now stored into the list of list instead of data map.
- The methods BOPAlgo_Tools::FillMap() have been replaced with the single template method BOPAlgo_

 Tools::FillMap().
- Package BVH now uses opencascade::handle instead of NCollection_Handle (for classes BVH_Properties, BVH_Builder, BVH_Tree, BVH_Object). Application code using BVH package directly should be updated accordingly.
- AIS_Shape now computes UV texture coordinates for AIS_Shaded presentation in case if texture mapping is
 enabled within Shaded Attributes. Therefore, redundant class AIS_TexturedShape is now deprecated applications can use AIS_Shape directly (texture mapping should be defined through AIS_Shape::Attributes()).
- Methods for managing active texture within OpenGl_Workspace class (ActiveTexture(), DisableTexture(), EnableTexture()) have been moved to OpenGl_Context::BindTextures().

13.9 BOP - Pairs of interfering indices

- The classes BOPDS_PassKey and BOPDS_PassKeyBoolean are too excessive and not used any more in Boolean Operations. To replace them the new BOPDS_Pair class has been implemented. Thus:
 - The method BOPDS DS::Interferences() now returns the BOPDS MapOfPair;
 - The method BOPDS_Iterator::Value() takes now only two parameters the indices of interfering subshapes.

13.10 Removal of the Draw commands based on old Boolean operations

- The commands *fubl* and *cubl* have been removed. The alternative for these commands are the commands *bfuseblend* and *bcutblend* respectively.
- The command ksection has been removed. The alternative for this command is the command bsection.

13.11 Change of Face/Face intersection in Boolean operations

- Previously, the intersection tolerance for all section curves between pair of faces has been calculated as the
 maximal tolerance among all curves. Now, each curve has its own valid tolerance calculated as the maximal
 deviation of the 3D curve from its 2D curves or surfaces in case there are no 2D curves.
- The methods IntTools_FaceFace::TolReached3d(), IntTools_FaceFace::TolReal() and IntTools_FaceFace::

 TolReached2d() have been removed.
- · Intersection tolerances of the curve can be obtained from the curve itself:
 - IntTools Curve::Tolerance() returns the valid tolerance for the curve;
 - IntTools_Curve::TangentialTolerance() returns the tangential tolerance, which reflects the size of the common between faces.
- 2d tolerance (IntTools_FaceFace::TolReached2d()) has been completely removed from the algorithm as unused.

13.12 Restore OCCT 6.9.1 persistence

The capability of reading / writing files in old format using *Storage_ShapeSchema* functionality from OCCT 6.9.1 has been restored in OCCT 7.2.0.

One can use this functionality in two ways:

- invoke DRAW Test Harness commands fsdread / fsdwrite for shapes;
- call StdStorage class Read / Write functions in custom code.

The code example below demonstrates how to read shapes from a storage driver using StdStorage class.

```
// aDriver should be created and opened for reading
Handle(StdStorage_Data) aData;
// Read data from the driver
// StdStorage::Read creates aData instance automatically if it is null
Storage_Error anError = StdStorage::Read(*aDriver, aData);
if (anError != Storage VSOk)
  // Error processing
// Get root objects
Handle(StdStorage_RootData) aRootData = aData->RootData();
Handle(StdStorage_HSequenceOfRoots) aRoots = aRootData->Roots();
if (!aRoots.IsNull())
  // Iterator over the sequence of root objects
  for (StdStorage_HSequenceOfRoots::Iterator anIt(*aRoots); anIt.More(); anIt.Next())
    Handle(StdStorage_Root)& aRoot = anIt.ChangeValue();
// Get a persistent root's object
    Handle(StdObjMgt_Persistent) aPObject = aRoot->Object();
    if (!aPObject.IsNull())
      Handle(ShapePersistent_TopoDS::HShape) aHShape =
       Handle(ShapePersistent_TopoDS::HShape)::DownCast(aPObject);
      if (aHShape) // Downcast to an expected type to import transient data
        TopoDS Shape aShape = aHShape->Import();
        shapes.Append(aShape);
```

```
}
```

The following code demonstrates how to write shapes in OCCT 7.2.0 using StdStorage class.

```
// Create a file driver
NCollection_Handle<Storage_BaseDriver> aFileDriver(new FSD_File());
// Try to open the file driver for writing
try
  OCC_CATCH_SIGNALS
  PCDM_ReadWriter::Open (*aFileDriver, TCollection_ExtendedString(theFilename), Storage_VSWrite);
catch (Standard Failure& e)
  // Error processing
// Create a storage data instance
Handle(StdStorage_Data) aData = new StdStorage_Data();
// Set an axiliary application name (optional)
aData->HeaderData()->SetApplicationName(TCollection_ExtendedString("Application"));
// Provide a map to track sharing
StdObjMgt_TransientPersistentMap aMap;
// Iterator over a collection of shapes
for (Standard_Integer i = 1; i <= shapes.Length(); ++i)</pre>
  TopoDS Shape aShape = shapes. Value(i);
    Translate a shape to a persistent object
  Handle(ShapePersistent_TopoDS::HShape) aPShape =
    ShapePersistent_TopoDS::Translate(aShape, aMap, ShapePersistent_WithTriangle);
  if (aPShape.IsNull())
    // Error processing
  // Construct a root name
  TCollection_AsciiString aName = TCollection_AsciiString("Shape_") + i;
  // Add a root to storage data
  Handle(StdStorage_Root) aRoot = new StdStorage_Root(aName, aPShape);
  aData->RootData()->AddRoot(aRoot);
// Write storage data to the driver
Storage Error anError = StdStorage::Write(*aFileDriver, aData);
if (anError != Storage_VSOk)
  // Error processing
```

13.13 Change in BRepLib_MakeFace algorithm

Previously, *BRepLib_MakeFace* algorithm changed orientation of the source wire in order to avoid creation of face as a hole (i.e. it is impossible to create the entire face as a hole; the hole can be created in context of another face only). New algorithm does not reverse the wire if it is open. Material of the face for the open wire will be located on the left side from the source wire.

13.14 Change in BRepFill OffsetWire algorithm

From now on, the offset will always be directed to the outer region in case of positive offset value and to the inner region in case of negative offset value. Inner/Outer region for an open wire is defined by the following rule: when we go along the wire (taking into account edges orientation) the outer region will be on the right side, the inner region will be on the left side. In case of a closed wire, the inner region will always be inside the wire (at that, the edges orientation is not taken into account).

13.15 Change in Geom(2d)Adaptor_Curve::IsPeriodic

Since 7.2.0 version, method IsPeriodic() returns the corresponding status of periodicity of the basis curve regardless of closure status of the adaptor curve (see method IsClosed()). Method IsClosed() for adaptor can return false even on periodic curve, in the case if its parametric range is not full period, e.g. for adaptor on circle in range $[0, \pi]$. In previous versions, IsPeriodic() always returned false if IsClosed() returned false.

13.16 Change in algorithm ShapeUpgrade UnifySameDomain

The history of the changing of the initial shape was corrected:

- all shapes created by the algorithm are considered as modified shapes instead of generated ones;
- method Generated was removed and its calls should be replaced by calls of method History()->Modified.

13.17 Changes in STL Reader / Writer

Class RWStl now uses class Poly_Triangulation for storing triangular mesh instead of StlMesh data classes; the latter have been removed.

13.18 Refactoring of the Error/Warning reporting system in Boolean Component

The Error/Warning reporting system of the algorithms in Boolean Component (in all BOPAlgo_* and BRepAlgoA← PI_* algorithms) has been refactored. The methods returning the status of errors and warnings of the algorithms (ErrorStatus() and WarningStatus()) have been removed. Instead use methods HasErrors() and HasWarnings() to check for presence of errors and warnings, respectively. The full list of errors and warnings, with associated data such as problematic sub-shapes, can be obtained by method GetReport().

14 Upgrade to OCCT 7.2.1

14.1 Changes in ShapeUpgrade_UnifySameDomain

The following public methods in the class ShapeUpgrade_UnifySameDomain became protected:

- · UnifyFaces
- · UnifyEdges

The following public method has been removed:

UnifyFacesAndEdges

14.2 Moving BuildPCurveForEdgeOnPlane from BOPTools_AlgoTools2D to BRepLib

The methods BuildPCurveForEdgeOnPlane and BuildPCurveForEdgesOnPlane have been moved from the class BOPTools_AlgoTools2D to the more lower level class BRepLib.

14.3 Removed features

The following obsolete features have been removed:

- · The package BOPCol has been fully removed:
 - BOPCol BaseAllocator is replaced with Handle(NCollection BaseAllocator);
 - BOPCol BoxBndTree is replaced with BOPTools BoxBndTree;
 - BOPCol Box2DBndTree is removed as unused;
 - BOPCol_DataMapOfIntegerInteger is replaced with TColStd_DataMapOfIntegerInteger,
 - BOPCol_DataMapOfIntegerListOfInteger is replaced with TColStd_DataMapOfIntegerListOfInteger,
 - BOPCol_DataMapOfIntegerListOfShape is replaced with TopTools_DataMapOfIntegerListOfShape;
 - BOPCol DataMapOfIntegerMapOfInteger.hxx is removed as unused;
 - BOPCol_DataMapOfIntegerReal is replaced with TColStd_DataMapOfIntegerReal;
 - BOPCol DataMapOfIntegerShape is replaced with TopTools DataMapOfIntegerShape;
 - BOPCol_DataMapOfShapeBox is replaced with TopTools_DataMapOfShapeBox;
 - BOPCol_DataMapOfShapeInteger is replaced with TopTools_DataMapOfShapeInteger,
 - BOPCol DataMapOfShapeListOfShape is replaced with TopTools DataMapOfShapeListOfShape;
 - BOPCol_DataMapOfShapeReal is replaced with TopTools_DataMapOfShapeReal;
 - BOPCol DataMapOfShapeShape is replaced with TopTools DataMapOfShapeShape;
 - BOPCol DataMapOfTransientAddress is removed as unused;
 - BOPCol_IndexedDataMapOfIntegerListOfInteger is removed as unused;
 - BOPCol_IndexedDataMapOfShapeBox is removed as unused;
 - BOPCol_IndexedDataMapOfShapeInteger is removed as unused;
 - BOPCol_IndexedDataMapOfShapeListOfShape is replaced with TopTools_IndexedDataMapOfShape
 ListOfShape;
 - BOPCol IndexedDataMapOfShapeReal is removed as unused;
 - BOPCol_IndexedDataMapOfShapeShape is replaced with TopTools_IndexedDataMapOfShapeShape;
 - BOPCol_IndexedMapOfInteger is replaced with TColStd_IndexedMapOfInteger,
 - BOPCol_IndexedMapOfOrientedShape is replaced with TopTools_IndexedMapOfOrientedShape;

14.3 Removed features 43

- BOPCol_IndexedMapOfShape is replaced with TopTools_IndexedMapOfShape;
- BOPCol_ListOfInteger is replaced with TColStd_ListOfInteger,
- BOPCol ListOfListOfShape is replaced with TopTools ListOfListOfShape;
- BOPCol_ListOfShape is replaced with TopTools_ListOfShape;
- BOPCol_MapOfInteger is replaced with TColStd_MapOfInteger,
- BOPCol_MapOfOrientedShape is replaced with TopTools_MapOfOrientedShape;
- BOPCol_MapOfShape is replaced with TopTools_MapOfShape;
- BOPCol_PListOfInteger is removed as unused;
- BOPCol PInteger is removed as unused
- BOPCol_SequenceOfPnt2d is replaced with TColgp_SequenceOfPnt2d;
- BOPCol SequenceOfReal is replaced with TColStd SequenceOfReal;
- BOPCol_SequenceOfShape is replaced with TopTools_SequenceOfShape;
- BOPCol Parallel is replaced with BOPTools Parallel;
- BOPCol_NCVector is replaced with NCollection_Vector,
- The class BOPDS_PassKey and containers for it have been removed as unused.
- The unused containers from *IntTools* package have been removed:
 - IntTools_DataMapOfShapeAddress is removed as unused;
 - IntTools_IndexedDataMapOfTransientAddress is removed as unused;
- The container BiTgte_DataMapOfShapeBox is replaced with TopTools_DataMapOfShapeBox;
- The class BOPTools has been removed as duplicate of the class TopExp;
- The method BOPAlgo_Builder::Splits() has been removed as excessive. The method BOPAlgo_Builder::
 Images() can be used instead.
- The method BOPTools_AlgoTools::CheckSameGeom() has been removed as excessive. The method BOP← Tools_AlgoTools::AreFacesSameDomain() can be used instead.

15 Upgrade to OCCT 7.3.0

15.1 Light sources

Multiple changes have been applied to lights management within TKV3d and TKOpenGI:

- V3d_Light class is now an alias to Graphic3d_CLight. Graphic3d_CLight is now a Handle class with refactored
 methods for managing light source parameters. Most methods of V3d_Light sub-classes have been preserved
 to simplify porting.
- Obsolete debugging functionality for drawing a light source has been removed from V3d_Light. Methods and
 constructors that take parameters for debug display and do not affect the light definition itself have also been
 removed.
- Light constructors taking *V3d_Viewer* have been marked as deprecated. Use method *AddLight()* of the class *V3d_Viewer* or *V3d_View* to add new light sources to a scene or a single view, respectively.
- The upper limit of 8 light sources has been removed.
- The classes for specific light source types: V3d_AmbientLight, V3d_DirectionalLight, V3d_PositionalLight and V3d_SpotLight have been preserved, but it is now possible to define the light of any type by creating base class Graphic3d_CLight directly. The specific classes only hide unrelated light properties depending on the type of light source.
- It is no more required to call V3d_Viewer::UpdateLights() after modifying the properties of light sources (color, position, etc.)

15.2 Shading Models

Graphic3d_AspectFillArea3d has been extended by a new property *ShadingModel()*, which previously has been defined globally for the entire View.

Previously, a triangle array without normal vertex attributes was implicitly considered as unshaded, but now such array will be shaded using *Graphic3d_TOSM_FACET* model (e.g. by computing per-triangle normals). Therefore, *Graphic3d_TOSM_UNLIT* should be explicitly specified to disable shading of triangles array. Alternatively, a material without reflectance properties can be used to disable shading (as before).

15.3 Custom low-level OpenGL elements

The following API changes should be considered while porting custom *OpenGI Element* objects:

• OpenGI_ShaderManager::BindFaceProgram(), BindLineProgram(), BindMarkerProgram() now take enumeration arguments instead of Boolean flags.

15.4 Changes in BOPAlgo_Section

The public method *BuildSection()* in the class *BOPAlgo_Section* has become protected. The methods *Perform()* or *PerformWithFiller()* should be called for construction of the result of SECTION operation.

15.5 Changes in BRepAdaptor_CompCurve

The method *BRepAdaptor_CompCurve::SetPeriodic* has been eliminated. Since the new version, the method *B*← *RepAdaptor_CompCurve::IsPeriodic()* will always return FALSE. Earlier, it could return TRUE in case if the wire contained only one edge based on a periodic curve.

15.6 Removed features 45

15.6 Removed features

• The methods SetDeflection, SetEpsilonT, SetDiscretize of the class IntTools_EdgeFace have been removed as redundant.

Deprecated functionality V3d_View::Export(), related enumerations Graphic3d_ExportFormat, Graphic3d_←
 SortType as well as optional dependency from gl2ps library have been removed.

15.7 Boolean Operations - Solid Builder algorithm

Previously, the unclassified faces of *BOPAlgo_BuilderSolid* algorithm (i.e. the faces not used for solids creation and located outside of all created solids) were used to form an additional (not closed) solid with INTERNAL orientation. Since the new version, these unclassified faces are no longer added into the resulting solids. Instead, the warning with a list of these faces appears.

The following public methods of the BOPAlgo_BuilderSolid class have been removed as redundant:

- void SetSolid(const TopoDS_Solid& theSolid);
- const TopoDS Solid& Solid() const;

15.8 Boolean Operation classes in BRepAlgo are deprecated

The API classes in the package BRepAlgo providing access to old Boolean operations are marked as deprecated:

- · BRepAlgo Fuse
- · BRepAlgo Common
- BRepAlgo_Cut
- BRepAlgo_Section Corresponding classes from the package BRepAlgoAPI should be used instead.

15.9 Unification of the Error/Warning reporting system of Application Framework

Class *CDM_MessageDriver* and its descendants have been removed; class *Message_Messenger* is used instead in all OCAF packages. By default, messenger returned by *Message::DefaultMessenger()* is used, thus all messages generated by OCAF are directed in the common message gueue of OCCT.

In classes implementing OCAF persistence for custom attributes (those inheriting from *BinMDF_ADriver*, *XmIM DF_ADriver*), uses of method *WriteMessage()* should be replaced by call to method *Send()* of the inherited field *myMessageDriver*. Note that this method takes additional argument indicating the gravity of the message (Trace, Info, Warning, Alarm, or Fail).

Class Message_PrinterOStream can be used instead of CDM_COutMessageDriver to direct all messages to a stream. If custom driver class is used in the application, that class shall be reimplemented inheriting from Message — Printer instead of CDM_MessageDriver. Method Send() should be redefined instead of method Write() of CDM—MessageDriver. To use the custom printer in OCAF, it can be either added to default messenger or set into the custom Message_Messenger object created in the method MessageDriver() of a class inheriting CDF_Application.

16 Upgrade to OCCT 7.4.0

16.1 Changes in BRepPrimAPI_MakeRevol algorithm

Previously the algorithm could create a shape with the same degenerated edge shared between some faces. Now it is prevented. The algorithm creates the different copy of this edge for each face. The method *Generated(...)* has been changed in order to apply restriction to the input shape: input shape can be only of type VERTEX, EDGE, FACE or SOLID. For input shape of another type the method always returns empty list.

16.2 Removed features

- The following methods of the class BRepAlgoAPI_BooleanOperation have been removed as obsolete or replaced:
 - BuilderCanWork can be replaced with IsDone or HasErrors method.
 - FuseEdges removed as obsolete.
 - RefineEdges replaced with new method SimplifyResult.
- The method *ImagesResult* of the class *BOPAlgo_BuilderShape* has been removed as unused. The functionality of this method can be completely replaced by the history methods *Modified* and *IsDeleted*.
- The method *TrackHistory* of the classes *BOPAlgo_RemoveFeatures* and *BRepAlgoAPI_Defeaturing* has been renamed to *SetToFillHistory*.
- The method GetHistory of the class BRepAlgoAPI_Defeaturing has been renamed to History.
- The classes BRepAlgo_BooleanOperations and BRepAlgo_DSAccess have been removed as obsolete. Please use the BRepAlgoAPI * classes to perform Boolean operations.
- BRepAlgo_DataMapOfShapeBoolean has been removed as unused.
- BRepAlgo_DataMapOfShapeInterference has been removed as unused.
- BRepAlgo EdgeConnector has been removed as unused.
- BRepAlgo_SequenceOfSequenceOfInteger has been removed as unused.

16.3 Local Context removal

Previously deprecated Local Context functionality has been removed from AIS package, so that related methods have been removed from AIS_InteractiveContext interface: HasOpenedContext(), HighestIndex(), LocalContext(), LocalSelector(), OpenLocalContext(), CloseLocalContext(), IndexOfCurrentLocal(), CloseAll—Contexts(), ResetOriginalState(), ClearLocalContext(), UseDisplayedObjects(), NotUseDisplayedObjects(), Set—ShapeDecomposition(), SetTemporaryAttributes(), ActivateStandardMode(), DeactivateStandardMode(), Keep—Temporary(), SubIntensityOn(), SubIntensityOff(), ActivatedStandardModes(), IsInLocal(), AddOrRemoveSelected() taking TopoDS_Shape.

A set of deprecated methods previously related to Local Context and now redirecting to other methods has been preserved to simplify porting; they will be removed in next release.

16.4 Changes in behavior of Convert algorithms

Now methods GeomConvert::ConcatG1, GeomConvert::ConcatC1, Geom2dConvert::ConcatG1, Geom2d← Convert::ConcatC1 modify the input argument representing the flag of closedness.

16.5 Changes in selection API and picked point calculation algorithm.

SelectBasics_PickResult structure has been extended, so that it now defines a 3D point on the detected entity in addition to Depth value along picking ray. SelectMgr_SelectingVolumeManager::Overlap() methods have been corrected to fill in SelectBasics_PickResult structure (depth and 3D point) instead of only depth value, so that custom Select3D_SensitiveEntity implementation should be updated accordingly (including Select3D_SensitiveSet subclasses).

16.6 Document format version management improvement.

Previously Document format version restored by *DocumentRetrievalDriver* was propagated using static methods of the corresponding units (like *MDataStd* or *MNaming*) to static variables of these units and after that became accessible to Drivers of these units. Now Document format version is available to drivers via *RelocationTable*. The Relocation table now keeps *HeaderData* of the document and a format version can be extracted in the following way: *theRelocTable.GetHeaderData()->StorageVersion()*. Obsolete methods: *static void SetDocumentVersion (const Standard_Integer DocVersion)* and *static Standard_Integer DocumentVersion()* have been removed from *BinMDataStd*, *BinMNaming*, *XmlMDataStd* and *XmlMNaming*.

16.7 BRepMesh - revision of the data model

The entire structure of *BRepMesh* component has been revised and separated into several logically connected classes

In new version, deflection is controlled more accurately, this may be necessary to tune parameters of call of the BRepMesh algorithm on the application side to obtain the same quality of presentation and/or performance as before

BRepMesh_FastDiscret and BRepMesh_FastDiscretFace classes have been removed.

The following changes have been introduced in the API of BRepMesh_IncrementalMesh, component entry point:

- Due to revised logic, adaptiveMin parameter of the constructor has been removed as meaningless;
- BRepMesh_FastDiscret::Parameters has been moved to a separate structure called IMeshTools_Parameters; the signatures of related methods have been changed correspondingly.
- Interface of BRepMesh_Delaun class has been changed.

Example of usage: Case 1 (explicit parameters):

```
#include <IMeshData_Status.hxx>
#include <IMeshTools Parameters.hxx>
#include <BRepMesh_IncrementalMesh.hxx>
Standard Boolean meshing explicit parameters()
  BRepMesh_IncrementalMesh aMesher (aShape, 0.1, Standard_False, 0.5, Standard_True);
 const Standard_Integer aStatus = aMesher.GetStatusFlags();
  return !aStatus;
Standard_Boolean meshing_new()
  IMeshTools_Parameters aMeshParams;
  aMeshParams.Deflection
                                       = 0.1;
                                       = 0.5;
  aMeshParams.Angle
  aMeshParams.Relative
                                       = Standard_False;
  aMeshParams.InParallel
                                       = Standard_True;
                                       = Precision::Confusion();
  aMeshParams.MinSize
  aMeshParams.InternalVerticesMode
                                       = Standard True:
  aMeshParams.ControlSurfaceDeflection = Standard True;
  BRepMesh_IncrementalMesh aMesher (aShape, aMeshParams);
  const Standard_Integer aStatus = aMesher.GetStatusFlags();
  return !aStatus;
```

16.8 Changes in API of Chamfer algorithms

Some public methods of the class BRepFilletAPI_MakeChamfer are released from excess arguments:

- method Add for symmetric chamfer now takes only 2 arguments: distance and edge;
- method GetDistAngle now takes only 3 arguments: index of contour, distance and angle.

16.9 Aspects unification

Fill Area, Line and Marker aspects (classes *Graphic3d_AspectFillArea3d*, *Graphic3d_AspectLine3d*, *Graphic3d_AspectSad_AspectSad_AspectSad_AspectSad_AspectSad_AspectSad_Aspects* providing a single state for rendering primitives of any type. The old per-primitive type aspect classes have been preserved as sub-classes of *Graphic3d_Aspects* with default values close to the previous behavior. All aspects except Graphic3d_AspectFillArea3d define Graphic3d_TOSM_UNLIT shading model.

The previous approach with dedicated aspects per primitive type was handy in simplified case, but lead to confusion otherwise. In fact, drawing points or lines with lighting applied is a valid use case, but only *Graphic3d_AspectFill*—*Area3d* previously defined necessary material properties.

As aspects for different primitive types have been merged, Graphic3d_Group does no more provide per-type aspect properties. Existing code relying on old behavior and putting interleaved per-type aspects into single Graphic3d_
Group should be updated. For example, the following pseudo-code will not work anymore, because all SetGroup

PrimitivesAspect calls will setup the same property:

```
Handle(Graphic3d_Group) aGroup = thePrs->NewGroup();
aGroup->SetGroupPrimitivesAspect (myDrawer->ShadingAspect()->Aspect());
aGroup->SetGroupPrimitivesAspect (myDrawer->LineAspect()->Aspect()); //!< overrides previous aspect
Handle(Graphic3d_ArrayOfSegments) aLines = new Graphic3d_ArrayOfSegments (2);
Handle(Graphic3d_ArrayOfTriangles) aTris = new Graphic3d_ArrayOfTriangles (3);
aGroup->AddPrimitiveArray (aLines); //!< both arrays will use the same aspect
aGroup->AddPrimitiveArray (aTris);
```

To solve the problem, the code should be modified to either put primitives into dedicated groups (preferred approach), or using *SetPrimitivesAspect* in proper order:

```
Handle(Graphic3d_Group) aGroup = thePrs->NewGroup();

aGroup->SetGroupPrimitivesAspect (myDrawer->ShadingAspect()->Aspect());
Handle(Graphic3d_ArrayOfTriangles) aTris = new Graphic3d_ArrayOfTriangles (3);
aGroup->AddPrimitiveArray (aTris);

Handle(Graphic3d_ArrayOfSegments) aLines = new Graphic3d_ArrayOfSegments (2);
aGroup->SetPrimitivesAspect (myDrawer->LineAspect()->Aspect()); //!< next array will use the new aspect aGroup->AddPrimitiveArray (aLines);
```

16.10 Material definition

Decomposition of Ambient, Diffuse, Specular and Emissive properties has been eliminated within $Graphic3d_$ ← MaterialAspect definition. As result, the following methods of $Graphic3d_MaterialAspect$ class have been removed ←: SetReflectionMode(), SetReflectionModeOn(), Ambient(), Diffuse(), Emissive(), Specular(), SetAmbient(), Set← Diffuse(), SetSpecular(), SetEmissive().

Previously, computation of final value required the following code:

New code looks like this:

```
Graphic3d_MaterialAspect theMaterial; Quantity_Color theInteriorColor;
Graphic3d_Vec3 anAmbient = theMaterial.AmbientColor();
if (theMaterial.MaterialType (Graphic3d_MATERIAL_ASPECT)) { anAmbient *= (Graphic3d_Vec3 )theInteriorColor;
}
```

Existing code should be updated to:

- Replace Graphic3d_MaterialAspect::SetReflectionModeOff() with setting black color; SetReflectionModeOn()
 calls can be simply removed. R.g. theMaterial.SetAmbientColor(Quantity_NOC_BLACK).
- Replace Graphic3d_MaterialAspect::Ambient(), SetAmbient(), Diffuse(), SetDiffuse(), Specular(), Set
 — Specular(), Emissive(), SetEmissive() with methods working with pre-multiplied color. E.g. theMaterial.Set
 — AmbientColor(Graphic3d Vec3 (1.0f, 0.0f, 0.0f) * 0.2f).
- Avoid using Graphic3d_MaterialAspect::Color() and SetColor() with non-physical materials (Graphic3d_M
 ATERIAL_ASPECT). These materials do not include color definition, because it is taken from Graphic3d
 _Aspects::InteriorColor() this has not been changed. However, previously it was possible storing the color with SetColor() call and then fetching it with Color() by application code (the rendering ignored this value); now SetColor() explicitly ignores call for Graphic3d_MATERIAL_ASPECT materials and Color() returns Diffuse
 Color() multiplication coefficients.

16.11 Changes in Graphic3d_Text and OpenGI_Text API

Parameters of *Text* in *Graphic3d_Group* are moved into a new *Graphic3d_Text* class. *AddText* of *Graphic3d_Group* should be used instead of the previous *Text*.

The previous code:

should be replaced by the new code:

```
Handle(Graphic3d_Text) aText = new Graphic3d_Text (theAspect->Height());
aText->SetText (theText.ToExtString());
aText->SetPosition (theAttachmentPoint);
aText->SetHorizontalAlignment (theAspect->HorizontalJustification());
aText->SetVerticalAlignment (theAspect->VerticalJustification());
theGroup->AddText (aText);
```

OpenGI_Text contains Graphic3d_Text field.

OpenGI_TextParam struct is removed. Constructor and Init of OpenGI_Text with OpenGI_TextParam are also removed. Instead of using them, change OpenGI Text.

Please, note, that after modifying OpenGI_Text, Reset of OpenGI_Text should be called.

FormatParams of OpenGI_Text is replaced by Text.

16.12 Presentation invalidation

Historically AIS_InteractiveObject provided two independent mechanisms invalidating presentation (asking presentation manager to recompute specific display mode or all modes):

1. AIS_InteractiveObject::SetToUpdate(), marking existing presentation for update. This is main invalidation API, which is expected to be followed by AIS_InteractiveContext::Update() call.

16.13 Interior styles 50

2. AIS_InteractiveObject::myToRecomputeModes + myRecomputeEveryPrs. This is auxiliary invalidation API, used internally by AIS_InteractiveContext::SetColor()/UnsetColor() and similar modification methods.

The latter one has been removed to avoid confusion and unexpected behavior. In addition, two methods $AIS \leftarrow _InteractiveObject::Update()$ have been deprecated in favor of new $AIS_InteractiveObject::UpdatePresentations()$ recomputing only invalidated presentations.

Custom presentations implementing interface methods *AIS_InteractiveObject::SetColor()* and others should be revised to use *AIS_InteractiveObject::SetToUpdate()* or updating presentation without recomputation (see *AIS_ InteractiveObject::SynchronizeAspects()* and *AIS_InteractiveObject::replaceAspects()*).

16.13 Interior styles

- Aspect_IS_HOLLOW is now an alias to Aspect_IS_EMPTY and does not implicitly enables drawing mesh
 edges anymore. Specify Graphic3d_AspectFillArea3d::SetDrawEdges(true) with Graphic3d_AspectFill
 Area3d::SetInteriorStyle(Aspect_IS_EMPTY) to get previous behavior of Aspect_IS_HOLLOW style.
- Aspect_IS_HIDDENLINE does not implicitly enables drawing mesh edges anymore. Specify Graphic3d_

 AspectFillArea3d::SetDrawEdges(true) with Graphic3d_AspectFillArea3d::SetInteriorStyle(Aspect_IS_HID← DENLINE) to get previous behavior of Aspect_IS_HIDDENLINE style.

16.14 PrsMgr and SelectMgr hierarchy clean up

Proxy classes *Prs3d_Presentation*, *PrsMgr_ModedPresentation* and *PrsMgr_Prs* have been removed. Code iterating through the list of low-level structures AIS_InteractiveObject::Presentations() should be updated to access PrsMgr_Presentation directly. Forward declarations of *Prs3d_Presentation* should be corrected, since it is now a typedef to *Graphic3d_Structure*.

Proxy classes *SelectBasics_SensitiveEntity* and *SelectBasics_EntityOwner* have been removed - *Select3D_ SensitiveEntity* and *SelectMgr EntityOwner* should be now used directly instead.

16.15 Polygon offset defaults

Graphic3d_PolygonOffset default constructor has been corrected to define Units=1 instead of Units=0. Default polygon offset settings Mode=Aspect_POM_Fill + Factor=1 + Units=1 are intended to push triangulation (Shaded presentation) a little bit behind of lines (Wireframe and Face Edges) for reducing z-fighting effect of Shaded+← Wireframe combination. The change in defaults (Units changed from 0 to 1) is intended to cover scenario when camera direction is perpendicular to model plane (like 2D view).

Application observing unexpected visual difference on this change should consider customizing this property within AIS_InteractiveContext default attributes or on per-presentation basis via <code>Graphic3d_Aspects::SetPolygonOffset()</code> methods.

16.16 Adding ZLayers in given position

Interface of insertion ZLayer in the viewer has been improved with ability to insert new layer before or after existing one. Previously undocumented behavior of V3d_Viewer::AddZlayer() method has been corrected to insert new layer before Graphic3d_ZLayerId_Top. Applications might need revising their custom layers creation code and specify precisely their order with new methods V3d Viewer::InsertLayerBefore() and V3d Viewer::InsertLayerAfter().

16.17 Modified enumerations

Applications using integer values of the following enumerations in persistence should be corrected as these enumerations have been modified:

Name
AIS_TypeOfAttribute
Aspect_InteriorStyle
Font_FontAspect

16.18 Custom defines within env.bat

env.bat produced by Visual Studio project generator genproj.bat has been modified so that CSF_DEFINES% variable is reset to initial state. Custom building environment relying on old behavior and setting extra macros within CSF_DEFINES% before env.bat should be updated to either modify custom.bat or setup new variable CSF_DEF←INES EXTRA% instead.

16.19 Switching Boolean Operations algorithm to use BVH tree instead of UB tree

Since OCCT 7.4.0 Boolean Operations algorithm uses BVH tree instead of UBTree to find the pairs of entities with interfering bounding boxes. The following API changes have been made:

- BOPTools_BoxBndTree and BOPTools_BoxBndTreeSelector have been removed. Use the BOPTools_Box
 —
 Tree and BOPTools_BoxTreeSelector instead.
- BOPTools BoxSelector::SetBox() method now accepts the BVH Box instead of Bnd Box.
- Methods BOPTools_BoxSelector::Reject and BOPTools_BoxSelector::Accept have been removed as unused.
- The RunParallel flag has been removed from the list of parameters of BOPAlgo_Tools::IntersectVertices method. Earlier, it performed selection from the UB tree in parallel mode. Now all interfering pairs are found in one pass, using pair traverse of the same BVH tree.

16.20 Standard_Stream.hxx no more has "using std::" statements

Standard_Stream.hxx header, commonly included by other OCCT header files, does no more add entities from std namespace related to streams (like std::cout, std::istream and others) into global namespace. The application code relying on this matter should be updated to either specify std namespace explicitly (like std::cout) or add "using std::" statements locally.