Synchronization II

- Lock implementation
 - o interrupts
 - > spinlock
 - yield()
 - queues
 - futex
- cache coherency
- Lock Free Data Structures
 - <u>Lockless patterns: more read-modify-write</u>
 <u>operations [LWN.net]</u>
 - C11 Atomic operations library
 - Atomic operations library
 - memory order cppreference.com
 - slides: Memory barriers in C
 - linux kernel memory barriers: Linux kernel documentation on memory barriers An introduction to lockless algorithms [LWN.net] https://www.scs.stanford.edu/23wi-cs21 2/sched/readings/why-memory-barriers.pdf
- RCU
- Deadlock
- Transactions

Can both critical sections run?

```
int flag1 = 0, flag2 = 0;
void p1(void *ignored) {
   flag1 = 1;
   if (!flag2) {
       critical section 1();
void p2(void *ignored) {
   flag2 = 1;
   if (!flag1) {
       critical_section_2();
int main() {
   tid id = thread create(p1, NULL);
  p2();
  thread join(id);
```

https://www.scs.stanford.edu/23wi-cs212/notes/concurrency.pdf

Can use () be called with value 0?

```
int data = 0;
int ready = 0;
void p1(void *ignored) {
   data = 2000;
   ready = 1;
void p2(void *ignored) {
   while (!ready)
   use (data) ;
int main() { ... }
```

If p1–3 run concurrently, can use be called with value 0?

```
int a = 0;
int b = 0;
void p1(void *ignored) { a = 1; }
void p2 (void *ignored) {
   if (a == 1) b = 1;
void p3(void *ignored) {
   if (b == 1) use(a);
```

Answers

We do not know!

- It depends on what machine you use
- If a system provides sequential consistency, then answers all No
- But not all hardware provides sequential consistency

Why doesn't all hardware support sequential consistency?

Sequential consistency(SC): The result of execution is as if all operations were executed in some sequential order, and the operations of each processor occurred in the order specified by the program. – Lamport

https://www.scs.stanford.edu/23wi-cs212/notes/concurrency.pdf

SC prevents hardware optimizations

Complicates write buffers

- E.g., read flagn before flag(3 - n) written through in Program A

Can't re-order overlapping write operations

- Concurrent writes to different memory modules
- Coalescing writes to same cache line

Complicates non-blocking reads

- E.g., speculatively prefetch data in Program B

Makes cache coherence more expensive

- Must delay write completion until invalidation/update (Program B)
- Can't allow overlapping updates if no globally visible order (Program C)

SC prevents hardware optimizations

Code motion

Caching value in register

- Collapse multiple loads/stores of same address into one operation

Common subexpression elimination

- Could cause memory location to be read fewer times

Loop blocking

- Re-arrange loops for better cache performance

Software pipelining

- Move instructions across iterations of a loop to overlap instruction latency with branch cost

x86 consistency [intel 3a, §8.2]

Intel® 64 and IA-32 Architectures Software Developer's Manual, Volume 3A: System Programming Guide, Part 1

x86 supports multiple consistency/caching models

- Memory Type Range Registers (MTRR) specify consistency for ranges of physical memory (e.g., frame buffer)
- Page Attribute Table (PAT) allows control for each 4K page

Choices include:

- WB: Write-back caching (the default)
- WT: Write-through caching (all writes go to memory)
- UC: Uncacheable (for device memory)
- WC: Write-combining weak consistency & no caching (used for frame buffers, when sending a lot of data to GPU)

Some instructions have weaker consistency

- String instructions (written cache-lines can be re-ordered)
- Special "non-temporal" store instructions (movnt*) that bypass cache and can be re-ordered with respect to other writes

- Exception: A read could finish before an earlier write to a different

location

- Which of Programs A, B, C might be affected?

Old x86s (e.g, 486, Pentium 1) had almost SC

Assuming sequential consistency

Peterson's solution

```
int flag[2] = {false, false}; /*flag[i] indicates that Pi wants to enter critical section (it's
ready) */
int turn = 0; /*indicates which process has the priority (lock) to enter in its CS*/
   // P0
                                                   // P1
                                                   while (true) {
   while (true) {
      // wants to enter
                                                      // wants to enter
      flag[0] = true;
                                                      flag[1] = true;
      turn = 1;
                                                      turn = 0;
      while (flag[1] && turn == 1) {
                                                      while (flag[0] && turn == 0) {
      /* critical section */
                                                      /* critical section */
      flag[0] = false;
                                                      flag[1] = false;
                                                      /* remainder section */
      /* remainder section */
                                           This will not work in modern architectures:
```

For multithreaded programs, reordering of the statements cause inconsistency!

example

https://preshing.com/20120515/memory-reordering-caught-in-the-act/

Peterson expensive, only works for 2 processes

- Can generalize to n, but for some fixed n

Must adapt to machine memory model if not SC

- If you need machine-specific barriers anyway, might as well take advantage of other instructions helpful for synchronization

Want to insulate programmer from implementing synchronization primitives

Libraries for User Apps

Pthread and other libraries

In System Programming and OOP courses, we have seen that there are libraries that allow us to write multithreaded programs.

Thread packages typically provide mutexes:

```
void mutex_init (mutex_t *m, ...);
void mutex_lock (mutex_t *m);
int mutex_trylock (mutex_t *m);
void mutex_unlock (mutex_t *m);
```

 Only one thread acquires m at a time, others wait

Pthread library (Posix thread library) is such an example that provides an API for multithreaded user programs. In the pthread library, we have seen two different synchronization tools: mutex and condition variables.

Mutexes

```
//m1 is a mutex variable
mutex_lock(m1);//acquire lock
critical_section
mutex_unlock(m1); //release lock
```

- You can consider lock as "a mic among participants that controls who has the right to speak",
 - o i.e whoever has the mic (m1) has the right to speak (in our case do ops on the memory shared among the participants).

Condition Variables (Monitors = cond var + mutex)

```
//two threads: e.g. producer/consumer
//Condition variables: c1 is for one condition, c2 is for another condition
//Locks: m1 to control the access to the critical section.
  //1st thread
                                   // 2nd thread
                                   mutex_lock(m1);
  mutex lock(m1);
  /*critical section entry*/
                                   /*critical section entry*/
  while(need_to_wait_1 ){
                                   while(need to wait 2){
      cond wait(c1, m1);
                                        cond wait(c2, m1);
                                   };
  /*critical section exit*/
                                   /*critical section exit*/
  cond signal(c2) //or
                                   cond signal(c1) //or
                                   broadcast
  broadcast
  mutex unlock(m1);
                                   mutex unlock(m1);
```

Monitors = cond var + mutex

Always acquire lock before accessing shared data

- Use condition variables to wait inside critical section
- → Three Operations: Wait(), Signal(), and Broadcast()
- Monitors represent the logic of the program
- Wait if necessary
- Signal when change something so any waiting threads can proceed

```
//1st thread
                               // 2nd thread
mutex lock(m1);
                               mutex lock(m1);
/*critical section entry*/
                               /*critical section entry*/
while(need_to_wait_1 ){
                               while(need to wait 2){
    cond wait(c1, m1);
                                   cond wait(c2, m1);
                               };
/*critical section exit*/
                               /*critical section exit*/
cond signal(c2) //or
                               cond signal(c1) //or
                               broadcast
broadcast
mutex unlock(m1);
                               mutex unlock(m1);
```

Semaphores

```
sem_t s;
sem_init(&s, 0, 10);
//a thread that wants to occupy a chair
sem_wait(&s); //down the value of s by 1
//After done with the chair
sem_post(&s); //up the value of s by 1
```

- If the return value of sem_wait is negative the thread waits as done in the mutex locks.
 - This happens when the value of s before sem_wait is 0.
- sem_wait and sem_post can be called from different processes/threads.

In Linux kernel

Pthread API is implemented by using NPTL (Native POSIX Thread Library - Wikipedia). It uses the system calls such as clone and futex, and atomic operations to create a library in glibc (The GNU C Library) (see pthread_create.c source code [glibc/nptl/pthread_create.c] - Codebrowser).

There are also alternative/different pthread implementations for Linux.

In the kernel space, similarly to processes, you can also spawn threads by using kernel threads(kthreads). There is also similar lock mechanism you can use(see locking — The Linux Kernel documentation)

Lock implementation

both user/kernel need synchronization!

Goals:

- Correctness
 - Mutual exclusion: only one thread in critical section at a time
 - Progress (deadlock-free): if several simultaneous requests, must allow one to proceed
 - Bounded wait (starvation-free): must eventually allow each waiting thread to enter
- Fairness: each thread waits for same amount of time
 - Also, threads acquire locks in the same order as requested
- Performance: CPU time is used efficiently

- Locks are variables in shared memory
 - Two main operations: acquire() and release()
 - Also called lock() and unlock()

- To check if locked,
 - read variable and check value

- To acquire,
 - write "locked" value to variable
 - Should only do this if already unlocked
 - If already locked, keep reading value until unlock observed

- To release,
 - write "unlocked" value to variable

Implementing as a straightforward data structure?

- ★ Fine, so long as we avoid data races on the mutex itself
- → Need lower-level lock 1k for mutual exclusion
 - ◆ Internally, mutex_* functions bracket code with lock(&mutex->lk) . . . unlock(&mutex->lk)
- → Otherwise, data races! (E.g., two threads manipulating waiters

How to implement lower_level_lock_t lk;?

 Could use Peterson's algorithm, but typically a bad idea (too slow and don't know maximum number of threads) Two approaches

Disable interrupts
 a. works only in kernel

2. Spinlocks

Naïve use of Interrupt Enable/Disable

- How can we build multi-instruction atomic operations?
 - Recall: dispatcher gets control in two ways.
 - Internal: Thread does something to relinquish the CPU
 - External: Interrupts cause dispatcher to take CPU
 - On a uniprocessor, can avoid context-switching by:
 - Avoiding internal events (although virtual memory tricky)
 - Preventing external events by disabling interrupts

Consequently, naïve Implementation of locks:

```
LockAcquire {
  disable interrupts;
}
LockRelease {
  enable interrupts;
}
```

- Problems with this approach:
 - O Can't let user do this!

```
LockAcquire();
while(true) {;}
```



- Real-Time system—no guarantees on timing!
 - Critical Sections might be arbitrarily long
- O What happens with I/O or other important events?
 - "Reactor about to meltdown. Help?"

Better Implementation of Locks by Disabling Interrupts

 Key idea: maintain a lock variable and impose mutual exclusion only during operations on that variable

```
int value = FREE;
Acquire() {
                                        Release() {
    disable interrupts;
                                             disable interrupts;
     if (value == BUSY) {
                                             if (anyone on wait queue) {
                                                 take thread off wait queue
         put thread on wait queue;
                                                 Place on ready queue;
         Go to sleep();
                                             } else {
         // Enable interrupts?
                                                 value = FREE;
     } else {
         value = BUSY;
                                             enable interrupts;
    enable interrupts;
```

Really only works in kernel – why?

Why do we need to disable interrupts at all?

- Avoid interruption between checking and setting lock value.
- Prevent switching to other thread that might be trying to acquire lock!
- Otherwise two threads could think that they both have lock!

```
Acquire() {
    disable interrupts;
    if (value == BUSY) {
        put thread on wait queue;
        Go to sleep();
        // Enable interrupts?
    } else {
        value = BUSY;
    }
    enable interrupts;
}

Critical
Section
```

- Note: unlike previous solution, this "meta-"critical section is very short
 - User of lock can take as long as they like in their own critical section: doesn't impact global machine behavior
 - Critical interrupts taken in time!

What about re-enabling ints when going to sleep?

- Before putting thread on the wait queue?
 - Release can check the queue and not wake up thread
- After putting the thread on the wait queue?
 - Release puts the thread on the ready queue, but the thread still thinks it needs to go to sleep
 - Misses wakeup and still holds lock (deadlock!)


```
Acquire() {
    disable interrupts;
    if (value == BUSY) {
         put thread on wait queue;
         Go to sleep();
      else {
         value = BUSY;
    enable interrupts;
```

Want to put it after sleep(). But – how?

How to Re-enable After Sleep()?

In scheduler, since interrupts are disabled when you call sleep:

- Responsibility of the next thread to re-enable ints
- When the sleeping thread wakes up, returns to acquire and re-enables interrupts



Problems with interrupt based locks

Can't give lock implementation to users

Doesn't work well on multiprocessor

 Disabling interrupts on all processors requires messages and would be very time consuming

But sometimes most efficient solution for uniprocessors

Only for apps with n: 1 threads (1 kthread)

Typical setup: periodic timer signal caught by thread scheduler

Have per-thread "do not interrupt" (DNI) bit

lock (lk): sets thread's DNI bit

If timer interrupt arrives

- Check interrupted thread's DNI bit
- If DNI clear, preempt current thread
- If DNI set, set "interrupted" (I) bit & resume current thread

unlock (lk): clears DNI bit and checks I bit - If I bit is set, immediately yields the CPU

Spinlocks

Idea is to implement something like this:

```
bool lock = false; // shared variable
void acquire(bool *lock) {
   while (*lock) /* wait */
    ;
   *lock = true;
}
void release(bool *lock) { *lock = false; }
```

This does not work!

Checking and writing of the lock value in acquire() need to happen atomically.

Spinlocks

Most CPUs support atomic read-[modify-]write

- Test and Set
- Fetch and Add
- Compare and Swap (CAS)
- Load Linked / Store Conditional

Hardware is responsible for implementing this correctly

```
Example: int test_and_set (int *lockp);
```

- atomically sets *lockp = 1
- and returns old value

Special instruction

- → no way to implement in portable C99
- → C11 supports with explicit atomic_flag_test_and_set function
- → C11 Atomic operations library

Synchronization on x86

```
x86 xchg instruction, exchanges reg with mem
test and set :
    movl 4(% esp), % edx # % edx = lockp
    movl $1, % eax # % eax = 1
    xchgl % eax, (% edx) # swap(% eax, *lockp)
    ret
// Implementation in x86 :
int TAS(volatile int *addr, int newval) {
   int result = newval;
   asm volatile("lock; xchg %0, %1"
                 : "+m" (*addr), "=r" (result)
                 : "1" (newval)
                 : "cc");
   return result;
```

CPU locks memory system around read and write

- xchgl always acts like it has implicit lock prefix
- Prevents other uses of the bus (e.g., DMA)

Usually runs at memory bus speed, not CPU speed

Much slower than cached read/buffered write

recall: using in critical section problem

```
volatile int lock = 0;

void critical() {
    while (test_and_set(&lock) == 1);/*spinlock*/

    /* critical section */

    lock = 0; /* release lock when finished CS*
}
```

Use spinlocks to implement mutex's lower_level_lock_t

```
typedef struct mutex {
    bool is_locked;
    thread_id_t owner;
    thread_list_t waiters;
    lower_level_lock_t lk;
};

#define lock(lockp) while (test_and_set (lockp))
    #define trylock(lockp) (test_and_set (lockp) == 0)
    #define unlock(lockp) *lockp = 0
```

Can you use spinlocks instead of mutexes?

- → Wastes CPU, especially if thread holding lock not running
- → Mutex functions have short C.S., less likely to be preempted
- → On multiprocessor, sometimes good to spin for a bit, then yield

Problem: Busy-Waiting for Lock

- Positives for this solution
 - Machine can receive interrupts
 - User code can use this lock
 - Works on a multiprocessor

Negatives

- This is very inefficient as thread will consume cycles waiting
- Waiting thread may take cycles away from thread holding lock (no one wins!)
- Priority Inversion: If busy-waiting thread has higher priority than thread holding lock ⇒ no progress!
- Priority Inversion problem with original Martian rover
- For higher-level synchronization primitives (e.g. semaphores or monitors),
 waiting thread may wait for an arbitrary long time!
 - Thus even if busy-waiting was OK for locks, definitely not ok for other primitives
 - Homework/exam solutions should avoid busy-waiting!



Kernel Synchronization

Should kernel use locks or disable interrupts?

Old UNIX had 1 CPU, non-preemptive threads, no mutexes

```
- Interface designed for single CPU, so count++ etc. not data race
```

```
- . . . Unless memory shared with an interrupt handler

int x = splhigh (); /* bsd Disable interrupts, preempt_disable() in Linux */

/* touch data shared with interrupt handler . . . */

splx (x); /* bsd Restore previous state, preempt enable in Linux */
```

Used arbitrary pointers like condition variables

```
int [t]sleep (void *ident, int priority, ...);
put thread to sleep; will wake up at priority (~cond_wait)
```

```
int wakeup (void *ident);
wake up all threads sleeping on ident (~cond broadcast)
```

Nowadays, should design for multiprocessors

- Even if first version of OS is for uniprocessor
- Someday may want multiple CPUs and need preemptive threads
- That's why Pintos uses sleeping locks (sleeping locks means mutexes, as opposed to spinlocks)

Multiprocessor performance needs fine-grained locks

Want to be able to call into the kernel on multiple CPUs

If kernel has locks, should it ever disable interrupts?

If kernel has locks, should it ever disable interrupts?

- Yes! Can't sleep in interrupt handler, so can't wait for lock
- So even modern OSes have support for disabling interrupts
- Often uses DNI trick when cheaper than masking interrupts in hardware

Improving spinlock performance

Kernel support for userspace sleeping locks

Cache Coherence

Recall: Where are we going with synchronization?

Programs	Shared Programs
Higher-le vel API	Locks Semaphores Monitors Send/Receive
Hardware	Load/Store Disable Ints Test&Set Compare&Swap

- We are going to implement various higher-level synchronization primitives using atomic operations
 - Everything is pretty painful if only atomic primitives are load and store
 - Need to provide primitives useful at user-level

Evaluating our lock Implementation with TAS


```
typedef struct lock t {
   int flag;
} lock t;
void init(lock t *lock) { lock->flag = 0; }
void acquire(lock t *lock) {
   while (test and set(&lock->flag, 1) == 1)
       ; // spin-wait (do nothing)
void release(lock t *lock) { lock->flag = 0; }
```

Evaluating our lock Implementation with TAS

- 1) Mutual exclusion: only one thread in critical section at a time
- 2) Progress (deadlock-free): if several simultaneous requests, must allow one to proceed
- 3) Bounded wait: must eventually allow each waiting thread to enter
- 4) Fairness: threads acquire lock in the order of requesting
- 5) Performance: CPU time is used efficiently

3, 4, 5 may NOT be satisfied in practice!

our spinlock is not fair!



- Scheduler is independent of locks/ dillock
- Busy-Waiting: thread consumes cycles while waiting
 - For multiprocessors: every test&set() is a write, which makes value ping-pong around in cache (using lots of network BW)

Fairness and Bounded Wait

Use Ticket Locks

Idea: reserve each thread's turn to use a lock.

Each thread spins until their turn.

Use new atomic primitive: fetch-and-add

```
// Semantic
int fetch and add(int *ptr) {
   int old = *ptr;
   *ptr = old + 1;
   return old;
// example implementation
// GCC's built-in atomic function
sync fetch and add(ptr, 1)
```

ticket-lock implementation

```
typedef struct {
   int ticket;
   int turn;
} lock t;
void lock init(lock t *lock) {
   lock->ticket = 0;
   lock - turn = 0;
void acquire(lock t *lock) {
   int myturn = fetch and add(&lock->ticket);
   while (lock->turn != myturn)
       ; // spin
void release(lock t *lock) {
    lock->turn += 1;
```

Busy-waiting(spinning) performance

Good when...


- many CPUs
- locks held a short time
- advantage: avoid context switch

Awful when...

- one CPU
- locks held a long time
- disadvantage: spinning is wasteful

CPU Scheduler Is Ignorant

busy-waiting (spinning) locks



CPU scheduler may run **B** instead of **A** even though **B** is waiting for **A**

Ticket Lock with <u>vield() (see Linus Torvalds comment)</u>

```
typedef struct {
   int ticket;
   int turn;
} lock_t;


void acquire(lock_t *lock) {
   int myturn = fetch_and_add(&lock->ticket);
   while (lock->turn != myturn) sched_yield();
}

void release(lock_t *lock) { lock->turn += 1; }
```

Wasted time

yielding instead of spinning

- Without yield: O(threads × time_slice)
- With yield: O(threads × context_switch_time)



https://compas.cs.stonybrook.edu/~nhonarmand/courses/ta17/cse306/slides/11-locks.pdf

Evaluating Ticket Lock

5) Performance: CPU time is used efficiently

→ 5 (even with yielding, too much overhead)

So even with yield, spinning is slow with high thread contention

Next improvement: instead of spinning, block and put thread on a wait queue

Blocking Locks with queues

acquire() removes waiting threads from run queue using special system call

release() returns waiting threads to run queue using special system call

Better Locks using test&set

- Can we build test&set locks without busy-waiting?
 - Mostly. Idea: only busy-wait to atomically check lock value



```
acquire(int *thelock) {
    // Short busy-wait time
    while (test_and_set(guard));
    if (*thelock == BUSY) {
        put thread on wait queue;
        go to sleep() & guard = 0;
        // guard == 0 on wakeup!
    } else {
        *thelock = BUSY;
        guard = 0;
    }
}
```

```
release(int *thelock) {
    // Short busy-wait time
    while (test_and_set(guard));
    if anyone on wait queue {
        take thread off wait queue
        Place on ready queue;
    } else {
        *thelock = FREE;
    }
    guard = 0;
```

- Note: sleep has to be sure to reset the guard variable
 - Why can't we do it just before or just after the sleep?

Kernel support for sleeping locks

Sleeping locks must interact with scheduler

- For processes or kernel threads, must go into kernel (expensive)
- Common case is you can acquire lock—how to optimize?
- Idea: never enter kernel for uncontested lock

futex abstraction solves the problem

- Ask kernel to sleep only if memory location hasn't changed
- void futex (int *uaddr, FUTEX_WAIT, int val. . .);
 - Go to sleep only if *uaddr == val
 - Extra arguments allow timeouts, etc.
- void futex (int *uaddr, FUTEX WAKE, int val. . .);
 - Wake up at most val threads sleeping on uaddr
- uaddr is translated down to offset in VM object
 - So works on memory mapped file at different virtual addresses in different processes

Recap: Locks using interrupts

```
acquire(int *thelock) {
                                                   // Short busy-wait time
                                                   disable interrupts;
                       acquire(int *thelock) {
                                                   if (*thelock == 1) {
                         disable interrupts;
int mylock=0;
                                                     put thread on wait-queue;
                                                     go to sleep() //??
                                                   } else {
acquire(&mylock)
                                                     *thelock = 1;
                                                     enable interrupts;
 critical section:
release (&mylock);
                       release(int *thelock)
                                                 release(int *thelock) {
                                                   // Short busy-wait time
                         enable interrupts;
                                                   disable interrupts;
                                                   if anyone on wait queue {
                                                     take thread off wait-queue
                     If one thread in critical
                                                     Place on ready queue;
                     section, no other activity
                                                   } else {
                                                     *thelock = 0;
                     (including OS) can run!
                                                   enable interrupts;
                     Lock argument not
```

https://inst.eecs.berkeley.edu/~cs162/sp22/static/lectures/8.pdf

Recap: Locks using test & set

```
int quard = 0; // global!
                                                 acquire(int *thelock) {
                                                   // Short busy-wait time
                                                   while(test&set(quard));
                    int mylock = 0;
                                                   if (*thelock == 1) {
                    acquire(int *thelock) {
                                                     put thread on wait-queue;
int mylock=0;
                      while(test&set(thelock))
                                                     go to sleep() & guard = 0;
                                                       // guard == 0 on wakeup
acquire (&mylock
                                                   } else {
                                                     *thelock = 1;
 critical section;
                                                     quard = 0;
release (&mylock);
                    release(int *thelock) {
                                               release(int *thelock) {
                      *thelock = 0;
                                                  // Short busy-wait time
                                                  while (test&set(guard));
                                                  if anyone on wait queue {
                                                    take thread off wait-queue
                                                    Place on ready queue;
                     Threads waiting to enter
                                                  } else {
                                                    *thelock = 0;
                          critical section
                                                  guard = 0;
                             busy-wait
```

Linux futex: Fast Userspace Mutex

uaddr points to a 32-bit value in user space
futex_op

- O FUTEX_WAIT if val == *uaddr sleep till FUTEX_WAIT
 - *Atomic* check that condition still holds after we disable interrupts (in kernel!)
- FUTEX_WAKE wake up at most val waiting threads
- O FUTEX_FD, FUTEX_WAKE_OP, FUTEX_CMP_REQUEUE: More interesting operations!
 timeout
 - o ptr to a *timespec* structure that specifies a timeout for the op
- Interface to the kernel sleep() functionality!
 - Let thread put themselves to sleep conditionally!
- futex is not exposed in libc; it is used within the implementation of pthreads
 - Can be used to implement locks, semaphores, monitors, etc...

Example: First try: T&S and futex

- Properties:
 - Sleep interface by using futex no busywaiting
- No overhead to acquire lock
 - O Good!
- Every unlock has to call kernel to potentially wake someone up even if none
 - O Doesn't quite give us no-kernel crossings when uncontended...!

Example: Try #2: T&S and futex

```
bool maybe_waiters = false;
int mylock = 0; // Interface:
acquire(&mylock,&maybe_waiters);
                                               release(int*thelock, bool *maybe) {
release(&mylock,&maybe_waiters);
                                                    thelock = 0;
                                                    if (*maybe) {
acquire(int *thelock, bool *maybe) {
                                                         *maybe = false;
    while (test&set(thelock)) {
                                                        // Try to wake up someone
         // Sleep, since lock busy!
                                                        futex(&value, FUTEX WAKE, 1);
         *maybe = true;
         futex(thelock, FUTEX_WAIT, 1);
         // Make sure other sleepers not stuck
         *maybe = true;
```

- This is syscall-free in the uncontended case
 - O Temporarily falls back to syscalls if multiple waiters, or concurrent acquire/release
- But it can be considerably optimized!
 - See "<u>Futexes are Tricky</u>" by Ulrich Drepper

Try #3: Better, using more atomics

- Much better: Three (3) states:
 - UNLOCKED: No one has lock
 - LOCKED: One thread has lock
 - CONTESTED: Possibly more than one (with someone sleeping)
- Clean interface!
- Lock grabbed cleanly by either
 - o compare_and_swap()
 - First swap()
- No overhead if uncontested!
- Could build semaphores in a similar way!


no one has to be woken up, and so no syscalls at all.

```
typedef enum { UNLOCKED,LOCKED,CONTESTED } Lock;
Lock mylock = UNLOCKED; // Interface:
acquire(&mylock);
release(&mylock);
acquire(Lock *thelock) {
    // If unlocked, grab lock!
    if (compare&swap(thelock,UNLOCKED,LOCKED))
         return;
    // Keep trying to grab lock, sleep in futex
    while (swap(mylock,CONTESTED) != UNLOCKED))
         // Sleep unless someone releases heard!
         futex(thelock, FUTEX_WAIT, CONTESTED);
release(Lock *thelock) {
    // If someone sleeping,
    if (swap(thelock,UNLOCKED) == CONTESTED)
         futex(thelock,FUTEX_WAKE,1);
```

• See also futex demo.c in futex(2) - Linux manual page

Cache coherence

https://www.scs.stanford.edu/23wi-c s212/notes/synchronization1.pdf



For detailed lecture see:

https://booksite.elsevier.com/9780123973375/powerpoint/c hapter_07.ppt

Important memory system properties

Coherence – concerns accesses to a single memory location

- There is a total order on all updates
- Must obey program order if access from only one CPU
- There is bounded latency before everyone sees a write

Consistency – concerns ordering across memory locations

- Even with coherence, different CPUs can see the same write happen at different times
- Sequential consistency is what matches our intuition

(As if operations from all CPUs interleaved on one CPU)

- Many architectures offer weaker consistency
- Yet well-defined weaker consistency can still be sufficient to implement thread API

Multicore cache coherence

Performance requires caches

- Divided into chunks of bytes called lines (e.g., 64 bytes)
- Caches create an opportunity for cores to disagree about memory

Bus-based approaches

- "Snoopy" protocols, each CPU listens to memory bus
- Use write-through and invalidate when you see a write bits
- Bus-based schemes limit scalability

Modern CPUs use networks (e.g., hypertransport, infinity fabric, QPI, UPI)

- CPUs pass each other messages about cache lines

MESI coherence protocol

Modified (M)

Exactly one cache has a valid copy

The copy in the current cache is *dirty* - (needs to be written back to memory)

Must invalidate all copies in other caches before entering this state

Exclusive (E)

Same as modified except the copy in the current cache is *clean* (it matches main memory).

Shared (S)

One or more caches and memory have a valid copy

Invalid (I)

Indicates that this cache line is invalid (unused).

Owned (for enhanced "MOESI" protocol)

has exclusive right to change, others can read but not write

	M	Е	S	1
М	X	X	X	1
Е	X	X	X	1
S	×	x	1	1
1	1	1	1	1

Core and Bus Actions

Actions performed by CPU core

- Read
- Write
- Evict (modified? must write back)

Transactions on bus (or interconnect)

- Read: without intent to modify, data can come from memory or another cache
- Read-exclusive: with intent to modify, must invalidate all other

cache copies

- Writeback: contents put on bus and memory is updated

cc-NUMA

Old machines used dance hall architectures

- Any CPU can "dance with" any memory equally

An alternative: Non-Uniform Memory Access (NUMA)

- Each CPU has fast access to some "close" memory
- Slower to access memory that is farther away
- Use a directory to keep track of who is caching what

Originally for esoteric machines with many CPUs

- But AMD and then intel integrated memory controller into CPU
- Faster to access memory controlled by the local socket (or even local die in a multi-chip module)

cc-NUMA = cache-coherent NUMA

- Rarely see non-cache-coherent NUMA (BBN Butterfly 1, Cray T3D)

Real World Coherence Costs

See [David] for a great reference. Xeon results:

- 3 cycle L1, 11 cycle L2, 44 cycle LLC, 355 cycle local RAM

If another core in same socket holds line in modified state:

- load: 109 cycles (LLC + 65)

- store: 115 cycles (LLC + 71)

- atomic CAS: 120 cycles (LLC + 76)

LLC: non-inclusive last-level cache

If a core in a different socket holds line in modified state:

- NUMA load: 289 cycles

- NUMA store: 320 cycles

- NUMA atomic CAS: 324 cycles

But only a partial picture

- Could be faster because of out-of-order execution
- Could be slower if interconnect contention or multiple hops

NUMA and spinlocks

Test-and-set spinlock has several advantages

- Simple to implement and understand
- One memory location for arbitrarily many CPUs

But also has disadvantages

- Lots of traffic over memory interconnect (especially w. > 1 spinner)
- Not necessarily fair (lacks bounded waiting)
- Even less fair on a NUMA machine

- → Idea 1: Avoid spinlocks altogether (lock free data structures)
- → Idea 2: Reduce interconnect traffic with better spinlocks
 - Design lock that spins only on local memory
 - Also gives better fairness

Useful macros

https://en.cppreference.com/w/c/atomic/memory_order

Atomic compare and swap: CAS (mem, old, new)

- If *mem == old,
 - then swap *mem ↔ new
 - and return true,
- else false
- On x86, can implement using locked cmpxchg instruction
- In C11, use atomic_compare_exchange_strong

(note: C atomics version sets old = *mem if *mem != old)

Atomic swap: XCHG (mem, new)

- Atomically exchanges *mem
 ←new
- Implement w. C11 atomic_exchange, or xchg on x86

Atomic fetch and add: FADD (mem, val)

- Atomically sets *mem += val and returns old value of *mem
- Implement w. C11 atomic_fetch_add, lock add on x86

Atomic fetch and subtract: FSUB (mem, val)

Note: atomics return previous value (like x++, not ++x)

All behave like sequentially consistent fences

 In C11, weaker _explicit versions take a memory_order argument

MCS Lock

Build a better spinlock

- Lock designed by <u>Mellor-Crummey</u> and <u>Scott</u>
- Goal: reduce bus traffic on cc machines, improve fairness

Each CPU has a quode structure in local memory

```
typedef struct qnode {
    _Atomic(struct qnode *) next;
    atomic_bool locked;
} qnode;
```

- Local can mean local memory in NUMA machine
- Or just its own cache line that gets cached in exclusive mode

While waiting, spin on your local locked flag

A lock is a qnode pointer: typedef _Atomic (qnode *) lock;

- Construct list of CPUs holding or waiting for lock
- lock itself points to tail of list list (or NULL when unlocked)

MCS acquire

```
If unlocked, L is NULL
    If locked, no waiters, L is owner's qnode
    If waiters, *L is tail of waiter list:
acquire(lock *L, qnode *I) {
   I->next = NULL;
   qnode *predecessor = I;
   XCHG(*L, predecessor);
   if (predecessor != NULL) {
        I->locked = true:
        predecessor->next = I;
        while (I->locked)
```

```
*L

owner 

waiter 

waiter
```

MCS acquire

```
If unlocked, L is NULL
    If locked, no waiters, L is owner's qnode
    If waiters, *L is tail of waiter list:
acquire(lock *L, qnode *I) {
                                                                         predecessor
   I->next = NULL;
                                      *L
   qnode *predecessor = I;
                                          next
                                                      next
                                                                 next
   XCHG(*L, predecessor);
                                             waiter
                                                        waiter
                                                                    ► NULL
                                                                                      ►NUL.L
                                   owner
   if (predecessor != NULL) {
        I->locked = true;
        predecessor->next = I;
        while (I->locked)
```

MCS acquire

```
If unlocked, L is NULL
    If locked, no waiters, L is owner's qnode
    If waiters, *L is tail of waiter list:
acquire(lock *L, qnode *I) {
   I->next = NULL;
   qnode *predecessor = I;
   XCHG(*L, predecessor);
   if (predecessor != NULL) {
        I->locked = true:
        predecessor->next = I;
        while (I->locked)
```

```
owner waiter waiter NULL *I NULL
```


MCS acquire

```
If unlocked, L is NULL
    If locked, no waiters, L is owner's qnode
    If waiters, *L is tail of waiter list:
acquire(lock *L, qnode *I) {
   I->next = NULL;
   qnode *predecessor = I;
   XCHG(*L, predecessor);
   if (predecessor != NULL) {
        I->locked = true;
        predecessor->next = I;
        while (I->locked)
                                                    predecessor
                                  *L
                                                  next
                                                              next
                                          waiter
                                                     waiter
                                                                                    -NUL.L
                                owner
```

MCS Release with CAS

```
release(lock *L, qnode *I) {
   if (!I->next)
       if (CAS(*L, I, NULL)) return;
   while (!I->next)
      ;
   I->next->locked = false;
}
If I->next NULL and *L == I
```

No one else is waiting for lock, OK to set
 *L = NULL



MCS Release with CAS

```
release(lock *L, qnode *I) {
   if (!I->next)
      if (CAS(*L, I, NULL)) return;
   while (!I->next)
   ;
   I->next->locked = false;
}
If I->next NULL and *L != I
```


- Another thread is in the middle of acquire
- Just wait for I->next to be non-NULL



MCS Release with CAS

```
release(lock *L, qnode *I) {
   if (!I->next)
      if (CAS(*L, I, NULL)) return;
   while (!I->next)
   ;
   I->next->locked = false;
}
If I->next is non-NULL
```

• I->next oldest waiter, wake up with I->next->locked = false



MCS Release without CAS

```
release(lock *L, gnode *I) {
    if (I->next)
         I->next->locked = false;
    else {
         qnode *old tail = NULL;
         XCHG(*L, old tail);
         if (old tail == I) return;
         /* old tail != I? CAS would have failed, so undo XCHG */
         qnode *userper = old tail;
         XCHG(*L, userper);
         while (I->next == NULL)
         if (userper) /* someone changed *L between 2 XCHGs */
             userper->next = I->next;
         else
             I->next->locked = false;
https://www.scs.stanford.edu/23wi-cs212/notes/svnchronization2.pdf
```

- 1. Atomically swap NULL into *L
 - If old value of *L was I, no waite and we are done
- 2. Atomically swap old *L value back into *L
 - If *L unchanged, same effect a CAS

Otherwise,

- Some "userper" attempted to acquire lock between 1 and 2
- Because *L was NULL, the userper succeeded (May be followed by zero or more waite
- Graft old list of waiters on to er of new last waiter (Sacrifice sm amount of fairness, but still saf

Lock "Free" Multithreading:

Non-blocking synchronization

source:

https://www.scs.stanford.edu/23wi-cs212/notes/synchronization 1.pdf

Atomic operations

Read-modify-write (RMW) atomic instructions

Memory barriers (see memory-barriers.txt)

In Linux kernel (mb(), smp_mb(), etc.),

assembly instruction asm volatile
("mfence" : : "memory")


C11 atomic library, Linux system calls

RCU

Acquire/release semantics

Passing information reliably between threads about a variable.

- Ideal in producer/consumer type situations (pairing!!).
- After an ACQUIRE on a given variable, all memory accesses preceding any prior RELEASE on that same variable are guaranteed to be visible.
- All accesses of all previous critical sections for that variable are guaranteed to have completed.
- C++11's memory_order_acquire, memory_order_release and memory_order_relaxed (see <u>Memory barriers in C</u>).



smp_store_release(lock-val, 0) <-> cmpxchg_acquire(lock-val, 0, LOCKED)

Recall: Producer/Consumer

```
/* PRODUCER */
for (;;) {
   item *nextProduced = produce item();
   mutex lock(&mutex);
   while (count == BUF SIZE)
     cond wait(&nonfull, &mutex);
   buffer[in] = nextProduced;
   in = (in + 1) % BUF SIZE;
   count++;
   cond signal(&nonempty);
   mutex unlock(&mutex);
```

```
/* CONSUMER */
for (;;) {
  mutex lock(&mutex);
  while (count == 0)
       cond wait(&nonempty, &mutex);
  nextConsumed = buffer[out];
  out = (out + 1) % BUF SIZE;
   count--;
   cond signal(&nonfull);
  mutex unlock(&mutex);
   consume item(nextConsumed);
```

Eliminating Locks

One use of locks is to coordinate multiple updates of single piece of state

How to remove locks here?

Factor state so that each variable only has a single writer

In Producer/Consumer example, Assume one producer, one consumer

Why do we need count variable, written by both?

To detect buffer full/empty

Have producer write in, consumer write out (both _Atomic)

- Use in/out to detect buffer state
- But note next example busy-waits, which is less good

Lock-free producer/consumer

```
atomic_int in, out;

void producer(void *ignored) {

for (;;) {

    item *nextProduced = produce_item();

    while (((in + 1) % BUF_SIZE) == out)

        thread_yield();

        thread_yield();

    buffer[in] = nextProduced;

    in = (in + 1) % BUF_SIZE;

    }
}
void consumer(void *ignored) {

    while (in == out)

    nextConsumed = buffer[out];

    out = (out + 1) % BUF_SIZE;

    consume_item(nextConsumed);

    }
}
```

Note fences not needed because no relaxed atomics example busy-waits, which is less good

Version with relaxed atomics

```
void producer(void *ignored) {
   for (;;) {
       item *nextProduced = produce item();
       int slot = atomic load explicit(&in, memory order relaxed);
       int next = (slot + 1) % BUF SIZE;
       while (atomic load explicit(&out, memory order acquire) ==
              next) // Could you use relaxed? ^^^^^^
           thread yield();
       buffer[slot] = nextProduced;
       atomic store explicit(&in, next, memory order release);
void consumer(void *ignored) {
   // Use memory order acquire to load in (for latest buffer[myin])
   // Use memory_order_release to store out
```

Non-blocking synchronization

Design algorithm to avoid critical sections

- Any threads can make progress if other threads are preempted
- Which wouldn't be the case if preempted thread held a lock

Requires that hardware provide the right kind of atomics

- Simple test-and-set is insufficient
- Atomic compare and swap is good:
 - CAS (mem, old, new) If *mem == old, then swap *mem←→new and return true, else false

Can implement many common data structures

Stacks, queues, even hash tables

Can implement any algorithm on right hardware

- Need operation such as atomic compare and swap (has property called consensus number =
 ∞ [Herlihy])
- Entire kernels have been written without locks [Greenwald]

Example non-blocking stack


```
struct item {
    /* data */
    _Atomic(struct item *) next;
};

typedef _Atomic(struct item *) stack_t;

void atomic_push(stack_t *stack, item *i) {
    do {
        i->next = *stack;
    } while (!CAS(stack, i->next, i));
}
```

```
item *atomic_pop(stack_t *stack) {
   item *i;
   do {
      i = *stack;
   } while (!CAS(stack, i, i->next));
   return i;
}
```

Wait-free stack issues



"ABA" race in pop if other thread pops, re-pushes i

- Can be solved by
 - o <u>counters</u>
 - or hazard pointers to delay re-use

"Benign" races

Could also eliminate locks by having race conditions

- Maybe you think you care more about speed than correctness
 - ++hits: /* each time someone accesses web site */
- Maybe you think you can get away with the race
 - o not really: https://www.cs.umd.edu/~pugh/java/memoryModel/DoubleCheckedLocking.html

```
if (!initialized) {
    lock(m);
    if (!initialized) {
        initialize();
        atomic_thread_fence(memory_order_release); /* why? */
        initialized = 1;
    }
    unlock(m);    But don't do this [Vyukov], [Boehm]! Not benign at all
```

- Again, UB really bad! Like user-after free or array overflow bad
- If needed for efficiency, use relaxed-memory-order atomics https://www.scs.stanford.edu/23wi-cs212/notes/synchronization1.pdf

Read Copy Update(RCU)

[McKenney, see also slides Read-Copy Update (RCU), What is RCU, Fundamentally? [LWN.net], What is RCU? -- "Read, Copy, Update" — The Linux Kernel documentation

- achieves scalability improvements by allowing reads to occur concurrently with updates.
- supports concurrency between
 - o a single updater
 - and multiple readers.

The basic idea behind RCU is to split updates into "removal" and "reclamation" phases

- the removal phase runs concurrently with readers
- the typical RCU update sequence goes something like the following:
 - Remove pointers to a data structure, so that subsequent readers cannot gain a reference to it.
 - Wait for all previous readers to complete their RCU read-side critical sections (lightweight synchronization).
 - we can separate reclamation phase into another thread
 - At this point, there cannot be any readers who hold references to the data structure, so it now may safely be reclaimed (e.g., kfree()d).

Read-copy update

Some data is read way more often than written

- Routing tables consulted for each forwarded packet
- Data maps in system with 100+ disks (updated on disk failure)

Optimize for the common case of reading without lock

- E.g., global variable: Atomic(routing table *) rt;
- use without lock

```
#define RELAXED(var) atomic load explicit(&(var), memory order relaxed)
    /* ... */
    route = lookup(RELAXED(rt), destination);
Update by making copy, swapping pointer
    /* update mutex held here, serializing updates */
    routing table *newrt = copy routing table(rt);
    update routing table(newrt);
    atomic store explicit(&rt, newrt, memory order release);
```

Is RCU really safe?

Consider the use of global rt with no fences:

lookup(RELAXED(rt), route);

Could a CPU read new pointer but then old contents of *rt?

Yes on alpha, No on all other existing architectures

When can you free memory of old routing table?

- When you are guaranteed no one is using it—how to determine?
 - for more info see <u>Read-Copy Update (RCU)</u>

Deadlock problem

```
mutex_t m1, m2;

void p1(void *ignored) {
    lock(m1);
    lock(m2);
    /* critical section */
    unlock(m2);
    unlock(m2);
    unlock(m1);
}
```

This program can cease to make progress – how? Can you have deadlock w/o mutexes?

Deadlock conditions

1. Limited access (mutual exclusion):

- Resource can only be shared with finite users

2. No preemption:

- Once resource granted, cannot be taken away

3. Multiple independent requests (hold and wait):

- Don't ask all at once (wait for next resource while holding current one)

4. Circularity in graph of requests

All of 1–4 necessary for deadlock to occur

Two approaches to dealing with deadlock:

- Pro-active: prevention

- Reactive: detection + corrective action

Prevent by eliminating one condition

1. Limited access (mutual exclusion):

- Resource can only be shared with finite users

2. No preemption:

- Once resource granted, cannot be taken away

3. Multiple independent requests (hold and wait):


- Don't ask all at once (wait for next resource while holding current one)

4. Circularity in graph of requests

- Single lock for entire system: (problems?)
- Partial ordering of resources (next)

Detecting deadlocks

- Static approaches (hard)
- Dynamically, program grinds to a halt
 - Threads package can diagnose by keeping track of locks held:



Resource-Allocation Graph Corresponding wait-for graph https://www.scs.stanford.edu/23wi-cs212/notes/synchronization2.pdf

Fixing and debugging deadlocks

Reboot system / restart application

Examine hung process with debugger

Threads package can deduce partial order

- For each lock acquired, order with other locks held
- If cycle occurs, abort with error
- Detects potential deadlocks even if they do not occur

Or use transactions. . .

- Another paradigm for handling concurrency
- Often provided by databases, but some OSes use them

Transactions

A transaction is a collection of the properties

- Atomicity all or none of actions happen
- Consistency T leaves data in valid state
- Isolation T's actions all appear to happen before or after every
- other transaction
- Durability T's effects will survive reboots

ACID a set of properties of <u>database transactions</u> intended to guarantee data validity despite errors, power failures, and other mishaps

Transactions typically executed concurrently

- But isolation means must appear not to
- Must roll-back transactions that use others' state
- Means you have to record all changes to undo them

- ★ When deadlock detected just abort a transaction
 - Breaks the dependency cycle

Transactional memory

Some modern processors support transactional memory

- ★ a promising alternative to lock-based synchronization mechanisms
 - Non-blocking

Transactional Synchronization Extensions (TSX) [intel1§16]

- xbegin abort handler begins a transaction
- xend commit a transaction
- xabort \$code abort transaction with 8-bit code
- Note: nested transactions okay (also xtest tests if in transaction)

During transaction, processor tracks accessed memory

- Keeps read-set and write-set of cache lines
- Nothing gets written back to memory during transaction
- Transaction aborts (at xend or earlier) if any conflicts
- Otherwise, all dirty cache lines are "written" atomically
- (in practice switch to non-transactional M state of MESI)

TM system ensure atomicity by detecting and resolving any conflict arising between concurrent transactions

https://en.wikipedia.org/wiki/Transactional_memory#Available_implementations

Using transactional memory

Idea: Use to get "free" fine-grained locking on a hash table

- E.g., concurrent inserts that don't touch same buckets are okay
 - Automatic Mutual Exclusion method

Can also use to poll for one of many asynchronous events

- Start transaction
- Fill cache with values to which you want to see changes
- Loop until a write causes your transaction to abort

Note: Transactions are never guaranteed to commit

Hardware lock elision (HLE)

concurrently executes lock critical sections as hardware transactions, but fallbacks to the original sequential lock fallback path when some hardware transaction fails.

- Begin a transaction when you acquire lock
- Other CPUs won't see lock acquired, can also enter critical section
- Okay not to have mutual exclusion when no memory conflicts!
- On conflict, abort and restart without transaction, thereby visibly acquiring lock (and aborting other concurrent transactions)

Intel support:

- Use xacquire prefix before xchgl (used for test and set)
- Use xrelease prefix before movl that releases lock
- Prefixes chosen to be noops on older CPUs (binary compatibility)

Hash table example:

- Use xacquire xchgl in table-wide test-and-set spinlock
- Works correctly on older CPUs (with coarse-grained lock)
- Allows safe concurrent accesses on newer CPUs!