#### **Condition Variables**


Mythili Vutukuru CSE, IIT Bombay

### Wait and signal mechanisms for threads

- Locks allow one type of synchronization between threads mutual exclusion when accessing critical sections
- Another common requirement in multi-threaded applications waiting for events and signaling when event occurs
  - E.g., Thread T2 wants to run only after T1 has finished some task (T1→T2)
- Naive solution: T2 keeps checking periodically if T1 is done
  - Wastes CPU cycles, inefficient
  - Need a new synchronization primitive to wait for an event


#### Condition variables

- Pthread library provides special variables called condition variables (CV)
  - A thread calls wait function on a CV, it is blocked and gets added to a list of threads waiting on that CV
  - Another thread calls signal on a CV, one of the waiting threads gets ready to run again, will be scheduled in the future (no immediate context switch)
- Example: we want T2 to run only after T1 does its work (T1→T2)
  - T1 does its work and calls signal
  - T2 checks if work is done, and calls wait if work is not done




## Atomicity in wait and signal (1)

- Checking condition and waiting must be atomic, deadlock otherwise
  - Thread T2 checks condition is false, context switch just before blocking
  - Meanwhile T1 makes condition true, calls signal. But signal doesn't wake up anyone (none sleeping yet)
  - T2 resumes, goes to sleep forever (no one will signal again)
- This is called missed wakeup problem: how to fix?



# Atomicity in wait and signal (2)

- Solution: use a lock/mutex to protect atomicity of sleeping
  - T2 holds a lock, checks condition, calls wait
  - Lock released only after T2 is added to list of waiting processes (ensures atomicity of checking condition and sleeping)
  - T1 acquires **same** lock before calling signal, ensuring that signal cannot happen in between checking condition and waiting
  - Pthread CV implementation releases lock during wait, reacquires on wakeup



### Example: parent waits for child

```
int done = 0;
   pthread mutex t m = PTHREAD MUTEX INITIALIZER;
    pthread_cond_t c = PTHREAD_COND_INITIALIZER;
   void thr_exit() {
        Pthread_mutex_lock(&m);
        done = 1;
        Pthread_cond_signal(&c);
        Pthread_mutex_unlock(&m);
10
11
   void *child(void *arg) (
12
        printf("child\n");
        thr_exit();
14
        return NULL;
   1
16
17
    void thr_join() {
        Pthread_mutex_lock(&m);
        while (done == 0)
20
            Pthread_cond_wait(&c, &m);
        Pthread_mutex_unlock(&m);
22
23
24
    int main(int argc, char *argv[]) {
        printf("parent: begin\n");
26
27
        pthread_t p;
28
        Pthread_create(&p, NULL, child, NULL);
29
        thr_join();
        printf("parent: end\n");
31
        return 0;
```

Image credit: OSTEP

Figure 30.3: Parent Waiting For Child: Use A Condition Variable

## Guidelines for using condition variables

- Use the same lock for wait and signal (maybe for other variables too)
- Before calling wait, confirm that the condition is indeed false
  - T2 must check "done" variable before calling wait (what if T1 has already run?)
- Signal broadcast wakes up all threads while signal wakes up any one
- Good habit to check condition with "while" loop and not "if"
  - To avoid corner cases of thread being woken up even when condition not true (may be an issue with some implementations)

```
if(condition)
  wait(condvar)
//small chance that condition may be false when wait returns
while(condition)
  wait(condvar)
//condition guaranteed to be true since we check in while-loop
```

## Example: Producer-consumer problem

- Producer and consumer threads, sharing data via a buffer of bounded size
  - Producers produce items, add into a shared buffer
  - Consumers consume item from shared buffer
- What kind of coordination is needed between threads?
  - Producer thread produces and places items into buffer, waits if the buffer is full ->
    Consumer signals after making space in the buffer
  - Consumer thread consumes items from buffer, waits if the buffer is empty → Producer signals after producing items



## Example: Multi-threaded server

- Master thread accepts requests and puts them in a queue
- Worker threads fetch requests from this queue and process them




Image credit: CSAPP

# Example: Producer-consumer problem

- Solution using condition variables
  - Mutex/lock used while modifying shared buffer
  - Two CVs: one for producers to wait, and one for consumers to wait

//Producer
lock(mutex)
if(no free space in buffer)
wait(cv\_producer, mutex)
produce item, add to buffer
signal(cv\_consumer)
unlock(mutex)

//Consumer
lock(mutex)

if(no items in buffer)
wait(cv\_consumer, mutex)
consume item from buffer
signal(cv\_producer)
unlock(mutex)

## Producer/Consumer with 2 CVs

```
cond_t empty, fill;
   mutex_t mutex;
3
    void *producer(void *arg) {
        int i;
5
        for (i = 0; i < loops; i++) {
            Pthread mutex lock (&mutex);
            while (count == MAX)
                 Pthread_cond_wait(&empty, &mutex);
9
            put(i);
10
            Pthread cond signal (&fill);
11
            Pthread mutex unlock (&mutex);
12
13
14
15
    void *consumer(void *arg) {
16
        int i;
17
        for (i = 0; i < loops; i++) {
18
            Pthread mutex lock (&mutex);
19
            while (count == 0)
20
                 Pthread_cond_wait(&fill, &mutex);
21
            int tmp = get();
22
            Pthread cond signal (&empty);
23
            Pthread mutex unlock (&mutex);
24
            printf("%d\n", tmp);
25
```

Image credit: OSTEP

## Example: Batched processing

- Example scenario: two kinds of threads in an application
  - Request threads, each containing an application request
  - Batch processor thread processes N requests at a time in a batch
- What kind of synchronization do we need?
  - Batch processing thread must wait until N requests arrive, then start batch
  - Request thread must wait until batch starts, then get processed and finish
- Example: suppose Covid-19 vaccination vial has 10 doses. Nurse waits for 10 patients to arrive, then opens the vial and vaccinates all 10

### Example: Batched processing

- Solution using two CVs: one for requests to wait, one for batch processor to wait
  - Other integer and Boolean variables, mutex/lock for atomicity

```
//Request thread
lock(mutex)
count++
if(count == N)
signal(cv_batch_processor)
while(not batch_started)
wait(cv_request, mutex)
unlock(mutex)

//Batch processor thread
lock(mutex)
while(count < N)
- wait(cv_batch_processor, mutex)
batch_started = true
signal_broadcast(cv_request)
unlock(mutex)
```

#### Example: Batched processing

- What is wrong with this solution?
  - Nth request thread calls wait before invoking signal to wake up batch processor
  - Batch processor never wakes up, all threads will sleep forever
  - Before you sleep, ensure that the signaling code can run in future

```
//Request thread
lock(mutex)
count++
while(not batch_started)
  wait(cv_request, mutex)
if(count == N)
  signal(cv_batch_processor)
unlock(mutex)
```


```
//Batch processor thread
lock(mutex)
while(count < N)
  wait(cv_batch_processor, mutex)
batch_started = true
signal_broadcast(cv_request)
unlock(mutex)</pre>
```

# Synchronization patterns using CVs

- Many examples in the practice problems
  - Scenario describing multiple threads/entities and how they should interact and coordinate with each other
  - Toy examples modelled after real world application design patterns
- How to write code with correct synchronization
  - Identify when each entity should wait and write the suitable waiting code
  - For each wait, figure out how the signaling will happen and write the code
  - Ensure that signaling path in the code is not blocked in any way, e.g., signal others first before calling wait and going to sleep
  - Update all extra variables (counts, flags) in the solution correctly
  - Run through your code in a few different scenarios and different order of execution of threads to convince yourself that it works correctly

#### Watch out for deadlocks

- Deadlock: threads are stuck in blocked state without making progress
- Example: thread sleeps by calling wait on CV, no other thread calls signal, so thread sleeps forever
- Example: circular wait when acquiring multiple locks
  - T1 acquires LockA and LockB, T2 acquires LockB and LockA
  - T1 acquires LockA, T2 acquires LockB, each is waiting for second lock
  - Deadlock if executions interleave in some ways
- Techniques to avoid deadlocks
  - Acquire locks in same order across all threads of process
  - When sleeping, ensure someone will wake you up!



LockA LockB

LockB LockA

T2

## Sleep and wakeup in xv6 (1)

- xv6 does not have userspace threads, only single threaded processes
- But multiple processes may be in kernel mode on different CPU
  - Uses locks to protect access to shared kernel data structures
- OS also needs a mechanism to let processes sleep (e.g., when process makes blocking disk read syscall) and wakeup when some events occur (e.g., disk has raised interrupt and data is ready)
- Process P1 in kernel mode calls sleep to give up CPU, gets blocked until event
- Another process P2 (in kernel mode) wakes up P1 when the event occurs

## Sleep and wakeup in xv6 (2)

- A process P1 that wishes to block and give up CPU calls "sleep"
  - Example: process reads a block from disk, must block until disk read completes
  - Read syscall → sleep → sched() to give up CPU
- Another process P2 calls "wakeup" when event to unblock P1 occurs
  - P2 calls wakeup → marks P1 as runnable, no context switch immediately
  - Example: disk interrupt occurred when P2 is running, P2 runs interrupt handler, which will call wakeup
- P1 will be scheduled at a later time, will resume at sched(), return
- Spinlock protects atomicity of sleep: P1 calls sleep with some spinlock L held, P2 calls wakeup with same spinlock L held

# Sleep and wakeup in xv6 (3)

- How does P2 know which process to wake up?
- When P1 sleeps, it sets a channel (void \* chan) in its struct proc
  - Arguments to sleep: channel, spinlock to protect atomicity of sleep
- P2 calls wakeup on same channel
  - Arguments to wakeup: channel (lock must be held)
- Channel = any value known to both P1 and P2
  - Example: channel value for disk read can be address of disk block

#### Example: wait and exit

 If wait called in parent while children are running, parent calls sleep and gives up CPU (channel is parent struct proc pts, lock is ptable.lock)

```
// Wait for children to exit. (See wakeup1 call in proc_exit.)
sleep(curproc, &ptable.lock);
```


• In exit, child acquires ptable.lock, wakes up parent using its channel

```
2650  // Parent might be sleeping in wait().
2651  wakeup1(curproc->parent);
```

- Why is terminated process memory cleaned up by parent?
  - When a process calls exit, kernel stack, page table etc are in use, all this memory cannot be cleared until terminated process has been taken off the CPU

## Example: pipes in xv6 (1)

- xv6 provides anonymous pipes for IPC between parent and child processes
- Example: Parent P and child C share anonymous pipe
- Child C writes into pipe, parent P reads from pipe
- One of P or C closes read end, other closes write end



```
//userspace code

int fd[2]
pipe(fd) //syscall to create pipe

int ret = fork()

if(ret == 0) {//child
    close(fd[0]) //close read end
    write(fd[1], message, ..)
}
else {//parent
    close(fd[1]) //close write end
    read(fd[0], message, ..)
}
```

# Example: pipes in xv6 (2)

- Internal implementation inside kernel
  - Common shared buffer, protected by a spinlock
  - Write system call stores data in shared buffer
  - Read system call returns data from shared buffer
  - Variables nread and nwrite indicate number of bytes read/written in buffer

```
6762 struct pipe {
6763    struct spinlock lock;
6764    char data[PIPESIZE];
6765    uint nread;    // number of bytes read
6766    uint nwrite;    // number of bytes written
6767    int readopen;    // read fd is still open
6768    int writeopen;    // write fd is still open
6769 };
```

# Example: pipes in xv6 (3)

- Implementation of pipe read and write system calls uses sleep/wakeup
- Pipe reader sleeps if pipe is empty, pipe writer wakes it up
- Pipe writer sleeps if pipe is full, pipe reader wakes it up
- Channel for sleep/wakeup = address of pipe structure variables

```
6829 int
6830 pipewrite(struct pipe *p, char *addr, int n)
6831 {
6832
       int i;
6833
6834
       acquire(&p->lock);
                                        pipe is full
       for(i = 0; i < n; i++){
6835
6836
         while(p->nwrite == p->nread + PIPESIZE){
6837
           if(p->readopen == 0 || myproc()->killed){
6838
              release(&p->lock);
6839
             return -1;
6840
                                writer's channel for sleep is
6841
           wakeup(&p->nread);
                                address of nwrite variable
6842
           sleep(&p->nwrite, &p->lock);
6843
6844
         p->data[p->nwrite++ % PIPESIZE] = addr[i];
6845
6846
       wakeup(&p->nread);
6847
       release(&p->lock);
6848
       return n;
6849 }
```

# Example: pipes in xv6 (4)

```
6850 int
6851 piperead(struct pipe *p, char *addr, int n)
6852 {
6853
       int i:
6854
                                                  pipe is empty
6855
       acquire(&p->lock);
6856
       while(p->nread == p->nwrite && p->writeopen){
         if(myproc()->killed){
6857
6858
           release(&p->lock);
6859
           return -1:
                                 reader's channel is address of nread variable
6860
6861
         sleep(&p->nread, &p->lock);
                                        pipe lock protects atomicity of sleep
6862
6863
       for(i = 0; i < n; i++){
6864
         if(p->nread == p->nwrite)
6865
           break:
         addr[i] = p->data[p->nread++ % PIPESIZE];
6866
6867
6868
       wakeup(&p->nwrite);
6869
       release(&p->lock):
6870
       return i;
6871 }
```

```
2873 void
2874 sleep(void *chan, struct spinlock *lk)
2875 {
2876
       struct proc *p = myproc();
2877
2878
       if(p == 0)
2879
         panic("sleep");
2880
2881
       if(1k == 0)
2882
         panic("sleep without lk");
2883
2884
       // Must acquire ptable.lock in order to
2885
       // change p->state and then call sched.
2886
       // Once we hold ptable.lock, we can be
2887
       // guaranteed that we won't miss any wakeup
2888
       // (wakeup runs with ptable.lock locked),
2889
       // so it's okay to release lk.
2890
       if(lk != &ptable.lock){
                                                      // Tidy up.
2891
                                                2900
         acquire(&ptable.lock);
                                                      p->chan = 0;
                                                2901
2892
         release(lk);
                                                2902
2893
                                                2903
                                                      // Reacquire original lock.
2894
       // Go to sleep.
                                               2904
                                                      if(lk != &ptable.lock){
2895
       p->chan = chan;
                                               2905
                                                        release(&ptable.lock);
2896
       p->state = SLEEPING;
                                                2906
                                                        acquire(1k);
2897
                                               2907
2898
       sched();
                                               2908 }
2899
```

### Sleep function

- Sleep and wakeup called by processes with same lock held (to protect atomicity of sleep)
- Acquire ptable lock (if not already taken), then release other spinlock
- Reacquire original lock on return

# Wakeup function

- Wakeup acquires ptable.lock to change process to runnable
- If lock protecting atomicity of sleep is ptable.lock itself, then directly call wakeup1
- Wakes up all processes sleeping on a channel in ptable (more like signal broadcast of condition variables)

```
2950 // Wake up all processes sleeping on chan.
2951 // The ptable lock must be held.
2952 static void
2953 wakeup1(void *chan)
2954 {
       struct proc *p;
2955
2956
2957
       for(p = ptable.proc; p < &ptable.proc[NPROC]; p++)</pre>
2958
         if(p->state == SLEEPING && p->chan == chan)
2959
           p->state = RUNNABLE;
2960 }
2961
2962 // Wake up all processes sleeping on chan.
2963 void
2964 wakeup(void *chan)
2965 {
       acquire(&ptable.lock);
2966
       wakeup1(chan);
2967
2968
       release(&ptable.lock);
2969 }
```