# **OMNeT++**Installation Guide

Version 4.1



Copyright © 2010 András Varga and OpenSim Ltd.

# **Table of Contents**

1.	General Information	. 1
2.	Windows	. 2
3.	Mac OS X	. 6
4.	Linux	11
	Ubuntu	
	Fedora 13	
	OpenSUSE	
	Generic Unix	
	Build Options	

# Chapter 1. General Information

#### 1.1. Introduction

This document describes how to install OMNeT++ on various platforms. One chapter is dedicated to each operating system.

#### 1.2. Supported Platforms

OMNeT++ has been tested and is supported on the following operating systems:

- Windows 7, Vista, XP
- Mac OS X 10.5 and 10.6
- Linux distributions covered in this Installation Guide

The Simulation IDE can be used on the following platforms:

- Linux x86 (32-bit / 64-bit)
- Windows 7, Vista, XP (32-bit)
- Mac OS X 10.5 and 10.6 (32-bit)



Simulations can be run practically on any unix-like environment with a decent and fairly up-to-date C++ compiler, for example gcc 4.x. Certain OMNeT++ features (Tkenv, parallel simulation, XML support, etc.) depend on the availability of external libraries (Tcl/Tk, MPI, LibXML or Expat, etc.)

IDE platforms are restricted because the IDE relies on a native shared library, which we compile for the above platforms and distribute in binary form for convenience.

# Chapter 2. Windows

#### 2.1. Supported Windows Versions

The supported Windows versions are the Intel 32-bit versions of Windows XP, and later Windows versions such as Vista and Windows 7.

## 2.2. Installing the Prerequisites

The only software that you need to download and install beforehand is the Java runtime (JRE). All other software, including a C++ compiler, is included in the OMNeT++ Windows package.

Download Java 5.0 or later from http://www.java.com and install it before proceeding. Java is needed for the Eclipse-based Simulation IDE.

# 2.3. Installing OMNeT++

Download the OMNeT++ source code from <a href="http://omnetpp.org">http://omnetpp.org</a>. Make sure you select the Windows-specific archive, named omnetpp-4.1-src-windows.zip.

The package is nearly self-contained: in addition to OMNeT++ files it includes a C++ compiler, a command-line build environment, and all libraries and programs required by OMNeT++.

Copy the OMNeT++ archive to the directory where you want to install it. Choose a directory whose full path **does not contain any space**; for example, do not put OMNeT++ under *Program Files*.

Extract the zip file. To do so, right-click the zip file in Windows Explorer, and select *Extract All* from the menu. You can also use external programs like Winzip or 7zip. Rename the resulting directory to omnetpp-4.1.

When you look into the new omnetpp-4.1 directory, should see directories named doc, images, include, msys, etc., and files named mingwenv.cmd, configure, Makefile, and others.

# 2.4. Configuring and Building OMNeT++

Start mingwenv.cmd in the omnetpp-4.1 directory by double-clicking it in Windows Explorer. It will bring up a console with the MSYS *bash* shell, where the path is already set to include the omnetpp-4.1/bin directory.



If you want to start simulations from outside the shell as well (for example from Explorer), you need to add OMNeT++'s bin directory to the path; instructions are provided later.

First, check the contents of the configure.user file to make sure it contains the settings you need. In most cases you don't need to change anything.

notepad configure.user

Then enter the following commands:

```
$ ./configure
$ make
```

The build process will create both debug and release binaries.

#### 2.5. Verifying the Installation

You should now test all samples and check they run correctly. As an example, the *dyna* example is started by entering the following commands:

```
$ cd samples/dyna
$ ./dyna
```

By default, the samples will run using the graphical Tkenv environment. You should see GUI windows and dialogs.

#### 2.6. Starting the IDE

OMNeT++ comes with an Eclipse-based Simulation IDE. You will need at least Java Runtime Environment 5.0 installed on your machine. You should be able to start the IDE by typing:

```
$ omnetpp
```

We recommend that you create a shortcut for starting the IDE. To do so, locate the omnetpp.exe program in the omnetpp-4.1/ide directory in Windows Explorer, right-click it, and choose  $Send\ To > Desktop\ (create\ shortcut)$  from the menu. On Windows 7, you can right-click the taskbar icon while the IDE is running, and select  $Pin\ this\ program\ to\ taskbar$  from the context menu.

When you try to build a project in the IDE, you may get the following warning message:

Toolchain "..." is not supported on this platform or installation. Please go to the Project menu, and activate a different build configuration. (You may need to switch to the C/C++ perspective first, so that the required menu items appear in the Project menu.)

If you encounter this message, choose Project > Properties > C/C++ Build > Tool  $Chain\ Editor > Current\ toolchain > GCC\ for\ OMNeT++.$ 

#### 2.7. Environment Variables

If you want to start OMNeT++ simulations outside the shell as well (for example from Exlorer), you need to add OMNeT++'s bin directory to the path.

First, open the Environment Variables dialog.

- On Windows XP and Vista: Right-click My Computer, and choose Properties > Advanced > Environment variables.
- On Windows 7: Click the Start button, then start typing environment variables into the search box. Choose *Edit environment variables for your account* when it appears in the list. The dialog comes up.

In the dialog, select path or PATH in the list, click *Edit*. Append ";<omnetpp-dir>\bin" to the value (without quotes), where <omnetpp-dir> is the name of the OMNeT++ root directory (for example C:\omnetpp-4.1). Hit Enter to accept.

You need to close and re-open any command windows for the changes to take effect in them.

#### 2.8. Reconfiguring the Libraries

If you need to recompile the OMNeT++ components with different flags (e.g. different optimization), then change the top-level OMNeT++ directory, edit configure.user accordingly, then type:

```
$ ./configure
$ make clean
$ make
```

If you want to recompile just a single library, then change to the directory of the library (e.g. cd src/sim) and type:

```
$ make clean
$ make
```

By default, libraries are compiled in both debug and release mode. If you want to make release or debug builds only, use:

```
$ make MODE=release
or
$ make MODE=debug
```

By default, shared libraries will be created. If you want to build static libraries, use:

```
$ make SHARED_LIBS=no
```



The built libraries and programs are immediately copied to the lib/ and bin/subdirs

# 2.9. Portability Issues

 $\mbox{OMNeT++}$  has been tested with the MinGW gcc compiler. The current distribution contains gcc 4.4 version.

Microsoft Visual C++ is not supported in the Academic Edition.

# 2.10. Additional Packages

Note that Doxygen and GraphViz are already included in the OMNeT++ package, and do not need to be downloaded.

#### 2.10.1. MPI

MPI is only needed if you would like to run parallel simulations.

There are several MPI implementations for Windows, and OMNeT++ does not mandate any specific one. We recommend DeinoMPI, which can be downloaded from <a href="http://mpi.deino.net">http://mpi.deino.net</a>.

After installing DeinoMPI, adjust the MPI\_DIR setting in OMNeT++'s configure.user, and reconfigure and recompile OMNeT++:

```
$ ./configure
$ make cleanall
$ make
```



In general, if you would like to run parallel simulations, we recommend that you use Linux,  $OS\ X$ , or another unix-like platform.

#### 2.10.2. PCAP

The optional WinPcap library allows simulation models to capture and transmit network packets bypassing the operating system's protocol stack. It is not used directly by OMNeT++, but OMNeT++ detects the necessary compiler and linker options for models in case they need it.

#### 2.10.3. Akaroa

Akaroa 2.6.7, which is the latest version at the time of writing, does not support Windows. You may try to port it using the porting guide from the Akaroa distribution.

# Chapter 3. Mac OS X

#### 3.1. Supported Releases

This chapter provides additional information for installing OMNeT++ on  $Mac\ OS\ X$ .

The following releases are covered:

- Mac OS X 10.5 (Leopard)
- Mac OS X 10.6 (Snow Leopard)

They were tested on the following architectures:

• Intel 32-bit

## 3.2. Installing the Prerequisite Packages

Install Xcode 3.0 or later on your machine. Xcode is available free of charge from Apple Inc.

Xcode can be downloaded from http://developer.apple.com/technology/xcode.html.

Installing additional packages will enable more functionality in OMNeT++; see the *Additional packages* section at the end of this chapter.

# 3.3. Downloading and Unpacking OMNeT++

Download OMNeT++ from http://omnetpp.org. Make sure you select to download the generic archive, omnetpp-4.1-src.tgz.

Copy the archive to the directory where you want to install it. This is usually your home directory, /Users/<you>. Open a terminal, and extract the archive using the following command:

```
$ tar zxvf omnetpp-4.1-src.tgz
```

A subdirectory called omnetpp-4.1 will be created, containing the simulator files.

Alternatively, you can also unpack the archive using Finder.



The Terminal can be found in the Applications / Utilities folder.

#### 3.4. Environment Variables

OMNeT++ needs its bin/directory to be in the path. To add bin/directory to PATH temporarily (in the current shell only), change into the OMNeT++ directory and source the setenv script:

```
$ cd omnetpp-4.1
$ . setenv
```

To set the environment variables permanently, edit .bashrc in your home directory. Use your favourite text editor to edit .bashrc, for example TextEdit:

```
$ touch ~/.bashrc
$ open -e ~/.bashrc
```



touch is needed because open -e only opens existing files. Alternatively, you can use the terminal-based pico editor (pico  $\sim$ /.bashrc)

Add the following line at the end of the file, then save it:

```
export PATH=$PATH:$HOME/omnetpp-4.1/bin
```

You need to close and re-open the terminal for the changes to take effect.

Alternatively, you can put the above line into ~/.bash\_profile, but then you need to log out and log in again for the changes to take effect.



If you use a shell other than the default one, *bash*, consult the man page of that shell to find out which startup file to edit, and how to set and export variables.

# 3.5. Configuring and Building OMNeT++

Check configure.user to make sure it contains the settings you need. In most cases you don't need to change anything in it.

In the top-level OMNeT++ directory, type:

```
$ ./configure
```

The configure script detects installed software and configuration of your system. It writes the results into the Makefile.inc file, which will be read by the makefiles during the build process.

Normally, the configure script needs to be running under the graphical environment in order to test for wish, the Tcl/Tk shell. If you are logged in via an ssh session or you want to compile OMNeT++ without Tcl/Tk, use the command

```
$ NO_TCL=1 ./configure
```

instead of plain ./configure.



If there is an error during configure, the output may give hints about what went wrong. Scroll up to see the messages. (You may need to increase the scrollback buffer size of the terminal and re-run ./configure.) The script also writes a very detailed log of its operation into config.log to help track down errors. Since config.log is very long, it is recommended that you open it in an editor and search for phrases like *error* or the name of the package associated with the problem.



OMNeT++ builds without the BLT Tcl/Tk extension, because BLT is not available for the native (Aqua) version of Tcl/Tk.

As an alternative to the Aqua version of Tcl/Tk, you may also use the X11 version from the Fink project (http://finkproject.org). The Fink version does not have the look and feel of OS X applications, but it may provide better performance with animations, and it also has BLT. To select Fink, you will need to adjust the Tcl/Tk settings in OMNeT++'s

configure.user file. Please note that we do not provide support for using the Fink version of Tcl/Tk.

When ./configure has finished, you can compile OMNeT++. Type in the terminal:

\$ make



To take advantage of multiple processor cores, add the -j2 option to the make command line.



The build process will not write anything outside its directory, so no special privileges are needed.



The make command will seemingly compile everything twice. This is because both debug and optimized versions of the libraries are built. If you only want to build one set of the libraries, specify MODE=debug or MODE=release:

\$ make MODE=release



The OMNeT++ build process creates 32-bit executables on both OS X 10.5 and 10.6. If you want to build a 64-bit executable on OS X 10.6, you must remove the -m32 flag from the CFLAGS\_RELEASE, CFLAGS\_DEBUG and LDFLAGS variables in the Makefile.inc file. Please note that you will not be able to debug your 64-bit code from the OMNeT++ IDE, because the version of CDT (C/C++ Development Toolkit) bundled with the IDE does not support 64-bit targets.

## 3.6. Verifying the Installation

You can now verify that the sample simulations run correctly. For example, the dyna simulation is started by entering the following commands:

```
$ cd samples/dyna
$ ./dyna
```

By default, the samples will run using the Tcl/Tk environment. You should see nice gui windows and dialogs.

# 3.7. Starting the IDE

OMNeT++ comes with an Eclipse-based Simulation IDE. Mac OS X already has Java installed, so you do not need to install it. You can start the IDE by typing:

\$ omnetpp

If you would like to be able to launch the IDE via Applications, the Dock or a desktop shortcut, do the following: open the omnetpp-4.1 folder in Finder, go into the ide subfolder, create an alias for the omnetpp program there (right-click, *Make Alias*), and drag the new alias into the Applications folder, onto the Dock, or onto the desktop.

Alternatively, run one or both of the commands below:

```
$ make install-menu-item
$ make install-desktop-icon
```

which will do roughly the same.

#### 3.8. Using the IDE

When you try to build a project in the IDE, you may get the following warning message:

Toolchain "..." is not supported on this platform or installation. Please go to the Project menu, and activate a different build configuration. (You may need to switch to the C/C++ perspective first, so that the required menu items appear in the Project menu.)

If you encounter this message, choose Project > Properties > C/C++ Build > Tool  $Chain\ Editor > Current\ toolchain > GCC\ for\ OMNeT++.$ 

The IDE is documented in detail in the User Guide.

#### 3.9. Reconfiguring the Libraries

If you need to recompile the OMNeT++ components with different flags (e.g. different optimization), then change the top-level OMNeT++ directory, edit configure.user accordingly, then type:

- \$ ./configure
- \$ make clean
- \$ make



To take advantage of multiple processor cores, add the -j2 option to the make command line.

If you want to recompile just a single library, then change to the directory of the library (e.g. cd src/sim) and type:

- \$ make clean
- \$ make

By default, libraries are compiled in both debug and release mode. If you want to make release or debug builds only, use:

\$ make MODE=release

or

\$ make MODE=debug

By default, shared libraries will be created. If you want to build static libraries, use:

\$ make SHARED\_LIBS=no



The built libraries and programs are immediately copied to the  $\verb|lib/|$  and  $\verb|bin/|$  subdirectories.



The Tcl/Tk environment uses the native Aqua version of Tcl/Tk, so you will see native widgets. However, due to problems in the Tk/Aqua port, you may experience minor UI quirks. We are aware of these problems, and are working on the solution.

# 3.10. Additional Packages

Note that OpenMPI is already bundled with OS X, so you do not need to manually install MPI.

#### 3.10.1. GraphViz

GraphViz is needed if you want to have diagrams in HTML documentation that you generate from NED files in the IDE (*Generate NED Documentation...* item in the project context menu).

Download and install the GraphViz OS X binaries from http://www.pixelglow.com/graphviz/download/. Download the latest, version 2.x package; at the time of writing, the link is at the top of the page.

After installation, make sure that the dot program is available from the command line. Open a terminal, and type

```
$ dot -V
```

Note the capital *V*. The command should normally work out of the box. If you get the "command not found" error, you need to put dot into the path. Find the dot program in the GraphViz installation directory, and soft link it into /usr/local/bin (sudo ln -s <path>/dot /usr/local/bin).

#### 3.10.2. Doxygen

Doxygen is needed if you want to generate documentation for C++ code, as part of the HTML documentation that you generate from NED files in the IDE (*Generate NED Documentation...* item in the project context menu).

Download the Doxygen OS X binaries from the Doxygen web site's download page, http://www.stack.nl/~dimitri/doxygen/download.html, and install it.

After installation, ensure that the doxygen program is available from the command line. Open a terminal, and type

```
$ doxygen
```

If you get the "command not found" error, you need to put doxygen into the path. Enter into a terminal:

```
$ cd /Applications/Doxygen.app/Contents/Resources/
$ sudo ln -s doxygen doxytags /usr/local/bin
```

#### 3.10.3. Akaroa

Akaroa 2.6.7, which is the latest version at the time of writing, does not support Mac OS X. You may try to port it using the porting guide from the Akaroa distribution.

# Chapter 4. Linux

## 4.1. Supported Linux Distributions

This chapter provides instructions for installing OMNeT++ on selected Linux distributions:

- Ubuntu 8.04 LTS, 10.04 LTS
- Fedora Core 13
- Red Hat Enterprise Linux Desktop Workstation 5.5
- OpenSUSE 11.2

This chapter describes the overall process. Distro-specific information, such as how to install the prerequisite packages, are covered by distro-specific chapters.



If your Linux distribution is not listed above, you still may be able to use some distrospecific instructions in this Guide.

Ubuntu derivatives (Ubuntu instructions may apply):

- Kubuntu, Xubuntu, Edubuntu, ...
- Linux Mint

- Knoppix and derivatives
- Mepis

Some Fedora-based distros (Fedora instructions may apply):

- Simplis
- Eeedora

# 4.2. Installing the Prerequisite Packages

OMNeT++ requires several packages to be installed on the computer. These packages include the C++ compiler (gcc), the Java runtime, and several other libraries and programs. These packages can be installed from the software repositories of your Linux distribution.

See the chapter specific to your Linux distribution for instructions on installing the packages needed by OMNeT++.

You may need superuser permissions to install packages.

Not all packages are available from software repositories; some (optional) ones need to be downloaded separately from their web sites, and installed manually. See the section *Additional Packages* later in this chapter.

## 4.3. Downloading and Unpacking

Download OMNeT++ from http://omnetpp.org. Make sure you select to download the generic archive, omnetpp-4.1-src.tgz.

Copy the archive to the directory where you want to install it. This is usually your home directory, /home/<you>. Open a terminal, and extract the archive using the following command:

```
$ tar xvfz omnetpp-4.1-src.tgz
```

This will create an omnetpp-4.1 subdirectory with the OMNeT++ files in it.



On how to open a terminal on your Linux installation, see the chapter specific to your Linux distribution.

#### 4.4. Environment Variables

OMNeT++ needs its bin/directory to be in the path. To add bin/directory to PATH temporarily (in the current shell only), change into the OMNeT++ directory and source the setenv script:

```
$ cd omnetpp-4.1
$ . setenv
```

The script also adds the lib/ subdirectory to LD\_LIBRARY\_PATH, which may be necessary on systems that don't support the rpath mechanism.

To set the environment variables permanently, edit .bashrc in your home directory. Use your favourite text editor to edit .bashrc, for example gedit:

```
$ gedit ~/.bashrc
```

Add the following line at the end of the file, then save it:

```
export PATH=$PATH:$HOME/omnetpp-4.1/bin
```

You need to close and re-open the terminal for the changes to take effect.

Alternatively, you can put the above line into ~/.bash\_profile, but then you need to log out and log in again for the changes to take effect.



If you use a shell other than bash, consult the man page of that shell to find out which startup file to edit, and how to set and export variables.

Note that all Linux distributions covered in this Installation Guide use *bash* unless the user has explicitly selected another shell.

# 4.5. Configuring and Building OMNeT++

In the top-level OMNeT++ directory, type:

```
$ ./configure
```

The configure script detects installed software and configuration of your system. It writes the results into the Makefile.inc file, which will be read by the makefiles during the build process.

```
<u>File Edit View Terminal Tabs Help</u>
checking for Akaroa with CFLAGS=" -02 -DNDEBUG=1 -fno-stack-protector SER=libxml " LIBS=""... no
                                                                                          -DXMLPAR
checking for Akaroa with CFLAGS=" -02 -DNDEBUG=1 -fno-stack-protector SER=libxml " LIBS="-lakaroa -lfl"... no configure: WARNING: Optional package Akaroa not found
                                                                                          -DXMLPAR
configure: creating ./config.status
config.status: creating Makefile.inc
config.status: creating test/core/runtest
patching the ide configuration file. default workspace is: /home/ubuntu/omnest-4
.0/samples
WARNING: The configuration script could not detect the following packages:
     MPI (optional) Akaroa (optional)
Scroll up to see the warning messages (use shift+PgUp key), and see config.log for more details. While you can use OMNEST in the current
configuration, please be aware that some functionality may be unavailable
Your PATH contains /home/ubuntu/omnest-4.0/bin. Good!
TCL LIBRARY is set. Good!
ubuntu@ubuntu-desktop:~/omnest-4.0$
```

Figure 4.1. Configuring OMNeT++

Normally, the configure script needs to be running under the graphical environment (X11) in order to test for wish, the Tcl/Tk shell. If you are logged in via an ssh session, or there is some other reason why X is not running, the easiest way to work around the problem is to tell OMNeT++ to build without Tcl/Tk. To do that, use the command

```
$ NO_TCL=1 ./configure
```

instead of plain ./configure.



If there is an error during configure, the output may give hints about what went wrong. Scroll up to see the messages. (Use Shift+PgUp; you may need to increase the scrollback buffer size of the terminal and re-run ./configure.) The script also writes a very detailed log of its operation into config.log to help track down errors. Since config.log is very long, it is recommended that you open it in an editor and search for phrases like *error* or the name of the package associated with the problem.

When ./configure has finished, you can compile OMNeT++. Type in the terminal:

\$ make

```
<u>F</u>ile <u>E</u>dit <u>V</u>iew <u>Terminal</u> Ta<u>b</u>s <u>H</u>elp
 g++ -c -g -Wall -fno-stack-protector
                                                                                                                                       -DXMLPARSER=libxml -DWITH PARSIM -DWITH N
  ETBUILDER
                                      -I. -Ihtdocs -I/home/ubuntu/omnest-4.0/include
                                                                                                                                                                                                       -o out/acc-debug//Http
Msg_m.o HttpMsg_m.cc
g++ -c -g -Wall -fno-stack-protector -DXMLPARSER=libxml -DWITH_PARSIM -DWITH_N
ETBUILDER -I. -Ihtdocs -I/home/ubuntu/omnest-4.0/include -o out/gcc-debug//NetP
  kt_m.o NetPkt_m.cc
              -c -g -Wall -fno-stack-protector
                                                                                                                                     -DXMLPARSER=libxml -DWITH PARSIM -DWITH N
 ETBUILDER -I. -Ihtdocs -I/home/ubuntu/omnest-4.0/include -o out/gcc-debug//Teln
 etPkt_m.o TelnetPkt_m.cc
  g++ -Wl,--export-dynamic
                                                                                          -Wl,-rpath,/home/ubuntu/omnest-4.0/lib:. -o out/gcc-de
 bug//sockets out/gcc-debug//Cloud.o out/gcc-debug//ExtHttpClient.o out/gcc-debug//HttpClient.o out/gcc-debug//HttpServer.o out
  /gcc-debug//QueueBase.o out/gcc-debug//SocketRTScheduler.o out/gcc-debug//Telnet
/gcc-debug//Techetory/socketory/socketory/socketory/socketory/socketory/rechetory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/socketory/sock
vird -loppsind -lot -lstdc++
ln -s -f out/gcc-debug//sockets .
make[2]: Leaving directory `/home/ubuntu/omnest-4.0/samples/sockets'
make[1]: Leaving directory `/home/ubuntu/omnest-4.0'
 Now you can type "omnest" to start the IDE
ubuntu@ubuntu-desktop:~/omnest-4.0$
```

Figure 4.2. Building OMNeT++



To take advantage of multiple processor cores, add the -j2 option to the make command line.



The build process will not write anything outside its directory, so no special privileges are needed.



The make command will seemingly compile everything twice. This is because both debug and optimized versions of the libraries are built. If you only want to build one set of the libraries, specify MODE=debug or MODE=release:

\$ make MODE=release

# 4.6. Verifying the Installation

You can now verify that the sample simulations run correctly. For example, the dyna simulation is started by entering the following commands:

```
$ cd samples/dyna
$ ./dyna
```

By default, the samples will run using the Tcl/Tk environment. You should see nice gui windows and dialogs.

# 4.7. Starting the IDE

You can launch the OMNeT++ Simulation IDE by typing the following command in the terminal:

\$ omnetpp




Figure 4.3. The Simulation IDE

If you would like to be able to access the IDE from the application launcher or via a desktop shortcut, run one or both of the commands below:

```
$ make install-menu-item
$ make install-desktop-icon
```

Or add a shortcut that points to the omnetpp program in the ide subdirectory by other means, for example using the Linux desktop's context menu.

#### 4.8. Using the IDE

When you try to build a project in the IDE, you may get the following warning message:

Toolchain "..." is not supported on this platform or installation. Please go to the Project menu, and activate a different build configuration. (You may need to switch to the C/C++ perspective first, so that the required menu items appear in the Project menu.)

If you encounter this message, choose Project > Properties > C/C++ Build > Tool  $Chain\ Editor > Current\ toolchain > GCC\ for\ OMNeT++.$ 

The IDE is documented in detail in the User Guide.

# 4.9. Reconfiguring the Libraries

If you need to recompile the OMNeT++ components with different flags (e.g. different optimization), then change the top-level OMNeT++ directory, edit configure.user accordingly, then type:

```
$ ./configure
$ make cleanall
$ make
```

If you want to recompile just a single library, then change to the directory of the library (e.g. cd src/sim) and type:

```
$ make clean
$ make
```

By default, libraries are compiled in both debug and release mode. If you want to make release or debug builds only, use:

```
$ make MODE=release
```

or

\$ make MODE=debug

By default, shared libraries will be created. If you want to build static libraries, use:

```
$ make SHARED_LIBS=no
```



For detailed description of all options please read the Build Options chapter.

#### 4.10. Additional Packages

Note that at this point, MPI, Doxygen and GraphViz have been installed as part of the prerequisites.

#### 4.10.1. Akaroa

Linux distributions do not contain the Akaroa package. It must be downloaded, compiled and installed manually before installing OMNeT++.

Download Akaroa 2.7.6 (which is the latest version at the time of writing) from the project's web site: http://www.cosc.canterbury.ac.nz/research/RG/net\_sim/simulation\_group/akaroa/download/

Extract it into a temporary directory:

```
$ tar xfz akaroa-2.7.6.tar.gz
```

Unfortunately, this version does not compile properly with gcc-4.4. A patch is available in the <mnetpproot>/contrib/akaroa directory to fix the compilation problems.
Change to the Akaroa root directory, and apply it to the sources.

```
$ cd akaroa-2.7.6
$ patch -p1 -i <omnetpproot>/contrib/akaroa/akaroa-2.7.6-gcc-4.4.patch
```

Configure, build, and install the Akaroa library. By default, it will be installed into the /usr/local/akaroa directory.

```
$ ./configure
$ make
$ sudo make install
```

Go to the OMNeT++ directory, and (re-)run the configure script. Akaroa will be automatically detected if you installed it to the default location.

#### 4.10.2. PCAP

The optional Pcap library allows simulation models to capture and transmit network packets bypassing the operating system's protocol stack. It is not used directly by OMNeT++, but OMNeT++ detects the necessary compiler and linker options for models in case they need it.

# Chapter 5. Ubuntu

#### 5.1. Supported Releases

This chapter provides additional information for installing OMNeT++ on Ubuntu Linux installations. The overall installation procedure is described in the Linux chapter.

The following Ubuntu releases are covered:

- Ubuntu 8.04 LTS (Hardy Heron)
- Ubuntu 10.04 LTS (Lucid Lynx)

They were tested on the following architectures:

• Intel 32-bit and 64-bit

The instructions below assume that you use the Gnome desktop and the bash shell, which are the defaults. If you use another desktop environment or shell, you may need to adjust the instructions accordingly.

#### 5.2. Opening a Terminal

Choose *Applications > Accessories > Terminal* from the menu.

This only applies if you use the Gnome Desktop (default).

# 5.3. Installing the Prerequisite Packages

You can perform the installation using the graphical user interface or from the terminal, whichever you prefer.

#### 5.3.1. Command-Line Installation

Before starting the installation, refresh the database of available packages. Type in the terminal:

```
$ sudo apt-get update
```

To install the required packages, type in the terminal:

At the confirmation questions (Do you want to continue? [Y/N]), answer Y.




Figure 5.1. Command-Line Package Installation

#### 5.3.2. Graphical Installation

Ubuntu's graphical installer, *Synaptic*, can be started with the *System > Administration > Synaptic package manager* menu item.

Since software installation requires root permissions, Synaptic will ask you to type your password.

Search for the following packages in the list, click the squares before the names, then choose *Mark for installation* or *Mark for upgrade*.

If the *Mark additional required changes?* dialog comes up, choose the *Mark* button.

The packages:

• build-essential, gcc, g++, bison, flex, perl, tcl-dev, tk-dev, blt, libxml2-dev, zlib1g-dev, openjdk-6-jre, doxygen, graphviz, openmpi-bin, libopenmpi-dev, libpcap-dev




Figure 5.2. Synaptic Package Manager

Click Apply, then in the Apply the following changes? window, click Apply again. In the Changes applied window, click Close.

# Chapter 6. Fedora 13

## 6.1. Supported Releases

This chapter provides additional information for installing OMNeT++ on Fedora installations. The overall installation procedure is described in the Linux chapter.

The following Fedora releases are covered:

• Fedora 13

They were tested on the following architectures:

• Intel 32-bit and 64-bit

## 6.2. Opening a Terminal

Choose *Applications > System Tools > Terminal* from the menu.

#### 6.3. Installing the Prerequisite Packages

You can perform the installation using the graphical user interface or from the terminal, whichever you prefer.

#### 6.3.1. Command-Line Installation

To install the required packages, type in the terminal:

```
$ su -c 'yum install make gcc gcc-c++ bison flex perl \
    tcl-devel tk-devel blt libxml2-devel zlib-devel \
    java-1.6.0-openjdk doxygen graphviz openmpi-devel libpcap-devel'
```

then follow the instruction on the console.

Note that *openmpi* will not be available by default, it needs to be activated in every session with the

```
$ module load openmpi_<arch>
```

command, where <code><arch></code> is your architecture (usually i386 or  $x86\_64$ ). When in doubt, use <code>module</code> avail to display the list of available modules. If you need MPI in every session, you may add the <code>module</code> load command to your startup script (.bashrc).

#### 6.3.2. Graphical Installation

The graphical installer can be launched by choosing *System > Administration > Add/Remove Software* from the menu.




Figure 6.1. Add/Remove Software

Search for the following packages in the list. Select the checkboxes in front of the names, and pick the latest version of each package.

#### The packages:

• bison, gcc, gcc-c++, flex, perl, tcl-devel, tk-devel, blt, libxml2-devel, zlib-devel, xulrunner, make, java-1.6.0-openjdk, doxygen, graphviz, openmpi-devel, libpcap-devel

Click Apply, then follow the instructions.

# Chapter 7. OpenSUSE

#### 7.1. Supported Releases

This chapter provides additional information for installing OMNeT++ on openSUSE installations. The overall installation procedure is described in the Linux chapter.

The following openSUSE releases are covered:

• openSUSE 11.2

They were tested on the following architectures:

• Intel 32-bit and 64-bit

#### 7.2. Opening a Terminal

 ${\it Choose Applications} > {\it System} > {\it Terminal} > {\it Terminal from the menu}.$ 

## 7.3. Installing the Prerequisite Packages

You can perform the installation using the graphical user interface or from the terminal, whichever you prefer.

#### 7.3.1. Command-Line Installation

To install the required packages, type in the terminal:

```
$ sudo zypper install make gcc gcc-c++ bison flex perl \
    tcl-devel tk-devel libxml2-devel zlib-devel \
    java-1_6_0-openjdk doxygen graphviz openmpi-devel libpcap-devel
```

then follow the instruction on the console.

Note that *openmpi* will not be available by default, first you need to log out and log in again, or source your .profile script:

```
$ . ~/.profile
```



OpenSUSE provides no BLT package, so it is missing from the above list. BLT is optional in OMNeT++ and its absence will not result in loss of functionality, but you can download a BLT source package from sourceforge.net, and compile and install it yourself if you wish. See the *Generic Unix* chapter of this Installation Guide for more information on BLT.

#### 7.3.2. Graphical Installation

The graphical installer can be launched by choosing *Computer > Yast > System > Software > Software Management* from the menu.




Figure 7.1. Yast Software Management

Search for the following packages in the list. Select the checkboxes in front of the names, and pick the latest version of each package.

#### The packages:

• make, gcc, gcc-c++, bison, flex, perl, tcl-devel, tk-devel, libxml2-devel, zlib-devel, java-1\_6\_0-openjdk, doxygen, graphviz, openmpi-devel, libpcap-devel

Click *Accept*, then follow the instructions.

# Chapter 8. Generic Unix

#### 8.1. Introduction

This chapter provides additional information for installing OMNeT++ on Unix-like operating systems not specifically covered by this Installation Guide. The list includes FreeBSD, Solaris, and Linux distributions not covered in other chapters.



In addition to Windows and Mac OS X, the Simulation IDE will only work on Linux x86 32/64-bit platforms. Other operating systems (FreeBSD, Solaris, etc.) and architectures may still be used as simulation platforms, without the IDE.

## 8.2. Dependencies

The following packages are required for OMNeT++ to work:

build-essential, GNU make, gcc, g++, bison (2.x+), flex, perl

These packages are needed for compiling OMNeT++ and simulation models, and also for certain OMNeT++ tools to work. Some C++ compilers other than g++, for example the Intel compiler, will also be accepted.

The following packages are strongly recommended, because their absence results in severe feature loss:

Tcl/Tk 8.4 or later Required by the Tkenv simulation runtime

environment. You need the *devel* packages that include the C header files as well. It is also possible to compile OMNeT++ without Tcl/Tk (and Tkenv), by

turning on the NO\_TCL environment variable.

BLT (2.4z) This is a Tk extension recommended for Tkenv. The

normal (non-devel) package suffices. This package is optional in the sense that if it is missing, Tkenv will be still fully functional, albeit it will have a less

sophisticated user interface.

LibXML2 or Expat Either one of these XML parsers are needed for

OMNeT++ to be able to read XML files. The *devel* packages (that include the header files) are needed.

LibXML2 is the preferred one.

SUN JRE or OpenJDK,

version 5.0 or later

The Java runtime is required to run the Eclipsebased Simulation IDE. Other implementations, for example Kaffe, have been found to have problems

running the IDE. You do not need this package if you

do not plan to use the Simulation IDE.

xulrunner This package is part of Firefox, and is needed by

the IDE to display documentation, styled tooltips and

other items.

The following packages are required if you want to take advantage of some advanced OMNeT++ features:

GraphViz, Doxygen These packages are used by the NED documentation

generation feature of the IDE. When they are missing,

documentation will have less content.

MPI openmpi or some other MPI implementation is required to

support parallel simulation execution.

Akaroa Implements Multiple Replications In Parallel (MRIP).

Akaroa can be downloaded from the project's website.

Pcap Allows simulation models to capture and transmit network

packets bypassing the operating system's protocol stack. It is not used directly by OMNeT++, but OMNeT++ detects the necessary compiler and linker options for models in

case they need it.

The exact names of these packages may differ across distributions.

# 8.3. Determining Package Names

If you have a distro unrelated to the ones covered in this Installation Guide, you need to figure out what is the established way of installing packages on your system, and what are the names of the packages you need.

#### 8.3.1. Tcl/Tk

Tcl/Tk may be present as separate packages (tcl and tk), or in one package (tcltk). The version number (e.g. 8.5) is usually part of the name in some form (85, 8.5, etc). You will need the development packages, which are usually denoted with the -dev or -devel name suffix.

Troubleshooting:

If your platform does not have suitable Tcl/Tk packages, you may still use OMNeT++ to run simulations from the command line. To disable the graphical runtime environment use:

```
$ NO_TCL=yes ./configure
```

This will prevent the build system to link with Tcl/Tk libraries. This is required also if you are installing OMNeT++ from a remote terminal session.

By default, the <code>configure</code> script expects to find the Tcl/Tk libraries in the standard linker path (without any <code>-Ldirectory</code> linker option) and under the standard names (i.e. with the <code>-ltcl8.4</code> or <code>-ltcl84</code> linker option). If you have them in different places or under different names, you have to edit <code>configure.user</code> and explicitly set <code>TK\_LIBS</code> there (see the Build Options chapter for further details).

If you get the error no display and DISPLAY environment variable not set, then you're either not running X (the wish command, and thus ./configure won't work just in the console) or you really need to set the DISPLAY variable (export DISPLAY=:0.0 usually does it).

If you get the error: Tcl\_Init failed: Can't find a usable init.tcl...

The TCL\_LIBRARY environment variable should point to the directory which contains init.tcl. That is, you probably want to put a line like

```
export TCL_LIBRARY=/usr/lib/tcl8.4
```

into your ~/.bashrc.

If you still have problems installing Tcl/Tk, we recommend visiting the OMNeT++ site's wiki packages for further troubleshooting tips: http://www.omnetpp.org/pmwiki/index.php?n=Main.TclTkRelatedProblems

#### 8.3.2. BLT

BLT is not a supported package in all Unix distributions. If your distro does not have it, then your can either use Tkenv without BLT (not a big problem), or download and build BLT yourself.

You can get the source tarball, BLT2.4z.tar.gz from the Sourceforge BLT project page, http://sourceforge.net/projects/blt.

Unpack the source tgz, change into its directory, then type ./configure, then make and make install. (For the last step you'll need root privileges—you may need to contact your sysadmin). If there's any problem, refer to the INSTALL file in the package.

You can try your installation by running bltwish, or running wish and typing

```
% package require BLT
```

in it.

If you don't have root privileges or you get an error during the build, please check the following page: http://www.omnetpp.org/pmwiki/index.php? n=Main.TclTkRelatedProblems

#### 8.3.3. The Java Runtime

You need to install the Sun JRE or OpenJDK. On Unix platforms other than Linux the IDE is not supported so JRE is not required either. We have tested various other Java runtimes (*gcj*, *kaffe*, etc.), and the IDE does not work well with them.

Java version 5.0 (i.e. JRE 1.5) or later is required.

#### 8.3.4. MPI

OMNeT++ is not sensitive to the particular MPI implementation. You may use OpenMPI, or any other standards-compliant MPI package.

# 8.4. Downloading and Unpacking

Download OMNeT++ from http://omnetpp.org. Make sure you select to download the generic archive, omnetpp-4.1-src.tgz.

Copy the archive to the directory where you want to install it. This is usually your home directory, /home/<you>. Open a terminal, and extract the archive using the following command:

```
$ tar xvfz omnetpp-4.1-src.tgz
```

This will create an omnetpp-4.1 subdirectory with the OMNeT++ files in it.

#### 8.5. Environment Variables

In general OMNeT++ requires that its bin directory should be in the PATH. You should add a line something like this to your .bashrc:

```
$ export PATH=$PATH:$HOME/omnetpp-4.1/bin
```

You may also have to specify the path where shared libraries are loaded from. Use:

\$ export LD\_LIBRARY\_PATH=\$LD\_LIBRARY\_PATH:\$HOME/omnetpp-4.1/lib

If configure complains about not finding the Tcl library directory, you may specify it by setting the TCL\_LIBRARY environment variable.



If you use a shell other than bash, consult the man page of that shell to find out which startup file to edit, and how to set and export variables.

#### 8.6. Configuring and Building OMNeT++

In the top-level OMNeT++ directory, type:

\$ ./configure

The configure script detects installed software and configuration of your system. It writes the results into the Makefile.inc file, which will be read by the makefiles during the build process.




Figure 8.1. Configuring OMNeT++

Normally, the configure script needs to be running under the graphical environment (X11) in order to test for wish, the Tcl/Tk shell. If you are logged in via an ssh session, or there is some other reason why X is not running, the easiest way to work around the problem is to tell OMNeT++ to build without Tcl/Tk. To do that, use the command

\$ NO\_TCL=1 ./configure

instead of plain ./configure.



If there is an error during configure, the output may give hints about what went wrong. Scroll up to see the messages. (Use Shift+PgUp; you may need to increase the scrollback buffer size of the terminal and re-run ./configure.) The script also writes a very detailed log of its operation into config.log to help track down errors. Since config.log is very long, it is recommended that you open it in an editor and search for phrases like *error* or the name of the package associated with the problem.

The configure script tries to build and run small test programs that are using specific libraries or features of the system. You can check the <code>config.log</code> file to see which test program has failed and why. In most cases the problem is that the script cannot figure out the location of a specific library. Specifying the include file or library location

in the configure.user file and then re-running the configure script usually solves the problem.

When ./configure has finished, you can compile OMNeT++. Type in the terminal:

\$ make

```
ubuntu@ubuntu-desktop: ~/omnest-4.0
 <u>F</u>ile <u>E</u>dit <u>V</u>iew <u>T</u>erminal Ta<u>b</u>s <u>H</u>elp
     -c -g -Wall -fno-stack-protector
                                                      -DXMLPARSER=libxml -DWITH PARSIM -DWITH N
ETBUILDER
               -I. -Ihtdocs -I/home/ubuntu/omnest-4.0/include -o out/gcc-debug//Http
Msg_m.o HttpMsg_m.cc
g++ -c -g -Wall -fno-stack-protector
                                                      -DXMLPARSER=libxml -DWITH_PARSIM -DWITH_N
ETBUILDER -I. -Ihtdocs -I/home/ubuntu/omnest-4.0/include -o out/gcc-debug//NetP
kt m.o NetPkt m.cc
      -c -g -Wa\overline{\text{l}}l -fno-stack-protector
                                                      -DXMLPARSER=libxml -DWITH_PARSIM -DWITH_N
ĒTBUILDEŘ
               -I. -Ihtdocs -I/home/ubuntu/omnest-4.0/include -o out/gcc-debug//Teln
etPkt_m.o TelnetPkt_m.cc
g++ -Wl,--export-dynamic
                                   -Wl,-rpath,/home/ubuntu/omnest-4.0/lib:. -o out/gcc-de
bug//sockets out/gcc-debug//Cloud.o out/gcc-debug//ExtHttpClient.o out/gcc-debu
g//ExtTelnetClient.o out/gcc-debug//HttpClient.o out/gcc-debug//HttpServer.o out
//gcc-debug//QueueBase.o out/gcc-debug//SocketRTScheduler.o out/gcc-debug//Telnet
Client.o out/gcc-debug//TelnetServer.o out/gcc-debug//HttpMsg_m.o out/gcc-debug//NetPkt_m.o out/gcc-debug//TelnetPkt_m.o -Wl,--whole-archive -Wl,--no-whole-archive -L"/home/ubuntu/omnest-4.0/lib/gcc" -L"/home/ubuntu/omnest-4.0/lib" -u _tk
env_lib -lopptkenvd -loppenvird -lopplayoutd -u _cmdenv_lib -loppcmdenvd -loppen
vird -loppsimd -ldl -lstdc++
ln -s -f out/gcc-debug//sockets .
make[2]: Leaving directory `/home/ubuntu/omnest-4.0/samples/sockets'
make[1]: Leaving directory `/home/ubuntu/omnest-4.0'
Now you can type "omnest" to start the IDE
ubuntu@ubuntu-desktop:~/omnest-4.0$
```

Figure 8.2. Building OMNeT++



To take advantage of multiple processor cores, add the -j2 option to the make command line.



The build process will not write anything outside its directory, so no special privileges are needed.



The make command will seemingly compile everything twice. This is because both debug and optimized versions of the libraries are built. If you only want to build one set of the libraries, specify MODE=debug or MODE=release:

\$ make MODE=release

# 8.7. Verifying the Installation

You can now verify that the sample simulations run correctly. For example, the dyna simulation is started by entering the following commands:

```
$ cd samples/dyna
$ ./dyna
```

By default, the samples will run using the Tcl/Tk environment. You should see nice gui windows and dialogs.

# 8.8. Starting the IDE



The IDE is supported only on Windows, Mac OS X (x86) and Linux (x86,x64).

You can run the IDE by typing the following command in the terminal:

\$ omnetpp




Figure 8.3. The Simulation IDE

If you would like to be able to access the IDE from the application launcher or via a desktop shortcut, run one or both of the commands below:

```
$ make install-menu-item
$ make install-desktop-icon
```



The above commands assume that your system has the xdg commands, which most modern distributions do.

# 8.9. Optional Packages

#### 8.9.1. Akaroa

Linux distributions do not contain the Akaroa package. It must be downloaded, compiled and installed manually before installing OMNeT++;.



Akaroa 2.7.6 is supported only on Linux and Solaris platforms.

 $Download\ Akaroa\ 2.7.6\ from:\ http://www.cosc.canterbury.ac.nz/research/RG/net\_sim/simulation\_group/akaroa/download/$ 

Extract it into a temporary directory:

```
$ tar xfz akaroa-2.7.6.tar.gz
```

Unfortunately, this version does not compile properly with gcc-4.4. A patch is available in the <mnetpproot>/contrib/akaroa directory to fix the compilation problems.
Change to the Akaroa root directory and apply the patch to the sources.

```
$ cd akaroa-2.7.6
$ patch -p1 -i <omnetpproot>/contrib/akaroa/akaroa-2.7.6-gcc-4.4.patch
```

Configure, build and install the Akaroa library. By default, it will be installed into the /usr/local/akaroa directory.

- \$ ./configure
- \$ make
- \$ sudo make install

Go to the OMNeT++ directory, and (re-)run the configure script. Akaroa will be automatically detected if you installed it to the default location.

#### 8.9.2. PCAP

The optional Pcap library allows simulation models to capture and transmit network packets bypassing the operating system's protocol stack. It is not used directly by OMNeT++, but OMNeT++ detects the necessary compiler and linker options for models in case they need it.

# Chapter 9. Build Options

## 9.1. Configure.user Options

The configure.user file contains several options that can be used to fine-tune the simulation libraries.

You always need to re-run the configure script in the installation root after changing the configure.user file.

\$ ./configure

After this step, you have to remove all previous libraries and recompile OMNeT++:

\$ make cleanall

\$ make

#### Options:

<COMPONENTNAME>\_CFLAGS,
<COMPONENTNAME>\_LIBS

The configure.user file contains variables for defining the compile and link options needed by various external libraries. By default, the configure command detects these automatically, but you may override the auto detection by specifying the values by hand. (e.g. <COMP>\_CFLAGS=-I/path/to/comp/includedir and <COMP>\_LIBS=-L/path/to/comp/libdir -lnameoflib.)

WITH\_PARSIM=no

Use this variable to explicitly disable parallel simulation support in OMNeT++.

WITH\_NETBUILDER=no

This option allows you to leave out the NED language parser and the network builder. (This is needed only if you are building your network with C++ API calls and you do not use the built-in NED language parser at all.)

NO TCL=yes

This will prevent the build system to link with Tcl/Tk libraries. Use this option if your platform does not have a suitable Tcl/Tk package and you will run the simulation only in command line mode. (i.e. You want to run OMNeT++ in a remote terminal session.)

EMBED\_TCL\_CODE=no

Tcl/Tk is a script language and the source of the graphical runtime environment is stored as .tcl files in the src/tkenv directory. By default, these files are not used directly, but are embedded as string literals in the executable file. Setting EMBED\_TCL\_CODE=yes allows you to move the OMNeT++ installation without caring about the location of the .tcl files. If you want to make changes to the Tcl code, you better switch off the embedding with the EMBED\_TCL\_CODE=no option. This way you can make changes to the .tcl files and see the changes

immediately without recompiling the OMNeT++ libraries.

CFLAGS\_[RELEASE/DEBUG]

To change the compiler command line options the build process is using, you should specify them in the CFLAGS\_RELEASE and CFLAGS\_DEBUG variables. By default, the flags required for debugging or optimization are detected automatically by the configure script. If you set them manually, you should specify all options you need. It is recommended to check what options are detected automatically (check the Makefile.inc after running configure and look for the CFLAGS\_[RELEASE/DEBUG] variables.) and add/modify those options manually in the configure.user file.

LDFLAGS

Linker command line options can be explicitly set using this variable. It is recommended to check what options are detected automatically (check the Makefile.inc after running configure and look for the LDFLAGS variable.) and add/modify those options manually in the configure.user file.

SHARED\_LIBS

This variable controls whether the OMNeT++ build process will create static or dynamic libraries. By default, the OMNeT++ runtime is built as shared libraries. If you want to build a single executable from your simulation, specify SHARED\_LIBS=no in configure.user to create static OMNeT++ libraries and then recompile OMNeT++ (make cleanall; make). Once the OMNeT++ static libraries are correctly built, your own project have to be rebuilt, too. You will get a single, statically linked executable, which requires only the NED and INI files to run.



It is important to completely delete the OMNeT++ libraries (make cleanall) and then rebuild them, otherwise it cannot be guaranteed that the created simulations are linked against the correct libraries.



The SHARED\_LIBS variable can be provided as the make command's argument, too. Use the make SHARED\_LIBS=no command to build static libraries.

The following symbols can be defined for the compiler if you need backward compatibility with some older OMNeT++ 3.x features. They should be specified on the compiler command line using the -DSYMBOLNAME syntax. You can add these options to the CFLAGS\_RELEASE or CFLAGS\_DEBUG variables (e.g. CFLAGS\_RELEASE='-O2 - DNDEBUG=1 -DSYMBOLNAME').

USE\_DOUBLE\_SIMTIME

OMNeT++ 3.x used double as the type for simulation time. In OMNeT++ 4.0 and later, the simulation time is a fixed-point number based on a 64-bit integer.. If you want to work with double simulation time for some reason (e.g. during porting an OMNeT++ 3.x model), define the USE\_DOUBLE\_SIMTIME symbol for the compiler.

WITHOUT\_CPACKET

In OMNeT++ 3.x, methods and data related to the modeling of network packets were included in the cMessage class. For these parameters, OMNeT++ 4.x has a new class called cPacket (derived from cMessage). If you want get back the old behavior (i.e. having a single cMessage class only), define the WITHOUT\_CPACKET symbol.

## 9.2. Moving the Installation

When you build OMNeT++ on your machine, several directory names are compiled into the binaries. This makes it easier to set up OMNeT++ in the first place, but if you rename the installation directory or move it to another location in the file system, the built-in paths become invalid and the correct paths have to be supplied via environment variables.

The following environment variables are affected (in addition to PATH, which also needs to be adjusted):

OMNETPP\_IMAGE\_PATH

This variable contains the list of directories where Tkenv looks for icons. Set it to point to the images/ subdirectory of your OMNeT++ installation.

OMNETPP\_TKENV\_DIR

This variable points to the directory that contains the Tcl script parts of Tkenv, which is by default the src/tkenv/subdirectory of your OMNeT++ installation. Normally you don't need to set this variable, because the Tkenv shared library contains all Tcl code compiled in as string literals. However, if you compile OMNeT++ with the EMBED\_TCL\_CODE=no setting and then you move the installation, then you need to set OMNETPP\_TKENV\_DIR, otherwise Tkenv won't start.

LD\_LIBRARY\_PATH

This variable contains the list of additional directories where shared libraries are looked for. Initially,  $\begin{tabular}{l} $\tt LD\_LIBRARY\_PATH$ is not needed because shared libraries are located via the $\it rpath$$ mechanism. When you move the installation, you need to add the $\tt lib/$$ subdirectory of your OMNeT++ installation to $\tt LD\_LIBRARY\_PATH$. \end{tabular}$ 



On Mac OS X,  $\mbox{DYLD\_LIBRARY\_PATH}$  is used instead of LD\_LIBRARY\_PATH. On Windows, the PATH variable must contain the directory where shared libraries (DLLs) are present.

# 9.3. Using Different Compilers

By default, the configure script detects the following compilers automatically in the path:

- Intel compiler (icc, icpc)
- GNU C/C++ (gcc, g++)
- Sun Studio (cc, cxx)
- IBM compiler (xlc, xlC)

If you want to use compilers other than the above ones, you should specify the compiler name in the CC and CXX variables, and re-run the configuration script.



Different compilers may have different command line options. If you use a compiler other than the default gcc, you may have to revise the CFLAGS\_[RELEASE/DEBUG] and LDFLAGS variables.