Job Order API

Overview

You can input Job Order data into Ecount ERP by linking it with the external service system.

However, since only the fields added to the default input screen template within ERP can be entered

Template Required Fields(Parameter) of the input API are different for each company code When sending a field that is not added to the input screen template, the data of that field is not entered.

Requested Data Format

Field Description

Calling Method POST Content-Type application/json

Test URL

https://sboapi{ZONE}.ecount.com/OAPI/V2/JobOrder/SaveJobOrder?SESSION_ID={SESSION_ID}

Request URL

https://oapi{ZONE}.ecount.com/OAPI/V2/JobOrder/SaveJobOrder?SESSION_ID={SESSION_ID}

Types of Data Format JSON(Paramenter, Result)

Types of Data Format

Parameter Parameter Name Characters Ecount Required Template Required Description

SESSION_ID Session ID STRING(50) Y SESSION_ID (Session ID) that is given after calling the Login API.

JobOrderList

[BulkDatas] Information by each Sales Order Slip Repeated part UPLOAD SER NO Order SMALLINT(4,0) Y Sequence

* Entries

- If you want to bundle them into the same slip, give the same order number.
- It will considered part of the same slip based on the entered [Sequence] and [Batch Import Bundling Settings].
- * Character Limit
- Up to 4 characters.

IO_DATE Date STRING(8) Job Order Date

If left blank, the current date will be used.

CUST Customer Code STRING(30) Job Order Customer Code

(Customer/Vendor Code from the ERP)

The field must be entered if set as [Required]. (Required status can be set up in Inv. I >

Production > New Job Order > Option > Input Screen Setting > Top tab)

CUST_DES Customer Name STRING(100) Job Order Customer Name (Customer/Vendor Name from the ERP)

The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Job Order > Option > Input Screen Setting > Top tab) EMP CD PIC STRING(30) PIC Code (PIC Code from the ERP) The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Job Order > Option > Input Screen Setting > Top tab) PJT CD Project STRING(14) **Project Code** The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Job Order > Option > Input Screen Setting > Top tab) DOC NO Job Order No. STRING(30) Job Order No. The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Job Order > Option > Input Screen Setting > Top tab) TTL CTT STRING(200) Title Title Enter the field only if set up in New Job Order > Option > Input Screen Setting > Top tab > 'Title' Default setting > Designate Manually. TIME DATE Delivery Date STRING(8) **Delivery Date** The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Job Order > Option > Input Screen Setting > Top tab) U MEMO1 Text Type 1 STRING(200) Enter the field if set up in Inv. I > Production > New Job Order > Option > Input Screen Setting > Top tab. The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Job Order > Option > Input Screen Setting > Top tab) Text Type 2 U MEMO2 STRING(200) Enter the field if set up in Inv. I > Production > New Job Order > Option > Input Screen Setting > Top tab. The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Job Order > Option > Input Screen Setting > Top tab) U MEMO3 Text Type 3 STRING(200) Enter the field if set up in Inv. I > Production > New Job Order > Option > Input Screen Setting > Top tab. The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Job Order > Option > Input Screen Setting > Top tab) U MEMO4 Text Type 4 STRING(200) Enter the field if set up in Inv. I > Production > New Job Order > Option > Input Screen Setting > Top tab. The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Job Order > Option > Input Screen Setting > Top tab) U MEMO5 Text Type 5 STRING(200) Enter the field if set up in Inv. I > Production > New Job Order > Option > Input Screen Setting > Top tab. The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Job Order > Option > Input Screen Setting > Top tab) U TXT1 Long Text Type1 STRING(2000) Enter the field if set up in Inv. I > Production > New Job Order > Option > Input Screen Setting > Top tab. The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Job Order > Option > Input Screen Setting > Top tab) PROD CD Item Code STRING(20) Y Item Code (Item Code from the

ERP)

```
PROD DES Item Name
                            STRING(100)
                                                         Item Name (Item Name from the
ERP)
If left blank, the item name of the entered ERP's item code will be used.
              Spec. STRING(100)
                                                 Specification (Spec. from the ERP)
SIZE DES
If left blank the specification of the entered ERP's item code will be used.
The field must be entered if set as [Required]. (Required status can be set up in Inv. I >
Production > New Job Order > Option > Input Screen Setting > Bottom tab)
UQTY Aux. Qtv.
                     NUMERIC(28,10)
                                                         Aux. Qtv.
The field must be entered if set as [Required]. (Required status can be set up in Inv. I >
Production > New Job Order > Option > Input Screen Setting > Bottom tab)
QTY Qtv.
              NUMERIC(28,10)
                                                 Job Order Quantity
WH CD
              Location Code STRING(5)
                                                         Job Order Location code
The field must be entered if set as [Required]. (Required status can be set up in Inv. I >
Production > New Job Order > Option > Input Screen Setting > Bottom tab)
REMARKS
              Remarks
                            STRING(200)
                                                         Remarks
The field must be entered if set as [Required]. (Required status can be set up in Inv. I >
Production > New Job Order > Option > Input Screen Setting > Bottom tab)
ITEM CD
              Mgmt. Field
                           STRING(14)
                                                         Mamt. Field Code
P AMT1
              Amount 1
                            NUMERIC(28,10)
                                                                Enter only if is active in Inv.
>Job Order input screen > Option > Input Screen Setting > Amount 1 Bottom tab.
The field must be entered if set as [Required]. (Required status can be set up in Inv. I >
Production > New Job Order > Option > Input Screen Setting > Bottom tab)
P AMT2
              Amount 2
                            NUMERIC(28,10)
                                                                Enter only if is active in Inv.
>Job Order input screen > Option > Input Screen Setting > Amount 2 Bottom tab.
The field must be entered if set as [Required]. (Required status can be set up in Inv. I >
Production > New Job Order > Option > Input Screen Setting > Bottom tab)
P REMARKS1
                     Remarks 1
                                   STRING(100)
                                                                Enter only if is active in Inv.
>Job Order input screen > Option > Input Screen Setting > Remarks 1 Bottom tab.
The field must be entered if set as [Required]. (Required status can be set up in Inv. I >
Production > New Job Order > Option > Input Screen Setting > Bottom tab)
P REMARKS2
                     Remarks 2
                                   STRING(100)
                                                                Enter only if is active in Inv.
>Job Order input screen > Option > Input Screen Setting > Remarks 2 Bottom tab.
The field must be entered if set as [Required]. (Required status can be set up in Inv. I >
Production > New Job Order > Option > Input Screen Setting > Bottom tab)
P REMARKS3
                     Remarks 3
                                   STRING(100)
                                                                Enter only if is active in Inv.
>Job Order input screen > Option > Input Screen Setting > Remarks 3 Bottom tab.
The field must be entered if set as [Required]. (Required status can be set up in Inv. I >
Production > New Job Order > Option > Input Screen Setting > Bottom tab)
PROD BOM DES
                     BOM ver.
                                   STRING(100)
                                                                Manufactured BOM Ver.
Enter the BOM version of the manufactured item
If not entered, the default BOM ver. will be applied
Result
Parameter
              Parameter Name
                                   Characters
                                                  Requirement Status Description
Status Processed Results
                                   Υ
                                          200 (Normal)
```

```
Error Error
                           If an error occurred
Code Error Code
Message
             Error Message
                    Error Details
MessageDetail
Data
                           Repeated part
SuccessCnt Number of SuccessesSTRING(20) Y
FailCnt Number of Failures
                          STRING(20) Y
ResultDetails Processed Results
                                 STRING(4000)
                                                      Υ
SlipNos
             Job Order No.(ERP) STRING(20) Y
                                                      Job Order No.(Blank if failed)
                    EXPIRE DATE
                                               Υ
                                                      The current API version will expire
EXPIRE DATE
on
                    Allowed Qty.
                                        Υ
                                               Qty. that can be allowed to send during 1
QUANTITY_INFO
hour, 1 day
             Sequence No. for Log Analysis
                                                      Υ
                                                             Sequence No. for Log
TRACE ID
Analysis When Error
Example Parameter
URL:
https://oapi{ZONE}.ecount.com/OAPI/V2/JobOrder/SaveJobOrder?SESSION ID={SESSION I
D}
// Replace {ZONE} with real zone information when entering Zone data.(Without {})
   "JobOrderList": [{
   "BulkDatas": {
   "IO DATE": "20180612",
    "UPLOAD_SER_NO": "",
    "CUST": "",
    "CUST_DES": "",
   "PJT CD": "",
    "EMP_CD": "",
    "TIME_DATE": "",
    "DOC_NO": "",
    "TTL CTT": "",
    "U_MEMO1": "",
    "U MEMO2": "",
    "U_MEMO3": "",
   "U MEMO4": "",
    "U_MEMO5": "",
    "U TXT1": "",
    "PROD_CD": "00001",
   "PROD DES": "test",
    "SIZE DES": "",
    "UQTY": "",
    "QTY": "1",
    "WH CD": "",
```

```
"REMARKS": "",
 "ITEM_CD": "",
 "P AMT1": "",
 "P_AMT2": "",
 "P_REMARKS1": "",
 "P_REMARKS2": "",
 "P_REMARKS3": "",
 "PROD_BOM_DES": ""
}
},{
"BulkDatas": {
 "IO_DATE": "20180612",
 "UPLOAD_SER_NO": "",
 "CUST": "",
 "CUST_DES": "",
 "PJT_CD": "",
 "EMP_CD": "",
 "TIME_DATE": "",
 "DOC_NO": "",
 "U MEMO1": "",
 "U_MEMO2": "",
 "U_MEMO3": "",
 "U_MEMO4": "",
 "U_MEMO5": "",
 "U_TXT1": "",
 "PROD_CD": "00001",
 "PROD_DES": "test",
 "SIZE_DES": "",
 "UQTY": "",
 "QTY": "1",
 "WH_CD": "",
 "REMARKS": "",
 "ITEM_CD": "",
 "P_AMT1": "",
 "P_AMT2": "",
 "P_REMARKS1": "",
 "P_REMARKS2": "",
 "P_REMARKS3": "",
 "PROD_BOM_DES": ""
}
}]
```

}

```
[SUCCESS]
   "Data": {
    "EXPIRE DATE":"",
    "QUANTITY INFO": Maximum number of consecutive errors per hour": 1/30," 1 hour
Allowable Amount": 3/6000," 1 day Allowable Amount": 3/10000",
   "TRACE_ID": "db6138411aad40e42dc5e209f65f6f3c".
    "SuccessCnt": 2,
   "FailCnt": 0,
    "ResultDetails": [{"IsSuccess": true, "TotalError": "[Slip Bundle1] OK", "Errors": [], "Code": null}
               {"IsSuccess": true, "TotalError": "[Slip Bundle1] OK", "Errors": [], "Code": null}]",
  ],
    "SlipNos": ["20180612-1"]
   "Status": "200",
   "Error": null,
   "Timestamp": "2018-06-12 13:15:47.613",
   "RequestKey": "",
   "IsEnableNoL4": false
}
[FAIL - Validation]
{
   "Data": {
    "EXPIRE_DATE":"",
    "QUANTITY INFO": Maximum number of consecutive errors per hour": 1/30," 1 hour
Allowable Amount": 3/6000," 1 day Allowable Amount": 3/10000",
    "SuccessCnt": 0,
   "FailCnt": 1,
    "ResultDetails": "[{"IsSuccess": false, "TotalError": "[Slip Bundle 1] Date (E.D.R.P.)", "Errors":
[{"ColCd": "IO_DATE", "Message": "Date (E.D.R.P.)"}], "Code": null},
               {"IsSuccess": false, "TotalError": "[Slip Bundle 2] Date (E.D.R.P.)", "Errors":
[{"ColCd": "IO DATE", "Message": "Date (E.D.R.P.)"}], "Code": null}]"
    "SlipNos": null
   },
   "Status": "200",
   "Error": null,
   "Timestamp": "2018-06-12 13:15:10.034",
   "RequestKey": "",
   "IsEnableNoL4": false
}
```

Description by Error Type Please click the View Details link for a detailed description of each error type. View Details

Goods Issued API

$\overline{}$			
Οv	Δr	1/14	$\Delta V A$
\smile v	CI.	VI	- v v

You can input Goods Issued data into Ecount ERP by linking it with the external service system.

However, since only the fields added to the default input screen template within ERP can be entered

Template Required Fields(Parameter) of the input API are different for each company code

When sending a field that is not added to the input screen template, the data of that field is not entered.

Requested Data Format

Field	Description
Calling Method	POST
Content-Ty	application/json
Test URL	https://sboapi{ZONE}.ecount.com/OAPI/V2/GoodsIssued/SaveGoodsIssued?SESSION_ID={SESSION_ID}
Request URL	https://oapi{ZONE}.ecount.com/OAPI/V2/GoodsIssued/SaveGoodsIssued?SESSION_ID={SESSION_ID}

Types of	
Data	JSON(Paramenter, Result)
Format	

Types of Data Format

Parameter	Parameter Name	Charact ers	nt	Templ ate Requi red	Description
SESSION_I	Session ID	STRIN G(50)	Y		SESSION_ID (Session ID) that is given after calling the Login API.
Goodslssue dList					
[BulkData s]	Information by each Sales Order Slip				Repeated part
					Sequence
UPLO AD_S ER_N O SMALLI NT(4,0)	Y		* Entries - If you want to bundle them into the same slip, give the same order number.		
					- It will considered part of the same slip based on the entered [Sequence] and [Batch Import Bundling Settings].

				* Character Limit - Up to 4 characters.
IO_DA TE	Date	STRIN G(8)		Goods Issue Date If left blank, the current date will be used.
EMP_ CD	PIC	STRIN G(30)		PIC Code (PIC Code from the ERP) The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Top tab)
WH_C D_F	Location-Out	STRIN G(5)	Y	Location-Out(Location Code from the ERP)
WH_C D_T	Factory	STRIN G(5)	Y	Factory(Location Code from the ERP)
PJT_C D	Project	STRIN G(14)		Project Code The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Top tab)
DOC_ NO	Goods Issued No.	STRIN G(30)		Goods Issued

			The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Top tab)
TTL_C TT	Title	STRIN G(200)	Title Enter the field only if set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Top tab > 'Title' Default setting > Designate Manually.
U_ME MO1	Text Type 1	STRIN G(200)	Enter the field if set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Top tab. The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Top tab)
U_ME MO2	Text Type 2	STRIN G(200)	Enter the field if set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Top tab. The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Top tab)
U_ME MO3	Text Type 3	STRIN G(200)	Enter the field if set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Top tab. The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Top tab)
U_ME MO4	Text Type 4	STRIN G(200)	Enter the field if set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Top tab.

			The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Top tab)
U_ME MO5	Text Type 5	STRIN G(200)	Enter the field if set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Top tab. The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Top tab)
U_TX T1	Long Text Type1	STRIN G(2000	Enter the field if set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Top tab. The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Top tab)
PLAN _DAT E	Job Order Date	STRIN G(8)	Job Order No. The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Bottom tab)
PLAN _NO	Job Order No.	NUME RIC(5,0	Enter the field if set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Top tab.
PLAN _PRO D	Job Order Items	STRIN G(20)	Job Order Item Code The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Bottom tab)

PROD _CD	Item Code	STRIN G(20)	Y	Item Code (Item Code from the ERP)
PROD _DES	Item Name	STRIN G(100)		Item Name (Item Name from the ERP) If left blank, the item name of the entered ERP's item code will be used.
SIZE_ DES	Spec.	STRIN G(100)		Specification (Spec. from the ERP) If left blank the specification of the entered ERP's item code will be used. The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Bottom tab)
UQTY	Aux. Qty.	NUME RIC(28, 10)		Enter only if using Aux. Qty. (* if set up to use Base Qty. and Aux. Qty. in User Customization > Configuration > Function Setup > Inv. tab > Quantity Units > Aux. Qty. Mgmt. Status > Status of Apply Aux. Quantity.) The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Bottom tab)
QTY	Qty.	NUME RIC(28, 10)	Y	Goods Issued Enter only if using Aux. Qty. (* if set up to use Base Qty. and Aux. Qty. in User Customization > Configuration > Function Setup > Inv. tab > Quantity Units > Aux. Qty. Mgmt. Status > Status of Apply Aux. Quantity.)

			The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Bottom tab)
REMA RKS	Remarks	STRIN G(200)	Remarks The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Bottom tab)
ITEM_ CD	Mgmt. Field	STRIN G(14)	Mgmt. Field Code
P_AM T1	Amount 1	NUME RIC(28, 10)	Enter only if is active in Inv. >Goods Issued input screen > Option > Input Screen Setting > Amount 1 Bottom tab. The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Bottom tab)
P_AM T2	Amount 2	NUME RIC(28, 10)	Enter only if is active in Inv. >Goods Issued input screen > Option > Input Screen Setting > Amount 2 Bottom tab. The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Bottom tab)
P_RE MARK S1	Remarks 1	STRIN G(100)	Enter only if is active in Inv. >Goods Issued input screen > Option > Input Screen Setting > Remarks 1 Bottom tab. The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Bottom tab)

P_RE MARK S2	Remarks 2	STRIN G(100)	Enter only if is active in Inv. >Goods Issued input screen > Option > Input Screen Setting > Remarks 2 Bottom tab. The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Bottom tab)
P_RE MARK S3	Remarks 3	STRIN G(100)	Enter only if is active in Inv. >Goods Issued input screen > Option > Input Screen Setting > Remarks 3 Bottom tab. The field must be entered if set as [Required]. (Required status can be set up in Inv. I > Production > New Goods Issued > Option > Input Screen Setting > Bottom tab)

Result

Parameter	Parameter Name	Chara cters	Req uire men t Stat us	Description
Status	Processed Results		Υ	200 (Normal)
Error	Error			If an error occurred
Code	Error Code			
Messag e	Error Message			

Messag eDetail	Error Details			
Data				Repeated part
Success Cnt	Number of Successes	STRIN G(20)	Y	
FailCnt	Number of Failures	STRIN G(20)	Y	
ResultD etails	Processed Results	STRIN G(400 0)	Y	
SlipNos	Goods Issued No.(ERP)	STRIN G(20)	Y	Goods Issued No.(Blank if failed)
EXPIRE _DATE	EXPIRE_DATE		Y	The current API version will expire on
QUANTI TY_INF O	Allowed Qty.		Y	Qty. that can be allowed to send during 1 hour, 1 day
TRACE_ ID	Sequence No. for Log Analysis		Y	Sequence No. for Log Analysis When Error

Example Parameter

```
// Replace {ZONE} with real zone information when entering Zone data.(Without {})
   "GoodsIssuedList": [{
   "BulkDatas": {
    "IO_DATE": "20180612",
    "UPLOAD_SER_NO": "",
    "EMP CD": "",
    "WH_CD_F": "00009",
    "WH_CD_T": "00022",
    "PJT_CD": "",
    "DOC_NO": "",
    "TTL_CTT": "",
    "U_MEMO1": "",
    "U_MEMO2": "",
    "U_MEMO3": "",
    "U_MEMO4": "",
    "U_MEMO5": "",
    "U_TXT1": "",
    "PLAN_DATE": "",
    "PLAN_NO": "",
    "PLAN_PROD": "",
    "PROD_CD": "00002",
    "PROD_DES": "테스트",
    "SIZE_DES": "",
    "UQTY": "",
    "QTY": "1",
    "REMARKS": "",
    "ITEM_CD": "",
    "P_AMT1": "",
    "P AMT2": "",
    "P_REMARKS1": "",
    "P_REMARKS2": "",
    "P_REMARKS3": ""
   }
  },{
   "BulkDatas": {
    "IO_DATE": "20180612",
    "UPLOAD_SER_NO": "",
    "EMP CD": "",
    "WH_CD_F": "00009",
    "WH_CD_T": "00022",
    "PJT_CD": "",
    "DOC_NO": "",
    "TTL_CTT": "",
    "U_MEMO1": "",
    "U_MEMO2": "",
    "U_MEMO3": "",
    "U_MEMO4": "",
    "U_MEMO5": "",
    "U_TXT1": "",
    "PLAN_DATE": "",
    "PLAN_NO": "",
    "PLAN_PROD": "",
    "PROD CD": "00002",
    "PROD_DES": "테스트",
    "SIZE_DES": "",
    "UQTY": "",
```

```
"QTY": "1",
    "REMARKS": "",
    "ITEM_CD": "",
    "P_AMT1": ""
    "P_AMT2": "",
    "P_REMARKS1": ""
    "P_REMARKS2": "",
    "P_REMARKS3": ""
  }]
}
Example Result
[SUCCESS]
   "Data": {
   "EXPIRE_DATE":"",
   "QUANTITY_INFO": Maximum number of consecutive errors per hour": 1/30," 1 hour Allowable Amount": 3/6000," 1
day Allowable Amount": 3/10000",
   "TRACE_ID": "db6138411aad40e42dc5e209f65f6f3c",
   "SuccessCnt": 2,
   "FailCnt": 0,
   "ResultDetails": [{"IsSuccess": true, "TotalError": "[Slip Bundle1] OK", "Errors": [], "Code": null}
               {"IsSuccess": true, "TotalError": "[Slip Bundle1] OK", "Errors": [], "Code": null}],
   "SlipNos": ["20180612-1"]
   "Status": "200",
   "Error": null,
   "Timestamp": "2018-06-12 13:20:30.218",
   "RequestKey": "",
   "IsEnableNoL4": false
}
[FAIL - Validation]
   "Data": {
   "EXPIRE_DATE":"",
   "QUANTITY_INFO": Maximum number of consecutive errors per hour": 1/30," 1 hour Allowable Amount": 3/6000," 1
day Allowable Amount": 3/10000",
   "SuccessCnt": 0,
   "FailCnt": 2,
   "ResultDetails":
   {"IsSuccess": false, "TotalError": "[Slip Bundle1] Location-Out (Required), Factory (Required), Item Code (Required),
Item Name (Required), Qty. (Required), Location-Out (Location-out and Factory are the same.)",
    "Errors": [{"ColCd": "WH_CD_F", "Message": "Location-Out (Required)},
           {"ColCd": "WH_CD_T", "Message": "Factory (Required)"},
```

```
{"ColCd": "PROD_CD", "Message": "Item Code (Required)"},
           {"ColCd": "PROD_DES", "Message": "Item Name (Required)"},
           {"ColCd": "QTY","Message": "Qty. (Required)"},
           {"ColCd": "WH_CD_F","Message": "Location-Out (Location-out and Factory are the same.)"}},
   {"IsSuccess": false, "TotalError": "[Slip Bundle1] Location-Out (Required), Factory (Required), Item Code (Required),
Item Name (Required), Qty. (Required), Location-Out (Location-out and Factory are the same.)",
     "Errors": [{"ColCd": "WH_CD_F", "Message": "Location-Out (Required)},
           {"ColCd": "WH_CD_T","Message": "Factory (Required)"},
           {"ColCd": "PROD_CD", "Message": "Item Code (Required)"},
           {"ColCd": "PROD_DES", "Message": "Item Name (Required)"},
           {"ColCd": "QTY", "Message": "Qty. (Required)"},
           {"ColCd": "WH_CD_F","Message": "Location-Out (Location-out and Factory are the same.)"}
   ],"Code": null}],
   "SlipNos": null
   "Status": "200",
   "Error": null,
   "Timestamp": "2018-06-12 13:17:38.181",
   "RequestKey": "",
   "IsEnableNoL4": false
}
Description by Error Type
```