NASM - The Netwide Assembler

version 2.15.05





Contents

Chapter 1: Introduction	7
1.1 What Is NASM?	7
1.1.1 License	7
Chapter 2: Running NASM	9
2.1 NASM Command-Line Syntax	9
2.1.1 The -o Option: Specifying the Output File Name	9
2.1.2 The -f Option: Specifying the Output File Format	0
2.1.3 The -l Option: Generating a Listing File	0
2.1.4 The -∟ Option: Additional or Modified Listing Info	0
2.1.5 The -м Option: Generate Makefile Dependencies	1
2.1.6 The -MG Option: Generate Makefile Dependencies	1
2.1.7 The -MF Option: Set Makefile Dependency File	1
2.1.8 The -MD Option: Assemble and Generate Dependencies	1
2.1.9 The -мт Option: Dependency Target Name	1
2.1.10 The -мQ Option: Dependency Target Name (Quoted)	1
2.1.11 The -MP Option: Emit phony targets	1
2.1.12 The -Mw Option: Watcom Make quoting style	1
2.1.13 The -F Option: Selecting a Debug Information Format	2
2.1.14 The -g Option: Enabling Debug Information	2
2.1.15 The -x Option: Selecting an Error Reporting Format	2
2.1.16 The -z Option: Send Errors to a File	2
2.1.17 The -s Option: Send Errors to stdout	2
2.1.18 The -i Option: Include File Search Directories	3
2.1.19 The -p Option: Pre-Include a File	3
2.1.20 The -d Option: Pre-Define a Macro	3
2.1.21 The -u Option: Undefine a Macro	3
2.1.22 The -E Option: Preprocess Only	4
2.1.23 The -a Option: Don't Preprocess At All	4
2.1.24 The -0 Option: Specifying Multipass Optimization	4
2.1.25 The -t Option: Enable TASM Compatibility Mode	4
2.1.26 The -w and -w Options: Enable or Disable Assembly Warnings	5
2.1.27 The -v Option: Display Version Info	9
2.1.28 The(g l)prefix,(g l)postfix Options	9

	2.1.29 Thepragma Option
	2.1.30 Thebefore Option
	2.1.31 Thelimit-x Option
	2.1.32 Thekeep-all Option
	2.1.33 Theno-line Option
	2.1.34 Thereproducible Option
	2.1.35 The NASMENV Environment Variable
2.2	2 Quick Start for MASM Users
	2.2.1 NASM Is Case-Sensitive
	2.2.2 NASM Requires Square Brackets For Memory References
	2.2.3 NASM Doesn't Store Variable Types
	2.2.4 NASM Doesn't ASSUME
	2.2.5 NASM Doesn't Support Memory Models
	2.2.6 Floating-Point Differences
	2.2.7 Other Differences
	2.2.8 MASM compatibility package
Chap	ter 3: The NASM Language
3.	L Layout of a NASM Source Line
3.2	2 Pseudo-Instructions
	3.2.1 Dx: Declaring Initialized Data
	3.2.2 RESB and Friends: Declaring Uninitialized Data
	3.2.3 INCBIN: Including External Binary Files
	3.2.4 Equ: Defining Constants
	3.2.5 TIMES: Repeating Instructions or Data
3.3	B Effective Addresses
3.4	1 Constants
	3.4.1 Numeric Constants
	3.4.2 Character Strings
	3.4.3 Character Constants
	3.4.4 String Constants
	3.4.5 Unicode Strings
	3.4.6 Floating-Point Constants
	3.4.7 Packed BCD Constants
3.5	Expressions
	3.5.1 ? :: Conditional Operator
	3.5.2: : Boolean OR Operator

	3.5.3 : ^^: Boolean XOR Operator	41
	3.5.4: &&: Boolean AND Operator	41
	3.5.5 : Comparison Operators	41
	3.5.6 : Bitwise OR Operator	42
	3.5.7 ^: Bitwise XOR Operator	42
	3.5.8 &: Bitwise AND Operator	42
	3.5.9 Bit Shift Operators	42
	3.5.10 + and -: Addition and Subtraction Operators	42
	3.5.11 Multiplication, Division and Modulo	42
	3.5.12 Unary Operators	42
3	3.6 seg and wr $ au$	43
3	3.7 STRICT: Inhibiting Optimization	43
3	3.8 Critical Expressions	44
3	3.9 Local Labels	44
Cha	apter 4: The NASM Preprocessor	47
4	4.1 Single-Line Macros	47
	4.1.1 The Normal Way: %define	47
	4.1.2 Resolving %define: %xdefine	48
	4.1.3 Macro Indirection: %[]	49
	4.1.4 Concatenating Single Line Macro Tokens: %+	49
	4.1.5 The Macro Name Itself: %? and %??	50
	4.1.6 The Single-Line Macro Name: **? and **??	50
	4.1.7 Undefining Single-Line Macros: %undef	51
	4.1.8 Preprocessor Variables: %assign	51
	4.1.9 Defining Strings: %defstr	51
	4.1.10 Defining Tokens: %deftok	52
	4.1.11 Defining Aliases: %defalias	52
	4.1.12 Conditional Comma Operator: %,	52
4	4.2 String Manipulation in Macros	52
	4.2.1 Concatenating Strings: %strcat	53
	4.2.2 String Length: %strlen	53
	4.2.3 Extracting Substrings: %substr	53
4	4.3 Multi-Line Macros: %macro	53
	4.3.1 Overloading Multi-Line Macros	54
	4.3.2 Macro-Local Labels	55
	4.3.3 Greedy Macro Parameters	55

4.3.4 Macro Parameters Range	56
4.3.5 Default Macro Parameters	56
4.3.6 %0: Macro Parameter Counter	57
4.3.7 %00: Label Preceeding Macro	57
4.3.8 %rotate: Rotating Macro Parameters	57
4.3.9 Concatenating Macro Parameters	58
4.3.10 Condition Codes as Macro Parameters	59
4.3.11 Disabling Listing Expansion	59
4.3.12 Undefining Multi-Line Macros: %unmacro	60
4.4 Conditional Assembly	60
4.4.1%ifdef: Testing Single-Line Macro Existence	60
4.4.2% ifmacro: Testing Multi-Line Macro Existence	61
4.4.3 %ifctx: Testing the Context Stack	61
4.4.4% if: Testing Arbitrary Numeric Expressions	61
4.4.5 %ifidn and %ifidni: Testing Exact Text Identity	61
4.4.6%ifid,%ifnum,%ifstr:Testing Token Types	62
4.4.7 %iftoken: Test for a Single Token	62
4.4.8% if empty: Test for Empty Expansion	63
4.4.9% i fenv: Test If Environment Variable Exists	63
4.5 Preprocessor Loops: %rep	63
4.6 Source Files and Dependencies	64
4.6.1%include: Including Other Files	64
4.6.2% pathsearch: Search the Include Path	64
4.6.3 %depend: Add Dependent Files	64
4.6.4 %use: Include Standard Macro Package	65
4.7 The Context Stack	65
4.7.1 %push and %pop: Creating and Removing Contexts	65
4.7.2 Context-Local Labels	65
4.7.3 Context-Local Single-Line Macros	66
4.7.4 Context Fall-Through Lookup (deprecated)	66
4.7.5 %repl: Renaming a Context	67
4.7.6 Example Use of the Context Stack: Block IFs	67
4.8 Stack Relative Preprocessor Directives	68
4.8.1% arg Directive	68
4.8.2 %stacksize Directive	69
4.8.3 %local Directive	69

4.9 Reporting User-Defined Errors: %error, %warning, %fatal	70
4.10 %pragma: Setting Options	70
4.10.1 Preprocessor Pragmas	71
4.11 Other Preprocessor Directives	71
4.11.1 %line Directive	71
4.11.2 %! variable: Read an Environment Variable	72
4.11.3 %clear: Clear All Macro Definitions	72
Chapter 5: Standard Macros	73
5.1 NASM Version Macros	73
5.1.1?NASM_VERSION_ID?: NASM Version ID	73
5.1.2?NASM_VER?: NASM Version String	73
5.2?FILE? and?LINE?: File Name and Line Number	73
5.3?BITS?: Current Code Generation Mode	74
5.4?OUTPUT_FORMAT?: Current Output Format	74
5.5?DEBUG_FORMAT?: Current Debug Format	74
5.6 Assembly Date and Time Macros	74
5.7?use_ <i>package</i> ?: Package Include Test	75
5.8?PASS?: Assembly Pass	75
5.9 Structure Data Types	75
5.9.1 STRUC and ENDSTRUC: Declaring Structure Data Types	75
5.9.2 ISTRUC, AT and IEND: Declaring Instances of Structures	76
5.10 Alignment Control	77
5.10.1 ALIGN and ALIGNB: Code and Data Alignment	77
5.10.2 SECTALIGN: Section Alignment	78
Chapter 6: Standard Macro Packages	79
6.1 altreg: Alternate Register Names	79
6.2 smartalign: Smart ALIGN Macro	79
6.3 fp: Floating-point macros	80
6.4 i func: Integer functions	80
6.4.1 Integer logarithms	80
6.5 masm: MASM compatibility	80
Chapter 7: Assembler Directives	83
7.1 BITS: Specifying Target Processor Mode	83
7.1.1 USE16 & USE32: Aliases for BITS	84
7.2 DEFAULT: Change the assembler defaults	84
7.2.1 REL & ABS: RIP-relative addressing	84

7.2.2 BND & NOBND: BND prefix	84
7.3 SECTION or SEGMENT: Changing and Defining Sections	84
7.3.1 The?SECT? Macro	84
7.4 ABSOLUTE: Defining Absolute Labels	85
7.5 EXTERN: Importing Symbols from Other Modules	86
7.6 REQUIRED: Unconditionally Importing Symbols from Other Modules	86
7.7 GLOBAL: Exporting Symbols to Other Modules	86
7.8 COMMON: Defining Common Data Areas	87
7.9 STATIC: Local Symbols within Modules	87
7.10 (G L)PREFIX, (G L)POSTFIX: Mangling Symbols	87
7.11 CPU: Defining CPU Dependencies	88
7.12 FLOAT: Handling of floating-point constants	88
7.13 [WARNING]: Enable or disable warnings	89
Chapter 8: Output Formats	91
8.1 bin: Flat-Form Binary Output	91
8.1.1 ORG: Binary File Program Origin	91
8.1.2 bin Extensions to the SECTION Directive, bin extensions to } $\dots \dots \dots$	91
8.1.3 Multisection Support for the bin Format	92
8.1.4 Map Files	92
8.2 ith: Intel Hex Output	92
8.3 srec: Motorola S-Records Output	92
8.4 obj: Microsoft OMF Object Files	93
8.4.1 obj Extensions to the SEGMENT Directive	93
8.4.2 GROUP: Defining Groups of Segments	94
8.4.3 UPPERCASE: Disabling Case Sensitivity in Output	94
8.4.4 IMPORT: Importing DLL Symbols	95
8.4.5 EXPORT: Exporting DLL Symbols	95
8.4.6 start: Defining the Program Entry Point	95
8.4.7 obj Extensions to the EXTERN Directive	96
8.4.8 obj Extensions to the COMMON Directive	96
8.4.9 Embedded File Dependency Information	97
8.5 win32: Microsoft Win32 Object Files	97
8.5.1 win32 Extensions to the SECTION Directive	97
8.5.2 win32: Safe Structured Exception Handling	98
8.5.3 Debugging formats for Windows	99
8.6 win64: Microsoft Win64 Object Files	99

	8.6.1 win64: Writing Position-Independent Code
	8.6.2 win64: Structured Exception Handling
	8.7 coff: Common Object File Format
	8.8 macho32 and macho64: Mach Object File Format
	8.8.1 macho extensions to the SECTION Directive
	8.8.2 Thread Local Storage in Mach-O: macho special symbols and WRT
	8.8.3 macho specfic directive subsections_via_symbols
	8.8.4 macho specfic directive no_dead_strip
	8.8.5 macho specific extensions to the GLOBAL Directive: private_extern
	8.9 elf32, elf64, elfx32: Executable and Linkable Format Object Files
	8.9.1 ELF specific directive osabi
	8.9.2 ELF extensions to the SECTION Directive
	8.9.3 Position-Independent Code: ELF Special Symbols and WRT
	8.9.4 Thread Local Storage in ELF: elf Special Symbols and wRT
	8.9.5 elf Extensions to the GLOBAL Directive
	8.9.6 elf Extensions to the EXTERN Directive
	8.9.7 elf Extensions to the COMMON Directive
	8.9.8 16-bit code and ELF
	8.9.9 Debug formats and ELF
	8.10 aout: Linux a.out Object Files
	8.11 aoutb: NetBSD/FreeBSD/OpenBSD a . out Object Files
	8.12 as86: Minix/Linux as86 Object Files
	8.13 rdf: Relocatable Dynamic Object File Format (deprecated)
	8.13.1 Requiring a Library: The LIBRARY Directive
	8.13.2 Specifying a Module Name: The MODULE Directive
	8.13.3 rdf Extensions to the GLOBAL Directive
	8.13.4 rdf Extensions to the EXTERN Directive
	8.14 dbg: Debugging Format
C	hapter 9: Writing 16-bit Code (DOS, Windows 3/3.1)
	9.1 Producing .EXE Files
	9.1.1 Using the obj Format To Generate .EXE Files
	9.1.2 Using the bin Format To Generate .EXE Files
	9.2 Producing .COM Files
	9.2.1 Using the bin Format To Generate .com Files
	9.2.2 Using the obj Format To Generate .com Files
	9.3 Producing .sys Files

9.4 Interfacing to 16-bit C Programs
9.4.1 External Symbol Names
9.4.2 Memory Models
9.4.3 Function Definitions and Function Calls
9.4.4 Accessing Data Items
9.4.5 c16.mac: Helper Macros for the 16-bit C Interface
9.5 Interfacing to Borland Pascal Programs
9.5.1 The Pascal Calling Convention
9.5.2 Borland Pascal Segment Name Restrictions
9.5.3 Using c16.mac With Pascal Programs
Chapter 10: Writing 32-bit Code (Unix, Win32, DJGPP)
10.1 Interfacing to 32-bit C Programs
10.1.1 External Symbol Names
10.1.2 Function Definitions and Function Calls
10.1.3 Accessing Data Items
10.1.4 c32.mac: Helper Macros for the 32-bit C Interface
10.2 Writing NetBSD/FreeBSD/OpenBSD and Linux/ELF Shared Libraries
10.2.1 Obtaining the Address of the GOT
10.2.2 Finding Your Local Data Items
10.2.3 Finding External and Common Data Items
10.2.4 Exporting Symbols to the Library User
10.2.5 Calling Procedures Outside the Library
10.2.6 Generating the Library File
Chapter 11: Mixing 16- and 32-bit Code
11.1 Mixed-Size Jumps
11.2 Addressing Between Different-Size Segments
11.3 Other Mixed-Size Instructions
Chapter 12: Writing 64-bit Code (Unix, Win64)
12.1 Register Names in 64-bit Mode
12.2 Immediates and Displacements in 64-bit Mode
12.3 Interfacing to 64-bit C Programs (Unix)
12.4 Interfacing to 64-bit C Programs (Win64)
Chapter 13: Troubleshooting
13.1 Common Problems
13.1.1 NASM Generates Inefficient Code
13.1.2 My Jumps are Out of Range

13.1.3 ORG Doesn't Work
13.1.4 TIMES Doesn't Work
Appendix A: Ndisasm
A.1 Introduction
A.2 Running NDISASM
A.2.1 COM Files: Specifying an Origin
A.2.2 Code Following Data: Synchronization
A.2.3 Mixed Code and Data: Automatic (Intelligent) Synchronization
A.2.4 Other Options
Appendix B: Instruction List
B.1 Introduction
B.1.1 Special instructions (pseudo-ops)
B.1.2 Conventional instructions
B.1.3 Katmai Streaming SIMD instructions (SSE a.k.a. KNI, XMM, MMX2)
B.1.4 Introduced in Deschutes but necessary for SSE support
B.1.5 XSAVE group (AVX and extended state)
B.1.6 Generic memory operations
B.1.7 New MMX instructions introduced in Katmai
B.1.8 AMD Enhanced 3DNow! (Athlon) instructions
B.1.9 Willamette SSE2 Cacheability Instructions
B.1.10 Willamette MMX instructions (SSE2 SIMD Integer Instructions)
B.1.11 Willamette Streaming SIMD instructions (SSE2)
B.1.12 Prescott New Instructions (SSE3)
B.1.13 VMX/SVM Instructions
B.1.14 Extended Page Tables VMX instructions
B.1.15 Tejas New Instructions (SSSE3)
B.1.16 AMD SSE4A
B.1.17 New instructions in Barcelona
B.1.18 Penryn New Instructions (SSE4.1)
B.1.19 Nehalem New Instructions (SSE4.2)
B.1.20 Intel SMX
B.1.21 Geode (Cyrix) 3DNow! additions
B.1.22 Intel new instructions in ???
B.1.23 Intel AES instructions
B.1.24 Intel AVX AES instructions
B.1.25 Intel instruction extension based on pub number 319433-030 dated October 2017173

	B.1.26 Intel AVX instructions	73
	B.1.27 Intel Carry-Less Multiplication instructions (CLMUL)	83
	B.1.28 Intel AVX Carry-Less Multiplication instructions (CLMUL)	83
	B.1.29 Intel Fused Multiply-Add instructions (FMA)	84
	B.1.30 Intel post-32 nm processor instructions	87
	B.1.31 VIA (Centaur) security instructions	87
	B.1.32 AMD Lightweight Profiling (LWP) instructions	87
	B.1.33 AMD XOP and FMA4 instructions (SSE5)	87
	B.1.34 Intel AVX2 instructions	90
	B.1.35 Intel Transactional Synchronization Extensions (TSX)	92
	B.1.36 Intel BMI1 and BMI2 instructions, AMD TBM instructions	93
	B.1.37 Intel Memory Protection Extensions (MPX)	93
	B.1.38 Intel SHA acceleration instructions	94
	B.1.39 AVX-512 mask register instructions	94
	B.1.40 AVX-512 mask register instructions (aliases requiring explicit size support)	95
	B.1.41 AVX-512 instructions	96
	B.1.42 Intel memory protection keys for userspace (PKU aka PKEYs)	27
	B.1.43 Read Processor ID	27
	B.1.44 New memory instructions	27
	B.1.45 Processor trace write	28
	B.1.46 Instructions from the Intel Instruction Set Extensions,	28
	B.1.47 doc 319433-034 May 2018	28
	B.1.48 Galois field operations (GFNI)	28
	B.1.49 AVX512 Vector Bit Manipulation Instructions 2	28
	B.1.50 AVX512 VNNI	29
	B.1.51 AVX512 Bit Algorithms	29
	B.1.52 AVX512 4-iteration Multiply-Add	30
	B.1.53 AVX512 4-iteration Dot Product	30
	B.1.54 Intel Software Guard Extensions (SGX)	30
	B.1.55 Intel Control-Flow Enforcement Technology (CET)	30
	B.1.56 Instructions from ISE doc 319433-040, June 2020	30
	B.1.57 AVX512 Bfloat16 instructions	30
	B.1.58 AVX512 mask intersect instructions	31
	B.1.59 Intel Advanced Matrix Extensions (AMX)	31
	B.1.60 Systematic names for the hinting nop instructions	31
Appe	ndix C: NASM Version History	35

C.1 NASM 2 Series	 .235
C.1.1 Version 2.15.05	 .235
C.1.2 Version 2.15.04	 .235
C.1.3 Version 2.15.03	 .235
C.1.4 Version 2.15.02	 .236
C.1.5 Version 2.15.01	 .236
C.1.6 Version 2.15	 .236
C.1.7 Version 2.14.03	 .237
C.1.8 Version 2.14.02	 .237
C.1.9 Version 2.14.01	 .237
C.1.10 Version 2.14	 .238
C.1.11 Version 2.13.03	 .239
C.1.12 Version 2.13.02	 .239
C.1.13 Version 2.13.01	 .239
C.1.14 Version 2.13	 .240
C.1.15 Version 2.12.02	 .241
C.1.16 Version 2.12.01	 .241
C.1.17 Version 2.12	 .241
C.1.18 Version 2.11.09	 .241
C.1.19 Version 2.11.08	 .242
C.1.20 Version 2.11.07	 .242
C.1.21 Version 2.11.06	 .242
C.1.22 Version 2.11.05	 .242
C.1.23 Version 2.11.04	 .242
C.1.24 Version 2.11.03	 .242
C.1.25 Version 2.11.02	 .242
C.1.26 Version 2.11.01	 .243
C.1.27 Version 2.11	 .243
C.1.28 Version 2.10.09	 .244
C.1.29 Version 2.10.08	 .244
C.1.30 Version 2.10.07	 .244
C.1.31 Version 2.10.06	 .244
C.1.32 Version 2.10.05	 .244
C.1.33 Version 2.10.04	 .244
C.1.34 Version 2.10.03	 .244
C.1.35 Version 2.10.02	.245

	C.1.36 Version 2.10.01		.245
	C.1.37 Version 2.10		.245
	C.1.38 Version 2.09.10		.245
	C.1.39 Version 2.09.09		.245
	C.1.40 Version 2.09.08		.245
	C.1.41 Version 2.09.07		.245
	C.1.42 Version 2.09.06		.245
	C.1.43 Version 2.09.05		.245
	C.1.44 Version 2.09.04		.246
	C.1.45 Version 2.09.03		.246
	C.1.46 Version 2.09.02		.246
	C.1.47 Version 2.09.01		.246
	C.1.48 Version 2.09		.246
	C.1.49 Version 2.08.02		.247
	C.1.50 Version 2.08.01		.247
	C.1.51 Version 2.08		.247
	C.1.52 Version 2.07		.248
	C.1.53 Version 2.06		.248
	C.1.54 Version 2.05.01		.249
	C.1.55 Version 2.05		.249
	C.1.56 Version 2.04		.249
	C.1.57 Version 2.03.01		.250
	C.1.58 Version 2.03		.250
	C.1.59 Version 2.02		.251
	C.1.60 Version 2.01		.251
	C.1.61 Version 2.00		.251
C.:	NASM 0.98 Series		.252
	C.2.1 Version 0.98.39		.252
	C.2.2 Version 0.98.38		.253
	C.2.3 Version 0.98.37		.253
	C.2.4 Version 0.98.36		.253
	C.2.5 Version 0.98.35		.253
	C.2.6 Version 0.98.34		.254
	C.2.7 Version 0.98.33		.254
	C.2.8 Version 0.98.32		.254
	C 2.9 Varsion 0.98.31		255

C.2.10 Version 0.98.30
C.2.11 Version 0.98.28
C.2.12 Version 0.98.26
C.2.13 Version 0.98.25alt
C.2.14 Version 0.98.25
C.2.15 Version 0.98.24p1
C.2.16 Version 0.98.24
C.2.17 Version 0.98.23
C.2.18 Version 0.98.22
C.2.19 Version 0.98.21
C.2.20 Version 0.98.20
C.2.21 Version 0.98.19
C.2.22 Version 0.98.18
C.2.23 Version 0.98.17
C.2.24 Version 0.98.16
C.2.25 Version 0.98.15
C.2.26 Version 0.98.14
C.2.27 Version 0.98.13
C.2.28 Version 0.98.12
C.2.29 Version 0.98.11
C.2.30 Version 0.98.10
C.2.31 Version 0.98.09
C.2.32 Version 0.98.08
C.2.33 Version 0.98.09b with John Coffman patches released 28-Oct-2001
C.2.34 Version 0.98.07 released 01/28/01
C.2.35 Version 0.98.06f released 01/18/01
C.2.36 Version 0.98.06e released 01/09/01
C.2.37 Version 0.98p1
C.2.38 Version 0.98bf (bug-fixed)
C.2.39 Version 0.98.03 with John Coffman's changes released 27-Jul-2000
C.2.40 Version 0.98.03
C.2.41 Version 0.98
C.2.42 Version 0.98p9
C.2.43 Version 0.98p8
C.2.44 Version 0.98p7
C.2.45 Version 0.98p6

C.2.46 Version 0.98p3.7
C.2.47 Version 0.98p3.6
C.2.48 Version 0.98p3.5
C.2.49 Version 0.98p3.4
C.2.50 Version 0.98p3.3
C.2.51 Version 0.98p3.2
C.2.52 Version 0.98p3-hpa
C.2.53 Version 0.98 pre-release 3
C.2.54 Version 0.98 pre-release 2
C.2.55 Version 0.98 pre-release 1
C.3 NASM 0.9 Series
C.3.1 Version 0.97 released December 1997
C.3.2 Version 0.96 released November 1997
C.3.3 Version 0.95 released July 1997
C.3.4 Version 0.94 released April 1997
C.3.5 Version 0.93 released January 1997
C.3.6 Version 0.92 released January 1997
C.3.7 Version 0.91 released November 1996
C.3.8 Version 0.90 released October 1996
Appendix D: Building NASM from Source
D.1 Building from a Source Archive
D.2 Building from the git Repository
D.3 Building the documentation
Appendix E: Contact Information
E.1 Website
E.1.1 User Forums
E.1.2 Development Community
E.2 Reporting Bugs

Chapter 1: Introduction

1.1 What Is NASM?

The Netwide Assembler, NASM, is an 80x86 and x86-64 assembler designed for portability and modularity. It supports a range of object file formats, including Linux and *BSD a.out, ELF, Mach-O, 16-bit and 32-bit .obj (OMF) format, COFF (including its Win32 and Win64 variants.) It can also output plain binary files, Intel hex and Motorola S-Record formats. Its syntax is designed to be simple and easy to understand, similar to the syntax in the Intel Software Developer Manual with minimal complexity. It supports all currently known x86 architectural extensions, and has strong support for macros.

1.1.1 License

NASM is under the so-called 2-clause BSD license, also known as the simplified BSD license:

Copyright 1996-2020 the NASM Authors – All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Chapter 2: Running NASM

2.1 NASM Command-Line Syntax

```
To assemble a file, you issue a command of the form
```

```
nasm -f <format> <filename> [-o <output>]
```

For example,

nasm -f elf myfile.asm

will assemble myfile.asm into an ELF object file myfile.o. And

nasm -f bin myfile.asm -o myfile.com

will assemble myfile.asm into a raw binary file myfile.com.

To produce a listing file, with the hex codes output from NASM displayed on the left of the original sources, use the -l option to give a listing file name, for example:

```
nasm -f coff myfile.asm -l myfile.lst
```

To get further usage instructions from NASM, try typing

nasm -h

The option --help is an alias for the -h option.

If you use Linux but aren't sure whether your system is a .out or ELF, type

file nasm

(in the directory in which you put the NASM binary when you installed it). If it says something like

```
nasm: ELF 32-bit LSB executable i386 (386 and up) Version 1
```

then your system is ELF, and you should use the option -f elf when you want NASM to produce Linux object files. If it says

```
nasm: Linux/i386 demand-paged executable (QMAGIC)
```

or something similar, your system is a .out, and you should use -f aout instead (Linux a .out systems have long been obsolete, and are rare these days.)

Like Unix compilers and assemblers, NASM is silent unless it goes wrong: you won't see any output at all, unless it gives error messages.

2.1.1 The -o Option: Specifying the Output File Name

NASM will normally choose the name of your output file for you; precisely how it does this is dependent on the object file format. For Microsoft object file formats (obj, win32 and win64), it will remove the .asm extension (or whatever extension you like to use – NASM doesn't care) from your source file name and substitute .obj. For Unix object file formats (aout, as86, coff, elf32, elf64, elfx32, ieee, macho32 and macho64) it will substitute .o. For dbg, rdf, ith and srec, it will use .dbg, .rdf, .ith and .srec, respectively, and for the bin format it will simply remove the extension, so that myfile.asm produces the output file myfile.

If the output file already exists, NASM will overwrite it, unless it has the same name as the input file, in which case it will give a warning and use nasm.out as the output file name instead.

For situations in which this behaviour is unacceptable, NASM provides the -o command-line option, which allows you to specify your desired output file name. You invoke -o by following it with the name you wish for the output file, either with or without an intervening space. For example:

```
nasm -f bin program.asm -o program.com
nasm -f bin driver.asm -odriver.sys
```

Note that this is a small o, and is different from a capital O, which is used to specify the number of optimization passes required. See section 2.1.24.

2.1.2 The -f Option: Specifying the Output File Format

If you do not supply the -f option to NASM, it will choose an output file format for you itself. In the distribution versions of NASM, the default is always bin; if you've compiled your own copy of NASM, you can redefine OF_DEFAULT at compile time and choose what you want the default to be.

Like -o, the intervening space between -f and the output file format is optional; so -f elf and -felf are both valid.

A complete list of the available output file formats can be given by issuing the command nasm -h.

2.1.3 The -1 Option: Generating a Listing File

If you supply the -1 option to NASM, followed (with the usual optional space) by a file name, NASM will generate a source-listing file for you, in which addresses and generated code are listed on the left, and the actual source code, with expansions of multi-line macros (except those which specifically request no expansion in source listings: see section 4.3.11) on the right. For example:

```
nasm -f elf myfile.asm -l myfile.lst
```

If a list file is selected, you may turn off listing for a section of your source with <code>[list -]</code>, and turn it back on with <code>[list +]</code>, (the default, obviously). There is no "user form" (without the brackets). This can be used to list only sections of interest, avoiding excessively long listings.

2.1.4 The -∟ Option: Additional or Modified Listing Info

Use this option to specify listing output details.

Supported options are:

- -Lb show builtin macro packages (standard and %use)
- -Ld show byte and repeat counts in decimal, not hex
- Le show the preprocessed input
- -Lf ignore .nolist and force listing output
- -Lm show multi-line macro calls with expanded parameters
- -Lp output a list file in every pass, in case of errors
- Ls show all single-line macro definitions
- -Lw flush the output after every line (very slow, mainly useful to debug NASM crashes)
- -L+ enable *all* listing options except -Lw (very verbose)

These options can be enabled or disabled at runtime using the %pragma list options directive:

```
%pragma list options [+|-]flags...
```

For example, to turn on the d and m flags but disable the s flag:

```
%pragma list options +dm -s
```

For forward compatility reasons, an undefined flag will be ignored. Thus, a new flag introduced in a newer version of NASM can be specified without breaking older versions. Listing flags will always be a single alphanumeric character and are case sensitive.

2.1.5 The -M Option: Generate Makefile Dependencies

This option can be used to generate makefile dependencies on stdout. This can be redirected to a file for further processing. For example:

nasm -M myfile.asm > myfile.dep

2.1.6 The -MG Option: Generate Makefile Dependencies

This option can be used to generate makefile dependencies on stdout. This differs from the -M option in that if a nonexisting file is encountered, it is assumed to be a generated file and is added to the dependency list without a prefix.

2.1.7 The -MF Option: Set Makefile Dependency File

This option can be used with the -M or -MG options to send the output to a file, rather than to stdout. For example:

nasm -M -MF myfile.dep myfile.asm

2.1.8 The -MD Option: Assemble and Generate Dependencies

The -MD option acts as the combination of the -M and -MF options (i.e. a filename has to be specified.) However, unlike the -M or -MG options, -MD does *not* inhibit the normal operation of the assembler. Use this to automatically generate updated dependencies with every assembly session. For example:

```
nasm -f elf -o myfile.o -MD myfile.dep myfile.asm
```

If the argument after -MD is an option rather than a filename, then the output filename is the first applicable one of:

- the filename set in the -MF option;
- the output filename from the -o option with .d appended;
- the input filename with the extension set to .d.

2.1.9 The -MT Option: Dependency Target Name

The -MT option can be used to override the default name of the dependency target. This is normally the same as the output filename, specified by the -o option.

2.1.10 The -MQ Option: Dependency Target Name (Quoted)

The -MQ option acts as the -MT option, except it tries to quote characters that have special meaning in Makefile syntax. This is not foolproof, as not all characters with special meaning are quotable in Make. The default output (if no -MT or -MQ option is specified) is automatically quoted.

2.1.11 The -MP Option: Emit phony targets

When used with any of the dependency generation options, the -MP option causes NASM to emit a phony target without dependencies for each header file. This prevents Make from complaining if a header file has been removed.

2.1.12 The -MW Option: Watcom Make quoting style

This option causes NASM to attempt to quote dependencies according to Watcom Make conventions rather than POSIX Make conventions (also used by most other Make variants.) This quotes # as \$# rather than \#, uses & rather than \ for continuation lines, and encloses filenames containing whitespace in double quotes.

2.1.13 The -F Option: Selecting a Debug Information Format

This option is used to select the format of the debug information emitted into the output file, to be used by a debugger (or *will* be). Prior to version 2.03.01, the use of this switch did *not* enable output of the selected debug info format. Use -g, see section 2.1.14, to enable output. Versions 2.03.01 and later automatically enable -g if -F is specified.

A complete list of the available debug file formats for an output format can be seen by issuing the command <code>nasm -h</code>. Not all output formats currently support debugging output.

This should not be confused with the -f dbg output format option, see section 8.14.

2.1.14 The -g Option: Enabling Debug Information.

This option can be used to generate debugging information in the specified format. See section 2.1.13. Using -g without -F results in emitting debug info in the default format, if any, for the selected output format. If no debug information is currently implemented in the selected output format, -g is *silently ignored*.

2.1.15 The -x Option: Selecting an Error Reporting Format

This option can be used to select an error reporting format for any error messages that might be produced by NASM.

Currently, two error reporting formats may be selected. They are the -xvc option and the -xgnu option. The GNU format is the default and looks like this:

```
filename.asm:65: error: specific error message
```

where filename.asm is the name of the source file in which the error was detected, 65 is the source file line number on which the error was detected, error is the severity of the error (this could be warning), and specific error message is a more detailed text message which should help pinpoint the exact problem.

The other format, specified by -Xvc is the style used by Microsoft Visual C++ and some other programs. It looks like this:

```
filename.asm(65) : error: specific error message
```

where the only difference is that the line number is in parentheses instead of being delimited by colons.

See also the Visual C++ output format, section 8.5.

2.1.16 The -z Option: Send Errors to a File

Under MS-DOS it can be difficult (though there are ways) to redirect the standard-error output of a program to a file. Since NASM usually produces its warning and error messages on stderr, this can make it hard to capture the errors if (for example) you want to load them into an editor.

NASM therefore provides the -z option, taking a filename argument which causes errors to be sent to the specified files rather than standard error. Therefore you can redirect the errors into a file by typing

```
nasm -Z myfile.err -f obj myfile.asm
```

In earlier versions of NASM, this option was called -E, but it was changed since -E is an option conventionally used for preprocessing only, with disastrous results. See section 2.1.22.

2.1.17 The -s Option: Send Errors to stdout

The -s option redirects error messages to stdout rather than stderr, so it can be redirected under MS-DOS. To assemble the file myfile.asm and pipe its output to the more program, you can type:

```
nasm -s -f obj myfile.asm | more
```

See also the -z option, section 2.1.16.

2.1.18 The -i Option: Include File Search Directories

When NASM sees the %include or %pathsearch directive in a source file (see section 4.6.1, section 4.6.2 or section 3.2.3), it will search for the given file not only in the current directory, but also in any directories specified on the command line by the use of the -i option. Therefore you can include files from a macro library, for example, by typing

```
nasm -ic:\macrolib\ -f obj myfile.asm
```

(As usual, a space between -i and the path name is allowed, and optional).

Prior NASM 2.14 a path provided in the option has been considered as a verbatim copy and providing a path separator been up to a caller. One could implicitly concatenate a search path together with a filename. Still this was rather a trick than something useful. Now the trailing path separator is made to always present, thus -ifoo will be considered as the -ifoo/ directory.

If you want to define a *standard* include search path, similar to /usr/include on Unix systems, you should place one or more -i directives in the NASMENV environment variable (see section 2.1.35).

For Makefile compatibility with many C compilers, this option can also be specified as -I.

2.1.19 The -p Option: Pre-Include a File

NASM allows you to specify files to be *pre-included* into your source file, by the use of the -p option. So running

```
nasm myfile.asm -p myinc.inc
```

is equivalent to running nasm myfile.asm and placing the directive %include "myinc.inc" at the start of the file.

--include option is also accepted.

For consistency with the -I, -D and -U options, this option can also be specified as -P.

2.1.20 The -d Option: Pre-Define a Macro

Just as the -p option gives an alternative to placing %include directives at the start of a source file, the -d option gives an alternative to placing a %define directive. You could code

```
nasm myfile.asm -dF00=100
```

as an alternative to placing the directive

```
%define F00 100
```

at the start of the file. You can miss off the macro value, as well: the option -dF00 is equivalent to coding %define F00. This form of the directive may be useful for selecting assembly-time options which are then tested using %ifdef, for example -dDEBUG.

For Makefile compatibility with many C compilers, this option can also be specified as -D.

2.1.21 The -u Option: Undefine a Macro

The -u option undefines a macro that would otherwise have been pre-defined, either automatically or by a -p or -d option specified earlier on the command lines.

For example, the following command line:

```
nasm myfile.asm -dF00=100 -uF00
```

would result in FOO *not* being a predefined macro in the program. This is useful to override options specified at a different point in a Makefile.

For Makefile compatibility with many C compilers, this option can also be specified as -u.

2.1.22 The -E Option: Preprocess Only

NASM allows the preprocessor to be run on its own, up to a point. Using the -E option (which requires no arguments) will cause NASM to preprocess its input file, expand all the macro references, remove all the comments and preprocessor directives, and print the resulting file on standard output (or save it to a file, if the -o option is also used).

This option cannot be applied to programs which require the preprocessor to evaluate expressions which depend on the values of symbols: so code such as

%assign tablesize (\$-tablestart)

will cause an error in preprocess-only mode.

For compatibility with older version of NASM, this option can also be written -e. -E in older versions of NASM was the equivalent of the current -z option, section 2.1.16.

2.1.23 The -a Option: Don't Preprocess At All

If NASM is being used as the back end to a compiler, it might be desirable to suppress preprocessing completely and assume the compiler has already done it, to save time and increase compilation speeds. The -a option, requiring no argument, instructs NASM to replace its powerful preprocessor with a stub preprocessor which does nothing.

2.1.24 The -0 Option: Specifying Multipass Optimization

Using the -0 option, you can tell NASM to carry out different levels of optimization. Multiple flags can be specified after the -0 options, some of which can be combined in a single option, e.g. -0xv.

- -00: No optimization. All operands take their long forms, if a short form is not specified, except conditional jumps. This is intended to match NASM 0.98 behavior.
- -01: Minimal optimization. As above, but immediate operands which will fit in a signed byte are optimized, unless the long form is specified. Conditional jumps default to the long form unless otherwise specified.
- -ox (where x is the actual letter x): Multipass optimization. Minimize branch offsets and signed immediate bytes, overriding size specification unless the strict keyword has been used (see section 3.7). For compatibility with earlier releases, the letter x may also be any number greater than one. This number has no effect on the actual number of passes.
- -0v: At the end of assembly, print the number of passes actually executed.

The -0x mode is recommended for most uses, and is the default since NASM 2.09.

Note that this is a capital o, and is different from a small o, which is used to specify the output file name. See section 2.1.1.

2.1.25 The -t Option: Enable TASM Compatibility Mode

NASM includes a limited form of compatibility with Borland's TASM. When NASM's -t option is used, the following changes are made:

- local labels may be prefixed with @@ instead of .
- size override is supported within brackets. In TASM compatible mode, a size override inside square
 brackets changes the size of the operand, and not the address type of the operand as it does in
 NASM syntax. E.g. mov eax,[DWORD val] is valid syntax in TASM compatibility mode. Note that you
 lose the ability to override the default address type for the instruction.
- unprefixed forms of some directives supported (arg, elif, else, endif, if, ifdef, ifdifi, ifndef, include, local)

2.1.26 The -w and -w Options: Enable or Disable Assembly Warnings

NASM can observe many conditions during the course of assembly which are worth mentioning to the user, but not a sufficiently severe error to justify NASM refusing to generate an output file. These conditions are reported like errors, but come up with the word 'warning' before the message. Warnings do not prevent NASM from generating an output file and returning a success status to the operating system.

Some conditions are even less severe than that: they are only sometimes worth mentioning to the user. Therefore NASM supports the -w command-line option, which enables or disables certain classes of assembly warning. Such warning classes are described by a name, for example label-orphan; you can enable warnings of this class by the command-line option -w+label-orphan and disable it by -w-label-orphan.

The current warning classes are:

- all is an group alias for *all* warning classes. Thus, -w+all enables all available warnings, and -w-all disables warnings entirely (since NASM 2.13).
- bad-pragma is a backwards compatibility alias for pragma-bad.
- bnd warns about ineffective use of the BND prefix when the JMP instruction is converted to the SHORT form. This should be extremely rare since the short JMP only is applicable to jumps inside the same module, but if it is legitimate, it may be necessary to use bnd jmp dword.

Enabled by default.

• db-empty warns about a DB, DW, etc declaration with no operands, producing no output. This is permitted, but often indicative of an error. See section 3.2.1.

Enabled by default.

• environment warns if a nonexistent environment variable is accessed using the %! preprocessor construct (see section 4.11.2.) Such environment variables are treated as empty (with this warning issued) starting in NASM 2.15; earlier versions of NASM would treat this as an error.

Enabled by default.

- float is a group alias for all warning classes prefixed by float-; currently float-denorm, float-overflow, float-toolong, and float-underflow.
- float-denorm warns about denormal floating point constants.

Disabled by default.

• float-overflow warns about floating point underflow.

Enabled by default.

• float-toolong warns about too many digits in floating-point numbers.

Enabled by default.

- float-underflow warns about floating point underflow (a nonzero constant rounded to zero.)
 Disabled by default.
- hle warns about invalid use of the HLE XACQUIRE or XRELEASE prefixes.

Enabled by default.

• label is a group alias for all warning classes prefixed by label-; currently label-orphan, label-redef, and label-redef-late.

• label-orphan warns about source lines which contain no instruction but define a label without a trailing colon. This is most likely indicative of a typo, but is technically correct NASM syntax (see section 3.1.)

Enabled by default.

• label-redef warns if a label is defined more than once, but the value is identical. It is an unconditional error to define the same label more than once to *different* values.

Disabled by default.

• label-redef-late the value of a label changed during the final, code-generation pass. This may be the result of strange use of the preprocessor. This is very likely to produce incorrect code and may end up being an unconditional error in a future version of NASM.

Enabled and promoted to error by default.

• lock warns about LOCK prefixes on unlockable instructions.

Enabled by default.

- macro is a group alias for all warning classes prefixed by macro-; currently macro-def-case-single, macro-def-greedy-single, macro-def-param-single, macro-defaults, macro-params-legacy, macro-params-multi, and macro-params-single.
- macro-def is a group alias for all warning classes prefixed by macro-def-; currently macro-def-case-single, macro-def-greedy-single, and macro-def-param-single.
- macro-def-case-single warns when a single-line macro is defined both case sensitive and case insensitive. The new macro definition will override (shadow) the original one, although the original macro is not deleted, and will be re-exposed if the new macro is deleted with <code>%undef</code>, or, if the original macro is the case insensitive one, the macro call is done with a different case.

Enabled by default.

 macro-def-greedy-single definition shadows greedy macro warns when a single-line macro is defined which would match a previously existing greedy definition. The new macro definition will override (shadow) the original one, although the original macro is not deleted, and will be re-exposed if the new macro is deleted with %undef, and will be invoked if called with a parameter count that does not match the new definition.

Enabled by default.

• macro-def-param-single warns if the same single-line macro is defined with and without parameters. The new macro definition will override (shadow) the original one, although the original macro is not deleted, and will be re-exposed if the new macro is deleted with <code>%undef</code>.

Enabled and promoted to error by default.

• macro-defaults warns when a macro has more default parameters than optional parameters. See section 4.3.5 for why might want to disable this warning.

Enabled by default.

- macro-params is a group alias for all warning classes prefixed by macro-params-; currently macro-params-legacy, macro-params-multi, and macro-params-single.
- macro-params-legacy warns about multi-line macros being invoked with the wrong number of parameters, but for bug-compatibility with NASM versions older than 2.15, NASM tried to fix up the parameters to match the legacy behavior and call the macro anyway. This can happen in certain cases where there are empty arguments without braces, sometimes as a result of macro expansion.

The legacy behavior is quite strange and highly context-dependent, and can be disabled with:

%pragma preproc sane_empty_expansion true

It is highly recommended to use this option in new code.

Enabled by default.

• macro-params-multi warns about multi-line macros being invoked with the wrong number of parameters. See section 4.3.1 for an example of why you might want to disable this warning.

Enabled by default.

• macro-params-single warns about single-line macros being invoked with the wrong number of parameters.

Enabled by default.

• negative-rep warns about negative counts given to the %rep preprocessor directive.

Enabled by default.

- not-my-pragma is a backwards compatibility alias for pragma-na.
- number-overflow covers warnings about numeric constants which don't fit in 64 bits.

Enabled by default.

- obsolete is a group alias for all warning classes prefixed by obsolete-; currently obsolete-nop, obsolete-removed, and obsolete-valid.
- obsolete-nop warns for an instruction which has been removed from the architecture, but has been architecturally defined to be a noop for future CPUs.

Enabled by default.

• obsolete-removed warns for an instruction which has been removed from the architecture, and is no longer included in the CPU definition given in the [CPU] directive, for example POP cs, the opcode for which, OFH, instead is an opcode prefix on CPUs newer than the first generation 8086.

Enabled by default.

• obsolete-valid warns for an instruction which has been removed from the architecture, but is still valid on the specific CPU given in the CPU directive. Code using these instructions is most likely not forward compatible.

Enabled by default.

- orphan-labels is a backwards compatibility alias for label-orphan.
- other specifies any warning not included in any specific warning class.

Enabled by default.

• phase warns about symbols having changed values during the second-to-last assembly pass. This is not inherently fatal, but may be a source of bugs.

Disabled by default.

- pragma is a group alias for all warning classes prefixed by pragma-; currently pragma-bad, pragma-empty, pragma-na, and pragma-unknown.
- pragma-bad warns about a malformed or otherwise unparsable %pragma directive.

Disabled by default.

• pragma-empty warns about a %pragma directive containing nothing. This is treated identically to %pragma ignore except for this optional warning.

Disabled by default.

• pragma-na warns about a %pragma directive which is not applicable to this particular assembly session. This is not yet implemented.

Disabled by default.

 pragma-unknown warns about an unknown %pragma directive. This is not yet implemented for most cases.

Disabled by default.

• ptr warns about keywords used in other assemblers that might indicate a mistake in the source code. Currently only the MASM PTR keyword is recognized. See also section 6.5.

Enabled by default.

• regsize warns about a register with implicit size (such as EAX, which is always 32 bits) been given an explicit size specification which is inconsistent with the size of the named register, e.g. word EAX. DWORD EAX or word AX are permitted, and do not trigger this warning. Some registers which do not imply a specific size, such as K0, may need this specification unless the instruction itself implies the instruction size:

Enabled by default.

- unknown-pragma is a backwards compatibility alias for pragma-unknown.
- unknown-warning warns about a -w or -w option or a [WARNING] directive that contains an unknown warning name or is otherwise not possible to process.

Disabled by default.

• user controls output of warning directives (see section 4.9).

Enabled by default.

• warn-stack-empty a [WARNING POP] directive was executed when the warning stack is empty. This is treated as a [WARNING *all] directive.

Enabled by default.

• zeroing a RESx directive was used in a section which contains initialized data, and the output format does not support this. Instead, this will be replaced with explicit zero content, which may produce a large output file.

Enabled by default.

• zext-reloc warns that a relocation has been zero-extended due to limitations in the output format.

Enabled by default.

Since version 2.15, NASM has group aliases for all prefixed warnings, so they can be used to enable or disable all warnings in the group. For example, –w+float enables all warnings with names starting with float-*.

Since version 2.00, NASM has also supported the gcc-like syntax -wwarning-class and -w-warning-class, respectively; both syntaxes work identically.

The option -w+error or -Werror can be used to treat warnings as errors. This can be controlled on a per warning class basis (-w+error=warning-class or -Werror=warning-class); if no warning-class is specified NASM treats it as -w+error=all; the same applies to -w-error or -Wno-error, of course.

In addition, you can control warnings in the source code itself, using the [WARNING] directive. See section 7.13.

2.1.27 The -v Option: Display Version Info

Typing NASM -v will display the version of NASM which you are using, and the date on which it was compiled.

You will need the version number if you report a bug.

For command-line compatibility with Yasm, the form --v is also accepted for this option starting in NASM version 2.11.05.

2.1.28 The --(g|l)prefix, --(g|l)postfix Options.

The --(g)prefix options prepend the given argument to all extern, common, static, and global symbols, and the --lprefix option prepends to all other symbols. Similarly, --(g)postfix and --lpostfix options append the argument in the exactly same way as the --xxprefix options does.

Running this:

```
nasm -f macho --gprefix _
```

is equivalent to place the directive with %pragma macho gprefix _ at the start of the file (section 7.10). It will prepend the underscore to all global and external variables, as C requires it in some, but not all, system calling conventions.

2.1.29 The --pragma Option

NASM accepts an argument as %pragma option, which is like placing a %pragma preprocess statement at the beginning of the source. Running this:

```
nasm -f macho --pragma "macho gprefix _"
```

is equivalent to the example in section 2.1.28. See section 4.10.

2.1.30 The --before Option

A preprocess statement can be accepted with this option. The example shown in section 2.1.29 is the same as running this:

```
nasm -f macho --before "%pragma macho gprefix _"
```

2.1.31 The --limit-x Option

This option allows user to setup various maximum values after which NASM will terminate with a fatal error rather than consume arbitrary amount of compute time. Each limit can be set to a positive number or unlimited.

- --limit-passes: Number of maximum allowed passes. Default is unlimited.
- --limit-stalled-passes: Maximum number of allowed unfinished passes. Default is 1000.
- --limit-macro-levels: Define maximum depth of macro expansion (in preprocess). Default is 10000
- --limit-macro-tokens: Maximum number of tokens processed during single-line macro expansion.
 Default is 10000000.
- --limit-mmacros: Maximum number of multi-line macros processed before returning to the top-level input. Default is 100000.
- --limit-rep: Maximum number of allowed preprocessor loop, defined under %rep. Default is 1000000.
- --limit-eval: This number sets the boundary condition of allowed expression length. Default is 8192 on most systems.

• --limit-lines: Total number of source lines allowed to be processed. Default is 2000000000.

For example, set the maximum line count to 1000:

```
nasm --limit-lines 1000
```

Limits can also be set via the directive %pragma limit, for example:

```
%pragma limit lines 1000
```

2.1.32 The --keep-all Option

This option prevents NASM from deleting any output files even if an error happens.

2.1.33 The --no-line Option

If this option is given, all %line directives in the source code are ignored. This can be useful for debugging already preprocessed code. See section 4.11.1.

2.1.34 The --reproducible Option

If this option is given, NASM will not emit information that is inherently dependent on the NASM version or different from run to run (such as timestamps) into the output file.

2.1.35 The NASMENV Environment Variable

If you define an environment variable called NASMENV, the program will interpret it as a list of extra command-line options, which are processed before the real command line. You can use this to define standard search directories for include files, by putting -i options in the NASMENV variable.

The value of the variable is split up at white space, so that the value -s -ic:\nasmlib\ will be treated as two separate options. However, that means that the value -dNAME="my name" won't do what you might want, because it will be split at the space and the NASM command-line processing will get confused by the two nonsensical words -dNAME="my and name".

To get round this, NASM provides a feature whereby, if you begin the NASMENV environment variable with some character that isn't a minus sign, then NASM will treat this character as the separator character for options. So setting the NASMENV variable to the value !-s!-ic:\nasmlib\ is equivalent to setting it to -s -ic:\nasmlib\, but !-dNAME="my name" will work.

This environment variable was previously called NASM. This was changed with version 0.98.31.

2.2 Quick Start for MASM Users

If you're used to writing programs with MASM, or with TASM in MASM-compatible (non-Ideal) mode, or with a86, this section attempts to outline the major differences between MASM's syntax and NASM's. If you're not already used to MASM, it's probably worth skipping this section.

2.2.1 NASM Is Case-Sensitive

One simple difference is that NASM is case-sensitive. It makes a difference whether you call your label foo, Foo or FOO. If you're assembling to DOS or OS/2 .OBJ files, you can invoke the UPPERCASE directive (documented in section 8.4) to ensure that all symbols exported to other code modules are forced to be upper case; but even then, within a single module, NASM will distinguish between labels differing only in case.

2.2.2 NASM Requires Square Brackets For Memory References

NASM was designed with simplicity of syntax in mind. One of the design goals of NASM is that it should be possible, as far as is practical, for the user to look at a single line of NASM code and tell what opcode is generated by it. You can't do this in MASM: if you declare, for example,

```
foo equ 1
bar dw 2
```

then the two lines of code

mov ax, foo mov ax, bar

generate completely different opcodes, despite having identical-looking syntaxes.

NASM avoids this undesirable situation by having a much simpler syntax for memory references. The rule is simply that any access to the *contents* of a memory location requires square brackets around the address, and any access to the *address* of a variable doesn't. So an instruction of the form mov ax, foo will *always* refer to a compile-time constant, whether it's an EQU or the address of a variable; and to access the *contents* of the variable bar, you must code mov ax, [bar].

This also means that NASM has no need for MASM's OFFSET keyword, since the MASM code mov ax,offset bar means exactly the same thing as NASM's mov ax,bar. If you're trying to get large amounts of MASM code to assemble sensibly under NASM, you can always code %idefine offset to make the preprocessor treat the OFFSET keyword as a no-op.

This issue is even more confusing in a86, where declaring a label with a trailing colon defines it to be a 'label' as opposed to a 'variable' and causes a86 to adopt NASM-style semantics; so in a86, mov ax, var has different behaviour depending on whether var was declared as var: dw 0 (a label) or var dw 0 (a word-size variable). NASM is very simple by comparison: everything is a label.

NASM, in the interests of simplicity, also does not support the hybrid syntaxes supported by MASM and its clones, such as mov ax,table[bx], where a memory reference is denoted by one portion outside square brackets and another portion inside. The correct syntax for the above is mov ax,[table+bx]. Likewise, mov ax,es:[di] is wrong and mov ax,[es:di] is right.

2.2.3 NASM Doesn't Store Variable Types

NASM, by design, chooses not to remember the types of variables you declare. Whereas MASM will remember, on seeing var dw 0, that you declared var as a word-size variable, and will then be able to fill in the ambiguity in the size of the instruction mov var,2, NASM will deliberately remember nothing about the symbol var except where it begins, and so you must explicitly code mov word [var],2.

For this reason, NASM doesn't support the LODS, MOVS, STOS, SCAS, CMPS, INS, or OUTS instructions, but only supports the forms such as LODSB, MOVSW, and SCASD, which explicitly specify the size of the components of the strings being manipulated.

2.2.4 NASM Doesn't ASSUME

As part of NASM's drive for simplicity, it also does not support the ASSUME directive. NASM will not keep track of what values you choose to put in your segment registers, and will never *automatically* generate a segment override prefix.

2.2.5 NASM Doesn't Support Memory Models

NASM also does not have any directives to support different 16-bit memory models. The programmer has to keep track of which functions are supposed to be called with a far call and which with a near call, and is responsible for putting the correct form of RET instruction (RETN or RETF; NASM accepts RET itself as an alternate form for RETN); in addition, the programmer is responsible for coding CALL FAR instructions where necessary when calling *external* functions, and must also keep track of which external variable definitions are far and which are near.

2.2.6 Floating-Point Differences

NASM uses different names to refer to floating-point registers from MASM: where MASM would call them ST(0), ST(1) and so on, and a86 would call them simply 0, 1 and so on, NASM chooses to call them st0, st1 etc.

As of version 0.96, NASM now treats the instructions with 'nowait' forms in the same way as MASM-compatible assemblers. The idiosyncratic treatment employed by 0.95 and earlier was based on a misunderstanding by the authors.

2.2.7 Other Differences

For historical reasons, NASM uses the keyword TWORD where MASM and compatible assemblers use TBYTE.

Historically, NASM does not declare uninitialized storage in the same way as MASM: where a MASM programmer might use stack db 64 dup (?), NASM requires stack resb 64, intended to be read as 'reserve 64 bytes'. For a limited amount of compatibility, since NASM treats ? as a valid character in symbol names, you can code? equ 0 and then writing dw? will at least do something vaguely useful.

As of NASM 2.15, the MASM syntax is also supported.

In addition to all of this, macros and directives work completely differently to MASM. See chapter 4 and chapter 7 for further details.

2.2.8 MASM compatibility package

See section 6.5.

Chapter 3: The NASM Language

3.1 Layout of a NASM Source Line

Like most assemblers, each NASM source line contains (unless it is a macro, a preprocessor directive or an assembler directive: see chapter 4 and chapter 7) some combination of the four fields

```
label: instruction operands ; comment
```

As usual, most of these fields are optional; the presence or absence of any combination of a label, an instruction and a comment is allowed. Of course, the operand field is either required or forbidden by the presence and nature of the instruction field.

NASM uses backslash (\) as the line continuation character; if a line ends with backslash, the next line is considered to be a part of the backslash-ended line.

NASM places no restrictions on white space within a line: labels may have white space before them, or instructions may have no space before them, or anything. The colon after a label is also optional. (Note that this means that if you intend to code lodsb alone on a line, and type lodab by accident, then that's still a valid source line which does nothing but define a label. Running NASM with the command-line option -w+orphan-labels will cause it to warn you if you define a label alone on a line without a trailing colon.)

Valid characters in labels are letters, numbers, _, \$, #, @, ~, ., and ?. The only characters which may be used as the *first* character of an identifier are letters, . (with special meaning: see section 3.9), _ and ?. An identifier may also be prefixed with a \$ to indicate that it is intended to be read as an identifier and not a reserved word; thus, if some other module you are linking with defines a symbol called eax, you can refer to \$eax in NASM code to distinguish the symbol from the register. Maximum length of an identifier is 4095 characters.

The instruction field may contain any machine instruction: Pentium and P6 instructions, FPU instructions, MMX instructions and even undocumented instructions are all supported. The instruction may be prefixed by LOCK, REP, REPE/REPZ, REPNE/REPNZ, XACQUIRE/XRELEASE OR BND/NOBND, in the usual way. Explicit address-size and operand-size prefixes A16, A32, A64, O16 and O32, O64 are provided – one example of their use is given in chapter 11. You can also use the name of a segment register as an instruction prefix: coding es mov [bx],ax is equivalent to coding mov [es:bx],ax. We recommend the latter syntax, since it is consistent with other syntactic features of the language, but for instructions such as LODSB, which has no operands and yet can require a segment override, there is no clean syntactic way to proceed apart from es lodsb.

An instruction is not required to use a prefix: prefixes such as CS, A32, LOCK or REPE can appear on a line by themselves, and NASM will just generate the prefix bytes.

In addition to actual machine instructions, NASM also supports a number of pseudo-instructions, described in section 3.2.

Instruction operands may take a number of forms: they can be registers, described simply by the register name (e.g. ax, bp, ebx, cr0: NASM does not use the gas-style syntax in which register names must be prefixed by a % sign), or they can be effective addresses (see section 3.3), constants (section 3.4) or expressions (section 3.5).

For x87 floating-point instructions, NASM accepts a wide range of syntaxes: you can use two-operand forms like MASM supports, or you can use NASM's native single-operand forms in most cases. For example, you can code:

```
fadd st1 ; this sets st0 := st0 + st1
fadd st0,st1 ; so does this
```

```
fadd st1,st0 ; this sets st1 := st1 + st0 fadd to st1 ; so does this
```

Almost any x87 floating-point instruction that references memory must use one of the prefixes DWORD, QWORD or TWORD to indicate what size of memory operand it refers to.

3.2 Pseudo-Instructions

Pseudo-instructions are things which, though not real x86 machine instructions, are used in the instruction field anyway because that's the most convenient place to put them. The current pseudo-instructions are DB, DW, DD, DQ, DT, DO, DY and DZ; their uninitialized counterparts RESB, RESW, RESD, REST, RESO, REST, RESO, REST, and RESZ; the INCBIN command, the EQU command, and the TIMES prefix.

In this documentation, the notation "Dx" and "RESx" is used to indicate all the DB and RESB type directives, respectively.

3.2.1 Dx: Declaring Initialized Data

DB, DW, DD, DQ, DT, DO, DY and DZ (collectively "Dx" in this documentation) are used, much as in MASM, to declare initialized data in the output file. They can be invoked in a wide range of ways:

```
db
                             ; just the byte 0x55
                           ; three bytes in succession
db
      0 \times 55, 0 \times 56, 0 \times 57
      'a',0x55; character constants are OK 'hello',13,10,'$'; so are string constants
db
db
dw
      0x1234
                           ; 0x34 0x12
                           ; 0x61 0x00 (it's just a number)
dw
      , a,
                           ; 0x61 0x62 (character constant)
      'ab'
dw
                           ; 0x61 0x62 0x63 0x00 (string)
      'abc'
dw
dd 0x12345678 ; 0x78 0x56 0x34 0x12
dd 1.234567e20 ; floating-point constant
dq 0x123456789abcdef0 ; eight byte constant
dq
     1.234567e20 ; double-precision float
      1.234567e20
                           ; extended-precision float
dt
```

DT, DO, DY and DZ do not accept integer numeric constants as operands.

Starting in NASM 2.15, a the following MASM-like features have been implemented:

• A? argument to declare uninitialized storage:

```
db ? ; uninitialized
```

• A superset of the DUP syntax. The NASM version of this has the following syntax specification; capital letters indicate literal keywords:

Note that a *list* needs to be prefixed with a % sign unless prefixed by either DUP or a *type* in order to avoid confusing it with a parentesis starting an expression. The following expressions are all valid:

```
db 6 dup (33)
db 6 dup (33, 34)
db 6 dup (33, 34), 35
db 7 dup (99)
db 7 dup dword (?, word ?, ?)
dw byte (?,44)
dw 3 dup (0xcc, 4 dup byte ('PQR'), ?), 0xabcd
dd 16 dup (0xaaaa, ?, 0xbbbbbb)
dd 64 dup (?)
```

The use of \$ (current address) in a Dx statement is undefined in the current version of NASM, except in the following cases:

- For the first expression in the statement, either a DUP or a data item.
- An expression of the form "value \$", which is converted to a self-relative relocation.

Future versions of NASM is likely to produce a different result or issue an error this case.

There is no such restriction on using \$\$ or section-relative symbols.

3.2.2 RESB and Friends: Declaring Uninitialized Data

RESB, RESD, RESQ, REST, RESO, RESY and RESZ are designed to be used in the BSS section of a module: they declare *uninitialized* storage space. Each takes a single operand, which is the number of bytes, words, doublewords or whatever to reserve. The operand to a RESB-type pseudo-instruction is a *critical expression*: see section 3.8.

For example:

```
buffer:
                                        ; reserve 64 bytes
                resb
                        64
                                        ; reserve a word
wordvar:
                        1
                resw
                                        ; array of ten reals
realarray
                resa
                        10
vmmval:
                                         ; one YMM register
                resy
                        1
zmmvals:
                        32
                                         ; 32 ZMM registers
                resz
```

Since NASM 2.15, the MASM syntax of using? and DUP in the Dx directives is also supported. Thus, the above example could also be written:

```
buffer:
                        64 dup (?)
                                         ; reserve 64 bytes
wordvar:
                dw
                                         ; reserve a word
                                         ; array of ten reals
realarray
                dq
                        10 dup (?)
ymmval:
                        ?
                                         ; one YMM register
                dy
zmmvals:
                        32 dup (?)
                                         ; 32 ZMM registers
                dz
```

3.2.3 INCBIN: Including External Binary Files

INCBIN includes binary file data verbatim into the output file. This can be handy for (for example) including graphics and sound data directly into a game executable file. It can be called in one of these three ways:

```
incbin "file.dat" ; include the whole file
incbin "file.dat",1024 ; skip the first 1024 bytes
incbin "file.dat",1024,512 ; skip the first 1024, and
; actually include at most 512
```

INCBIN is both a directive and a standard macro; the standard macro version searches for the file in the include file search path and adds the file to the dependency lists. This macro can be overridden if desired.

3.2.4 EQU: Defining Constants

EQU defines a symbol to a given constant value: when EQU is used, the source line must contain a label. The action of EQU is to define the given label name to the value of its (only) operand. This definition is absolute, and cannot change later. So, for example,

```
message db 'hello, world' msglen equ $-message
```

defines msglen to be the constant 12. msglen may not then be redefined later. This is not a preprocessor definition either: the value of msglen is evaluated *once*, using the value of \$ (see section 3.5 for an explanation of \$) at the point of definition, rather than being evaluated wherever it is referenced and using the value of \$ at the point of reference.

3.2.5 TIMES: Repeating Instructions or Data

The TIMES prefix causes the instruction to be assembled multiple times. This is partly present as NASM's equivalent of the DUP syntax supported by MASM-compatible assemblers, in that you can code

```
zerobuf: times 64 db 0
```

or similar things; but TIMES is more versatile than that. The argument to TIMES is not just a numeric constant, but a numeric expression, so you can do things like

which will store exactly enough spaces to make the total length of buffer up to 64. Finally, TIMES can be applied to ordinary instructions, so you can code trivial unrolled loops in it:

```
times 100 movsb
```

Note that there is no effective difference between times 100 resb 1 and resb 100, except that the latter will be assembled about 100 times faster due to the internal structure of the assembler.

The operand to TIMES is a critical expression (section 3.8).

Note also that TIMES can't be applied to macros: the reason for this is that TIMES is processed after the macro phase, which allows the argument to TIMES to contain expressions such as 64-\$+buffer as above. To repeat more than one line of code, or a complex macro, use the preprocessor %rep directive.

3.3 Effective Addresses

An effective address is any operand to an instruction which references memory. Effective addresses, in NASM, have a very simple syntax: they consist of an expression evaluating to the desired address, enclosed in square brackets. For example:

Anything not conforming to this simple system is not a valid memory reference in NASM, for example es:wordvar[bx].

More complicated effective addresses, such as those involving more than one register, work in exactly the same way:

```
mov eax,[ebx*2+ecx+offset]
mov ax,[bp+di+8]
```

NASM is capable of doing algebra on these effective addresses, so that things which don't necessarily *look* legal are perfectly all right:

```
mov eax,[ebx*5] ; assembles as [ebx*4+ebx]
mov eax,[label1*2-label2] ; ie [label1+(label1-label2)]
```

Some forms of effective address have more than one assembled form; in most such cases NASM will generate the smallest form it can. For example, there are distinct assembled forms for the 32-bit effective addresses <code>[eax*2+0]</code> and <code>[eax+eax]</code>, and NASM will generally generate the latter on the grounds that the former requires four bytes to store a zero offset.

NASM has a hinting mechanism which will cause <code>[eax+ebx]</code> and <code>[ebx+eax]</code> to generate different opcodes; this is occasionally useful because <code>[esi+ebp]</code> and <code>[ebp+esi]</code> have different default segment registers.

However, you can force NASM to generate an effective address in a particular form by the use of the keywords BYTE, WORD, DWORD and NOSPLIT. If you need [eax+3] to be assembled using a double-word offset field instead of the one byte NASM will normally generate, you can code [dword eax+3]. Similarly, you can force NASM to use a byte offset for a small value which it hasn't seen on the first pass (see section 3.8 for an example of such a code fragment) by using [byte eax+offset]. As special cases, [byte eax] will code [eax+0] with a byte offset of zero, and [dword eax] will code it with a double-word offset of zero. The normal form, [eax], will be coded with no offset field.

The form described in the previous paragraph is also useful if you are trying to access data in a 32-bit segment from within 16 bit code. For more information on this see the section on mixed-size addressing (section 11.2). In particular, if you need to access data with a known offset that is larger than will fit in a 16-bit value, if you don't specify that it is a dword offset, nasm will cause the high word of the offset to be lost.

Similarly, NASM will split [eax*2] into [eax+eax] because that allows the offset field to be absent and space to be saved; in fact, it will also split [eax*2+offset] into [eax+eax+offset]. You can combat this behaviour by the use of the NOSPLIT keyword: [nosplit eax*2] will force [eax*2+0] to be generated literally. [nosplit eax*1] also has the same effect. In another way, a split EA form [0, eax*2] can be used, too. However, NOSPLIT in [nosplit eax+eax] will be ignored because user's intention here is considered as [eax+eax].

In 64-bit mode, NASM will by default generate absolute addresses. The REL keyword makes it produce RIP-relative addresses. Since this is frequently the normally desired behaviour, see the DEFAULT directive (section 7.2). The keyword ABS overrides REL.

A new form of split effective addres syntax is also supported. This is mainly intended for mib operands as used by MPX instructions, but can be used for any memory reference. The basic concept of this form is splitting base and index.

```
mov eax,[ebx+8,ecx*4] ; ebx=base, ecx=index, 4=scale, 8=disp
```

For mib operands, there are several ways of writing effective address depending on the tools. NASM supports all currently possible ways of mib syntax:

When broadcasting decorator is used, the opsize keyword should match the size of each element.

```
VDIVPS zmm4, zmm5, dword [rbx]{1to16} ; single-precision float
VDIVPS zmm4, zmm5, zword [rbx] ; packed 512 bit memory
```

3.4 Constants

NASM understands four different types of constant: numeric, character, string and floating-point.

3.4.1 Numeric Constants

A numeric constant is simply a number. NASM allows you to specify numbers in a variety of number bases, in a variety of ways: you can suffix H or X, D or T, Q or D, and D or D for hexadecimal, decimal, octal and binary respectively, or you can prefix D for hexadecimal in the style of D, or you can prefix D for hexadecimal in the style of Borland Pascal or Motorola Assemblers. Note, though, that the D prefix does

double duty as a prefix on identifiers (see section 3.1), so a hex number prefixed with a \$ sign must have a digit after the \$ rather than a letter. In addition, current versions of NASM accept the prefix 0h for hexadecimal, 0d or 0t for decimal, 0o or 0q for octal, and 0b or 0y for binary. Please note that unlike C, a 0 prefix by itself does *not* imply an octal constant!

Numeric constants can have underscores (_) interspersed to break up long strings.

Some examples (all producing exactly the same code):

```
; decimal
mov
         ax,200
mov
         ax,0200
                          ; still decimal
                          ; explicitly decimal
         ax,0200d
mov
         ax,0d200
mov
                          ; also decimal
         ax,0c8h
                          ; hex
mov
                          ; hex again: the 0 is required
         ax.$0c8
mov
                          ; hex yet again
         ax,0xc8
mov
                          ; still hex
         ax,0hc8
mov.
mov
         ax,310q
                          ; octal
         ax,310o
                          ; octal again
mov
         ax,0o310
                         ; octal yet again
mov
                         ; octal yet again
mov
         ax,0q310
         ax,11001000b ; binary ax,1100_1000b ; same binary constant
mov
mov
         ax,1100_1000y ; same binary constant once more
ax,0b1100_1000 ; same binary constant yet again
mov
         ax,0y1100_1000 ; same binary constant yet again
mov
```

3.4.2 Character Strings

A character string consists of up to eight characters enclosed in either single quotes ('...'), double quotes ("...") or backquotes ('...'). Single or double quotes are equivalent to NASM (except of course that surrounding the constant with single quotes allows double quotes to appear within it and vice versa); the contents of those are represented verbatim. Strings enclosed in backquotes support C-style \-escapes for special characters.

The following escape sequences are recognized by backquoted strings:

```
single quote (')
            double quote (")
\'
            backquote (')
            backslash (\)
            question mark (?)
\?
            BEL (ASCII 7)
\a
            BS (ASCII 8)
\b
\t
            TAB (ASCII 9)
\n
            LF (ASCII 10)
            VT (ASCII 11)
FF (ASCII 12)
\ v
\ f
            CR (ASCII 13)
\r
            ESC (ASCII 27)
\ e
\377
            Up to 3 octal digits - literal byte
            Up to 2 hexadecimal digits - literal byte
\xFF
\u1234
            4 hexadecimal digits - Unicode character
\U12345678 8 hexadecimal digits - Unicode character
```

All other escape sequences are reserved. Note that \0, meaning a NUL character (ASCII 0), is a special case of the octal escape sequence.

Unicode characters specified with \u or \U are converted to UTF-8. For example, the following lines are all equivalent:

```
db '\u263a' ; UTF-8 smiley face db '\xe2\x98\xba' ; UTF-8 smiley face db 0E2h, 098h, 0BAh ; UTF-8 smiley face
```

3.4.3 Character Constants

A character constant consists of a string up to eight bytes long, used in an expression context. It is treated as if it was an integer.

A character constant with more than one byte will be arranged with little-endian order in mind: if you code

```
mov eax, 'abcd'
```

then the constant generated is not 0x61626364, but 0x64636261, so that if you were then to store the value into memory, it would read abcd rather than dcba. This is also the sense of character constants understood by the Pentium's CPUID instruction.

3.4.4 String Constants

String constants are character strings used in the context of some pseudo-instructions, namely the DB family and INCBIN (where it represents a filename.) They are also used in certain preprocessor directives.

A string constant looks like a character constant, only longer. It is treated as a concatenation of maximum-size character constants for the conditions. So the following are equivalent:

```
db 'hello' ; string constant
db 'h','e','l','o' ; equivalent character constants
```

And the following are also equivalent:

Note that when used in a string-supporting context, quoted strings are treated as a string constants even if they are short enough to be a character constant, because otherwise db 'ab' would have the same effect as db 'a', which would be silly. Similarly, three-character or four-character constants are treated as strings when they are operands to DW, and so forth.

3.4.5 Unicode Strings

The special operators __?utf16?__, __?utf16le?__, __?utf16be?__, __?utf32?__, __?utf32le?__ and __?utf32be?__ allows definition of Unicode strings. They take a string in UTF-8 format and converts it to UTF-16 or UTF-32, respectively. Unless the be forms are specified, the output is littleendian.

For example:

```
%define u(x) __?utf16?__(x)
%define w(x) __?utf32?__(x)

dw u('C:\WINDOWS'), 0 ; Pathname in UTF-16
    dd w('A + B = \u206a'), 0 ; String in UTF-32
```

The UTF operators can be applied either to strings passed to the DB family instructions, or to character constants in an expression context.

3.4.6 Floating-Point Constants

Floating-point constants are acceptable only as arguments to DB, DW, DD, DQ, DT, and DO, or as arguments to the special operators __?float8?__, __?float16?__, __?float16?__, __?float32?__, __?float64?__, __?float80m?__, __?float80e?__, __?float128l?__, and __?float128h?__. See also section 6.3.

Floating-point constants are expressed in the traditional form: digits, then a period, then optionally more digits, then optionally an E followed by an exponent. The period is mandatory, so that NASM can

distinguish between dd 1, which declares an integer constant, and dd 1.0 which declares a floating-point constant.

NASM also support C99-style hexadecimal floating-point: 0x, hexadecimal digits, period, optionally more hexadeximal digits, then optionally a P followed by a *binary* (not hexadecimal) exponent in decimal notation. As an extension, NASM additionally supports the 0h and \$ prefixes for hexadecimal, as well binary and octal floating-point, using the 0b or 0y and 0o or 0g prefixes, respectively.

Underscores to break up groups of digits are permitted in floating-point constants as well.

Some examples:

```
db
     -0.2
                             ; "Quarter precision"
     -0.5
                             ; IEEE 754r/SSE5 half precision
dw
dd
     1.2
                             ; an easy one
     1.222_222_222
                             ; underscores are permitted
dd
dd
     0x1p+2
                             ; 1.0 \times 2^2 = 4.0
                             ; 1.0 \times 2^3 = 4294967296.0
dq
     0x1p+32
dq
     1.e10
                              ; 10 000 000 000.0
                              ; synonymous with 1.e10
dq
     1.e+10
                              ; 0.000 000 000 1
     1.e-10
dq
     3.141592653589793238462 ; pi
dt
     1.e+4000
                              ; IEEE 754r quad precision
```

The 8-bit "quarter-precision" floating-point format is sign:exponent:mantissa = 1:4:3 with an exponent bias of 7. This appears to be the most frequently used 8-bit floating-point format, although it is not covered by any formal standard. This is sometimes called a "minifloat."

The bfloat16 format is effectively a compressed version of the 32-bit single precision format, with a reduced mantissa. It is effectively the same as truncating the 32-bit format to the upper 16 bits, except for rounding. There is no Dx directive that corresponds to bfloat16 as it obviously has the same size as the IEEE standard 16-bit half precision format, see however section 6.3.

The special operators are used to produce floating-point numbers in other contexts. They produce the binary representation of a specific floating-point number as an integer, and can use anywhere integer constants are used in an expression. __?float80m?__ and __?float80e?__ produce the 64-bit mantissa and 16-bit exponent of an 80-bit floating-point number, and __?float128l?__ and __?float128h?__ produce the lower and upper 64-bit halves of a 128-bit floating-point number, respectively.

For example:

```
mov rax,__?float64?__(3.141592653589793238462)
```

... would assign the binary representation of pi as a 64-bit floating point number into RAX. This is exactly equivalent to:

```
mov rax,0x400921fb54442d18
```

NASM cannot do compile-time arithmetic on floating-point constants. This is because NASM is designed to be portable – although it always generates code to run on x86 processors, the assembler itself can run on any system with an ANSI C compiler. Therefore, the assembler cannot guarantee the presence of a floating-point unit capable of handling the Intel number formats, and so for NASM to be able to do floating arithmetic it would have to include its own complete set of floating-point routines, which would significantly increase the size of the assembler for very little benefit.

The special tokens __?Infinity?__, __?QNaN?__ (or __?NaN?__) and __?SNaN?__ can be used to generate infinities, quiet NaNs, and signalling NaNs, respectively. These are normally used as macros:

```
%define Inf __?Infinity?__
%define NaN __?QNaN?__

dq +1.5, -Inf, NaN ; Double-precision constants
```

The <code>%use fp</code> standard macro package contains a set of convenience macros. See section 6.3.

3.4.7 Packed BCD Constants

x87-style packed BCD constants can be used in the same contexts as 80-bit floating-point numbers. They are suffixed with p or prefixed with op, and can include up to 18 decimal digits.

As with other numeric constants, underscores can be used to separate digits.

For example:

```
dt 12_345_678_901_245_678p
dt -12_345_678_901_245_678p
dt +0p33
dt 33p
```

3.5 Expressions

Expressions in NASM are similar in syntax to those in C. Expressions are evaluated as 64-bit integers which are then adjusted to the appropriate size.

NASM supports two special tokens in expressions, allowing calculations to involve the current assembly position: the \$ and \$\$ tokens. \$ evaluates to the assembly position at the beginning of the line containing the expression; so you can code an infinite loop using JMP \$. \$\$ evaluates to the beginning of the current section; so you can tell how far into the section you are by using (\$-\$\$).

The arithmetic operators provided by NASM are listed here, in increasing order of precedence.

A *boolean* value is true if nonzero and false if zero. The operators which return a boolean value always return 1 for true and 0 for false.

3.5.1 ? ... :: Conditional Operator

The syntax of this operator, similar to the C conditional operator, is:

boolean? trueval: falseval

This operator evaluates to *trueval* if *boolean* is true, otherwise to *falseval*.

Note that NASM allows? characters in symbol names. Therefore, it is highly advisable to always put spaces around the? and: characters.

3.5.2: | |: Boolean OR Operator

The $|\cdot|$ operator gives a boolean OR: it evaluates to 1 if both sides of the expression are nonzero, otherwise 0.

3.5.3: ^^: Boolean XOR Operator

The ^^ operator gives a boolean XOR: it evaluates to 1 if any one side of the expression is nonzero, otherwise 0.

3.5.4: &&: Boolean AND Operator

The && operator gives a boolean AND: it evaluates to 1 if both sides of the expression is nonzero, otherwise 0.

3.5.5 : Comparison Operators

NASM supports the following comparison operators:

- = or == compare for equality.
- != or <> compare for inequality.
- < compares signed less than.
- <= compares signed less than or equal.

- > compares signed greater than.
- >= compares signed greather than or equal.

These operators evaluate to 0 for false or 1 for true.

• <=> does a signed comparison, and evaluates to -1 for less than, 0 for equal, and 1 for greater than.

At this time, NASM does not provide unsigned comparison operators.

3.5.6 |: Bitwise OR Operator

The | operator gives a bitwise OR, exactly as performed by the OR machine instruction.

3.5.7 ^: Bitwise XOR Operator

^ provides the bitwise XOR operation.

3.5.8 &: Bitwise AND Operator

& provides the bitwise AND operation.

3.5.9 Bit Shift Operators

<< gives a bit-shift to the left, just as it does in C. So 5<<3 evaluates to 5 times 8, or 40. >> gives an unsigned (logical) bit-shift to the right; the bits shifted in from the left are set to zero.

<<< gives a bit-shift to the left, exactly equivalent to the << operator; it is included for completeness. >>> gives an *signed* (arithmetic) bit-shift to the right; the bits shifted in from the left are filled with copies of the most significant (sign) bit.

3.5.10 + and -: Addition and Subtraction Operators

The + and - operators do perfectly ordinary addition and subtraction.

3.5.11 Multiplication, Division and Modulo

* is the multiplication operator.

/ and // are both division operators: / is unsigned division and // is signed division.

Similarly, % and %% provide unsigned and signed modulo operators respectively.

Since the % character is used extensively by the macro preprocessor, you should ensure that both the signed and unsigned modulo operators are followed by white space wherever they appear.

NASM, like ANSI C, provides no guarantees about the sensible operation of the signed modulo operator. On most systems it will match the signed division operator, such that:

$$b * (a // b) + (a \% b) = a$$
 (b != 0)

3.5.12 Unary Operators

The highest-priority operators in NASM's expression grammar are those which only apply to one argument. These are:

- - negates (2's complement) its operand.
- + does nothing; it's provided for symmetry with -.
- ~ computes the bitwise negation (1's complement) of its operand.
- ! is the boolean negation operator. It evaluates to 1 if the argument is 0, otherwise 0.
- SEG provides the segment address of its operand (explained in more detail in section 3.6).

• A set of additional operators with leading and trailing double underscores are used to implement the integer functions of the ifunc macro package, see section 6.4.

3.6 SEG and WRT

When writing large 16-bit programs, which must be split into multiple segments, it is often necessary to be able to refer to the segment part of the address of a symbol. NASM supports the SEG operator to perform this function.

The SEG operator evaluates to the *preferred* segment base of a symbol, defined as the segment base relative to which the offset of the symbol makes sense. So the code

```
mov ax,seg symbol mov es,ax mov bx,symbol
```

will load ES:BX with a valid pointer to the symbol symbol.

Things can be more complex than this: since 16-bit segments and groups may overlap, you might occasionally want to refer to some symbol using a different segment base from the preferred one. NASM lets you do this, by the use of the WRT (With Reference To) keyword. So you can do things like

```
mov ax,weird_seg ; weird_seg is a segment base
mov es,ax
mov bx,symbol wrt weird_seg
```

to load ES:BX with a different, but functionally equivalent, pointer to the symbol symbol.

NASM supports far (inter-segment) calls and jumps by means of the syntax call segment:offset, where segment and offset both represent immediate values. So to call a far procedure, you could code either of

```
call (seg procedure):procedure
call weird_seg:(procedure wrt weird_seg)
```

(The parentheses are included for clarity, to show the intended parsing of the above instructions. They are not necessary in practice.)

NASM supports the syntax call far procedure as a synonym for the first of the above usages. JMP works identically to CALL in these examples.

To declare a far pointer to a data item in a data segment, you must code

```
dw symbol, seg symbol
```

NASM supports no convenient synonym for this, though you can always invent one using the macro processor.

3.7 STRICT: Inhibiting Optimization

When assembling with the optimizer set to level 2 or higher (see section 2.1.24), NASM will use size specifiers (BYTE, WORD, DWORD, QWORD, TWORD, OWORD, YWORD or ZWORD), but will give them the smallest possible size. The keyword STRICT can be used to inhibit optimization and force a particular operand to be emitted in the specified size. For example, with the optimizer on, and in BITS 16 mode,

```
push dword 33
```

is encoded in three bytes 66 6A 21, whereas

```
push strict dword 33
```

is encoded in six bytes, with a full dword immediate operand 66 68 21 00 00 00.

With the optimizer off, the same code (six bytes) is generated whether the STRICT keyword was used or not.

3.8 Critical Expressions

Although NASM has an optional multi-pass optimizer, there are some expressions which must be resolvable on the first pass. These are called *Critical Expressions*.

The first pass is used to determine the size of all the assembled code and data, so that the second pass, when generating all the code, knows all the symbol addresses the code refers to. So one thing NASM can't handle is code whose size depends on the value of a symbol declared after the code in question. For example,

```
times (label-$) db 0
label: db 'Where am I?'
```

The argument to TIMES in this case could equally legally evaluate to anything at all; NASM will reject this example because it cannot tell the size of the TIMES line when it first sees it. It will just as firmly reject the slightly paradoxical code

```
times (label-$+1) db 0 label: db 'NOW where am I?'
```

in which any value for the TIMES argument is by definition wrong!

NASM rejects these examples by means of a concept called a *critical expression*, which is defined to be an expression whose value is required to be computable in the first pass, and which must therefore depend only on symbols defined before it. The argument to the TIMES prefix is a critical expression.

3.9 Local Labels

NASM gives special treatment to symbols beginning with a period. A label beginning with a single period is treated as a *local* label, which means that it is associated with the previous non-local label. So, for example:

In the above code fragment, each JNE instruction jumps to the line immediately before it, because the two definitions of .loop are kept separate by virtue of each being associated with the previous non-local label.

This form of local label handling is borrowed from the old Amiga assembler DevPac; however, NASM goes one step further, in allowing access to local labels from other parts of the code. This is achieved by means of *defining* a local label in terms of the previous non-local label: the first definition of .loop above is really defining a symbol called label1.loop, and the second defines a symbol called label2.loop. So, if you really needed to, you could write

```
label3 ; some more code
; and some more

jmp label1.loop
```

Sometimes it is useful – in a macro, for instance – to be able to define a label which can be referenced from anywhere but which doesn't interfere with the normal local-label mechanism. Such a label can't be non-local because it would interfere with subsequent definitions of, and references to, local labels; and it can't be local because the macro that defined it wouldn't know the label's full name. NASM therefore introduces a third type of label, which is probably only useful in macro definitions: if a label begins with the special prefix . . @, then it does nothing to the local label mechanism. So you could code

```
label1:
.local:
.local:
.@foo:
! this is really label1.local
.@foo:
! this is a special symbol
! another non-local label
.local:
! this is really label2.local

jmp ..@foo ; this will jump three lines up
```

NASM has the capacity to define other special symbols beginning with a double period: for example, ..start is used to specify the entry point in the obj output format (see section 8.4.6), ..imagebase is used to find out the offset from a base address of the current image in the win64 output format (see section 8.6.1). So just keep in mind that symbols beginning with a double period are special.

Chapter 4: The NASM Preprocessor

NASM contains a powerful macro processor, which supports conditional assembly, multi-level file inclusion, two forms of macro (single-line and multi-line), and a 'context stack' mechanism for extra macro power. Preprocessor directives all begin with a % sign.

The preprocessor collapses all lines which end with a backslash (\) character into a single line. Thus:

```
%define THIS_VERY_LONG_MACRO_NAME_IS_DEFINED_TO \
    THIS VALUE
```

will work like a single-line macro without the backslash-newline sequence.

4.1 Single-Line Macros

4.1.1 The Normal Way: %define

Single-line macros are defined using the %define preprocessor directive. The definitions work in a similar way to C; so you can do things like

When the expansion of a single-line macro contains tokens which invoke another macro, the expansion is performed at invocation time, not at definition time. Thus the code

```
%define a(x) 1+b(x)
%define b(x) 2*x
```

will evaluate in the expected way to mov ax,1+2*8, even though the macro b wasn't defined at the time of definition of a.

Note that single-line macro argument list cannot be preceded by whitespace. Otherwise it will be treated as an expansion. For example:

```
%define foo (a,b) ; no arguments, (a,b) is the expansion %define bar(a,b) ; two arguments, empty expansion
```

Macros defined with %define are case sensitive: after %define foo bar, only foo will expand to bar: Foo or FOO will not. By using %idefine instead of %define (the 'i' stands for 'insensitive') you can define all the case variants of a macro at once, so that %idefine foo bar would cause foo, Foo, FOO, fOO and so on all to expand to bar.

There is a mechanism which detects when a macro call has occurred as a result of a previous expansion of the same macro, to guard against circular references and infinite loops. If this happens, the preprocessor will only expand the first occurrence of the macro. Hence, if you code

```
%define a(x) 1+a(x) mov ax,a(3)
```

the macro a(3) will expand once, becoming 1+a(3), and will then expand no further. This behaviour can be useful: see section 10.1 for an example of its use.

You can overload single-line macros: if you write

```
%define foo(x) 1+x %define foo(x,y) 1+x*y
```

the preprocessor will be able to handle both types of macro call, by counting the parameters you pass; so foo(3) will become 1+3 whereas foo(ebx,2) will become 1+ebx*2. However, if you define

```
%define foo bar
```

then no other definition of foo will be accepted: a macro with no parameters prohibits the definition of the same name as a macro with parameters, and vice versa.

This doesn't prevent single-line macros being redefined: you can perfectly well define a macro with

```
%define foo bar
```

and then re-define it later in the same source file with

```
%define foo baz
```

Then everywhere the macro foo is invoked, it will be expanded according to the most recent definition. This is particularly useful when defining single-line macros with %assign (see section 4.1.8).

The following additional features were added in NASM 2.15:

It is possible to define an empty string instead of an argument name if the argument is never used. For example:

```
%define ereg(foo,) e %+ foo
mov eax,ereg(dx,cx)
```

A single pair of parentheses is a subcase of a single, unused argument:

```
%define myreg() eax
mov edx,myreg()
```

This is similar to the behavior of the C preprocessor.

- If declared with an =, NASM will evaluate the argument as an expression after expansion.
- If an argument declared with an &, a macro parameter will be turned into a quoted string after expansion.
- If declared with a +, it is a greedy or variadic parameter; it includes any subsequent commas and parameters.
- If declared with an !, NASM will not strip whitespace and braces (useful in conjunction with &).

For example:

```
%define xyzzy(=expr,&val) expr, str
%define plugh(x) xyzzy(x,x)
db plugh(3+5), '\0'; Expands to: db 8, "3+5", '\0'
```

You can pre-define single-line macros using the '-d' option on the NASM command line: see section 2.1.20.

4.1.2 Resolving %define: %xdefine

To have a reference to an embedded single-line macro resolved at the time that the embedding macro is *defined*, as opposed to when the embedding macro is *expanded*, you need a different mechanism to the one offered by <code>%define</code>. The solution is to use <code>%xdefine</code>, or it's case-insensitive counterpart <code>%ixdefine</code>.

Suppose you have the following code:

```
%define isTrue 1
%define isFalse isTrue
%define isTrue 0
```

```
val1: db isFalse
%define isTrue 1
val2: db isFalse
```

In this case, val1 is equal to 0, and val2 is equal to 1. This is because, when a single-line macro is defined using %define, it is expanded only when it is called. As isFalse expands to isTrue, the expansion will be the current value of isTrue. The first time it is called that is 0, and the second time it is 1.

If you wanted isFalse to expand to the value assigned to the embedded macro isTrue at the time that isFalse was defined, you need to change the above code to use %xdefine.

```
%xdefine isTrue 1
%xdefine isFalse isTrue
%xdefine isTrue 0
val1:    db    isFalse
%xdefine isTrue 1
val2:    db    isFalse
```

Now, each time that isFalse is called, it expands to 1, as that is what the embedded macro isTrue expanded to at the time that isFalse was defined.

%xdefine and %ixdefine supports argument expansion exactly the same way that %define and %idefine does.

4.1.3 Macro Indirection: %[...]

The %[...] construct can be used to expand macros in contexts where macro expansion would otherwise not occur, including in the names other macros. For example, if you have a set of macros named Foo16, Foo32 and Foo64, you could write:

```
mov ax,Foo%[__?BITS?__] ; The Foo value
```

to use the builtin macro __?BITS?__ (see section 5.3) to automatically select between them. Similarly, the two statements:

```
%xdefine Bar Quux ; Expands due to %xdefine
%define Bar %[Quux] ; Expands due to %[...]
```

have, in fact, exactly the same effect.

%[...] concatenates to adjacent tokens in the same way that multi-line macro parameters do, see section 4.3.9 for details.

4.1.4 Concatenating Single Line Macro Tokens: %+

Individual tokens in single line macros can be concatenated, to produce longer tokens for later processing. This can be useful if there are several similar macros that perform similar functions.

Please note that a space is required after %+, in order to disambiguate it from the syntax %+1 used in multiline macros.

As an example, consider the following:

Now, if we need to access the elements of tBIOSDA in different places, we can end up with:

```
mov ax,BDASTART + tBIOSDA.COM1addr
mov bx,BDASTART + tBIOSDA.COM2addr
```

This will become pretty ugly (and tedious) if used in many places, and can be reduced in size significantly by using the following macro:

Using this feature, we can simplify references to a lot of macros (and, in turn, reduce typing errors).

4.1.5 The Macro Name Itself: %? and %??

The special symbols %? and %?? can be used to reference the macro name itself inside a macro expansion, this is supported for both single-and multi-line macros. %? refers to the macro name as *invoked*, whereas %?? refers to the macro name as *declared*. The two are always the same for case-sensitive macros, but for case-insensitive macros, they can differ.

For example:

```
%imacro Foo 0
mov %?,%??
%endmacro

foo
F00

will expand to:
mov foo,Foo
mov F00,Foo
```

These tokens can be used for single-line macros if defined outside any multi-line macros. See below.

4.1.6 The Single-Line Macro Name: **? and **??

If the tokens %? and %?? are used inside a multi-line macro, they are expanded before any directives are processed. As a result,

which may or may not be what you expected. The tokens *?? and *?? behave like *? and *?? but are only expanded inside single-line macros. Thus:

will expand to:

```
mov _BAR,_bAr
mov eax,_bar
```

The %*? can be used to make a keyword "disappear", for example in case a new instruction has been used as a label in older code. For example:

```
%idefine pause $%*? ; Hide the PAUSE instruction %*? and %*?? were introduced in NASM 2.15.04.
```

4.1.7 Undefining Single-Line Macros: %undef

Single-line macros can be removed with the %undef directive. For example, the following sequence:

```
%define foo bar
%undef foo
mov eax, foo
```

will expand to the instruction mov eax, foo, since after %undef the macro foo is no longer defined.

Macros that would otherwise be pre-defined can be undefined on the command-line using the '-u' option on the NASM command line: see section 2.1.21.

4.1.8 Preprocessor Variables: %assign

An alternative way to define single-line macros is by means of the <code>%assign</code> command (and its case-insensitive counterpart <code>%iassign</code>, which differs from <code>%assign</code> in exactly the same way that <code>%idefine</code> differs from <code>%define</code>).

%assign is used to define single-line macros which take no parameters and have a numeric value. This value can be specified in the form of an expression, and it will be evaluated once, when the %assign directive is processed.

Like %define, macros defined using %assign can be re-defined later, so you can do things like

```
%assign i i+1
```

to increment the numeric value of a macro.

%assign is useful for controlling the termination of %rep preprocessor loops: see section 4.5 for an example of this. Another use for %assign is given in section 9.4 and section 10.1.

The expression passed to %assign is a critical expression (see section 3.8), and must also evaluate to a pure number (rather than a relocatable reference such as a code or data address, or anything involving a register).

4.1.9 Defining Strings: %defstr

%defstr, and its case-insensitive counterpart %idefstr, define or redefine a single-line macro without parameters but converts the entire right-hand side, after macro expansion, to a quoted string before definition.

```
For example:

%defstr test TEST

is equivalent to

%define test 'TEST'

This can be used, for example, with the %! construct (see section 4.11.2):

%defstr PATH %!PATH ; The operating system PATH variable
```

4.1.10 Defining Tokens: %deftok

%deftok, and its case-insensitive counterpart %ideftok, define or redefine a single-line macro without parameters but converts the second parameter, after string conversion, to a sequence of tokens.

```
For example:
```

```
%deftok test 'TEST'
is equivalent to
%define test TEST
```

4.1.11 Defining Aliases: %defalias

%defalias, and its case-insensitive counterpart %idefalias, define an alias to a macro, i.e. equivalent of a symbolic link.

When used with various macro defining and undefining directives, it affects the aliased macro. This functionality is intended for being able to rename macros while retaining the legacy names.

When an alias is defined, but the aliased macro is then undefined, the aliases can legitimately point to nonexistent macros.

The alias can be undefined using the <code>%undefalias</code> directive. All aliases can be undefined using the <code>%clear defalias</code> directive. This includes backwards compatibility aliases defined by NASM itself.

To disable aliases without undefining them, use the %aliases off directive.

To check whether an alias is defined, regardless of the existence of the aliased macro, use %ifdefalias.

For example:

```
%defalias OLD NEW
  ; OLD and NEW both undefined
%define NEW 123
  ; OLD and NEW both 123
%undef OLD
  ; OLD and NEW both undefined
%define OLD 456
  ; OLD and NEW both 456
%undefalias OLD
  ; OLD undefined, NEW defined to 456
```

4.1.12 Conditional Comma Operator: %,

As of version 2.15, NASM has a conditional comma operator %, that expands to a comma *unless* followed by a null expansion, which allows suppressing the comma before an empty argument. This is especially useful with greedy single-line macros.

For example, all the expressions below are valid:

```
%define greedy(a,b,c+) a + 66 %, b * 3 %, c

db greedy(1,2) ; db 1 + 66, 2 * 3
db greedy(1,2,3) ; db 1 + 66, 2 * 3, 3
db greedy(1,2,3,4) ; db 1 + 66, 2 * 3, 3, 4
db greedy(1,2,3,4,5) ; db 1 + 66, 2 * 3, 3, 4, 5
```

4.2 String Manipulation in Macros

It's often useful to be able to handle strings in macros. NASM supports a few simple string handling macro operators from which more complex operations can be constructed.

All the string operators define or redefine a value (either a string or a numeric value) to a single-line macro. When producing a string value, it may change the style of quoting of the input string or strings, and possibly use \-escapes inside '-quoted strings.

4.2.1 Concatenating Strings: %strcat

The %strcat operator concatenates quoted strings and assign them to a single-line macro.

For example:

```
%strcat alpha "Alpha: ", '12" screen'
... would assign the value 'Alpha: 12" screen' to alpha. Similarly:
%strcat beta '"foo"\', "'bar'"
... would assign the value '"foo"\\'bar' to beta.
```

The use of commas to separate strings is permitted but optional.

4.2.2 String Length: %strlen

The %strlen operator assigns the length of a string to a macro. For example:

```
%strlen charcnt 'my string'
```

In this example, charcont would receive the value 9, just as if an %assign had been used. In this example, 'my string' was a literal string but it could also have been a single-line macro that expands to a string, as in the following example:

```
%define sometext 'my string'
%strlen charcnt sometext
```

As in the first case, this would result in charcnt being assigned the value of 9.

4.2.3 Extracting Substrings: %substr

Individual letters or substrings in strings can be extracted using the %substr operator. An example of its use is probably more useful than the description:

```
%substr mychar 'xyzw' 1 ; equivalent to %define mychar 'x' %substr mychar 'xyzw' 2 ; equivalent to %define mychar 'y' %substr mychar 'xyzw' 3 ; equivalent to %define mychar 'z' %substr mychar 'xyzw' 2,2 ; equivalent to %define mychar 'yz' %substr mychar 'xyzw' 2,-1 ; equivalent to %define mychar 'yzw' %substr mychar 'xyzw' 2,-2 ; equivalent to %define mychar 'yz'
```

As with %strlen (see section 4.2.2), the first parameter is the single-line macro to be created and the second is the string. The third parameter specifies the first character to be selected, and the optional fourth parameter preceded by comma) is the length. Note that the first index is 1, not 0 and the last index is equal to the value that %strlen would assign given the same string. Index values out of range result in an empty string. A negative length means "until N-1 characters before the end of string", i.e. -1 means until end of string, -2 until one character before, etc.

4.3 Multi-Line Macros: %macro

Multi-line macros are much more like the type of macro seen in MASM and TASM: a multi-line macro definition in NASM looks something like this.

```
%macro prologue 1

push ebp
mov ebp,esp
sub esp,%1
```

This defines a C-like function prologue as a macro: so you would invoke the macro with a call such as:

```
myfunc: prologue 12
```

%endmacro

which would expand to the three lines of code

```
myfunc: push ebp
mov ebp,esp
sub esp,12
```

The number 1 after the macro name in the <code>%macro</code> line defines the number of parameters the macro prologue expects to receive. The use of <code>%1</code> inside the macro definition refers to the first parameter to the macro call. With a macro taking more than one parameter, subsequent parameters would be referred to as <code>%2</code>, <code>%3</code> and so on.

Multi-line macros, like single-line macros, are case-sensitive, unless you define them using the alternative directive %imacro.

If you need to pass a comma as *part* of a parameter to a multi-line macro, you can do that by enclosing the entire parameter in braces. So you could code things like:

The behavior with regards to empty arguments at the end of multi-line macros before NASM 2.15 was often very strange. For backwards compatibility, NASM attempts to recognize cases where the legacy behavior would give unexpected results, and issues a warning, but largely tries to match the legacy behavior. This can be disabled with the %pragma (see section 4.10.1):

```
%pragma preproc sane_empty_expansion
```

4.3.1 Overloading Multi-Line Macros

As with single-line macros, multi-line macros can be overloaded by defining the same macro name several times with different numbers of parameters. This time, no exception is made for macros with no parameters at all. So you could define

```
%macro prologue 0

push ebp
mov ebp,esp
```

%endmacro

to define an alternative form of the function prologue which allocates no local stack space.

Sometimes, however, you might want to 'overload' a machine instruction; for example, you might want to define

Ordinarily, NASM will give a warning for the first of the above two lines, since push is now defined to be a macro, and is being invoked with a number of parameters for which no definition has been given. The correct code will still be generated, but the assembler will give a warning. This warning can be disabled by the use of the -w-macro-params command-line option (see section 2.1.26).

4.3.2 Macro-Local Labels

NASM allows you to define labels within a multi-line macro definition in such a way as to make them local to the macro call: so calling the same macro multiple times will use a different label each time. You do this by prefixing 5% to the label name. So you can invent an instruction which executes a RET if the z flag is set by doing this:

%endmacro

You can call this macro as many times as you want, and every time you call it NASM will make up a different 'real' name to substitute for the label <code>%%skip</code>. The names NASM invents are of the form ..@2345.skip, where the number 2345 changes with every macro call. The ..@ prefix prevents macro-local labels from interfering with the local label mechanism, as described in section 3.9. You should avoid defining your own labels in this form (the ..@ prefix, then a number, then another period) in case they interfere with macro-local labels.

These labels are really macro-local *tokens*, and can be used for other purposes where a token unique to each macro invocation is desired, e.g. to name single-line macros without using the context feature (section 4.7.2).

4.3.3 Greedy Macro Parameters

Occasionally it is useful to define a macro which lumps its entire command line into one parameter definition, possibly after extracting one or two smaller parameters from the front. An example might be a macro to write a text string to a file in MS-DOS, where you might want to be able to write

```
writefile [filehandle], "hello, world", 13, 10
```

NASM allows you to define the last parameter of a macro to be *greedy*, meaning that if you invoke the macro with more parameters than it expects, all the spare parameters get lumped into the last defined one along with the separating commas. So if you code:

%macro writefile 2+

%endmacro

then the example call to writefile above will work as expected: the text before the first comma, [filehandle], is used as the first macro parameter and expanded when %1 is referred to, and all the subsequent text is lumped into %2 and placed after the db.

The greedy nature of the macro is indicated to NASM by the use of the + sign after the parameter count on the %macro line.

If you define a greedy macro, you are effectively telling NASM how it should expand the macro given *any* number of parameters from the actual number specified up to infinity; in this case, for example, NASM now knows what to do when it sees a call to writefile with 2, 3, 4 or more parameters. NASM will take this into account when overloading macros, and will not allow you to define another form of writefile taking 4 parameters (for example).

Of course, the above macro could have been implemented as a non-greedy macro, in which case the call to it would have had to look like

```
writefile [filehandle], {"hello, world",13,10}
```

NASM provides both mechanisms for putting commas in macro parameters, and you choose which one you prefer for each macro definition.

See section 7.3.1 for a better way to write the above macro.

4.3.4 Macro Parameters Range

NASM allows you to expand parameters via special construction $\{x:y\}$ where x is the first parameter index and y is the last. Any index can be either negative or positive but must never be zero.

For example

```
%macro mpar 1-*
    db %{3:5}
%endmacro

mpar 1,2,3,4,5,6
expands to 3,4,5 range.
```

Even more, the parameters can be reversed so that

But even this is not the last. The parameters can be addressed via negative indices so NASM will count them reversed. The ones who know Python may see the analogue here.

```
%macro mpar 1-*
    db %{-1:-3}
%endmacro

mpar 1,2,3,4,5,6
expands to 6,5,4 range.
```

Note that NASM uses comma to separate parameters being expanded.

By the way, here is a trick – you might use the index %{-1:-1} which gives you the last argument passed to a macro.

4.3.5 Default Macro Parameters

NASM also allows you to define a multi-line macro with a *range* of allowable parameter counts. If you do this, you can specify defaults for omitted parameters. So, for example:

```
%macro die 0-1 "Painful program death has occurred."

writefile 2,%1

mov ax,0x4c01
int 0x21
```

%endmacro

This macro (which makes use of the writefile macro defined in section 4.3.3) can be called with an explicit error message, which it will display on the error output stream before exiting, or it can be called with no parameters, in which case it will use the default error message supplied in the macro definition.

In general, you supply a minimum and maximum number of parameters for a macro of this type; the minimum number of parameters are then required in the macro call, and then you provide defaults for the optional ones. So if a macro definition began with the line

```
%macro foobar 1-3 eax,[ebx+2]
```

then it could be called with between one and three parameters, and %1 would always be taken from the macro call. %2, if not specified by the macro call, would default to eax, and %3 if not specified would default to [ebx+2].

You can provide extra information to a macro by providing too many default parameters:

```
%macro quux 1 something
```

This will trigger a warning by default; see section 2.1.26 for more information. When quux is invoked, it receives not one but two parameters. something can be referred to as %2. The difference between passing something this way and writing something in the macro body is that with this way something is evaluated when the macro is defined, not when it is expanded.

You may omit parameter defaults from the macro definition, in which case the parameter default is taken to be blank. This can be useful for macros which can take a variable number of parameters, since the %0 token (see section 4.3.6) allows you to determine how many parameters were really passed to the macro call.

This defaulting mechanism can be combined with the greedy-parameter mechanism; so the die macro above could be made more powerful, and more useful, by changing the first line of the definition to

```
%macro die 0-1+ "Painful program death has occurred.",13,10
```

The maximum parameter count can be infinite, denoted by *. In this case, of course, it is impossible to provide a *full* set of default parameters. Examples of this usage are shown in section 4.3.8.

4.3.6 %0: Macro Parameter Counter

The parameter reference %0 will return a numeric constant giving the number of parameters received, that is, if %0 is n then %n is the last parameter. %0 is mostly useful for macros that can take a variable number of parameters. It can be used as an argument to %rep (see section 4.5) in order to iterate through all the parameters of a macro. Examples are given in section 4.3.8.

4.3.7 %00: Label Preceeding Macro

%00 will return the label preceding the macro invocation, if any. The label must be on the same line as the macro invocation, may be a local label (see section 3.9), and need not end in a colon.

If %00 is present anywhere in the macro body, the label itself will not be emitted by NASM. You can, of course, put %00: explicitly at the beginning of your macro.

4.3.8 %rotate: Rotating Macro Parameters

Unix shell programmers will be familiar with the shift shell command, which allows the arguments passed to a shell script (referenced as \$1, \$2 and so on) to be moved left by one place, so that the argument previously referenced as \$2 becomes available as \$1, and the argument previously referenced as \$1 is no longer available at all.

NASM provides a similar mechanism, in the form of %rotate. As its name suggests, it differs from the Unix shift in that no parameters are lost: parameters rotated off the left end of the argument list reappear on the right, and vice versa.

%rotate is invoked with a single numeric argument (which may be an expression). The macro parameters are rotated to the left by that many places. If the argument to %rotate is negative, the macro parameters are rotated to the right.

So a pair of macros to save and restore a set of registers might work as follows:

```
%macro multipush 1-*
    %rep %0
        push %1
    %rotate 1
    %endrep
```

%endmacro

This macro invokes the PUSH instruction on each of its arguments in turn, from left to right. It begins by pushing its first argument, %1, then invokes %rotate to move all the arguments one place to the left, so that the original second argument is now available as %1. Repeating this procedure as many times as there were arguments (achieved by supplying %0 as the argument to %rep) causes each argument in turn to be pushed.

Note also the use of * as the maximum parameter count, indicating that there is no upper limit on the number of parameters you may supply to the multipush macro.

It would be convenient, when using this macro, to have a POP equivalent, which *didn't* require the arguments to be given in reverse order. Ideally, you would write the multipush macro call, then cut-and-paste the line to where the pop needed to be done, and change the name of the called macro to multipop, and the macro would take care of popping the registers in the opposite order from the one in which they were pushed.

This can be done by the following definition:

```
%macro multipop 1-*
    %rep %0
    %rotate -1
        pop %1
    %endrep

%endmacro
```

This macro begins by rotating its arguments one place to the *right*, so that the original *last* argument appears as %1. This is then popped, and the arguments are rotated right again, so the second-to-last argument becomes %1. Thus the arguments are iterated through in reverse order.

4.3.9 Concatenating Macro Parameters

NASM can concatenate macro parameters and macro indirection constructs on to other text surrounding them. This allows you to declare a family of symbols, for example, in a macro definition. If, for example, you wanted to generate a table of key codes along with offsets into the table, you could code something like

```
%macro keytab_entry 2
    kevpos%1
                        $-keytab
                eau
                db
                        %2
%endmacro
keytab:
          keytab_entry F1,128+1
          keytab_entry F2,128+2
          keytab_entry Return,13
which would expand to
keyposF1
                equ
                        $-keytab
                db
                       128+1
keyposF2
                        $-keytab
                equ
                db
                        128+2
```

```
keyposReturn equ $-keytab
db 13
```

You can just as easily concatenate text on to the other end of a macro parameter, by writing %1 foo.

If you need to append a *digit* to a macro parameter, for example defining labels foo1 and foo2 when passed the parameter foo, you can't code %11 because that would be taken as the eleventh macro parameter. Instead, you must code %{1}1, which will separate the first 1 (giving the number of the macro parameter) from the second (literal text to be concatenated to the parameter).

This concatenation can also be applied to other preprocessor in-line objects, such as macro-local labels (section 4.3.2) and context-local labels (section 4.7.2). In all cases, ambiguities in syntax can be resolved by enclosing everything after the % sign and before the literal text in braces: so %{%foo}bar concatenates the text bar to the end of the real name of the macro-local label %%foo. (This is unnecessary, since the form NASM uses for the real names of macro-local labels means that the two usages %{%foo}bar and %%foobar would both expand to the same thing anyway; nevertheless, the capability is there.)

The single-line macro indirection construct, %[...] (section 4.1.3), behaves the same way as macro parameters for the purpose of concatenation.

See also the %+ operator, section 4.1.4.

4.3.10 Condition Codes as Macro Parameters

NASM can give special treatment to a macro parameter which contains a condition code. For a start, you can refer to the macro parameter %1 by means of the alternative syntax %+1, which informs NASM that this macro parameter is supposed to contain a condition code, and will cause the preprocessor to report an error message if the macro is called with a parameter which is *not* a valid condition code.

Far more usefully, though, you can refer to the macro parameter by means of %-1, which NASM will expand as the *inverse* condition code. So the retz macro defined in section 4.3.2 can be replaced by a general conditional-return macro like this:

%endmacro

This macro can now be invoked using calls like retc ne, which will cause the conditional-jump instruction in the macro expansion to come out as JE, or retc po which will make the jump a JPE.

The %+1 macro-parameter reference is quite happy to interpret the arguments CXZ and ECXZ as valid condition codes; however, %-1 will report an error if passed either of these, because no inverse condition code exists.

4.3.11 Disabling Listing Expansion

When NASM is generating a listing file from your program, it will generally expand multi-line macros by means of writing the macro call and then listing each line of the expansion. This allows you to see which instructions in the macro expansion are generating what code; however, for some macros this clutters the listing up unnecessarily.

NASM therefore provides the .nolist qualifier, which you can include in a macro definition to inhibit the expansion of the macro in the listing file. The .nolist qualifier comes directly after the number of parameters, like this:

```
%macro foo 1.nolist
```

Or like this:

```
%macro bar 1-5+.nolist a,b,c,d,e,f,g,h
```

4.3.12 Undefining Multi-Line Macros: %unmacro

Multi-line macros can be removed with the <code>%unmacro</code> directive. Unlike the <code>%undef</code> directive, however, <code>%unmacro</code> takes an argument specification, and will only remove exact matches with that argument specification.

For example:

does not remove the macro bar, since the argument specification does not match exactly.

4.4 Conditional Assembly

Similarly to the C preprocessor, NASM allows sections of a source file to be assembled only if certain conditions are met. The general syntax of this feature looks like this:

```
%if<condition>
   ; some code which only appears if <condition> is met
%elif<condition2>
   ; only appears if <condition> is not met but <condition2> is
%else
   ; this appears if neither <condition> nor <condition2> was met
%endif
```

The inverse forms %ifn and %elifn are also supported.

The %else clause is optional, as is the %elif clause. You can have more than one %elif clause as well.

There are a number of variants of the %if directive. Each has its corresponding %elif, %ifn, and %elifn directives; for example, the equivalents to the %ifdef directive are %elifdef, %ifndef, and %elifndef.

4.4.1 %ifdef: Testing Single-Line Macro Existence

Beginning a conditional-assembly block with the line %ifdef MACRO will assemble the subsequent code if, and only if, a single-line macro called MACRO is defined. If not, then the %elif and %else blocks (if any) will be processed instead.

For example, when debugging a program, you might want to write code such as

Then you could use the command-line option -dDEBUG to create a version of the program which produced debugging messages, and remove the option to generate the final release version of the program.

You can test for a macro *not* being defined by using <code>%ifndef</code> instead of <code>%ifdef</code>. You can also test for macro definitions in <code>%elif</code> blocks by using <code>%elif</code> and <code>%elif</code> ndef.

4.4.2 %ifmacro: Testing Multi-Line Macro Existence

The %ifmacro directive operates in the same way as the %ifdef directive, except that it checks for the existence of a multi-line macro.

For example, you may be working with a large project and not have control over the macros in a library. You may want to create a macro with one name if it doesn't already exist, and another name if one with that name does exist.

The %ifmacro is considered true if defining a macro with the given name and number of arguments would cause a definitions conflict. For example:

This will create the macro "MyMacro 1-3" if no macro already exists which would conflict with it, and emits a warning if there would be a definition conflict.

You can test for the macro not existing by using the %ifnmacro instead of %ifmacro. Additional tests can be performed in %elif blocks by using %elifmacro and %elifnmacro.

4.4.3 %ifctx: Testing the Context Stack

%endif

The conditional-assembly construct <code>%ifctx</code> will cause the subsequent code to be assembled if and only if the top context on the preprocessor's context stack has the same name as one of the arguments. As with <code>%ifdef</code>, the inverse and <code>%elif</code> forms <code>%ifnctx</code>, <code>%elifctx</code> and <code>%elifnctx</code> are also supported.

For more details of the context stack, see section 4.7. For a sample use of %ifctx, see section 4.7.6.

4.4.4 %if: Testing Arbitrary Numeric Expressions

The conditional-assembly construct %if expr will cause the subsequent code to be assembled if and only if the value of the numeric expression expr is non-zero. An example of the use of this feature is in deciding when to break out of a %rep preprocessor loop: see section 4.5 for a detailed example.

The expression given to %if, and its counterpart %elif, is a critical expression (see section 3.8).

Like other %if constructs, %if has a counterpart %elif, and negative forms %ifn and %elifn.

4.4.5 %ifidn and %ifidni: Testing Exact Text Identity

The construct %ifidn text1, text2 will cause the subsequent code to be assembled if and only if text1 and text2, after expanding single-line macros, are identical pieces of text. Differences in white space are not counted.

%ifidni is similar to %ifidn, but is case-insensitive.

For example, the following macro pushes a register or number on the stack, and allows you to treat IP as a real register:

```
%%label:
%else
    push %1
%endif
```

%endmacro

Like other %if constructs, %ifidn has a counterpart %elifidn, and negative forms %ifnidn and %elifnidn. Similarly, %ifidni has counterparts %elifidni, %ifnidni and %elifnidni.

4.4.6 %ifid, %ifnum, %ifstr: Testing Token Types

Some macros will want to perform different tasks depending on whether they are passed a number, a string, or an identifier. For example, a string output macro might want to be able to cope with being passed either a string constant or a pointer to an existing string.

The conditional assembly construct %ifid, taking one parameter (which may be blank), assembles the subsequent code if and only if the first token in the parameter exists and is an identifier. %ifnum works similarly, but tests for the token being a numeric constant; %ifstr tests for it being a string.

For example, the writefile macro defined in section 4.3.3 can be extended to take advantage of %ifstr in the following fashion:

%macro writefile 2-3+

```
%ifstr %2
               %%endstr
      jmp
  %if %0 = 3
    %%str:
               db
                       %2,%3
  %else
    %%str:
               db
                       %2
  %endif
    %%endstr: mov
                       dx, %%str
                       cx, %% endstr-%% str
               mov
%else
                       dx,%2
                       cx,%3
               mov
%endif
                       bx,%1
                       ah,0x40
               mov
                       0x21
```

%endmacro

Then the writefile macro can cope with being called in either of the following two ways:

```
writefile [file], strpointer, length
writefile [file], "hello", 13, 10
```

In the first, strpointer is used as the address of an already-declared string, and length is used as its length; in the second, a string is given to the macro, which therefore declares it itself and works out the address and length for itself.

Note the use of %if inside the %ifstr: this is to detect whether the macro was passed two arguments (so the string would be a single string constant, and db %2 would be adequate) or more (in which case, all but the first two would be lumped together into %3, and db %2,%3 would be required).

The usual %elif..., %ifn..., and %elifn... versions exist for each of %ifid, %ifnum and %ifstr.

4.4.7 %iftoken: Test for a Single Token

Some macros will want to do different things depending on if it is passed a single token (e.g. paste it to something else using %+) versus a multi-token sequence.

The conditional assembly construct %iftoken assembles the subsequent code if and only if the expanded parameters consist of exactly one token, possibly surrounded by whitespace.

For example:

```
%iftoken 1
```

will assemble the subsequent code, but

```
%iftoken -1
```

will not, since -1 contains two tokens: the unary minus operator -, and the number 1.

The usual %eliftoken, %ifntoken, and %elifntoken variants are also provided.

4.4.8 %ifempty: Test for Empty Expansion

The conditional assembly construct %ifempty assembles the subsequent code if and only if the expanded parameters do not contain any tokens at all, whitespace excepted.

The usual %elifempty, %ifnempty, and %elifnempty variants are also provided.

4.4.9 %ifenv: Test If Environment Variable Exists

The conditional assembly construct %ifenv assembles the subsequent code if and only if the environment variable referenced by the %! variable directive exists.

The usual %elifenv, %ifnenv, and %elifnenv variants are also provided.

Just as for %! variable the argument should be written as a string if it contains characters that would not be legal in an identifier. See section 4.11.2.

4.5 Preprocessor Loops: %rep

NASM's TIMES prefix, though useful, cannot be used to invoke a multi-line macro multiple times, because it is processed by NASM after macros have already been expanded. Therefore NASM provides another form of loop, this time at the preprocessor level: %rep.

The directives <code>%rep</code> and <code>%endrep</code> (<code>%rep</code> takes a numeric argument, which can be an expression; <code>%endrep</code> takes no arguments) can be used to enclose a chunk of code, which is then replicated as many times as specified by the preprocessor:

```
%assign i 0
%rep 64
    inc word [table+2*i]
%assign i i+1
%endrep
```

This will generate a sequence of 64 INC instructions, incrementing every word of memory from [table] to [table+126].

For more complex termination conditions, or to break out of a repeat loop part way along, you can use the <code>%exitrep</code> directive to terminate the loop, like this:

This produces a list of all the Fibonacci numbers that will fit in 16 bits. Note that a maximum repeat count must still be given to %rep. This is to prevent the possibility of NASM getting into an infinite loop in the preprocessor, which (on multitasking or multi-user systems) would typically cause all the system memory to be gradually used up and other applications to start crashing.

Note the maximum repeat count is limited to the value specified by the --limit-rep option or %pragma limit rep, see section 2.1.31.

4.6 Source Files and Dependencies

These commands allow you to split your sources into multiple files.

4.6.1 %include: Including Other Files

Using, once again, a very similar syntax to the C preprocessor, NASM's preprocessor lets you include other source files into your code. This is done by the use of the %include directive:

```
%include "macros.mac"
```

will include the contents of the file macros.mac into the source file containing the %include directive.

Include files are searched for in the current directory (the directory you're in when you run NASM, as opposed to the location of the NASM executable or the location of the source file), plus any directories specified on the NASM command line using the -i option.

The standard C idiom for preventing a file being included more than once is just as applicable in NASM: if the file macros.mac has the form

then including the file more than once will not cause errors, because the second time the file is included nothing will happen because the macro MACROS_MAC will already be defined.

You can force a file to be included even if there is no %include directive that explicitly includes it, by using the -p option on the NASM command line (see section 2.1.19).

4.6.2 %pathsearch: Search the Include Path

The %pathsearch directive takes a single-line macro name and a filename, and declare or redefines the specified single-line macro to be the include-path-resolved version of the filename, if the file exists (otherwise, it is passed unchanged.)

For example,

```
%pathsearch MyFoo "foo.bin"
```

... with -Ibins/ in the include path may end up defining the macro MyFoo to be "bins/foo.bin".

4.6.3 %depend: Add Dependent Files

The %depend directive takes a filename and adds it to the list of files to be emitted as dependency generation when the -M options and its relatives (see section 2.1.5) are used. It produces no output.

This is generally used in conjunction with %pathsearch. For example, a simplified version of the standard macro wrapper for the INCBIN directive looks like:

```
%imacro incbin 1-2+ 0
%pathsearch dep %1
%depend dep
        incbin dep,%2
%endmacro
```

This first resolves the location of the file into the macro dep, then adds it to the dependency lists, and finally issues the assembler-level INCBIN directive.

4.6.4 %use: Include Standard Macro Package

The <code>%use</code> directive is similar to <code>%include</code>, but rather than including the contents of a file, it includes a named standard macro package. The standard macro packages are part of NASM, and are described in chapter 6.

Unlike the %include directive, package names for the %use directive do not require quotes, but quotes are permitted. In NASM 2.04 and 2.05 the unquoted form would be macro-expanded; this is no longer true. Thus, the following lines are equivalent:

```
%use altreg
%use 'altreg'
```

Standard macro packages are protected from multiple inclusion. When a standard macro package is used, a testable single-line macro of the form __?USE_package?__ is also defined, see section 5.7.

4.7 The Context Stack

Having labels that are local to a macro definition is sometimes not quite powerful enough: sometimes you want to be able to share labels between several macro calls. An example might be a REPEAT ... UNTIL loop, in which the expansion of the REPEAT macro would need to be able to refer to a label which the UNTIL macro had defined. However, for such a macro you would also want to be able to nest these loops.

NASM provides this level of power by means of a *context stack*. The preprocessor maintains a stack of *contexts*, each of which is characterized by a name. You add a new context to the stack using the %push directive, and remove one using %pop. You can define labels that are local to a particular context on the stack.

4.7.1 %push and %pop: Creating and Removing Contexts

The %push directive is used to create a new context and place it on the top of the context stack. %push takes an optional argument, which is the name of the context. For example:

```
%push foobar
```

This pushes a new context called foobar on the stack. You can have several contexts on the stack with the same name: they can still be distinguished. If no name is given, the context is unnamed (this is normally used when both the %push and the %pop are inside a single macro definition.)

The directive %pop, taking one optional argument, removes the top context from the context stack and destroys it, along with any labels associated with it. If an argument is given, it must match the name of the current context, otherwise it will issue an error.

4.7.2 Context-Local Labels

Just as the usage %%foo defines a label which is local to the particular macro call in which it is used, the usage %\$foo is used to define a label which is local to the context on the top of the context stack. So the REPEAT and UNTIL example given above could be implemented by means of:

%pop

%endmacro

and invoked by means of, for example,

```
mov cx,string
repeat
add cx,3
scasb
until e
```

which would scan every fourth byte of a string in search of the byte in AL.

If you need to define, or access, labels local to the context *below* the top one on the stack, you can use %\$\$foo, or %\$\$\$foo for the context below that, and so on.

4.7.3 Context-Local Single-Line Macros

NASM also allows you to define single-line macros which are local to a particular context, in just the same way:

```
%define %$localmac 3
```

will define the single-line macro %\$localmac to be local to the top context on the stack. Of course, after a subsequent %push, it can then still be accessed by the name %\$\$localmac.

4.7.4 Context Fall-Through Lookup (deprecated)

Context fall-through lookup (automatic searching of outer contexts) is a feature that was added in NASM version 0.98.03. Unfortunately, this feature is unintuitive and can result in buggy code that would have otherwise been prevented by NASM's error reporting. As a result, this feature has been deprecated. NASM version 2.09 will issue a warning when usage of this deprecated feature is detected. Starting with NASM version 2.10, usage of this deprecated feature will simply result in an expression syntax error.

An example usage of this deprecated feature follows:

As demonstrated, %\$external is being defined in the ctx1 context and referenced within the ctx2 context. With context fall-through lookup, referencing an undefined context-local macro like this implicitly searches through all outer contexts until a match is made or isn't found in any context. As a result, %\$external referenced within the ctx2 context would implicitly use %\$external as defined in ctx1. Most people would expect NASM to issue an error in this situation because %\$external was never defined within ctx2 and also isn't qualified with the proper context depth, %\$\$external.

Here is a revision of the above example with proper context depth:

```
%pop
%endmacro
```

As demonstrated, %\$external is still being defined in the ctx1 context and referenced within the ctx2 context. However, the reference to %\$external within ctx2 has been fully qualified with the proper context depth, %\$\$external, and thus is no longer ambiguous, unintuitive or erroneous.

4.7.5 %repl: Renaming a Context

If you need to change the name of the top context on the stack (in order, for example, to have it respond differently to %ifctx), you can execute a %pop followed by a %push; but this will have the side effect of destroying all context-local labels and macros associated with the context that was just popped.

NASM provides the directive %repl, which replaces a context with a different name, without touching the associated macros and labels. So you could replace the destructive code

```
%pop
%push newname
```

%endmacro

with the non-destructive version %repl newname.

4.7.6 Example Use of the Context Stack: Block IFs

This example makes use of almost all the context-stack features, including the conditional-assembly construct %ifctx, to implement a block IF statement as a set of macros.

```
%macro if 1
    %push if
    j%-1 %$ifnot
%endmacro
%macro else 0
  %ifctx if
        %repl
                else
                %$ifend
        jmp
        %$ifnot:
  %else
        %error "expected 'if' before 'else'"
  %endif
%endmacro
%macro endif 0
  %ifctx if
        %$ifnot:
        %pop
  %elifctx
                else
        %$ifend:
        %рор
  %else
        %error "expected 'if' or 'else' before 'endif'"
  %endif
```

This code is more robust than the REPEAT and UNTIL macros given in section 4.7.2, because it uses conditional assembly to check that the macros are issued in the right order (for example, not calling endif before if) and issues a %error if they're not.

In addition, the endif macro has to be able to cope with the two distinct cases of either directly following an if, or following an else. It achieves this, again, by using conditional assembly to do different things depending on whether the context on top of the stack is if or else.

The else macro has to preserve the context on the stack, in order to have the %\$ifnot referred to by the if macro be the same as the one defined by the endif macro, but has to change the context's name so that endif will know there was an intervening else. It does this by the use of %repl.

A sample usage of these macros might look like:

```
cmp
        ax,bx
if ae
       cmp
                bx,cx
       if ae
                mov
                         ax,cx
       else
                mov
                         ax,bx
       endif
else
       cmp
                ax,cx
       if ae
                mov
                         ax,cx
       endif
endif
```

The block-IF macros handle nesting quite happily, by means of pushing another context, describing the inner if, on top of the one describing the outer if; thus else and endif always refer to the last unmatched if or else.

4.8 Stack Relative Preprocessor Directives

The following preprocessor directives provide a way to use labels to refer to local variables allocated on the stack.

- %arg (see section 4.8.1)
- %stacksize (see section 4.8.2)
- %local (see section 4.8.3)

4.8.1 %arg Directive

The %arg directive is used to simplify the handling of parameters passed on the stack. Stack based parameter passing is used by many high level languages, including C, C++ and Pascal.

While NASM has macros which attempt to duplicate this functionality (see section 9.4.5), the syntax is not particularly convenient to use and is not TASM compatible. Here is an example which shows the use of %arg without any external macros:

some_function:

```
%push
          mycontext
                           ; save the current context
                           ; tell NASM to use bp
%stacksize large
          i:word, j_ptr:word
%arg
    mov
            ax,[i]
    mov
            bx,[j_ptr]
    add
            ax,[bx]
    ret
                           ; restore original context
%pop
```

This is similar to the procedure defined in section 9.4.5 and adds the value in i to the value pointed to by j_ptr and returns the sum in the ax register. See section 4.7.1 for an explanation of push and pop and the use of context stacks.

4.8.2 %stacksize Directive

The %stacksize directive is used in conjunction with the %arg (see section 4.8.1) and the %local (see section 4.8.3) directives. It tells NASM the default size to use for subsequent %arg and %local directives. The %stacksize directive takes one required argument which is one of flat, flat64, large or small.

```
%stacksize flat
```

This form causes NASM to use stack-based parameter addressing relative to ebp and it assumes that a near form of call was used to get to this label (i.e. that eip is on the stack).

```
%stacksize flat64
```

This form causes NASM to use stack-based parameter addressing relative to rbp and it assumes that a near form of call was used to get to this label (i.e. that rip is on the stack).

```
%stacksize large
```

This form uses bp to do stack-based parameter addressing and assumes that a far form of call was used to get to this address (i.e. that ip and cs are on the stack).

```
%stacksize small
```

This form also uses bp to address stack parameters, but it is different from large because it also assumes that the old value of bp is pushed onto the stack (i.e. it expects an ENTER instruction). In other words, it expects that bp, ip and cs are on the top of the stack, underneath any local space which may have been allocated by ENTER. This form is probably most useful when used in combination with the %local directive (see section 4.8.3).

4.8.3 %local Directive

The %local directive is used to simplify the use of local temporary stack variables allocated in a stack frame. Automatic local variables in C are an example of this kind of variable. The %local directive is most useful when used with the %stacksize (see section 4.8.2 and is also compatible with the %arg directive (see section 4.8.1). It allows simplified reference to variables on the stack which have been allocated typically by using the ENTER instruction. An example of its use is the following:

```
silly_swap:
```

```
; save the current context
%push mycontext
%stacksize small
                            ; tell NASM to use bp
%assign %$localsize 0
                            ; see text for explanation
%local old_ax:word, old_dx:word
                           ; see text for explanation
    enter
            %$localsize,0
                          ; swap ax & bx
   mov
            [old_ax],ax
   mov
            [old_dx],dx
                            ; and swap dx & cx
            ax,bx
   mov
    mov
            dx,cx
            bx,[old_ax]
   mov
   mov
            cx,[old_dx]
                            ; restore old bp
    leave
    ret
                            ; restore original context
```

The <code>%\$localsize</code> variable is used internally by the <code>%local</code> directive and <code>must</code> be defined within the current context before the <code>%local</code> directive may be used. Failure to do so will result in one expression syntax error for each <code>%local</code> variable declared. It then may be used in the construction of an appropriately sized ENTER instruction as shown in the example.

4.9 Reporting User-Defined Errors: %error, %warning, %fatal

The preprocessor directive %error will cause NASM to report an error if it occurs in assembled code. So if other users are going to try to assemble your source files, you can ensure that they define the right macros by means of code like this:

Then any user who fails to understand the way your code is supposed to be assembled will be quickly warned of their mistake, rather than having to wait until the program crashes on being run and then not knowing what went wrong.

Similarly, warning issues a warning, but allows assembly to continue:

%error and %warning are issued only on the final assembly pass. This makes them safe to use in conjunction with tests that depend on symbol values.

%fatal terminates assembly immediately, regardless of pass. This is useful when there is no point in continuing the assembly further, and doing so is likely just going to cause a spew of confusing error messages.

It is optional for the message string after %error, %warning or %fatal to be quoted. If it is *not*, then single-line macros are expanded in it, which can be used to display more information to the user. For example:

4.10 %pragma: Setting Options

The %pragma directive controls a number of options in NASM. Pragmas are intended to remain backwards compatible, and therefore an unknown %pragma directive is not an error.

The various pragmas are documented with the options they affect.

The general structure of a NASM pragma is:

%pragma namespace directive [arguments...]

Currently defined namespaces are:

- ignore: this %pragma is unconditionally ignored.
- preproc: preprocessor, see section 4.10.1.
- limit: resource limits, see section 2.1.31.
- asm: the parser and assembler proper. Currently no such pragmas are defined.
- list: listing options, see section 2.1.4.

- file: general file handling options. Currently no such pragmas are defined.
- input: input file handling options. Currently no such pragmas are defined.
- output: output format options.
- debug: debug format options.

In addition, the name of any output or debug format, and sometimes groups thereof, also constitue %pragma namespaces. The namespaces output and debug simply refer to *any* output or debug format, respectively.

For example, to prepend an underscore to global symbols regardless of the output format (see section 7.10):

```
%pragma output gprefix _
```

... whereas to prepend an underscore to global symbols only when the output is either win32 or win64:

%pragma win gprefix _

4.10.1 Preprocessor Pragmas

The only preprocessor %pragma defined in NASM 2.15 is:

• %pragma preproc sane_empty_expansion: disables legacy compatibility handling of braceless empty arguments to multi-line macros. See section 4.3 and section 2.1.26.

4.11 Other Preprocessor Directives

4.11.1 %line Directive

The %line directive is used to notify NASM that the input line corresponds to a specific line number in another file. Typically this other file would be an original source file, with the current NASM input being the output of a pre-processor. The %line directive allows NASM to output messages which indicate the line number of the original source file, instead of the file that is being read by NASM.

This preprocessor directive is not generally used directly by programmers, but may be of interest to preprocessor authors. The usage of the %line preprocessor directive is as follows:

```
%line nnn[+mmm] [filename]
```

In this directive, nnn identifies the line of the original source file which this line corresponds to. mmm is an optional parameter which specifies a line increment value; each line of the input file read in is considered to correspond to mmm lines of the original source file. Finally, filename is an optional parameter which specifies the file name of the original source file. It may be a quoted string, in which case any additional argument after the quoted string will be ignored.

After reading a %line preprocessor directive, NASM will report all file name and line numbers relative to the values specified therein.

If the command line option --no-line is given, all %line directives are ignored. This may be useful for debugging preprocessed code. See section 2.1.33.

Starting in NASM 2.15, %line directives are processed before any other processing takes place.

For compatibility with the output from some other preprocessors, including many C preprocessors, a # character followed by whitespace at the very beginning of a line is also treated as a %line directive, except that double quotes surrounding the filename are treated like NASM backquotes, with \-escaped sequences decoded.

4.11.2 %! variable: Read an Environment Variable.

The %! variable directive makes it possible to read the value of an environment variable at assembly time. This could, for example, be used to store the contents of an environment variable into a string, which could be used at some other point in your code.

For example, suppose that you have an environment variable FOO, and you want the contents of FOO to be embedded in your program as a quoted string. You could do that as follows:

```
%defstr F00 %!F00
```

See section 4.1.9 for notes on the %defstr directive.

If the name of the environment variable contains non-identifier characters, you can use string quotes to surround the name of the variable, for example:

```
%defstr C_colon %!'C:'
```

4.11.3 %clear: Clear All Macro Definitions

The directive %clear clears all definitions of a certain type, *including the ones defined by NASM itself.* This can be useful when preprocessing non-NASM code, or to drop backwards compatibility aliases.

The syntax is:

```
%clear [global|context] type...
```

... where context indicates that this applies to context-local macros only; the default is global.

type can be one or more of:

- define single-line macros
- defalias single-line macro aliases (useful to remove backwards compatibility aliases)
- alldefine same as define defalias
- macro multi-line macros
- all same as alldefine macro (default)

In NASM 2.14 and earlier, only the single syntax %clear was supported, which is equivalent to %clear global all.

Chapter 5: Standard Macros

NASM defines a set of standard macros, which are already defined when it starts to process any source file. If you really need a program to be assembled with no pre-defined macros, you can use the %clear directive to empty the preprocessor of everything but context-local preprocessor variables and single-line macros, see section 4.11.3.

Most user-level directives (see chapter 7) are implemented as macros which invoke primitive directives; these are described in chapter 7. The rest of the standard macro set is described here.

For compability with NASM versions before NASM 2.15, most standard macros of the form __?foo?__ have aliases of form __foo__ (see section 4.1.11). These can be removed with the directive %clear defalias.

5.1 NASM Version Macros

The single-line macros __?NASM_MAJOR?__, __?NASM_MINOR?__, __?NASM_SUBMINOR?__ and __?NASM_PATCHLEVEL?__ expand to the major, minor, subminor and patch level parts of the version number of NASM being used. So, under NASM 0.98.32p1 for example, __?NASM_MAJOR?__ would be defined to be 0, __?NASM_MINOR?__ would be defined as 98, __?NASM_SUBMINOR?__ would be defined to 32, and __?NASM_PATCHLEVEL?__ would be defined as 1.

Additionally, the macro __?NASM_SNAPSHOT?__ is defined for automatically generated snapshot releases only.

5.1.1 __?NASM_VERSION_ID?__: NASM Version ID

The single-line macro __?NASM_VERSION_ID?__ expands to a dword integer representing the full version number of the version of nasm being used. The value is the equivalent to __?NASM_MAJOR?__, __?NASM_MINOR?__, and __?NASM_PATCHLEVEL?__ concatenated to produce a single doubleword. Hence, for 0.98.32p1, the returned number would be equivalent to:

```
dd 0x00622001
or
db 1,32,98,0
```

Note that the above lines are generate exactly the same code, the second line is used just to give an indication of the order that the separate values will be present in memory.

5.1.2 __?NASM_VER?__: NASM Version String

The single-line macro __?NASM_VER?__ expands to a string which defines the version number of nasm being used. So, under NASM 0.98.32 for example,

```
db __?NASM_VER?__
would expand to
db "0.98.32"
```

5.2 __?FILE?__ and __?LINE?__: File Name and Line Number

Like the C preprocessor, NASM allows the user to find out the file name and line number containing the current instruction. The macro __?FILE?__ expands to a string constant giving the name of the current input file (which may change through the course of assembly if %include directives are used), and __?LINE?__ expands to a numeric constant giving the current line number in the input file.

These macros could be used, for example, to communicate debugging information to a macro, since invoking __?LINE?__ inside a macro definition (either single-line or multi-line) will return the line

number of the macro *call*, rather than *definition*. So to determine where in a piece of code a crash is occurring, for example, one could write a routine stillhere, which is passed a line number in EAX and outputs something like line 155: still here. You could then write a macro:

```
%macro notdeadyet 0

push eax
mov eax,__?LINE?__
call stillhere
pop eax
```

%endmacro

and then pepper your code with calls to notdeadyet until you find the crash point.

5.3 __?BITS?__: Current Code Generation Mode

The __?BITS?__ standard macro is updated every time that the BITS mode is set using the BITS XX or [BITS XX] directive, where XX is a valid mode number of 16, 32 or 64. __?BITS?__ receives the specified mode number and makes it globally available. This can be very useful for those who utilize mode-dependent macros.

5.4 __?OUTPUT_FORMAT?__: Current Output Format

The __?OUTPUT_FORMAT?__ standard macro holds the current output format name, as given by the -f option or NASM's default. Type nasm -h for a list.

```
%ifidn __?OUTPUT_FORMAT?__, win32
%define NEWLINE 13, 10
%elifidn __?OUTPUT_FORMAT?__, elf32
%define NEWLINE 10
%endif
```

5.5 __?DEBUG_FORMAT?__: Current Debug Format

If debugging information generation is enabled, The __?DEBUG_FORMAT?__ standard macro holds the current debug format name as specified by the -F or -g option or the output format default. Type nasm -f output y for a list.

__?DEBUG_FORMAT?__ is not defined if debugging is not enabled, or if the debug format specified is null.

5.6 Assembly Date and Time Macros

NASM provides a variety of macros that represent the timestamp of the assembly session.

- The __?DATE?__ and __?TIME?__ macros give the assembly date and time as strings, in ISO 8601 format ("YYYY-MM-DD" and "HH:MM:SS", respectively.)
- The __?DATE_NUM?__ and __?TIME_NUM?__ macros give the assembly date and time in numeric form; in the format YYYYMMDD and HHMMSS respectively.
- The __?UTC_DATE?__ and __?UTC_TIME?__ macros give the assembly date and time in universal time (UTC) as strings, in ISO 8601 format ("YYYY-MM-DD" and "HH:MM:SS", respectively.) If the host platform doesn't provide UTC time, these macros are undefined.
- The __?UTC_DATE_NUM?__ and __?UTC_TIME_NUM?__ macros give the assembly date and time universal time (UTC) in numeric form; in the format YYYYMMDD and HHMMSS respectively. If the host platform doesn't provide UTC time, these macros are undefined.
- The __?POSIX_TIME?__ macro is defined as a number containing the number of seconds since the POSIX epoch, 1 January 1970 00:00:00 UTC; excluding any leap seconds. This is computed using UTC time if available on the host platform, otherwise it is computed using the local time as if it was UTC.

All instances of time and date macros in the same assembly session produce consistent output. For example, in an assembly session started at 42 seconds after midnight on January 1, 2010 in Moscow (timezone UTC+3) these macros would have the following values, assuming, of course, a properly configured environment with a correct clock:

```
__?DATE?__
                        "2010-01-01"
__?TIME?_
                        "00:00:42"
__?DATE_NUM?_
                        20100101
__?TIME_NUM?__
                        000042
__?UTC_DATE?__
                        "2009-12-31"
                       "21:00:42"
__?UTC_TIME?__
__?UTC_DATE_NUM?_
                        20091231
__?UTC_TIME_NUM?__
                        210042
__?POSIX_TIME?__
                        1262293242
```

5.7 __?USE_package?__: Package Include Test

When a standard macro package (see chapter 6) is included with the %use directive (see section 4.6.4), a single-line macro of the form __use_package__ is automatically defined. This allows testing if a particular package is invoked or not.

For example, if the altreg package is included (see section 6.1), then the macro __?USE_ALTREG?__ is defined.

5.8 __?PASS?__: Assembly Pass

The macro __?PASS?__ is defined to be 1 on preparatory passes, and 2 on the final pass. In preprocess-only mode, it is set to 3, and when running only to generate dependencies (due to the -M or -MG option, see section 2.1.5) it is set to 0.

Avoid using this macro if at all possible. It is tremendously easy to generate very strange errors by misusing it, and the semantics may change in future versions of NASM.

5.9 Structure Data Types

5.9.1 STRUC and ENDSTRUC: Declaring Structure Data Types

The core of NASM contains no intrinsic means of defining data structures; instead, the preprocessor is sufficiently powerful that data structures can be implemented as a set of macros. The macros STRUC and ENDSTRUC are used to define a structure data type.

STRUC takes one or two parameters. The first parameter is the name of the data type. The second, optional parameter is the base offset of the structure. The name of the data type is defined as a symbol with the value of the base offset, and the name of the data type with the suffix _size appended to it is defined as an EQU giving the size of the structure. Once STRUC has been issued, you are defining the structure, and should define fields using the RESB family of pseudo-instructions, and then invoke ENDSTRUC to finish the definition.

For example, to define a structure called mytype containing a longword, a word, a byte and a string of bytes, you might code

```
struc mytype

mt_long: resd 1
mt_word: resw 1
mt_byte: resb 1
mt_str: resb 32
endstruc
```

The above code defines six symbols: mt_long as 0 (the offset from the beginning of a mytype structure to the longword field), mt_word as 4, mt_byte as 6, mt_str as 7, mytype_size as 39, and mytype itself as zero.

The reason why the structure type name is defined at zero by default is a side effect of allowing structures to work with the local label mechanism: if your structure members tend to have the same names in more than one structure, you can define the above structure like this:

struc mytype

```
.long: resd 1
.word: resw 1
.byte: resb 1
.str: resb 32
```

endstruc

This defines the offsets to the structure fields as mytype.long, mytype.word, mytype.byte and mytype.str.

NASM, since it has no *intrinsic* structure support, does not support any form of period notation to refer to the elements of a structure once you have one (except the above local-label notation), so code such as mov ax,[mystruc.mt_word] is not valid. mt_word is a constant just like any other constant, so the correct syntax is mov ax,[mystruc+mt_word] or mov ax,[mystruc+mytype.word].

Sometimes you only have the address of the structure displaced by an offset. For example, consider this standard stack frame setup:

```
push ebp
mov ebp, esp
sub esp, 40

In this case, you could access an element by subtracting the offset:
mov [ebp - 40 + mytype.word], ax

However, if you do not want to repeat this offset, you can use -40 as a base offset:
struc mytype, -40

And access an element this way:
mov [ebp + mytype.word], ax
```

5.9.2 ISTRUC, AT and IEND: Declaring Instances of Structures

Having defined a structure type, the next thing you typically want to do is to declare instances of that structure in your data segment. NASM provides an easy way to do this in the ISTRUC mechanism. To declare a structure of type mytype in a program, you code something like this:

The function of the AT macro is to make use of the TIMES prefix to advance the assembly position to the correct point for the specified structure field, and then to declare the specified data. Therefore the structure fields must be declared in the same order as they were specified in the structure definition.

If the data to go in a structure field requires more than one source line to specify, the remaining source lines can easily come after the AT line. For example:

```
at mt_str, db 123,134,145,156,167,178,189
db 190,100,0
```

Depending on personal taste, you can also omit the code part of the AT line completely, and start the structure field on the next line:

```
at mt_str
db 'hello, world'
db 13,10,0
```

5.10 Alignment Control

5.10.1 ALIGN and ALIGNB: Code and Data Alignment

The ALIGN and ALIGNB macros provides a convenient way to align code or data on a word, longword, paragraph or other boundary. (Some assemblers call this directive EVEN.) The syntax of the ALIGN and ALIGNB macros is

```
align 4 ; align on 4-byte boundary align 16 ; align on 16-byte boundary align 8,db 0 ; pad with 0s rather than NOPs align 4,resb 1 ; align to 4 in the BSS alignb 4 ; equivalent to previous line
```

Both macros require their first argument to be a power of two; they both compute the number of additional bytes required to bring the length of the current section up to a multiple of that power of two, and then apply the TIMES prefix to their second argument to perform the alignment.

If the second argument is not specified, the default for ALIGN is NOP, and the default for ALIGNB is RESB 1. So if the second argument is specified, the two macros are equivalent. Normally, you can just use ALIGNB in code and data sections and ALIGNB in BSS sections, and never need the second argument except for special purposes.

ALIGN and ALIGNB, being simple macros, perform no error checking: they cannot warn you if their first argument fails to be a power of two, or if their second argument generates more than one byte of code. In each of these cases they will silently do the wrong thing.

ALIGNB (or ALIGN with a second argument of RESB 1) can be used within structure definitions:

endstruc

This will ensure that the structure members are sensibly aligned relative to the base of the structure.

A final caveat: ALIGN and ALIGNB work relative to the beginning of the section, not the beginning of the address space in the final executable. Aligning to a 16-byte boundary when the section you're in is only guaranteed to be aligned to a 4-byte boundary, for example, is a waste of effort. Again, NASM does not check that the section's alignment characteristics are sensible for the use of ALIGN OF ALIGNB.

Both ALIGN and ALIGNB do call SECTALIGN macro implicitly. See section 5.10.2 for details.

See also the smartalign standard macro package, section 6.2.

5.10.2 SECTALIGN: Section Alignment

The SECTALIGN macros provides a way to modify alignment attribute of output file section. Unlike the align= attribute (which is allowed at section definition only) the SECTALIGN macro may be used at any time.

For example the directive

SECTALIGN 16

sets the section alignment requirements to 16 bytes. Once increased it can not be decreased, the magnitude may grow only.

Note that ALIGN (see section 5.10.1) calls the SECTALIGN macro implicitly so the active section alignment requirements may be updated. This is by default behaviour, if for some reason you want the ALIGN do not call SECTALIGN at all use the directive

SECTALIGN OFF

It is still possible to turn in on again by

SECTALIGN ON

Note that SECTALIGN <ON|OFF> affects only the ALIGN/ALIGNB directives, not an explicit SECTALIGN directive.

Chapter 6: Standard Macro Packages

The %use directive (see section 4.6.4) includes one of the standard macro packages included with the NASM distribution and compiled into the NASM binary. It operates like the %include directive (see section 4.6.1), but the included contents is provided by NASM itself.

The names of standard macro packages are case insensitive and can be quoted or not.

As of version 2.15, NASM has %ifusable and %ifusing directives to help the user understand whether an individual package available in this version of NASM (%ifusable) or a particular package already loaded (%ifusing).

6.1 altreg: Alternate Register Names

The altreg standard macro package provides alternate register names. It provides numeric register names for all registers (not just R8-R15), the Intel-defined aliases R8L-R15L for the low bytes of register (as opposed to the NASM/AMD standard names R8B-R15B), and the names R0H-R3H (by analogy with R0L-R3L) for AH, CH, DH, and BH.

Example use:

See also section 12.1.

6.2 smartalign: Smart ALIGN Macro

The smartalign standard macro package provides for an ALIGN macro which is more powerful than the default (and backwards-compatible) one (see section 5.10.1). When the smartalign package is enabled, when ALIGN is used without a second argument, NASM will generate a sequence of instructions more efficient than a series of NOP. Furthermore, if the padding exceeds a specific threshold, then NASM will generate a jump over the entire padding sequence.

The specific instructions generated can be controlled with the new ALIGNMODE macro. This macro takes two parameters: one mode, and an optional jump threshold override. If (for any reason) you need to turn off the jump completely just set jump threshold value to -1 (or set it to nojmp). The following modes are possible:

- generic: Works on all x86 CPUs and should have reasonable performance. The default jump threshold is 8. This is the default.
- nop: Pad out with NOP instructions. The only difference compared to the standard ALIGN macro is that NASM can still jump over a large padding area. The default jump threshold is 16.
- k7: Optimize for the AMD K7 (Athlon/Althon XP). These instructions should still work on all x86 CPUs. The default jump threshold is 16.
- k8: Optimize for the AMD K8 (Opteron/Althon 64). These instructions should still work on all x86 CPUs. The default jump threshold is 16.
- p6: Optimize for Intel CPUs. This uses the long NOP instructions first introduced in Pentium Pro. This is incompatible with all CPUs of family 5 or lower, as well as some VIA CPUs and several virtualization solutions. The default jump threshold is 16.

The macro __?ALIGNMODE?__ is defined to contain the current alignment mode. A number of other macros beginning with __?ALIGN_ are used internally by this macro package.

6.3 fp: Floating-point macros

This packages contains the following floating-point convenience macros:

```
%define Inf
                       __?Infinity?__
                       __?QNaN?__
%define NaN
%define QNaN
                       __?QNaN?__
%define SNaN
                        __?SNaN?__
%define float8(x)
                       __?float8?__(x)
                       __?float16?__(x)
%define float16(x)
%define bfloat16(x)
                       __?bfloat16?__(x)
%define float32(x)
                       __?float32?__(x)
%define float64(x)
                       __?float64?__(x)
                      __?float80m?__(x)
%define float80m(x)
%define float80e(x)
                       __?float80e?__(x)
                       __?float128l?__(x)
%define float128l(x)
%define float128h(x)
                       __?float128h?__(x)
```

It also defines the a multi-line macro bf16 that can be used in a similar way to the DX directives for the other floating-point numbers:

```
bf16 -3.1415, NaN, 2000.0, +Inf
```

6.4 ifunc: Integer functions

This package contains a set of macros which implement integer functions. These are actually implemented as special operators, but are most conveniently accessed via this macro package.

The macros provided are:

6.4.1 Integer logarithms

These functions calculate the integer logarithm base 2 of their argument, considered as an unsigned integer. The only differences between the functions is their respective behavior if the argument provided is not a power of two.

The function <code>ilog2e()</code> (alias <code>ilog2()</code>) generates an error if the argument is not a power of two.

The function <code>ilog2f()</code> rounds the argument down to the nearest power of two; if the argument is zero it returns zero.

The function ilog2c() rounds the argument up to the nearest power of two.

The functions ilog2fw() (alias ilog2w()) and ilog2cw() generate a warning if the argument is not a power of two, but otherwise behaves like ilog2f() and ilog2c(), respectively.

6.5 masm: MASM compatibility

Since version 2.15, NASM has a MASM compatibility package with minimal functionality, as intended to be used primarily with machine-generated code. It does not include any "programmer-friendly" shortcuts, nor does it in any way support ASSUME, symbol typing, or MASM-style structures.

To enable the package, use the directive:

```
%use masm
```

Currently, the MASM compatibility package emulates:

- The FLAT and OFFSET keywords are recognized and ignored.
- The PTR keyword signifies a memory reference, as if the argument had been put in square brackets:

```
mov eax,offset foo ; address mov eax,foo ; address (ambiguous syntax in MASM)
```

• The SEGMENT ... ENDS syntax:

```
segname SEGMENT ... segname ENDS
```

• The PROC ... ENDP syntax:

```
procname PROC [FAR]
    ...
procname ENDP
```

PROC will also define RET as a macro expanding to either RETF if FAR is specified and RETN otherwise. Any keyword after PROC other than FAR is ignored.

- The TBYTE keyword as an alias for TWORD (see section 2.2.7).
- The END directive is ignored.
- In 64-bit mode relative addressing is the default (DEFAULT REL, see section 7.2.1).

In addition, NASM now natively supports, regardless of whether this package is used or not:

- ? and DUP syntax for the DB etc data declaration directives (see section 3.2.1).
- displacement[base+index] syntax for memory operations, instead of [base+index+displacement].
- seg:[addr] instead of [seg:addr] syntax.
- A pure offset can be given to LEA without square brackets:

Chapter 7: Assembler Directives

NASM, though it attempts to avoid the bureaucracy of assemblers like MASM and TASM, is nevertheless forced to support a *few* directives. These are described in this chapter.

NASM's directives come in two types: *user-level* directives and *primitive* directives. Typically, each directive has a user-level form and a primitive form. In almost all cases, we recommend that users use the user-level forms of the directives, which are implemented as macros which call the primitive forms.

Primitive directives are enclosed in square brackets; user-level directives are not.

In addition to the universal directives described in this chapter, each object file format can optionally supply extra directives in order to control particular features of that file format. These *format-specific* directives are documented along with the formats that implement them, in chapter 8.

7.1 BITS: Specifying Target Processor Mode

The BITS directive specifies whether NASM should generate code designed to run on a processor operating in 16-bit mode, 32-bit mode or 64-bit mode. The syntax is BITS XX, where XX is 16, 32 or 64.

In most cases, you should not need to use BITS explicitly. The aout, coff, elf*, macho, win32 and win64 object formats, which are designed for use in 32-bit or 64-bit operating systems, all cause NASM to select 32-bit or 64-bit mode, respectively, by default. The obj object format allows you to specify each segment you define as either USE16 or USE32, and NASM will set its operating mode accordingly, so the use of the BITS directive is once again unnecessary.

The most likely reason for using the BITS directive is to write 32-bit or 64-bit code in a flat binary file; this is because the bin output format defaults to 16-bit mode in anticipation of it being used most frequently to write DOS .COM programs, DOS .SYS device drivers and boot loader software.

The BITS directive can also be used to generate code for a different mode than the standard one for the output format.

You do *not* need to specify BITS 32 merely in order to use 32-bit instructions in a 16-bit DOS program; if you do, the assembler will generate incorrect code because it will be writing code targeted at a 32-bit platform, to be run on a 16-bit one.

When NASM is in BITS 16 mode, instructions which use 32-bit data are prefixed with an 0x66 byte, and those referring to 32-bit addresses have an 0x67 prefix. In BITS 32 mode, the reverse is true: 32-bit instructions require no prefixes, whereas instructions using 16-bit data need an 0x66 and those working on 16-bit addresses need an 0x67.

When NASM is in BITS 64 mode, most instructions operate the same as they do for BITS 32 mode. However, there are 8 more general and SSE registers, and 16-bit addressing is no longer supported.

The default address size is 64 bits; 32-bit addressing can be selected with the 0x67 prefix. The default operand size is still 32 bits, however, and the 0x66 prefix selects 16-bit operand size. The REX prefix is used both to select 64-bit operand size, and to access the new registers. NASM automatically inserts REX prefixes when necessary.

When the REX prefix is used, the processor does not know how to address the AH, BH, CH or DH (high 8-bit legacy) registers. Instead, it is possible to access the the low 8-bits of the SP, BP SI and DI registers as SPL, BPL, SIL and DIL, respectively; but only when the REX prefix is used.

The BITS directive has an exactly equivalent primitive form, [BITS 16], [BITS 32] and [BITS 64]. The user-level form is a macro which has no function other than to call the primitive form.

Note that the space is neccessary, e.g. BITS32 will *not* work!

7.1.1 USE16 & USE32: Aliases for BITS

The 'USE16' and 'USE32' directives can be used in place of 'BITS 16' and 'BITS 32', for compatibility with other assemblers.

7.2 DEFAULT: Change the assembler defaults

The DEFAULT directive changes the assembler defaults. Normally, NASM defaults to a mode where the programmer is expected to explicitly specify most features directly. However, this is occasionally obnoxious, as the explicit form is pretty much the only one one wishes to use.

Currently, DEFAULT can set REL & ABS and BND & NOBND.

7.2.1 REL & ABS: RIP-relative addressing

This sets whether registerless instructions in 64-bit mode are RIP-relative or not. By default, they are absolute unless overridden with the REL specifier (see section 3.3). However, if DEFAULT REL is specified, REL is default, unless overridden with the ABS specifier, except when used with an FS or GS segment override.

The special handling of FS and GS overrides are due to the fact that these registers are generally used as thread pointers or other special functions in 64-bit mode, and generating RIP-relative addresses would be extremely confusing.

DEFAULT REL is disabled with DEFAULT ABS.

7.2.2 BND & NOBND: BND prefix

If DEFAULT BND is set, all bnd-prefix available instructions following this directive are prefixed with bnd. To override it, NOBND prefix can be used.

```
DEFAULT BND
call foo ; BND will be prefixed
nobnd call foo ; BND will NOT be prefixed
```

DEFAULT NOBND can disable DEFAULT BND and then BND prefix will be added only when explicitly specified in code.

DEFAULT BND is expected to be the normal configuration for writing MPX-enabled code.

7.3 SECTION or SEGMENT: Changing and Defining Sections

The SECTION directive (SEGMENT is an exactly equivalent synonym) changes which section of the output file the code you write will be assembled into. In some object file formats, the number and names of sections are fixed; in others, the user may make up as many as they wish. Hence SECTION may sometimes give an error message, or may define a new section, if you try to switch to a section that does not (yet) exist.

The Unix object formats, and the bin object format (but see section 8.1.3), all support the standardized section names .text, .data and .bss for the code, data and uninitialized-data sections. The obj format, by contrast, does not recognize these section names as being special, and indeed will strip off the leading period of any section name that has one.

7.3.1 The __?SECT?__ Macro

The SECTION directive is unusual in that its user-level form functions differently from its primitive form. The primitive form, [SECTION xyz], simply switches the current target section to the one given. The user-level form, SECTION xyz, however, first defines the single-line macro __?SECT?__ to be the primitive [SECTION] directive which it is about to issue, and then issues it. So the user-level directive

```
SECTION .text
```

expands to the two lines

Users may find it useful to make use of this in their own macros. For example, the writefile macro defined in section 4.3.3 can be usefully rewritten in the following more sophisticated form:

```
%macro writefile 2+
         [section .data]
                          %2
  %%str:
                 db
  %%endstr:
        __?SECT?__
                 dx, %%str
        mov
                 cx, %% endstr-%% str
        mov
        mov
                 bx,%1
                 ah,0x40
        mov
        int
                 0x21
```

This form of the macro, once passed a string to output, first switches temporarily to the data section of the file, using the primitive form of the SECTION directive so as not to modify __?SECT?__. It then declares its string in the data section, and then invokes __?SECT?__ to switch back to *whichever* section the user was previously working in. It thus avoids the need, in the previous version of the macro, to include a JMP instruction to jump over the data, and also does not fail if, in a complicated OBJ format module, the user could potentially be assembling the code in any of several separate code sections.

7.4 ABSOLUTE: Defining Absolute Labels

The ABSOLUTE directive can be thought of as an alternative form of SECTION: it causes the subsequent code to be directed at no physical section, but at the hypothetical section starting at the given absolute address. The only instructions you can use in this mode are the RESB family.

ABSOLUTE is used as follows:

%endmacro

```
absolute 0x1A

kbuf_chr resw 1
kbuf_free resw 1
kbuf resw 16
```

This example describes a section of the PC BIOS data area, at segment address 0x40: the above code defines kbuf_chr to be 0x1A, kbuf_free to be 0x1C, and kbuf to be 0x1E.

The user-level form of ABSOLUTE, like that of SECTION, redefines the __?SECT?__ macro when it is invoked.

STRUC and ENDSTRUC are defined as macros which use ABSOLUTE (and also __?SECT?__).

ABSOLUTE doesn't have to take an absolute constant as an argument: it can take an expression (actually, a critical expression: see section 3.8) and it can be a value in a segment. For example, a TSR can re-use its setup code as run-time BSS like this:

```
org 100h ; it's a .COM program

jmp setup ; setup code comes last

; the resident part of the TSR goes here

setup:

; now write the code that installs the TSR here

absolute setup
```

```
runtimevar1 resw 1
runtimevar2 resd 20
tsr_end:
```

This defines some variables 'on top of' the setup code, so that after the setup has finished running, the space it took up can be re-used as data storage for the running TSR. The symbol 'tsr_end' can be used to calculate the total size of the part of the TSR that needs to be made resident.

7.5 EXTERN: Importing Symbols from Other Modules

EXTERN is similar to the MASM directive EXTRN and the C keyword extern: it is used to declare a symbol which is not defined anywhere in the module being assembled, but is assumed to be defined in some other module and needs to be referred to by this one. Not every object-file format can support external variables: the bin format cannot.

The EXTERN directive takes as many arguments as you like. Each argument is the name of a symbol:

```
extern _printf
extern _sscanf,_fscanf
```

Some object-file formats provide extra features to the EXTERN directive. In all cases, the extra features are used by suffixing a colon to the symbol name followed by object-format specific text. For example, the obj format allows you to declare that the default segment base of an external should be the group dgroup by means of the directive

```
extern _variable:wrt dgroup
```

The primitive form of EXTERN differs from the user-level form only in that it can take only one argument at a time: the support for multiple arguments is implemented at the preprocessor level.

You can declare the same variable as EXTERN more than once: NASM will quietly ignore the second and later redeclarations.

If a variable is declared both GLOBAL and EXTERN, or if it is declared as EXTERN and then defined, it will be treated as GLOBAL. If a variable is declared both as COMMON and EXTERN, it will be treated as COMMON.

7.6 REQUIRED: Unconditionally Importing Symbols from Other Modules

The REQUIRED keyword is similar to EXTERN one. The difference is that the EXTERN keyword as of version 2.15 does not generate unknown symbols as that prevents using common header files, as it might cause the linker to pull in a bunch of unnecessary modules.

If the old behavior is required, use REQUIRED keyword instead.

7.7 GLOBAL: Exporting Symbols to Other Modules

GLOBAL is the other end of EXTERN: if one module declares a symbol as EXTERN and refers to it, then in order to prevent linker errors, some other module must actually *define* the symbol and declare it as GLOBAL. Some assemblers use the name PUBLIC for this purpose.

GLOBAL uses the same syntax as EXTERN, except that it must refer to symbols which *are* defined in the same module as the GLOBAL directive. For example:

```
global _main
_main:
    ; some code
```

GLOBAL, like EXTERN, allows object formats to define private extensions by means of a colon. The ELF object format, for example, lets you specify whether global data items are functions or data:

```
global hashlookup:function, hashtable:data
```

Like EXTERN, the primitive form of GLOBAL differs from the user-level form only in that it can take only one argument at a time.

7.8 COMMON: Defining Common Data Areas

The COMMON directive is used to declare *common variables*. A common variable is much like a global variable declared in the uninitialized data section, so that

```
common intvar 4
is similar in function to
global intvar
section .bss
intvar resd 1
```

The difference is that if more than one module defines the same common variable, then at link time those variables will be *merged*, and references to intvar in all modules will point at the same piece of memory.

Like GLOBAL and EXTERN, COMMON supports object-format specific extensions. For example, the obj format allows common variables to be NEAR or FAR, and the ELF format allows you to specify the alignment requirements of a common variable:

```
common commvar 4:near ; works in OBJ
common intarray 100:4 ; works in ELF: 4 byte aligned
```

Once again, like EXTERN and GLOBAL, the primitive form of COMMON differs from the user-level form only in that it can take only one argument at a time.

7.9 STATIC: Local Symbols within Modules

Opposite to EXTERN and GLOBAL, STATIC is local symbol, but should be named according to the global mangling rules (named by analogy with the C keyword static as applied to functions or global variables).

Unlike GLOBAL, STATIC does not allow object formats to accept private extensions mentioned in section 7.7.

7.10 (G|L)PREFIX, (G|L)POSTFIX: Mangling Symbols

PREFIX, GPREFIX, LPREFIX, POSTFIX, GPOSTFIX, and LPOSTFIX directives can prepend or append a string to a certain type of symbols, normally to fit specific ABI conventions

- PREFIX GPREFIX: Prepend the argument to all EXTERN COMMON, STATIC, and GLOBAL symbols.
- LPREFIX: Prepend the argument to all other symbols such as local labels and backend defined symbols.
- POSTFIX|GPOSTFIX: Append the argument to all EXTERN COMMON, STATIC, and GLOBAL symbols.
- LPOSTFIX: Append the argument to all other symbols such as local labels and backend defined symbols.

These a macros implemented as pragmas, and using %pragma syntax can be restricted to specific backends (see section 4.10):

```
%pragma macho lprefix L_
```

Command line options are also available. See also section 2.1.28.

One example which supports many ABIs:

```
; The most common conventions
%pragma output gprefix _
%pragma output lprefix L_
; ELF uses a different convention
%pragma elf gprefix ; empty
%pragma elf lprefix .L
```

Some toolchains is aware of a particular prefix for its own optimization options, such as code elimination. For instance, Mach-O backend has a linker that uses a simplistic naming scheme to chunk up sections into a meta section. When the subsections_via_symbols directive (section 8.8.4) is declared, each symbol is the start of a separate block. The meta section is, then, defined to include sections before the one that starts with a 'L'. LPREFIX is useful here to mark all local symbols with the 'L' prefix to be excluded to the meta section. It converts local symbols compatible with the particular toolchain. Note that local symbols declared with STATIC (section 7.9) are excluded from the symbol mangling and also not marked as global.

7.11 CPU: Defining CPU Dependencies

The CPU directive restricts assembly to those instructions which are available on the specified CPU.

Options are:

- CPU 8086 Assemble only 8086 instruction set
- CPU 186 Assemble instructions up to the 80186 instruction set
- CPU 286 Assemble instructions up to the 286 instruction set
- CPU 386 Assemble instructions up to the 386 instruction set
- CPU 486 486 instruction set
- CPU 586 Pentium instruction set
- CPU PENTIUM Same as 586
- CPU 686 P6 instruction set
- CPU PPRO Same as 686
- CPU P2 Same as 686
- CPU P3 Pentium III (Katmai) instruction sets
- CPU KATMAI Same as P3
- CPU P4 Pentium 4 (Willamette) instruction set
- CPU WILLAMETTE Same as P4
- CPU PRESCOTT Prescott instruction set
- CPU X64 x86-64 (x64/AMD64/Intel 64) instruction set
- CPU IA64 IA64 CPU (in x86 mode) instruction set

All options are case insensitive. All instructions will be selected only if they apply to the selected CPU or lower. By default, all instructions are available.

7.12 FLOAT: Handling of floating-point constants

By default, floating-point constants are rounded to nearest, and IEEE denormals are supported. The following options can be set to alter this behaviour:

FLOAT DAZ Flush denormals to zero

- FLOAT NODAZ Do not flush denormals to zero (default)
- FLOAT NEAR Round to nearest (default)
- FLOAT UP Round up (toward +Infinity)
- FLOAT DOWN Round down (toward –Infinity)
- FLOAT ZERO Round toward zero
- FLOAT DEFAULT Restore default settings

The standard macros __?FLOAT_DAZ?__, __?FLOAT_ROUND?__, and __?FLOAT?__ contain the current state, as long as the programmer has avoided the use of the brackeded primitive form, ([FLOAT]).

__?FLOAT?__ contains the full set of floating-point settings; this value can be saved away and invoked later to restore the setting.

7.13 [WARNING]: Enable or disable warnings

The [WARNING] directive can be used to enable or disable classes of warnings in the same way as the -w option, see section 2.1.26 for more details about warning classes.

- [warning +warning-class] enables warnings for warning-class.
- [warning -warning-class] disables warnings for warning-class.
- [warning *warning-class] restores warning-class to the original value, either the default value or as specified on the command line.
- [warning push] saves the current warning state on a stack.
- [warning pop] restores the current warning state from the stack.

The [WARNING] directive also accepts the all, error and error=warning-class specifiers.

No "user form" (without the brackets) currently exists.

Chapter 8: Output Formats

NASM is a portable assembler, designed to be able to compile on any ANSI C-supporting platform and produce output to run on a variety of Intel x86 operating systems. For this reason, it has a large number of available output formats, selected using the -f option on the NASM command line. Each of these formats, along with its extensions to the base NASM syntax, is detailed in this chapter.

As stated in section 2.1.1, NASM chooses a default name for your output file based on the input file name and the chosen output format. This will be generated by removing the extension (.asm, .s, or whatever you like to use) from the input file name, and substituting an extension defined by the output format. The extensions are given with each format below.

8.1 bin: Flat-Form Binary Output

The bin format does not produce object files: it generates nothing in the output file except the code you wrote. Such 'pure binary' files are used by MS-DOS: .com executables and .sys device drivers are pure binary files. Pure binary output is also useful for operating system and boot loader development.

The bin format supports multiple section names. For details of how NASM handles sections in the bin format, see section 8.1.3.

Using the bin format puts NASM by default into 16-bit mode (see section 7.1). In order to use bin to write 32-bit or 64-bit code, such as an OS kernel, you need to explicitly issue the BITS 32 or BITS 64 directive.

bin has no default output file name extension: instead, it leaves your file name as it is once the original extension has been removed. Thus, the default is for NASM to assemble binprog.asm into a binary file called binprog.

8.1.1 ORG: Binary File Program Origin

The bin format provides an additional directive to the list given in chapter 7: ORG. The function of the ORG directive is to specify the origin address which NASM will assume the program begins at when it is loaded into memory.

For example, the following code will generate the longword 0x00000104:

org 0x100 dd label

label:

Unlike the ORG directive provided by MASM-compatible assemblers, which allows you to jump around in the object file and overwrite code you have already generated, NASM's ORG does exactly what the directive says: *origin*. Its sole function is to specify one offset which is added to all internal address references within the section; it does not permit any of the trickery that MASM's version does. See section 13.1.3 for further comments.

8.1.2 bin Extensions to the SECTION Directive, bin extensions to

The bin output format extends the SECTION (or SEGMENT) directive to allow you to specify the alignment requirements of segments. This is done by appending the ALIGN qualifier to the end of the section-definition line. For example,

section .data align=16

switches to the section .data and also specifies that it must be aligned on a 16-byte boundary.

The parameter to ALIGN specifies how many low bits of the section start address must be forced to zero. The alignment value given may be any power of two.

8.1.3 Multisection Support for the bin Format

The bin format allows the use of multiple sections, of arbitrary names, besides the "known" .text, .data, and .bss names.

- Sections may be designated progbits or nobits. Default is progbits (except .bss, which defaults to nobits, of course).
- Sections can be aligned at a specified boundary following the previous section with align=, or at an arbitrary byte-granular position with start=.
- Sections can be given a virtual start address, which will be used for the calculation of all memory references within that section with vstart=.
- Sections can be ordered using follows=<section> or vfollows=<section> as an alternative to specifying an explicit start address.
- Arguments to org, start, vstart, and align= are critical expressions. See section 3.8. E.g. align=(1 << ALIGN_SHIFT) ALIGN_SHIFT must be defined before it is used here.
- Any code which comes before an explicit SECTION directive is directed by default into the .text section.
- If an ORG statement is not given, ORG 0 is used by default.
- The .bss section will be placed after the last progbits section, unless start=, vstart=, follows=, or vfollows= has been specified.
- All sections are aligned on dword boundaries, unless a different alignment has been specified.
- Sections may not overlap.
- NASM creates the section.<secname>.start for each section, which may be used in your code.

8.1.4 Map Files

Map files can be generated in -f bin format by means of the [map] option. Map types of all (default), brief, sections, segments, or symbols may be specified. Output may be directed to stdout (default), stderr, or a specified file. E.g. [map symbols myfile.map]. No "user form" exists, the square brackets must be used.

8.2 ith: Intel Hex Output

The ith file format produces Intel hex-format files. Just as the bin format, this is a flat memory image format with no support for relocation or linking. It is usually used with ROM programmers and similar utilities.

All extensions supported by the bin file format is also supported by the ith file format.

ith provides a default output file-name extension of .ith.

8.3 srec: Motorola S-Records Output

The srec file format produces Motorola S-records files. Just as the bin format, this is a flat memory image format with no support for relocation or linking. It is usually used with ROM programmers and similar utilities.

All extensions supported by the bin file format is also supported by the srec file format.

srec provides a default output file-name extension of .srec.

8.4 obj: Microsoft OMF Object Files

The obj file format (NASM calls it obj rather than omf for historical reasons) is the one produced by MASM and TASM, which is typically fed to 16-bit DOS linkers to produce .EXE files. It is also the format used by OS/2.

obj provides a default output file-name extension of .obj.

obj is not exclusively a 16-bit format, though: NASM has full support for the 32-bit extensions to the format. In particular, 32-bit obj format files are used by Borland's Win32 compilers, instead of using Microsoft's newer win32 object file format.

The obj format does not define any special segment names: you can call your segments anything you like. Typical names for segments in obj format files are CODE, DATA and BSS.

If your source file contains code before specifying an explicit SEGMENT directive, then NASM will invent its own segment called __NASMDEFSEG for you.

When you define a segment in an obj file, NASM defines the segment name as a symbol as well, so that you can access the segment address of the segment. So, for example:

```
segment data

dvar: dw 1234

segment code

function:

mov ax,data ; get segment address of data mov ds,ax ; and move it into DS inc word [dvar] ; now this reference will work ret
```

The obj format also enables the use of the SEG and WRT operators, so that you can write code which does things like

```
extern foo

mov ax,seg foo ; get preferred segment of foo mov ds,ax
mov ax,data ; a different segment mov es,ax
mov ax,[ds:foo] ; this accesses 'foo' mov [es:foo wrt data],bx ; so does this
```

8.4.1 obj Extensions to the SEGMENT Directive

The obj output format extends the SEGMENT (or SECTION) directive to allow you to specify various properties of the segment you are defining. This is done by appending extra qualifiers to the end of the segment-definition line. For example,

```
segment code private align=16
```

defines the segment code, but also declares it to be a private segment, and requires that the portion of it described in this code module must be aligned on a 16-byte boundary.

The available qualifiers are:

- PRIVATE, PUBLIC, COMMON and STACK specify the combination characteristics of the segment. PRIVATE segments do not get combined with any others by the linker; PUBLIC and STACK segments get concatenated together at link time; and COMMON segments all get overlaid on top of each other rather than stuck end-to-end.
- ALIGN is used, as shown above, to specify how many low bits of the segment start address must be forced to zero. The alignment value given may be any power of two from 1 to 4096; in reality, the

only values supported are 1, 2, 4, 16, 256 and 4096, so if 8 is specified it will be rounded up to 16, and 32, 64 and 128 will all be rounded up to 256, and so on. Note that alignment to 4096-byte boundaries is a PharLap extension to the format and may not be supported by all linkers.

- CLASS can be used to specify the segment class; this feature indicates to the linker that segments of the same class should be placed near each other in the output file. The class name can be any word, e.g. CLASS=CODE.
- OVERLAY, like CLASS, is specified with an arbitrary word as an argument, and provides overlay information to an overlay-capable linker.
- Segments can be declared as USE16 or USE32, which has the effect of recording the choice in the object file and also ensuring that NASM's default assembly mode when assembling in that segment is 16-bit or 32-bit respectively.
- When writing OS/2 object files, you should declare 32-bit segments as FLAT, which causes the default segment base for anything in the segment to be the special group FLAT, and also defines the group if it is not already defined.
- The obj file format also allows segments to be declared as having a pre-defined absolute segment address, although no linkers are currently known to make sensible use of this feature; nevertheless, NASM allows you to declare a segment such as SEGMENT SCREEN ABSOLUTE=0xB800 if you need to. The ABSOLUTE and ALIGN keywords are mutually exclusive.

NASM's default segment attributes are PUBLIC, ALIGN=1, no class, no overlay, and USE16.

8.4.2 GROUP: Defining Groups of Segments

The obj format also allows segments to be grouped, so that a single segment register can be used to refer to all the segments in a group. NASM therefore supplies the GROUP directive, whereby you can code

segment data

; some data

segment bss

; some uninitialized data

group dgroup data bss

which will define a group called dgroup to contain the segments data and bss. Like SEGMENT, GROUP causes the group name to be defined as a symbol, so that you can refer to a variable var in the data segment as var wrt data or as var wrt dgroup, depending on which segment value is currently in your segment register.

If you just refer to var, however, and var is declared in a segment which is part of a group, then NASM will default to giving you the offset of var from the beginning of the *group*, not the *segment*. Therefore SEG var, also, will return the group base rather than the segment base.

NASM will allow a segment to be part of more than one group, but will generate a warning if you do this. Variables declared in a segment which is part of more than one group will default to being relative to the first group that was defined to contain the segment.

A group does not have to contain any segments; you can still make WRT references to a group which does not contain the variable you are referring to. OS/2, for example, defines the special group FLAT with no segments in it.

8.4.3 UPPERCASE: Disabling Case Sensitivity in Output

Although NASM itself is case sensitive, some OMF linkers are not; therefore it can be useful for NASM to output single-case object files. The UPPERCASE format-specific directive causes all segment, group and

symbol names that are written to the object file to be forced to upper case just before being written. Within a source file, NASM is still case-sensitive; but the object file can be written entirely in upper case if desired.

UPPERCASE is used alone on a line; it requires no parameters.

8.4.4 IMPORT: Importing DLL Symbols

The IMPORT format-specific directive defines a symbol to be imported from a DLL, for use if you are writing a DLL's import library in NASM. You still need to declare the symbol as EXTERN as well as using the IMPORT directive.

The IMPORT directive takes two required parameters, separated by white space, which are (respectively) the name of the symbol you wish to import and the name of the library you wish to import it from. For example:

```
import WSAStartup wsock32.dll
```

A third optional parameter gives the name by which the symbol is known in the library you are importing it from, in case this is not the same as the name you wish the symbol to be known by to your code once you have imported it. For example:

```
import asyncsel wsock32.dll WSAAsyncSelect
```

8.4.5 EXPORT: Exporting DLL Symbols

The EXPORT format-specific directive defines a global symbol to be exported as a DLL symbol, for use if you are writing a DLL in NASM. You still need to declare the symbol as GLOBAL as well as using the EXPORT directive.

EXPORT takes one required parameter, which is the name of the symbol you wish to export, as it was defined in your source file. An optional second parameter (separated by white space from the first) gives the *external* name of the symbol: the name by which you wish the symbol to be known to programs using the DLL. If this name is the same as the internal name, you may leave the second parameter off.

Further parameters can be given to define attributes of the exported symbol. These parameters, like the second, are separated by white space. If further parameters are given, the external name must also be specified, even if it is the same as the internal name. The available attributes are:

- resident indicates that the exported name is to be kept resident by the system loader. This is an optimization for frequently used symbols imported by name.
- nodata indicates that the exported symbol is a function which does not make use of any initialized data.
- parm=NNN, where NNN is an integer, sets the number of parameter words for the case in which the symbol is a call gate between 32-bit and 16-bit segments.
- An attribute which is just a number indicates that the symbol should be exported with an identifying number (ordinal), and gives the desired number.

For example:

```
export myfunc
export myfunc TheRealMoreFormalLookingFunctionName
export myfunc myfunc 1234 ; export by ordinal
export myfunc myfunc resident parm=23 nodata
```

8.4.6 ..start: Defining the Program Entry Point

OMF linkers require exactly one of the object files being linked to define the program entry point, where execution will begin when the program is run. If the object file that defines the entry point is assembled

using NASM, you specify the entry point by declaring the special symbol ..start at the point where you wish execution to begin.

8.4.7 obj Extensions to the EXTERN Directive

If you declare an external symbol with the directive

```
extern foo
```

then references such as mov ax, foo will give you the offset of foo from its preferred segment base (as specified in whichever module foo is actually defined in). So to access the contents of foo you will usually need to do something like

```
mov ax,seg foo ; get preferred segment base
mov es,ax ; move it into ES
mov ax,[es:foo] ; and use offset 'foo' from it
```

This is a little unwieldy, particularly if you know that an external is going to be accessible from a given segment or group, say dgroup. So if DS already contained dgroup, you could simply code

```
mov ax,[foo wrt dgroup]
```

However, having to type this every time you want to access foo can be a pain; so NASM allows you to declare foo in the alternative form

```
extern foo:wrt dgroup
```

This form causes NASM to pretend that the preferred segment base of foo is in fact dgroup; so the expression seg foo will now return dgroup, and the expression foo is equivalent to foo wrt dgroup.

This default-wrt mechanism can be used to make externals appear to be relative to any group or segment in your program. It can also be applied to common variables: see section 8.4.8.

8.4.8 obj Extensions to the COMMON Directive

The obj format allows common variables to be either near or far; NASM allows you to specify which your variables should be by the use of the syntax

```
common nearvar 2:near ; 'nearvar' is a near common
common farvar 10:far ; and 'farvar' is far
```

Far common variables may be greater in size than 64Kb, and so the OMF specification says that they are declared as a number of *elements* of a given size. So a 10-byte far common variable could be declared as ten one-byte elements, five two-byte elements, two five-byte elements or one ten-byte element.

Some OMF linkers require the element size, as well as the variable size, to match when resolving common variables declared in more than one module. Therefore NASM must allow you to specify the element size on your far common variables. This is done by the following syntax:

```
common c_5by2 10:far 5
common c_2by5 10:far 2
; two five-byte elements
; five two-byte elements
```

If no element size is specified, the default is 1. Also, the FAR keyword is not required when an element size is specified, since only far commons may have element sizes at all. So the above declarations could equivalently be

```
common c_5by2 10:5 ; two five-byte elements common c_2by5 10:2 ; five two-byte elements
```

In addition to these extensions, the COMMON directive in obj also supports default-WRT specification like EXTERN does (explained in section 8.4.7). So you can also declare things like

```
common foo 10:wrt dgroup
common bar 16:far 2:wrt data
common baz 24:wrt data:6
```

8.4.9 Embedded File Dependency Information

Since NASM 2.13.02, obj files contain embedded dependency file information. To suppress the generation of dependencies, use

```
%pragma obj nodepend
```

8.5 win32: Microsoft Win32 Object Files

The win32 output format generates Microsoft Win32 object files, suitable for passing to Microsoft linkers such as Visual C++. Note that Borland Win32 compilers do not use this format, but use obj instead (see section 8.4).

win32 provides a default output file-name extension of .obj.

Note that although Microsoft say that Win32 object files follow the COFF (Common Object File Format) standard, the object files produced by Microsoft Win32 compilers are not compatible with COFF linkers such as DJGPP's, and vice versa. This is due to a difference of opinion over the precise semantics of PC-relative relocations. To produce COFF files suitable for DJGPP, use NASM's coff output format; conversely, the coff format does not produce object files that Win32 linkers can generate correct output from.

8.5.1 win32 Extensions to the SECTION Directive

Like the obj format, win32 allows you to specify additional information on the SECTION directive line, to control the type and properties of sections you declare. Section types and properties are generated automatically by NASM for the standard section names .text, .data and .bss, but may still be overridden by these qualifiers.

The available qualifiers are:

- code, or equivalently text, defines the section to be a code section. This marks the section as
 readable and executable, but not writable, and also indicates to the linker that the type of the
 section is code.
- data and bss define the section to be a data section, analogously to code. Data sections are marked as readable and writable, but not executable. data declares an initialized data section, whereas bss declares an uninitialized data section.
- rdata declares an initialized data section that is readable but not writable. Microsoft compilers use this section to place constants in it.
- info defines the section to be an informational section, which is not included in the executable file
 by the linker, but may (for example) pass information to the linker. For example, declaring an
 info-type section called .drectve causes the linker to interpret the contents of the section as
 command-line options.
- align=, used with a trailing number as in obj, gives the alignment requirements of the section. The
 maximum you may specify is 64: the Win32 object file format contains no means to request a greater
 section alignment than this. If alignment is not explicitly specified, the defaults are 16-byte
 alignment for code sections, 8-byte alignment for rdata sections and 4-byte alignment for data (and
 BSS) sections. Informational sections get a default alignment of 1 byte (no alignment), though the
 value does not matter.

The defaults assumed by NASM if you do not specify the above qualifiers are:

```
section .text code align=16
section .data data align=4
section .rdata rdata align=8
section .bss bss align=4
```

The win64 format also adds:

```
section .pdata rdata align=4
section .xdata rdata align=8
```

Any other section name is treated by default like .text.

8.5.2 win32: Safe Structured Exception Handling

Among other improvements in Windows XP SP2 and Windows Server 2003 Microsoft has introduced concept of "safe structured exception handling." General idea is to collect handlers' entry points in designated read-only table and have alleged entry point verified against this table prior exception control is passed to the handler. In order for an executable module to be equipped with such "safe exception handler table," all object modules on linker command line has to comply with certain criteria. If one single module among them does not, then the table in question is omitted and above mentioned run-time checks will not be performed for application in question. Table omission is by default silent and therefore can be easily overlooked. One can instruct linker to refuse to produce binary without such table by passing /safeseh command line option.

Without regard to this run-time check merits it's natural to expect NASM to be capable of generating modules suitable for /safeseh linking. From developer's viewpoint the problem is two-fold:

- how to adapt modules not deploying exception handlers of their own;
- how to adapt/develop modules utilizing custom exception handling;

Former can be easily achieved with any NASM version by adding following line to source code:

```
$@feat.00 equ 1
```

As of version 2.03 NASM adds this absolute symbol automatically. If it's not already present to be precise. I.e. if for whatever reason developer would choose to assign another value in source file, it would still be perfectly possible.

Registering custom exception handler on the other hand requires certain "magic." As of version 2.03 additional directive is implemented, safeseh, which instructs the assembler to produce appropriately formatted input data for above mentioned "safe exception handler table." Its typical use would be:

```
section .text
extern _MessageBoxA@16
%if
        __?NASM_VERSION_ID?__ >= 0x02030000
                        ; register handler as "safe handler"
safeseh handler
%endif
handler:
        push
                DWORD 1 ; MB_OKCANCEL
        push
                DWORD caption
        push
                DWORD text
                DWORD 0
        push
        call
                MessageBoxA@16
                eax,1 ; incidentally suits as return value
        sub
                         ; for exception handler
        ret
global
        _main
_main:
                DWORD handler
        push
                DWORD [fs:0]
        push
                DWORD [fs:0],esp; engage exception handler
        mov
        xor
                eax,eax
                eax,DWORD[eax]
        mov
                                  ; cause exception
                DWORD [fs:0]
                                  ; disengage exception handler
        gog
        add
        ret
text:
                'OK to rethrow, CANCEL to generate core dump',0
caption:db
                'SEGV',0
section .drectve info
                '/defaultlib:user32.lib /defaultlib:msvcrt.lib '
        db
```

As you might imagine, it's perfectly possible to produce .exe binary with "safe exception handler table" and yet engage unregistered exception handler. Indeed, handler is engaged by simply manipulating [fs:0] location at run-time, something linker has no power over, run-time that is. It should be explicitly mentioned that such failure to register handler's entry point with safeseh directive has undesired side effect at run-time. If exception is raised and unregistered handler is to be executed, the application is abruptly terminated without any notification whatsoever. One can argue that system could at least have logged some kind "non-safe exception handler in x.exe at address n" message in event log, but no, literally no notification is provided and user is left with no clue on what caused application failure.

Finally, all mentions of linker in this paragraph refer to Microsoft linker version 7.x and later. Presence of @feat.00 symbol and input data for "safe exception handler table" causes no backward incompatibilities and "safeseh" modules generated by NASM 2.03 and later can still be linked by earlier versions or non-Microsoft linkers.

8.5.3 Debugging formats for Windows

The win32 and win64 formats support the Microsoft CodeView debugging format. Currently CodeView version 8 format is supported (cv8), but newer versions of the CodeView debugger should be able to handle this format as well.

8.6 win64: Microsoft Win64 Object Files

The win64 output format generates Microsoft Win64 object files, which is nearly 100% identical to the win32 object format (section 8.5) with the exception that it is meant to target 64-bit code and the x86-64 platform altogether. This object file is used exactly the same as the win32 object format (section 8.5), in NASM, with regard to this exception.

8.6.1 win64: Writing Position-Independent Code

While REL takes good care of RIP-relative addressing, there is one aspect that is easy to overlook for a Win64 programmer: indirect references. Consider a switch dispatch table:

```
jmp qword [dsptch+rax*8]
...
dsptch: dq case0
dq case1
```

Even a novice Win64 assembler programmer will soon realize that the code is not 64-bit savvy. Most notably linker will refuse to link it with

```
'ADDR32' relocation to '.text' invalid without /LARGEADDRESSAWARE:NO
```

So [s]he will have to split jmp instruction as following:

```
lea    rbx,[rel dsptch]
jmp    qword [rbx+rax*8]
```

What happens behind the scene is that effective address in lea is encoded relative to instruction pointer, or in perfectly position-independent manner. But this is only part of the problem! Trouble is that in .dll context caseN relocations will make their way to the final module and might have to be adjusted at .dll load time. To be specific when it can't be loaded at preferred address. And when this occurs, pages with such relocations will be rendered private to current process, which kind of undermines the idea of sharing .dll. But no worry, it's trivial to fix:

```
lea rbx,[rel dsptch]
add rbx,[rbx+rax*8]
jmp rbx
...
dsptch: dq case0-dsptch
dq case1-dsptch
...
```

NASM version 2.03 and later provides another alternative, wrt ..imagebase operator, which returns offset from base address of the current image, be it .exe or .dll module, therefore the name. For those acquainted with PE-COFF format base address denotes start of IMAGE_DOS_HEADER structure. Here is how to implement switch with these image-relative references:

One can argue that the operator is redundant. Indeed, snippet before last works just fine with any NASM version and is not even Windows specific... The real reason for implementing wrt ..imagebase will become apparent in next paragraph.

It should be noted that wrt ...imagebase is defined as 32-bit operand only:

```
dd label wrt ..imagebase
dq label wrt ..imagebase
mov eax,label wrt ..imagebase
mov rax,label wrt ..imagebase
; ok
; bad
```

8.6.2 win64: Structured Exception Handling

Structured exception handing in Win64 is completely different matter from Win32. Upon exception program counter value is noted, and linker-generated table comprising start and end addresses of all the functions [in given executable module] is traversed and compared to the saved program counter. Thus so called UNWIND_INFO structure is identified. If it's not found, then offending subroutine is assumed to be "leaf" and just mentioned lookup procedure is attempted for its caller. In Win64 leaf function is such function that does not call any other function *nor* modifies any Win64 non-volatile registers, including stack pointer. The latter ensures that it's possible to identify leaf function's caller by simply pulling the value from the top of the stack.

While majority of subroutines written in assembler are not calling any other function, requirement for non-volatile registers' immutability leaves developer with not more than 7 registers and no stack frame, which is not necessarily what [s]he counted with. Customarily one would meet the requirement by saving non-volatile registers on stack and restoring them upon return, so what can go wrong? If [and only if] an exception is raised at run-time and no UNWIND_INFO structure is associated with such "leaf" function, the stack unwind procedure will expect to find caller's return address on the top of stack immediately followed by its frame. Given that developer pushed caller's non-volatile registers on stack, would the value on top point at some code segment or even addressable space? Well, developer can attempt copying caller's return address to the top of stack and this would actually work in some very specific circumstances. But unless developer can guarantee that these circumstances are always met, it's more appropriate to assume worst case scenario, i.e. stack unwind procedure going berserk. Relevant question is what happens then? Application is abruptly terminated without any notification whatsoever. Just like in Win32 case, one can argue that system could at least have logged "unwind procedure went berserk in x.exe at address n" in event log, but no, no trace of failure is left.

Now, when we understand significance of the UNWIND_INFO structure, let's discuss what's in it and/or how it's processed. First of all it is checked for presence of reference to custom language-specific exception handler. If there is one, then it's invoked. Depending on the return value, execution flow is resumed (exception is said to be "handled"), or rest of UNWIND_INFO structure is processed as following. Beside optional reference to custom handler, it carries information about current callee's stack frame and where non-volatile registers are saved. Information is detailed enough to be able to reconstruct contents of caller's non-volatile registers upon call to current callee. And so caller's context is reconstructed, and then unwind procedure is repeated, i.e. another UNWIND_INFO structure is associated, this time, with caller's instruction pointer, which is then checked for presence of reference

to language-specific handler, etc. The procedure is recursively repeated till exception is handled. As last resort system "handles" it by generating memory core dump and terminating the application.

As for the moment of this writing NASM unfortunately does not facilitate generation of above mentioned detailed information about stack frame layout. But as of version 2.03 it implements building blocks for generating structures involved in stack unwinding. As simplest example, here is how to deploy custom exception handler for leaf function:

```
default rel
section .text
extern MessageBoxA
handler:
        sub
                rsp,40
        mov
                rcx,0
        lea
                rdx,[text]
                r8, [caption]
        lea
        mov
                r9,1
                        ; MB_OKCANCEL
        call
                MessageBoxA
                        ; incidentally suits as return value
                eax,1
                          for exception handler
        add
                rsp,40
        ret
global
        main
main:
                rax.rax
                rax,QWORD[rax] ; cause exception
        mov
        ret
main_end:
text:
        db
                'OK to rethrow, CANCEL to generate core dump',0
caption:db
                'SEGV',0
section .pdata rdata align=4
        dd
                main wrt ..imagebase
        dd
                main_end wrt ..imagebase
        dd
                xmain wrt ..imagebase
section .xdata
                rdata align=8
xmain: db
                9,0,0,0
        dd
                handler wrt ..imagebase
section .drectve info
                '/defaultlib:user32.lib /defaultlib:msvcrt.lib '
```

What you see in .pdata section is element of the "table comprising start and end addresses of function" along with reference to associated UNWIND_INFO structure. And what you see in .xdata section is UNWIND_INFO structure describing function with no frame, but with designated exception handler. References are required to be image-relative (which is the real reason for implementing wrt ..imagebase operator). It should be noted that rdata align=n, as well as wrt ..imagebase, are optional in these two segments' contexts, i.e. can be omitted. Latter means that all 32-bit references, not only above listed required ones, placed into these two segments turn out image-relative. Why is it important to understand? Developer is allowed to append handler-specific data to UNWIND_INFO structure, and if [s]he adds a 32-bit reference, then [s]he will have to remember to adjust its value to obtain the real pointer.

As already mentioned, in Win64 terms leaf function is one that does not call any other function *nor* modifies any non-volatile register, including stack pointer. But it's not uncommon that assembler programmer plans to utilize every single register and sometimes even have variable stack frame. Is there anything one can do with bare building blocks? I.e. besides manually composing fully-fledged UNWIND_INFO structure, which would surely be considered error-prone? Yes, there is. Recall that exception handler is called first, before stack layout is analyzed. As it turned out, it's perfectly possible to manipulate current callee's context in custom handler in manner that permits further stack unwinding. General idea is that handler would not actually "handle" the exception, but instead restore callee's context, as it was at its entry point and thus mimic leaf function. In other words, handler would simply undertake part of unwinding procedure. Consider following example:

```
function:
        mov.
                rax,rsp
                                ; copy rsp to volatile register
                r15
                                ; save non-volatile registers
        push
        push
                rbx
        push
                rbp
        mov
                r11,rsp
                                ; prepare variable stack frame
        sub
                r11,rcx
        and
                r11,-64
                QWORD[r11], rax ; check for exceptions
        mov
        mov
                rsp,r11
                                ; allocate stack frame
                QWORD[rsp],rax ; save original rsp value
        mov
magic_point:
                r11,QWORD[rsp] ; pull original rsp value
        mov
                rbp,QWORD[r11-24]
        mov
                rbx,QWORD[r11-16]
        mov
        mov
                r15,QWORD[r11-8]
        mov
                rsp,r11
                                ; destroy frame
        ret
```

The keyword is that up to magic_point original rsp value remains in chosen volatile register and no non-volatile register, except for rsp, is modified. While past magic_point rsp remains constant till the very end of the function. In this case custom language-specific exception handler would look like this:

```
EXCEPTION_DISPOSITION handler (EXCEPTION_RECORD *rec,ULONG64 frame,
        CONTEXT *context,DISPATCHER_CONTEXT *disp)
    ULONG64 *rsp;
    if (context->Rip<(ULONG64)magic point)</pre>
        rsp = (ULONG64 *)context->Rax;
    else
       rsp = ((ULONG64 **)context->Rsp)[0];
        context->Rbp = rsp[-3];
        context->Rbx = rsp[-2];
        context->R15 = rsp[-1];
    context->Rsp = (ULONG64)rsp;
    memcpy (disp->ContextRecord,context,sizeof(CONTEXT));
    RtlVirtualUnwind(UNW_FLAG_NHANDLER, disp->ImageBase,
        dips->ControlPc, disp->FunctionEntry, disp->ContextRecord,
        &disp->HandlerData,&disp->EstablisherFrame,NULL);
    return ExceptionContinueSearch;
}
```

As custom handler mimics leaf function, corresponding UNWIND_INFO structure does not have to contain any information about stack frame and its layout.

8.7 coff: Common Object File Format

The coff output type produces COFF object files suitable for linking with the DJGPP linker.

coff provides a default output file-name extension of .o.

The coff format supports the same extensions to the SECTION directive as win32 does, except that the align qualifier and the info section type are not supported.

8.8 macho32 and macho64: Mach Object File Format

The macho32 and macho64 output formts produces Mach-O object files suitable for linking with the MacOS X linker. macho is a synonym for macho32.

macho provides a default output file-name extension of .o.

8.8.1 macho extensions to the SECTION Directive

The macho output format specifies section names in the format "segment, section". No spaces are allowed around the comma. The following flags can also be specified:

- data this section contains initialized data items
- code this section contains code exclusively
- mixed this section contains both code and data
- bss this section is uninitialized and filled with zero
- zerofill same as bss
- no_dead_strip inhibit dead code stripping for this section
- live_support set the live support flag for this section
- strip_static_syms strip static symbols for this section
- debug this section contains debugging information
- align=alignment specify section alignment

The default is data, unless the section name is __text or __bss in which case the default is text or bss, respectively.

For compatibility with other Unix platforms, the following standard names are also supported:

```
.text = __TEXT,__text text
.rodata = __DATA,__const data
.data = __DATA,__data data
.bss = __DATA,__bss bss
```

If the .rodata section contains no relocations, it is instead put into the __TEXT,__const section unless this section has already been specified explicitly. However, it is probably better to specify __TEXT,__const and __DATA,__const explicitly as appropriate.

8.8.2 Thread Local Storage in Mach-O: macho special symbols and WRT

Mach-O defines the following special symbols that can be used on the right-hand side of the WRT operator:

- ..tlvp is used to specify access to thread-local storage.
- ..gotpcrel is used to specify references to the Global Offset Table. The GOT is supported in the macho64 format only.

8.8.3 macho specfic directive subsections_via_symbols

The directive subsections_via_symbols sets the MH_SUBSECTIONS_VIA_SYMBOLS flag in the Mach-O header, that effectively separates a block (or a subsection) based on a symbol. It is often used for eliminating dead codes by a linker.

This directive takes no arguments.

This is a macro implemented as a %pragma. It can also be specified in its %pragma form, in which case it will not affect non-Mach-O builds of the same source code:

```
%pragma macho subsections_via_symbols
```

8.8.4 macho specfic directive no_dead_strip

The directive no_dead_strip sets the Mach-O SH_NO_DEAD_STRIP section flag on the section containing a a specific symbol. This directive takes a list of symbols as its arguments.

This is a macro implemented as a %pragma. It can also be specified in its %pragma form, in which case it will not affect non-Mach-O builds of the same source code:

%pragma macho no_dead_strip symbol...

8.8.5 macho specific extensions to the GLOBAL Directive: private_extern

The directive extension to GLOBAL marks the symbol with limited global scope. For example, you can specify the global symbol with this extension:

```
global foo:private_extern
foo:
    ; codes
```

Using with static linker will clear the private extern attribute. But linker option like -keep_private_externs can avoid it.

8.9 elf32, elf64, elfx32: Executable and Linkable Format Object Files

The elf32, elf64 and elfx32 output formats generate ELF32 and ELF64 (Executable and Linkable Format) object files, as used by Linux as well as Unix System V, including Solaris x86, UnixWare and SCO Unix. ELF provides a default output file-name extension of .o. elf is a synonym for elf32.

The elfx32 format is used for the x32 ABI, which is a 32-bit ABI with the CPU in 64-bit mode.

8.9.1 ELF specific directive osabi

The ELF header specifies the application binary interface for the target operating system (OSABI). This field can be set by using the osabi directive with the numeric value (0-255) of the target system. If this directive is not used, the default value will be "UNIX System V ABI" (0) which will work on most systems which support ELF.

8.9.2 ELF extensions to the SECTION Directive

Like the obj format, elf allows you to specify additional information on the SECTION directive line, to control the type and properties of sections you declare. Section types and properties are generated automatically by NASM for the standard section names, but may still be overridden by these qualifiers.

The available qualifiers are:

- alloc defines the section to be one which is loaded into memory when the program is run. noalloc defines it to be one which is not, such as an informational or comment section.
- exec defines the section to be one which should have execute permission when the program is run.
- write defines the section to be one which should be writable when the program is run. nowrite defines it as one which should not.
- progbits defines the section to be one with explicit contents stored in the object file: an ordinary code or data section, for example.
- nobits defines the section to be one with no explicit contents given, such as a BSS section.
- note indicates that this section contains ELF notes. The content of ELF notes are specified using normal assembly instructions; it is up to the programmer to ensure these are valid ELF notes.
- preinit_array indicates that this section contains function addresses to be called before any other initialization has happened.
- init_array indicates that this section contains function addresses to be called during initialization.
- fini_array indicates that this section contains function pointers to be called during termination.
- align=, used with a trailing number as in obj, gives the alignment requirements of the section.

- byte, word, dword, qword, tword, oword, yword, or zword with an optional *multiplier specify the fundamental data item size for a section which contains either fixed-sized data structures or strings; it also sets a default alignment. This is generally used with the strings and merge attributes (see below.) For example byte*4 defines a unit size of 4 bytes, with a default alignment of 1; dword also defines a unit size of 4 bytes, but with a default alignment of 4. The align= attribute, if specified, overrides this default alignment.
- pointer is equivalent to dword for elf32 or elfx32, and qword for elf64.
- strings indicate that this section contains exclusively null-terminated strings. By default these are assumed to be byte strings, but a size specifier can be used to override that.
- merge indicates that duplicate data elements in this section should be merged with data elements from other object files. Data elements can be either fixed-sized objects or null-terminatedstrings (with the strings attribute.) A size specifier is required unless strings is specified, in which case the size defaults to byte.
- tls defines the section to be one which contains thread local variables.

The defaults assumed by NASM if you do not specify the above qualifiers are:

```
progbits
                                   alloc
                                                   nowrite align=16
section .text
                                           exec
section .rodata
                      progbits
                                   alloc
                                           noexec nowrite
                                                           align=4
section .lrodata
                      progbits
                                   alloc
                                           noexec
                                                   nowrite
                                                           align=4
                                           noexec write
                                                           align=4
section .data
                      progbits
                                   alloc
                                                           align=4
section .ldata
                      progbits
                                   alloc
                                           noexec write
section .bss
                      nobits
                                   alloc
                                           noexec write
                                                            align=4
                                                           align=4
section .lbss
                      nobits
                                   alloc
                                           noexec write
                                                           align=4
section .tdata
                      progbits
                                   alloc
                                           noexec
                                                   write
                                                                     tls
                                                           align=4
section .tbss
                      nobits
                                   alloc
                                           noexec
                                                  write
                                                                     tls
                                                           align=1
section .comment
                      progbits
                                   noalloc noexec nowrite
section .preinit_array preinit_array alloc noexec
                                                   nowrite
                                                           pointer
section .init_array
                      init_array
                                   alloc
                                           noexec
                                                   nowrite
                                                           pointer
section .fini_array
                      fini_array
                                   alloc
                                           noexec
                                                   nowrite
                                                           pointer
section .note
                      note
                                   noalloc noexec
                                                   nowrite
                                                           align=4
                                   alloc noexec nowrite align=1
                      progbits
section other
```

(Any section name other than those in the above table is treated by default like other in the above table. Please note that section names are case sensitive.)

8.9.3 Position-Independent Code: ELF Special Symbols and WRT

Since ELF does not support segment-base references, the WRT operator is not used for its normal purpose; therefore NASM's elf output format makes use of WRT for a different purpose, namely the PIC-specific relocation types.

elf defines five special symbols which you can use as the right-hand side of the WRT operator to obtain PIC relocation types. They are ..gotpc, ..gotoff, ..got, ..plt and ..sym. Their functions are summarized here:

- Referring to the symbol marking the global offset table base using wrt ..gotpc will end up giving
 the distance from the beginning of the current section to the global offset table.
 (_GLOBAL_OFFSET_TABLE_ is the standard symbol name used to refer to the GOT.) So you would then
 need to add \$\$ to the result to get the real address of the GOT.
- Referring to a location in one of your own sections using wrt ..gotoff will give the distance from
 the beginning of the GOT to the specified location, so that adding on the address of the GOT would
 give the real address of the location you wanted.
- Referring to an external or global symbol using wrt ..got causes the linker to build an entry in the GOT containing the address of the symbol, and the reference gives the distance from the beginning

of the GOT to the entry; so you can add on the address of the GOT, load from the resulting address, and end up with the address of the symbol.

- Referring to a procedure name using wrt ..plt causes the linker to build a procedure linkage table entry for the symbol, and the reference gives the address of the PLT entry. You can only use this in contexts which would generate a PC-relative relocation normally (i.e. as the destination for CALL or JMP), since ELF contains no relocation type to refer to PLT entries absolutely.
- Referring to a symbol name using wrt ..sym causes NASM to write an ordinary relocation, but instead of making the relocation relative to the start of the section and then adding on the offset to the symbol, it will write a relocation record aimed directly at the symbol in question. The distinction is a necessary one due to a peculiarity of the dynamic linker.

A fuller explanation of how to use these relocation types to write shared libraries entirely in NASM is given in section 10.2.

8.9.4 Thread Local Storage in ELF: elf Special Symbols and WRT

• In ELF32 mode, referring to an external or global symbol using wrt ..tlsie causes the linker to build an entry *in* the GOT containing the offset of the symbol within the TLS block, so you can access the value of the symbol with code such as:

```
mov eax,[tid wrt ..tlsie]
mov [gs:eax],ebx
```

• In ELF64 or ELFx32 mode, referring to an external or global symbol using wrt ..gottpoff causes the linker to build an entry *in* the GOT containing the offset of the symbol within the TLS block, so you can access the value of the symbol with code such as:

```
mov rax,[rel tid wrt ..gottpoff]
mov rcx,[fs:rax]
```

8.9.5 elf Extensions to the GLOBAL Directive

ELF object files can contain more information about a global symbol than just its address: they can contain the size of the symbol and its type as well. These are not merely debugger conveniences, but are actually necessary when the program being written is a shared library. NASM therefore supports some extensions to the GLOBAL directive, allowing you to specify these features.

You can specify whether a global variable is a function or a data object by suffixing the name with a colon and the word function or data. (object is a synonym for data.) For example:

```
global hashlookup:function, hashtable:data
```

exports the global symbol hashlookup as a function and hashtable as a data object.

Optionally, you can control the ELF visibility of the symbol. Just add one of the visibility keywords: default, internal, hidden, or protected. The default is default of course. For example, to make hashlookup hidden:

```
global hashlookup:function hidden
```

Since version 2.15, it is possible to specify symbols binding. The keywords are: weak to generate weak symbol or strong. The default is strong.

You can also specify the size of the data associated with the symbol, as a numeric expression (which may involve labels, and even forward references) after the type specifier. Like this:

This makes NASM automatically calculate the length of the table and place that information into the ELF symbol table.

Declaring the type and size of global symbols is necessary when writing shared library code. For more information, see section 10.2.4.

8.9.6 elf Extensions to the EXTERN Directive

Since version 2.15 it is possible to specify keyword weak to generate weak external reference. Example: extern weak_ref:weak

8.9.7 elf Extensions to the COMMON Directive

ELF also allows you to specify alignment requirements on common variables. This is done by putting a number (which must be a power of two) after the name and size of the common variable, separated (as usual) by a colon. For example, an array of doublewords would benefit from 4-byte alignment:

common dwordarray 128:4

This declares the total size of the array to be 128 bytes, and requires that it be aligned on a 4-byte boundary.

8.9.8 16-bit code and ELF

Older versions of the ELF32 specification did not provide relocations for 8- and 16-bit values. It is now part of the formal specification, and any new enough linker should support them.

ELF has currently no support for segmented programming.

8.9.9 Debug formats and ELF

ELF provides debug information in STABS and DWARF formats. Line number information is generated for all executable sections, but please note that only the ".text" section is executable by default.

8.10 aout: Linux a.out Object Files

The aout format generates a.out object files, in the form used by early Linux systems (current Linux systems use ELF, see section 8.9.) These differ from other a.out object files in that the magic number in the first four bytes of the file is different; also, some implementations of a.out, for example NetBSD's, support position-independent code, which Linux's implementation does not.

a.out provides a default output file-name extension of .o.

a.out is a very simple object format. It supports no special directives, no special symbols, no use of SEG or WRT, and no extensions to any standard directives. It supports only the three standard section names .text, .data and .bss.

8.11 aoutb: NetBSD/FreeBSD/OpenBSD a.out Object Files

The aoutb format generates a.out object files, in the form used by the various free BSD Unix clones, NetBSD, FreeBSD and OpenBSD. For simple object files, this object format is exactly the same as aout except for the magic number in the first four bytes of the file. However, the aoutb format supports position-independent code in the same way as the elf format, so you can use it to write BSD shared libraries.

aoutb provides a default output file-name extension of .o.

aouth supports no special directives, no special symbols, and only the three standard section names .text, .data and .bss. However, it also supports the same use of WRT as elf does, to provide position-independent code relocation types. See section 8.9.3 for full documentation of this feature.

aouth also supports the same extensions to the GLOBAL directive as elf does: see section 8.9.5 for documentation of this.

8.12 as86: Minix/Linux as86 Object Files

The Minix/Linux 16-bit assembler as86 has its own non-standard object file format. Although its companion linker ld86 produces something close to ordinary a.out binaries as output, the object file format used to communicate between as86 and ld86 is not itself a.out.

NASM supports this format, just in case it is useful, as as86. as86 provides a default output file-name extension of .o.

as86 is a very simple object format (from the NASM user's point of view). It supports no special directives, no use of SEG or WRT, and no extensions to any standard directives. It supports only the three standard section names .text, .data and .bss. The only special symbol supported is ..start.

8.13 rdf: Relocatable Dynamic Object File Format (deprecated)

The RDOFF format is strongly deprecated and has been disabled starting in NASM 2.15.04. The RDOFF backend has been broken since at least NASM 2.14. The RDOFF utilities are scheduled to be removed from the NASM distribution in NASM 2.16. If you have a strong use case for the RDOFF format, file a bug report at https://bugs.nasm.us/ as soon as possible.

The rdf output format produces RDOFF object files. RDOFF (Relocatable Dynamic Object File Format) is a home-grown object-file format, designed alongside NASM itself and reflecting in its file format the internal structure of the assembler.

RDOFF is not used by any well-known operating systems. Those writing their own systems, however, may well wish to use RDOFF as their object format, on the grounds that it is designed primarily for simplicity and contains very little file-header bureaucracy.

The Unix NASM archive, and the DOS archive which includes sources, both contain an rdoff subdirectory holding a set of RDOFF utilities: an RDF linker, an RDF static-library manager, an RDF file dump utility, and a program which will load and execute an RDF executable under Linux.

8.13.1 Requiring a Library: The LIBRARY Directive

RDOFF contains a mechanism for an object file to demand a given library to be linked to the module, either at load time or run time. This is done by the LIBRARY directive, which takes one argument which is the name of the module:

library mylib.rdl

8.13.2 Specifying a Module Name: The MODULE Directive

Special RDOFF header record is used to store the name of the module. It can be used, for example, by run-time loader to perform dynamic linking. MODULE directive takes one argument which is the name of current module:

module mymodname

Note that when you statically link modules and tell linker to strip the symbols from output file, all module names will be stripped too. To avoid it, you should start module names with \$, like:

module \$kernel.core

8.13.3 rdf Extensions to the GLOBAL Directive

RDOFF global symbols can contain additional information needed by the static linker. You can mark a global symbol as exported, thus telling the linker do not strip it from target executable or library file. Like in ELF, you can also specify whether an exported symbol is a procedure (function) or data object.

Suffixing the name with a colon and the word export you make the symbol exported:

```
global sys_open:export
```

To specify that exported symbol is a procedure (function), you add the word proc or function after declaration:

```
global sys_open:export proc
```

Similarly, to specify exported data object, add the word data or object to the directive:

```
global kernel_ticks:export data
```

8.13.4 rdf Extensions to the EXTERN Directive

By default the EXTERN directive in RDOFF declares a "pure external" symbol (i.e. the static linker will complain if such a symbol is not resolved). To declare an "imported" symbol, which must be resolved later during a dynamic linking phase, RDOFF offers an additional import modifier. As in GLOBAL, you can also specify whether an imported symbol is a procedure (function) or data object. For example:

```
library $libc
extern _open:import
extern _printf:import proc
extern _errno:import data
```

Here the directive LIBRARY is also included, which gives the dynamic linker a hint as to where to find requested symbols.

8.14 dbg: Debugging Format

The dbg format does not output an object file as such; instead, it outputs a text file which contains a complete list of all the transactions between the main body of NASM and the output-format back end module. It is primarily intended to aid people who want to write their own output drivers, so that they can get a clearer idea of the various requests the main program makes of the output driver, and in what order they happen.

For simple files, one can easily use the dbg format like this:

```
nasm -f dbg filename.asm
```

which will generate a diagnostic file called filename.dbg. However, this will not work well on files which were designed for a different object format, because each object format defines its own macros (usually user-level forms of directives), and those macros will not be defined in the dbg format. Therefore it can be useful to run NASM twice, in order to do the preprocessing with the native object format selected:

```
nasm -e -f rdf -o rdfprog.i rdfprog.asm
nasm -a -f dbg rdfprog.i
```

This preprocesses rdfprog.asminto rdfprog.i, keeping the rdf object format selected in order to make sure RDF special directives are converted into primitive form correctly. Then the preprocessed source is fed through the dbg format to generate the final diagnostic output.

This workaround will still typically not work for programs intended for obj format, because the obj SEGMENT and GROUP directives have side effects of defining the segment and group names as symbols; dbg will not do this, so the program will not assemble. You will have to work around that by defining the symbols yourself (using EXTERN, for example) if you really need to get a dbg trace of an obj-specific source file.

dbg accepts any section name and any directives at all, and logs them all to its output file.

dbg accepts and logs any %pragma, but the specific %pragma:

```
%pragma dbg maxdump <size>
```

where <size> is either a number or unlimited, can be used to control the maximum size for dumping the full contents of a rawdata output object.

Chapter 9: Writing 16-bit Code (DOS, Windows 3/3.1)

This chapter attempts to cover some of the common issues encountered when writing 16-bit code to run under MS-DOS or Windows 3.x. It covers how to link programs to produce .EXE or .COM files, how to write .SYS device drivers, and how to interface assembly language code with 16-bit C compilers and with Borland Pascal.

9.1 Producing .EXE Files

Any large program written under DOS needs to be built as a .EXE file: only .EXE files have the necessary internal structure required to span more than one 64K segment. Windows programs, also, have to be built as .EXE files, since Windows does not support the .COM format.

In general, you generate .EXE files by using the obj output format to produce one or more .obj files, and then linking them together using a linker. However, NASM also supports the direct generation of simple DOS .EXE files using the bin output format (by using DB and DW to construct the .EXE file header), and a macro package is supplied to do this. Thanks to Yann Guidon for contributing the code for this.

NASM may also support .EXE natively as another output format in future releases.

9.1.1 Using the obj Format To Generate .EXE Files

This section describes the usual method of generating .EXE files by linking .OBJ files together.

Most 16-bit programming language packages come with a suitable linker; if you have none of these, there is a free linker called VAL, available in LZH archive format from x2ftp.oulu.fi. An LZH archiver can be found at ftp.simtel.net. There is another 'free' linker (though this one doesn't come with sources) called FREELINK, available from www.pcorner.com. A third, djlink, written by DJ Delorie, is available at www.delorie.com. A fourth linker, ALINK, written by Anthony A.J. Williams, is available at alink.sourceforge.net.

When linking several .OBJ files into a .EXE file, you should ensure that exactly one of them has a start point defined (using the ..start special symbol defined by the obj format: see section 8.4.6). If no module defines a start point, the linker will not know what value to give the entry-point field in the output file header; if more than one defines a start point, the linker will not know which value to use.

An example of a NASM source file which can be assembled to a .OBJ file and linked on its own to a .EXE is given here. It demonstrates the basic principles of defining a stack, initialising the segment registers, and declaring a start point. This file is also provided in the test subdirectory of the NASM archives, under the name object.asm.

```
segment code
..start:

mov ax,data
mov ds,ax
mov ax,stack
mov ss,ax
mov sp.stacktor
```

This initial piece of code sets up DS to point to the data segment, and initializes SS and SP to point to the top of the provided stack. Notice that interrupts are implicitly disabled for one instruction after a move into SS, precisely for this situation, so that there's no chance of an interrupt occurring between the loads of SS and SP and not having a stack to execute on.

Note also that the special symbol ..start is defined at the beginning of this code, which means that will be the entry point into the resulting executable file.

```
mov dx,hello
mov ah,9
int 0x21
```

The above is the main program: load DS:DX with a pointer to the greeting message (hello is implicitly relative to the segment data, which was loaded into DS in the setup code, so the full pointer is valid), and call the DOS print-string function.

```
mov ax,0x4c00
int 0x21
```

This terminates the program using another DOS system call.

```
segment data

hello: db 'hello, world', 13, 10, '$'

The data segment contains the string we want to display.

segment stack stack

resb 64

stacktop:
```

The above code declares a stack segment containing 64 bytes of uninitialized stack space, and points stacktop at the top of it. The directive segment stack stack defines a segment *called* stack, and also of *type* STACK. The latter is not necessary to the correct running of the program, but linkers are likely to issue warnings or errors if your program has no segment of type STACK.

The above file, when assembled into a .OBJ file, will link on its own to a valid .EXE file, which when run will print 'hello, world' and then exit.

9.1.2 Using the bin Format To Generate . EXE Files

The .EXE file format is simple enough that it's possible to build a .EXE file by writing a pure-binary program and sticking a 32-byte header on the front. This header is simple enough that it can be generated using DB and DW commands by NASM itself, so that you can use the bin output format to directly generate .EXE files.

Included in the NASM archives, in the misc subdirectory, is a file exebin.mac of macros. It defines three macros: EXE_begin, EXE_stack and EXE_end.

To produce a .EXE file using this method, you should start by using %include to load the exebin.mac macro package into your source file. You should then issue the EXE_begin macro call (which takes no arguments) to generate the file header data. Then write code as normal for the bin format – you can use all three standard sections .text, .data and .bss. At the end of the file you should call the EXE_end macro (again, no arguments), which defines some symbols to mark section sizes, and these symbols are referred to in the header code generated by EXE_begin.

In this model, the code you end up writing starts at 0×100 , just like a .COM file – in fact, if you strip off the 32-byte header from the resulting .EXE file, you will have a valid .COM program. All the segment bases are the same, so you are limited to a 64K program, again just like a .COM file. Note that an ORG directive is issued by the EXE_begin macro, so you should not explicitly issue one of your own.

You can't directly refer to your segment base value, unfortunately, since this would require a relocation in the header, and things would get a lot more complicated. So you should get your segment base by copying it out of cs instead.

On entry to your .EXE file, SS:SP are already set up to point to the top of a 2Kb stack. You can adjust the default stack size of 2Kb by calling the EXE_stack macro. For example, to change the stack size of your program to 64 bytes, you would call EXE_stack 64.

A sample program which generates a .EXE file in this way is given in the test subdirectory of the NASM archive, as binexe.asm.

9.2 Producing . com Files

While large DOS programs must be written as .EXE files, small ones are often better written as .COM files. .COM files are pure binary, and therefore most easily produced using the bin output format.

9.2.1 Using the bin Format To Generate . COM Files

.COM files expect to be loaded at offset 100h into their segment (though the segment may change). Execution then begins at 100h, i.e. right at the start of the program. So to write a .COM program, you would create a source file looking like

```
org 100h
section .text
start:
; put your code here
section .data
; put data items here
section .bss
; put uninitialized data here
```

The bin format puts the .text section first in the file, so you can declare data or BSS items before beginning to write code if you want to and the code will still end up at the front of the file where it belongs.

The BSS (uninitialized data) section does not take up space in the .com file itself: instead, addresses of BSS items are resolved to point at space beyond the end of the file, on the grounds that this will be free memory when the program is run. Therefore you should not rely on your BSS being initialized to all zeros when you run.

To assemble the above program, you should use a command line like

```
nasm myprog.asm -fbin -o myprog.com
```

The bin format would produce a file called myprog if no explicit output file name were specified, so you have to override it and give the desired file name.

9.2.2 Using the obj Format To Generate . COM Files

If you are writing a .COM program as more than one module, you may wish to assemble several .OBJ files and link them together into a .COM program. You can do this, provided you have a linker capable of outputting .COM files directly (TLINK does this), or alternatively a converter program such as EXE2BIN to transform the .EXE file output from the linker into a .COM file.

If you do this, you need to take care of several things:

- The first object file containing code should start its code segment with a line like RESB 100h. This is to ensure that the code begins at offset 100h relative to the beginning of the code segment, so that the linker or converter program does not have to adjust address references within the file when generating the .COM file. Other assemblers use an ORG directive for this purpose, but ORG in NASM is a format-specific directive to the bin output format, and does not mean the same thing as it does in MASM-compatible assemblers.
- You don't need to define a stack segment.
- All your segments should be in the same group, so that every time your code or data references a symbol offset, all offsets are relative to the same segment base. This is because, when a .COM file is loaded, all the segment registers contain the same value.

9.3 Producing .sys Files

MS-DOS device drivers – .sys files – are pure binary files, similar to .com files, except that they start at origin zero rather than 100h. Therefore, if you are writing a device driver using the bin format, you do not need the ORG directive, since the default origin for bin is zero. Similarly, if you are using obj, you do not need the RESB 100h at the start of your code segment.

.sys files start with a header structure, containing pointers to the various routines inside the driver which do the work. This structure should be defined at the start of the code segment, even though it is not actually code.

For more information on the format of .sys files, and the data which has to go in the header structure, a list of books is given in the Frequently Asked Questions list for the newsgroup comp.os.msdos.programmer.

9.4 Interfacing to 16-bit C Programs

This section covers the basics of writing assembly routines that call, or are called from, C programs. To do this, you would typically write an assembly module as a .OBJ file, and link it with your C modules to produce a mixed-language program.

9.4.1 External Symbol Names

C compilers have the convention that the names of all global symbols (functions or data) they define are formed by prefixing an underscore to the name as it appears in the C program. So, for example, the function a C programmer thinks of as printf appears to an assembly language programmer as _printf. This means that in your assembly programs, you can define symbols without a leading underscore, and not have to worry about name clashes with C symbols.

If you find the underscores inconvenient, you can define macros to replace the GLOBAL and EXTERN directives as follows:

```
%macro cglobal 1
  global _%1
  %define %1 _%1
%endmacro

%macro cextern 1
  extern _%1
  %define %1 _%1
%endmacro
```

(These forms of the macros only take one argument at a time; a %rep construct could solve this.)

If you then declare an external like this:

```
cextern printf
```

then the macro will expand it as

```
extern _printf
%define printf _printf
```

Thereafter, you can reference printf as if it was a symbol, and the preprocessor will put the leading underscore on where necessary.

The cglobal macro works similarly. You must use cglobal before defining the symbol in question, but you would have had to do that anyway if you used GLOBAL.

Also see section 2.1.28.

9.4.2 Memory Models

NASM contains no mechanism to support the various C memory models directly; you have to keep track yourself of which one you are writing for. This means you have to keep track of the following things:

- In models using a single code segment (tiny, small and compact), functions are near. This means that function pointers, when stored in data segments or pushed on the stack as function arguments, are 16 bits long and contain only an offset field (the CS register never changes its value, and always gives the segment part of the full function address), and that functions are called using ordinary near CALL instructions and return using RETN (which, in NASM, is synonymous with RET anyway). This means both that you should write your own routines to return with RETN, and that you should call external C routines with near CALL instructions.
- In models using more than one code segment (medium, large and huge), functions are far. This means that function pointers are 32 bits long (consisting of a 16-bit offset followed by a 16-bit segment), and that functions are called using CALL FAR (or CALL seg:offset) and return using RETF. Again, you should therefore write your own routines to return with RETF and use CALL FAR to call external routines.
- In models using a single data segment (tiny, small and medium), data pointers are 16 bits long, containing only an offset field (the DS register doesn't change its value, and always gives the segment part of the full data item address).
- In models using more than one data segment (compact, large and huge), data pointers are 32 bits long, consisting of a 16-bit offset followed by a 16-bit segment. You should still be careful not to modify DS in your routines without restoring it afterwards, but ES is free for you to use to access the contents of 32-bit data pointers you are passed.
- The huge memory model allows single data items to exceed 64K in size. In all other memory models, you can access the whole of a data item just by doing arithmetic on the offset field of the pointer you are given, whether a segment field is present or not; in huge model, you have to be more careful of your pointer arithmetic.
- In most memory models, there is a *default* data segment, whose segment address is kept in DS throughout the program. This data segment is typically the same segment as the stack, kept in SS, so that functions' local variables (which are stored on the stack) and global data items can both be accessed easily without changing DS. Particularly large data items are typically stored in other segments. However, some memory models (though not the standard ones, usually) allow the assumption that SS and DS hold the same value to be removed. Be careful about functions' local variables in this latter case.

In models with a single code segment, the segment is called _TEXT, so your code segment must also go by this name in order to be linked into the same place as the main code segment. In models with a single data segment, or with a default data segment, it is called _DATA.

9.4.3 Function Definitions and Function Calls

The C calling convention in 16-bit programs is as follows. In the following description, the words *caller* and *callee* are used to denote the function doing the calling and the function which gets called.

- The caller pushes the function's parameters on the stack, one after another, in reverse order (right to left, so that the first argument specified to the function is pushed last).
- The caller then executes a CALL instruction to pass control to the callee. This CALL is either near or far depending on the memory model.
- The callee receives control, and typically (although this is not actually necessary, in functions which do not need to access their parameters) starts by saving the value of SP in BP so as to be able to use BP as a base pointer to find its parameters on the stack. However, the caller was probably doing this

too, so part of the calling convention states that BP must be preserved by any C function. Hence the callee, if it is going to set up BP as a *frame pointer*, must push the previous value first.

- The callee may then access its parameters relative to BP. The word at [BP] holds the previous value of BP as it was pushed; the next word, at [BP+2], holds the offset part of the return address, pushed implicitly by CALL. In a small-model (near) function, the parameters start after that, at [BP+4]; in a large-model (far) function, the segment part of the return address lives at [BP+4], and the parameters begin at [BP+6]. The leftmost parameter of the function, since it was pushed last, is accessible at this offset from BP; the others follow, at successively greater offsets. Thus, in a function such as printf which takes a variable number of parameters, the pushing of the parameters in reverse order means that the function knows where to find its first parameter, which tells it the number and type of the remaining ones.
- The callee may also wish to decrease SP further, so as to allocate space on the stack for local variables, which will then be accessible at negative offsets from BP.
- The callee, if it wishes to return a value to the caller, should leave the value in AL, AX or DX:AX depending on the size of the value. Floating-point results are sometimes (depending on the compiler) returned in STO.
- Once the callee has finished processing, it restores SP from BP if it had allocated local stack space, then pops the previous value of BP, and returns via RETN or RETF depending on memory model.
- When the caller regains control from the callee, the function parameters are still on the stack, so it typically adds an immediate constant to SP to remove them (instead of executing a number of slow POP instructions). Thus, if a function is accidentally called with the wrong number of parameters due to a prototype mismatch, the stack will still be returned to a sensible state since the caller, which knows how many parameters it pushed, does the removing.

It is instructive to compare this calling convention with that for Pascal programs (described in section 9.5.1). Pascal has a simpler convention, since no functions have variable numbers of parameters. Therefore the callee knows how many parameters it should have been passed, and is able to deallocate them from the stack itself by passing an immediate argument to the RET or RETF instruction, so the caller does not have to do it. Also, the parameters are pushed in left-to-right order, not right-to-left, which means that a compiler can give better guarantees about sequence points without performance suffering.

Thus, you would define a function in C style in the following way. The following example is for small model:

```
global _myfunc
myfunc:
        push
                dd
        mov
                bp,sp
                                ; 64 bytes of local stack space
        sub
                sp,0x40
                bx,[bp+4]
                                 ; first parameter to function
        mov
        ; some more code
                                 ; undo "sub sp,0x40" above
        mov
                sp,bp
        pop
                bp
        ret
```

For a large-model function, you would replace RET by RETF, and look for the first parameter at [BP+6] instead of [BP+4]. Of course, if one of the parameters is a pointer, then the offsets of *subsequent* parameters will change depending on the memory model as well: far pointers take up four bytes on the stack when passed as a parameter, whereas near pointers take up two.

At the other end of the process, to call a C function from your assembly code, you would do something like this:

```
extern _printf
      ; and then, further down...
              word [myint]
                               ; one of my integer variables
      push
      push
              word mystring
                                  ; pointer into my data segment
      call
              _printf
                                  ; 'byte' saves space
      add
              sp, byte 4
      ; then those data items...
segment _DATA
myint
              dw
mystring
              db
                    'This number -> %d <- should be 1234',10,0
```

This piece of code is the small-model assembly equivalent of the C code

```
int myint = 1234;
printf("This number -> %d <- should be 1234\n", myint);</pre>
```

In large model, the function-call code might look more like this. In this example, it is assumed that DS already holds the segment base of the segment _DATA. If not, you would have to initialize it first.

```
push word [myint]
push word seg mystring ; Now push the segment, and...
push word mystring ; ... offset of "mystring"
call far _printf
add sp,byte 6
```

The integer value still takes up one word on the stack, since large model does not affect the size of the int data type. The first argument (pushed last) to printf, however, is a data pointer, and therefore has to contain a segment and offset part. The segment should be stored second in memory, and therefore must be pushed first. (Of course, PUSH DS would have been a shorter instruction than PUSH WORD SEG mystring, if DS was set up as the above example assumed.) Then the actual call becomes a far call, since functions expect far calls in large model; and SP has to be increased by 6 rather than 4 afterwards to make up for the extra word of parameters.

9.4.4 Accessing Data Items

To get at the contents of C variables, or to declare variables which C can access, you need only declare the names as GLOBAL or EXTERN. (Again, the names require leading underscores, as stated in section 9.4.1.) Thus, a C variable declared as int i can be accessed from assembler as

```
extern _i
mov ax,[_i]
```

And to declare your own integer variable which C programs can access as extern int j, you do this (making sure you are assembling in the _DATA segment, if necessary):

```
global _j
_j dw 0
```

To access a C array, you need to know the size of the components of the array. For example, int variables are two bytes long, so if a C program declares an array as int a[10], you can access a[3] by coding mov ax, [_a+6]. (The byte offset 6 is obtained by multiplying the desired array index, 3, by the size of the array element, 2.) The sizes of the C base types in 16-bit compilers are: 1 for char, 2 for short and int, 4 for long and float, and 8 for double.

To access a C data structure, you need to know the offset from the base of the structure to the field you are interested in. You can either do this by converting the C structure definition into a NASM structure definition (using STRUC), or by calculating the one offset and using just that.

To do either of these, you should read your C compiler's manual to find out how it organizes data structures. NASM gives no special alignment to structure members in its own STRUC macro, so you have to specify alignment yourself if the C compiler generates it. Typically, you might find that a structure like

```
struct {
    char c;
    int i;
} foo;
```

might be four bytes long rather than three, since the int field would be aligned to a two-byte boundary. However, this sort of feature tends to be a configurable option in the C compiler, either using command-line options or #pragma lines, so you have to find out how your own compiler does it.

9.4.5 c16.mac: Helper Macros for the 16-bit C Interface

Included in the NASM archives, in the misc directory, is a file c16.mac of macros. It defines three macros: proc, arg and endproc. These are intended to be used for C-style procedure definitions, and they automate a lot of the work involved in keeping track of the calling convention.

(An alternative, TASM compatible form of arg is also now built into NASM's preprocessor. See section 4.8 for details.)

An example of an assembly function using the macro set is given here:

```
proc __nearproc

%$i          arg
%$j          arg
mov          ax,[bp + %$i]
mov          bx,[bp + %$j]
add          ax,[bx]
```

endproc

This defines $_{nearproc}$ to be a procedure taking two arguments, the first (i) an integer and the second (j) a pointer to an integer. It returns i + *j.

Note that the arg macro has an EQU as the first line of its expansion, and since the label before the macro call gets prepended to the first line of the expanded macro, the EQU works, defining %\$i to be an offset from BP. A context-local variable is used, local to the context pushed by the proc macro and popped by the endproc macro, so that the same argument name can be used in later procedures. Of course, you don't have to do that.

The macro set produces code for near functions (tiny, small and compact-model code) by default. You can have it generate far functions (medium, large and huge-model code) by means of coding %define FARCODE. This changes the kind of return instruction generated by endproc, and also changes the starting point for the argument offsets. The macro set contains no intrinsic dependency on whether data pointers are far or not.

arg can take an optional parameter, giving the size of the argument. If no size is given, 2 is assumed, since it is likely that many function parameters will be of type int.

The large-model equivalent of the above function would look like this:

%define FARCODE

```
proc _farproc

%$i     arg
%$j     arg     4
     mov     ax,[bp + %$i]
     mov     bx,[bp + %$j]
     mov     es,[bp + %$j + 2]
     add     ax,[bx]
```

endproc

This makes use of the argument to the arg macro to define a parameter of size 4, because j is now a far pointer. When we load from j, we must load a segment and an offset.

9.5 Interfacing to Borland Pascal Programs

Interfacing to Borland Pascal programs is similar in concept to interfacing to 16-bit C programs. The differences are:

- The leading underscore required for interfacing to C programs is not required for Pascal.
- The memory model is always large: functions are far, data pointers are far, and no data item can be more than 64K long. (Actually, some functions are near, but only those functions that are local to a Pascal unit and never called from outside it. All assembly functions that Pascal calls, and all Pascal functions that assembly routines are able to call, are far.) However, all static data declared in a Pascal program goes into the default data segment, which is the one whose segment address will be in DS when control is passed to your assembly code. The only things that do not live in the default data segment are local variables (they live in the stack segment) and dynamically allocated variables. All data pointers, however, are far.
- The function calling convention is different described below.
- Some data types, such as strings, are stored differently.
- There are restrictions on the segment names you are allowed to use Borland Pascal will ignore code or data declared in a segment it doesn't like the name of. The restrictions are described below.

9.5.1 The Pascal Calling Convention

The 16-bit Pascal calling convention is as follows. In the following description, the words *caller* and *callee* are used to denote the function doing the calling and the function which gets called.

- The caller pushes the function's parameters on the stack, one after another, in normal order (left to right, so that the first argument specified to the function is pushed first).
- The caller then executes a far CALL instruction to pass control to the callee.
- The callee receives control, and typically (although this is not actually necessary, in functions which do not need to access their parameters) starts by saving the value of SP in BP so as to be able to use BP as a base pointer to find its parameters on the stack. However, the caller was probably doing this too, so part of the calling convention states that BP must be preserved by any function. Hence the callee, if it is going to set up BP as a frame pointer, must push the previous value first.
- The callee may then access its parameters relative to BP. The word at [BP] holds the previous value of BP as it was pushed. The next word, at [BP+2], holds the offset part of the return address, and the next one at [BP+4] the segment part. The parameters begin at [BP+6]. The rightmost parameter of the function, since it was pushed last, is accessible at this offset from BP; the others follow, at successively greater offsets.
- The callee may also wish to decrease SP further, so as to allocate space on the stack for local variables, which will then be accessible at negative offsets from BP.
- The callee, if it wishes to return a value to the caller, should leave the value in AL, AX or DX:AX depending on the size of the value. Floating-point results are returned in STO. Results of type Real (Borland's own custom floating-point data type, not handled directly by the FPU) are returned in DX:BX:AX. To return a result of type String, the caller pushes a pointer to a temporary string before pushing the parameters, and the callee places the returned string value at that location. The pointer is not a parameter, and should not be removed from the stack by the RETF instruction.

- Once the callee has finished processing, it restores SP from BP if it had allocated local stack space, then pops the previous value of BP, and returns via RETF. It uses the form of RETF with an immediate parameter, giving the number of bytes taken up by the parameters on the stack. This causes the parameters to be removed from the stack as a side effect of the return instruction.
- When the caller regains control from the callee, the function parameters have already been removed from the stack, so it needs to do nothing further.

Thus, you would define a function in Pascal style, taking two Integer-type parameters, in the following way:

```
global myfunc
myfunc: push
                bp
                bp,sp
        sub
                sp,0x40
                                 ; 64 bytes of local stack space
                                 ; first parameter to function
                bx,[bp+8]
        mov
                bx,[bp+6]
                                 ; second parameter to function
        ; some more code
                                 ; undo "sub sp,0x40" above
        mov
                sp,bp
                bp
        pop
        retf
                                 ; total size of params is 4
                4
```

At the other end of the process, to call a Pascal function from your assembly code, you would do something like this:

```
extern SomeFunc
; and then, further down...

push word seg mystring ; Now push the segment, and...
push word mystring ; ... offset of "mystring"
push word [myint] ; one of my variables
call far SomeFunc
```

This is equivalent to the Pascal code

```
procedure SomeFunc(String: PChar; Int: Integer);
    SomeFunc(@mystring, myint);
```

9.5.2 Borland Pascal Segment Name Restrictions

Since Borland Pascal's internal unit file format is completely different from OBJ, it only makes a very sketchy job of actually reading and understanding the various information contained in a real OBJ file when it links that in. Therefore an object file intended to be linked to a Pascal program must obey a number of restrictions:

- Procedures and functions must be in a segment whose name is either code, cseg, or something ending in _TEXT.
- initialized data must be in a segment whose name is either CONST or something ending in _DATA.
- Uninitialized data must be in a segment whose name is either DATA, DSEG, or something ending in _BSS.
- Any other segments in the object file are completely ignored. GROUP directives and segment attributes are also ignored.

9.5.3 Using c16.mac With Pascal Programs

The c16.mac macro package, described in section 9.4.5, can also be used to simplify writing functions to be called from Pascal programs, if you code %define PASCAL. This definition ensures that functions are far (it implies FARCODE), and also causes procedure return instructions to be generated with an operand.

Defining PASCAL does not change the code which calculates the argument offsets; you must declare your function's arguments in reverse order. For example:

%define PASCAL

```
proc _pascalproc

%$j          arg 4
%$i          arg
          mov          ax,[bp + %$i]
          mov          bx,[bp + %$j]
          mov          es,[bp + %$j] + 2]
          add          ax,[bx]
```

endproc

This defines the same routine, conceptually, as the example in section 9.4.5: it defines a function taking two arguments, an integer and a pointer to an integer, which returns the sum of the integer and the contents of the pointer. The only difference between this code and the large-model C version is that PASCAL is defined instead of FARCODE, and that the arguments are declared in reverse order.

Chapter 10: Writing 32-bit Code (Unix, Win32, DJGPP)

This chapter attempts to cover some of the common issues involved when writing 32-bit code, to run under Win32 or Unix, or to be linked with C code generated by a Unix-style C compiler such as DJGPP. It covers how to write assembly code to interface with 32-bit C routines, and how to write position-independent code for shared libraries.

Almost all 32-bit code, and in particular all code running under win32, DJGPP or any of the PC Unix variants, runs in *flat* memory model. This means that the segment registers and paging have already been set up to give you the same 32-bit 4Gb address space no matter what segment you work relative to, and that you should ignore all segment registers completely. When writing flat-model application code, you never need to use a segment override or modify any segment register, and the code-section addresses you pass to CALL and JMP live in the same address space as the data-section addresses you access your variables by and the stack-section addresses you access local variables and procedure parameters by. Every address is 32 bits long and contains only an offset part.

10.1 Interfacing to 32-bit C Programs

A lot of the discussion in section 9.4, about interfacing to 16-bit C programs, still applies when working in 32 bits. The absence of memory models or segmentation worries simplifies things a lot.

10.1.1 External Symbol Names

Most 32-bit C compilers share the convention used by 16-bit compilers, that the names of all global symbols (functions or data) they define are formed by prefixing an underscore to the name as it appears in the C program. However, not all of them do: the ELF specification states that C symbols do not have a leading underscore on their assembly-language names.

The older Linux a.out C compiler, all Win32 compilers, DJGPP, and NetBSD and FreeBSD, all use the leading underscore; for these compilers, the macros cextern and cglobal, as given in section 9.4.1, will still work. For ELF, though, the leading underscore should not be used.

See also section 2.1.28.

10.1.2 Function Definitions and Function Calls

The C calling convention in 32-bit programs is as follows. In the following description, the words *caller* and *callee* are used to denote the function doing the calling and the function which gets called.

- The caller pushes the function's parameters on the stack, one after another, in reverse order (right to left, so that the first argument specified to the function is pushed last).
- The caller then executes a near CALL instruction to pass control to the callee.
- The callee receives control, and typically (although this is not actually necessary, in functions which do not need to access their parameters) starts by saving the value of ESP in EBP so as to be able to use EBP as a base pointer to find its parameters on the stack. However, the caller was probably doing this too, so part of the calling convention states that EBP must be preserved by any C function. Hence the callee, if it is going to set up EBP as a frame pointer, must push the previous value first.
- The callee may then access its parameters relative to EBP. The doubleword at [EBP] holds the previous value of EBP as it was pushed; the next doubleword, at [EBP+4], holds the return address, pushed implicitly by CALL. The parameters start after that, at [EBP+8]. The leftmost parameter of the function, since it was pushed last, is accessible at this offset from EBP; the others follow, at successively greater offsets. Thus, in a function such as printf which takes a variable number of parameters, the pushing of the parameters in reverse order means that the function knows where to find its first parameter, which tells it the number and type of the remaining ones.

- The callee may also wish to decrease ESP further, so as to allocate space on the stack for local variables, which will then be accessible at negative offsets from EBP.
- The callee, if it wishes to return a value to the caller, should leave the value in AL, AX or EAX depending on the size of the value. Floating-point results are typically returned in STO.
- Once the callee has finished processing, it restores ESP from EBP if it had allocated local stack space, then pops the previous value of EBP, and returns via RET (equivalently, RETN).
- When the caller regains control from the callee, the function parameters are still on the stack, so it typically adds an immediate constant to ESP to remove them (instead of executing a number of slow POP instructions). Thus, if a function is accidentally called with the wrong number of parameters due to a prototype mismatch, the stack will still be returned to a sensible state since the caller, which knows how many parameters it pushed, does the removing.

There is an alternative calling convention used by Win32 programs for Windows API calls, and also for functions called *by* the Windows API such as window procedures: they follow what Microsoft calls the __stdcall convention. This is slightly closer to the Pascal convention, in that the callee clears the stack by passing a parameter to the RET instruction. However, the parameters are still pushed in right-to-left order.

Thus, you would define a function in C style in the following way:

```
global _myfunc
myfunc:
        push
                ebp
                ebp,esp
        mov
        sub
                esp,0x40
                                ; 64 bytes of local stack space
                ebx,[ebp+8]
        mov
                                 ; first parameter to function
        ; some more code
        leave
                                 ; mov esp,ebp / pop ebp
        ret
```

At the other end of the process, to call a C function from your assembly code, you would do something like this:

```
extern _printf
        ; and then, further down...
                dword [myint] ; one of my integer variables
        push
                dword mystring ; pointer into my data segment
        push
                _printf
        call
                                 ; 'byte' saves space
        hhs
                esp, byte 8
        ; then those data items...
segment _DATA
myint
            Ьb
                 1234
                 'This number -> %d <- should be 1234',10,0
This piece of code is the assembly equivalent of the C code
    int myint = 1234;
    printf("This number -> %d <- should be 1234\n", myint);</pre>
```

10.1.3 Accessing Data Items

To get at the contents of C variables, or to declare variables which C can access, you need only declare the names as GLOBAL or EXTERN. (Again, the names require leading underscores, as stated in section 10.1.1.) Thus, a C variable declared as int i can be accessed from assembler as

```
extern _i
mov eax,[_i]
```

And to declare your own integer variable which C programs can access as extern int j, you do this (making sure you are assembling in the _DATA segment, if necessary):

```
global _j
_j dd 0
```

To access a C array, you need to know the size of the components of the array. For example, int variables are four bytes long, so if a C program declares an array as int a[10], you can access a[3] by coding mov ax, [_a+12]. (The byte offset 12 is obtained by multiplying the desired array index, 3, by the size of the array element, 4.) The sizes of the C base types in 32-bit compilers are: 1 for char, 2 for short, 4 for int, long and float, and 8 for double. Pointers, being 32-bit addresses, are also 4 bytes long.

To access a C data structure, you need to know the offset from the base of the structure to the field you are interested in. You can either do this by converting the C structure definition into a NASM structure definition (using STRUC), or by calculating the one offset and using just that.

To do either of these, you should read your C compiler's manual to find out how it organizes data structures. NASM gives no special alignment to structure members in its own STRUC macro, so you have to specify alignment yourself if the C compiler generates it. Typically, you might find that a structure like

```
struct {
    char c;
    int i;
} foo;
```

might be eight bytes long rather than five, since the int field would be aligned to a four-byte boundary. However, this sort of feature is sometimes a configurable option in the C compiler, either using command-line options or #pragma lines, so you have to find out how your own compiler does it.

10.1.4 c32.mac: Helper Macros for the 32-bit C Interface

Included in the NASM archives, in the misc directory, is a file c32.mac of macros. It defines three macros: proc, arg and endproc. These are intended to be used for C-style procedure definitions, and they automate a lot of the work involved in keeping track of the calling convention.

An example of an assembly function using the macro set is given here:

```
proc _proc32
%$i          arg
%$j          arg
mov          eax,[ebp + %$i]
mov          ebx,[ebp + %$j]
add          eax,[ebx]
```

endproc

This defines _proc32 to be a procedure taking two arguments, the first (i) an integer and the second (j) a pointer to an integer. It returns i + *j.

Note that the arg macro has an EQU as the first line of its expansion, and since the label before the macro call gets prepended to the first line of the expanded macro, the EQU works, defining %\$i to be an offset from BP. A context-local variable is used, local to the context pushed by the proc macro and popped by the endproc macro, so that the same argument name can be used in later procedures. Of course, you don't have to do that.

arg can take an optional parameter, giving the size of the argument. If no size is given, 4 is assumed, since it is likely that many function parameters will be of type int or pointers.

10.2 Writing NetBSD/FreeBSD/OpenBSD and Linux/ELF Shared Libraries

ELF replaced the older a.out object file format under Linux because it contains support for position-independent code (PIC), which makes writing shared libraries much easier. NASM supports the ELF position-independent code features, so you can write Linux ELF shared libraries in NASM.

NetBSD, and its close cousins FreeBSD and OpenBSD, take a different approach by hacking PIC support into the a.out format. NASM supports this as the aoutb output format, so you can write BSD shared libraries in NASM too.

The operating system loads a PIC shared library by memory-mapping the library file at an arbitrarily chosen point in the address space of the running process. The contents of the library's code section must therefore not depend on where it is loaded in memory.

Therefore, you cannot get at your variables by writing code like this:

```
mov eax,[myvar]; WRONG
```

Instead, the linker provides an area of memory called the *global offset table*, or GOT; the GOT is situated at a constant distance from your library's code, so if you can find out where your library is loaded (which is typically done using a CALL and POP combination), you can obtain the address of the GOT, and you can then load the addresses of your variables out of linker-generated entries in the GOT.

The *data* section of a PIC shared library does not have these restrictions: since the data section is writable, it has to be copied into memory anyway rather than just paged in from the library file, so as long as it's being copied it can be relocated too. So you can put ordinary types of relocation in the data section without too much worry (but see section 10.2.4 for a caveat).

10.2.1 Obtaining the Address of the GOT

Each code module in your shared library should define the GOT as an external symbol:

```
extern _GLOBAL_OFFSET_TABLE_ ; in ELF
extern __GLOBAL_OFFSET_TABLE_ ; in BSD a.out
```

At the beginning of any function in your shared library which plans to access your data or BSS sections, you must first calculate the address of the GOT. This is typically done by writing the function in this form:

```
func:
        push
                ebp
                ebp,esp
        mov
        push
                ebx
        call
                .get_GOT
.get_GOT:
        gog
                ebx,_GLOBAL_OFFSET_TABLE_+$$-.get_GOT wrt ..gotpc
        add
        ; the function body comes here
                ebx,[ebp-4]
        mov
        mov
                esp,ebp
        pop
                ebp
        ret
```

(For BSD, again, the symbol _GLOBAL_OFFSET_TABLE requires a second leading underscore.)

The first two lines of this function are simply the standard C prologue to set up a stack frame, and the last three lines are standard C function epilogue. The third line, and the fourth to last line, save and restore the EBX register, because PIC shared libraries use this register to store the address of the GOT.

The interesting bit is the CALL instruction and the following two lines. The CALL and POP combination obtains the address of the label .get_GOT, without having to know in advance where the program was loaded (since the CALL instruction is encoded relative to the current position). The ADD instruction makes use of one of the special PIC relocation types: GOTPC relocation. With the WRT ..gotpc qualifier

specified, the symbol referenced (here _GLOBAL_OFFSET_TABLE_, the special symbol assigned to the GOT) is given as an offset from the beginning of the section. (Actually, ELF encodes it as the offset from the operand field of the ADD instruction, but NASM simplifies this deliberately, so you do things the same way for both ELF and BSD.) So the instruction then *adds* the beginning of the section, to get the real address of the GOT, and subtracts the value of .get_GOT which it knows is in EBX. Therefore, by the time that instruction has finished, EBX contains the address of the GOT.

If you didn't follow that, don't worry: it's never necessary to obtain the address of the GOT by any other means, so you can put those three instructions into a macro and safely ignore them:

10.2.2 Finding Your Local Data Items

Having got the GOT, you can then use it to obtain the addresses of your data items. Most variables will reside in the sections you have declared; they can be accessed using the ..gotoff special WRT type. The way this works is like this:

```
lea eax,[ebx+myvar wrt ..gotoff]
```

The expression myvar wrt ..gotoff is calculated, when the shared library is linked, to be the offset to the local variable myvar from the beginning of the GOT. Therefore, adding it to EBX as above will place the real address of myvar in EAX.

If you declare variables as GLOBAL without specifying a size for them, they are shared between code modules in the library, but do not get exported from the library to the program that loaded it. They will still be in your ordinary data and BSS sections, so you can access them in the same way as local variables, using the above ..gotoff mechanism.

Note that due to a peculiarity of the way BSD a.out format handles this relocation type, there must be at least one non-local symbol in the same section as the address you're trying to access.

10.2.3 Finding External and Common Data Items

If your library needs to get at an external variable (external to the *library*, not just to one of the modules within it), you must use the ..got type to get at it. The ..got type, instead of giving you the offset from the GOT base to the variable, gives you the offset from the GOT base to a GOT *entry* containing the address of the variable. The linker will set up this GOT entry when it builds the library, and the dynamic linker will place the correct address in it at load time. So to obtain the address of an external variable extvar in EAX, you would code

```
mov eax,[ebx+extvar wrt ..got]
```

This loads the address of <code>extvar</code> out of an entry in the GOT. The linker, when it builds the shared library, collects together every relocation of type ...got, and builds the GOT so as to ensure it has every necessary entry present.

Common variables must also be accessed in this way.

10.2.4 Exporting Symbols to the Library User

If you want to export symbols to the user of the library, you have to declare whether they are functions or data, and if they are data, you have to give the size of the data item. This is because the dynamic linker has to build procedure linkage table entries for any exported functions, and also moves exported data items away from the library's data section in which they were declared.

So to export a function to users of the library, you must use

```
global func:function ; declare it as a function
func: push ebp
; etc.
And to export a data item such as an array, you would have to code
global array:data array.end-array ; give the size too
```

Be careful: If you export a variable to the library user, by declaring it as GLOBAL and supplying a size, the variable will end up living in the data section of the main program, rather than in your library's data section, where you declared it. So you will have to access your own global variable with the ..got mechanism rather than ..gotoff, as if it were external (which, effectively, it has become).

Equally, if you need to store the address of an exported global in one of your data sections, you can't do it by means of the standard sort of code:

NASM will interpret this code as an ordinary relocation, in which global_data_item is merely an offset from the beginning of the .data section (or whatever); so this reference will end up pointing at your data section instead of at the exported global which resides elsewhere.

Instead of the above code, then, you must write

128

array: resd

.end:

which makes use of the special WRT type ...sym to instruct NASM to search the symbol table for a particular symbol at that address, rather than just relocating by section base.

Either method will work for functions: referring to one of your functions by means of

```
funcptr: dd my_function
```

will give the user the address of the code you wrote, whereas

```
funcptr: dd my_function wrt ..sym
```

will give the address of the procedure linkage table for the function, which is where the calling program will *believe* the function lives. Either address is a valid way to call the function.

10.2.5 Calling Procedures Outside the Library

Calling procedures outside your shared library has to be done by means of a *procedure linkage table*, or PLT. The PLT is placed at a known offset from where the library is loaded, so the library code can make calls to the PLT in a position-independent way. Within the PLT there is code to jump to offsets contained in the GOT, so function calls to other shared libraries or to routines in the main program can be transparently passed off to their real destinations.

To call an external routine, you must use another special PIC relocation type, wrt ..plt. This is much easier than the GOT-based ones: you simply replace calls such as CALL printf with the PLT-relative version CALL printf WRT ..plt.

10.2.6 Generating the Library File

Having written some code modules and assembled them to .o files, you then generate your shared library with a command such as

```
ld -shared -o library.so module1.o module2.o # for ELF
ld -Bshareable -o library.so module1.o module2.o # for BSD
```

For ELF, if your shared library is going to reside in system directories such as /usr/lib or /lib, it is usually worth using the -soname flag to the linker, to store the final library file name, with a version number, into the library:

ld -shared -soname library.so.1 -o library.so.1.2 *.o

You would then copy library.so.1.2 into the library directory, and create library.so.1 as a symbolic link to it.

Chapter 11: Mixing 16- and 32-bit Code

This chapter tries to cover some of the issues, largely related to unusual forms of addressing and jump instructions, encountered when writing operating system code such as protected-mode initialization routines, which require code that operates in mixed segment sizes, such as code in a 16-bit segment trying to modify data in a 32-bit one, or jumps between different-size segments.

11.1 Mixed-Size Jumps

The most common form of mixed-size instruction is the one used when writing a 32-bit OS: having done your setup in 16-bit mode, such as loading the kernel, you then have to boot it by switching into protected mode and jumping to the 32-bit kernel start address. In a fully 32-bit OS, this tends to be the *only* mixed-size instruction you need, since everything before it can be done in pure 16-bit code, and everything after it can be pure 32-bit.

This jump must specify a 48-bit far address, since the target segment is a 32-bit one. However, it must be assembled in a 16-bit segment, so just coding, for example,

```
jmp 0x1234:0x56789ABC ; wrong!
```

will not work, since the offset part of the address will be truncated to 0x9ABC and the jump will be an ordinary 16-bit far one.

The Linux kernel setup code gets round the inability of as86 to generate the required instruction by coding it manually, using DB instructions. NASM can go one better than that, by actually generating the right instruction itself. Here's how to do it right:

```
jmp dword 0x1234:0x56789ABC ; right
```

The DWORD prefix (strictly speaking, it should come *after* the colon, since it is declaring the *offset* field to be a doubleword; but NASM will accept either form, since both are unambiguous) forces the offset part to be treated as far, in the assumption that you are deliberately writing a jump from a 16-bit segment to a 32-bit one.

You can do the reverse operation, jumping from a 32-bit segment to a 16-bit one, by means of the word prefix:

```
jmp word 0x8765:0x4321 ; 32 to 16 bit
```

If the WORD prefix is specified in 16-bit mode, or the DWORD prefix in 32-bit mode, they will be ignored, since each is explicitly forcing NASM into a mode it was in anyway.

11.2 Addressing Between Different-Size Segments

If your OS is mixed 16 and 32-bit, or if you are writing a DOS extender, you are likely to have to deal with some 16-bit segments and some 32-bit ones. At some point, you will probably end up writing code in a 16-bit segment which has to access data in a 32-bit segment, or vice versa.

If the data you are trying to access in a 32-bit segment lies within the first 64K of the segment, you may be able to get away with using an ordinary 16-bit addressing operation for the purpose; but sooner or later, you will want to do 32-bit addressing from 16-bit mode.

The easiest way to do this is to make sure you use a register for the address, since any effective address containing a 32-bit register is forced to be a 32-bit address. So you can do

```
mov eax,offset_into_32_bit_segment_specified_by_fs
mov dword [fs:eax],0x11223344
```

This is fine, but slightly cumbersome (since it wastes an instruction and a register) if you already know the precise offset you are aiming at. The x86 architecture does allow 32-bit effective addresses to

specify nothing but a 4-byte offset, so why shouldn't NASM be able to generate the best instruction for the purpose?

It can. As in section 11.1, you need only prefix the address with the DWORD keyword, and it will be forced to be a 32-bit address:

```
mov dword [fs:dword my_offset],0x11223344
```

Also as in section 11.1, NASM is not fussy about whether the DWORD prefix comes before or after the segment override, so arguably a nicer-looking way to code the above instruction is

```
mov dword [dword fs:my_offset],0x11223344
```

Don't confuse the DWORD prefix *outside* the square brackets, which controls the size of the data stored at the address, with the one inside the square brackets which controls the length of the address itself. The two can quite easily be different:

```
mov word [dword 0x12345678],0x9ABC
```

This moves 16 bits of data to an address specified by a 32-bit offset.

You can also specify WORD or DWORD prefixes along with the FAR prefix to indirect far jumps or calls. For example:

```
call dword far [fs:word 0x4321]
```

This instruction contains an address specified by a 16-bit offset; it loads a 48-bit far pointer from that (16-bit segment and 32-bit offset), and calls that address.

11.3 Other Mixed-Size Instructions

The other way you might want to access data might be using the string instructions (LODSx, STOSx and so on) or the XLATB instruction. These instructions, since they take no parameters, might seem to have no easy way to make them perform 32-bit addressing when assembled in a 16-bit segment.

This is the purpose of NASM's a16, a32 and a64 prefixes. If you are coding LODSB in a 16-bit segment but it is supposed to be accessing a string in a 32-bit segment, you should load the desired address into ESI and then code

```
a32 lodsb
```

The prefix forces the addressing size to 32 bits, meaning that LODSB loads from [DS:ESI] instead of [DS:SI]. To access a string in a 16-bit segment when coding in a 32-bit one, the corresponding ale prefix can be used.

The a16, a32 and a64 prefixes can be applied to any instruction in NASM's instruction table, but most of them can generate all the useful forms without them. The prefixes are necessary only for instructions with implicit addressing: CMPSX, SCASX, LODSX, STOSX, MOVSX, INSX, OUTSX, and XLATB. Also, the various push and pop instructions (PUSHA and POPF as well as the more usual PUSH and POP) can accept a16, a32 or a64 prefixes to force a particular one of SP, ESP or RSP to be used as a stack pointer, in case the stack segment in use is a different size from the code segment.

PUSH and POP, when applied to segment registers in 32-bit mode, also have the slightly odd behaviour that they push and pop 4 bytes at a time, of which the top two are ignored and the bottom two give the value of the segment register being manipulated. To force the 16-bit behaviour of segment-register push and pop instructions, you can use the operand-size prefix o16:

```
o16 push ss
o16 push ds
```

This code saves a doubleword of stack space by fitting two segment registers into the space which would normally be consumed by pushing one.

(You can also use the o32 prefix to force the 32-bit behaviour when in 16-bit mode, but this seems less useful.)

Chapter 12: Writing 64-bit Code (Unix, Win64)

This chapter attempts to cover some of the common issues involved when writing 64-bit code, to run under Win64 or Unix. It covers how to write assembly code to interface with 64-bit C routines, and how to write position-independent code for shared libraries.

All 64-bit code uses a flat memory model, since segmentation is not available in 64-bit mode. The one exception is the FS and GS registers, which still add their bases.

Position independence in 64-bit mode is significantly simpler, since the processor supports RIP-relative addressing directly; see the REL keyword (section 3.3). On most 64-bit platforms, it is probably desirable to make that the default, using the directive DEFAULT REL (section 7.2).

64-bit programming is relatively similar to 32-bit programming, but of course pointers are 64 bits long; additionally, all existing platforms pass arguments in registers rather than on the stack. Furthermore, 64-bit platforms use SSE2 by default for floating point. Please see the ABI documentation for your platform.

64-bit platforms differ in the sizes of the C/C++ fundamental datatypes, not just from 32-bit platforms but from each other. If a specific size data type is desired, it is probably best to use the types defined in the standard C header <inttypes.h>.

All known 64-bit platforms except some embedded platforms require that the stack is 16-byte aligned at the entry to a function. In order to enforce that, the stack pointer (RSP) needs to be aligned on an odd multiple of 8 bytes before the CALL instruction.

In 64-bit mode, the default instruction size is still 32 bits. When loading a value into a 32-bit register (but not an 8- or 16-bit register), the upper 32 bits of the corresponding 64-bit register are set to zero.

12.1 Register Names in 64-bit Mode

NASM uses the following names for general-purpose registers in 64-bit mode, for 8-, 16-, 32- and 64-bit references, respectively:

```
AL/AH, CL/CH, DL/DH, BL/BH, SPL, BPL, SIL, DIL, R8B-R15B AX, CX, DX, BX, SP, BP, SI, DI, R8W-R15W EAX, ECX, EDX, EBX, ESP, EBP, ESI, EDI, R8D-R15D RAX, RCX, RDX, RBX, RSP, RBP, RSI, RDI, R8-R15
```

This is consistent with the AMD documentation and most other assemblers. The Intel documentation, however, uses the names R8L-R15L for 8-bit references to the higher registers. It is possible to use those names by definiting them as macros; similarly, if one wants to use numeric names for the low 8 registers, define them as macros. The standard macro package altreg (see section 6.1) can be used for this purpose.

12.2 Immediates and Displacements in 64-bit Mode

In 64-bit mode, immediates and displacements are generally only 32 bits wide. NASM will therefore truncate most displacements and immediates to 32 bits.

The only instruction which takes a full 64-bit immediate is:

```
MOV reg64, imm64
```

NASM will produce this instruction whenever the programmer uses MOV with an immediate into a 64-bit register. If this is not desirable, simply specify the equivalent 32-bit register, which will be automatically zero-extended by the processor, or specify the immediate as DWORD:

```
mov eax,foo ; 32-bit immediate, zero-extended mov rax,dword foo ; 32-bit immediate, sign-extended
```

The length of these instructions are 10, 5 and 7 bytes, respectively.

If optimization is enabled and NASM can determine at assembly time that a shorter instruction will suffice, the shorter instruction will be emitted unless of course STRICT QWORD or STRICT DWORD is specified (see section 3.7):

Note that lea rax,[rel symbol] is position-independent, whereas mov rax,symbol is not. Most ABIs prefer or even require position-independent code in 64-bit mode. However, the MOV instruction is able to reference a symbol anywhere in the 64-bit address space, whereas LEA is only able to access a symbol within within 2 GB of the instruction itself (see below.)

The only instructions which take a full 64-bit *displacement* is loading or storing, using MOV, AL, AX, EAX or RAX (but no other registers) to an absolute 64-bit address. Since this is a relatively rarely used instruction (64-bit code generally uses relative addressing), the programmer has to explicitly declare the displacement size as ABS QWORD:

A sign-extended absolute displacement can access from -2 GB to +2 GB; a zero-extended absolute displacement can access from 0 to 4 GB.

12.3 Interfacing to 64-bit C Programs (Unix)

On Unix, the 64-bit ABI as well as the x32 ABI (32-bit ABI with the CPU in 64-bit mode) is defined by the documents at:

```
http://www.nasm.us/abi/unix64
```

Although written for AT&T-syntax assembly, the concepts apply equally well for NASM-style assembly. What follows is a simplified summary.

The first six integer arguments (from the left) are passed in RDI, RSI, RDX, RCX, R8, and R9, in that order. Additional integer arguments are passed on the stack. These registers, plus RAX, R10 and R11 are destroyed by function calls, and thus are available for use by the function without saving.

Integer return values are passed in RAX and RDX, in that order.

Floating point is done using SSE registers, except for long double, which is 80 bits (TWORD) on most platforms (Android is one exception; there long double is 64 bits and treated the same as double.) Floating-point arguments are passed in XMM0 to XMM7; return is XMM0 and XMM1. long double are passed on the stack, and returned in STO and ST1.

All SSE and x87 registers are destroyed by function calls.

On 64-bit Unix, long is 64 bits.

Integer and SSE register arguments are counted separately, so for the case of

void foo(long a, double b, int c)

a is passed in RDI, b in XMMO, and c in ESI.

12.4 Interfacing to 64-bit C Programs (Win64)

The Win64 ABI is described by the document at:

http://www.nasm.us/abi/win64

What follows is a simplified summary.

The first four integer arguments are passed in RCX, RDX, R8 and R9, in that order. Additional integer arguments are passed on the stack. These registers, plus RAX, R10 and R11 are destroyed by function calls, and thus are available for use by the function without saving.

Integer return values are passed in RAX only.

Floating point is done using SSE registers, except for long double. Floating-point arguments are passed in XMM0 to XMM3; return is XMM0 only.

On Win64, long is 32 bits; long long or _int64 is 64 bits.

Integer and SSE register arguments are counted together, so for the case of

void foo(long long a, double b, int c)

a is passed in RCX, b in XMM1, and c in R8D.

Chapter 13: Troubleshooting

This chapter describes some of the common problems that users have been known to encounter with NASM, and answers them. If you think you have found a bug in NASM, please see section E.2.

13.1 Common Problems

13.1.1 NASM Generates Inefficient Code

We sometimes get 'bug' reports about NASM generating inefficient, or even 'wrong', code on instructions such as ADD ESP,8. This is a deliberate design feature, connected to predictability of output: NASM, on seeing ADD ESP,8, will generate the form of the instruction which leaves room for a 32-bit offset. You need to code ADD ESP,BYTE 8 if you want the space-efficient form of the instruction. This isn't a bug, it's user error: if you prefer to have NASM produce the more efficient code automatically enable optimization with the -o option (see section 2.1.24).

13.1.2 My Jumps are Out of Range

Similarly, people complain that when they issue conditional jumps (which are SHORT by default) that try to jump too far, NASM reports 'short jump out of range' instead of making the jumps longer.

This, again, is partly a predictability issue, but in fact has a more practical reason as well. NASM has no means of being told what type of processor the code it is generating will be run on; so it cannot decide for itself that it should generate <code>Jcc NEAR</code> type instructions, because it doesn't know that it's working for a 386 or above. Alternatively, it could replace the out-of-range short <code>JNE</code> instruction with a very short <code>JE</code> instruction that jumps over a <code>JMP NEAR</code>; this is a sensible solution for processors below a 386, but hardly efficient on processors which have good branch prediction <code>and</code> could have used <code>JNE NEAR</code> instead. So, once again, it's up to the user, not the assembler, to decide what instructions should be generated. See section 2.1.24.

13.1.3 ORG Doesn't Work

People writing boot sector programs in the bin format often complain that ORG doesn't work the way they'd like: in order to place the <code>0xAA55</code> signature word at the end of a 512-byte boot sector, people who are used to MASM tend to code

```
ORG 0
; some boot sector code
ORG 510
DW 0xAA55
```

This is not the intended use of the ORG directive in NASM, and will not work. The correct way to solve this problem in NASM is to use the TIMES directive, like this:

```
ORG 0
; some boot sector code
TIMES 510-($-$$) DB 0
DW 0xAA55
```

The TIMES directive will insert exactly enough zero bytes into the output to move the assembly point up to 510. This method also has the advantage that if you accidentally fill your boot sector too full, NASM will catch the problem at assembly time and report it, so you won't end up with a boot sector that you have to disassemble to find out what's wrong with it.

13.1.4 TIMES Doesn't Work

The other common problem with the above code is people who write the TIMES line as

TIMES 510-\$ DB 0

by reasoning that \$ should be a pure number, just like 510, so the difference between them is also a pure number and can happily be fed to TIMES.

NASM is a *modular* assembler: the various component parts are designed to be easily separable for re-use, so they don't exchange information unnecessarily. In consequence, the bin output format, even though it has been told by the ORG directive that the .text section should start at 0, does not pass that information back to the expression evaluator. So from the evaluator's point of view, \$ isn't a pure number: it's an offset from a section base. Therefore the difference between \$ and 510 is also not a pure number, but involves a section base. Values involving section bases cannot be passed as arguments to TIMES.

The solution, as in the previous section, is to code the ${\tt TIMES}$ line in the form

TIMES 510-(\$-\$\$) DB 0

in which \$ and \$\$ are offsets from the same section base, and so their difference is a pure number. This will solve the problem and generate sensible code.

Appendix A: Ndisasm

The Netwide Disassembler, NDISASM

A.1 Introduction

The Netwide Disassembler is a small companion program to the Netwide Assembler, NASM. It seemed a shame to have an x86 assembler, complete with a full instruction table, and not make as much use of it as possible, so here's a disassembler which shares the instruction table (and some other bits of code) with NASM.

The Netwide Disassembler does nothing except to produce disassemblies of *binary* source files. NDISASM does not have any understanding of object file formats, like <code>objdump</code>, and it will not understand <code>DOS</code> .EXE files like <code>debug</code> will. It just disassembles.

A.2 Running NDISASM

To disassemble a file, you will typically use a command of the form

```
ndisasm -b {16|32|64} filename
```

NDISASM can disassemble 16-, 32- or 64-bit code equally easily, provided of course that you remember to specify which it is to work with. If no -b switch is present, NDISASM works in 16-bit mode by default. The -u switch (for USE32) also invokes 32-bit mode.

Two more command line options are -r which reports the version number of NDISASM you are running, and -h which gives a short summary of command line options.

A.2.1 COM Files: Specifying an Origin

To disassemble a DOS . COM file correctly, a disassembler must assume that the first instruction in the file is loaded at address 0×100 , rather than at zero. NDISASM, which assumes by default that any file you give it is loaded at zero, will therefore need to be informed of this.

The -o option allows you to declare a different origin for the file you are disassembling. Its argument may be expressed in any of the NASM numeric formats: decimal by default, if it begins with '\$' or '0x' or ends in 'H' it's hex, if it ends in 'Q' it's octal, and if it ends in 'B' it's binary.

Hence, to disassemble a . com file:

ndisasm -o100h filename.com

will do the trick.

A.2.2 Code Following Data: Synchronization

Suppose you are disassembling a file which contains some data which isn't machine code, and *then* contains some machine code. NDISASM will faithfully plough through the data section, producing machine instructions wherever it can (although most of them will look bizarre, and some may have unusual prefixes, e.g. 'FS OR AX,0x240A'), and generating 'DB' instructions ever so often if it's totally stumped. Then it will reach the code section.

Supposing NDISASM has just finished generating a strange machine instruction from part of the data section, and its file position is now one byte *before* the beginning of the code section. It's entirely possible that another spurious instruction will get generated, starting with the final byte of the data section, and then the correct first instruction in the code section will not be seen because the starting point skipped over it. This isn't really ideal.

To avoid this, you can specify a 'synchronization' point, or indeed as many synchronization points as you like (although NDISASM can only handle 2147483647 sync points internally). The definition of a sync point is this: NDISASM guarantees to hit sync points exactly during disassembly. If it is thinking about generating an instruction which would cause it to jump over a sync point, it will discard that instruction and output a 'db' instead. So it will start disassembly exactly from the sync point, and so you will see all the instructions in your code section.

Sync points are specified using the -s option: they are measured in terms of the program origin, not the file position. So if you want to synchronize after 32 bytes of a .COM file, you would have to do

```
ndisasm -o100h -s120h file.com ratherthan
```

ndisasm -o100h -s20h file.com

As stated above, you can specify multiple sync markers if you need to, just by repeating the -s option.

A.2.3 Mixed Code and Data: Automatic (Intelligent) Synchronization

Suppose you are disassembling the boot sector of a DOS floppy (maybe it has a virus, and you need to understand the virus so that you know what kinds of damage it might have done you). Typically, this will contain a JMP instruction, then some data, then the rest of the code. So there is a very good chance of NDISASM being *misaligned* when the data ends and the code begins. Hence a sync point is needed.

On the other hand, why should you have to specify the sync point manually? What you'd do in order to find where the sync point would be, surely, would be to read the JMP instruction, and then to use its target address as a sync point. So can NDISASM do that for you?

The answer, of course, is yes: using either of the synonymous switches -a (for automatic sync) or -i (for intelligent sync) will enable auto-sync mode. Auto-sync mode automatically generates a sync point for any forward-referring PC-relative jump or call instruction that NDISASM encounters. (Since NDISASM is one-pass, if it encounters a PC-relative jump whose target has already been processed, there isn't much it can do about it...)

Only PC-relative jumps are processed, since an absolute jump is either through a register (in which case NDISASM doesn't know what the register contains) or involves a segment address (in which case the target code isn't in the same segment that NDISASM is working in, and so the sync point can't be placed anywhere useful).

For some kinds of file, this mechanism will automatically put sync points in all the right places, and save you from having to place any sync points manually. However, it should be stressed that auto-sync mode is *not* guaranteed to catch all the sync points, and you may still have to place some manually.

Auto-sync mode doesn't prevent you from declaring manual sync points: it just adds automatically generated ones to the ones you provide. It's perfectly feasible to specify -i and some -s options.

Another caveat with auto-sync mode is that if, by some unpleasant fluke, something in your data section should disassemble to a PC-relative call or jump instruction, NDISASM may obediently place a sync point in a totally random place, for example in the middle of one of the instructions in your code section. So you may end up with a wrong disassembly even if you use auto-sync. Again, there isn't much I can do about this. If you have problems, you'll have to use manual sync points, or use the -k option (documented below) to suppress disassembly of the data area.

A.2.4 Other Options

The -e option skips a header on the file, by ignoring the first N bytes. This means that the header is *not* counted towards the disassembly offset: if you give -e10 -o10, disassembly will start at byte 10 in the file, and this will be given offset 10, not 20.

The -k option is provided with two comma-separated numeric arguments, the first of which is an assembly offset and the second is a number of bytes to skip. This *will* count the skipped bytes towards

the assembly offset: its use is to suppress disassembly of a data section which wouldn't contain anything you wanted to see anyway.

Appendix B: Instruction List

B.1 Introduction

The following sections show the instructions which NASM currently supports. For each instruction, there is a separate entry for each supported addressing mode. The third column shows the processor type in which the instruction was introduced and, when appropriate, one or more usage flags.

B.1.1 Special instructions (pseudo-ops)

```
DB
DW
DD
DQ
DT
DO
DY
DΖ
RESB
                                             8086
                  imm
RESW
                                             8086
                  imm
RESD
                  imm
                                             8086
RESQ
                  imm
                                             8086
REST
                                             8086
                  imm
RESO
                  imm
                                             8086
RESY
                  imm
                                             8086
RESZ
                  imm
                                             8086
INCBIN
```

B.1.2 Conventional instructions

AAA		8086,NOLONG
AAD		8086,NOLONG
AAD	imm	8086, NOLONG
AAM		8086,NOLONG
AAM	imm	8086, NOLONG
AAS		8086,NOLONG
ADC	mem,reg8	8086,LOCK
ADC	reg8, reg8	8086
ADC	mem,reg16	8086,LOCK
ADC	reg16,reg16	8086
ADC	mem,reg32	386,LOCK
ADC	reg32,reg32	386
ADC	mem,reg64	X86_64,LONG,LOCK
ADC	reg64,reg64	X86_64,LONG
ADC	reg8,mem	8086
ADC	reg8,reg8	8086
ADC	reg16,mem	8086
ADC	reg16,reg16	8086
ADC	reg32,mem	386
ADC	reg32,reg32	386
ADC	reg64,mem	X86_64,LONG
ADC	reg64,reg64	X86_64,LONG
ADC	rm16,imm8	8086,LOCK
ADC	rm32,imm8	386,LOCK
ADC	rm64,imm8	X86_64,LONG,LOCK
ADC	reg_al,imm	8086
ADC	reg_ax,sbyteword	8086,ND
ADC	reg_ax,imm	8086
ADC	reg_eax,sbytedword	386,ND
ADC	reg_eax,imm	386
ADC	reg_rax,sbytedword	X86_64,LONG,ND
ADC	reg_rax,imm	X86_64,LONG
ADC	rm8,imm	8086,LOCK

ADC	rm16,sbyteword	8086,LOCK,ND
ADC	rm16,imm	8086, LOCK
ADC	rm32,sbytedword	386,LOCK,ND
ADC	rm32,imm	386,LOCK
ADC	rm64,sbytedword	X86_64,LONG,LOCK,ND
	· -	
ADC	rm64,imm	X86_64,LONG,LOCK
ADC	mem,imm8	8086,LOCK,ND
ADC	mem,sbyteword16	8086,LOCK,ND
ADC	mem,imm16	8086,LOCK
ADC	mem,sbytedword32	386,LOCK,ND
ADC	mem,imm32	386,LOCK
ADC	rm8,imm	8086, LOCK, ND, NOLONG
ADD	mem,reg8	8086,LOCK
ADD	reg8,reg8	8086
ADD	mem,reg16	8086,LOCK
ADD	reg16,reg16	8086
ADD		
	mem,reg32	386,LOCK
ADD	reg32,reg32	386
ADD	mem,reg64	X86_64,LONG,LOCK
ADD	reg64,reg64	X86_64,LONG
ADD	reg8,mem	8086
ADD	reg8,reg8	8086
ADD	reg16,mem	8086
ADD	reg16,reg16	8086
ADD	reg32,mem	386
ADD	reg32,reg32	386
ADD	reg64,mem	X86_64,LONG
ADD	reg64,reg64	X86_64,LONG
ADD	rm16,imm8	8086,LOCK
ADD	rm32,imm8	386,LOCK
		-
ADD	rm64,imm8	X86_64,LONG,LOCK
ADD	reg_al,imm	8086
ADD	reg_ax,sbyteword	8086,ND
ADD	reg_ax,imm	8086
ADD	reg_eax,sbytedword	386,ND
ADD	reg_eax,imm	386
ADD	reg_rax,sbytedword	X86_64,LONG,ND
ADD	reg_rax,imm	X86_64,LONG
ADD	rm8,imm	8086,LÓCK
ADD	rm16,sbyteword	8086,LOCK,ND
ADD	rm16,imm	8086,LOCK
ADD	rm32,sbytedword	386,LOCK,ND
ADD	rm32,imm	386,LOCK
ADD	rm64,sbytedword	
AUU		
ADD		X86_64,LONG,LOCK,ND
ADD	rm64,imm	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK
ADD	rm64,imm mem,imm8	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK
ADD ADD	rm64,imm mem,imm8 mem,sbyteword16	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND
ADD ADD ADD	rm64,imm mem,imm8 mem,sbyteword16 mem,imm16	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND 8086,LOCK
ADD ADD ADD ADD	rm64,imm mem,imm8 mem,sbyteword16 mem,imm16 mem,sbytedword32	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND 8086,LOCK 386,LOCK,ND
ADD ADD ADD	rm64,imm mem,imm8 mem,sbyteword16 mem,imm16	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND 8086,LOCK 386,LOCK,ND 386,LOCK
ADD ADD ADD ADD	rm64,imm mem,imm8 mem,sbyteword16 mem,imm16 mem,sbytedword32	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND 8086,LOCK 386,LOCK,ND
ADD ADD ADD ADD ADD	rm64,imm mem,imm8 mem,sbyteword16 mem,imm16 mem,sbytedword32 mem,imm32	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND 8086,LOCK 386,LOCK,ND 386,LOCK
ADD ADD ADD ADD ADD ADD	rm64,imm mem,imm8 mem,sbyteword16 mem,imm16 mem,sbytedword32 mem,imm32 rm8,imm mem,reg8	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND 8086,LOCK 386,LOCK,ND 386,LOCK 8086,LOCK
ADD ADD ADD ADD ADD ADD ADD ADD ADD	rm64,imm mem,imm8 mem,sbyteword16 mem,imm16 mem,sbytedword32 mem,imm32 rm8,imm mem,reg8 reg8,reg8	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND 8086,LOCK,ND 386,LOCK,ND 386,LOCK 8086,LOCK,ND,NOLONG 8086,LOCK
ADD ADD ADD ADD ADD ADD ADD AND AND AND	rm64,imm mem,imm8 mem,sbyteword16 mem,imm16 mem,sbytedword32 mem,imm32 rm8,imm mem,reg8 reg8,reg8 mem,reg16	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND 8086,LOCK,ND 386,LOCK,ND 386,LOCK 8086,LOCK,ND,NOLONG 8086,LOCK 8086
ADD ADD ADD ADD ADD ADD AND AND AND AND	rm64,imm mem,imm8 mem,sbyteword16 mem,imm16 mem,sbytedword32 mem,imm32 rm8,imm mem,reg8 reg8,reg8 mem,reg16 reg16,reg16	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND 8086,LOCK,ND 386,LOCK,ND 386,LOCK 8086,LOCK,ND,NOLONG 8086,LOCK 8086 8086,LOCK
ADD ADD ADD ADD ADD ADD AND AND AND AND	rm64,imm mem,imm8 mem,sbyteword16 mem,imm16 mem,sbytedword32 mem,imm32 rm8,imm mem,reg8 reg8,reg8 mem,reg16 reg16,reg16 mem,reg32	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND 8086,LOCK,ND 386,LOCK,ND 386,LOCK 8086,LOCK,ND,NOLONG 8086,LOCK 8086 8086,LOCK 8086 386,LOCK
ADD ADD ADD ADD ADD ADD AND AND AND AND	rm64,imm mem,imm8 mem,sbyteword16 mem,imm16 mem,sbytedword32 mem,imm32 rm8,imm mem,reg8 reg8,reg8 mem,reg16 reg16,reg16 mem,reg32 reg32,reg32	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND 8086,LOCK,ND 386,LOCK,ND 386,LOCK 8086,LOCK,ND,NOLONG 8086,LOCK 8086 8086,LOCK 8086 386,LOCK
ADD ADD ADD ADD ADD ADD AND AND AND AND	rm64,imm mem,imm8 mem,sbyteword16 mem,imm16 mem,sbytedword32 mem,imm32 rm8,imm mem,reg8 reg8,reg8 mem,reg16 reg16,reg16 mem,reg32 reg32,reg32 mem,reg64	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND 8086,LOCK,ND 386,LOCK 8086,LOCK,ND,NOLONG 8086,LOCK 8086,LOCK 8086 8086,LOCK 8086 8086,LOCK 8086 X86_64,LOCK
ADD ADD ADD ADD ADD ADD AND AND AND AND	rm64,imm mem,imm8 mem,sbyteword16 mem,imm16 mem,sbytedword32 mem,imm32 rm8,imm mem,reg8 reg8,reg8 mem,reg16 reg16,reg16 mem,reg32 reg32,reg32 mem,reg64 reg64,reg64	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND 8086,LOCK,ND 386,LOCK,ND 386,LOCK,ND,NOLONG 8086,LOCK 8086 8086,LOCK 8086 386,LOCK 8086 386,LOCK 8086 386,LOCK 8086 386,LOCK 8086
ADD ADD ADD ADD ADD ADD AND AND AND AND	rm64,imm mem,imm8 mem,sbyteword16 mem,imm16 mem,sbytedword32 mem,imm32 rm8,imm mem,reg8 reg8,reg8 mem,reg16 reg16,reg16 mem,reg32 reg32,reg32 mem,reg64 reg64,reg64 reg8,mem	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND 8086,LOCK,ND 386,LOCK,ND,NOLONG 8086,LOCK,ND,NOLONG 8086,LOCK 8086 8086,LOCK 8086 386,LOCK 8086 386,LOCK 8086 386,LOCK 8086 386,LOCK 8086 386,LOCK 8086
ADD ADD ADD ADD ADD AND AND AND AND AND	rm64,imm mem,imm8 mem,sbyteword16 mem,imm16 mem,sbytedword32 mem,imm32 rm8,imm mem,reg8 reg8,reg8 mem,reg16 reg16,reg16 mem,reg32 reg32,reg32 mem,reg64 reg64,reg64 reg8,mem reg8,reg8	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND 8086,LOCK,ND 386,LOCK,ND,NOLONG 8086,LOCK,ND,NOLONG 8086,LOCK 8086 8086,LOCK 8086 386,LOCK 386 386,LOCK 386 386,LOCK 386 386,LOCK 8086 386,LOCK 386 386,LOCK
ADD ADD ADD ADD ADD AND AND AND AND AND	rm64,imm mem,imm8 mem,sbyteword16 mem,imm16 mem,sbytedword32 mem,imm32 rm8,imm mem,reg8 reg8,reg8 mem,reg16 reg16,reg16 mem,reg32 reg32,reg32 mem,reg64 reg64,reg64 reg8,mem reg8,reg8 reg8,mem reg8,reg8	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND 8086,LOCK,ND 386,LOCK,ND,NOLONG 8086,LOCK 8086,LOCK 8086 8086,LOCK 8086 \$886,LOCK 8086 \$886,LOCK 8086 \$886,LOCK 8086 \$886,LOCK 8086 \$886,LOCK 8086 \$886,LOCK 8086 \$886,LOCK 8086 \$886,LOCK 8086 \$886,LOCK 8086
ADD ADD ADD ADD ADD ADD AND AND AND AND	rm64,imm mem,imm8 mem,sbyteword16 mem,imm16 mem,sbytedword32 mem,imm32 rm8,imm mem,reg8 reg8,reg8 mem,reg16 reg16,reg16 mem,reg32 reg32,reg32 mem,reg64 reg64,reg64 reg84,reg8 reg8,mem reg8,mem reg8,mem reg8,reg8 reg16,mem reg16,reg16	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND 8086,LOCK,ND 386,LOCK 8086,LOCK,ND,NOLONG 8086,LOCK 8086 8086,LOCK 8086 8086,LOCK 8086 386,LOCK 8086 8086,LOCK 8086 8086,LOCK 8086 8086,LOCK 8086 8086,LOCK 8086
ADD ADD ADD ADD ADD AND AND AND AND AND	rm64,imm mem,imm8 mem,sbyteword16 mem,imm16 mem,sbytedword32 mem,imm32 rm8,imm mem,reg8 reg8,reg8 mem,reg16 reg16,reg16 mem,reg32 reg32,reg32 mem,reg64 reg64,reg64 reg64,reg64 reg8,mem reg8,mem reg8,reg8 reg16,mem reg16,reg16 reg32,mem	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND 8086,LOCK,ND 386,LOCK,ND,NOLONG 8086,LOCK 8086,LOCK 8086 8086,LOCK 8086 \$886,LOCK 8086 \$886,LOCK 8086 \$886,LOCK 8086 \$886,LOCK 8086 \$886,LOCK 8086 \$886,LOCK 8086 \$886,LOCK 8086 \$886,LOCK 8086 \$886,LOCK 8086
ADD ADD ADD ADD ADD ADD AND AND AND AND	rm64,imm mem,imm8 mem,sbyteword16 mem,imm16 mem,sbytedword32 mem,imm32 rm8,imm mem,reg8 reg8,reg8 mem,reg16 reg16,reg16 mem,reg32 reg32,reg32 mem,reg64 reg64,reg64 reg84,reg8 reg8,mem reg8,mem reg8,mem reg8,reg8 reg16,mem reg16,reg16	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND 8086,LOCK,ND 386,LOCK 8086,LOCK,ND,NOLONG 8086,LOCK 8086 8086,LOCK 8086 8086,LOCK 8086 386,LOCK 8086 8086,LOCK 8086 8086,LOCK 8086 8086,LOCK 8086 8086,LOCK 8086
ADD ADD ADD ADD ADD ADD AND AND AND AND	rm64,imm mem,imm8 mem,sbyteword16 mem,imm16 mem,sbytedword32 mem,imm32 rm8,imm mem,reg8 reg8,reg8 mem,reg16 reg16,reg16 mem,reg32 reg32,reg32 mem,reg64 reg64,reg64 reg64,reg64 reg8,mem reg8,mem reg8,reg8 reg16,mem reg16,reg16 reg32,mem	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND 8086,LOCK,ND 386,LOCK 8086,LOCK,ND,NOLONG 8086,LOCK 8086 8086,LOCK 8086 386,LOCK 8086 386,LOCK 8086 8086,LOCK 8086 8086,LOCK 8086 386,LOCK 8086 8086,LOCK 8086 386,LOCK 8086 8086,LOCK 8086
ADD ADD ADD ADD ADD ADD AND AND AND AND	rm64,imm mem,imm8 mem,sbyteword16 mem,imm16 mem,sbytedword32 mem,imm32 rm8,imm mem,reg8 reg8,reg8 mem,reg16 reg16,reg16 mem,reg32 reg32,reg32 mem,reg64 reg64,reg64 reg64,reg64 reg8,mem reg8,mem reg8,reg8 reg16,mem reg16,reg16 reg32,mem reg32,reg32	X86_64,LONG,LOCK,ND X86_64,LONG,LOCK 8086,LOCK 8086,LOCK,ND 8086,LOCK,ND 386,LOCK 8086,LOCK,ND,NOLONG 8086,LOCK 8086 8086,LOCK 8086 386,LOCK 8086 386,LOCK 8086 8086 8086 8086 8086 8086 8086 808

```
AND
                   rm16, imm8
                                               8086, LOCK
AND
                   rm32,imm8
                                               386,LOCK
AND
                   rm64,imm8
                                               X86_64, LONG, LOCK
AND
                   reg_al,imm
                                               8086
                   reg_ax,sbyteword
AND
                                               8086,ND
AND
                   reg_ax,imm
                                               8086
                   reg_eax,sbytedword
                                               386,ND
AND
AND
                   reg_eax,imm
                                               386
                                               X86_64,LONG,ND
AND
                   reg_rax,sbytedword
                   reg_rax,imm
AND
                                               X86_64,LONG
AND
                   rm8,imm
                                               8086, LOCK
AND
                   rm16, sbyteword
                                               8086, LOCK, ND
AND
                   rm16,imm
                                               8086, LOCK
AND
                   rm32, sbytedword
                                               386, LOCK, ND
AND
                   rm32,imm
                                               386,LOCK
                   rm64, sbytedword
                                               X86_64, LONG, LOCK, ND
AND
AND
                   rm64,imm
                                               X86_64, LONG, LOCK
                                               8086, LOCK
AND
                  mem, imm8
AND
                  mem, sbyteword16
                                               8086, LOCK, ND
AND
                  mem, imm16
                                               8086, LOCK
                  mem, sbytedword32
AND
                                               386, LOCK, ND
                  mem,imm32
AND
                                               386,LOCK
AND
                   rm8,imm
                                               8086, LOCK, ND, NOLONG
ARPL
                  mem, reg16
                                               286, PROT, NOLONG
                   reg16, reg16
                                               286, PROT, NOLONG
ARPL
                                               PENT, CYRIX, ND, OBSOLETE
BB0_RESET
BB1_RESET
                                               PENT, CYRIX, ND, OBSOLETE
BOUND
                   reg16,mem
                                               186, NOLONG
BOUND
                   reg32, mem
                                               386, NOLONG
BSF
                   reg16,mem
                                               386
BSF
                   reg16, reg16
                                               386
                                               386
BSF
                   reg32,mem
BSF
                   reg32,reg32
                                               386
                                               X86_64,LONG
BSF
                   reg64, mem
BSF
                   reg64, reg64
                                               X86_64,LONG
BSR
                   reg16,mem
                                               386
BSR
                   reg16, reg16
                                               386
BSR
                                               386
                   reg32,mem
BSR
                   reg32, reg32
                                               386
BSR
                                               X86_64,LONG
                   reg64, mem
BSR
                   reg64, reg64
                                               X86_64,LONG
BSWAP
                   reg32
                                               486
                                               X86_64,LONG
BSWAP
                   reg64
                                               386
ВТ
                  mem, reg16
ВТ
                   reg16, reg16
                                               386
вт
                                               386
                  mem, reg32
ВТ
                   reg32, reg32
                                               386
                                               X86_64,LONG
ВТ
                  mem, reg64
вт
                   reg64, reg64
                                               X86_64,LONG
ВТ
                   rm16,imm8
                                               386
ВТ
                   rm32,imm8
                                               386
ВТ
                   rm64,imm8
                                               X86 64,LONG
BTC
                  mem, reg16
                                               386,LOCK
BTC
                   reg16, reg16
                                               386
                  mem,reg32
BTC
                                               386,LOCK
BTC
                   reg32, reg32
                                               386
BTC
                                               X86_64, LONG, LOCK
                  mem, reg64
втс
                   reg64, reg64
                                               X86_64,LONG
                                               386,LOCK
BTC
                   rm16,imm8
втс
                   rm32,imm8
                                               386,LOCK
втс
                   rm64,imm8
                                               X86_64, LONG, LOCK
BTR
                                               386,LOCK
                  mem, reg16
BTR
                   reg16, reg16
                                               386
                                               386,LOCK
BTR
                  mem, reg32
BTR
                                               386
                   reg32, reg32
BTR
                                               X86_64, LONG, LOCK
                   mem, reg64
```

BTR

reg64, reg64

X86_64,LONG

```
BTR
                   rm16, imm8
                                               386,LOCK
BTR
                   rm32,imm8
                                               386,LOCK
BTR
                   rm64,imm8
                                               X86_64, LONG, LOCK
                                               386,LOCK
BTS
                  mem, reg16
BTS
                   reg16, reg16
                                               386
BTS
                  mem, reg32
                                               386,LOCK
BTS
                   reg32, reg32
                                               386
BTS
                                               X86_64,LONG,LOCK
                  mem, reg64
BTS
                   reg64, reg64
                                               X86_64,LONG
                   rm16,imm8
BTS
                                               386,LOCK
BTS
                   rm32,imm8
                                               386,LOCK
                   rm64,imm8
                                               X86_64, LONG, LOCK
BTS
CALL
                   imm
                                               8086,BND
CALL
                   imm|near
                                               8086, ND, BND
CALL
                   imm|far
                                               8086, ND, NOLONG
                   imm16
                                               8086, NOLONG, BND
CALL
CALL
                   imm16|near
                                               8086, ND, NOLONG, BND
CALL
                   imm16|far
                                               8086, ND, NOLONG
                                               386, NOLONG, BND
CALL
                   imm32
CALL
                   imm32|near
                                               386, ND, NOLONG, BND
                                               386, ND, NOLONG
CALL
                   imm32|far
                   imm64
CALL
                                               X86_64,LONG,BND
CALL
                   imm64|near
                                               X86_64, LONG, ND, BND
CALL
                   imm:imm
                                               8086, NOLONG
CALL
                   imm16:imm
                                               8086, NOLONG
CALL
                   imm:imm16
                                               8086, NOLONG
CALL
                   imm32:imm
                                               386,NOLONG
CALL
                   imm:imm32
                                               386, NOLONG
                  mem|far
CALL
                                               8086, NOLONG
CALL
                  mem | far
                                               X86_64,LONG
CALL
                  mem16|far
                                               8086
CALL
                  mem32|far
                                               386
                  mem64|far
CALL
                                               X86_64,LONG
CALL
                  mem|near
                                               8086, ND, BND
                  rm16|near
CALL
                                               8086, NOLONG, ND, BND
                   rm32 near
                                               386.NOLONG.ND.BND
CALL
CALL
                   rm64|near
                                               X86_64, LONG, ND, BND
                                               8086,BND
CALL
                  mem
CALL
                   rm16
                                               8086, NOLONG, BND
CALL
                                               386, NOLONG, BND
                   rm32
CALL
                   rm64
                                               X86_64, LONG, BND
CBW
                                               8086
CDQ
                                               386
                                               X86_64,LONG
CDQE
CLC
                                               8086
CLD
                                              8086
CLI
                                               8086
CLTS
                                               286, PRIV
CMC
                                               8086
CMP
                                               8086
                  mem, reg8
CMP
                   reg8, reg8
                                               8086
CMP
                  mem, reg16
                                              8086
CMP
                   reg16, reg16
                                               8086
CMP
                  mem, reg32
                                               386
CMP
                   reg32, reg32
                                               386
CMP
                  mem, reg64
                                               X86_64,LONG
CMP
                                               X86_64,LONG
                   reg64, reg64
CMP
                   reg8,mem
                                               8086
CMP
                   reg8, reg8
                                               8086
CMP
                                               8086
                   reg16,mem
CMP
                                               8086
                   reg16, reg16
CMP
                   reg32,mem
                                               386
CMP
                   reg32, reg32
                                               386
CMP
                   reg64, mem
                                               X86_64,LONG
CMP
                   reg64, reg64
                                               X86_64,LONG
CMP
                   rm16,imm8
                                               8086
CMP
                   rm32, imm8
                                               386
```

```
CMP
                   rm64, imm8
                                              X86_64,LONG
                   reg_al,imm
CMP
                                              8086
CMP
                   reg_ax,sbyteword
                                              8086,ND
CMP
                   reg_ax,imm
                                              8086
CMP
                   reg_eax,sbytedword
                                              386,ND
CMP
                   reg_eax, imm
                                              386
                                              X86_64,LONG,ND
CMP
                   reg_rax,sbytedword
CMP
                   reg_rax,imm
                                              X86_64,LONG
CMP
                   rm8, imm
                                              8086
                   rm16,sbyteword
                                              8086,ND
CMP
CMP
                   rm16,imm
                                              8086
CMP
                   rm32, sbytedword
                                              386,ND
CMP
                  rm32,imm
                                              386
CMP
                   rm64, sbytedword
                                              X86_64,LONG,ND
CMP
                   rm64,imm
                                              X86_64,LONG
                  mem,imm8
                                              8086
CMP
CMP
                  mem, sbyteword16
                                              8086,ND
                  mem,imm16
                                              8086
CMP
                  mem, sbytedword32
CMP
                                              386,ND
CMP
                  mem,imm32
                                              386
                  rm8,imm
                                              8086, ND, NOLONG
CMP
CMPSB
                                              8086
CMPSD
                                              386
CMPS0
                                              X86_64,LONG
CMPSW
                                              8086
CMPXCHG
                  mem, reg8
                                              PENT, LOCK
CMPXCHG
                  reg8, reg8
                                              PENT
CMPXCHG
                  mem, reg16
                                              PENT, LOCK
CMPXCHG
                  reg16, reg16
                                              PENT
CMPXCHG
                  mem, reg32
                                              PENT, LOCK
CMPXCHG
                  reg32, reg32
                                              PENT
                                              X86_64, LONG, LOCK
CMPXCHG
                  mem, reg64
CMPXCHG
                   reg64, reg64
                                              X86_64,LONG
                                              486, UNDOC, ND, LOCK, OBSOLETE
CMPXCHG486
                  mem, reg8
                  reg8, reg8
                                              486, UNDOC, ND, OBSOLETE
CMPXCHG486
                                              486, UNDOC, ND, LOCK, OBSOLETE
CMPXCHG486
                  mem, reg16
                                              486, UNDOC, ND, OBSOLETE
CMPXCHG486
                   reg16, reg16
CMPXCHG486
                                              486, UNDOC, ND, LOCK, OBSOLETE
                  mem,reg32
CMPXCHG486
                  reg32,reg32
                                              486, UNDOC, ND, OBSOLETE
                  mem64
                                              PENT, LOCK
CMPXCHG8B
CMPXCHG16B
                  mem128
                                              X86_64, LONG, LOCK
CPUID
                                              PENT
CPU_READ
                                              PENT, CYRIX
CPU_WRITE
                                              PENT, CYRIX
CQ0
                                              X86_64,LONG
CWD
                                              8086
CWDE
                                              386
                                              8086, NOLONG
DAA
                                              8086, NOLONG
DAS
DEC
                   reg16
                                              8086, NOLONG
DEC
                   reg32
                                              386, NOLONG
DEC
                   rm8
                                              8086, LOCK
DEC
                   rm16
                                              8086, LOCK
DEC
                   rm32
                                              386,LOCK
                                              X86_64,LONG,LOCK
DEC
                   rm64
DIV
                   rm8
                                              8086
DIV
                                              8086
                   rm16
DIV
                   rm32
                                              386
                                              X86_64,LONG
DIV
                   rm64
DMINT
                                              P6,CYRIX
EMMS
                                              PENT, MMX
ENTER
                   imm,imm
                                              186
EQU
                   imm
                                              8086
EQU
                   imm:imm
                                              8086
F2XM1
                                              8086,FPU
FABS
                                              8086, FPU
FADD
                  mem32
                                              8086, FPU
```

FADD	mem64	8086,FPU
FADD	fpureg to	8086,FPU
FADD	fpureg	8086,FPU
FADD	fpureg,fpu0	8086,FPU
FADD	fpu0,fpureg	8086,FPU
FADD	. ,	8086, FPU, ND
FADDP	fpureg	8086,FPU
FADDP	fpureg, fpu0	8086,FPU
FADDP	. pa. 08, . pa0	8086,FPU,ND
FBLD	mem80	8086,FPU
FBLD		
	mem	8086, FPU
FBSTP	mem80	8086,FPU
FBSTP	mem	8086,FPU
FCHS		8086,FPU
FCLEX		8086,FPU
FCMOVB	fpureg	P6,FPU
FCMOVB	fpu0,fpureg	P6,FPU
FCMOVB		P6,FPU,ND
FCMOVBE	fpureg	P6,FPU
FCMOVBE	fpu0,fpureg	P6,FPU
FCMOVBE		P6,FPU,ND
FCMOVE	fpureg	P6,FPU
FCMOVE	fpu0,fpureg	P6,FPU
FCMOVE	, , ,	P6,FPU,ND
FCMOVNB	fpureg	P6,FPU
FCMOVNB	fpu0,fpureg	P6,FPU
FCMOVNB	· pao , · pai eg	P6,FPU,ND
FCMOVNBE	fpureg	P6,FPU
FCMOVNBE	fpu0,fpureg	P6,FPU
	ipuo, ipui eg	
FCMOVNE	£	P6,FPU,ND
FCMOVNE	fpureg	P6,FPU
FCMOVNE	fpu0,fpureg	P6,FPU
FCMOVNE		P6,FPU,ND
FCMOVNU	fpureg	P6,FPU
FCMOVNU	fpu0,fpureg	P6,FPU
FCMOVNU		P6,FPU,ND
FCMOVU	fpureg	P6,FPU
FCMOVU	fpu0,fpureg	P6,FPU
FCMOVU		P6,FPU,ND
FCOM	mem32	8086,FPU
FCOM	mem64	8086,FPU
FCOM	fpureg	8086,FPU
FCOM	fpu0,fpureg	8086,FPU
FCOM	1	8086, FPU, ND
FCOMI	fpureg	P6,FPU
FCOMI	fpu0,fpureg	P6,FPU
FCOMI	· pao ; · pai eg	P6,FPU,ND
FCOMIP	fpureg	P6,FPU
FCOMIP	fpu0,fpureg	P6,FPU
	ipuo, ipui eg	P6,FPU,ND
FCOMP	22	, ,
FCOMP	mem32	8086,FPU
FCOMP	mem64	8086,FPU
FCOMP	fpureg	8086,FPU
FCOMP	fpu0,fpureg	8086,FPU
FCOMP		8086,FPU,ND
FCOMPP		8086,FPU
FCOS		386,FPU
FDECSTP		8086,FPU
FDISI		8086,FPU
FDIV	mem32	8086,FPU
FDIV	mem64	8086,FPU
FDIV	fpureg to	8086,FPU
FDIV	fpureg	8086,FPU
FDIV	fpureg,fpu0	8086,FPU
FDIV	fpu0,fpureg	8086,FPU
FDIV		8086,FPU,ND
FDIVP	fpureg	8086, FPU
IDTAI	i pui Cg	5000,170

FDIVP	fpureg,fpu0	8086,FPU
FDIVP		8086,FPU,ND
FDIVR	mem32	8086,FPU
FDIVR	mem64	8086,FPU
FDIVR	fpureg to	8086,FPU
FDIVR	fpureg,fpu0	8086,FPU
FDIVR	fpureg	8086,FPU
FDIVR	fpu0,fpureg	8086,FPU
FDIVR		8086,FPU,ND
FDIVRP	fpureg	8086,FPU
FDIVRP	fpureg,fpu0	8086,FPU
FDIVRP	i pui eg, i puo	
		8086, FPU, ND
FEMMS		PENT,3DNOW
FENI	_	8086,FPU
FFREE	fpureg	8086,FPU
FFREE		8086,FPU
FFREEP	fpureg	286, FPU, UNDOC
FFREEP		286, FPU, UNDOC
FIADD	mem32	8086,FPÚ
FIADD	mem16	8086,FPU
FICOM		•
	mem32	8086,FPU
FICOM	mem16	8086,FPU
FICOMP	mem32	8086,FPU
FICOMP	mem16	8086,FPU
FIDIV	mem32	8086,FPU
FIDIV	mem16	8086,FPU
FIDIVR	mem32	8086,FPU
FIDIVR	mem16	8086,FPU
		•
FILD	mem32	8086,FPU
FILD	mem16	8086,FPU
FILD	mem64	8086,FPU
FIMUL	mem32	8086,FPU
FIMUL	mem16	8086,FPU
FINCSTP		8086,FPU
FINIT		8086,FPU
FIST	mem32	8086,FPU
FIST	mem16	8086, FPU
FISTP	mem32	8086,FPU
FISTP	mem16	8086,FPU
FISTP	mem64	8086,FPU
FISTTP	mem16	PRESCOTT, FPU
FISTTP	mem32	PRESCOTT, FPU
FISTTP	mem64	PRESCOTT, FPU
FISUB	mem32	8086,FPU
	mem16	
FISUB		8086, FPU
FISUBR	mem32	8086,FPU
FISUBR	mem16	8086,FPU
FLD	mem32	8086,FPU
FLD	mem64	8086,FPU
FLD	mem80	8086,FPU
FLD	fpureg	8086,FPU
FLD	. F	8086, FPU, ND
FLD1		8086,FPU
	mom	,
FLDCW	mem	8086, FPU, SW
FLDENV	mem	8086,FPU
FLDL2E		8086,FPU
FLDL2T		8086,FPU
FLDLG2		8086,FPU
FLDLN2		8086,FPU
FLDPI		8086,FPU
FLDZ		8086,FPU
FMUL	mem32	•
		8086, FPU
FMUL	mem64	8086,FPU
FMUL	fpureg to	8086,FPU
FMUL	fpureg,fpu0	8086,FPU
FMUL	fpureg	8086,FPU
FMUL	fpu0,fpureg	8086,FPU
	· · -	•

FMUL		8086,FPU,ND
FMULP	fpureg	8086,FPU
FMULP	fpureg,fpu0	8086,FPU
FMULP	. pa. 08, . pa0	8086,FPU,ND
FNCLEX		8086,FPU
FNDISI		8086,FPU
FNENI		8086, FPU
FNINIT		8086,FPU
FNOP		8086,FPU
FNSAVE	mem	8086,FPU
FNSTCW	mem	8086, FPU, SW
FNSTENV	mem	8086,FPU
FNSTSW	mem	8086, FPU, SW
FNSTSW	reg_ax	286,FPU
FPATAN		8086,FPU
FPREM		8086,FPU
FPREM1		386,FPU
FPTAN		8086,FPU
FRNDINT		8086,FPU
FRSTOR	mem	8086,FPU
FSAVE	mem	8086,FPU
FSCALE		8086,FPU
FSETPM		286,FPU
FSIN		•
		386,FPU
FSINCOS		386,FPU
FSQRT		8086,FPU
FST	mem32	8086,FPU
FST	mem64	8086,FPU
FST	fpureg	8086,FPU
	i pui eg	,
FST		8086, FPU, ND
FSTCW	mem	8086,FPU,SW
FSTENV	mem	8086,FPU
FSTP	mem32	8086,FPU
FSTP	mem64	8086,FPU
FSTP	mem80	8086,FPU
FSTP	fpureg	8086,FPU
FSTP		8086,FPU,ND
FSTSW	mem	8086, FPU, SW
FSTSW	reg_ax	286,FPU
FSUB	mem32	
		8086,FPU
FSUB	mem64	8086,FPU
FSUB	fpureg to	8086,FPU
FSUB	fpureg,fpu0	8086,FPU
FSUB	fpureg	8086,FPU
FSUB	fpu0,fpureg	8086,FPU
	ipuo, ipuicg	
FSUB	•	8086, FPU, ND
FSUBP	fpureg	8086, FPU
FSUBP	fpureg,fpu0	8086,FPU
FSUBP		8086, FPU, ND
FSUBR	mem32	8086,FPU
FSUBR	mem64	8086,FPU
		,
FSUBR	fpureg to	8086,FPU
FSUBR	fpureg,fpu0	8086,FPU
FSUBR	fpureg	8086,FPU
FSUBR	fpu0,fpureg	8086,FPU
FSUBR		8086, FPU, ND
	£	
FSUBRP	fpureg	8086,FPU
FSUBRP	fpureg,fpu0	8086,FPU
FSUBRP		8086,FPU,ND
FTST		8086,FPU
FUCOM	fpureg	386,FPU
FUCOM	fpu0,fpureg	386,FPU
	ipuo, ipui eg	•
FUCOM	•	386,FPU,ND
FUCOMI	fpureg	P6,FPU
FUCOMI	fpu0,fpureg	P6,FPU
FUCOMI		P6,FPU,ND
FUCOMIP	fpureg	P6,FPU
	·	,

```
FUCOMIP
                   fpu0, fpureg
                                               P6,FPU
FUCOMIP
                                               P6, FPU, ND
FUCOMP
                                               386,FPU
                   fpureg
                                               386,FPU
FUCOMP
                   fpu0, fpureg
FUCOMP
                                               386, FPU, ND
FUCOMPP
                                               386,FPU
FXAM
                                               8086, FPU
FXCH
                   fpureg
                                               8086, FPU
FXCH
                   fpureg, fpu0
                                               8086, FPU
                                               8086, FPU
FXCH
                   fpu0,fpureg
                                               8086, FPU, ND
FXCH
FXTRACT
                                               8086, FPU
                                               8086, FPU
FYL2X
FYL2XP1
                                               8086, FPU
HLT
                                               8086, PRIV
                                               386, SW, UNDOC, ND, OBSOLETE
TBTS
                  mem, reg16
IBTS
                   reg16, reg16
                                               386, UNDOC, ND, OBSOLETE
IBTS
                                               386, SD, UNDOC, ND, OBSOLETE
                  mem, reg32
                                               386, UNDOC, ND, OBSOLETE
IBTS
                   reg32, reg32
ICEBP
                                               386,ND
                                               8086
TDTV
                   rm8
IDIV
                                               8086
                   rm16
IDIV
                   rm32
                                               386
TDTV
                   rm64
                                               X86_64,LONG
IMUL
                                               8086
                   rm8
IMUL
                   rm16
                                               8086
IMUL
                   rm32
                                               386
IMUL
                   rm64
                                               X86_64,LONG
IMUL
                   reg16, mem
                                               386
IMUL
                   reg16, reg16
                                               386
IMUL
                   reg32,mem
                                               386
IMUL
                   reg32, reg32
                                               386
IMUL
                   reg64, mem
                                               X86_64,LONG
IMUL
                   reg64, reg64
                                               X86_64,LONG
                   reg16,mem,imm8
IMUL
                                               186
IMUL
                                               186.ND
                   reg16, mem, sbyteword
IMUL
                   reg16, mem, imm16
                                               186
IMUL
                   reg16,mem,imm
                                               186,ND
IMUL
                   reg16, reg16, imm8
                                               186
IMUL
                   reg16, reg16, sbyteword
                                               186,ND
IMUL
                   reg16, reg16, imm16
                                               186
IMUL
                   reg16, reg16, imm
                                               186,ND
                   reg32,mem,imm8
IMUL
                                               386
IMUL
                   reg32, mem, sbytedword
                                               386,ND
IMUL
                   reg32, mem, imm32
                                               386
IMUL
                                               386,ND
                   reg32, mem, imm
IMUL
                   reg32, reg32, imm8
                                               386
IMUL
                   reg32, reg32, sbytedword
                                               386,ND
IMUL
                   reg32,reg32,imm32
                                               386
                   reg32,reg32,imm
IMUL
                                               386,ND
                   reg64,mem,imm8
                                               X86_64,LONG
TMUI
IMUL
                   reg64, mem, sbytedword
                                               X86_64, LONG, ND
IMUL
                   reg64, mem, imm32
                                               X86_64,LONG
                                               X86_64,LONG,ND
IMUL
                   reg64, mem, imm
IMUL
                                               X86_64,LONG
                   reg64, reg64, imm8
IMUL
                   reg64, reg64, sbytedword
                                               X86_64, LONG, ND
IMUL
                   reg64, reg64, imm32
                                               X86_64,LONG
IMUL
                   reg64, reg64, imm
                                               X86_64, LONG, ND
IMUL
                   reg16,imm8
                                               186
                   reg16,sbyteword
IMUL
                                               186,ND
IMUL
                   reg16,imm16
                                               186
IMUL
                                               186,ND
                   reg16,imm
IMUL
                   reg32,imm8
                                               386
IMUL
                   reg32, sbytedword
                                               386,ND
TMUI
                   reg32,imm32
                                               386
IMUL
                   reg32,imm
                                               386,ND
IMUL
                   reg64, imm8
                                               X86_64,LONG
```

IMUL	reg64,sbytedword	X86_64,LONG,ND
IMUL	reg64,imm32	X86_64,LONG
IMUL	reg64,imm	X86_64,LONG,ND
	0 ,	
IN	reg_al,imm	8086
IN	reg_ax,imm	8086
IN	reg_eax,imm	386
IN	reg_al,reg_dx	8086
IN	reg_ax,reg_dx	8086
IN	reg_eax,reg_dx	386
INC	reg16	8086,NOLONG
INC	reg32	386,NOLONG
INC	rm8	8086,LOCK
		•
INC	rm16	8086,LOCK
INC	rm32	386,LOCK
INC	rm64	X86_64,LONG,LOCK
INSB		186
INSD		386
INSW		186
INT	imm	8086
INT01		386,ND
INT1		386
INT03		8086,ND
		•
INT3		8086
INTO		8086,NOLONG
INVD		486,PRIV
INVPCID	reg32,mem128	INVPCID, PRIV, NOLONG
INVPCID	reg64,mem128	INVPCID, PRIV, LONG
	• ,	, ,
INVLPG	mem	486,PRIV
INVLPGA	reg_ax,reg_ecx	X86_64,AMD,NOLONG
INVLPGA	reg_eax,reg_ecx	X86_64,AMD
INVLPGA	reg_rax,reg_ecx	X86_64,LONG,AMD
	reg_rux,reg_eex	
INVLPGA		X86_64,AMD
IRET		8086
IRETD		386
IRETQ		X86_64,LONG
IRETW		8086
	-i mm	
JCXZ	imm	8086, NOLONG
JECXZ	imm	386
JRCXZ	imm	X86_64,LONG
JMP	imm short	8086
JMP	imm	8086,ND
		,
JMP	imm	8086,BND
JMP	imm near	8086,ND,BND
JMP	imm far	8086,ND,NOLONG
JMP	imm16	8086, NOLONG, BND
JMP	imm16 near	8086,ND,NOLONG,BND
JMP	imm16 far	8086, ND, NOLONG
JMP	imm32	386,NOLONG,BND
JMP	imm32 near	386,ND,NOLONG,BND
JMP	imm32 far	386,ND,NOLONG
JMP	imm64	X86_64,LONG,BND
JMP	imm64 near	X86_64,LONG,ND,BND
JMP	imm:imm	8086,NOLONG
JMP	imm16:imm	8086,NOLONG
JMP	imm:imm16	8086, NOLONG
	imm32:imm	386,NOLONG
JMP		,
JMP	imm:imm32	386,NOLONG
JMP	mem far	8086,NOLONG
JMP	mem far	X86_64,LONG
JMP	mem16 far	8086
	mem32 far	
JMP		386
JMP	mem64 far	X86_64,LONG
JMP	mem near	8086,ND,BND
JMP	rm16 near	8086, NOLONG, ND, BND
JMP	rm32 near	386, NOLONG, ND, BND
	•	
JMP	rm64 near	X86_64,LONG,ND,BND
JMP	mem	8086,BND

```
JMP
                   rm16
                                               8086, NOLONG, BND
ПМР
                   rm32
                                               386, NOLONG, BND
JMP
                   rm64
                                               X86_64,LONG,BND
JMPE
                   imm
                                               IA64
JMPE
                   imm16
                                               IA64
JMPE
                   imm32
                                               IA64
JMPE
                                               IA64
                   rm16
JMPE
                   rm32
                                               IA64
LAHF
                                               8086
                                               286, PROT, SW
LAR
                   reg16,mem
LAR
                   reg16, reg16
                                               286, PROT
LAR
                   reg16, reg32
                                               386, PROT
LAR
                   reg16,reg64
                                               X86_64, LONG, PROT, ND
LAR
                                               386, PROT, SW
                   reg32,mem
LAR
                   reg32, reg16
                                               386, PROT
                   reg32,reg32
                                               386,PROT
IAR
LAR
                   reg32, reg64
                                               X86_64, LONG, PROT, ND
LAR
                   reg64,mem
                                               X86_64, LONG, PROT, SW
LAR
                   reg64, reg16
                                               X86_64, LONG, PROT
LAR
                   reg64, reg32
                                               X86_64, LONG, PROT
LAR
                   reg64, reg64
                                               X86_64, LONG, PROT
LDS
                   reg16,mem
                                               8086, NOLONG
LDS
                   reg32,mem
                                               386, NOLONG
LEA
                                               8086, ANYSIZE
                   reg16,mem
                                               386, ANYSIZE
LEA
                   reg32,mem
LEA
                   reg64, mem
                                               X86_64, LONG, ANYSIZE
LEA
                   reg16,imm
                                               8086, ND, ANYSIZE
LEA
                                               386,ND,ANYSIZE
                   reg32, imm
LEA
                   reg64, imm
                                               X86_64, LONG, ND, ANYSIZE
LEAVE
                                               186
LES
                   reg16, mem
                                               8086, NOLONG
LES
                                               386, NOLONG
                   reg32,mem
LFENCE
                                               X86_64, LONG, AMD
LFS
                   reg16,mem
                                               386
LFS
                   reg32,mem
                                               386
                   reg64,mem
                                               X86_64,LONG
LFS
                                               286, PRIV
LGDT
                   mem
LGS
                   reg16,mem
                                               386
LGS
                   reg32, mem
                                               386
                                               X86_64,LONG
LGS
                   reg64, mem
LIDT
                                               286, PRIV
                   mem
LLDT
                   mem
                                               286, PROT, PRIV
                                               286, PROT, PRIV
LLDT
                   mem16
LLDT
                                               286, PROT, PRIV
                   reg16
LMSW
                   mem
                                               286, PRIV
LMSW
                                               286, PRIV
                   mem16
                                               286,PRIV
LMSW
                   reg16
                                               386, UNDOC, ND, OBSOLETE
LOADALL
LOADALL286
                                               286, UNDOC, ND, OBSOLETE
LODSB
                                               8086
LODSD
                                               386
LODS0
                                               X86_64,LONG
LODSW
                                               8086
L00P
                   imm
                                               8086
L00P
                   imm, reg_cx
                                               8086, NOLONG
L00P
                   imm,reg_ecx
                                               386
L00P
                   imm,reg_rcx
                                               X86_64,LONG
L00PE
                   imm
                                               8086
L00PE
                   imm,reg_cx
                                               8086, NOLONG
L00PE
                                               386
                   imm,reg_ecx
L00PE
                                               X86_64,LONG
                   imm,reg_rcx
LOOPNE
                   imm
                                               8086
LOOPNE
                   imm,reg_cx
                                               8086, NOLONG
LOOPNE
                   imm,reg_ecx
                                               386
LOOPNE
                   imm,reg_rcx
                                               X86_64,LONG
L00PNZ
                   imm
                                               8086
L00PNZ
                   imm, reg_cx
                                               8086, NOLONG
```

LOOPNZ	imm,reg_ecx	386
LOOPNZ	imm,reg_rcx	X86_64,LONG
	imm	•
LOOPZ		8086
L00PZ	imm,reg_cx	8086,NOLONG
L00PZ	imm,reg_ecx	386
L00PZ	imm,reg_rcx	X86_64,LONG
LSL	reg16,mem	286,PROT,SW
LSL	reg16,reg16	286,PROT
LSL	reg16,reg32	386,PROT
LSL	reg16,reg64	X86_64, LONG, PROT, ND
LSL	reg32,mem	386, PROT, SW
LSL		
	reg32,reg16	386,PROT
LSL	reg32,reg32	386,PROT
LSL	reg32,reg64	X86_64,LONG,PROT,ND
LSL	reg64,mem	X86_64,LONG,PROT,SW
LSL	reg64,reg16	X86_64,LONG,PROT
LSL	reg64,reg32	X86_64,LONG,PROT
LSL	reg64,reg64	X86_64,LONG,PROT
LSS	reg16,mem	386
LSS	reg32,mem	386
LSS	reg64,mem	X86_64,LONG
	<u> </u>	
LTR	mem	286,PROT,PRIV
LTR	mem16	286,PROT,PRIV
LTR	reg16	286,PROT,PRIV
MFENCE	S .	X86_64,LONG,AMD
MONITOR		PRESCOTT
MONITOR	reg_eax,reg_ecx,reg_edx	PRESCOTT, NOLONG, ND
MONITOR	reg_rax,reg_ecx,reg_edx	X86_64,LONG,ND
MONITORX		AMD
MONITORX	reg_rax,reg_ecx,reg_edx	X86_64,LONG,AMD,ND
MONITORX	reg_eax,reg_ecx,reg_edx	AMD, ND
MONITORX	reg_ax,reg_ecx,reg_edx	AMD,ND
MOV	mem,reg_sreg	8086,SW
MOV	reg16,reg_sreg	8086
MOV		
	reg32,reg_sreg	386
MOV	reg64,reg_sreg	X86_64,LONG,OPT,ND
MOV	rm64,reg_sreg	X86_64,LONG
MOV	reg_sreg,mem	8086,SW
MOV	reg_sreg,reg16	8086,OPT,ND
MOV	reg_sreg,reg32	386,0PT,ND
MOV	reg_sreg,reg64	X86_64,LONG,OPT,ND
MOV	reg_sreg,reg16	8086
MOV	reg_sreg,reg32	386
MOV	reg_sreg,rm64	X86_64,LONG
MOV	reg_al,mem_offs	8086
MOV	reg_ax,mem_offs	8086
MOV	reg_eax,mem_offs	386
MOV	reg_rax,mem_offs	X86_64,LONG
MOV	mem_offs,reg_al	8086,NOHLE
	, ,	•
MOV	mem_offs,reg_ax	8086,NOHLE
MOV	mem_offs,reg_eax	386,NOHLE
MOV	<pre>mem_offs,reg_rax</pre>	X86_64,LONG,NOHLE
MOV	reg32,reg_creg	386, PRIV, NOLONG
MOV	reg64,reg_creg	X86_64,LONG,PRIV
MOV	reg_creg,reg32	386,PRIV,NOLONG
MOV	reg_creg,reg64	X86_64,LONG,PRIV
MOV	reg32,reg_dreg	386, PRIV, NOLONG
MOV	reg64,reg_dreg	X86_64,LONG,PRIV
	- ,	386, PRIV, NOLONG
MOV	reg_dreg,reg32	
MOV	reg_dreg,reg64	X86_64,LONG,PRIV
MOV	reg32,reg_treg	386,NOLONG,ND
MOV	reg_treg,reg32	386,NOLONG,ND
MOV	mem,reg8	8086
MOV	reg8,reg8	8086
MOV	mem,reg16	8086
MOV	reg16,reg16	8086
MOV	mem,reg32	386

```
MOV
                   reg32, reg32
                                               386
MOV
                                               X86_64,LONG
                  mem, reg64
MOV
                   reg64, reg64
                                               X86_64, LONG
MOV
                   reg8, mem
                                               8086
MOV
                                               8086
                   reg8, reg8
MOV
                   reg16,mem
                                               8086
MOV
                                              8086
                   reg16, reg16
MOV
                                              386
                   reg32,mem
MOV
                   reg32, reg32
                                               386
MOV
                                               X86_64,LONG
                   reg64,mem
MOV
                   reg64, reg64
                                               X86_64,LONG
MOV
                   reg8, imm
                                               8086
MOV
                   reg16,imm
                                              8086
                   reg32,imm
MOV
                                               386
MOV
                   reg64,udword
                                               X86_64,LONG,OPT,ND
MOV
                   reg64,sdword
                                               X86_64, LONG, OPT, ND
MOV
                   reg64, imm
                                               X86_64, LONG
                   rm8,imm
MOV
                                               8086
                   rm16,imm
MOV
                                              8086
MOV
                   rm32, imm
                                               386
MOV
                   rm64,imm
                                               X86_64,LONG
                   rm64,imm32
MOV
                                               X86_64,LONG
MOV
                  mem,imm8
                                               8086
MOV
                  mem, imm16
                                              8086
MOV
                  mem,imm32
                                              386
                                               PENT, MMX, SD
MOVD
                  mmxreg,rm32
                                               PENT, MMX, SD
MOVD
                   rm32,mmxreg
MOVD
                  mmxreg,rm64
                                               X86 64, LONG, MMX, SX, ND
MOVD
                  rm64,mmxreg
                                               X86_64, LONG, MMX, SX, ND
MOVQ
                  mmxreg, mmxrm
                                               PENT, MMX
MOVQ
                  mmxrm, mmxreg
                                               PENT, MMX
                                               X86_64, LONG, MMX
MOVO
                  mmxreg,rm64
MOVO
                   rm64,mmxreg
                                               X86_64, LONG, MMX
MOVSB
                                               8086
MOVSD
                                              386
MOVSO
                                               X86_64,LONG
MOVSW
                                               8086
MOVSX
                                               386
                   reg16,mem
MOVSX
                   reg16, reg8
                                               386
MOVSX
                   reg32, rm8
                                              386
MOVSX
                   reg32, rm16
                                              386
MOVSX
                   reg64, rm8
                                               X86_64,LONG
                                               X86_64,LONG
                   reg64, rm16
MOVSX
MOVSXD
                   reg64,rm32
                                               X86_64, LONG
MOVSX
                   reg64, rm32
                                               X86_64, LONG, ND
MOVZX
                   reg16,mem
                                              386
MOVZX
                   reg16, reg8
                                               386
MOVZX
                   reg32,rm8
                                               386
MOVZX
                   reg32,rm16
                                               386
MOVZX
                   reg64, rm8
                                               X86_64,LONG
MOVZX
                   reg64, rm16
                                               X86_64,LONG
MUL
                   rm8
                                              8086
MUL
                   rm16
                                               8086
MUL
                   rm32
                                               386
MUL
                   rm64
                                               X86_64,LONG
MWAIT
                                               PRESCOTT
                                               PRESCOTT, ND
MWAIT
                   reg_eax,reg_ecx
MWAITX
                                               AMD
                                               AMD,ND
MWAITX
                   reg_eax, reg_ecx
NEG
                                               8086, LOCK
                   rm8
NEG
                   rm16
                                               8086, LOCK
NEG
                   rm32
                                               386,LOCK
NEG
                   rm64
                                               X86_64, LONG, LOCK
NOP
                                               8086
NOP
                   rm16
                                              Р6
NOP
                   rm32
                                               Р6
                                               X86_64,LONG
NOP
                   rm64
```

```
NOT
                   rm8
                                              8086, LOCK
NOT
                  rm16
                                              8086, LOCK
NOT
                                              386,LOCK
                  rm32
                                              X86_64,LONG,LOCK
NOT
                   rm64
OR
                  mem, reg8
                                              8086, LOCK
OR
                  reg8, reg8
                                              8086
                                              8086, LOCK
OR
                  mem, reg16
OR
                                              8086
                  reg16, reg16
OR
                  mem, reg32
                                              386,LOCK
OR
                  reg32, reg32
                                              386
OR
                                              X86_64,LONG,LOCK
                  mem, reg64
OR
                  reg64, reg64
                                              X86_64,LONG
OR
                  reg8, mem
                                              8086
OR
                                              8086
                  reg8, reg8
OR
                   reg16,mem
                                              8086
                                              8086
ΟR
                  reg16, reg16
OR
                                              386
                  reg32,mem
OR
                   reg32, reg32
                                              386
                                              X86_64,LONG
OR
                  reg64,mem
OR
                   reg64, reg64
                                              X86_64,LONG
OR
                   rm16,imm8
                                              8086, LOCK
OR
                   rm32,imm8
                                              386,LOCK
OR
                   rm64,imm8
                                              X86_64, LONG, LOCK
                  reg_al,imm
ΟR
                                              8086
                                              8086,ND
OR
                  reg_ax,sbyteword
OR
                   reg_ax,imm
                                              8086
                   reg_eax,sbytedword
OR
                                              386,ND
                   reg_eax,imm
OR
                                              386
OR
                  reg_rax,sbytedword
                                              X86_64,LONG,ND
OR
                                              X86_64,LONG
                  reg_rax,imm
OR
                  rm8, imm
                                              8086, LOCK
                                              8086, LOCK, ND
OR
                   rm16, sbyteword
OR
                   rm16,imm
                                              8086, LOCK
OR
                  rm32, sbytedword
                                              386, LOCK, ND
                  rm32,imm
OR
                                              386,LOCK
                                              X86_64, LONG, LOCK, ND
OR
                  rm64, sbytedword
OR
                   rm64,imm
                                              X86_64,LONG,LOCK
OR
                  mem,imm8
                                              8086,LOCK
OR
                  mem, sbyteword16
                                              8086, LOCK, ND
OR
                  mem, imm16
                                              8086, LOCK
OR
                  mem, sbytedword32
                                              386, LOCK, ND
OR
                  mem,imm32
                                              386,LOCK
                                              8086, LOCK, ND, NOLONG
OR
                  rm8,imm
OUT
                   imm, reg_al
                                              8086
OUT
                   imm, reg_ax
                                              8086
                   imm, reg_eax
                                              386
OUT
OUT
                  reg_dx,reg_al
                                              8086
OUT
                  reg_dx,reg_ax
                                              8086
OUT
                  reg_dx,reg_eax
                                              386
OUTSB
                                              186
OUTSD
                                              386
OUTSW
                                              186
PACKSSDW
                                              PENT, MMX
                  mmxreg,mmxrm
PACKSSWB
                                              PENT, MMX
                  mmxreg,mmxrm
PACKUSWB
                  mmxreg,mmxrm
                                              PENT, MMX
PADDB
                  mmxreg,mmxrm
                                              PENT, MMX
PADDD
                                              PENT, MMX
                  mmxreg, mmxrm
PADDSB
                  mmxreg,mmxrm
                                              PENT, MMX
                                              PENT, MMX, CYRIX
PADDSIW
                  mmxreg, mmxrm
PADDSW
                                              PENT, MMX
                  mmxreg, mmxrm
PADDUSB
                                              PENT, MMX
                  mmxreg, mmxrm
                                              PENT, MMX
PADDUSW
                  mmxreg, mmxrm
PADDW
                  mmxreg, mmxrm
                                              PENT, MMX
PAND
                                              PENT, MMX
                  mmxreg,mmxrm
PANDN
                                              PENT, MMX
                  mmxreg, mmxrm
PAUSE
                                              8086
PAVEB
                  mmxreg, mmxrm
                                              PENT, MMX, CYRIX
```

DAVIGUED		DENT ORNOLI
PAVGUSB	mmxreg,mmxrm	PENT, 3DNOW
PCMPEQB	mmxreg,mmxrm	PENT,MMX
PCMPEQD	mmxreg,mmxrm	PENT, MMX
PCMPEQW	mmxreg,mmxrm	PENT, MMX
PCMPGTB	mmxreg,mmxrm	PENT, MMX
PCMPGTD	mmxreg,mmxrm	PENT, MMX
PCMPGTW	mmxreg, mmxrm	PENT, MMX
PDISTIB	mmxreg, mem	PENT, MMX, CYRIX
PF2ID	mmxreg,mmxrm	PENT, 3DNÓW
PFACC	mmxreg,mmxrm	PENT, 3DNOW
PFADD	mmxreg,mmxrm	PENT,3DNOW
PFCMPEQ	mmxreg,mmxrm	PENT,3DNOW
PFCMPGE	= :	•
PFCMPGT	mmxreg,mmxrm	PENT, 3DNOW
	mmxreg,mmxrm	PENT, 3DNOW
PFMAX	mmxreg,mmxrm	PENT, 3DNOW
PFMIN	mmxreg,mmxrm	PENT, 3DNOW
PFMUL	mmxreg,mmxrm	PENT,3DNOW
PFRCP	mmxreg,mmxrm	PENT,3DNOW
PFRCPIT1	mmxreg,mmxrm	PENT,3DNOW
PFRCPIT2	mmxreg,mmxrm	PENT,3DNOW
PFRSQIT1	mmxreg,mmxrm	PENT,3DNOW
PFRSQRT	mmxreg, mmxrm	PENT, 3DNOW
PFSUB	mmxreg,mmxrm	PENT, 3DNOW
PFSUBR	mmxreg,mmxrm	PENT, 3DNOW
PI2FD	mmxreg,mmxrm	PENT,3DNOW
PMACHRIW	mmxreg,mem	PENT, MMX, CYRIX
PMADDWD		PENT, MMX
PMAGW	mmxreg,mmxrm	PENT, MMX, CYRIX
PMULHRIW	mmxreg,mmxrm	PENT, MMX, CYRIX
	mmxreg,mmxrm	, ,
PMULHRWA	mmxreg,mmxrm	PENT, 3DNOW
PMULHRWC	mmxreg,mmxrm	PENT, MMX, CYRIX
PMULHW	mmxreg,mmxrm	PENT, MMX
PMULLW	mmxreg,mmxrm	PENT, MMX
PMVGEZB	mmxreg,mem	PENT, MMX, CYRIX
PMVLZB	mmxreg,mem	PENT, MMX, CYRIX
PMVNZB	mmxreg,mem	PENT,MMX,CYRIX
PMVZB	mmxreg,mem	PENT, MMX, CYRIX
POP	reg16	8086
POP	reg32	386,NOLONG
POP	reg64	X86_64,LONG
POP	rm16	8086
POP	rm32	386,NOLONG
POP	rm64	X86_64,LONG
POP	reg_es	8086, NÓLONG
POP	reg_cs	8086,UNDOC,ND,OBSOLETE
POP	reg_ss	8086,NOLONG
POP	reg_ds	8086,NOLONG
POP	reg_fs	386
POP	reg_gs	386
POPA	1 08_83	186,NOLONG
POPAD		•
		386, NOLONG
POPAW		186,NOLONG
POPF		8086
POPFD		386, NOLONG
POPFQ		X86_64,LONG
POPFW		8086
POR	mmxreg,mmxrm	PENT, MMX
PREFETCH	mem	PENT, 3DNOW
PREFETCHW	mem	PENT,3DNOW
PSLLD	mmxreg,mmxrm	PENT, MMX
PSLLD	mmxreg,imm	PENT, MMX
PSLLQ	mmxreg,mmxrm	PENT, MMX
PSLLQ	mmxreg,imm	PENT, MMX
PSLLW	mmxreg,mmxrm	PENT, MMX
PSLLW	mmxreg,imm	PENT, MMX
PSRAD	mmxreg,mmxrm	PENT, MMX
PSRAD	mmxreg,imm	PENT, MMX

```
PSRAW
                   mmxreg,mmxrm
                                               PENT, MMX
PSRAW
                                               PENT, MMX
                  mmxreg, imm
PSRLD
                                               PENT, MMX
                  mmxreg, mmxrm
PSRLD
                  mmxreg, imm
                                              PENT, MMX
                  mmxreg,mmxrm
PSRLQ
                                               PENT, MMX
PSRLQ
                  mmxreg, imm
                                               PENT, MMX
                                               PENT, MMX
PSRLW
                  mmxreg, mmxrm
PSRLW
                                               PENT, MMX
                  mmxreg, imm
PSUBB
                  mmxreg,mmxrm
                                               PENT, MMX
PSUBD
                                               PENT, MMX
                  mmxreg,mmxrm
PSUBSB
                                               PENT, MMX
                  mmxreg,mmxrm
                                               PENT, MMX, CYRIX
PSUBSIW
                  mmxreg,mmxrm
PSUBSW
                                               PENT, MMX
                  mmxreg, mmxrm
PSUBUSB
                  mmxreg, mmxrm
                                               PENT, MMX
PSUBUSW
                  mmxreg, mmxrm
                                               PENT, MMX
PSUBW
                                               PENT, MMX
                  mmxreg, mmxrm
PUNPCKHBW
                                               PENT, MMX
                  mmxreg,mmxrm
                                               PENT, MMX
PUNPCKHDQ
                  mmxreg, mmxrm
                                               PENT, MMX
PUNPCKHWD
                  mmxreg, mmxrm
PUNPCKLBW
                  mmxreg,mmxrm
                                               PENT, MMX
PUNPCKLDQ
                                               PENT, MMX
                  mmxreg, mmxrm
PUNPCKLWD
                  mmxreg, mmxrm
                                               PENT, MMX
PUSH
                   reg16
                                               8086
PUSH
                                               386, NOLONG
                   reg32
PUSH
                                               X86_64,LONG
                   reg64
PUSH
                   rm16
                                               8086
PUSH
                   rm32
                                               386,NOLONG
PUSH
                   rm64
                                               X86 64,LONG
PUSH
                   reg_es
                                               8086, NOLONG
                                               8086, NOLONG
PUSH
                   reg_cs
PUSH
                   reg_ss
                                               8086, NOLONG
PUSH
                                               8086, NOLONG
                   reg_ds
PUSH
                                               386
                   reg_fs
PUSH
                   reg_gs
                                               386
PUSH
                   imm8
                                               186
PUSH
                                               186, ARO, SIZE, ND
                   sbyteword16
PUSH
                   imm16
                                               186,AR0,SIZE
PUSH
                   sbytedword32
                                               386, NOLONG, ARO, SIZE, ND
PUSH
                   imm32
                                               386, NOLONG, ARO, SIZE
PUSH
                   sbytedword32
                                               386, NOLONG, SD, ND
PUSH
                   imm32
                                               386, NOLONG, SD
PUSH
                   sbytedword64
                                               X86_64, LONG, ARO, SIZE, ND
PUSH
                                               X86_64,LONG,AR0,SIZE
                   imm64
PUSH
                   sbytedword32
                                               X86_64, LONG, ARO, SIZE, ND
PUSH
                   imm32
                                               X86_64, LONG, AR0, SIZE
PUSHA
                                               186, NOLONG
                                               386, NOLONG
PUSHAD
PUSHAW
                                               186, NOLONG
PUSHF
                                               8086
PUSHFD
                                               386, NOLONG
PUSHFQ
                                               X86_64,LONG
PUSHFW
                                               8086
PXOR
                                               PENT, MMX
                   mmxreg, mmxrm
RCI
                   rm8,unity
                                               8086
RCL
                   rm8, reg_cl
                                               8086
RCL
                   rm8, imm8
                                               186
                   rm16, unity
                                              8086
RCL
RCL
                   rm16, reg_cl
                                               8086
RCL
                   rm16,imm8
                                              186
RCL
                   rm32, unity
                                               386
                   rm32,reg_cl
RCL
                                               386
                   rm32,imm8
RCL
                                               386
RCL
                   rm64, unity
                                               X86_64,LONG
RCL
                   rm64, reg_cl
                                               X86_64,LONG
RCL
                   rm64,imm8
                                               X86_64,LONG
RCR
                   rm8, unity
                                               8086
RCR
                   rm8, reg_cl
                                               8086
```

```
RCR
                   rm8, imm8
                                               186
RCR
                                               8086
                   rm16,unity
RCR
                   rm16,reg_cl
                                               8086
RCR
                   rm16,imm8
                                               186
                                               386
RCR
                   rm32,unity
                  rm32,reg_cl
rm32,imm8
RCR
                                               386
                                               386
RCR
RCR
                   rm64, unity
                                               X86_64,LONG
RCR
                   rm64, reg_cl
                                               X86_64,LONG
                                               X86_64,LONG
RCR
                   rm64,imm8
                                               P6,CYRIX,SMM
RDSHR
                   rm32
                                               PENT, PRIV
RDMSR
RDPMC
                                               Р6
RDTSC
                                               PENT
RDTSCP
                                               X86_64
                                               8086,BND
RET
RET
                   imm
                                               8086, SW, BND
RETF
                                               8086
                                               8086,SW
RETF
                   imm
RETN
                                               8086, BND
                                               8086, SW, BND
RETN
                   imm
RETW
                                               8086,BND
RETW
                   imm
                                               8086, SW, BND
RETFW
                                               8086
RETFW
                                               8086,SW
                   imm
                                               8086,BND
RETNW
RETNW
                   imm
                                               8086, SW, BND
RETD
                                               8086, BND, NOLONG
                                               8086, SW, BND, NOLONG
RETD
                   imm
RETFD
                                               8086
RETFD
                   imm
                                               8086,SW
                                               8086, BND, NOLONG
RETND
RETND
                   imm
                                               8086, SW, BND, NOLONG
RETQ
                                               X86_64, LONG, BND
RETQ
                                               X86_64, LONG, SW, BND
                   imm
                                               X86 64.LONG
RETF0
                                               X86_64,LONG,SW
RETFQ
                   imm
                                               X86_64,LONG,BND
RETNQ
RETNQ
                   imm
                                               X86_64, LONG, SW, BND
ROL
                   rm8, unity
                                               8086
ROL
                   rm8, reg_cl
                                               8086
ROL
                   rm8,imm8
                                               186
                                               8086
ROL
                   rm16,unity
ROL
                   rm16,reg_cl
                                               8086
                   rm16,imm8
ROL
                                               186
                                               386
ROL
                  rm32, unity
ROL
                   rm32, reg_cl
                                               386
ROL
                   rm32,imm8
                                               386
ROL
                   rm64,unity
                                               X86_64,LONG
ROL
                   rm64, reg_cl
                                               X86_64,LONG
ROL
                   rm64,imm8
                                               X86_64,LONG
ROR
                   rm8,unity
                                               8086
ROR
                   rm8,reg_cl
                                               8086
ROR
                                               186
                   rm8,imm8
ROR
                                               8086
                   rm16, unity
ROR
                   rm16, reg_cl
                                               8086
ROR
                                               186
                  rm16,imm8
ROR
                   rm32,unity
                                               386
ROR
                   rm32,reg_cl
                                               386
ROR
                   rm32,imm8
                                               386
ROR
                   rm64, unity
                                               X86_64,LONG
ROR
                                               X86_64,LONG
                   rm64,reg_cl
                                               X86_64, LONG
ROR
                   rm64,imm8
RDM
                                               P6, CYRIX, ND
RSDC
                   reg_sreg,mem80
                                               486, CYRIX, SMM
RSLDT
                  mem80
                                               486, CYRIX, SMM
RSM
                                               PENT, SMM
```

RSTS	mem80	486,CYRIX,SMM
SAHF		8086
SAL	rm8,unity	8086,ND
SAL	rm8,reg_cl	8086,ND
	, •	
SAL	rm8,imm8	186,ND
SAL	rm16,unity	8086,ND
SAL	rm16,reg_cl	8086,ND
SAL	rm16,imm8	186,ND
SAL	rm32,unity	386,ND
SAL	rm32,reg_cl	386,ND
SAL	, ,	-
	rm32,imm8	386,ND
SAL	rm64,unity_	X86_64,LONG,ND
SAL	rm64,reg_cl	X86_64,LONG,ND
SAL	rm64,imm8	X86_64,LONG,ND
SALC		8086,UNDOC
SAR	rm8,unity	8086
SAR	rm8,reg_cl	8086
	, ,	
SAR	rm8,imm8	186
SAR	rm16,unity	8086
SAR	rm16,reg_cl	8086
SAR	rm16,imm8	186
SAR	rm32,unity	386
SAR	rm32,reg_cl	386
	, ,	
SAR	rm32,imm8	386
SAR	rm64,unity_	X86_64,LONG
SAR	rm64,reg_cl	X86_64,LONG
SAR	rm64,imm8	X86_64,LONG
SBB	mem,reg8	8086,LOCK
SBB	reg8,reg8	8086
SBB	mem,reg16	8086,LOCK
	, ,	
SBB	reg16,reg16	8086
SBB	mem,reg32	386,LOCK
SBB	reg32,reg32	386
SBB	mem,reg64	X86_64,LONG,LOCK
SBB	reg64, reg64	X86_64,LONG
SBB	reg8,mem	8086
SBB	reg8,reg8	8086
SBB	reg16,mem	8086
SBB	reg16,reg16	8086
SBB	reg32,mem	386
SBB	reg32,reg32	386
SBB	reg64,mem	X86_64,LONG
SBB	reg64, reg64	X86_64,LONG
	- , -	-
SBB	rm16,imm8	8086,LOCK
SBB	rm32,imm8	386,LOCK
SBB	rm64,imm8	X86_64,LONG,LOCK
SBB	reg_al,imm	8086
SBB	reg_ax,sbyteword	8086,ND
SBB	reg_ax,imm	8086
SBB	reg_eax,sbytedword	386,ND
SBB	reg_eax,imm	386
SBB	reg_rax,sbytedword	X86_64,LONG,ND
SBB	reg_rax,imm	X86_64,LONG
SBB	rm8,imm	8086,LOCK
SBB	rm16,sbyteword	8086,LOCK,ND
SBB	rm16,imm	8086,LOCK
SBB	rm32,sbytedword	386,LOCK,ND
	rm32,imm	
SBB		386,LOCK
SBB	rm64,sbytedword	X86_64,LONG,LOCK,ND
SBB	rm64,imm	X86_64,LONG,LOCK
SBB	mem,imm8	8086,LOCK
SBB	mem, sbyteword16	8086,LOCK,ND
SBB	mem,imm16	8086,LOCK
SBB	mem,sbytedword32	386,LOCK,ND
SBB	mem,imm32	386,LOCK
SBB	rm8,imm	8086, LOCK, ND, NOLONG
SCASB		8086

```
SCASD
                                               386
SCASQ
                                               X86_64,LONG
SCASW
                                               8086
                                               X86_64,LONG,AMD
SFENCE
SGDT
                                               286
                  mem
SHL
                   rm8,unity
                                               8086
SHL
                   rm8,reg_cl
                                              8086
SHL
                   rm8,imm8
                                              186
SHL
                   rm16, unity
                                               8086
                                               8086
SHI
                   rm16,reg_cl
SHL
                   rm16,imm8
                                               186
SHL
                   rm32, unity
                                               386
SHL
                   rm32, reg_cl
                                              386
SHL
                   rm32,imm8
                                               386
SHL
                   rm64, unity
                                               X86_64,LONG
SHI
                                               X86_64,LONG
                   rm64,reg_cl
SHL
                   rm64,imm8
                                               X86_64, LONG
SHLD
                  mem, reg16, imm
                                               386
SHLD
                  reg16, reg16, imm
                                              386
SHLD
                  mem, reg32, imm
                                               386
SHLD
                   reg32, reg32, imm
                                               386
                                               X86_64,LONG
SHLD
                  mem, reg64, imm
SHLD
                   reg64, reg64, imm
                                               X86_64,LONG
SHLD
                  mem, reg16, reg_cl
                                              386
SHLD
                                               386
                   reg16, reg16, reg_cl
SHLD
                  mem, reg32, reg_cl
                                               386
SHLD
                   reg32, reg32, reg_cl
                                               386
SHLD
                  mem, reg64, reg_cl
                                               X86 64,LONG
                                              X86_64,LONG
SHLD
                   reg64, reg64, reg_cl
SHR
                   rm8,unity
                                               8086
SHR
                   rm8, reg_cl
                                               8086
                                               186
SHR
                   rm8, imm8
SHR
                   rm16,unity
                                               8086
SHR
                   rm16, reg_cl
                                              8086
                   rm16,imm8
SHR
                                              186
SHR
                   rm32, unity
                                               386
SHR
                   rm32,reg_cl
                                               386
SHR
                   rm32,imm8
                                               386
SHR
                   rm64, unity
                                               X86_64,LONG
SHR
                                               X86_64,LONG
                   rm64, reg_cl
SHR
                                               X86_64,LONG
                   rm64,imm8
SHRD
                   mem, reg16, imm
                                               386
SHRD
                   reg16, reg16, imm
                                               386
SHRD
                                               386
                  mem, reg32, imm
SHRD
                   reg32, reg32, imm
                                               386
SHRD
                  mem, reg64, imm
                                               X86_64,LONG
SHRD
                   reg64, reg64, imm
                                               X86_64, LONG
SHRD
                  mem, reg16, reg_cl
                                               386
SHRD
                   reg16,reg_cl
                                               386
                  mem,reg32,reg_cl
SHRD
                                               386
SHRD
                   reg32, reg32, reg_cl
                                               386
SHRD
                  mem, reg64, reg_cl
                                               X86 64,LONG
SHRD
                   reg64, reg64, reg_cl
                                               X86_64,LONG
SIDT
                  mem
                                               286
SLDT
                  mem
                                               286
SLDT
                  mem16
                                               286
                                               286
SLDT
                   reg16
SLDT
                   reg32
                                               386
                                               X86_64,LONG,ND
SLDT
                   reg64
SLDT
                   reg64
                                               X86_64,LONG
SKINIT
                                               X86_64,LONG
SMI
                                               386, UNDOC
SMINT
                                               P6,CYRIX,ND
SMINTOLD
                                               486, CYRIX, ND, OBSOLETE
SMSW
                                               286
                  mem
SMSW
                  mem16
                                               286
```

SMSW

reg16

286

SMSW	r0g22	386
SMSW	reg32	
	reg64	X86_64,LONG
STC		8086
STD		8086
STI		8086
STOSB		8086
STOSD		386
STOSQ		X86_64,LONG
STOSW		8086
STR	mem	286,PROT
STR	mem16	286,PROT
STR	reg16	286,PROT
STR	reg32	386, PROT
STR	reg64	X86_64,LONG
SUB SUB	mem,reg8	8086,LOCK 8086
SUB	reg8, reg8	8086,LOCK
SUB	mem,reg16	8086
SUB	reg16, reg16	386,LOCK
SUB	mem,reg32	386
SUB	reg32,reg32 mem,reg64	X86_64,LONG,LOCK
SUB	reg64,reg64	X86_64,LONG
SUB	reg8,mem	8086
SUB	reg8,reg8	8086
SUB		8086
SUB	reg16,mem reg16,reg16	8086
SUB	reg32,mem	386
SUB	reg32,reg32	386
SUB	reg64,mem	X86_64,LONG
SUB	reg64,reg64	X86_64,LONG
SUB	rm16,imm8	8086,LOCK
SUB	rm32,imm8	386,LOCK
SUB	rm64,imm8	X86_64,LONG,LOCK
SUB	reg_al,imm	8086
SUB	reg_ax,sbyteword	8086,ND
SUB	reg_ax,imm	8086
SUB	reg_eax,sbytedword	386,ND
SUB	reg_eax,imm	386
SUB	reg_rax,sbytedword	X86_64,LONG,ND
SUB	reg_rax,imm	X86_64,LONG
SUB	rm8,imm	8086,LOCK
SUB	rm16,sbyteword	8086,LOCK,ND
SUB	rm16,imm	8086,LOCK
SUB	rm32,sbytedword	386,LOCK,ND
SUB	rm32,imm	386,LOCK
SUB	rm64,sbytedword	X86_64,LONG,LOCK,ND
SUB	rm64,imm	X86_64,LONG,LOCK
SUB	mem,imm8	8086,LOCK
SUB	mem,sbyteword16	8086,LOCK,ND
SUB	mem,imm16	8086,LOCK
SUB	mem,sbytedword32	386,LOCK,ND
SUB	mem,imm32	386, LOCK ND NOLONG
SUB	rm8,imm	8086, LOCK, ND, NOLONG
SVDC SVLDT	mem80,reg_sreg mem80	486,CYRIX,SMM 486,CYRIX,SMM,ND
SVTS	mem80	486,CYRIX,SMM
SWAPGS	illelilou	X86_64,LONG
SYSCALL		P6,AMD
SYSENTER		P6
SYSEXIT		P6,PRIV
SYSRET		P6,PRIV,AMD
TEST	mem,reg8	8086
TEST	reg8,reg8	8086
TEST	mem,reg16	8086
TEST	reg16,reg16	8086
TEST	mem,reg32	386
TEST	reg32,reg32	386

TEST	mem,reg64	X86_64,LONG
TEST	reg64,reg64	X86_64,LONG
TEST		8086
	reg8,mem	
TEST	reg16,mem	8086
TEST	reg32,mem	386
TEST	reg64,mem	X86_64,LONG
TEST	reg_al,imm	8086
	•	
TEST	reg_ax,imm	8086
TEST	reg_eax,imm	386
TEST	reg_rax,imm	X86_64,LONG
TEST	rm8,imm	8086
TEST	•	8086
	rm16,imm	
TEST	rm32,imm	386
TEST	rm64,imm	X86_64,LONG
TEST	mem,imm8	8086
TEST	mem,imm16	8086
	,	
TEST	mem,imm32	386
UD0		186,0BSOLETE
UD0	reg16,rm16	186
UD0	reg32,rm32	186
	•	
UD0	reg64,rm64	186
UD1	reg16,rm16	186
UD1	reg32,rm32	186
UD1	reg64,rm64	186
	1 0 9 0 + 3 1 1110 +	
UD1		186,ND
UD2B		186,ND
UD2B	reg16,rm16	186,ND
UD2B	reg32,rm32	186,ND
UD2B	9 ,	,
	reg64,rm64	186,ND
UD2		186
UD2A		186,ND
UMOV	mem, reg8	386,UNDOC,ND
UMOV	reg8,reg8	386,UNDOC,ND
UMOV	mem,reg16	386,UNDOC,ND
UMOV	reg16,reg16	386,UNDOC,ND
UMOV	mem,reg32	386,UNDOC,ND
UMOV	reg32,reg32	386,UNDOC,ND
UMOV	reg8,mem	386,UNDOC,ND
UMOV	reg8,reg8	386,UNDOC,ND
UMOV	reg16,mem	386,UNDOC,ND
UMOV	reg16,reg16	386,UNDOC,ND
UMOV		
	reg32,mem	386,UNDOC,ND
UMOV	reg32,reg32	386,UNDOC,ND
VERR	mem	286,PROT
VERR	mem16	286,PROT
VERR		286,PROT
	reg16	
VERW	mem	286,PROT
VERW	mem16	286,PROT
VERW	reg16	286,PROT
FWAIT	S .	8086
WBINVD		486,PRIV
WRSHR	rm32	P6,CYRIX,SMM
WRMSR		PENT, PRIV
XADD	mem,reg8	486,ĹOCK
		•
XADD	reg8,reg8	486
XADD	mem,reg16	486,LOCK
XADD	reg16,reg16	486
XADD	mem,reg32	486,LOCK
XADD	, ,	486
	reg32,reg32	
XADD	mem,reg64	X86_64,LONG,LOCK
XADD	reg64,reg64	X86_64,LONG
XBTS	reg16,mem	386,SW,UNDOC,ND
XBTS		386,UNDOC,ND
	reg16,reg16	, ,
XBTS	reg32,mem	386,SD,UNDOC,ND
XBTS	reg32,reg32	386,UNDOC,ND
XCHG	reg_ax,reg16	8086
XCHG	reg_eax,reg32na	386
7.0110	1 08_000,1 0802110	300

```
XCHG
                   reg_rax, reg64
                                               X86_64,LONG
XCHG
                                               8086
                   reg16,reg_ax
XCHG
                                               386
                   reg32na,reg_eax
                                               X86_64,LONG
XCHG
                   reg64, reg_rax
XCHG
                                               386, NOLONG
                   reg_eax, reg_eax
XCHG
                   reg8, mem
                                               8086, LOCK
                                               8086
XCHG
                   reg8, reg8
XCHG
                                              8086, LOCK
                   reg16,mem
XCHG
                   reg16, reg16
                                               8086
XCHG
                                               386,LOCK
                   reg32,mem
XCHG
                   reg32,reg32
                                               386
XCHG
                   reg64, mem
                                               X86_64, LONG, LOCK
XCHG
                   reg64, reg64
                                               X86_64,LONG
XCHG
                                               8086, LOCK
                  mem, reg8
XCHG
                   reg8, reg8
                                               8086
                                               8086,LOCK
XCHG
                  mem, reg16
XCHG
                   reg16, reg16
                                               8086
                                               386,LOCK
XCHG
                  mem, reg32
XCHG
                  reg32, reg32
                                               386
XCHG
                  mem, reg64
                                               X86_64, LONG, LOCK
XCHG
                   reg64, reg64
                                               X86_64,LONG
XLATB
                                               8086
XLAT
                                               8086
XOR
                                              8086, LOCK
                  mem, reg8
XOR
                                               8086
                   reg8, reg8
XOR
                  mem, reg16
                                               8086, LOCK
XOR
                   reg16, reg16
                                               8086
XOR
                                               386,LOCK
                  mem, reg32
XOR
                   reg32, reg32
                                               386
XOR
                                               X86_64, LONG, LOCK
                  mem, reg64
XOR
                   reg64, reg64
                                               X86_64,LONG
                                               8086
XOR
                   reg8, mem
XOR
                   reg8, reg8
                                               8086
XOR
                   reg16,mem
                                              8086
XOR
                   reg16, reg16
                                              8086
XOR
                   reg32,mem
                                              386
XOR
                   reg32, reg32
                                               386
XOR
                                               X86_64,LONG
                   reg64,mem
XOR
                   reg64, reg64
                                               X86_64,LONG
XOR
                   rm16,imm8
                                               8086, LOCK
XOR
                   rm32,imm8
                                               386,LOCK
XOR
                   rm64,imm8
                                               X86_64, LONG, LOCK
                   reg_al,imm
                                               8086
XOR
XOR
                   reg_ax,sbyteword
                                               8086,ND
XOR
                   reg_ax,imm
                                               8086
                   reg_eax,sbytedword
                                              386,ND
XOR
XOR
                   reg_eax, imm
                                               386
                                               X86_64,LONG,ND
XOR
                   reg_rax, sbytedword
XOR
                   reg_rax,imm
                                               X86_64,LONG
XOR
                   rm8,imm
                                               8086, LOCK
XOR
                   rm16, sbyteword
                                               8086, LOCK, ND
XOR
                                               8086, LOCK
                   rm16,imm
XOR
                   rm32, sbytedword
                                               386, LOCK, ND
XOR
                   rm32,imm
                                               386,LOCK
                                               X86_64,LONG,LOCK,ND
XOR
                   rm64, sbytedword
XOR
                   rm64, imm
                                               X86_64, LONG, LOCK
                  mem,imm8
XOR
                                               8086, LOCK
XOR
                  mem, sbyteword16
                                               8086, LOCK, ND
XOR
                  mem, imm16
                                               8086,LOCK
                  mem, sbytedword32
XOR
                                               386, LOCK, ND
                  mem,imm32
XOR
                                               386,LOCK
                                               8086, LOCK, ND, NOLONG
XOR
                  rm8,imm
CMOVcc
                   reg16,mem
                                               Р6
CMOVcc
                   reg16, reg16
                                               Р6
CMOVcc
                                               Р6
                   reg32,mem
CMOVcc
                   reg32,reg32
                                               Р6
CMOVcc
                   reg64, mem
                                               X86_64,LONG
```

CMOVcc	reg64,reg64	X86_64,LONG
Jcc	imm near	386,BND
Jcc	imm16 near	386,NOLONG,BND
Jcc	imm32 near	386,NOLONG,BND
Jcc	imm64 near	X86_64,LONG,BND
Jcc	imm short	8086,ND,BND
Jcc	imm	8086,ND,BND
Jcc	imm	386,ND,BND
Jcc	imm	8086,ND,BND
Jcc	imm	8086,BND
SETcc	mem	386
SETcc	reg8	386

B.1.3 Katmai Streaming SIMD instructions (SSE -- a.k.a. KNI, XMM, MMX2)

Macinal Stream	ing shirt mistractions (s	ose a.k.a. Kiti, Airiii
ADDPS	xmmreg,xmmrm128	KATMAI,SSE
ADDSS	xmmreg,xmmrm32	KATMAI,SSE
ANDNPS	xmmreg,xmmrm128	KATMAI,SSE
ANDPS	xmmreg,xmmrm128	KATMAI,SSE
CMPEQPS	xmmreg,xmmrm128	KATMAI,SSE
CMPEQSS	xmmreg,xmmrm32	KATMAI,SSE
CMPLEPS	xmmreg,xmmrm128	KATMAI,SSE
CMPLESS	xmmreg,xmmrm32	KATMAI,SSE
CMPLTPS	xmmreg,xmmrm128	KATMAI,SSE
CMPLTSS	xmmreg,xmmrm32	KATMAI,SSE
CMPNEQPS	xmmreg,xmmrm128	KATMAI,SSE
CMPNEQSS	xmmreg,xmmrm32	KATMAI,SSE
CMPNLEPS	xmmreg,xmmrm128	KATMAI,SSE
CMPNLESS	xmmreg,xmmrm32	KATMAI,SSE
CMPNLTPS	xmmreg,xmmrm128	KATMAI,SSE
CMPNLTSS	xmmreg,xmmrm32	KATMAI,SSE
CMPORDPS	xmmreg,xmmrm128	KATMAI,SSE
CMPORDSS	xmmreg,xmmrm32	KATMAI,SSE
CMPUNORDPS	xmmreg,xmmrm128	KATMAI,SSE
CMPUNORDSS	xmmreg,xmmrm32	KATMAI,SSE
CMPPS	xmmreg,xmmrm128,imm8	KATMAI,SSE
CMPSS	xmmreg,xmmrm32,imm8	KATMAI,SSE
COMISS	xmmreg,xmmrm32	KATMAI,SSE
CVTPI2PS	xmmreg,mmxrm64	KATMAI,SSE,MMX
CVTPS2PI	mmxreg,xmmrm64	KATMAI,SSE,MMX
CVTSI2SS	xmmreg,mem	KATMAI,SSE,SD,AR1,ND
CVTSI2SS	xmmreg,rm32	KATMAI,SSE,SD,AR1
CVTSI2SS	xmmreg,rm64	X86_64,LONG,SSE,AR1
CVTSS2SI	reg32,xmmreg	KATMAI,SSE,SD,AR1
CVTSS2SI	reg32,mem	KATMAI,SSE,SD,AR1
CVTSS2SI	reg64,xmmreg	X86_64,LONG,SSE,SD,AR1
CVTSS2SI	reg64,mem	X86_64,LONG,SSE,SD,AR1
CVTTPS2PI	mmxreg,xmmrm	KATMAI,SSE,MMX
CVTTSS2SI	reg32,xmmrm	KATMAI,SSE,SD,AR1
CVTTSS2SI	reg64,xmmrm	X86_64,LONG,SSE,SD,AR1
DIVPS	xmmreg,xmmrm128	KATMAI,SSE
DIVSS	xmmreg,xmmrm32	KATMAI,SSE
LDMXCSR	mem32	KATMAI,SSE
MAXPS	xmmreg,xmmrm128	KATMAI,SSE
MAXSS	xmmreg,xmmrm32	KATMAI,SSE
MINPS	xmmreg,xmmrm128	KATMAI,SSE
MINSS	xmmreg,xmmrm32	KATMAI,SSE
MOVAPS	xmmreg,xmmrm128	KATMAI,SSE
MOVAPS	xmmrm128,xmmreg	KATMAI,SSE
MOVHPS	xmmreg,mem64	KATMAI,SSE
MOVHPS	mem64,xmmreg	KATMAI,SSE
MOVLHPS	xmmreg,xmmreg	KATMAI,SSE
MOVLPS	xmmreg,mem64	KATMAI,SSE
MOVLPS	mem64,xmmreg	KATMAI,SSE
MOVHLPS	xmmreg,xmmreg	KATMAI,SSE
MOVMSKPS	reg32,xmmreg	KATMAI,SSE
MOVMSKPS	reg64,xmmreg	X86_64,LONG,SSE

MOVNTPS	mem128,xmmreg	KATMAI,SSE
MOVSS	xmmreg,xmmrm32	KATMAI,SSE
MOVSS	xmmrm32,xmmreg	KATMAI,SSE
MOVUPS	xmmreg,xmmrm128	KATMAI,SSE
MOVUPS	xmmrm128,xmmreg	KATMAI,SSE
MULPS	xmmreg,xmmrm128	KATMAI,SSE
MULSS	xmmreg,xmmrm32	KATMAI,SSE
ORPS	xmmreg,xmmrm128	KATMAI,SSE
RCPPS	xmmreg,xmmrm128	KATMAI,SSE
RCPSS	xmmreg,xmmrm32	KATMAI,SSE
RSQRTPS	xmmreg,xmmrm128	KATMAI,SSE
RSQRTSS	xmmreg,xmmrm32	KATMAI,SSE
SHUFPS	xmmreg,xmmrm128,imm8	KATMAI,SSE
SQRTPS	xmmreg,xmmrm128	KATMAI,SSE
SQRTSS	xmmreg,xmmrm32	KATMAI,SSE
STMXCSR	mem32	KATMAI,SSE
SUBPS	xmmreg,xmmrm128	KATMAI,SSE
SUBSS	xmmreg,xmmrm32	KATMAI,SSE
UCOMISS	xmmreg,xmmrm32	KATMAI,SSE
UNPCKHPS	xmmreg,xmmrm128	KATMAI,SSE
UNPCKLPS	xmmreg,xmmrm128	KATMAI,SSE
XORPS	xmmreg,xmmrm128	KATMAI,SSE

B.1.4 Introduced in Deschutes but necessary for SSE support

FXRSTOR	mem	P6,SSE,FPU
FXRSTOR64	mem	X86_64,LONG,SSE,FPU
FXSAVE	mem	P6,SSE,FPU
FXSAVE64	mem	X86_64,LONG,SSE,FPU

B.1.5 XSAVE group (AVX and extended state)

XGETBV		NEHALEM
XSETBV		NEHALEM, PRIV
XSAVE	mem	NEHALEM
XSAVE64	mem	LONG, NEHALEM
XSAVEC	mem	
XSAVEC64	mem	LONG
XSAVEOPT	mem	
XSAVEOPT64	mem	LONG
XSAVES	mem	
XSAVES64	mem	LONG
XRSTOR	mem	NEHALEM
XRSTOR64	mem	LONG, NEHALEM
XRSTORS	mem	
XRSTORS64	mem	LONG

B.1.6 Generic memory operations

PREFETCHNTA	mem8	KATMAI
PREFETCHT0	mem8	KATMAI
PREFETCHT1	mem8	KATMAI
PREFETCHT2	mem8	KATMAI
SFENCE		KATMAI

B.1.7 New MMX instructions introduced in Katmai

MASKMOVQ	mmxreg,mmxreg	KATMAI,MMX
MOVNTQ	mem,mmxreg	KATMAI,MMX
PAVGB	mmxreg,mmxrm	KATMAI,MMX
PAVGW	mmxreg,mmxrm	KATMAI,MMX
PEXTRW	reg32,mmxreg,imm	KATMAI, MMX
PINSRW	mmxreg,mem,imm	KATMAI,MMX
PINSRW	mmxreg,rm16,imm	KATMAI,MMX
PINSRW	mmxreg,reg32,imm	KATMAI,MMX
PMAXSW	mmxreg,mmxrm	KATMAI,MMX
PMAXUB	mmxreg,mmxrm	KATMAI,MMX
PMTNSW	mmxreg.mmxrm	KATMAT.MMX

PMINUB	mmxreg,mmxrm	KATMAI,MMX
PMOVMSKB	reg32,mmxreg	KATMAI,MMX
PMULHUW	mmxreg,mmxrm	KATMAI,MMX
PSADBW	mmxreg,mmxrm	KATMAI, MMX
PSHUFW	mmxreg,mmxrm,imm	KATMAI,MMX

B.1.8 AMD Enhanced 3DNow! (Athlon) instructions

PF2IW	mmxreg,mmxrm	PENT,3DNOW
PFNACC	mmxreg,mmxrm	PENT,3DNOW
PFPNACC	mmxreg,mmxrm	PENT,3DNOW
PI2FW	mmxreg,mmxrm	PENT,3DNOW
PSWAPD	mmxreg,mmxrm	PENT,3DNOW

B.1.9 Willamette SSE2 Cacheability Instructions

MASKMOVDQU	xmmreg,xmmreg	WILLAMETTE,SSE2
CLFLUSH	mem	WILLAMETTE, SSE2
MOVNTDQ	mem,xmmreg	WILLAMETTE, SSE2, SO
MOVNTI	mem,reg32	WILLAMETTE,SD
MOVNTI	mem,reg64	X86_64,LONG
MOVNTPD	mem,xmmreg	WILLAMETTE, SSE2, SO
LFENCE		WILLAMETTE, SSE2
MFENCE		WILLAMETTE.SSE2

B.1.10 Willamette MMX instructions (SSE2 SIMD Integer Instructions)

MOVD	mem,xmmreg	WILLAMETTE, SSE2, SD
MOVD	xmmreg,mem	WILLAMETTE, SSE2, SD
MOVD	xmmreg,rm32	WILLAMETTE,SSE2
MOVD	rm32,xmmreg	WILLAMETTE,SSE2
MOVDQA	xmmreg,xmmrm128	WILLAMETTE, SSE2, SO
MOVDQA	xmmrm128,xmmreg	WILLAMETTE, SSE2, SO
MOVDQU	xmmreg,xmmrm128	WILLAMETTE, SSE2, SO
MOVDQU	xmmrm128,xmmreg	WILLAMETTE, SSE2, SO
MOVDQ2Q	mmxreg,xmmreg	WILLAMETTE,SSE2
MOVQ	xmmreg,xmmreg	WILLAMETTE,SSE2
MOVQ	xmmreg,xmmreg	WILLAMETTE,SSE2
MOVQ	mem,xmmreg	WILLAMETTE,SSE2
MOVQ	xmmreg,mem	WILLAMETTE,SSE2
MOVQ	xmmreg,rm64	X86_64,LONG,SSE2
MOVQ	rm64,xmmreg	X86_64,LONG,SSE2
MOVQ2DQ	xmmreg,mmxreg	WILLAMETTE, SSE2
PACKSSWB	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
PACKSSDW	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
PACKUSWB	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
PADDB	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
PADDW	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
PADDD	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
PADDQ	mmxreg, mmxrm	WILLAMETTE, MMX
PADDQ	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
PADDSB	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
PADDSW	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
PADDUSB	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
PADDUSW	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
PAND	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
PANDN	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
PAVGB	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
PAVGW	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
PCMPEQB	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
PCMPEQW	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
PCMPEQD	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
PCMPGTB	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
PCMPGTW	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
PCMPGTD	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
PEXTRW	reg32,xmmreg,imm	WILLAMETTE, SSE2
PEXTRW	reg64,xmmreg,imm	X86_64,LONG,SSE2,NI
PINSRW	xmmreg,reg16,imm	WILLAMETTE, SSE2

PINSRW WILLAMETTE, SSE2, ND xmmreg,reg32,imm **PINSRW** xmmreg,reg64,imm X86_64,LONG,SSE2,ND **PINSRW** xmmreg, mem, imm WILLAMETTE, SSE2 PINSRW xmmreg,mem16,imm WILLAMETTE, SSE2 PMADDWD WILLAMETTE, SSE2, SO xmmreg,xmmrm **PMAXSW** xmmreg,xmmrm WILLAMETTE, SSE2, SO WILLAMETTE, SSE2, SO **PMAXUB** xmmreg,xmmrm **PMINSW** xmmreg,xmmrm WILLAMETTE, SSE2, SO **PMINUB** WILLAMETTE, SSE2, SO xmmreg,xmmrm **PMOVMSKB** reg32,xmmreg WILLAMETTE, SSE2 PMULHUW WILLAMETTE, SSE2, SO xmmreg,xmmrm **PMULHW** WILLAMETTE, SSE2, SO xmmreg,xmmrm PMULLW WILLAMETTE, SSE2, SO xmmreg,xmmrm mmxreg,mmxrm **PMULUDQ** WILLAMETTE, SSE2, SO **PMULUDQ** xmmreg,xmmrm WILLAMETTE, SSE2, SO POR xmmreg,xmmrm WILLAMETTE, SSE2, SO WILLAMETTE, SSE2, SO **PSADBW** xmmreg,xmmrm WILLAMETTE, SSE2 **PSHUFD** xmmreg,xmmreg,imm **PSHUFD** WILLAMETTE, SSE2 xmmreg,mem,imm **PSHUFHW** xmmreg,xmmreg,imm WILLAMETTE, SSE2 **PSHUFHW** xmmreg,mem,imm WILLAMETTE, SSE2 **PSHUFLW** xmmreg,xmmreg,imm WILLAMETTE, SSE2 **PSHUFLW** xmmreg,mem,imm WILLAMETTE, SSE2 xmmreg, imm WILLAMETTE, SSE2, AR1 PSLLDQ PSLLW xmmreg,xmmrm WILLAMETTE, SSE2, SO **PSLLW** xmmreg, imm WILLAMETTE, SSE2, AR1 **PSLLD** WILLAMETTE, SSE2, SO xmmreg,xmmrm **PSLLD** xmmreg, imm WILLAMETTE, SSE2, AR1 **PSLLQ** xmmreg,xmmrm WILLAMETTE, SSE2, SO **PSLLQ** xmmreg,imm WILLAMETTE, SSE2, AR1 **PSRAW** xmmreg,xmmrm WILLAMETTE, SSE2, SO **PSRAW** xmmreg,imm WILLAMETTE, SSE2, AR1 **PSRAD** WILLAMETTE, SSE2, SO xmmreg,xmmrm **PSRAD** WILLAMETTE, SSE2, AR1 xmmreg, imm PSRLDQ xmmreg,imm WILLAMETTE, SSE2, AR1 PSRLW xmmreg,xmmrm WILLAMETTE, SSE2, SO **PSRLW** xmmreg,imm WILLAMETTE, SSE2, AR1 WILLAMETTE, SSE2, SO **PSRLD** xmmreg,xmmrm **PSRLD** xmmreg,imm WILLAMETTE, SSE2, AR1 **PSRLQ** xmmreg,xmmrm WILLAMETTE, SSE2, SO **PSRLQ** WILLAMETTE, SSE2, AR1 xmmreg,imm **PSUBB** WILLAMETTE, SSE2, SO xmmreg,xmmrm WILLAMETTE, SSE2, SO **PSUBW** xmmreg,xmmrm **PSUBD** WILLAMETTE, SSE2, SO xmmreg,xmmrm **PSUBQ** mmxreg, mmxrm WILLAMETTE, SSE2, SO **PSUBQ** WILLAMETTE, SSE2, SO xmmreg,xmmrm **PSUBSB** xmmreg,xmmrm WILLAMETTE, SSE2, SO xmmreg,xmmrm **PSUBSW** WILLAMETTE, SSE2, SO **PSUBUSB** WILLAMETTE, SSE2, SO xmmreg,xmmrm **PSUBUSW** xmmreg,xmmrm WILLAMETTE, SSE2, SO **PUNPCKHBW** xmmreg,xmmrm WILLAMETTE, SSE2, SO **PUNPCKHWD** xmmreg,xmmrm WILLAMETTE, SSE2, SO WILLAMETTE, SSE2, SO **PUNPCKHDQ** xmmreg,xmmrm PUNPCKHQDQ xmmreg,xmmrm WILLAMETTE, SSE2, SO PUNPCKLBW xmmreg,xmmrm WILLAMETTE, SSE2, SO **PUNPCKLWD** WILLAMETTE, SSE2, SO xmmreg,xmmrm PUNPCKLDQ WILLAMETTE, SSE2, SO xmmreg,xmmrm **PUNPCKLQDQ** WILLAMETTE, SSE2, SO xmmreg,xmmrm PXOR xmmreg,xmmrm WILLAMETTE, SSE2, SO

B.1.11 Willamette Streaming SIMD instructions (SSE2)

ADDPD	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
ADDSD	xmmreg,xmmrm	WILLAMETTE, SSE2
ANDNPD	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
ANDPD	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
CMPEQPD	xmmreg,xmmrm	WILLAMETTE, SSE2, SO

CMPEQSD	xmmreg,xmmrm	WILLAMETTE, SSE2
CMPLEPD	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
CMPLESD	= :	WILLAMETTE, SSE2
	xmmreg,xmmrm	•
CMPLTPD	xmmreg,xmmrm	WILLAMETTE,SSE2,SO
CMPLTSD	xmmreg,xmmrm	WILLAMETTE,SSE2
CMPNEQPD	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
CMPNEQSD		WILLAMETTE, SSE2
•	xmmreg,xmmrm	•
CMPNLEPD	xmmreg,xmmrm	WILLAMETTE,SSE2,SO
CMPNLESD	xmmreg,xmmrm	WILLAMETTE,SSE2
CMPNLTPD	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
		· · ·
CMPNLTSD	xmmreg,xmmrm	WILLAMETTE, SSE2
CMPORDPD	xmmreg,xmmrm	WILLAMETTE,SSE2,SO
CMPORDSD	xmmreg,xmmrm	WILLAMETTE, SSE2
CMPUNORDPD	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
CMPUNORDSD	xmmreg,xmmrm	WILLAMETTE, SSE2
CMPPD	xmmreg,xmmrm128,imm8	WILLAMETTE,SSE2
CMPSD	xmmreg,xmmrm128,imm8	WILLAMETTE, SSE2
COMISD	xmmreg,xmmrm64	WILLAMETTE, SSE2
CVTDQ2PD	xmmreg,xmmrm	WILLAMETTE, SSE2
CVTDQ2PS	xmmreg,xmmrm	WILLAMETTE,SSE2,SO
CVTPD2DQ	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
CVTPD2PI	mmxreg,xmmrm	WILLAMETTE, SSE2, SO
CVTPD2PS	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
CVTPI2PD	xmmreg,mmxrm	WILLAMETTE,SSE2
CVTPS2D0	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
CVTPS2PD	xmmreg,xmmrm	WILLAMETTE, SSE2
		•
CVTSD2SI	reg32,xmmreg	WILLAMETTE, SSE2, AR1
CVTSD2SI	reg32,mem	WILLAMETTE,SSE2,AR1
CVTSD2SI	reg64,xmmreg	X86_64,LONG,SSE2,AR1
CVTSD2SI	reg64,mem	X86_64,LONG,SSE2,AR1
	= '	
CVTSD2SS	xmmreg,xmmrm	WILLAMETTE, SSE2
CVTSI2SD	xmmreg,mem	WILLAMETTE, SSE2, SD, AR1, ND
CVTSI2SD	xmmreg,rm32	WILLAMETTE, SSE2, SD, AR1
CVTSI2SD	xmmreg,rm64	X86_64,LONG,SSE2,AR1
CVTSS2SD		WILLAMETTE, SSE2, SD
	xmmreg,xmmrm	
CVTTPD2PI	mmxreg,xmmrm	WILLAMETTE,SSE2,SO
CVTTPD2DQ	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
CVTTPS2DQ	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
CVTTSD2SI	<u>.</u>	WILLAMETTE, SSE2, AR1
	reg32,xmmreg	
CVTTSD2SI	reg32,mem	WILLAMETTE,SSE2,AR1
CVTTSD2SI	reg64,xmmreg	X86_64,LONG,SSE2,AR1
CVTTSD2SI	reg64,mem	X86_64,LONG,SSE2,AR1
DIVPD	= :	
	xmmreg,xmmrm	WILLAMETTE, SSE2, SO
DIVSD	xmmreg,xmmrm	WILLAMETTE,SSE2
MAXPD	xmmreg,xmmrm	
MAYCD	Annin Cg, Annin III	WILLAMETTE,SSE2,SO
MAXSD		WILLAMETTE, SSE2, SO WILLAMETTE. SSE2
MAXSD MTNPD	xmmreg,xmmrm	WILLAMETTE, SSE2
MINPD	xmmreg,xmmrm xmmreg,xmmrm	WILLAMETTE,SSE2 WILLAMETTE,SSE2,SO
MINPD MINSD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm	WILLAMETTE,SSE2 WILLAMETTE,SSE2,SO WILLAMETTE,SSE2
MINPD	xmmreg,xmmrm xmmreg,xmmrm	WILLAMETTE,SSE2 WILLAMETTE,SSE2,SO
MINPD MINSD	<pre>xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128</pre>	WILLAMETTE,SSE2 WILLAMETTE,SSE2,SO WILLAMETTE,SSE2 WILLAMETTE,SSE2
MINPD MINSD MOVAPD MOVAPD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128 xmmrm128,xmmreg	WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2 WILLAMETTE, SSE2 WILLAMETTE, SSE2
MINPD MINSD MOVAPD MOVAPD MOVHPD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128 xmmrm128,xmmreg mem64,xmmreg	WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2 WILLAMETTE, SSE2 WILLAMETTE, SSE2 WILLAMETTE, SSE2 WILLAMETTE, SSE2
MINPD MINSD MOVAPD MOVAPD MOVHPD MOVHPD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128 xmmrm128,xmmreg mem64,xmmreg xmmreg,mem64	WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2 WILLAMETTE, SSE2 WILLAMETTE, SSE2 WILLAMETTE, SSE2 WILLAMETTE, SSE2 WILLAMETTE, SSE2
MINPD MINSD MOVAPD MOVAPD MOVHPD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128 xmmrm128,xmmreg mem64,xmmreg	WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2 WILLAMETTE, SSE2 WILLAMETTE, SSE2 WILLAMETTE, SSE2 WILLAMETTE, SSE2
MINPD MINSD MOVAPD MOVAPD MOVHPD MOVHPD MOVLPD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128 xmmrm128,xmmreg mem64,xmmreg xmmreg,mem64 mem64,xmmreg	WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2
MINPD MINSD MOVAPD MOVAPD MOVHPD MOVHPD MOVLPD MOVLPD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128 xmmrm128,xmmreg mem64,xmmreg xmmreg,mem64 mem64,xmmreg xmmreg,mem64	WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2
MINPD MINSD MOVAPD MOVAPD MOVHPD MOVHPD MOVLPD MOVLPD MOVLPD MOVLPD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128 xmmrm128,xmmreg mem64,xmmreg xmmreg,mem64 mem64,xmmreg xmmreg,mem64 reg32,xmmreg	WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2
MINPD MINSD MOVAPD MOVAPD MOVHPD MOVHPD MOVLPD MOVLPD MOVLPD MOVMSKPD MOVMSKPD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128 xmmrm128,xmmreg mem64,xmmreg xmmreg,mem64 mem64,xmmreg xmmreg,mem64 reg32,xmmreg reg64,xmmreg	WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2 X86_64, LONG, SSE2
MINPD MINSD MOVAPD MOVAPD MOVHPD MOVHPD MOVLPD MOVLPD MOVLPD MOVLPD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128 xmmrm128,xmmreg mem64,xmmreg xmmreg,mem64 mem64,xmmreg xmmreg,mem64 reg32,xmmreg	WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2 X86_64, LONG, SSE2 WILLAMETTE, SSE2
MINPD MINSD MOVAPD MOVAPD MOVHPD MOVHPD MOVLPD MOVLPD MOVLPD MOVMSKPD MOVMSKPD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128 xmmrm128,xmmreg mem64,xmmreg xmmreg,mem64 mem64,xmmreg xmmreg,mem64 reg32,xmmreg reg64,xmmreg	WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2 X86_64, LONG, SSE2
MINPD MINSD MOVAPD MOVAPD MOVHPD MOVHPD MOVLPD MOVLPD MOVLPD MOVMSKPD MOVMSKPD MOVSD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128 xmmrm128,xmmreg mem64,xmmreg xmmreg,mem64 mem64,xmmreg xmmreg,mem64 reg32,xmmreg reg64,xmmreg xmmreg,xmmred xmmreg,xmmreg	WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2
MINPD MINSD MOVAPD MOVAPD MOVHPD MOVHPD MOVLPD MOVLPD MOVLPD MOVMSKPD MOVMSKPD MOVSD MOVSD MOVUPD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128 xmmrm128,xmmreg mem64,xmmreg xmmreg,mem64 mem64,xmmreg xmmreg,mem64 reg32,xmmreg reg64,xmmreg xmmreg,xmmreg xmmreg,xmmreg xmmreg,xmmreg xmmreg,xmmrm64 xmmrm64,xmmreg xmmreg,xmmrm128	WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2
MINPD MINSD MOVAPD MOVAPD MOVHPD MOVHPD MOVLPD MOVLPD MOVLPD MOVMSKPD MOVMSKPD MOVSD MOVSD MOVUPD MOVUPD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128 xmmrm128,xmmreg mem64,xmmreg xmmreg,mem64 mem64,xmmreg xmmreg,mem64 reg32,xmmreg reg64,xmmreg xmmreg,xmmrm64 xmmrm64,xmmreg xmmrm64,xmmreg xmmrm128,xmmreg	WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2
MINPD MINSD MOVAPD MOVAPD MOVHPD MOVHPD MOVLPD MOVLPD MOVLPD MOVMSKPD MOVMSKPD MOVSD MOVSD MOVUPD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128 xmmrm128,xmmreg mem64,xmmreg xmmreg,mem64 mem64,xmmreg xmmreg,mem64 reg32,xmmreg reg64,xmmreg xmmreg,xmmrm64 xmmrm64,xmmreg xmmrm128,xmmreg xmmrm128,xmmreg xmmrm128,xmmreg	WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2
MINPD MINSD MOVAPD MOVAPD MOVHPD MOVHPD MOVLPD MOVLPD MOVLPD MOVMSKPD MOVMSKPD MOVSD MOVSD MOVUPD MOVUPD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128 xmmrm128,xmmreg mem64,xmmreg xmmreg,mem64 mem64,xmmreg xmmreg,mem64 reg32,xmmreg reg64,xmmreg xmmreg,xmmrm64 xmmrm64,xmmreg xmmrm64,xmmreg xmmrm128,xmmreg	WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2
MINPD MINSD MOVAPD MOVAPD MOVHPD MOVHPD MOVLPD MOVLPD MOVLPD MOVMSKPD MOVSD MOVSD MOVUPD MOVUPD MOVUPD MOVUPD MOVUPD MULPD MULSD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128 xmmrm128,xmmreg mem64,xmmreg xmmreg,mem64 mem64,xmmreg xmmreg,mem64 reg32,xmmreg reg64,xmmreg xmmreg,xmmrm64 xmmrm64,xmmreg xmmreg,xmmrm128 xmmrm128,xmmreg xmmreg,xmmrm128 xmmreg,xmmrm128 xmmreg,xmmrm64	WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2, SO
MINPD MINSD MOVAPD MOVAPD MOVHPD MOVHPD MOVLPD MOVLPD MOVMSKPD MOVSSD MOVSD MOVUPD MOVUPD MOVUPD MOVUPD MOVUPD MOVUPD MOVUPD MOVUPD MOULSD ORPD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128 xmmrm128,xmmreg mem64,xmmreg xmmreg,mem64 mem64,xmmreg xmmreg,mem64 reg32,xmmreg reg64,xmmreg xmmreg,xmmrm64 xmmrm64,xmmreg xmmreg,xmmrm128 xmmreg,xmmrm128 xmmreg,xmmrm128 xmmreg,xmmrm128 xmmreg,xmmrm128	WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO
MINPD MINSD MOVAPD MOVAPD MOVHPD MOVHPD MOVLPD MOVLPD MOVMSKPD MOVSD MOVSD MOVUPD MOVUPD MOVUPD MULPD MULPD MULPD MULPD SHUFPD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128 xmmrm128,xmmreg mem64,xmmreg xmmreg,mem64 mem64,xmmreg xmmreg,mem64 reg32,xmmreg reg64,xmmreg xmmreg,xmmrm64 xmmrm64,xmmreg xmmreg,xmmrm128 xmmreg,xmmrm128,xmmreg xmmreg,xmmrm128,xmmreg xmmreg,xmmrm128 xmmreg,xmmrm128 xmmreg,xmmrm128 xmmreg,xmmrm128,imm8	WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO
MINPD MINSD MOVAPD MOVAPD MOVHPD MOVHPD MOVLPD MOVLPD MOVSD MOVSD MOVUPD MOVUPD MOVUPD MULPD MULPD MULPD SQRTPD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128 xmmrm128,xmmreg mem64,xmmreg xmmreg,mem64 mem64,xmmreg xmmreg,mem64 reg32,xmmreg reg64,xmmreg xmmreg,xmmrm64 xmmreg,xmmrm128	WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2
MINPD MINSD MOVAPD MOVAPD MOVHPD MOVHPD MOVLPD MOVLPD MOVMSKPD MOVSD MOVSD MOVUPD MOVUPD MOVUPD MULPD MULPD MULPD MULPD SHUFPD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128 xmmrm128,xmmreg mem64,xmmreg xmmreg,mem64 mem64,xmmreg xmmreg,mem64 reg32,xmmreg reg64,xmmreg xmmreg,xmmrm64 xmmrm64,xmmreg xmmreg,xmmrm128 xmmreg,xmmrm128,xmmreg xmmreg,xmmrm128,xmmreg xmmreg,xmmrm128 xmmreg,xmmrm128 xmmreg,xmmrm128 xmmreg,xmmrm128,imm8	WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO
MINPD MINSD MOVAPD MOVAPD MOVHPD MOVHPD MOVLPD MOVLPD MOVSD MOVSD MOVUPD MOVUPD MOVUPD MULPD MULPD MULPD SQRTPD	xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm xmmreg,xmmrm128 xmmrm128,xmmreg mem64,xmmreg xmmreg,mem64 mem64,xmmreg xmmreg,mem64 reg32,xmmreg reg64,xmmreg xmmreg,xmmrm64 xmmreg,xmmrm128	WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2 WILLAMETTE, SSE2, SO WILLAMETTE, SSE2

SUBSD	xmmreg,xmmrm64	WILLAMETTE, SSE2
UCOMISD	xmmreg,xmmrm64	WILLAMETTE, SSE2
UNPCKHPD	xmmreg,xmmrm128	WILLAMETTE, SSE2
UNPCKLPD	xmmreg,xmmrm128	WILLAMETTE, SSE2
XORPD	xmmreg,xmmrm128	WILLAMETTE, SSE2

B.1.12 Prescott New Instructions (SSE3)

ADDSUBPD	xmmreg,xmmrm128	PRESCOTT, SSE3, SO
ADDSUBPS	xmmreg,xmmrm128	PRESCOTT, SSE3, SO
HADDPD	xmmreg,xmmrm128	PRESCOTT, SSE3, SO
HADDPS	xmmreg,xmmrm128	PRESCOTT, SSE3, SO
HSUBPD	xmmreg,xmmrm128	PRESCOTT, SSE3, SO
HSUBPS	xmmreg,xmmrm128	PRESCOTT, SSE3, SO
LDDQU	xmmreg,mem128	PRESCOTT, SSE3, SO
MOVDDUP	xmmreg,xmmrm64	PRESCOTT, SSE3
MOVSHDUP	xmmreg,xmmrm128	PRESCOTT, SSE3
MOVSLDUP	xmmreg,xmmrm128	PRESCOTT, SSE3

B.1.13 VMX/SVM Instructions

CLCT		VMV AMB
CLGI		VMX,AMD
STGI		VMX,AMD
VMCALL		VMX
VMCLEAR	mem	VMX
VMFUNC		VMX
VMLAUNCH		VMX
VMLOAD		VMX,AMD
VMMCALL		VMX,AMD
VMPTRLD	mem	VMX
VMPTRST	mem	VMX
VMREAD	rm32,reg32	VMX,NOLONG,SD
VMREAD	rm64, reg64	X86_64,LONG,VMX
VMRESUME	· -	VMX
VMRUN		VMX,AMD
VMSAVE		VMX, AMD
VMWRITE	reg32,rm32	VMX, NOLONG, SD
VMWRITE	reg64,rm64	X86_64,LONG,VMX
VMXOFF		VMX
VMXON	mem	VMX

B.1.14 Extended Page Tables VMX instructions

INVEPT	reg32,mem	VMX,SO,NOLONG
INVEPT	reg64,mem	VMX,SO,LONG
INVVPID	reg32,mem	VMX,SO,NOLONG
INVVPID	reg64,mem	VMX,SO,LONG

B.1.15 Tejas New Instructions (SSSE3)

PABSB	mmxreg,mmxrm	SSSE3,MMX
PABSB	xmmreg,xmmrm128	SSSE3
PABSW	mmxreg,mmxrm	SSSE3,MMX
PABSW	xmmreg,xmmrm128	SSSE3
PABSD	mmxreg,mmxrm	SSSE3,MMX
PABSD	xmmreg,xmmrm128	SSSE3
PALIGNR	mmxreg,mmxrm,imm	SSSE3,MMX
PALIGNR	xmmreg,xmmrm,imm	SSSE3
PHADDW	mmxreg,mmxrm	SSSE3,MMX
PHADDW	xmmreg,xmmrm128	SSSE3
PHADDD	mmxreg,mmxrm	SSSE3,MMX
PHADDD	xmmreg,xmmrm128	SSSE3
PHADDSW	mmxreg,mmxrm	SSSE3,MMX
PHADDSW	xmmreg,xmmrm128	SSSE3
PHSUBW	mmxreg,mmxrm	SSSE3,MMX
PHSUBW	xmmreg,xmmrm128	SSSE3
PHSUBD	mmxreg,mmxrm	SSSE3,MMX
PHSUBD	xmmreg,xmmrm128	SSSE3

PHSUBSW	mmxreg,mmxrm	SSSE3,MMX
PHSUBSW	xmmreg,xmmrm128	SSSE3
PMADDUBSW	mmxreg,mmxrm	SSSE3,MMX
PMADDUBSW	xmmreg,xmmrm128	SSSE3
PMULHRSW	mmxreg,mmxrm	SSSE3,MMX
PMULHRSW	xmmreg,xmmrm128	SSSE3
PSHUFB	mmxreg,mmxrm	SSSE3,MMX
PSHUFB	xmmreg,xmmrm128	SSSE3
PSIGNB	mmxreg,mmxrm	SSSE3,MMX
PSIGNB	xmmreg,xmmrm128	SSSE3
PSIGNW	mmxreg,mmxrm	SSSE3,MMX
PSIGNW	xmmreg,xmmrm128	SSSE3
PSIGND	mmxreg,mmxrm	SSSE3,MMX
PSIGND	xmmreg,xmmrm128	SSSE3

B.1.16 AMD SSE4A

reg,imm,imm	SSE4A,AMD
reg,xmmreg	SSE4A,AMD
reg,xmmreg,imm,imm	SSE4A,AMD
reg,xmmreg	SSE4A,AMD
164,xmmreg	SSE4A,AMD
32,xmmreg	SSE4A,AMD,SD
	nreg,imm,imm nreg,xmmreg nreg,xmmreg,imm,imm nreg,xmmreg 164,xmmreg 132,xmmreg

B.1.17 New instructions in Barcelona

LZCNT	reg16,rm16	P6,AMD
LZCNT	reg32,rm32	P6,AMD

LZCNT reg64, rm64 X86_64, LONG, AMD

B.1.18 Penryn New Instructions (SSE4.1)

BLENDPD	xmmreg,xmmrm128,imm8	SSE41
BLENDPS	xmmreg,xmmrm128,imm8	SSE41
BLENDVPD	xmmreg,xmmrm128,xmm0	SSE41
BLENDVPD	xmmreg,xmmrm128	SSE41
BLENDVPS	xmmreg,xmmrm128,xmm0	SSE41
BLENDVPS	xmmreg,xmmrm128	SSE41
DPPD	xmmreg,xmmrm128,imm8	SSE41
DPPS	xmmreg,xmmrm128,imm8	SSE41
EXTRACTPS	rm32,xmmreg,imm8	SSE41
EXTRACTPS	reg64,xmmreg,imm8	SSE41,X86_64,LONG
INSERTPS	xmmreg,xmmrm32,imm8	SSE41
MOVNTDQA	xmmreg,mem128	SSE41
MPSADBW	xmmreg,xmmrm128,imm8	SSE41
PACKUSDW	xmmreg,xmmrm128	SSE41
PBLENDVB	xmmreg,xmmrm,xmm0	SSE41
PBLENDVB	xmmreg,xmmrm128	SSE41
PBLENDW	xmmreg,xmmrm128,imm8	SSE41
PCMPEQQ	xmmreg,xmmrm128	SSE41
PEXTRB	reg32,xmmreg,imm8	SSE41
PEXTRB	mem8,xmmreg,imm8	SSE41
PEXTRB	reg64,xmmreg,imm8	SSE41,X86_64,LONG
PEXTRD	rm32,xmmreg,imm8	SSE41
PEXTRQ	rm64,xmmreg,imm8	SSE41,X86_64,LONG
PEXTRW	reg32,xmmreg,imm8	SSE41
PEXTRW	mem16,xmmreg,imm8	SSE41
PEXTRW	reg64,xmmreg,imm8	SSE41,X86_64,LONG
PHMINPOSUW	xmmreg,xmmrm128	SSE41
PINSRB	xmmreg,mem,imm8	SSE41
PINSRB	xmmreg,rm8,imm8	SSE41
PINSRB	xmmreg,reg32,imm8	SSE41
PINSRD	xmmreg,rm32,imm8	SSE41
PINSRQ	xmmreg,rm64,imm8	SSE41,X86_64,LONG
PMAXSB	xmmreg,xmmrm128	SSE41
PMAXSD	xmmreg,xmmrm128	SSE41
PMAXUD	xmmreg,xmmrm128	SSE41
PMAXUW	xmmreg,xmmrm128	SSE41

PMINSB	xmmreg,xmmrm128	SSE41
PMINSD	xmmreg,xmmrm128	SSE41
PMINUD	xmmreg,xmmrm128	SSE41
PMINUW	xmmreg,xmmrm128	SSE41
PMOVSXBW	xmmreg,xmmrm64	SSE41
PMOVSXBD	xmmreg,xmmrm32	SSE41,SD
PMOVSXBQ	xmmreg,xmmrm16	SSE41,SW
PMOVSXWD	xmmreg,xmmrm64	SSE41
PMOVSXWQ	xmmreg,xmmrm32	SSE41,SD
PMOVSXDQ	xmmreg,xmmrm64	SSE41
PMOVZXBW	xmmreg,xmmrm64	SSE41
PMOVZXBD	xmmreg,xmmrm32	SSE41,SD
PMOVZXBQ	xmmreg,xmmrm16	SSE41,SW
PMOVZXWD	xmmreg,xmmrm64	SSE41
PMOVZXWQ	xmmreg,xmmrm32	SSE41,SD
PMOVZXDQ	xmmreg,xmmrm64	SSE41
PMULDQ	xmmreg,xmmrm128	SSE41
PMULLD	xmmreg,xmmrm128	SSE41
PTEST	xmmreg,xmmrm128	SSE41
ROUNDPD	xmmreg,xmmrm128,imm8	SSE41
ROUNDPS	xmmreg,xmmrm128,imm8	SSE41
ROUNDSD	xmmreg,xmmrm64,imm8	SSE41
ROUNDSS	xmmreg,xmmrm32,imm8	SSE41

B.1.19 Nehalem New Instructions (SSE4.2)

CRC32	reg32,rm8	SSE42
CRC32	reg32,rm16	SSE42
CRC32	reg32,rm32	SSE42
CRC32	reg64,rm8	SSE42,X86_64,LONG
CRC32	reg64,rm64	SSE42,X86_64,LONG
PCMPESTRI	xmmreg,xmmrm128,imm8	SSE42
PCMPESTRM	xmmreg,xmmrm128,imm8	SSE42
PCMPISTRI	xmmreg,xmmrm128,imm8	SSE42
PCMPISTRM	xmmreg,xmmrm128,imm8	SSE42
PCMPGTQ	xmmreg,xmmrm128	SSE42
POPCNT	reg16,rm16	NEHALEM,SW
POPCNT	reg32,rm32	NEHALEM,SD
POPCNT	reg64,rm64	NEHALEM,LONG

B.1.20 Intel SMX

GETSEC KATMAI

B.1.21 Geode (Cyrix) 3DNow! additions

PFRCPV mmxreg,mmxrm PENT,3DNOW,CYRIX PFRSQRTV mmxreg,mmxrm PENT,3DNOW,CYRIX

B.1.22 Intel new instructions in ???

MOVBE	reg16,mem16	NEHALEM
MOVBE	reg32,mem32	NEHALEM
MOVBE	reg64, mem64	NEHALEM
MOVBE	mem16,reg16	NEHALEM
MOVBE	mem32,reg32	NEHALEM
MOVBE	mem64, reg64	NEHALEM

B.1.23 Intel AES instructions

AESENC	xmmreg,xmmrm128	SSE, WESTMERE
AESENCLAST	xmmreg,xmmrm128	SSE, WESTMERE
AESDEC	xmmreg,xmmrm128	SSE, WESTMERE
AESDECLAST	xmmreg,xmmrm128	SSE, WESTMERE
AESIMC	xmmreg,xmmrm128	SSE, WESTMERE
AESKEYGENASSIST	xmmreg,xmmrm128,imm8	SSE, WESTMERE

B.1.24 Intel AVX AES instructions

```
VAESENC
                 xmmreg,xmmreg*,xmmrm128 AVX,SANDYBRIDGE
VAESENCLAST
                 xmmreg,xmmreg*,xmmrm128
                                           AVX.SANDYBRIDGE
                 xmmreg,xmmreg*,xmmrm128
VAESDEC
                                           AVX, SANDYBRIDGE
                                           AVX, SANDYBRIDGE
VAESDECLAST
                 xmmreg,xmmreg*,xmmrm128
                 xmmreg,xmmrm128
                                           AVX, SANDYBRIDGE
VAESTMC
VAESKEYGENASSIST xmmreg,xmmrm128,imm8
                                           AVX, SANDYBRIDGE
```

B.1.25 Intel instruction extension based on pub number 319433-030 dated October 2017

```
ymmreg,ymmreg*,ymmrm256 VAES
VAESENC
VAESENCLAST
                  ymmreg,ymmreg*,ymmrm256
                                               VAFS
                   ymmreg,ymmreg*,ymmrm256
VAESDEC
                                               VAFS
                  ymmreg,ymmreg*,ymmrm256
xmmreg,xmmreg*,xmmrm128
ymmreg,ymmreg*,ymmrm256
VAESDECLAST
                                               VAES
VAESENC
                                               AVX512VL, VAES
                                              AVX512VL, VAES
VAESENC
VAESENCLAST
                  xmmreg,xmmreg*,xmmrm128 AVX512VL,VAES
VAESENCLAST
                   ymmreg,ymmreg*,ymmrm256 AVX512VL,VAES
                   xmmreg,xmmreg*,xmmrm128 AVX512VL,VAES
VAFSDEC
                  ymmreg,ymmreg*,ymmrm256
xmmreg,xmmreg*,xmmrm128
VAESDEC
                                               AVX512VL, VAES
VAESDECLAST
                                              AVX512VL, VAES
                  ymmreg,ymmreg*,ymmrm256 AVX512VL,VAES
VAESDECLAST
VAESENC
                   zmmreg,zmmreg*,zmmrm512 AVX512,VAES
                   zmmreg,zmmreg*,zmmrm512 AVX512,VAES
VAESENCLAST
VAESDEC
                   zmmreg,zmmreg*,zmmrm512 AVX512,VAES
VAESDECLAST
                   zmmreg,zmmreg*,zmmrm512 AVX512,VAES
```

B.1.26 Intel AVX instructions

```
VADDPD
                     xmmreg,xmmreg*,xmmrm128 AVX,SANDYBRIDGE
VADDPD
                    ymmreg,ymmreg*,ymmrm256
                                                   AVX.SANDYBRIDGE
                     xmmreg,xmmreg*,xmmrm128
VADDPS
                                                   AVX, SANDYBRIDGE
                    ymmreg,ymmreg*,ymmrm256 AVX,SANDYBRIDGE
VADDES
                    xmmreg,xmmreg*,xmmrm64 AVX,SANDYBRIDGE xmmreg,xmmreg*,xmmrm32 AVX,SANDYBRIDGE xmmreg,xmmreg*,xmmrm128 AVX,SANDYBRIDGE
VADDSD
VADDSS
VADDSUBPD
VADDSUBPD
                    ymmreg,ymmreg*,ymmrm256
                                                   AVX, SANDYBRIDGE
VADDSUBPS
                    xmmreg,xmmreg*,xmmrm128
                                                   AVX, SANDYBRIDGE
                    ymmreg,ymmreg*,ymmrm256 AVX,SANDYBRIDGE
xmmreg,xmmreg*,xmmrm128 AVX,SANDYBRIDGE
ymmreg,ymmreg*,ymmrm256 AVX,SANDYBRIDGE
VADDSUBPS
VANDPD
VANDED
                    xmmreg,xmmreg*,xmmrm128 AVX,SANDYBRIDGE
VANDPS
VANDPS
                    ymmreg,ymmreg*,ymmrm256 AVX,SANDYBRIDGE
                     xmmreg,xmmreg*,xmmrm128 AVX,SANDYBRIDGE
VANDNPD
                    ymmreg,ymmreg*,ymmrm256
xmmreg,xmmreg*,xmmrm128
VANDNPD
                                                   AVX, SANDYBRIDGE
VANDNPS
                                                  AVX, SANDYBRIDGE
                    ymmreg,ymmreg*,ymmrm256 AVX,SANDYBRIDGE
VANDNPS
VBLENDPD
                    xmmreg,xmmreg*,xmmrm128,imm8 AVX,SANDYBRIDGE
                    ymmreg,ymmreg*,ymmrm256,imm8 AVX,SANDYBRIDGE
VBI FNDPD
VBLENDPS
                    xmmreg,xmmreg*,xmmrm128,imm8 AVX,SANDYBRIDGE
                    ymmreg,ymmreg*,ymmrm256,imm8 AVX,SANDYBRIDGE
xmmreg,xmmreg*,xmmrm128,xmmreg AVX,SANDYBRIDGE
VBLENDPS
VBLENDVPD
                    ymmreg,ymmreg*,ymmrm256,ymmreg AVX,SANDYBRIDGE
VBLENDVPD
VBLENDVPS
                     xmmreg,xmmreg*,xmmrm128,xmmreg AVX,SANDYBRIDGE
                    ymmreg,ymmreg*,ymmrm256,ymmreg AVX,SANDYBRIDGE
VBI FNDVPS
                                                   AVX.SANDYBRIDGE
VBROADCASTSS
                     xmmreg, mem32
VBROADCASTSS
                    ymmreg, mem32
                                                   AVX, SANDYBRIDGE
VBROADCASTSD
                                                   AVX, SANDYBRIDGE
                    ymmreg, mem64
VBROADCASTF128
                    ymmreg, mem128
                                                   AVX, SANDYBRIDGE
                     xmmreg,xmmreg*,xmmrm128 AVX,SANDYBRIDGE
VCMPEQ_OSPD
                    ymmreg,ymmreg*,ymmrm256
xmmreg,xmmreg*,xmmrm128
ymmreg,ymmreg*,ymmrm256
xmmreg,xmmreg*,xmmrm128
VCMPEQ_OSPD
                                                   AVX, SANDYBRIDGE
VCMPEQPD
                                                   AVX, SANDYBRIDGE
VCMPFOPD
                                                   AVX, SANDYBRIDGE
VCMPLT_OSPD
                                                   AVX, SANDYBRIDGE
VCMPLT_OSPD
                    ymmreg,ymmreg*,ymmrm256 AVX,SANDYBRIDGE
VCMPLTPD
                    xmmreg,xmmreg*,xmmrm128 AVX,SANDYBRIDGE
```

VCMPLTPD		
	ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPLE_OSPD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
-		•
VCMPLE_OSPD	ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPLEPD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VCMPLEPD	ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
		· .
VCMPUNORD_QPD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VCMPUNORD_QPD	ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPUNORDPD		· .
	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VCMPUNORDPD	ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPNEQ_UQPD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
		· .
VCMPNEQ_UQPD	ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPNEQPD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VCMPNEOPD	ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
		· .
VCMPNLT_USPD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VCMPNLT_USPD	ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPNLTPD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
		· .
VCMPNLTPD	ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPNLE_USPD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
-		· .
VCMPNLE_USPD	ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPNLEPD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VCMPNLEPD	ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
		· .
VCMPORD_QPD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VCMPORD_QPD	ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPORDPD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
		· .
VCMPORDPD	ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPEQ_UQPD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VCMPEQ_UQPD	ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
		· .
VCMPNGE_USPD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VCMPNGE_USPD	ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPNGEPD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VCMPNGEPD	ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
		· .
VCMPNGT_USPD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VCMPNGT_USPD	ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPNGTPD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VCMPNGTPD		
	ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPFALSE_OQPD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VCMPFALSE_OQPD	ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPFALSEPD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
		· .
VCMPFALSEPD	ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPNEQ_OQPD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VCMPNEQ_OQPD	ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
	J 08, J 08, J 200	
VCMDCE OCDD		· .
VCMPGE_OSPD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGE_OSPD		· .
VCMPGE_OSPD	<pre>xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256</pre>	AVX, SANDYBRIDGE AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD	<pre>xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,xmmrm128</pre>	AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD	<pre>xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256</pre>	AVX,SANDYBRIDGE AVX,SANDYBRIDGE AVX,SANDYBRIDGE AVX,SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD	<pre>xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,xmmrm128</pre>	AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD	<pre>xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,xmmrm128</pre>	AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGT_OSPD	<pre>xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm128 ymmreg,ymmreg*,ymmrm256</pre>	AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGT_OSPD VCMPGTPD	<pre>xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,xmmrm128</pre>	AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGT_OSPD	<pre>xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm128 ymmreg,ymmreg*,ymmrm256</pre>	AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGT_OSPD VCMPGTPD	<pre>xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm128 ymmreg,ymmreg*,ymmrm256</pre>	AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGT_OSPD VCMPGTPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD	<pre>xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,xmmrm128</pre>	AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGT_OSPD VCMPGTPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD VCMPTRUE_UQPD	<pre>xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256</pre>	AVX, SANDYBRIDGE AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGT_OSPD VCMPGTPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD	<pre>xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,xmmrm128</pre>	AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGT_OSPD VCMPGTPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD VCMPTRUE_UQPD	<pre>xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,xmmrm128</pre>	AVX, SANDYBRIDGE AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGT_OSPD VCMPGTPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD VCMPTRUE_UQPD VCMPTRUEPD VCMPTRUEPD	xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 ymmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGTT_OSPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD VCMPTRUE_UQPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD	xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm286 xmmreg,ymmreg*,ymmrm286 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,xmmrm128	AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGTT_OSPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD VCMPTRUE_UQPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD VCMPEQ_OSPD VCMPEQ_OSPD	xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGTT_OSPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD VCMPTRUE_UQPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD	xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGTT_OSPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD VCMPTRUE_UQPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD VCMPEQ_OSPD VCMPLT_OQPD	xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGTT_OSPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD VCMPTRUE_UQPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD VCMPEQ_OSPD VCMPLT_OQPD VCMPLT_OQPD	xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD VCMPEQ_OSPD VCMPLT_OQPD VCMPLT_OQPD VCMPLT_OQPD	xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGTT_OSPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD VCMPTRUE_UQPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD VCMPEQ_OSPD VCMPLT_OQPD VCMPLT_OQPD	xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD VCMPEQ_OSPD VCMPLT_OQPD VCMPLT_OQPD VCMPLT_OQPD	xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGT_OSPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD VCMPTRUE_UQPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD VCMPEQ_OSPD VCMPLT_OQPD VCMPLT_OQPD VCMPLT_OQPD VCMPLE_OQPD VCMPLE_OQPD VCMPLE_OQPD	xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGT_OSPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD VCMPTRUE_UQPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD VCMPEQ_OSPD VCMPLT_OQPD VCMPLT_OQPD VCMPLT_OQPD VCMPLE_OQPD VCMPLE_OQPD VCMPLE_OQPD VCMPLE_OQPD VCMPUNORD_SPD VCMPUNORD_SPD	xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGT_OSPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD VCMPTRUE_UQPD VCMPTRUEPD VCMPTRUEPD VCMPEQ_OSPD VCMPLT_OQPD VCMPLT_OQPD VCMPLT_OQPD VCMPLE_OQPD VCMPLE_OQPD VCMPLE_OQPD VCMPUNORD_SPD VCMPUNORD_SPD VCMPUNORD_SPD VCMPNEQ_USPD	xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGT_OSPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD VCMPTRUE_UQPD VCMPTRUEPD VCMPTRUEPD VCMPTRUEPD VCMPEQ_OSPD VCMPLT_OQPD VCMPLT_OQPD VCMPLT_OQPD VCMPLE_OQPD VCMPLE_OQPD VCMPLE_OQPD VCMPLE_OQPD VCMPUNORD_SPD VCMPUNORD_SPD	xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGT_OSPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD VCMPTRUE_UQPD VCMPTRUEPD VCMPTRUEPD VCMPEQ_OSPD VCMPLT_OQPD VCMPLT_OQPD VCMPLE_OQPD VCMPLE_OQPD VCMPLE_OQPD VCMPLE_OQPD VCMPUNORD_SPD VCMPUNORD_SPD VCMPNEQ_USPD VCMPNEQ_USPD	xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGTT_OSPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD VCMPTRUE_UQPD VCMPTRUEPD VCMPTRUEPD VCMPEQ_OSPD VCMPLT_OQPD VCMPLT_OQPD VCMPLE_OQPD VCMPLE_OQPD VCMPLE_OQPD VCMPUNORD_SPD VCMPUNORD_SPD VCMPNEQ_USPD VCMPNEQ_USPD VCMPNEQ_USPD VCMPNLT_UQPD	xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGTT_OSPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD VCMPTRUEPD VCMPTRUEPD VCMPEQ_OSPD VCMPLT_OQPD VCMPLT_OQPD VCMPLE_OQPD VCMPLE_OQPD VCMPLE_OQPD VCMPUNORD_SPD VCMPUNORD_SPD VCMPNEQ_USPD VCMPNLT_UQPD VCMPNLT_UQPD VCMPNLT_UQPD VCMPNLT_UQPD VCMPNLT_UQPD VCMPNLT_UQPD	xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGT_OSPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD VCMPTRUE_UQPD VCMPTRUEPD VCMPTRUEPD VCMPEQ_OSPD VCMPLT_OQPD VCMPLT_OQPD VCMPLT_OQPD VCMPLE_OQPD VCMPUNORD_SPD VCMPUNORD_SPD VCMPNEQ_USPD VCMPNEQ_USPD VCMPNLT_UQPD	xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,ymmreg*,ymmmm256 xmmreg,ymmreg*,ymmmm256	AVX, SANDYBRIDGE
VCMPGE_OSPD VCMPGEPD VCMPGEPD VCMPGEPD VCMPGT_OSPD VCMPGTT_OSPD VCMPGTPD VCMPGTPD VCMPTRUE_UQPD VCMPTRUEPD VCMPTRUEPD VCMPEQ_OSPD VCMPLT_OQPD VCMPLT_OQPD VCMPLE_OQPD VCMPLE_OQPD VCMPLE_OQPD VCMPUNORD_SPD VCMPUNORD_SPD VCMPNEQ_USPD VCMPNLT_UQPD VCMPNLT_UQPD VCMPNLT_UQPD VCMPNLT_UQPD VCMPNLT_UQPD VCMPNLT_UQPD	xmmreg,xmmreg*,xmmrm128 ymmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256 xmmreg,xmmreg*,ymmrm256 xmmreg,ymmreg*,ymmrm256	AVX, SANDYBRIDGE

```
VCMPORD_SPD
                                               AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
                   ymmreg,ymmreg*,ymmrm256
xmmreg,xmmreg*,xmmrm128
VCMPORD_SPD
                                               AVX, SANDYBRIDGE
VCMPEQ_USPD
                                                AVX, SANDYBRIDGE
VCMPEQ_USPD
                   ymmreg, ymmreg*, ymmrm256
                                                AVX, SANDYBRIDGE
VCMPNGE_UQPD
                                               AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
VCMPNGE_UQPD
                                               AVX, SANDYBRIDGE
                   ymmreg,ymmreg*,ymmrm256
                   xmmreg,xmmreg*,xmmrm128
ymmreg,ymmreg*,ymmrm256
xmmreg,xmmreg*,xmmrm128
VCMPNGT_UQPD
                                                AVX, SANDYBRIDGE
VCMPNGT UQPD
                                                AVX, SANDYBRIDGE
VCMPFALSE_OSPD
                                                AVX, SANDYBRIDGE
VCMPFALSE_OSPD
                   ymmreg,ymmreg*,ymmrm256
                                                AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
VCMPNEQ_OSPD
                                                AVX, SANDYBRIDGE
VCMPNEQ_OSPD
                   ymmreg,ymmreg*,ymmrm256
                                                AVX, SANDYBRIDGE
VCMPGE_OQPD
                   xmmreg,xmmreg*,xmmrm128
ymmreg,ymmreg*,ymmrm256
                                               AVX, SANDYBRIDGE
VCMPGE_OQPD
                                               AVX, SANDYBRIDGE
VCMPGT_OQPD
                   xmmreg,xmmreg*,xmmrm128
                                                AVX, SANDYBRIDGE
VCMPGT_OQPD
                   ymmreg,ymmreg*,ymmrm256
                                               AVX, SANDYBRIDGE
VCMPTRUE_USPD
                                                AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
                   ymmreg,ymmreg*,ymmrm256 AVX,SANDYBRIDGE
xmmreg,xmmreg*,xmmrm128,imm8 AVX,SANDYBRIDGE
VCMPTRUE_USPD
VCMPPD
VCMPPD
                   ymmreg,ymmreg*,ymmrm256,imm8 AVX,SANDYBRIDGE
VCMPEQ_OSPS
                   xmmreg,xmmreg*,xmmrm128
                                               AVX, SANDYBRIDGE
VCMPEQ_OSPS
                   ymmreg,ymmreg*,ymmrm256
                                                AVX, SANDYBRIDGE
VCMPEOPS
                   xmmreg,xmmreg*,xmmrm128
                                                AVX, SANDYBRIDGE
VCMPEQPS
                   ymmreg,ymmreg*,ymmrm256
                                               AVX.SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
VCMPLT_OSPS
                                               AVX, SANDYBRIDGE
VCMPLT_OSPS
                   ymmreg,ymmreg*,ymmrm256
                                                AVX, SANDYBRIDGE
VCMPLTPS
                   xmmreg,xmmreg*,xmmrm128
                                               AVX, SANDYBRIDGE
VCMPLTPS
                                               AVX, SANDYBRIDGE
                   ymmreg,ymmreg*,ymmrm256
VCMPLE_OSPS
                   xmmreg,xmmreg*,xmmrm128
                                               AVX, SANDYBRIDGE
VCMPLE_OSPS
                   ymmreg,ymmreg*,ymmrm256
                                               AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
VCMPLEPS
                                                AVX, SANDYBRIDGE
VCMPLEPS
                   ymmreg,ymmreg*,ymmrm256
                                                AVX, SANDYBRIDGE
VCMPUNORD_QPS
                                                AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
VCMPUNORD_QPS
                   ymmreg,ymmreg*,ymmrm256
                                                AVX, SANDYBRIDGE
VCMPUNORDPS
                   xmmreg,xmmreg*,xmmrm128
                                               AVX, SANDYBRIDGE
                                               AVX, SANDYBRIDGE
VCMPUNORDPS
                   ymmreg,ymmreg*,ymmrm256
VCMPNEQ_UQPS
                   xmmreg,xmmreg*,xmmrm128
                                                AVX, SANDYBRIDGE
VCMPNEQ_UQPS
                                               AVX, SANDYBRIDGE
                   ymmreg,ymmreg*,ymmrm256
VCMPNEQPS
                                               AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
VCMPNEQPS
                                               AVX, SANDYBRIDGE
                   ymmreg,ymmreg*,ymmrm256
                   xmmreg,xmmreg*,xmmrm128
VCMPNLT_USPS
                                               AVX, SANDYBRIDGE
                   ymmreg,ymmreg*,ymmrm256
VCMPNLT_USPS
                                                AVX, SANDYBRIDGE
VCMPNLTPS
                   xmmreg,xmmreg*,xmmrm128
                                                AVX, SANDYBRIDGE
VCMPNLTPS
                                                AVX, SANDYBRIDGE
                   ymmreg,ymmreg*,ymmrm256
VCMPNLE_USPS
                   xmmreg,xmmreg*,xmmrm128
                                                AVX, SANDYBRIDGE
                   ymmreg,ymmreg*,ymmrm256
xmmreg,xmmreg*,xmmrm128
VCMPNLE_USPS
                                               AVX, SANDYBRIDGE
VCMPNLEPS
                                               AVX, SANDYBRIDGE
VCMPNLEPS
                   ymmreg,ymmreg*,ymmrm256
                                                AVX, SANDYBRIDGE
VCMPORD_QPS
                   xmmreg,xmmreg*,xmmrm128
                                               AVX, SANDYBRIDGE
VCMPORD_QPS
                                               AVX, SANDYBRIDGE
                   ymmreg,ymmreg*,ymmrm256
                   xmmreg,xmmreg*,xmmrm128
ymmreg,ymmreg*,ymmrm256
VCMPORDPS
                                                AVX, SANDYBRIDGE
VCMPORDPS
                                                AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
VCMPEQ_UQPS
                                                AVX, SANDYBRIDGE
VCMPEQ_UQPS
                   ymmreg,ymmreg*,ymmrm256
                                                AVX, SANDYBRIDGE
VCMPNGE_USPS
                   xmmreg,xmmreg*,xmmrm128
                                                AVX, SANDYBRIDGE
                   {\tt ymmreg,ymmreg^*_.,ymmrm256}
VCMPNGE_USPS
                                                AVX, SANDYBRIDGE
VCMPNGEPS
                   xmmreg,xmmreg*,xmmrm128
                                               AVX, SANDYBRIDGE
VCMPNGEPS
                   ymmreg,ymmreg*,ymmrm256
                                                AVX, SANDYBRIDGE
VCMPNGT_USPS
                   xmmreg, xmmreg*, xmmrm128
                                                AVX, SANDYBRIDGE
VCMPNGT_USPS
                                               AVX, SANDYBRIDGE
                   ymmreg,ymmreg*,ymmrm256
VCMPNGTPS
                   xmmreg,xmmreg*,xmmrm128
                                               AVX, SANDYBRIDGE
                   ymmreg,ymmreg*,ymmrm256
xmmreg,xmmreg*,xmmrm128
ymmreg,ymmreg*,ymmrm256
VCMPNGTPS
                                                AVX, SANDYBRIDGE
VCMPFALSE_OQPS
                                                AVX, SANDYBRIDGE
VCMPFALSE_OQPS
                                                AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
VCMPFALSEPS
                                                AVX, SANDYBRIDGE
                   {\tt ymmreg,ymmreg*,ymmrm256}
VCMPFALSEPS
                                                AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
VCMPNEQ_OQPS
                                               AVX, SANDYBRIDGE
```

```
VCMPNEQ_OQPS
                  ymmreg,ymmreg*,ymmrm256
                                              AVX, SANDYBRIDGE
                  xmmreg,xmmreg*,xmmrm128
ymmreg,ymmreg*,ymmrm256
VCMPGE_OSPS
                                              AVX, SANDYBRIDGE
VCMPGE_OSPS
                                               AVX, SANDYBRIDGE
VCMPGEPS
                   xmmreg,xmmreg*,xmmrm128
                                               AVX, SANDYBRIDGE
                                              AVX, SANDYBRIDGE
VCMPGEPS
                   ymmreg,ymmreg*,ymmrm256
VCMPGT_OSPS
                                              AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
                  ymmreg,ymmreg*,ymmrm256
xmmreg,xmmreg*,xmmrm128
ymmreg,ymmreg*,ymmrm256
VCMPGT_OSPS
                                               AVX, SANDYBRIDGE
VCMPGTPS
                                               AVX, SANDYBRIDGE
VCMPGTPS
                                               AVX, SANDYBRIDGE
VCMPTRUE_UQPS
                   xmmreg,xmmreg*,xmmrm128
                                               AVX, SANDYBRIDGE
VCMPTRUE_UQPS
                   ymmreg,ymmreg*,ymmrm256
                                               AVX, SANDYBRIDGE
VCMPTRUEPS
                   xmmreg,xmmreg*,xmmrm128
                                               AVX, SANDYBRIDGE
                  ymmreg,ymmreg*,ymmrm256
xmmreg,xmmreg*,xmmrm128
VCMPTRUEPS
                                               AVX, SANDYBRIDGE
VCMPEQ_OSPS
                                              AVX, SANDYBRIDGE
VCMPEQ_OSPS
                   ymmreg,ymmreg*,ymmrm256
                                               AVX, SANDYBRIDGE
VCMPLT_OQPS
                   xmmreg,xmmreg*,xmmrm128
                                              AVX, SANDYBRIDGE
VCMPLT_OQPS
                   ymmreg,ymmreg*,ymmrm256
                                              AVX, SANDYBRIDGE
                  xmmreg,xmmreg*,xmmrm128
ymmreg,ymmreg*,ymmrm256
VCMPLE_OQPS
                                               AVX, SANDYBRIDGE
VCMPLE_OQPS
                                               AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
VCMPUNORD_SPS
                                               AVX, SANDYBRIDGE
VCMPUNORD_SPS
                   ymmreg, ymmreg*, ymmrm256
                                               AVX, SANDYBRIDGE
VCMPNEQ_USPS
                   xmmreg,xmmreg*,xmmrm128
                                               AVX, SANDYBRIDGE
VCMPNEQ_USPS
                   ymmreg,ymmreg*,ymmrm256
                                               AVX, SANDYBRIDGE
VCMPNLT_UQPS
                   xmmreg,xmmreg*,xmmrm128
                                              AVX, SANDYBRIDGE
VCMPNLT_UQPS
                                              AVX, SANDYBRIDGE
                   ymmreg,ymmreg*,ymmrm256
                   xmmreg,xmmreg*,xmmrm128
VCMPNLE_UQPS
                                               AVX, SANDYBRIDGE
VCMPNLE_UQPS
                   ymmreg,ymmreg*,ymmrm256
                                              AVX, SANDYBRIDGE
VCMPORD_SPS
                                              AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
VCMPORD_SPS
                                               AVX, SANDYBRIDGE
                   ymmreg,ymmreg*,ymmrm256
VCMPEQ_USPS
                   xmmreg,xmmreg*,xmmrm128
                                              AVX, SANDYBRIDGE
VCMPEQ_USPS
                   ymmreg,ymmreg*,ymmrm256
                                              AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
VCMPNGE_UQPS
                                               AVX, SANDYBRIDGE
VCMPNGE_UQPS
                                               AVX, SANDYBRIDGE
                   ymmreg,ymmreg*,ymmrm256
VCMPNGT_UQPS
                   xmmreg,xmmreg*,xmmrm128
                                               AVX, SANDYBRIDGE
VCMPNGT_UQPS
                   ymmreg,ymmreg*,ymmrm256
                                              AVX, SANDYBRIDGE
VCMPFALSE_OSPS
                   xmmreg,xmmreg*,xmmrm128
                                              AVX, SANDYBRIDGE
VCMPFALSE_OSPS
                   ymmreg,ymmreg*,ymmrm256
                                               AVX, SANDYBRIDGE
VCMPNEQ_OSPS
                                              AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
VCMPNEQ_OSPS
                                              AVX, SANDYBRIDGE
                   ymmreg,ymmreg*,ymmrm256
VCMPGE_OQPS
                                              AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
VCMPGE_OQPS
                   {\tt ymmreg,ymmreg*,ymmrm256}
                                               AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
VCMPGT_OQPS
                                               AVX, SANDYBRIDGE
VCMPGT_OQPS
                   ymmreg,ymmreg*,ymmrm256
                                               AVX, SANDYBRIDGE
VCMPTRUE_USPS
                   xmmreg,xmmreg*,xmmrm128
                                               AVX, SANDYBRIDGE
VCMPTRUE_USPS
                   ymmreg,ymmreg*,ymmrm256
                                              AVX, SANDYBRIDGE
VCMPPS
                   xmmreg,xmmreg*,xmmrm128,imm8 AVX,SANDYBRIDGE
VCMPPS
                   ymmreg,ymmreg*,ymmrm256,imm8 AVX,SANDYBRIDGE
VCMPEQ_OSSD
                   xmmreg,xmmreg*,xmmrm64
                                               AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm64
                                              AVX, SANDYBRIDGE
VCMPEQSD
VCMPLT_OSSD
                                              AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm64
                  xmmreg,xmmreg*,xmmrm64
xmmreg,xmmreg*,xmmrm64
VCMPLTSD
                                               AVX, SANDYBRIDGE
VCMPLE OSSD
                                               AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm64
VCMPLESD
                                               AVX, SANDYBRIDGE
VCMPUNORD_QSD
                   xmmreg,xmmreg*,xmmrm64
                                               AVX, SANDYBRIDGE
VCMPUNORDSD
                   xmmreg,xmmreg*,xmmrm64
                                               AVX, SANDYBRIDGE
VCMPNEQ_UQSD
                                               AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm64
VCMPNEQSD
                   xmmreg,xmmreg*,xmmrm64
                                               AVX, SANDYBRIDGE
VCMPNLT USSD
                   xmmreg,xmmreg*,xmmrm64
                                               AVX, SANDYBRIDGE
VCMPNLTSD
                   xmmreg, xmmreg*, xmmrm64
                                               AVX, SANDYBRIDGE
                                               AVX, SANDYBRIDGE
VCMPNLE_USSD
                   xmmreg,xmmreg*,xmmrm64
VCMPNLESD
                                               AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm64
VCMPORD_QSD
                                               AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm64
                  xmmreg,xmmreg*,xmmrm64
xmmreg,xmmreg*,xmmrm64
VCMPORDSD
                                               AVX, SANDYBRIDGE
VCMPEQ_UQSD
                                               AVX, SANDYBRIDGE
VCMPNGE_USSD
                   xmmreg,xmmreg*,xmmrm64
                                               AVX, SANDYBRIDGE
                   xmmreg, xmmreg*, xmmrm64
                                               AVX, SANDYBRIDGE
VCMPNGESD
VCMPNGT_USSD
                   xmmreg,xmmreg*,xmmrm64
                                               AVX, SANDYBRIDGE
```

AVX, SANDYBRIDGE **VCMPNGTSD** xmmreg,xmmreg*,xmmrm64 VCMPFALSE_OQSD xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE xmmreg,xmmreg*,xmmrm64 VCMPFALSESD AVX, SANDYBRIDGE VCMPNEQ_OQSD xmmreg, xmmreg*, xmmrm64 AVX, SANDYBRIDGE VCMPGE_OSSD AVX, SANDYBRIDGE xmmreg,xmmreg*,xmmrm64 **VCMPGESD** AVX, SANDYBRIDGE xmmreg,xmmreg*,xmmrm64 xmmreg,xmmreg*,xmmrm64
xmmreg,xmmreg*,xmmrm64 VCMPGT_OSSD AVX, SANDYBRIDGE VCMPGTSD AVX, SANDYBRIDGE xmmreg,xmmreg*,xmmrm64 VCMPTRUE_UQSD AVX, SANDYBRIDGE **VCMPTRUESD** xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE VCMPEQ_OSSD xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE VCMPLT_OQSD xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE VCMPLE_OQSD xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE xmmreg,xmmreg*,xmmrm64 VCMPUNORD_SSD AVX, SANDYBRIDGE VCMPNEQ_USSD xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE VCMPNLT_UQSD xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE VCMPNLE_UQSD AVX, SANDYBRIDGE xmmreg,xmmreg*,xmmrm64 xmmreg,xmmreg*,xmmrm64
xmmreg,xmmreg*,xmmrm64 VCMPORD_SSD AVX, SANDYBRIDGE VCMPEQ_USSD AVX, SANDYBRIDGE xmmreg,xmmreg*,xmmrm64 VCMPNGE_UQSD AVX, SANDYBRIDGE VCMPNGT_UQSD xmmreg, xmmreg*, xmmrm64 AVX, SANDYBRIDGE VCMPFALSE_OSSD $\verb|xmmreg,xmmreg*|, \verb|xmmrm64||$ AVX, SANDYBRIDGE VCMPNEQ_OSSD xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE VCMPGE_OQSD xmmreg,xmmreg*,xmmrm64 AVX.SANDYBRIDGE VCMPGT_OQSD xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE VCMPTRUE_USSD xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE VCMPSD xmmreg,xmmreg*,xmmrm64,imm8 AVX,SANDYBRIDGE VCMPEQ OSSS AVX, SANDYBRIDGE xmmreg,xmmreg*,xmmrm64 **VCMPEQSS** xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE VCMPLT_OSSS xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE **VCMPLTSS** xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE VCMPLE_OSSS xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE AVX, SANDYBRIDGE **VCMPLESS** xmmreg,xmmreg*,xmmrm64 VCMPUNORD_QSS AVX, SANDYBRIDGE xmmreg,xmmreg*,xmmrm64 **VCMPUNORDSS** xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE VCMPNEO UOSS xmmreg,xmmreg*,xmmrm64 AVX.SANDYBRIDGE **VCMPNEQSS** xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE VCMPNLT_USSS AVX, SANDYBRIDGE xmmreg,xmmreg*,xmmrm64 **VCMPNLTSS** AVX, SANDYBRIDGE xmmreg,xmmreg*,xmmrm64 VCMPNLE_USSS AVX, SANDYBRIDGE xmmreg,xmmreg*,xmmrm64 xmmreg,xmmreg*,xmmrm64 **VCMPNLESS** AVX.SANDYBRIDGE xmmreg,xmmreg*,xmmrm64 VCMPORD_QSS AVX, SANDYBRIDGE **VCMPORDSS** xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE AVX, SANDYBRIDGE VCMPEQ_UQSS xmmreg,xmmreg*,xmmrm64 VCMPNGE_USSS xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE **VCMPNGESS** xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE xmmreg,xmmreg*,xmmrm64 VCMPNGT USSS AVX, SANDYBRIDGE **VCMPNGTSS** xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE VCMPFALSE_OQSS AVX, SANDYBRIDGE xmmreg,xmmreg*,xmmrm64 **VCMPFALSESS** AVX, SANDYBRIDGE xmmreg,xmmreg*,xmmrm64 xmmreg,xmmreg*,xmmrm64
xmmreg,xmmreg*,xmmrm64 VCMPNEQ_OQSS AVX, SANDYBRIDGE VCMPGE OSSS AVX, SANDYBRIDGE xmmreg,xmmreg*,xmmrm64 **VCMPGESS** AVX, SANDYBRIDGE VCMPGT_OSSS xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE VCMPGTSS xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE VCMPTRUE_UQSS xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE **VCMPTRUESS** xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE VCMPEQ OSSS xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE VCMPLT_OQSS xmmreg, xmmreg*, xmmrm64 AVX, SANDYBRIDGE VCMPLE_OQSS AVX, SANDYBRIDGE xmmreg,xmmreg*,xmmrm64 VCMPUNORD_SSS AVX, SANDYBRIDGE xmmreg,xmmreg*,xmmrm64 VCMPNEQ_USSS xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE VCMPNLT UOSS xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE xmmreg,xmmreg*,xmmrm64 VCMPNLE_UQSS AVX, SANDYBRIDGE VCMPORD_SSS xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE VCMPEQ_USSS AVX, SANDYBRIDGE xmmreg,xmmreg*,xmmrm64 AVX, SANDYBRIDGE VCMPNGE_UQSS xmmreg,xmmreg*,xmmrm64

```
AVX, SANDYBRIDGE
VCMPNGT_UQSS
                   xmmreg,xmmreg*,xmmrm64
                  xmmreg,xmmreg*,xmmrm64
xmmreg,xmmreg*,xmmrm64
VCMPFALSE_OSSS
                                              AVX, SANDYBRIDGE
                                              AVX, SANDYBRIDGE
VCMPNEQ OSSS
VCMPGE_OQSS
                   xmmreg,xmmreg*,xmmrm64
                                              AVX, SANDYBRIDGE
VCMPGT_OQSS
                                              AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm64
VCMPTRUE_USSS
                                              AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm64
VCMPSS
                   xmmreg,xmmreg*,xmmrm64,imm8 AVX,SANDYBRIDGE
VCOMISD
                                              AVX, SANDYBRIDGE
                  xmmreg,xmmrm64
VCOMISS
                   xmmreg,xmmrm32
                                              AVX, SANDYBRIDGE
VCVTDQ2PD
                                              AVX, SANDYBRIDGE
                   xmmreg,xmmrm64
VCVTDQ2PD
                                              AVX, SANDYBRIDGE
                  ymmreg,xmmrm128
VCVTDQ2PS
                   xmmreg,xmmrm128
                                              AVX, SANDYBRIDGE
VCVTDQ2PS
                                              AVX, SANDYBRIDGE
                  ymmreg,ymmrm256
                                              AVX, SANDYBRIDGE
VCVTPD2DQ
                   xmmreg,xmmreg
VCVTPD2DQ
                                              AVX, SANDYBRIDGE, SO
                   xmmreg, mem128
VCVTPD2D0
                   xmmreg, ymmreg
                                              AVX, SANDYBRIDGE
VCVTPD2DQ
                                              AVX, SANDYBRIDGE, SY
                  xmmreg,mem256
VCVTPD2PS
                   xmmreg,xmmreg
                                              AVX, SANDYBRIDGE
VCVTPD2PS
                                              AVX, SANDYBRIDGE, SO
                  xmmreg,mem128
VCVTPD2PS
                                              AVX, SANDYBRIDGE
                  xmmreg,ymmreg
VCVTPD2PS
                                              AVX, SANDYBRIDGE, SY
                   xmmreg, mem256
VCVTPS2DQ
                                              AVX, SANDYBRIDGE
                  xmmreg,xmmrm128
VCVTPS2DQ
                  ymmreg,ymmrm256
                                              AVX, SANDYBRIDGE
VCVTPS2PD
                  xmmreg,xmmrm64
                                              AVX, SANDYBRIDGE
VCVTPS2PD
                                              AVX, SANDYBRIDGE
                  ymmreg,xmmrm128
                                              AVX, SANDYBRIDGE
VCVTSD2SI
                   reg32,xmmrm64
VCVTSD2SI
                   reg64,xmmrm64
                                              AVX, SANDYBRIDGE, LONG
VCVTSD2SS
                                              AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm64
                  xmmreg,xmmreg*,rm32
xmmreg,xmmreg*,mem32
VCVTSI2SD
                                              AVX, SANDYBRIDGE, SD
VCVTSI2SD
                                              AVX, SANDYBRIDGE, ND, SD
                   xmmreg,xmmreg*,rm64
VCVTSI2SD
                                              AVX, SANDYBRIDGE, LONG
VCVTSI2SS
                   xmmreg,xmmreg*,rm32
                                              AVX, SANDYBRIDGE, SD
VCVTSI2SS
                                              AVX, SANDYBRIDGE, ND, SD
                  xmmreg,xmmreg*,mem32
VCVTSI2SS
                   xmmreg,xmmreg*,rm64
                                              AVX, SANDYBRIDGE, LONG
VCVTSS2SD
                   xmmreg,xmmreg*,xmmrm32
                                              AVX, SANDYBRIDGE
VCVTSS2SI
                                              AVX, SANDYBRIDGE
                   reg32,xmmrm32
VCVTSS2SI
                                              AVX, SANDYBRIDGE, LONG
                   reg64,xmmrm32
VCVTTPD2DQ
                                              AVX, SANDYBRIDGE
                   xmmreg, xmmreg
VCVTTPD2DQ
                                              AVX, SANDYBRIDGE, SO
                   xmmreg,mem128
VCVTTPD2DQ
                                              AVX, SANDYBRIDGE
                   xmmreg,ymmreg
VCVTTPD2DQ
                  xmmreg, mem256
                                              AVX, SANDYBRIDGE, SY
VCVTTPS2DQ
                                              AVX, SANDYBRIDGE
                   xmmreg,xmmrm128
VCVTTPS2DQ
                  ymmreg,ymmrm256
                                              AVX, SANDYBRIDGE
VCVTTSD2SI
                                              AVX, SANDYBRIDGE
                   reg32,xmmrm64
VCVTTSD2SI
                   reg64,xmmrm64
                                              AVX, SANDYBRIDGE, LONG
VCVTTSS2SI
                   reg32,xmmrm32
                                              AVX, SANDYBRIDGE
VCVTTSS2SI
                   reg64,xmmrm32
                                              AVX, SANDYBRIDGE, LONG
VDIVPD
                                              AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
VDIVPD
                  ymmreg,ymmreg*,ymmrm256
                                              AVX, SANDYBRIDGE
VDIVPS
                   xmmreg,xmmreg*,xmmrm128
                                              AVX, SANDYBRIDGE
                  ymmreg,ymmreg*,ymmrm256
xmmreg,xmmreg*,xmmrm64
VDIVPS
                                              AVX, SANDYBRIDGE
VDIVSD
                                              AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm32
VDIVSS
                                              AVX, SANDYBRIDGE
VDPPD
                   xmmreg,xmmreg*,xmmrm128,imm8 AVX,SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128,imm8 AVX,SANDYBRIDGE
VDPPS
                  {\tt ymmreg,ymmreg*,ymmrm256,imm8~AVX,SANDYBRIDGE}
VDPPS
VEXTRACTF128
                   xmmrm128,ymmreg,imm8
                                              AVX, SANDYBRIDGE
VEXTRACTPS
                                              AVX, SANDYBRIDGE
                   rm32,xmmreg,imm8
VHADDPD
                   xmmreg,xmmreg*,xmmrm128
                                              AVX, SANDYBRIDGE
                  ymmreg,ymmreg*,ymmrm256
                                              AVX, SANDYBRIDGE
VHADDPD
VHADDPS
                   xmmreg,xmmreg*,xmmrm128
                                              AVX, SANDYBRIDGE
                  ymmreg,ymmreg*,ymmrm256
xmmreg,xmmreg*,xmmrm128
ymmreg,ymmreg*,ymmrm256
VHADDPS
                                              AVX, SANDYBRIDGE
VHSUBPD
                                              AVX, SANDYBRIDGE
VHSUBPD
                                              AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
VHSUBPS
                                              AVX, SANDYBRIDGE
                  ymmreg,ymmreg*,ymmrm256
                                              AVX, SANDYBRIDGE
VHSUBPS
VINSERTF128
                  ymmreg,ymmreg*,xmmrm128,imm8 AVX,SANDYBRIDGE
```

```
VINSERTPS
                   xmmreg,xmmreg*,xmmrm32,imm8 AVX,SANDYBRIDGE
VLDDOU
                   xmmreg, mem128
                                              AVX, SANDYBRIDGE
VLDQQU
                  ymmreg, mem256
                                              AVX, SANDYBRIDGE
VLDDQU
                  ymmreg, mem256
                                              AVX, SANDYBRIDGE
VLDMXCSR
                  mem32
                                              AVX, SANDYBRIDGE
VMASKMOVDQU
                   xmmreg,xmmreg
                                              AVX, SANDYBRIDGE
VMASKMOVPS
                  xmmreg, xmmreg, mem128
                                              AVX, SANDYBRIDGE
VMASKMOVPS
                                              AVX, SANDYBRIDGE
                  ymmreg, ymmreg, mem256
VMASKMOVPS
                  mem128,xmmreg,xmmreg
                                              AVX, SANDYBRIDGE, SO
VMASKMOVPS
                                              AVX, SANDYBRIDGE, SY
                  mem256,ymmreg,ymmreg
VMASKMOVPD
                                              AVX, SANDYBRIDGE
                   xmmreg,xmmreg,mem128
VMASKMOVPD
                  ymmreg, ymmreg, mem256
                                              AVX, SANDYBRIDGE
VMASKMOVPD
                                              AVX, SANDYBRIDGE
                  mem128,xmmreg,xmmreg
VMASKMOVPD
                  mem256,ymmreg,ymmreg
                                              AVX, SANDYBRIDGE
VMAXPD
                  xmmreg,xmmreg*,xmmrm128
                                              AVX, SANDYBRIDGE
                  {\tt ymmreg,ymmreg*,ymmrm256}
VMAXPD
                                              AVX, SANDYBRIDGE
                  xmmreg,xmmreg*,xmmrm128
ymmreg,ymmreg*,ymmrm256
xmmreg,xmmreg*,xmmrm64
VMAXPS
                                              AVX, SANDYBRIDGE
VMAXPS
                                              AVX, SANDYBRIDGE
VMAXSD
                                              AVX, SANDYBRIDGE
VMAXSS
                   xmmreg,xmmreg*,xmmrm32
                                              AVX, SANDYBRIDGE
                                              AVX, SANDYBRIDGE
VMINPD
                   xmmreg,xmmreg*,xmmrm128
VMINPD
                  ymmreg,ymmreg*,ymmrm256
                                              AVX, SANDYBRIDGE
                  xmmreg,xmmreg*,xmmrm128
ymmreg,ymmreg*,ymmrm256
VMINPS
                                              AVX, SANDYBRIDGE
VMINPS
                                              AVX, SANDYBRIDGE
                  xmmreg,xmmreg*,xmmrm64
VMINSD
                                              AVX, SANDYBRIDGE
VMINSS
                   xmmreg,xmmreg*,xmmrm32
                                              AVX, SANDYBRIDGE
                   xmmreg,xmmrm128
VMOVAPD
                                              AVX, SANDYBRIDGE
VMOVAPD
                   xmmrm128,xmmreg
                                              AVX, SANDYBRIDGE
VMOVAPD
                  ymmreg,ymmrm256
                                              AVX, SANDYBRIDGE
VMOVAPD
                  ymmrm256,ymmreg
                                              AVX, SANDYBRIDGE
VMOVAPS
                   xmmreg,xmmrm128
                                              AVX, SANDYBRIDGE
                                              AVX, SANDYBRIDGE
VMOVAPS
                   xmmrm128,xmmreg
VMOVAPS
                  ymmreg,ymmrm256
                                              AVX, SANDYBRIDGE
VMOVAPS
                  ymmrm256,ymmreg
                                              AVX, SANDYBRIDGE
VMOVD
                  xmmreg, rm32
                                              AVX, SANDYBRIDGE
VMOVD
                   rm32.xmmreg
                                              AVX.SANDYBRIDGE
VMOVQ
                   xmmreg,xmmrm64
                                              AVX, SANDYBRIDGE
                                              AVX, SANDYBRIDGE
VMOVO
                   xmmrm64,xmmreg
VMOVQ
                   xmmreg, rm64
                                              AVX, SANDYBRIDGE, LONG
VMOVQ
                   rm64,xmmreg
                                              AVX, SANDYBRIDGE, LONG
VMOVDDUP
                  xmmreg,xmmrm64
                                              AVX, SANDYBRIDGE
VMOVDDUP
                                              AVX, SANDYBRIDGE
                  ymmreg,ymmrm256
VMOVDOA
                   xmmreg,xmmrm128
                                              AVX, SANDYBRIDGE
VMOVDQA
                   xmmrm128,xmmreg
                                              AVX, SANDYBRIDGE
VMOVQQA
                  ymmreg,ymmrm256
                                              AVX, SANDYBRIDGE
VMOVQQA
                  ymmrm256,ymmreg
                                              AVX, SANDYBRIDGE
VMOVDQA
                  ymmreg,ymmrm256
                                              AVX, SANDYBRIDGE
VMOVDQA
                  ymmrm256,ymmreg
                                              AVX, SANDYBRIDGE
VMOVDQU
                                              AVX, SANDYBRIDGE
                   xmmreg,xmmrm128
VMOVDQU
                   xmmrm128,xmmreg
                                              AVX, SANDYBRIDGE
VMOVQQU
                  ymmreg,ymmrm256
                                              AVX, SANDYBRIDGE
VMOVQQU
                  ymmrm256,ymmreg
                                              AVX.SANDYBRIDGE
VMOVDQU
                                              AVX, SANDYBRIDGE
                  ymmreg,ymmrm256
                                              AVX, SANDYBRIDGE
VMOVDOU
                  ymmrm256,ymmreg
                   xmmreg,xmmreg*,xmmreg
VMOVHLPS
                                              AVX, SANDYBRIDGE
VMOVHPD
                   xmmreg,xmmreg*,mem64
                                              AVX, SANDYBRIDGE
VMOVHPD
                                              AVX, SANDYBRIDGE
                  mem64,xmmreg
VMOVHPS
                  xmmreg,xmmreg*,mem64
                                              AVX, SANDYBRIDGE
                  mem64,xmmreg
VMOVHPS
                                              AVX, SANDYBRIDGE
VMOVI HPS
                                              AVX, SANDYBRIDGE
                  xmmreg,xmmreg*,xmmreg
VMOVLPD
                   xmmreg,xmmreg*,mem64
                                              AVX, SANDYBRIDGE
VMOVLPD
                  mem64,xmmreg
                                              AVX, SANDYBRIDGE
VMOVLPS
                  xmmreg,xmmreg*,mem64
                                              AVX, SANDYBRIDGE
VMOVLPS
                  mem64,xmmreg
                                              AVX, SANDYBRIDGE
                                              AVX, SANDYBRIDGE, LONG
VMOVMSKPD
                   reg64,xmmreg
VMOVMSKPD
                                              AVX, SANDYBRIDGE
                   reg32,xmmreg
VMOVMSKPD
                                              AVX, SANDYBRIDGE, LONG
                   reg64, ymmreg
```

```
VMOVMSKPD
                                                AVX, SANDYBRIDGE
                   reg32, ymmreg
VMOVMSKPS
                   reg64,xmmreg
                                                AVX, SANDYBRIDGE, LONG
VMOVMSKPS
                   reg32,xmmreg
                                                AVX, SANDYBRIDGE
VMOVMSKPS
                   reg64, ymmreg
                                                AVX, SANDYBRIDGE, LONG
VMOVMSKPS
                                                AVX, SANDYBRIDGE
                   reg32, ymmreg
VMOVNTDQ
                   mem128,xmmreg
                                                AVX, SANDYBRIDGE
VMOVNTQQ
                   mem256,ymmreg
                                                AVX, SANDYBRIDGE
VMOVNTDO
                   mem256,ymmreg
                                                AVX, SANDYBRIDGE
VMOVNTDQA
                                                AVX, SANDYBRIDGE
                   xmmreg, mem128
                                                AVX, SANDYBRIDGE
VMOVNTPD
                   mem128,xmmreg
VMOVNTPD
                                                AVX, SANDYBRIDGE
                   mem256,ymmreg
VMOVNTPS
                                                AVX, SANDYBRIDGE
                   mem128,xmmreg
VMOVNTPS
                                                AVX, SANDYBRIDGE
                   mem256,ymmreg
VMOVSD
                   xmmreg,xmmreg*,xmmreg
                                                AVX, SANDYBRIDGE
VMOVSD
                   xmmreg, mem64
                                                AVX, SANDYBRIDGE
                                                AVX, SANDYBRIDGE
VMOVSD
                   xmmreg,xmmreg*,xmmreg
                   mem64,xmmreg
VMOVSD
                                                AVX, SANDYBRIDGE
VMOVSHDUP
                   xmmreg,xmmrm128
                                                AVX, SANDYBRIDGE
                                                AVX, SANDYBRIDGE
VMOVSHDUP
                   ymmreg,ymmrm256
VMOVSLDUP
                   xmmreg,xmmrm128
                                                AVX, SANDYBRIDGE
                                                AVX, SANDYBRIDGE
VMOVSLDUP
                   ymmreg,ymmrm256
VMOVSS
                   xmmreg,xmmreg*,xmmreg
                                                AVX, SANDYBRIDGE
VMOVSS
                                                AVX, SANDYBRIDGE
                   xmmreg, mem32
VMOVSS
                   xmmreg,xmmreg*,xmmreg
                                                AVX, SANDYBRIDGE
VMOVSS
                                                AVX, SANDYBRIDGE
                   mem32,xmmreg
VMOVUPD
                   xmmreg,xmmrm128
                                                AVX, SANDYBRIDGE
VMOVUPD
                                                AVX, SANDYBRIDGE
                   xmmrm128,xmmreg
                   ymmreg,ymmrm256
VMOVUPD
                                                AVX, SANDYBRIDGE
VMOVUPD
                   ymmrm256,ymmreg
                                                AVX, SANDYBRIDGE
VMOVUPS
                                                AVX, SANDYBRIDGE
                   xmmreg,xmmrm128
VMOVUPS
                   xmmrm128,xmmreg
                                                AVX, SANDYBRIDGE
                                                AVX, SANDYBRIDGE
VMOVUPS
                   ymmreg,ymmrm256
VMOVUPS
                   ymmrm256,ymmreg
                                                AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128,imm8 AVX,SANDYBRIDGE xmmreg,xmmreg*,xmmrm128 AVX,SANDYBRIDGE
VMPSADBW
VMUI PD
                   ymmreg,ymmreg*,ymmrm256
VMULPD
                                                AVX.SANDYBRIDGE
VMULPS
                   xmmreg,xmmreg*,xmmrm128
                                                AVX, SANDYBRIDGE
VMULPS
                   ymmreg,ymmreg*,ymmrm256
                                                AVX, SANDYBRIDGE
VMUL SD
                   \verb|xmmreg,xmmreg*|, \verb|xmmrm64||
                                                AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm32
xmmreg,xmmreg*,xmmrm128
VMULSS
                                                AVX, SANDYBRIDGE
VORPD
                                                AVX, SANDYBRIDGE
VORPD
                   ymmreg,ymmreg*,ymmrm256
                                                AVX, SANDYBRIDGE
VORPS
                   xmmreg,xmmreg*,xmmrm128
                                                AVX, SANDYBRIDGE
                   {\tt ymmreg,ymmreg*,ymmrm256}
VORPS
                                                AVX, SANDYBRIDGE
VPABSB
                   xmmreg,xmmrm128
                                                AVX, SANDYBRIDGE
                                                AVX, SANDYBRIDGE
VPABSW
                   xmmreg,xmmrm128
VPABSD
                   xmmreg,xmmrm128
                                                AVX, SANDYBRIDGE
VPACKSSWB
                   xmmreg,xmmreg*,xmmrm128
                                                AVX, SANDYBRIDGE
VPACKSSDW
                   \verb|xmmreg,xmmreg*|, \verb|xmmrm128||
                                                AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
xmmreg,xmmreg*,xmmrm128
xmmreg,xmmreg*,xmmrm128
VPACKUSWB
                                                AVX, SANDYBRIDGE
VPACKUSDW
                                                AVX, SANDYBRIDGE
VPADDB
                                                AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
                                                AVX, SANDYBRIDGE
VPADDW
                   xmmreg,xmmreg*,xmmrm128
VPADDD
                                                AVX, SANDYBRIDGE
                                                AVX, SANDYBRIDGE
VPADDO
                   xmmreg,xmmreg*,xmmrm128
                   xmmreg,xmmreg*,xmmrm128
xmmreg,xmmreg*,xmmrm128
VPADDSB
                                                AVX, SANDYBRIDGE
                                                AVX, SANDYBRIDGE
VPADDSW
VPADDUSB
                   xmmreg,xmmreg*,xmmrm128
                                                AVX, SANDYBRIDGE
VPADDUSW
                   xmmreg,xmmreg*,xmmrm128
                                                AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128,imm8 AVX,SANDYBRIDGE
VPALIGNR
                   xmmreg,xmmreg*,xmmrm128
xmmreg,xmmreg*,xmmrm128
xmmreg,xmmreg*,xmmrm128
VPAND
                                                AVX, SANDYBRIDGE
VPANDN
                                                AVX, SANDYBRIDGE
VPAVGB
                                                AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
                                                AVX, SANDYBRIDGE
VPAVGW
VPBLENDVB
                   xmmreg,xmmreg*,xmmrm128,xmmreg AVX,SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128,imm8 AVX,SANDYBRIDGE
VPBI FNDW
VPCMPESTRI
                                                AVX, SANDYBRIDGE
                   xmmreg,xmmrm128,imm8
```

```
VPCMPESTRM
                    xmmreg,xmmrm128,imm8
                                                 AVX, SANDYBRIDGE
VPCMPISTRI
                   xmmreg,xmmrm128,imm8
                                                 AVX, SANDYBRIDGE
VPCMPISTRM
                   xmmreg,xmmrm128,imm8
                                                 AVX, SANDYBRIDGE
VPCMPEQB
                   xmmreg,xmmreg*,xmmrm128
                                                 AVX, SANDYBRIDGE
VPCMPEQW
                   xmmreg,xmmreg*,xmmrm128
                                                 AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
xmmreg,xmmreg*,xmmrm128
xmmreg,xmmreg*,xmmrm128
VPCMPEQD
                                                 AVX, SANDYBRIDGE
VPCMPEQQ
                                                 AVX, SANDYBRIDGE
VPCMPGTB
                                                 AVX, SANDYBRIDGE
                    xmmreg,xmmreg*,xmmrm128
VPCMPGTW
                                                 AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
                                                 AVX, SANDYBRIDGE
VPCMPGTD
                   xmmreg,xmmreg*,xmmrm128
xmmreg,xmmreg*,xmmrm128
ymmreg,ymmreg*,ymmrm256
VPCMPGTO
                                                 AVX, SANDYBRIDGE
VPERMILPD
                                                 AVX, SANDYBRIDGE
VPERMILPD
                                                 AVX, SANDYBRIDGE
                   xmmreg,xmmrm128,imm8
VPERMILPD
                                                 AVX, SANDYBRIDGE
VPERMILPD
                   ymmreg,ymmrm256,imm8
                                                 AVX, SANDYBRIDGE
                    xmmreg,xmmreg*,xmmrm128
                                                 AVX, SANDYBRIDGE
VPFRMTI PS
VPERMILPS
                   ymmreg,ymmreg*,ymmrm256
                                                 AVX, SANDYBRIDGE
VPERMILPS
                   xmmreg,xmmrm128,imm8
                                                 AVX, SANDYBRIDGE
VPERMILPS
                   ymmreg,ymmrm256,imm8
                                                 AVX, SANDYBRIDGE
VPERM2F128
                   ymmreg,ymmreg*,ymmrm256,imm8 AVX,SANDYBRIDGE
VPEXTRB
                    reg64,xmmreg,imm8
                                                 AVX, SANDYBRIDGE, LONG
                    reg32,xmmreg,imm8
VPEXTRB
                                                 AVX, SANDYBRIDGE
VPEXTRB
                   mem8,xmmreg,imm8
                                                 AVX, SANDYBRIDGE
VPFXTRW
                   reg64,xmmreg,imm8
                                                 AVX, SANDYBRIDGE, LONG
VPEXTRW
                    reg32,xmmreg,imm8
                                                 AVX, SANDYBRIDGE
VPEXTRW
                    reg64,xmmreg,imm8
                                                 AVX, SANDYBRIDGE, LONG
VPEXTRW
                    reg32,xmmreg,imm8
                                                 AVX, SANDYBRIDGE
VPEXTRW
                   mem16,xmmreg,imm8
                                                 AVX, SANDYBRIDGE
VPEXTRD
                   reg64,xmmreg,imm8
                                                 AVX, SANDYBRIDGE, LONG
                   rm32,xmmreg,imm8
VPFXTRD
                                                 AVX, SANDYBRIDGE
VPEXTRQ
                    rm64,xmmreg,imm8
                                                 AVX, SANDYBRIDGE, LONG
                    xmmreg,xmmreg*,xmmrm128
                                                 AVX, SANDYBRIDGE
VPHADDW
                   xmmreg,xmmreg*,xmmrm128
xmmreg,xmmreg*,xmmrm128
VPHADDD
                                                 AVX, SANDYBRIDGE
VPHADDSW
                                                 AVX, SANDYBRIDGE
VPHMINPOSUW
                   xmmreg,xmmrm128
                                                 AVX, SANDYBRIDGE
VPHSUBW
                   xmmreg,xmmreg*,xmmrm128
                                                 AVX.SANDYBRIDGE
VPHSUBD
                    xmmreg,xmmreg*,xmmrm128
                                                 AVX, SANDYBRIDGE
                    xmmreg,xmmreg*,xmmrm128 AVX,SANDYBRIDGE
VPHSUBSW
                   xmmreg,xmmreg*,mem8,imm8 AVX,SANDYBRIDGE
xmmreg,xmmreg*,rm8,imm8 AVX,SANDYBRIDGE
VPTNSRB
VPINSRB
                   xmmreg,xmmreg*,reg32,imm8 AVX,SANDYBRIDGE
VPTNSRB
                    xmmreg,xmmreg*,mem16,imm8 AVX,SANDYBRIDGE
VPINSRW
                   xmmreg,xmmreg*,rm16,imm8 AVX,SANDYBRIDGE
VPINSRW
                   xmmreg,xmmreg*,reg32,imm8 AVX,SANDYBRIDGE
xmmreg,xmmreg*,mem32,imm8 AVX,SANDYBRIDGE
VPINSRW
VPINSRD
                   xmmreg,xmmreg*,rm32,imm8 AVX,SANDYBRIDGE
VPINSRD
VPINSRQ
                   xmmreg,xmmreg*,mem64,imm8 AVX,SANDYBRIDGE,LONG
VPINSRQ
                   xmmreg, xmmreg*, rm64, imm8 AVX, SANDYBRIDGE, LONG
VPMADDWD
                   xmmreg,xmmreg*,xmmrm128 AVX,SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
xmmreg,xmmreg*,xmmrm128
xmmreg,xmmreg*,xmmrm128
VPMADDUBSW
                                                 AVX, SANDYBRIDGE
VPMAXSB
                                                 AVX, SANDYBRIDGE
VPMAXSW
                                                 AVX, SANDYBRIDGE
                    xmmreg,xmmreg*,xmmrm128
                                                 AVX, SANDYBRIDGE
VPMAXSD
VPMAXUB
                   xmmreg,xmmreg*,xmmrm128
                                                 AVX, SANDYBRIDGE
                   \verb|xmmreg,xmmreg*,xmmrm128||\\
                                                 AVX, SANDYBRIDGE
VPMAXUW
                   xmmreg,xmmreg*,xmmrm128
xmmreg,xmmreg*,xmmrm128
                                                 AVX, SANDYBRIDGE
VPMAXUD
                                                 AVX, SANDYBRIDGE
VPMINSB
VPMINSW
                   xmmreg,xmmreg*,xmmrm128
                                                 AVX, SANDYBRIDGE
VPMINSD
                    xmmreg,xmmreg*,xmmrm128
                                                 AVX, SANDYBRIDGE
VPMTNUB
                   xmmreg,xmmreg*,xmmrm128
                                                 AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
xmmreg,xmmreg*,xmmrm128
VPMINUW
                                                 AVX, SANDYBRIDGE
VPMINUD
                                                 AVX, SANDYBRIDGE
VPMOVMSKB
                   reg64,xmmreg
                                                 AVX, SANDYBRIDGE, LONG
VPMOVMSKB
                   reg32,xmmreg
                                                 AVX, SANDYBRIDGE
                                                 AVX, SANDYBRIDGE
VPMOVSXBW
                   xmmreg,xmmrm64
VPMOVSXBD
                                                 AVX, SANDYBRIDGE
                   xmmreg,xmmrm32
VPMOVSXBQ
                   xmmreg,xmmrm16
                                                 AVX, SANDYBRIDGE
```

VPMOVSXWD	xmmreg,xmmrm64	AVX, SANDYBRIDGE
VPMOVSXWQ	xmmreg,xmmrm32	AVX, SANDYBRIDGE
•	= :	· .
VPMOVSXDQ	xmmreg,xmmrm64	AVX, SANDYBRIDGE
VPMOVZXBW	xmmreg,xmmrm64	AVX, SANDYBRIDGE
VPMOVZXBD	xmmreg,xmmrm32	AVX, SANDYBRIDGE
VPMOVZXBO	xmmreg,xmmrm16	AVX, SANDYBRIDGE
VPMOVZXWD	xmmreg,xmmrm64	AVX, SANDYBRIDGE
VPMOVZXWQ		· .
	xmmreg,xmmrm32	AVX, SANDYBRIDGE
VPMOVZXDQ	xmmreg,xmmrm64	AVX, SANDYBRIDGE
VPMULHUW	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPMULHRSW	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPMULHW	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPMULLW	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
		•
VPMULLD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPMULUDQ	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPMULDQ	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPOR	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPSADBW	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPSHUFB	xmmreg,xmmreg*,xmmrm128	•
		AVX, SANDYBRIDGE
VPSHUFD	xmmreg,xmmrm128,imm8	AVX, SANDYBRIDGE
VPSHUFHW	xmmreg,xmmrm128,imm8	AVX, SANDYBRIDGE
VPSHUFLW	xmmreg,xmmrm128,imm8	AVX, SANDYBRIDGE
VPSIGNB	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPSIGNW	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPSIGND	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPSLLDQ	xmmreg,xmmreg*,imm8	AVX, SANDYBRIDGE
VPSRLDQ	xmmreg,xmmreg*,imm8	AVX, SANDYBRIDGE
VPSLLW	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPSLLW	xmmreg,xmmreg*,imm8	AVX, SANDYBRIDGE
VPSLLD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
		· .
VPSLLD	xmmreg,xmmreg*,imm8	AVX, SANDYBRIDGE
VPSLLQ	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPSLLQ	xmmreg,xmmreg*,imm8	AVX, SANDYBRIDGE
VPSRAW	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPSRAW	xmmreg,xmmreg*,imm8	AVX, SANDYBRIDGE
VPSRAD		· .
	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPSRAD	xmmreg,xmmreg*,imm8	AVX, SANDYBRIDGE
VPSRLW	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPSRLW	xmmreg,xmmreg*,imm8	AVX, SANDYBRIDGE
VPSRLD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPSRLD	xmmreg,xmmreg*,imm8	AVX, SANDYBRIDGE
		· .
VPSRLQ	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPSRLQ	xmmreg,xmmreg*,imm8	AVX, SANDYBRIDGE
VPTEST	xmmreg,xmmrm128	AVX, SANDYBRIDGE
VPTEST	ymmreg,ymmrm256	AVX, SANDYBRIDGE
VPSUBB	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPSUBW	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPSUBD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPSUBQ	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPSUBSB	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPSUBSW	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPSUBUSB	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPSUBUSW	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
		· .
VPUNPCKHBW	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPUNPCKHWD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPUNPCKHDQ	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPUNPCKHQDQ	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPUNPCKLBW	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPUNPCKLWD	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
	Vmmrog Vmmrog* Vmmrm120	
VPUNPCKLDQ	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPUNPCKLQDQ	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VPXOR	xmmreg,xmmreg*,xmmrm128	AVX, SANDYBRIDGE
VRCPPS	xmmreg,xmmrm128	AVX, SANDYBRIDGE
VRCPPS	ymmreg,ymmrm256	AVX, SANDYBRIDGE
VRCPSS	xmmreg,xmmreg*,xmmrm32	AVX, SANDYBRIDGE
VRSQRTPS	xmmreg,xmmrm128	AVX, SANDYBRIDGE
VRSQRTPS	ymmreg,ymmrm256	AVX, SANDYBRIDGE

```
VRSQRTSS
                   xmmreg,xmmreg*,xmmrm32
                                               AVX, SANDYBRIDGE
VROUNDPD
                   xmmreg,xmmrm128,imm8
                                               AVX, SANDYBRIDGE
VROUNDPD
                   ymmreg,ymmrm256,imm8
                                               AVX, SANDYBRIDGE
VROUNDPS
                   xmmreg,xmmrm128,imm8
                                               AVX, SANDYBRIDGE
VROUNDPS
                   ymmreg,ymmrm256,imm8
                                               AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm64,imm8 AVX,SANDYBRIDGE
xmmreg,xmmreg*,xmmrm32,imm8 AVX,SANDYBRIDGE
VROUNDSD
VROUNDSS
VSHUFPD
                   xmmreg,xmmreg*,xmmrm128,imm8 AVX,SANDYBRIDGE
VSHUFPD
                   ymmreg,ymmreg*,ymmrm256,imm8 AVX,SANDYBRIDGE
VSHUFPS
                   xmmreg,xmmreg*,xmmrm128,imm8 AVX,SANDYBRIDGE
VSHUFPS
                   ymmreg,ymmreg*,ymmrm256,imm8 AVX,SANDYBRIDGE
                   xmmreg,xmmrm128
VSQRTPD
                                               AVX, SANDYBRIDGE
                                               AVX, SANDYBRIDGE
VSQRTPD
                   ymmreg,ymmrm256
VSQRTPS
                   xmmreg,xmmrm128
                                               AVX, SANDYBRIDGE
VSQRTPS
                   ymmreg,ymmrm256
                                               AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm64
VSQRTSD
                                               AVX, SANDYBRIDGE
VSQRTSS
                                               AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm32
                                               AVX, SANDYBRIDGE
VSTMXCSR
                   mem32
                   xmmreg,xmmreg*,xmmrm128
VSUBPD
                                               AVX, SANDYBRIDGE
VSUBPD
                   ymmreg,ymmreg*,ymmrm256
                                               AVX, SANDYBRIDGE
VSUBPS
                   xmmreg,xmmreg*,xmmrm128
                                               AVX, SANDYBRIDGE
VSUBPS
                   ymmreg,ymmreg*,ymmrm256
                                               AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm64
xmmreg,xmmreg*,xmmrm32
VSUBSD
                                               AVX, SANDYBRIDGE
VSUBSS
                                               AVX, SANDYBRIDGE
VTESTPS
                   xmmreg,xmmrm128
                                               AVX, SANDYBRIDGE
VTESTPS
                   ymmreg,ymmrm256
                                               AVX, SANDYBRIDGE
                                               AVX, SANDYBRIDGE
VTESTPD
                   xmmreg,xmmrm128
VTESTPD
                   ymmreg,ymmrm256
                                               AVX, SANDYBRIDGE
VUCOMISD
                   xmmreg,xmmrm64
                                               AVX, SANDYBRIDGE
                                               AVX, SANDYBRIDGE
VUCOMTSS
                   xmmreg,xmmrm32
VUNPCKHPD
                   xmmreg,xmmreg*,xmmrm128 AVX,SANDYBRIDGE
                   ymmreg,ymmreg*,ymmrm256 AVX,SANDYBRIDGE
VUNPCKHPD
                  xmmreg,xmmreg*,xmmrm128 AVX,SANDYBRIDGE
ymmreg,ymmreg*,ymmrm256 AVX,SANDYBRIDGE
xmmreg,xmmreg*,xmmrm128 AVX,SANDYBRIDGE
VUNPCKHPS
VUNPCKHPS
VUNPCKI PD
                   ymmreg,ymmreg*,ymmrm256 AVX,SANDYBRIDGE
VUNPCKLPD
                   xmmreg,xmmreg*,xmmrm128 AVX,SANDYBRIDGE
VUNPCKLPS
                   ymmreg,ymmreg*,ymmrm256 AVX,SANDYBRIDGE
VUNPCKLPS
                   xmmreg,xmmreg*,xmmrm128
ymmreg,ymmreg*,ymmrm256
VXORPD
                                               AVX, SANDYBRIDGE
VXORPD
                                               AVX, SANDYBRIDGE
                   xmmreg,xmmreg*,xmmrm128
VXORPS
                                               AVX, SANDYBRIDGE
VXORPS
                   ymmreg,ymmreg*,ymmrm256
                                               AVX, SANDYBRIDGE
VZEROALL
                                               AVX, SANDYBRIDGE
VZEROUPPER
                                               AVX, SANDYBRIDGE
```

B.1.27 Intel Carry-Less Multiplication instructions (CLMUL)

PCLMULLQLQDQ	xmmreg,xmmrm128	SSE, WESTMERE
PCLMULHQLQDQ	xmmreg,xmmrm128	SSE, WESTMERE
PCLMULLQHQDQ	xmmreg,xmmrm128	SSE, WESTMERE
PCLMULHQHQDQ	xmmreg,xmmrm128	SSE, WESTMERE
PCLMULQDQ	xmmreg,xmmrm128,imm8	SSE, WESTMERE

B.1.28 Intel AVX Carry-Less Multiplication instructions (CLMUL)

```
xmmreg,xmmreg*,xmmrm128
xmmreg,xmmreg*,xmmrm128
VPCLMULLOLODO
                                                  AVX, SANDYBRIDGE
VPCLMULHQLQDQ
                                                  AVX, SANDYBRIDGE
                    xmmreg,xmmreg*,xmmrm128
VPCLMULLQHQDQ
                                                 AVX, SANDYBRIDGE
VPCLMULHQHQDQ
                    xmmreg,xmmreg*,xmmrm128 AVX,SANDYBRIDGE
                    xmmreg,xmmreg*,xmmrm128,imm8 AVX,SANDYBRIDGE
VPCLMULQDQ
                   ymmreg,ymmreg*,ymmrm256 VPCLMULQDQ
ymmreg,ymmreg*,ymmrm256 VPCLMULQDQ
ymmreg,ymmreg*,ymmrm256 VPCLMULQDQ
VPCLMULLQLQDQ
VPCLMULHQLQDQ
VPCLMULLQHQDQ
                    ymmreg,ymmreg*,ymmrm256 VPCLMULQDQ
VPCLMULHOHODO
VPCLMULQDQ
                    ymmreg,ymmreg*,ymmrm256,imm8 VPCLMULQDQ
VPCLMULLQLQDQ
                    xmmreg,xmmreg*,xmmrm128 AVX512VL,VPCLMULQDQ
                    xmmreg,xmmreg*,xmmrm128 AVX512VL,VPCLMULQDQ
VPCLMULHQLQDQ
```

```
VPCLMULLQHQDQ xmmreg,xmmreg*,xmmrm128 AVX512VL,VPCLMULQDQ xmmreg,xmmreg*,xmmrm128 AVX512VL,VPCLMULQDQ xmmreg,xmmreg*,xmmrm128,imm8 AVX512VL,VPCLMULQDQ ymmreg,ymmreg*,ymmrm256 AVX512VL,VPCLMULQDQ ymmreg,ymmreg*,ymmrm256 AVX512VL,VPCLMULQDQ ymmreg,ymmreg*,ymmrm256 AVX512VL,VPCLMULQDQ ymmreg,ymmreg*,ymmrm256 AVX512VL,VPCLMULQDQ ymmreg,ymmreg*,ymmrm256 AVX512VL,VPCLMULQDQ ymmreg,ymmreg*,ymmrm256,imm8 AVX512VL,VPCLMULQDQ ymmreg,ymmreg*,ymmrm256,imm8 AVX512VL,VPCLMULQDQ ymmreg,ymmreg*,ymmrm256,imm8 AVX512VL,VPCLMULQDQ ymceg,zmmreg*,zmmrm512 AVX512,VPCLMULQDQ zmmreg,zmmreg*,zmmrm512 AVX512,VPCLMULQDQ zmmreg,zmmreg*,zmmrm512 AVX512,VPCLMULQDQ zmmreg,zmmreg*,zmmrm512 AVX512,VPCLMULQDQ zmmreg,zmmreg*,zmmrm512,imm8 AVX512,VPCLMULQDQ zmmreg,zmmreg*,zmmrm512,imm8 AVX512,VPCLMULQDQ
```

B.1.29 Intel Fused Multiply-Add instructions (FMA)

	-	
VFMADD132PS	xmmreg,xmmreg,xmmrm128	FMA
VFMADD132PS	ymmreg,ymmreg,ymmrm256	FMA
VFMADD132PD	xmmreg,xmmreg,xmmrm128	FMA
VFMADD132PD	ymmreg,ymmreg,ymmrm256	FMA
VFMADD312PS	xmmreg,xmmreg,xmmrm128	FMA
VFMADD312PS	ymmreg,ymmreg,ymmrm256	FMA
VFMADD312PD	xmmreg,xmmreg,xmmrm128	FMA
VFMADD312PD	ymmreg,ymmreg,ymmrm256	FMA
VFMADD213PS	xmmreg,xmmreg,xmmrm128	FMA
VFMADD213PS	ymmreg,ymmreg,ymmrm256	FMA
VFMADD213PD	xmmreg,xmmreg,xmmrm128	FMA
VFMADD213PD	ymmreg,ymmreg,ymmrm256	FMA
VFMADD123PS	xmmreg,xmmreg,xmmrm128	FMA
VFMADD123PS	ymmreg,ymmreg,ymmrm256	FMA
VFMADD123PD	xmmreg,xmmreg,xmmrm128	FMA
VFMADD123PD	ymmreg,ymmreg,ymmrm256	FMA
VFMADD231PS	xmmreg,xmmreg,xmmrm128	FMA
VFMADD231PS	ymmreg,ymmreg,ymmrm256	FMA
VFMADD231PD	xmmreg,xmmreg,xmmrm128	FMA
VFMADD231PD	ymmreg,ymmreg,ymmrm256	FMA
VFMADD321PS	xmmreg,xmmreg,xmmrm128	FMA
VFMADD321PS	ymmreg,ymmreg,ymmrm256	FMA
VFMADD321PD	xmmreg,xmmreg,xmmrm128	FMA
VFMADD321PD	ymmreg,ymmreg,ymmrm256	FMA
VFMADDSUB132PS	xmmreg,xmmreg,xmmrm128	FMA
VFMADDSUB132PS	ymmreg,ymmreg,ymmrm256	FMA
VFMADDSUB132PD	xmmreg,xmmreg,xmmrm128	FMA
VFMADDSUB132PD	ymmreg,ymmreg,ymmrm256	FMA
VFMADDSUB312PS VFMADDSUB312PS	xmmreg,xmmreg,xmmrm128	FMA FMA
VFMADDSUB312PD	ymmreg,ymmreg,ymmrm256	FMA
VFMADDSUB312PD	xmmreg,xmmreg,xmmrm128	FMA
VFMADDSUB213PS	ymmreg,ymmreg,ymmrm128	FMA
VFMADDSUB213FS	xmmreg,xmmreg,xmmrm128	FMA
VFMADDSUB213P3	ymmreg,ymmreg,ymmrm128	FMA
VFMADDSUB213FD VFMADDSUB213PD	xmmreg,xmmreg,xmmrm128	FMA
VFMADDSUB123PS	ymmreg,ymmreg,ymmrm256 xmmreg,xmmreg,xmmrm128	FMA
VFMADDSUB123FS	ymmreg,ymmreg,ymmrm256	FMA
VFMADDSUB123F5	xmmreg,xmmreg,xmmrm128	FMA
VFMADDSUB123PD	ymmreg,ymmreg,ymmrm256	FMA
VFMADDSUB231PS	xmmreg,xmmreg,xmmrm128	FMA
VFMADDSUB231PS	ymmreg,ymmreg,ymmrm256	FMA
VFMADDSUB231PD	xmmreg,xmmreg,xmmrm128	FMA
VFMADDSUB231PD	ymmreg,ymmreg,ymmrm256	FMA
VFMADDSUB321PS	xmmreg,xmmreg,xmmrm128	FMA
VFMADDSUB321PS	ymmreg,ymmreg,ymmrm256	FMA
VFMADDSUB321PD	xmmreg,xmmreg,xmmrm128	FMA
VFMADDSUB321PD	ymmreg,ymmreg,ymmrm256	FMA
VFMSUB132PS	xmmreg,xmmreg,xmmrm128	FMA
VFMSUB132PS	ymmreg,ymmreg,ymmrm256	FMA
VFMSUB132PD	xmmreg,xmmreg,xmmrm128	FMA
	-6, -6,	•

VFMSUB132PD	ymmreg,ymmreg,ymmrm256	FMA
VFMSUB312PS	xmmreg,xmmreg,xmmrm128	FMA
VFMSUB312PS	ymmreg,ymmreg,ymmrm256	FMA
VFMSUB312PD	xmmreg,xmmreg,xmmrm128	FMA
VFMSUB312PD	ymmreg,ymmreg,ymmrm256	FMA
VFMSUB213PS	xmmreg,xmmreg,xmmrm128	FMA
VFMSUB213PS	ymmreg,ymmreg,ymmrm256	FMA
VFMSUB213PD	xmmreg,xmmreg,xmmrm128	FMA
VFMSUB213PD	ymmreg,ymmreg,ymmrm256	FMA
VFMSUB123PS	xmmreg,xmmreg,xmmrm128	FMA
VFMSUB123PS	ymmreg,ymmreg,ymmrm256	FMA
VFMSUB123PD	xmmreg,xmmreg,xmmrm128	FMA
VFMSUB123PD	ymmreg,ymmreg,ymmrm256	FMA
VFMSUB231PS	xmmreg,xmmreg,xmmrm128	FMA
VFMSUB231PS	ymmreg,ymmreg,ymmrm256	FMA
VFMSUB231PD	xmmreg,xmmreg,xmmrm128	FMA
VFMSUB231PD	ymmreg,ymmreg,ymmrm256	FMA
VFMSUB321PS	xmmreg,xmmreg,xmmrm128	FMA
VFMSUB321PS	ymmreg,ymmreg,ymmrm256	FMA
VFMSUB321PD	xmmreg,xmmreg,xmmrm128	FMA
VFMSUB321PD	ymmreg,ymmreg,ymmrm256	FMA
VFMSUBADD132PS	xmmreg,xmmreg,xmmrm128	FMA
VFMSUBADD132PS	ymmreg,ymmreg,ymmrm256	FMA
VFMSUBADD132PD	xmmreg,xmmreg,xmmrm128	FMA
VFMSUBADD132PD	ymmreg,ymmreg,ymmrm256	FMA
VFMSUBADD312PS	xmmreg,xmmreg,xmmrm128	FMA
VFMSUBADD312PS	ymmreg,ymmreg,ymmrm256	FMA
VFMSUBADD312PD	xmmreg,xmmreg,xmmrm128	FMA
VFMSUBADD312PD	ymmreg,ymmreg,ymmrm256	FMA
VFMSUBADD213PS	xmmreg,xmmreg,xmmrm128	FMA
VFMSUBADD213PS	ymmreg,ymmreg,ymmrm256	FMA
VFMSUBADD213PD	xmmreg,xmmreg,xmmrm128	FMA
VFMSUBADD213PD	ymmreg,ymmreg,ymmrm256	FMA
VFMSUBADD123PS	xmmreg,xmmreg,xmmrm128	FMA
VFMSUBADD123PS	ymmreg,ymmreg,ymmrm256	FMA
VFMSUBADD123PD	xmmreg,xmmreg,xmmrm128	FMA
VFMSUBADD123PD	ymmreg,ymmreg,ymmrm256	FMA
VFMSUBADD231PS	xmmreg,xmmreg,xmmrm128	FMA
VFMSUBADD231PS	ymmreg,ymmreg,ymmrm256	FMA
VFMSUBADD231PD	xmmreg,xmmreg,xmmrm128	FMA
VFMSUBADD231PD	ymmreg,ymmreg,ymmrm256	FMA
VFMSUBADD321PS	xmmreg,xmmreg,xmmrm128	FMA
VFMSUBADD321PS	ymmreg,ymmreg,ymmrm256	FMA
VFMSUBADD321PD	xmmreg,xmmreg,xmmrm128	FMA
VFMSUBADD321PD	ymmreg,ymmreg,ymmrm256	FMA
VFNMADD132PS	xmmreg,xmmreg,xmmrm128	FMA
VFNMADD132PS VFNMADD132PD	ymmreg,ymmreg,ymmrm256	FMA
	xmmreg,xmmreg,xmmrm128	FMA FMA
VFNMADD132PD	ymmreg,ymmreg,ymmrm256	
VFNMADD312PS VFNMADD312PS	xmmreg,xmmreg,xmmrm128	FMA
VFNMADD312PD	ymmreg,ymmreg,ymmrm256	FMA FMA
	xmmreg,xmmreg,xmmrm128	
VFNMADD312PD VFNMADD213PS	ymmreg,ymmreg,ymmrm256	FMA FMA
	xmmreg,xmmreg,xmmrm128	FMA
VFNMADD213PS VFNMADD213PD	ymmreg,ymmreg,ymmrm256	
VFNMADD213PD VFNMADD213PD	xmmreg,xmmreg,xmmrm128	FMA
VFNMADD213PD VFNMADD123PS	ymmreg,ymmreg,ymmrm256	FMA FMA
VFNMADD123PS	xmmreg,xmmreg,xmmrm128	FMA
VFNMADD123PD	ymmreg,ymmreg,ymmrm128	FMA
VFNMADD123PD VFNMADD123PD	xmmreg,xmmreg,xmmrm128	FMA
VFNMADD123PD VFNMADD231PS	ymmreg,ymmreg,ymmrm256 xmmreg,xmmreg,xmmrm128	FMA
VFNMADD231PS		FMA
VFNMADD231PD	ymmreg,ymmreg,ymmrm256 xmmreg,xmmreg,xmmrm128	FMA
VFNMADD231PD	ymmreg,ymmreg,ymmrm256	FMA
VFNMADD321PS	xmmreg,xmmreg,xmmrm128	FMA
VFNMADD321PS	ymmreg,ymmreg,ymmrm256	FMA
	J 25, J 25, J 11230	

VFNMADD321PD	xmmreg,xmmreg,xmmrm128	FMA
VFNMADD321PD	ymmreg,ymmreg,ymmrm256	FMA
VFNMSUB132PS	xmmreg,xmmreg,xmmrm128	FMA
VFNMSUB132PS	ymmreg,ymmreg,ymmrm256	FMA
VFNMSUB132PD	xmmreg,xmmreg,xmmrm128	FMA
VFNMSUB132PD	ymmreg,ymmreg,ymmrm256	FMA
VFNMSUB312PS	xmmreg,xmmreg,xmmrm128	FMA
VFNMSUB312PS		FMA
	ymmreg,ymmreg,ymmrm256	
VFNMSUB312PD	xmmreg,xmmreg,xmmrm128	FMA
VFNMSUB312PD	ymmreg,ymmreg,ymmrm256	FMA
VFNMSUB213PS	xmmreg,xmmreg,xmmrm128	FMA
VFNMSUB213PS	ymmreg,ymmreg,ymmrm256	FMA
VFNMSUB213PD	xmmreg,xmmreg,xmmrm128	FMA
VFNMSUB213PD	ymmreg,ymmreg,ymmrm256	FMA
VFNMSUB123PS	xmmreg,xmmreg,xmmrm128	FMA
VFNMSUB123PS		FMA
	ymmreg,ymmreg,ymmrm256	
VFNMSUB123PD	xmmreg,xmmreg,xmmrm128	FMA
VFNMSUB123PD	ymmreg,ymmreg,ymmrm256	FMA
VFNMSUB231PS		FMA
	xmmreg,xmmreg,xmmrm128	
VFNMSUB231PS	ymmreg,ymmreg,ymmrm256	FMA
VFNMSUB231PD	xmmreg,xmmreg,xmmrm128	FMA
	<u> </u>	
VFNMSUB231PD	ymmreg,ymmreg,ymmrm256	FMA
VFNMSUB321PS	xmmreg,xmmreg,xmmrm128	FMA
VFNMSUB321PS	ymmreg,ymmreg,ymmrm256	FMA
VFNMSUB321PD	xmmreg,xmmreg,xmmrm128	FMA
VFNMSUB321PD	ymmreg,ymmreg,ymmrm256	FMA
VFMADD132SS	xmmreg,xmmreg,xmmrm32	FMA
VFMADD132SD	xmmreg,xmmreg,xmmrm64	FMA
VFMADD312SS	xmmreg,xmmreg,xmmrm32	FMA
VFMADD312SD	xmmreg,xmmreg,xmmrm64	FMA
VFMADD213SS		FMA
	xmmreg,xmmreg,xmmrm32	
VFMADD213SD	xmmreg,xmmreg,xmmrm64	FMA
VFMADD123SS	xmmreg,xmmreg,xmmrm32	FMA
VFMADD123SD	xmmreg,xmmreg,xmmrm64	FMA
VFMADD231SS	xmmreg,xmmreg,xmmrm32	FMA
VFMADD231SD	xmmreg,xmmreg,xmmrm64	FMA
VFMADD321SS	xmmreg,xmmreg,xmmrm32	FMA
VFMADD321SD		FMA
	xmmreg,xmmreg,xmmrm64	
VFMSUB132SS	xmmreg,xmmreg,xmmrm32	FMA
VFMSUB132SD	xmmreg,xmmreg,xmmrm64	FMA
VFMSUB312SS	xmmreg,xmmreg,xmmrm32	FMA
VFMSUB312SD	xmmreg,xmmreg,xmmrm64	FMA
VFMSUB213SS	xmmreg,xmmreg,xmmrm32	FMA
VFMSUB213SD	xmmreg,xmmreg,xmmrm64	FMA
VFMSUB123SS	xmmreg,xmmreg,xmmrm32	FMA
VFMSUB123SD	xmmreg,xmmreg,xmmrm64	FMA
VFMSUB231SS	xmmreg,xmmreg,xmmrm32	FMA
VFMSUB231SD		FMA
	xmmreg,xmmreg,xmmrm64	
VFMSUB321SS	xmmreg,xmmreg,xmmrm32	FMA
VFMSUB321SD	xmmreg,xmmreg,xmmrm64	FMA
VFNMADD132SS		FMA
	xmmreg,xmmreg,xmmrm32	
VFNMADD132SD	xmmreg,xmmreg,xmmrm64	FMA
VFNMADD312SS	xmmreg,xmmreg,xmmrm32	FMA
VFNMADD312SD	xmmreg,xmmreg,xmmrm64	FMA
VFNMADD213SS	xmmreg,xmmreg,xmmrm32	FMA
VFNMADD213SD	xmmreg,xmmreg,xmmrm64	FMA
VFNMADD123SS	xmmreg,xmmreg,xmmrm32	FMA
VFNMADD123SD	xmmreg,xmmreg,xmmrm64	FMA
VFNMADD231SS	xmmreg,xmmreg,xmmrm32	FMA
VFNMADD231SD	xmmreg,xmmreg,xmmrm64	FMA
VFNMADD321SS		FMA
	xmmreg,xmmreg,xmmrm32	
VFNMADD321SD	xmmreg,xmmreg,xmmrm64	FMA
VFNMSUB132SS	xmmreg,xmmreg,xmmrm32	FMA
VFNMSUB132SD	xmmreg,xmmreg,xmmrm64	FMA
VFNMSUB312SS	xmmreg,xmmreg,xmmrm32	FMA
VFNMSUB312SD	xmmreg,xmmreg,xmmrm64	FMA
VFNMSUB213SS	xmmreg,xmmreg,xmmrm32	FMA
	· · · · · · · · · · · · · · · · · · ·	

VFNMSUB213SD	xmmreg,xmmreg,xmmrm64	FMA
VFNMSUB123SS	xmmreg,xmmreg,xmmrm32	FMA
VFNMSUB123SD	xmmreg,xmmreg,xmmrm64	FMA
VFNMSUB231SS	xmmreg,xmmreg,xmmrm32	FMA
VFNMSUB231SD	xmmreg,xmmreg,xmmrm64	FMA
VFNMSUB321SS	xmmreg,xmmreg,xmmrm32	FMA
VFNMSUB321SD	xmmreg,xmmreg,xmmrm64	FMA

B.1.30 Intel post-32 nm processor instructions

RDFSBASE	reg32	LONG
RDFSBASE	reg64	LONG
RDGSBASE	reg32	LONG
RDGSBASE	reg64	LONG
RDRAND	reg16	
RDRAND	reg32	
RDRAND	reg64	LONG
WRFSBASE	reg32	LONG
WRFSBASE	reg64	LONG
WRGSBASE	reg32	LONG
WRGSBASE	reg64	LONG
VCVTPH2PS	ymmreg,xmmrm128	AVX
VCVTPH2PS	xmmreg,xmmrm64	AVX
VCVTPS2PH	xmmrm128,ymmreg,imm8	AVX
VCVTPS2PH	xmmrm64,xmmreg,imm8	AVX
ADCX	reg32,rm32	
ADCX	reg64,rm64	LONG
ADOX	reg32,rm32	
ADOX	reg64,rm64	LONG
RDSEED	reg16	
RDSEED	reg32	
RDSEED	reg64	LONG
CLAC		PRIV
STAC		PRIV

B.1.31 VIA (Centaur) security instructions

XSTORE	PENT, CYRIX
XCRYPTECB	PENT, CYRIX
XCRYPTCBC	PENT, CYRIX
XCRYPTCTR	PENT, CYRIX
XCRYPTCFB	PENT, CYRIX
XCRYPTOFB	PENT, CYRIX
MONTMUL	PENT, CYRIX
XSHA1	PENT, CYRIX
XSHA256	PENT, CYRIX

B.1.32 AMD Lightweight Profiling (LWP) instructions

LLWPCB	reg32	AMD,386
LLWPCB	reg64	AMD,X86_64,LONG
SLWPCB	reg32	AMD,386
SLWPCB	reg64	AMD,X86_64,LONG
LWPVAL	reg32,rm32,imm32	AMD,386
LWPVAL	reg64,rm32,imm32	AMD,X86_64,LONG
LWPINS	reg32,rm32,imm32	AMD,386
LWPINS	reg64,rm32,imm32	AMD, X86_64, LONG

B.1.33 AMD XOP and FMA4 instructions (SSE5)

```
VFMADDPD xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
VFMADDPD ymmreg,ymmreg*,ymmr256,ymmreg AMD,SSE5
VFMADDPD xmmreg,xmmreg*,xmmreg,xmmr128 AMD,SSE5
VFMADDPD ymmreg,ymmreg*,ymmreg,ymmr256 AMD,SSE5
VFMADDPS xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
VFMADDPS ymmreg,ymmreg*,ymmrm256,ymmreg AMD,SSE5
VFMADDPS xmmreg,xmmreg*,xmmreg,xmmrm128 AMD,SSE5
VFMADDPS ymmreg,ymmreg*,ymmrm256 AMD,SSE5
VFMADDPS ymmreg,ymmreg*,ymmrm256 AMD,SSE5
```

```
VFMADDSD
                   xmmreg,xmmreg*,xmmrm64,xmmreg AMD,SSE5
                   xmmreg,xmmreg*,xmmreg,xmmrm64 AMD,SSE5
xmmreg,xmmreg*,xmmrm32,xmmreg AMD,SSE5
VFMADDSD
VFMADDSS
VFMADDSS
                   xmmreg,xmmreg*,xmmreg,xmmrm32 AMD,SSE5
VFMADDSUBPD
                   xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
VFMADDSUBPD
                   ymmreg,ymmreg*,ymmrm256,ymmreg AMD,SSE5
VFMADDSUBPD
                   xmmreg,xmmreg*,xmmreg,xmmrm128 AMD,SSE5
                   ymmreg,ymmreg*,ymmreg,ymmrm256 AMD,SSE5
xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
VFMADDSUBPD
VFMADDSUBPS
VFMADDSUBPS
                   ymmreg,ymmreg*,ymmrm256,ymmreg AMD,SSE5
VEMADDSUBPS
                   xmmreg,xmmreg*,xmmreg,xmmrm128 AMD,SSE5
VFMADDSUBPS
                   ymmreg,ymmreg*,ymmreg,ymmrm256 AMD,SSE5
                   xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
ymmreg,ymmreg*,ymmrm256,ymmreg AMD,SSE5
VFMSUBADDPD
VFMSUBADDPD
VFMSUBADDPD
                   xmmreg,xmmreg*,xmmreg,xmmrm128 AMD,SSE5
VFMSUBADDPD
                   ymmreg,ymmreg*,ymmrm256 AMD,SSE5
VFMSUBADDPS
                   xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
                   ymmreg,ymmreg*,ymmrm256,ymmreg AMD,SSE5
xmmreg,xmmreg*,xmmreg,xmmrm128 AMD,SSE5
VFMSUBADDPS
VFMSUBADDPS
VFMSUBADDPS
                   ymmreg,ymmreg*,ymmreg,ymmrm256 AMD,SSE5
VFMSUBPD
                   xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
VFMSUBPD
                   ymmreg,ymmreg*,ymmrm256,ymmreg AMD,SSE5
VFMSUBPD
                   xmmreg,xmmreg*,xmmreg,xmmrm128 AMD,SSE5
                   ymmreg,ymmreg*,ymmreg,ymmrm256 AMD,SSE5
xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
VFMSUBPD
VFMSUBPS
                   ymmreg,ymmreg*,ymmrm256,ymmreg AMD,SSE5
VFMSUBPS
VFMSUBPS
                   xmmreg,xmmreg*,xmmreg,xmmrm128 AMD,SSE5
VFMSUBPS
                   ymmreg,ymmreg*,ymmreg,ymmrm256 AMD,SSE5
VFMSUBSD
                   xmmreg,xmmreg*,xmmrm64,xmmreg AMD,SSE5
VFMSUBSD
                   xmmreg,xmmreg*,xmmreg,xmmrm64 AMD,SSE5
VFMSUBSS
                   xmmreg,xmmreg*,xmmrm32,xmmreg AMD,SSE5
VFMSUBSS
                   xmmreg,xmmreg*,xmmreg,xmmrm32 AMD,SSE5
VFNMADDPD
                   xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
VFNMADDPD
                   ymmreg,ymmreg*,ymmrm256,ymmreg AMD,SSE5
VFNMADDPD
                   xmmreg,xmmreg*,xmmreg,xmmrm128 AMD,SSE5
VFNMADDPD
                   ymmreg,ymmreg*,ymmrm256 AMD,SSE5
                   xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
VFNMADDPS
VFNMADDPS
                   ymmreg,ymmreg*,ymmrm256,ymmreg AMD,SSE5
VFNMADDPS
                   xmmreg,xmmreg*,xmmreg,xmmrm128 AMD,SSE5
                   ymmreg,ymmreg*,ymmrm256 AMD,SSE5
VFNMADDPS
                   xmmreg,xmmreg*,xmmrm64,xmmreg AMD,SSE5
xmmreg,xmmreg*,xmmreg,xmmrm64 AMD,SSE5
VFNMADDSD
VFNMADDSD
VFNMADDSS
                   xmmreg,xmmreg*,xmmrm32,xmmreg AMD,SSE5
VFNMADDSS
                   xmmreg,xmmreg*,xmmreg,xmmrm32 AMD,SSE5
VFNMSUBPD
                   xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
                   ymmreg,ymmreg*,ymmrm256,ymmreg AMD,SSE5
xmmreg,xmmreg*,xmmreg,xmmrm128 AMD,SSE5
VFNMSUBPD
VFNMSUBPD
VFNMSUBPD
                   ymmreg,ymmreg*,ymmreg,ymmrm256 AMD,SSE5
VFNMSUBPS
                   xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
VFNMSUBPS
                   ymmreg,ymmreg*,ymmrm256,ymmreg AMD,SSE5
                   xmmreg,xmmreg*,xmmreg,xmmrm128 AMD,SSE5
ymmreg,ymmreg*,ymmreg,ymmrm256 AMD,SSE5
xmmreg,xmmreg*,xmmrm64,xmmreg AMD,SSE5
VFNMSUBPS
VFNMSUBPS
VFNMSUBSD
VFNMSUBSD
                   xmmreg,xmmreg*,xmmreg,xmmrm64 AMD,SSE5
VENMSUBSS
                   xmmreg,xmmreg*,xmmrm32,xmmreg AMD,SSE5
VFNMSUBSS
                   xmmreg,xmmreg*,xmmreg,xmmrm32 AMD,SSE5
VFRCZPD
                   xmmreg,xmmrm128*
                                                AMD, SSE5
                   ymmreg,ymmrm256*
VFRCZPD
                                                AMD, SSE5
                   xmmreg,xmmrm128*
VFRCZPS
                                                AMD, SSE5
VFRCZPS
                                                AMD, SSE5
                   ymmreg,ymmrm256*
                                                AMD, SSE5
VFRCZSD
                   xmmreg,xmmrm64*
VFRCZSS
                   xmmreg,xmmrm32*
                                                AMD, SSE5
VPCMOV
                   xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
                   ymmreg,ymmreg*,ymmrm256,ymmreg AMD,SSE5
VPCMOV
                   xmmreg,xmmreg*,xmmreg,xmmrm128 AMD,SSE5
VPCMOV
VPCMOV
                   ymmreg,ymmreg*,ymmrm256 AMD,SSE5
VPCOMB
                   xmmreg,xmmreg*,xmmrm128,imm8 AMD,SSE5
```

```
VPCOMD
                   xmmreg,xmmreg*,xmmrm128,imm8 AMD,SSE5
                   xmmreg,xmmreg*,xmmrm128,imm8 AMD,SSE5
VPCOMO
                   xmmreg,xmmreg*,xmmrm128,imm8 AMD,SSE5
VPCOMUB
VPCOMUD
                   xmmreg,xmmreg*,xmmrm128,imm8 AMD,SSE5
                   xmmreg,xmmreg*,xmmrm128,imm8 AMD,SSE5
VPCOMUQ
                   xmmreg,xmmreg*,xmmrm128,imm8 AMD,SSE5
xmmreg,xmmreg*,xmmrm128,imm8 AMD,SSE5
VPCOMUW
VPCOMW
VPHADDBD
                   xmmreg,xmmrm128*
                                                AMD, SSE5
VPHADDBQ
                   xmmreg,xmmrm128*
                                                AMD, SSE5
                                                AMD, SSE5
VPHADDBW
                   xmmreg,xmmrm128*
                   xmmreg,xmmrm128*
VPHADDDO
                                                AMD, SSE5
VPHADDUBD
                   xmmreg,xmmrm128*
                                                AMD, SSE5
                                                AMD, SSE5
VPHADDUBQ
                   xmmreg,xmmrm128*
VPHADDUBW
                   xmmreg,xmmrm128*
                                                AMD, SSE5
VPHADDUDQ
                   xmmreg,xmmrm128*
                                                AMD, SSE5
                                                AMD, SSE5
VPHADDUWD
                   xmmreg,xmmrm128*
VPHADDUWQ
                                                AMD, SSE5
                   xmmreg,xmmrm128*
VPHADDWD
                   xmmreg,xmmrm128*
                                                AMD, SSE5
VPHADDWO
                   xmmreg,xmmrm128*
                                                AMD, SSE5
VPHSUBBW
                   xmmreg,xmmrm128*
                                                AMD, SSE5
                                                AMD, SSE5
VPHSUBDO
                   xmmreg,xmmrm128*
                   xmmreg,xmmrm128*
VPHSUBWD
                                                AMD, SSE5
                   xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
VPMACSDD
VPMACSDOH
                   xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
VPMACSDQL
VPMACSSDD
                   xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
                   xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
VPMACSSDQH
                   xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
VPMACSSDQL
VPMACSSWD
VPMACSSWW
VPMACSWD
                   xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
                   xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
VPMACSWW
                   xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
xmmreg,xmmreg*,xmmreg,xmmrm128 AMD,SSE5
VPMADCSSWD
VPMADCSWD
VPPFRM
                   xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
VPPERM
                   xmmreg,xmmrm128*,xmmreg AMD,SSE5
VPROTB
                   xmmreg,xmmreg*,xmmrm128
                                                AMD, SSE5
VPROTR
VPROTB
                   xmmreg,xmmrm128*,imm8
                                                AMD, SSE5
                   xmmreg,xmmrm128*,xmmreg
VPROTD
                                                AMD, SSE5
                                                AMD, SSE5
VPROTD
                   xmmreg,xmmreg*,xmmrm128
VPROTD
                   xmmreg,xmmrm128*,imm8
                                                AMD, SSE5
                                                AMD, SSE5
VPROTO
                   xmmreg,xmmrm128*,xmmreg
VPROTQ
                   xmmreg,xmmreg*,xmmrm128
                                                AMD, SSE5
VPROTQ
                   xmmreg,xmmrm128*,imm8
                                                AMD, SSE5
                                                AMD, SSE5
                   xmmreg,xmmrm128*,xmmreg
VPROTW
VPROTW
                   xmmreg,xmmreg*,xmmrm128
                                                AMD, SSE5
VPROTW
                   xmmreg,xmmrm128*,imm8
                                                AMD, SSE5
                   xmmreg,xmmrm128*,xmmreg
                                                AMD, SSE5
VPSHAB
VPSHAB
                                                AMD, SSE5
                   xmmreg,xmmreg*,xmmrm128
VPSHAD
                   xmmreg,xmmrm128*,xmmreg
                                                AMD, SSE5
                                                AMD, SSE5
VPSHAD
                   xmmreg,xmmreg*,xmmrm128
VPSHAQ
                   xmmreg,xmmrm128*,xmmreg
                                                AMD, SSE5
                                                AMD, SSE5
VPSHAQ
                   xmmreg,xmmreg*,xmmrm128
VPSHAW
                   xmmreg,xmmrm128*,xmmreg
                                                AMD, SSE5
VPSHAW
                   xmmreg,xmmreg*,xmmrm128
                                                AMD, SSE5
                                                AMD, SSE5
VPSHLB
                   xmmreg,xmmrm128*,xmmreg
VPSHLB
                   xmmreg,xmmreg*,xmmrm128
                                                AMD, SSE5
VPSHLD
                   xmmreg,xmmrm128*,xmmreg
                                                AMD, SSE5
                                                AMD, SSE5
VPSHI D
                   xmmreg,xmmreg*,xmmrm128
                   xmmreg,xmmrm128*,xmmreg
                                                AMD, SSE5
VPSHLQ
VPSHLQ
                   xmmreg,xmmreg*,xmmrm128
                                                AMD, SSE5
VPSHLW
                   xmmreg,xmmrm128*,xmmreg
                                                AMD, SSE5
                                                AMD, SSE5
VPSHLW
                   xmmreg,xmmreg*,xmmrm128
```

B.1.34 Intel AVX2 instructions

VMPSADBW	ymmreg,ymmreg*,ymmrm256,	imm8 AVX2
VPABSB	ymmreg,ymmrm256	AVX2
VPABSW	ymmreg,ymmrm256	AVX2
VPABSD	ymmreg,ymmrm256	AVX2
VPACKSSWB	ymmreg,ymmreg*,ymmrm256	AVX2
VPACKSSDW	ymmreg,ymmreg*,ymmrm256	AVX2
VPACKUSDW	ymmreg,ymmreg*,ymmrm256	AVX2
VPACKUSWB	ymmreg,ymmreg*,ymmrm256	AVX2
VPADDB	ymmreg,ymmreg*,ymmrm256	AVX2
VPADDW	ymmreg,ymmreg*,ymmrm256	AVX2
VPADDD	ymmreg,ymmreg*,ymmrm256	AVX2
VPADDQ	ymmreg,ymmreg*,ymmrm256	AVX2
VPADDSB	ymmreg,ymmreg*,ymmrm256	AVX2
VPADDSW	ymmreg,ymmreg*,ymmrm256	AVX2
VPADDUSB	ymmreg,ymmreg*,ymmrm256	AVX2
VPADDUSW	ymmreg,ymmreg*,ymmrm256	AVX2
VPALIGNR	ymmreg,ymmreg*,ymmrm256,	imm8 AVX2
VPAND	ymmreg,ymmreg*,ymmrm256	AVX2
VPANDN	ymmreg,ymmreg*,ymmrm256	AVX2
VPAVGB	ymmreg,ymmreg*,ymmrm256	AVX2
VPAVGW	ymmreg,ymmreg*,ymmrm256	AVX2
VPBLENDVB	ymmreg,ymmreg*,ymmrm256,	ymmreg AVX2
VPBLENDW	ymmreg,ymmreg*,ymmrm256,	imm8 AVX2
VPCMPEQB	ymmreg,ymmreg*,ymmrm256	AVX2
VPCMPEQW	ymmreg,ymmreg*,ymmrm256	AVX2
VPCMPEOD	ymmreg,ymmreg*,ymmrm256	AVX2
VPCMPEQQ	ymmreg,ymmreg*,ymmrm256	AVX2
VPCMPGTB	ymmreg,ymmreg*,ymmrm256	AVX2
VPCMPGTW	ymmreg,ymmreg*,ymmrm256	AVX2
VPCMPGTD	ymmreg,ymmreg*,ymmrm256	AVX2
VPCMPGTQ	ymmreg,ymmreg*,ymmrm256	AVX2
VPHADDW	ymmreg,ymmreg*,ymmrm256	AVX2
VPHADDD	ymmreg,ymmreg*,ymmrm256	AVX2
VPHADDSW	ymmreg,ymmreg*,ymmrm256	AVX2
VPHSUBW	ymmreg,ymmreg*,ymmrm256	AVX2
VPHSUBD	ymmreg,ymmreg*,ymmrm256	AVX2
VPHSUBSW	ymmreg,ymmreg*,ymmrm256	AVX2
VPMADDUBSW	ymmreg,ymmreg*,ymmrm256	AVX2
VPMADDWD	ymmreg,ymmreg*,ymmrm256	AVX2
VPMAXSB	ymmreg,ymmreg*,ymmrm256	AVX2
VPMAXSW	ymmreg,ymmreg*,ymmrm256	AVX2
VPMAXSD	ymmreg,ymmreg*,ymmrm256	AVX2
VPMAXUB	ymmreg,ymmreg*,ymmrm256	AVX2
VPMAXUW	ymmreg,ymmreg*,ymmrm256	AVX2
VPMAXUD	ymmreg,ymmreg*,ymmrm256	AVX2
VPMINSB	ymmreg,ymmreg*,ymmrm256	AVX2
VPMINSW	ymmreg,ymmreg*,ymmrm256	AVX2
VPMINSD	ymmreg,ymmreg*,ymmrm256	AVX2
VPMINUB	ymmreg,ymmreg*,ymmrm256	AVX2
VPMINUW	ymmreg,ymmreg*,ymmrm256	AVX2
VPMINUD	ymmreg,ymmreg*,ymmrm256	AVX2
VPMOVMSKB	reg32,ymmreg	AVX2
VPMOVMSKB	reg64,ymmreg	AVX2
VPMOVSXBW	ymmreg,xmmrm128	AVX2
VPMOVSXBD	ymmreg, mem64	AVX2
VPMOVSXBD	ymmreg,xmmreg	AVX2
VPMOVSXBD	ymmreg,mem32	AVX2
VPMOVSXBQ	ymmreg,xmmreg	AVX2
VPMOVSXWD	ymmreg,xmmrm128	AVX2
VPMOVSXWD	ymmreg,mem64	AVX2
VPMOVSXWQ	ymmreg,xmmreg	AVX2
VPMOVSXWQ	ymmreg,xmmrm128	AVX2
VPMOVZXBW	ymmreg,xmmrm128	AVX2
VPMOVZXBD	ymmreg,mem64	AVX2
VPMOVZXBD	ymmreg,xmmreg	AVX2
	,0, ~6	

\/DMO\/Z\/DO	vmmsog mom32	AVX2
VPMOVZXBQ	ymmreg,mem32	
VPMOVZXBQ	ymmreg,xmmreg	AVX2
VPMOVZXWD	ymmreg,xmmrm128	AVX2
VPMOVZXWQ	ymmreg,mem64	AVX2
VPMOVZXWQ	ymmreg,xmmreg	AVX2
VPMOVZXDQ	ymmreg,xmmrm128	AVX2
VPMULDQ	ymmreg,ymmreg*,ymmrm256	AVX2
VPMULHRSW	ymmreg,ymmreg*,ymmrm256	AVX2
VPMULHUW	ymmreg,ymmreg*,ymmrm256	AVX2
VPMULHW		AVX2
	ymmreg,ymmreg*,ymmrm256	
VPMULLW	ymmreg,ymmreg*,ymmrm256	AVX2
VPMULLD	ymmreg,ymmreg*,ymmrm256	AVX2
VPMULUDQ	ymmreg,ymmreg*,ymmrm256	AVX2
VPOR	ymmreg,ymmreg*,ymmrm256	AVX2
VPSADBW	ymmreg,ymmreg*,ymmrm256	AVX2
VPSHUFB	ymmreg,ymmreg*,ymmrm256	AVX2
VPSHUFD	ymmreg,ymmrm256,imm8	AVX2
VPSHUFHW		AVX2
	ymmreg,ymmrm256,imm8	
VPSHUFLW	ymmreg,ymmrm256,imm8	AVX2
VPSIGNB	ymmreg,ymmreg*,ymmrm256	AVX2
VPSIGNW	ymmreg,ymmreg*,ymmrm256	AVX2
VPSIGND	ymmreg,ymmreg*,ymmrm256	AVX2
VPSLLDQ	ymmreg,ymmreg*,imm8	AVX2
VPSLLW	ymmreg,ymmreg*,xmmrm128	AVX2
VPSLLW	ymmreg,ymmreg*,imm8	AVX2
VPSLLD	vmmrog vmmrog* vmmrm129	AVX2
VPSLLD	ymmreg,ymmreg*,xmmrm128	AVX2
	ymmreg,ymmreg*,imm8	
VPSLLQ	ymmreg,ymmreg*,xmmrm128	AVX2
VPSLLQ	ymmreg,ymmreg*,imm8	AVX2
VPSRAW	ymmreg,ymmreg*,xmmrm128	AVX2
VPSRAW	ymmreg,ymmreg*,imm8	AVX2
VPSRAD	ymmreg,ymmreg*,xmmrm128	AVX2
VPSRAD	ymmreg,ymmreg*,imm8	AVX2
VPSRLDQ	ymmreg,ymmreg*,imm8	AVX2
VPSRLW	ymmreg,ymmreg*,xmmrm128	AVX2
		AVX2
VPSRLW	ymmreg,ymmreg*,imm8	
VPSRLD	ymmreg,ymmreg*,xmmrm128	AVX2
VPSRLD	ymmreg,ymmreg*,imm8	AVX2
VPSRLQ	ymmreg,ymmreg*,xmmrm128	AVX2
VPSRLQ	ymmreg,ymmreg*,imm8	AVX2
VPSUBB	ymmreg,ymmreg*,ymmrm256	AVX2
VPSUBW	ymmreg,ymmreg*,ymmrm256	AVX2
VPSUBD	ymmreg,ymmreg*,ymmrm256	AVX2
VPSUBQ	ymmreg,ymmreg*,ymmrm256	AVX2
VPSUBSB		AVX2
	ymmreg,ymmreg*,ymmrm256	
VPSUBSW	ymmreg,ymmreg*,ymmrm256	AVX2
VPSUBUSB	ymmreg,ymmreg*,ymmrm256	AVX2
VPSUBUSW	ymmreg,ymmreg*,ymmrm256	AVX2
VPUNPCKHBW	ymmreg,ymmreg*,ymmrm256	AVX2
VPUNPCKHWD	ymmreg,ymmreg*,ymmrm256	AVX2
VPUNPCKHDQ	ymmreg,ymmreg*,ymmrm256	AVX2
VPUNPCKHQDQ	ymmreg,ymmreg*,ymmrm256	AVX2
VPUNPCKLBW	ymmreg,ymmreg*,ymmrm256	AVX2
VPUNPCKLWD	ymmreg,ymmreg*,ymmrm256	AVX2
		AVX2
VPUNPCKLDQ	ymmreg,ymmreg*,ymmrm256	
VPUNPCKLQDQ	ymmreg,ymmreg*,ymmrm256	AVX2
VPXOR	ymmreg,ymmreg*,ymmrm256	AVX2
VMOVNTDQA	ymmreg,mem256	AVX2
VBROADCASTSS	xmmreg,xmmreg	AVX2
VBROADCASTSS	ymmreg,xmmreg	AVX2
VBROADCASTSD	ymmreg,xmmreg	AVX2
VBROADCASTI128	ymmreg,mem128	AVX2
VPBLENDD	xmmreg,xmmreg*,xmmrm128,	
VPBLENDD	ymmreg,ymmreg*,ymmrm256,	imm8 AVX2
VPBROADCASTB		AVX2
	xmmreg,mem8	
VPBROADCASTB	xmmreg,xmmreg	AVX2
VPBROADCASTB	ymmreg,mem8	AVX2

VPBROADCASTB	ymmreg,xmmreg	AVX2
VPBROADCASTW	xmmreg,mem16	AVX2
VPBROADCASTW	xmmreg,xmmreg	AVX2
VPBROADCASTW	ymmreg,mem16	AVX2
VPBROADCASTW	ymmreg,xmmreg	AVX2
VPBROADCASTD	xmmreg,mem32	AVX2
VPBROADCASTD	xmmreg,xmmreg	AVX2
VPBROADCASTD	ymmreg,mem32	AVX2
VPBROADCASTD	ymmreg,xmmreg	AVX2
VPBROADCASTQ	xmmreg,mem64	AVX2
VPBROADCASTQ	xmmreg,xmmreg	AVX2
VPBROADCASTQ	ymmreg,mem64	AVX2
VPBROADCASTQ	ymmreg,xmmreg	AVX2
VPERMD	ymmreg,ymmreg*,ymmrm256	AVX2
VPERMPD	ymmreg,ymmrm256,imm8	AVX2
VPERMPS	ymmreg,ymmreg*,ymmrm256	AVX2
VPERMQ	ymmreg,ymmrm256,imm8	AVX2
VPERM2I128	ymmreg,ymmreg*,ymmrm256,	imm8 AVX2
VEXTRACTI128	xmmrm128,ymmreg,imm8	AVX2
VINSERTI128	ymmreg,ymmreg*,xmmrm128,	imm8 AVX2
VPMASKMOVD	xmmreg,xmmreg*,mem128	AVX2
VPMASKMOVD	ymmreg,ymmreg*,mem256	AVX2
VPMASKMOVO	xmmreg,xmmreg*,mem128	AVX2
VPMASKMOVQ	ymmreg,ymmreg*,mem256	AVX2
VPMASKMOVD	mem128,xmmreg*,xmmreg	AVX2
VPMASKMOVD	mem256,ymmreg*,ymmreg	AVX2
VPMASKMOVQ	mem128,xmmreg*,xmmreg	AVX2
VPMASKMOVQ	mem256,ymmreg*,ymmreg	AVX2
VPSLLVD	xmmreg,xmmreg*,xmmrm128	AVX2
VPSLLVQ	xmmreg,xmmreg*,xmmrm128	AVX2
VPSLLVD	ymmreg,ymmreg*,ymmrm256	AVX2
VPSLLVQ	ymmreg,ymmreg*,ymmrm256	AVX2
VPSRAVD		AVX2
VPSRAVD	xmmreg,xmmreg*,xmmrm128	AVX2 AVX2
VPSRLVD	ymmreg,ymmreg*,ymmrm256	AVX2
VPSRLVO	xmmreg,xmmreg*,xmmrm128	AVX2
VPSRLVQ	xmmreg,xmmreg*,xmmrm128	
	ymmreg,ymmreg*,ymmrm256	AVX2
VPSRLVQ	ymmreg, ymmreg*, ymmrm256	AVX2
VGATHEROPD	xmmreg,xmem64,xmmreg	AVX2
VGATHERDED	xmmreg,xmem64,xmmreg	AVX2
VGATHEROPD	ymmreg,xmem64,ymmreg	AVX2
VGATHERQPD	ymmreg,ymem64,ymmreg	AVX2
VGATHERDPS	xmmreg,xmem32,xmmreg	AVX2
VGATHEROPS	xmmreg,xmem32,xmmreg	AVX2
VGATHERDPS	ymmreg,ymem32,ymmreg	AVX2
VGATHERQPS	xmmreg,ymem32,xmmreg	AVX2
VPGATHERDD	xmmreg,xmem32,xmmreg	AVX2
VPGATHERQD	xmmreg,xmem32,xmmreg	AVX2
VPGATHERDD	ymmreg,ymem32,ymmreg	AVX2
VPGATHERQD	xmmreg,ymem32,xmmreg	AVX2
VPGATHERDQ	xmmreg,xmem64,xmmreg	AVX2
VPGATHERQQ	xmmreg,xmem64,xmmreg	AVX2
VPGATHERDQ	ymmreg,xmem64,ymmreg	AVX2
VPGATHERQQ	ymmreg,ymem64,ymmreg	AVX2

B.1.35 Intel Transactional Synchronization Extensions (TSX)

XABORT	imm	RTM
XABORT	imm8	RTM
XBEGIN	imm	RTM
XBEGIN	imm near	RTM,ND
XBEGIN	imm16	RTM, NOLONG
XBEGIN	imm16 near	RTM, NOLONG, ND
XBEGIN	imm32	RTM, NOLONG
XBEGIN	imm32 near	RTM, NOLONG, ND
XBEGIN	imm64	RTM,LONG
XBEGIN	imm64 near	RTM,LONG,ND

XEND RTM XTEST HLE,RTM

B.1.36 Intel BMI1 and BMI2 instructions, AMD TBM instructions

	•	
ANDN	reg32,reg32,rm32	BMI1
ANDN	reg64, reg64, rm64	LONG, BMI1
BEXTR	reg32,rm32,reg32	BMI1
BEXTR	reg64,rm64,reg64	LONG, BMI1
BEXTR	reg32,rm32,imm32	TBM
BEXTR	reg64,rm64,imm32	LONG, TBM
BLCI	reg32,rm32	TBM
BLCI	reg64,rm64	LONG, TBM
BLCIC	reg32,rm32	TBM
BLCIC	reg64,rm64	LONG, TBM
BLSI	reg32,rm32	BMI1
BLSI	reg64,rm64	LONG, BMI1
BLSIC	reg32,rm32	TBM
BLSIC		LONG, TBM
	reg64,rm64	TBM
BLCFILL	reg32,rm32	
BLCFILL	reg64,rm64	LONG, TBM
BLSFILL	reg32,rm32	TBM
BLSFILL	reg64,rm64	LONG, TBM
BLCMSK	reg32,rm32	TBM
BLCMSK	reg64,rm64	LONG, TBM
BLSMSK	reg32,rm32	BMI1
BLSMSK	reg64,rm64	LONG,BMI1
BLSR	reg32,rm32	BMI1
BLSR	reg64,rm64	LONG, BMI1
BLCS	reg32,rm32	TBM
BLCS	reg64,rm64	LONG, TBM
BZHI	reg32,rm32,reg32	BMI2
BZHI	reg64,rm64,reg64	LONG,BMI2
MULX	reg32,reg32,rm32	BMI2
MULX	reg64,reg64,rm64	LONG, BMI2
PDEP	reg32,reg32,rm32	BMI2
PDEP	reg64,reg64,rm64	LONG, BMI2
PEXT	reg32,reg32,rm32	BMI2
PEXT	reg64, reg64, rm64	LONG, BMI2
RORX	reg32,rm32,imm8	BMI2
RORX	reg64,rm64,imm8	LONG, BMI2
SARX	reg32,rm32,reg32	BMI2
SARX	reg64,rm64,reg64	LONG, BMI2
SHLX	reg32,rm32,reg32	BMI2
SHLX	reg64,rm64,reg64	LONG, BMI2
SHRX	reg32,rm32,reg32	BMI2
SHRX	reg64,rm64,reg64	LONG, BMI2
TZCNT	reg16,rm16	BMI1
TZCNT	reg32,rm32	BMI1
TZCNT	reg64,rm64	LONG, BMI1
TZMSK	reg32,rm32	TBM
TZMSK	reg64,rm64	
T1MSKC		LONG, TBM
	reg32,rm32	
T1MSKC	reg64,rm64	LONG, TBM
PREFETCHWT1	mem8	PREFETCHWT1

B.1.37 Intel Memory Protection Extensions (MPX)

BNDMK	bndreg,mem	MPX,MIB
BNDCL	bndreg, mem	MPX
BNDCL	bndreg,reg32	MPX,NOLONG
BNDCL	bndreg,reg64	MPX,LONG
BNDCU	bndreg, mem	MPX
BNDCU	bndreg,reg32	MPX,NOLONG
BNDCU	bndreg,reg64	MPX,LONG
BNDCN	bndreg, mem	MPX
BNDCN	bndreg,reg32	MPX,NOLONG

BNDCN	bndreg,reg64	MPX,LONG
BNDMOV	bndreg, bndreg	MPX
BNDMOV	bndreg,mem	MPX
BNDMOV	bndreg,bndreg	MPX
BNDMOV	mem,bndreg	MPX
BNDLDX	bndreg, mem	MPX,MIB
BNDLDX	bndreg,mem,reg32	MPX,MIB,NOLONG
BNDLDX	bndreg,mem,reg64	MPX,MIB,LONG
BNDSTX	mem,bndreg	MPX,MIB
BNDSTX	mem,reg32,bndreg	MPX,MIB,NOLONG
BNDSTX	mem,reg64,bndreg	MPX,MIB,LONG
BNDSTX	mem,bndreg,reg32	MPX,MIB,NOLONG
BNDSTX	mem,bndreg,reg64	MPX,MIB,LONG

B.1.38 Intel SHA acceleration instructions

SHA1MSG1	xmmreg,xmmrm128	SHA
SHA1MSG2	xmmreg,xmmrm128	SHA
SHA1NEXTE	xmmreg,xmmrm128	SHA
SHA1RNDS4	xmmreg,xmmrm128,imm8	SHA
SHA256MSG1	xmmreg,xmmrm128	SHA
SHA256MSG2	xmmreg,xmmrm128	SHA
SHA256RNDS2	xmmreg,xmmrm128,xmm0	SHA
SHA256RNDS2	xmmreg,xmmrm128	SHA

B.1.39 AVX-512 mask register instructions

ATA SIZ MUSIKI	egister motractions	
KADDB	kreg,kreg,kreg	
KADDD	kreg,kreg,kreg	
KADDQ	kreg, kreg	
KADDW	kreg,kreg,kreg	
KANDB	kreg,kreg,kreg	
KANDD	kreg,kreg,kreg	
KANDNB	kreg,kreg,kreg	
KANDND	kreg,kreg,kreg	
KANDNQ	kreg,kreg,kreg	
KANDNW	kreg,kreg,kreg	
KANDQ	kreg,kreg,kreg	
KANDW	kreg,kreg,kreg	
KMOVB	kreg,krm8	
KMOVB	mem8,kreg	
KMOVB	kreg,reg32	
KMOVB	kreg,reg8	ND
KMOVB	reg32,kreg	
KMOVD	kreg,krm32	
KMOVD	mem32,kreg	
KMOVD	kreg,reg32	
KMOVD	reg32,kreg	
KMOVQ	kreg,krm64	
KMOVQ	mem64,kreg	
KMOVQ	kreg,reg64	
KMOVQ	reg64,kreg	
KMOVW	kreg,krm16	
KMOVW	mem16,kreg	
KMOVW	kreg,reg32	
KMOVW	kreg,reg16	ND
KMOVW	reg32,kreg	
KNOTB	kreg,kreg	
KNOTD	kreg,kreg	
KNOTQ	kreg,kreg	
KNOTW	kreg,kreg	
KORB	kreg,kreg,kreg	
KORD	kreg,kreg,kreg	
KORQ	kreg,kreg,kreg	
KORW	kreg,kreg,kreg	
KORTESTB	kreg,kreg	
KORTESTD	kreg,kreg	

KORTESTQ kreg, kreg KORTESTW kreg, kreg KSHIFTLB kreg, kreg, imm8 **KSHIFTLD** kreg, kreg, imm8 kreg, kreg, imm8 **KSHIFTLQ** KSHIFTLW kreg, kreg, imm8 **KSHIFTRB** kreg, kreg, imm8 **KSHIFTRD** kreg, kreg, imm8 **KSHIFTRQ** kreg, kreg, imm8 kreg, kreg, imm8 **KSHIFTRW** KTESTB kreg, kreg **KTESTD** kreg, kreg kreg, kreg **KTESTQ** KTESTW kreg, kreg KUNPCKBW kreg, kreg, kreg KUNPCKDO kreg, kreg, kreg KUNPCKWD kreg, kreg, kreg **KXNORB** kreg, kreg, kreg KXNORD kreg, kreg, kreg **KXNORQ** kreg, kreg, kreg kreg, kreg, kreg **KXNORW KXORB** kreg, kreg, kreg **KXORD** kreg, kreg, kreg **KXORO** kreg, kreg, kreg **KXORW** kreg, kreg, kreg

B.1.40 AVX-512 mask register instructions (aliases requiring explicit size support)

KADD ND kreg8, kreg, kreg KADD ND kreg32,kreg,kreg KADD kreg64, kreg, kreg ND KADD kreg16,kreg,kreg ND kreg8, kreg, kreg KAND ND KAND kreg32, kreg, kreg ND KANDN kreg64,kreg,kreg ND KANDN kreg16,kreg,kreg ND KANDN kreg8, kreg, kreg ND KANDN kreg32, kreg, kreg ND kreg64, kreg, kreg KAND ND KAND kreg16, kreg, kreg ND KMOV kreg8,krm8 ND KMOV mem8, kreg8 ND KMOV kreg8, reg32 ND,SX KMOV kreg8, reg8 ND KMOV reg32, kreg8 ND,SX KMOV kreg32, krm32 ND mem32,kreg32 KMOV ND KMOV kreg32, reg32 ND reg32, kreg32 KMOV ND KMOV kreg64, krm64 ND KMOV mem64, kreg64 ND KMOV kreg64, reg64 ND KMOV reg64, kreg64 ND kreg16,krm16 KMOV ND KMOV mem16, kreg16 ND KMOV kreg16, reg32 ND,SX KMOV reg32, kreg16 ND,SX KMOV kreg16,reg32 ND,SX KMOV kreg16, reg16 ND KNOT kreg8, kreg8 ND KNOT kreg32, kreg32 ND KNOT kreg64, kreg64 ND KNOT kreg16,kreg16 ND KOR kreg8, kreg, kreg ND KOR kreg32,kreg,kreg ND kreg64, kreg, kreg KOR ND KOR kreg16,kreg,kreg ND

KORTEST	kreg8,kreg	ND
KORTEST	kreg32,kreg	ND
KORTEST	kreg64,kreg	ND
KORTEST	kreg16,kreg	ND
KSHIFTL	kreg8,kreg,imm8	ND
KSHIFTL	kreg32,kreg,imm8	ND
KSHIFTL	kreg64,kreg,imm8	ND
KSHIFTL	kreg16,kreg,imm8	ND
KSHIFTR	kreg8,kreg,imm8	ND
KSHIFTR	kreg32,kreg,imm8	ND
KSHIFTR	kreg64,kreg,imm8	ND
KSHIFTR	kreg16,kreg,imm8	ND
KTEST	kreg8,kreg	ND
KTEST	kreg32,kreg	ND
KTEST	kreg64,kreg	ND
KTEST	kreg16,kreg	ND
KUNPCK	kreg16,kreg8,kreg8	ND
KUNPCK	kreg64,kreg32,kreg32	ND
KUNPCK	kreg32,kreg16,kreg16	ND
KXNOR	kreg8,kreg,kreg	ND
KXNOR	kreg32,kreg,kreg	ND
KXNOR	kreg64,kreg,kreg	ND
KXNOR	kreg16,kreg,kreg	ND
KXOR	kreg8,kreg,kreg	ND
KXOR	kreg32,kreg,kreg	ND
KXOR	kreg64,kreg,kreg	ND
KXOR	kreg16,kreg,kreg	ND

B.1.41 AVX-512 instructions

```
VADDPD
                     xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
                    ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b64|er AVX512
VADDPD
VADDPD
VADDPS
                    xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
VADDPS
                    ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
VADDPS
                     zmmreg|mask|z,zmmreg*,zmmrm512|b32|er AVX512
                    xmmreg|mask|z,xmmreg*,xmmrm64|er AVX512
xmmreg|mask|z,xmmreg*,xmmrm32|er AVX512
VADDSD
VADDSS
                    xmmreg|mask|z,xmmreg*,xmmrm128|b32,imm8 AVX512VL
VALIGND
                    ymmreg|mask|z,ymmreg*,ymmrm256|b32,imm8 AVX512VL
VALIGND
VAL TGND
                     zmmreg|mask|z,zmmreg*,zmmrm512|b32,imm8 AVX512
                    xmmreg|mask|z,xmmreg*,xmmrm128|b64,imm8 AVX512VL
ymmreg|mask|z,ymmreg*,ymmrm256|b64,imm8 AVX512VL
VALIGNO
VALIGNO
                    zmmreg|mask|z,zmmreg*,zmmrm512|b64,imm8 AVX512
VALIGNO
                    xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL/DQ
VANDNPD
VANDNPD
                    ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL/DQ
                    zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512VL/DQ xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL/DQ ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL/DQ
VANDNPD
VANDNPS
VANDNPS
VANDNPS
                    zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512DQ
                    xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL/DQ
VANDPD
                    ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL/DQ zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512DQ xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL/DQ
VANDPD
VANDPD
VANDPS
                    ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL/DQ
VANDPS
VANDPS
                    zmmreg | mask | z, zmmreg*, zmmrm512 | b32 AVX512DQ
VBLENDMPD
                    xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
VBLENDMPD
                    ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
VBLENDMPD
                    zmmreg|mask|z,zmmreg,zmmrm512|b64 AVX512
VBLENDMPS
                    xmmreg|mask|z,xmmreg,xmmrm128|b32 AVX512VL
VBLENDMPS
                    ymmreg | mask | z,ymmreg,ymmrm256 | b32 AVX512VL
VBLENDMPS
                    zmmreg|mask|z,zmmreg,zmmrm512|b32 AVX512
VBROADCASTF32X2
                    ymmreg|mask|z,xmmrm64
                                                   AVX512VL/DQ
VBROADCASTF32X2
                    zmmreg|mask|z,xmmrm64
                                                   AVX512DQ
VBROADCASTF32X4
                    ymmreg|mask|z,mem128
                                                   AVX512VI
VBROADCASTF32X4 zmmreg|mask|z,mem128
                                                   AVX512
VBROADCASTF32X8 zmmreg|mask|z,mem256
                                                   AVX512DQ
```

```
VBROADCASTF64X2 ymmreg|mask|z,mem128
                                            AVX512VL/DQ
VBROADCASTF64X2 zmmreg|mask|z,mem128
                                            AVX512D0
                 zmmreg|mask|z,mem256
VBROADCASTF64X4
                                            AVX512
VBROADCASTI32X2
                 xmmreg|mask|z,xmmrm64
                                            AVX512VL/DQ
VBROADCASTI32X2
                 ymmreg|mask|z,xmmrm64
                                            AVX512VL/DQ
VBROADCASTI32X2
                 zmmreg|mask|z,xmmrm64
                                            AVX512DQ
VBROADCASTI32X4
                                            AVX512VL
                 ymmreg|mask|z,mem128
VBROADCASTI32X4
                 zmmreg|mask|z,mem128
                                            AVX512
VBROADCASTI32X8
                 zmmreg mask z, mem256
                                            AVX512DQ
VBROADCASTI64X2
                 ymmreg|mask|z,mem128
                                            AVX512VL/DQ
VBROADCASTI64X2
                  zmmreg|mask|z,mem128
                                            AVX512D0
VBROADCASTI64X4
                 zmmreg|mask|z,mem256
                                            AVX512
VBROADCASTSD
                 ymmreg|mask|z,mem64
                                            AVX512VL
VBROADCASTSD
                 zmmreg|mask|z,mem64
                                            AVX512
VBROADCASTSD
                 ymmreg|mask|z,xmmreg
                                            AVX512VL
                 zmmreg|mask|z,xmmreg
VBROADCASTSD
                                            AVX512
VBROADCASTSS
                 xmmreg|mask|z,mem32
                                            AVX512VL
VBROADCASTSS
                 ymmreg|mask|z,mem32
                                            AVX512VL
                 zmmreg|mask|z.mem32
                                            AVX512
VBROADCASTSS
VBROADCASTSS
                 xmmreg|mask|z,xmmreg
                                            AVX512VL
VBROADCASTSS
                 ymmreg|mask|z,xmmreg
                                            AVX512VI
VBROADCASTSS
                  zmmreg|mask|z,xmmreg
                                            AVX512
VCMPEQPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPFOPD
                  kreg mask, ymmreg, ymmrm256 b64 AVX512VL
VCMPEQPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPEQPS
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VCMPEQPS
                  kreg | mask, ymmreg, ymmrm256 | b32 AVX512VL
VCMPEQPS
                  kreg | mask, zmmreg, zmmrm512 | b32 | sae AVX512
VCMPEQSD
                  kreg | mask, xmmreg, xmmrm64 | sae AVX512
VCMPEOSS
                  kreg | mask, xmmreg, xmmrm32 | sae AVX512
VCMPEQ_OQPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPEQ_OQPD
VCMPEQ_OQPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPEQ_OQPS
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPEO OOPS
VCMPEO OOPS
                  kreg|mask.zmmreg.zmmrm512|b32|sae AVX512
VCMPEQ_OQSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPEQ_OQSS
                  kreg | mask, xmmreg, xmmrm32 | sae AVX512
VCMPLTPD
                  kreg | mask, xmmreg, xmmrm128 | b64 AVX512VL
VCMPI TPD
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPLTPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPLTPS
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VCMPI TPS
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPLTPS
                  kreg | mask, zmmreg, zmmrm512 | b32 | sae AVX512
VCMPLTSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPLTSS
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPLT OSPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPLT_OSPD
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPLT_OSPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPLT_OSPS
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VCMPLT_OSPS
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPLT OSPS
                  kreg | mask, zmmreg, zmmrm512 | b32 | sae AVX512
VCMPLT_OSSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPLT_OSSS
VCMPLEPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPLEPD
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPI FPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPLEPS
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VCMPL FPS
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPLEPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPLESD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
                  kreg | mask, xmmreg, xmmrm32 | sae AVX512
VCMPI FSS
VCMPLE OSPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPLE_OSPD
                  kreg mask, ymmreg, ymmrm256 b64 AVX512VL
VCMPLE_OSPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPLE_OSPS
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VCMPLE OSPS
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
```

```
VCMPLE_OSPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPLE_OSSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPLE OSSS
                  kreg | mask, xmmreg, xmmrm32 | sae AVX512
VCMPUNORDPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPUNORDPD
VCMPUNORDPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPUNORDPS
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VCMPUNORDPS
                  kreg | mask, ymmreg, ymmrm256 | b32 AVX512VL
VCMPUNORDPS
                  kreg | mask, zmmreg, zmmrm512 | b32 | sae AVX512
VCMPUNORDSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPUNORDSS
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPUNORD OPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPUNORD_QPD
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPUNORD_QPD
                  kreg | mask, zmmreg, zmmrm512 | b64 | sae AVX512
VCMPUNORD_QPS
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VCMPUNORD_QPS
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPUNORD_QPS
VCMPUNORD_QSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPUNORD_QSS
                  kreg | mask, xmmreg, xmmrm32 | sae AVX512
VCMPNEOPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPNEOPD
VCMPNEQPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPNEQPS
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VCMPNEOPS
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPNEQPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPNEQSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPNEQSS
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPNEQ UOPD
VCMPNEQ_UQPD
                  kreg mask, ymmreg, ymmrm256 b64 AVX512VL
VCMPNEQ_UQPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPNEQ_UQPS
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VCMPNEQ_UQPS
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPNEQ_UQPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPNEQ_UQSD
                  kreg | mask, xmmreg, xmmrm64 | sae AVX512
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPNEQ_UQSS
VCMPNLTPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPNLTPD
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPNI TPD
VCMPNLTPS
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VCMPNLTPS
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPNLTPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPNLTSD
                  kreg | mask, xmmreg, xmmrm64 | sae AVX512
VCMPNLTSS
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPNLT_USPD
                  kreg | mask, xmmreg, xmmrm128 | b64 AVX512VL
VCMPNLT_USPD
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPNLT USPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPNLT USPS
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VCMPNLT_USPS
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPNLT_USPS
VCMPNLT_USSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPNLT_USSS
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPNLEPD
VCMPNLEPD
                  kreg | mask, ymmreg, ymmrm256 | b64 AVX512VL
VCMPNI FPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPNLEPS
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VCMPNLEPS
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPNLEPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPNLESD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPNI FSS
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPNLE_USPD
VCMPNLE_USPD
                  kreg | mask, ymmreg, ymmrm256 | b64 AVX512VL
VCMPNLE USPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VCMPNLE USPS
VCMPNLE_USPS
                  kreg mask, ymmreg, ymmrm256 b32 AVX512VL
VCMPNLE_USPS
                 kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPNLE_USSD
                  kreg | mask, xmmreg, xmmrm64 | sae AVX512
VCMPNLE USSS
                 kreg|mask,xmmreg,xmmrm32|sae AVX512
```

```
VCMPORDPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPORDPD
VCMPORDPD
                  kreg | mask, zmmreg, zmmrm512 | b64 | sae AVX512
VCMPORDPS
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPORDPS
VCMPORDPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPORDSD
                  kreg | mask, xmmreg, xmmrm64 | sae AVX512
VCMPORDSS
                  kreg | mask, xmmreg, xmmrm32 | sae AVX512
VCMPORD_QPD
                  kreg | mask, xmmreg, xmmrm128 | b64 AVX512VL
VCMPORD_QPD
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPORD_QPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPORD QPS
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VCMPORD OPS
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPORD_QPS
                  kreg | mask, zmmreg, zmmrm512 | b32 | sae AVX512
VCMPORD_QSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPORD_QSS
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPEQ_UQPD
                  kreg | mask, xmmreg, xmmrm128 | b64 AVX512VL
                  kreg | mask, ymmreg, ymmrm256 | b64 AVX512VL
VCMPEQ_UQPD
VCMPEO UOPD
                  kreg | mask, zmmreg, zmmrm512 | b64 | sae AVX512
VCMPEQ_UQPS
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VCMPEQ_UQPS
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPEQ_UQPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPEQ_UQSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPEO UOSS
                  kreg mask, xmmreg, xmmrm32 sae AVX512
VCMPNGEPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPNGEPD
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPNGEPD
VCMPNGEPS
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VCMPNGEPS
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPNGEPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPNGESD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPNGESS
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPNGE USPD
                  kreg | mask, xmmreg, xmmrm128 | b64 AVX512VL
VCMPNGE_USPD
                  kreg mask, ymmreg, ymmrm256 b64 AVX512VL
VCMPNGE USPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPNGE USPS
                  kreg|mask.xmmreg.xmmrm128|b32 AVX512VL
VCMPNGE_USPS
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPNGE_USPS
VCMPNGE_USSD
                  kreg | mask, xmmreg, xmmrm64 | sae AVX512
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPNGE_USSS
VCMPNGTPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPNGTPD
                  kreg | mask, ymmreg, ymmrm256 | b64 AVX512VL
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPNGTPD
VCMPNGTPS
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VCMPNGTPS
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPNGTPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPNGTSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPNGTSS
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPNGT_USPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPNGT_USPD
                  kreg | mask, ymmreg, ymmrm256 | b64 AVX512VL
VCMPNGT_USPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPNGT USPS
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VCMPNGT_USPS
                  kreg | mask, ymmreg, ymmrm256 | b32 AVX512VL
VCMPNGT_USPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPNGT_USSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPNGT_USSS
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPFALSEPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPFALSEPD
                  kreg | mask, ymmreg, ymmrm256 | b64 AVX512VL
VCMPFALSEPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPFALSEPS
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VCMPFALSEPS
                  kreg | mask, ymmreg, ymmrm256 | b32 AVX512VL
VCMPFALSEPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPFALSESD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPFALSESS
                  kreg | mask, xmmreg, xmmrm32 | sae AVX512
VCMPFALSE_OQPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPFALSE_OQPD
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPFALSE OOPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
```

```
VCMPFALSE_OQPS
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VCMPFALSE_OQPS
                  kreg | mask, ymmreg, ymmrm256 | b32 AVX512VL
VCMPFALSE OOPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPFALSE_OQSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPFALSE_OQSS
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPNEQ_OQPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPNEQ_OQPD
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPNEQ OOPD
                  kreg | mask, zmmreg, zmmrm512 | b64 | sae AVX512
VCMPNEQ_OQPS
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPNEQ_OQPS
VCMPNEQ_OQPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPNEQ OOSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPNEQ_OQSS
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPGEPD
                  kreg | mask, xmmreg, xmmrm128 | b64 AVX512VL
VCMPGEPD
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPGEPD
VCMPGEPS
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VCMPGEPS
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPGEPS
                  kreg | mask, zmmreg, zmmrm512 | b32 | sae AVX512
VCMPGESD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPGESS
VCMPGE OSPD
                  kreg | mask, xmmreg, xmmrm128 | b64 AVX512VL
VCMPGE OSPD
                  kreg | mask, ymmreg, ymmrm256 | b64 AVX512VL
VCMPGE OSPD
                  kreg | mask, zmmreg, zmmrm512 | b64 | sae AVX512
VCMPGE_OSPS
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VCMPGE_OSPS
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPGE_OSPS
VCMPGE OSSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPGE_OSSS
                  kreg | mask, xmmreg, xmmrm32 | sae AVX512
VCMPGTPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPGTPD
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPGTPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPGTPS
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VCMPGTPS
                  kreg mask, ymmreg, ymmrm256 b32 AVX512VL
VCMPGTPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPGTSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPGTSS
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPGT_OSPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPGT_OSPD
                  kreg mask, ymmreg, ymmrm256 b64 AVX512VL
VCMPGT_OSPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPGT OSPS
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VCMPGT_OSPS
                  kreg | mask, ymmreg, ymmrm256 | b32 AVX512VL
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPGT_OSPS
VCMPGT_OSSD
                  kreg | mask, xmmreg, xmmrm64 | sae AVX512
VCMPGT_OSSS
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPTRUEPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPTRUEPD
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPTRUEPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPTRUEPS
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VCMPTRUEPS
                  kreg | mask, ymmreg, ymmrm256 | b32 AVX512VL
VCMPTRUEPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPTRUESD
                  kreg | mask, xmmreg, xmmrm64 | sae AVX512
VCMPTRUESS
                  kreg | mask, xmmreg, xmmrm32 | sae AVX512
VCMPTRUE_UQPD
                  kreg | mask, xmmreg, xmmrm128 | b64 AVX512VL
VCMPTRUE_UQPD
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPTRUE_UQPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPTRUE_UQPS
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VCMPTRUE UQPS
                  kreg | mask, ymmreg, ymmrm256 | b32 AVX512VL
VCMPTRUE_UQPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPTRUE_UQSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPTRUE_UQSS
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPEQ_OSPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPEQ OSPD
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPEQ_OSPD
                  kreg | mask, zmmreg, zmmrm512 | b64 | sae AVX512
VCMPEQ_OSPS
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPEQ_OSPS
VCMPEQ OSPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
```

```
VCMPEQ_OSSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPEQ_OSSS
                  kreg | mask, xmmreg, xmmrm32 | sae AVX512
VCMPLT OOPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPLT_OQPD
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPLT_OQPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPLT_OQPS
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VCMPLT_OQPS
                  kreg | mask, ymmreg, ymmrm256 | b32 AVX512VL
VCMPLT OOPS
                  kreg | mask, zmmreg, zmmrm512 | b32 | sae AVX512
VCMPLT_OQSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPLT_OQSS
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPLE_OQPD
                  kreg | mask, xmmreg, xmmrm128 | b64 AVX512VL
VCMPLE_OQPD
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPLE_OQPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPLE_OQPS
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VCMPLE_OQPS
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPLE_OQPS
VCMPLE_OQSD
                  kreg | mask, xmmreg, xmmrm64 | sae AVX512
VCMPLE_OQSS
                  kreg | mask, xmmreg, xmmrm32 | sae AVX512
VCMPUNORD SPD
                  kreg | mask, xmmreg, xmmrm128 | b64 AVX512VL
VCMPUNORD_SPD
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPUNORD_SPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPUNORD SPS
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VCMPUNORD SPS
                  kreg | mask, ymmreg, ymmrm256 | b32 AVX512VL
VCMPUNORD SPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPUNORD_SSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPUNORD_SSS
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPNEQ USPD
                  kreg | mask, xmmreg, xmmrm128 | b64 AVX512VL
VCMPNEQ USPD
                  kreg | mask, ymmreg, ymmrm256 | b64 AVX512VL
VCMPNEQ_USPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPNEO USPS
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VCMPNEQ_USPS
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPNEQ_USPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPNEQ USSD
                  kreg | mask, xmmreg, xmmrm64 | sae AVX512
VCMPNEQ_USSS
                  kreg | mask, xmmreg, xmmrm32 | sae AVX512
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPNLT UOPD
VCMPNLT UOPD
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPNLT_UQPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VCMPNLT_UQPS
VCMPNLT_UQPS
                  kreg mask, ymmreg, ymmrm256 b32 AVX512VL
VCMPNLT_UQPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPNLT_UQSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPNLT_UQSS
                  kreg | mask, xmmreg, xmmrm32 | sae AVX512
VCMPNLE_UQPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPNLE_UQPD
                  kreg mask, ymmreg, ymmrm256 b64 AVX512VL
VCMPNLE_UQPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPNLE_UQPS
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VCMPNLE UOPS
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPNLE_UQPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPNLE_UQSD
                  kreg | mask, xmmreg, xmmrm64 | sae AVX512
VCMPNLE_UQSS
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPORD_SPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPORD SPD
                  kreg mask, ymmreg, ymmrm256 b64 AVX512VL
VCMPORD_SPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPORD_SPS
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VCMPORD SPS
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPORD_SPS
                  kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPORD SSD
                  kreg | mask, xmmreg, xmmrm64 | sae AVX512
VCMPORD SSS
                  kreg | mask, xmmreg, xmmrm32 | sae AVX512
VCMPEQ_USPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPEQ_USPD
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPEQ_USPD
                  kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPEQ_USPS
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPEO USPS
VCMPEQ_USPS
                  kreg | mask, zmmreg, zmmrm512 | b32 | sae AVX512
VCMPEQ_USSD
                  kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPEQ_USSS
                  kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPNGE UOPD
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
```

```
VCMPNGE_UQPD
                 kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPNGE UQPD
                 kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPNGE UQPS
                 kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VCMPNGE_UQPS
                 kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPNGE_UQPS
                 kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPNGE_UQSD
                 kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPNGE UQSS
                 kreg | mask, xmmreg, xmmrm32 | sae AVX512
VCMPNGT UOPD
                 kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPNGT_UQPD
                 kreg mask, ymmreg, ymmrm256 b64 AVX512VL
VCMPNGT_UQPD
                 kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPNGT_UQPS
                 kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VCMPNGT UOPS
                 kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPNGT UOPS
                 kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPNGT_UQSD
                 kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPNGT_UQSS
                 kreg|mask,xmmreg,xmmrm32|sae AVX512
                 kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPFALSE_OSPD
VCMPFALSE_OSPD
                 kreg | mask, ymmreg, ymmrm256 | b64 AVX512VL
VCMPFALSE_OSPD
                 kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPFALSE OSPS
                 kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VCMPFALSE_OSPS
                 kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
                 kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPFALSE_OSPS
VCMPFALSE_OSSD
                 kreg | mask, xmmreg, xmmrm64 | sae AVX512
VCMPFALSE OSSS
                 kreg | mask, xmmreg, xmmrm32 | sae AVX512
                 kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPNEO OSPD
VCMPNEQ_OSPD
                 kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPNEQ_OSPD
                 kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
                 kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VCMPNEQ_OSPS
VCMPNEQ OSPS
                 kreg | mask, ymmreg, ymmrm256 | b32 AVX512VL
VCMPNEQ_OSPS
                 kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPNEQ_OSSD
                 kreg | mask, xmmreg, xmmrm64 | sae AVX512
VCMPNEQ_OSSS
                 kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPGE_OQPD
                 kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VCMPGE_OQPD
                 kreg | mask, ymmreg, ymmrm256 | b64 AVX512VL
VCMPGE_OQPD
                 kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPGE OOPS
                 kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VCMPGE OOPS
                 kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPGE_OQPS
                 kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPGE_OQSD
                 kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPGE_OQSS
                 kreg | mask, xmmreg, xmmrm32 | sae AVX512
VCMPGT_OQPD
                 kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
                 kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPGT_OQPD
VCMPGT_OQPD
                 kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPGT_OQPS
                 kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VCMPGT_OQPS
                 kreg mask, ymmreg, ymmrm256 b32 AVX512VL
VCMPGT_OQPS
                 kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPGT_OQSD
                 kreg|mask,xmmreg,xmmrm64|sae AVX512
VCMPGT OOSS
                 kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPTRUE_USPD
                 kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
                 kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VCMPTRUE_USPD
VCMPTRUE_USPD
                 kreg|mask,zmmreg,zmmrm512|b64|sae AVX512
VCMPTRUE_USPS
                 kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
                 kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VCMPTRUE USPS
VCMPTRUE_USPS
                 kreg|mask,zmmreg,zmmrm512|b32|sae AVX512
VCMPTRUE_USSD
                 kreg | mask, xmmreg, xmmrm64 | sae AVX512
VCMPTRUE USSS
                 kreg|mask,xmmreg,xmmrm32|sae AVX512
VCMPPD
                 kreg|mask,xmmreg,xmmrm128|b64,imm8 AVX512VL
VCMPPD
                 kreg|mask,ymmreg,ymmrm256|b64,imm8 AVX512VL
VCMPPD
                 kreg|mask,zmmreg,zmmrm512|b64|sae,imm8 AVX512
VCMPPS
                 kreg|mask,xmmreg,xmmrm128|b32,imm8 AVX512VL
VCMPPS
                 kreg|mask,ymmreg,ymmrm256|b32,imm8 AVX512VL
VCMPPS
                 kreg|mask,zmmreg,zmmrm512|b32|sae,imm8 AVX512
VCMPSD
                 kreg|mask,xmmreg,xmmrm64|sae,imm8 AVX512
VCMPSS
                 kreg|mask,xmmreg,xmmrm32|sae,imm8 AVX512
VCOMISD
                 xmmreg,xmmrm64|sae
                                           AVX512
                                           AVX512
VCOMTSS
                 xmmreg,xmmrm32|sae
VCOMPRESSPD
                 mem128 | mask, xmmreg
                                           AVX512VL
VCOMPRESSPD
                 mem256 | mask, ymmreg
                                           AVX512VL
```

```
VCOMPRESSPD
                 mem512 | mask,zmmreg
                                           AVX512
VCOMPRESSED
                 xmmreg|mask|z,xmmreg
                                           AVX512VL
VCOMPRESSPD
                                           AVX512VL
                 ymmreg|mask|z,ymmreg
VCOMPRESSPD
                 zmmreg|mask|z,zmmreg
                                           AVX512
VCOMPRESSPS
                 mem128 | mask, xmmreg
                                           AVX512VL
VCOMPRESSPS
                 mem256 | mask, ymmreg
                                           AVX512VL
VCOMPRESSPS
                 mem512 | mask,zmmreg
                                           AVX512
VCOMPRESSPS
                 xmmreg | mask | z, xmmreg
                                           AVX512VL
VCOMPRESSPS
                 ymmreg | mask | z, ymmreg
                                           AVX512VL
                                           AVX512
VCOMPRESSPS
                 zmmreg|mask|z,zmmreg
VCVTD02PD
                 xmmreg|mask|z,xmmrm64|b32 AVX512VL
VCVTDQ2PD
                 ymmreg|mask|z,xmmrm128|b32 AVX512VL
                 zmmreg|mask|z,ymmrm256|b32|er AVX512
VCVTDQ2PD
VCVTDQ2PS
                 xmmreg|mask|z,xmmrm128|b32 AVX512VL
VCVTDQ2PS
                 ymmreg|mask|z,ymmrm256|b32 AVX512VL
VCVTD02PS
                 zmmreg|mask|z,zmmrm512|b32|er AVX512
VCVTPD2D0
                 xmmreg|mask|z,xmmrm128|b64 AVX512VL
VCVTPD2D0
                 xmmreg|mask|z,ymmrm256|b64 AVX512VL
                 ymmreg|mask|z,zmmrm512|b64|er AVX512
VCVTPD2D0
VCVTPD2PS
                 xmmreg|mask|z,xmmrm128|b64 AVX512VL
VCVTPD2PS
                 xmmreg|mask|z,ymmrm256|b64 AVX512VL
VCVTPD2PS
                 ymmreg|mask|z,zmmrm512|b64|er AVX512
VCVTPD200
                 xmmreg | mask | z, xmmrm128 | b64 AVX512VL/DQ
                 ymmreg|mask|z,ymmrm256|b64 AVX512VL/D0
VCVTPD200
                 zmmreg|mask|z,zmmrm512|b64|er AVX512DQ
VCVTPD2QQ
VCVTPD2UDQ
                 xmmreg|mask|z,xmmrm128|b64 AVX512VL
                 xmmreg|mask|z,ymmrm256|b64 AVX512VL
VCVTPD2UD0
VCVTPD2UD0
                 ymmreg|mask|z,zmmrm512|b64|er AVX512
VCVTPD2UQQ
                 xmmreg|mask|z,xmmrm128|b64 AVX512VL/DQ
VCVTPD2U00
                 ymmreg|mask|z,ymmrm256|b64 AVX512VL/DQ
VCVTPD2U00
                 zmmreg|mask|z,zmmrm512|b64|er AVX512DQ
VCVTPH2PS
                 xmmreg|mask|z,xmmrm64
                                           AVX512VL
VCVTPH2PS
                 ymmreg|mask|z,xmmrm128
                                           AVX512VL
VCVTPH2PS
                 zmmreg|mask|z,ymmrm256|sae AVX512
VCVTPS2D0
                 xmmreg|mask|z,xmmrm128|b32 AVX512VL
VCVTPS2D0
                 ymmreg|mask|z,ymmrm256|b32 AVX512VL
VCVTPS2DQ
                 zmmreg|mask|z,zmmrm512|b32|er AVX512
                 xmmreg|mask|z,xmmrm64|b32 AVX512VL
VCVTPS2PD
VCVTPS2PD
                 ymmreg|mask|z,xmmrm128|b32 AVX512VL
VCVTPS2PD
                 zmmreg|mask|z,ymmrm256|b32|sae AVX512
VCVTPS2PH
                 xmmreg|mask|z,xmmreg,imm8 AVX512VL
VCVTPS2PH
                 xmmreg|mask|z,ymmreg,imm8 AVX512VL
VCVTPS2PH
                 ymmreg|mask|z,zmmreg|sae,imm8 AVX512
VCVTPS2PH
                 mem64 | mask, xmmreg, imm8
                                           AVX512VL
VCVTPS2PH
                 mem128 | mask, ymmreg, imm8 AVX512VL
VCVTPS2PH
                 mem256 | mask, zmmreg | sae, imm8 AVX512
VCVTPS200
                 xmmreg|mask|z,xmmrm64|b32 AVX512VL/DQ
VCVTPS200
                 ymmreg|mask|z,xmmrm128|b32 AVX512VL/DQ
VCVTPS2QQ
                 zmmreg|mask|z,ymmrm256|b32|er AVX512DQ
VCVTPS2UDQ
                 xmmreg|mask|z,xmmrm128|b32 AVX512VL
VCVTPS2UDQ
                 ymmreg|mask|z,ymmrm256|b32 AVX512VL
VCVTPS2UDQ
                 zmmreg|mask|z,zmmrm512|b32|er AVX512
VCVTPS2UQQ
                 xmmreg|mask|z,xmmrm64|b32 AVX512VL/DQ
                 ymmreg|mask|z,xmmrm128|b32 AVX512VL/DQ
VCVTPS2UQQ
VCVTPS2U00
                 zmmreg|mask|z,ymmrm256|b32|er AVX512DQ
VCVTQQ2PD
                 xmmreg|mask|z,xmmrm128|b64 AVX512VL/DQ
                 ymmreg|mask|z,ymmrm256|b64 AVX512VL/DQ
VCVTQQ2PD
VCVTQ02PD
                 zmmreg|mask|z,zmmrm512|b64|er AVX512D0
VCVTQQ2PS
                 xmmreg|mask|z,xmmrm128|b64 AVX512VL/DQ
VCVTQQ2PS
                 xmmreg|mask|z,ymmrm256|b64 AVX512VL/DQ
                 ymmreg|mask|z,zmmrm512|b64|er AVX512DQ
VCVTQQ2PS
                 reg32,xmmrm64|er
VCVTSD2SI
                                           AVX512
VCVTSD2SI
                 reg64,xmmrm64 er
                                           AVX512
VCVTSD2SS
                 xmmreg|mask|z,xmmreg,xmmrm64|er AVX512
VCVTSD2UST
                 reg32,xmmrm64|er
                                           AVX512
VCVTSD2USI
                 reg64,xmmrm64|er
                                           AVX512
VCVTSI2SD
                 xmmreg,xmmreg|er,rm32
                                           AVX512
```

```
VCVTSI2SD
                 xmmreg,xmmreg|er,rm64
                                            AVX512
VCVTST2SS
                                            AVX512
                 xmmreg,xmmreg|er,rm32
                                            AVX512
VCVTSI2SS
                 xmmreg,xmmreg|er,rm64
VCVTSS2SD
                 xmmreg|mask|z,xmmreg,xmmrm32|sae AVX512
VCVTSS2ST
                 reg32,xmmrm32|er
                                           AVX512
VCVTSS2SI
                  reg64,xmmrm32|er
                                            AVX512
VCVTSS2UST
                                           AVX512
                  reg32,xmmrm32|er
VCVTSS2USI
                 reg64,xmmrm32 er
                                           AVX512
VCVTTPD2DQ
                  xmmreg|mask|z,xmmrm128|b64 AVX512VL
VCVTTPD2DQ
                  xmmreg|mask|z,ymmrm256|b64 AVX512VL
VCVTTPD2D0
                 ymmreg|mask|z,zmmrm512|b64|sae AVX512
VCVTTPD200
                  xmmreg|mask|z,xmmrm128|b64 AVX512VL/DQ
                 ymmreg|mask|z,ymmrm256|b64 AVX512VL/DQ
VCVTTPD200
VCVTTPD2QQ
                  zmmreg|mask|z,zmmrm512|b64|sae AVX512DQ
VCVTTPD2UDQ
                  xmmreg|mask|z,xmmrm128|b64 AVX512VL
                  xmmreg|mask|z,ymmrm256|b64 AVX512VL
VCVTTPD2UD0
VCVTTPD2UD0
                 ymmreg|mask|z,zmmrm512|b64|sae AVX512
VCVTTPD2UQQ
                 xmmreg|mask|z,xmmrm128|b64 AVX512VL/DQ
VCVTTPD2U00
                 ymmreg|mask|z,ymmrm256|b64 AVX512VL/DQ
VCVTTPD2U00
                  zmmreg|mask|z,zmmrm512|b64|sae AVX512DQ
VCVTTPS2DQ
                  xmmreg|mask|z,xmmrm128|b32 AVX512VL
VCVTTPS2D0
                 ymmreg|mask|z,ymmrm256|b32 AVX512VL
VCVTTPS2DQ
                  zmmreg|mask|z,zmmrm512|b32|sae AVX512
VCVTTPS200
                 xmmreg|mask|z,xmmrm64|b32 AVX512VL/D0
VCVTTPS2QQ
                 ymmreg|mask|z,xmmrm128|b32 AVX512VL/DQ
VCVTTPS2QQ
                  zmmreg|mask|z,ymmrm256|b32|sae AVX512DQ
VCVTTPS2UDQ
                  xmmreg|mask|z,xmmrm128|b32 AVX512VL
VCVTTPS2UD0
                 ymmreg|mask|z,ymmrm256|b32 AVX512VL
VCVTTPS2UD0
                 zmmreg|mask|z,zmmrm512|b32|sae AVX512
VCVTTPS2U00
                 xmmreg|mask|z,xmmrm64|b32 AVX512VL/DQ
VCVTTPS2UQQ
                 ymmreg|mask|z,xmmrm128|b32 AVX512VL/DQ
VCVTTPS2U00
                  zmmreg|mask|z,ymmrm256|b32|sae AVX512DQ
VCVTTSD2SI
                  reg32,xmmrm64|sae
                                           AVX512
VCVTTSD2SI
                  reg64,xmmrm64|sae
                                           AVX512
                  reg32,xmmrm64|sae
VCVTTSD2IIST
                                           ΔV/X512
VCVTTSD2USI
                  reg64.xmmrm64|sae
                                           AVX512
VCVTTSS2SI
                  reg32,xmmrm32|sae
                                           AVX512
VCVTTSS2SI
                  reg64,xmmrm32|sae
                                            AVX512
VCVTTSS2USI
                  reg32,xmmrm32|sae
                                           AVX512
VCVTTSS2UST
                  reg64,xmmrm32|sae
                                           AVX512
VCVTUD02PD
                 xmmreg|mask|z,xmmrm64|b32 AVX512VL
VCVTUDQ2PD
                 ymmreg|mask|z,xmmrm128|b32 AVX512VL
VCVTUDQ2PD
                  zmmreg|mask|z,ymmrm256|b32|er AVX512
VCVTUDQ2PS
                  xmmreg|mask|z,xmmrm128|b32 AVX512VL
VCVTUDQ2PS
                 ymmreg|mask|z,ymmrm256|b32 AVX512VL
VCVTUD02PS
                 zmmreg|mask|z,zmmrm512|b32|er AVX512
VCVTUQQ2PD
                  xmmreg|mask|z,xmmrm128|b64 AVX512VL/DQ
VCVTUQQ2PD
                 ymmreg|mask|z,ymmrm256|b64 AVX512VL/DQ
VCVTUQQ2PD
                  zmmreg|mask|z,zmmrm512|b64|er AVX512DQ
VCVTUQQ2PS
                  xmmreg|mask|z,xmmrm128|b64 AVX512VL/DQ
VCVTUQQ2PS
                 xmmreg|mask|z,ymmrm256|b64 AVX512VL/DQ
VCVTUQQ2PS
                 ymmreg|mask|z,zmmrm512|b64|er AVX512D0
VCVTUSI2SD
                  xmmreg,xmmreg|er,rm32
                                           AVX512
VCVTUST2SD
                  xmmreg,xmmreg|er,rm64
                                            ΔVX512
VCVTUSI2SS
                  xmmreg,xmmreg|er,rm32
                                            AVX512
VCVTUSI2SS
                 xmmreg,xmmreg|er,rm64
                                           AVX512
                 xmmreg|mask|z,xmmreg*,xmmrm128,imm8 AVX512VL/BW
VDRPSADRW
VDBPSADBW
                 ymmreg|mask|z,ymmreg*,ymmrm256,imm8 AVX512VL/BW
VDBPSADBW
                  zmmreg|mask|z,zmmreg*,zmmrm512,imm8 AVX512BW
VDIVPD
                 xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
                 ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b64|er AVX512
VDIVPD
VDTVPD
                 xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
VDIVPS
                 ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
VDIVPS
VDTVPS
                 zmmreg|mask|z,zmmreg*,zmmrm512|b32|er AVX512
                 xmmreg|mask|z,xmmreg*,xmmrm64|er AVX512
xmmreg|mask|z,xmmreg*,xmmrm32|er AVX512
VDIVSD
VDIVSS
```

```
VEXP2PD
                 zmmreg|mask|z,zmmrm512|b64|sae AVX512ER
VFXP2PS
                 zmmreg|mask|z,zmmrm512|b32|sae AVX512ER
VEXPANDPD
                 xmmreg|mask|z,mem128
                                           AVX512VL
VEXPANDPD
                 ymmreg|mask|z,mem256
                                           AVX512VI
VEXPANDPD
                                           AVX512
                 zmmreg|mask|z,mem512
                                           AVX512VL
VEXPANDPD
                 xmmreg|mask|z,xmmreg
VEXPANDED
                 ymmreg|mask|z,ymmreg
                                           AVX512VL
VEXPANDPD
                 zmmreg|mask|z,zmmreg
                                           AVX512
VEXPANDPS
                 xmmreg | mask | z, mem128
                                           AVX512VL
                                           AVX512VL
VEXPANDES
                 ymmreg|mask|z,mem256
VEXPANDPS
                 zmmreg|mask|z,mem512
                                           AVX512
VEXPANDPS
                 xmmreg|mask|z,xmmreg
                                           AVX512VL
VEXPANDES
                 ymmreg|mask|z,ymmreg
                                           AVX512VL
VEXPANDPS
                 zmmreg|mask|z,zmmreg
                                           AVX512
VEXTRACTF32X4
                 xmmreg|mask|z,ymmreg,imm8 AVX512VL
VEXTRACTE32X4
                 xmmreg|mask|z,zmmreg,imm8 AVX512
VEXTRACTF32X4
                 mem128 | mask, ymmreg, imm8 AVX512VL
VEXTRACTF32X4
                 mem128 | mask, zmmreg, imm8 AVX512
VEXTRACTF32X8
                 ymmreg|mask|z,zmmreg,imm8 AVX512DQ
VEXTRACTF32X8
                 mem256|mask,zmmreg,imm8 AVX512DQ
                 xmmreg|mask|z,ymmreg,imm8 AVX512VL/DQ
VEXTRACTF64X2
VEXTRACTF64X2
                 xmmreg | mask | z, zmmreg, imm8 AVX512DQ
VEXTRACTF64X2
                 mem128 | mask, ymmreg, imm8 AVX512VL/DQ
VFXTRACTF64X2
                 mem128|mask,zmmreg,imm8 AVX512DQ
VEXTRACTF64X4
                 ymmreg|mask|z,zmmreg,imm8 AVX512
VEXTRACTF64X4
                 mem256 | mask, zmmreg, imm8 AVX512
                 xmmreg|mask|z,ymmreg,imm8 AVX512VL
VEXTRACTI32X4
VEXTRACTI32X4
                 xmmreg|mask|z,zmmreg,imm8 AVX512
VEXTRACTI32X4
                 mem128 | mask, ymmreg, imm8 AVX512VL
                 mem128 | mask, zmmreg, imm8 AVX512
VFXTRACTT32X4
VEXTRACTI32X8
                 ymmreg|mask|z,zmmreg,imm8 AVX512DQ
                 mem256|mask,zmmreg,imm8 AVX512DQ
VEXTRACTI32X8
VEXTRACTI64X2
                 xmmreg|mask|z,ymmreg,imm8 AVX512VL/DQ
VEXTRACTI64X2
                 xmmreg|mask|z,zmmreg,imm8 AVX512DQ
                 mem128|mask,ymmreg,imm8 AVX512VL/DQ
VEXTRACTT64X2
VEXTRACTI64X2
                 mem128 | mask, zmmreg, imm8 AVX512DQ
VEXTRACTI64X4
                 ymmreg|mask|z,zmmreg,imm8 AVX512
VEXTRACTI64X4
                 mem256 mask,zmmreg,imm8 AVX512
VEXTRACTPS
                 reg32,xmmreg,imm8
                                           AVX512
VEXTRACTES
                 reg64,xmmreg,imm8
                                          AVX512
VEXTRACTPS
                                          AVX512
                 mem32,xmmreg,imm8
VFIXUPIMMPD
                 xmmreg|mask|z,xmmreg*,xmmrm128|b64,imm8 AVX512VL
VETXUPTMMPD
                 ymmreg|mask|z,ymmreg*,ymmrm256|b64,imm8 AVX512VL
VFIXUPIMMPD
                 zmmreg|mask|z,zmmreg*,zmmrm512|b64|sae,imm8 AVX512
                 xmmreg|mask|z,xmmreg*,xmmrm128|b32,imm8 AVX512VL
VFIXUPIMMPS
                 ymmreg|mask|z,ymmreg*,ymmrm256|b32,imm8 AVX512VL
VETXIIPTMMPS
VFIXUPIMMPS
                 zmmreg|mask|z,zmmreg*,zmmrm512|b32|sae,imm8 AVX512
VFIXUPIMMSD
                 xmmreg|mask|z,xmmreg*,xmmrm64|sae,imm8 AVX512
VFIXUPIMMSS
                 xmmreg|mask|z,xmmreg*,xmmrm32|sae,imm8 AVX512
VFMADD132PD
                 xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
VFMADD132PD
                 ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
VFMADD132PD
                 zmmreg|mask|z,zmmreg,zmmrm512|b64|er AVX512
VFMADD132PS
                 xmmreg|mask|z,xmmreg,xmmrm128|b32 AVX512VL
VFMADD132PS
                 ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
VFMADD132PS
                 zmmreg|mask|z,zmmreg,zmmrm512|b32|er AVX512
VFMADD132SD
                 xmmreg|mask|z,xmmreg,xmmrm64|er AVX512
                 xmmreg|mask|z,xmmreg,xmmrm32|er AVX512
VFMADD132SS
VFMADD213PD
                 xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
VFMADD213PD
                 ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
VFMADD213PD
                 zmmreg|mask|z,zmmreg,zmmrm512|b64|er AVX512
VFMADD213PS
                 xmmreg|mask|z,xmmreg,xmmrm128|b32 AVX512VL
VFMADD213PS
                 ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
VFMADD213PS
                 zmmreg|mask|z,zmmreg,zmmrm512|b32|er AVX512
VFMADD213SD
                 xmmreg|mask|z,xmmreg,xmmrm64|er AVX512
VFMADD213SS
                 xmmreg|mask|z,xmmreg,xmmrm32|er AVX512
VFMADD231PD
                 xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
VFMADD231PD
                 ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
```

```
zmmreg|mask|z,zmmreg,zmmrm512|b64|er AVX512
VFMADD231PD
VFMADD231PS
                  xmmreg|mask|z,xmmreg,xmmrm128|b32 AVX512VL
VFMADD231PS
                  \verb|ymmreg|| mask|| \verb|z|, \verb|ymmreg|, \verb|ymmrm256|| b32 AVX512VL|
VFMADD231PS
                  zmmreg|mask|z,zmmreg,zmmrm512|b32|er AVX512
VFMADD231SD
                  xmmreg|mask|z,xmmreg,xmmrm64|er AVX512
VFMADD231SS
                  xmmreg|mask|z,xmmreg,xmmrm32|er AVX512
VFMADDSUB132PD
                  xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
VFMADDSUB132PD
                  ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
VFMADDSUB132PD
                  zmmreg|mask|z,zmmreg,zmmrm512|b64|er AVX512
VFMADDSUB132PS
                  xmmreg|mask|z,xmmreg,xmmrm128|b32 AVX512VL
VFMADDSUB132PS
                  ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
VFMADDSUB132PS
                  zmmreg|mask|z,zmmreg,zmmrm512|b32|er AVX512
VFMADDSUB213PD
                  xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
                  ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
VFMADDSUB213PD
VFMADDSUB213PD
                  zmmreg|mask|z,zmmreg,zmmrm512|b64|er AVX512
                  xmmreg|mask|z,xmmreg,xmmrm128|b32 AVX512VL
VFMADDSUB213PS
                  ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
VFMADDSUB213PS
VFMADDSUB213PS
                  zmmreg|mask|z,zmmreg,zmmrm512|b32|er AVX512
VFMADDSUB231PD
                  xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
VFMADDSUB231PD
                  ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
VFMADDSUB231PD
                  zmmreg|mask|z,zmmreg,zmmrm512|b64|er AVX512
VFMADDSUB231PS
                  xmmreg|mask|z,xmmreg,xmmrm128|b32 AVX512VL
VFMADDSUB231PS
                  ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
                  zmmreg|mask|z,zmmreg,zmmrm512|b32|er AVX512
VFMADDSUB231PS
                  xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
VFMSUB132PD
VFMSUB132PD
                  ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
VFMSUB132PD
                  zmmreg|mask|z,zmmreg,zmmrm512|b64|er AVX512
                  \verb|xmmreg|| mask|| \verb|z|, \verb|xmmreg|, \verb|xmmrm128|| b32 AVX512VL|
VFMSUB132PS
VFMSUB132PS
                  ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
VFMSUB132PS
                  zmmreg|mask|z,zmmreg,zmmrm512|b32|er AVX512
VFMSUB132SD
                  xmmreg|mask|z,xmmreg,xmmrm64|er AVX512
VFMSUB132SS
                  xmmreg|mask|z,xmmreg,xmmrm32|er AVX512
VFMSUB213PD
                  xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
VFMSUB213PD
                  ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
VFMSUB213PD
                  {\tt zmmreg|mask|z,zmmreg,zmmrm512|b64|er~AVX512}
                  xmmreg|mask|z,xmmreg,xmmrm128|b32 AVX512VL
VFMSUB213PS
                  ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
VFMSUB213PS
VFMSUB213PS
                  zmmreg|mask|z,zmmreg,zmmrm512|b32|er AVX512
                  \verb|xmmreg|| mask|| \verb|z|, \verb|xmmreg|, \verb|xmmrm64|| er | AVX512|
VFMSUB213SD
VFMSUB213SS
                  xmmreg|mask|z,xmmreg,xmmrm32|er AVX512
VFMSUB231PD
                  xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
VFMSUB231PD
                  ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
VFMSUB231PD
                  zmmreg|mask|z,zmmreg,zmmrm512|b64|er AVX512
                  xmmreg|mask|z,xmmreg,xmmrm128|b32 AVX512VL
VFMSUB231PS
VFMSUB231PS
                  ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
VFMSUB231PS
                  zmmreg|mask|z,zmmreg,zmmrm512|b32|er AVX512
VFMSUB231SD
                  xmmreg|mask|z,xmmreg,xmmrm64|er AVX512
VFMSUB231SS
                  xmmreg|mask|z,xmmreg,xmmrm32|er AVX512
VFMSUBADD132PD
                  xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
VFMSUBADD132PD
                  ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
VFMSUBADD132PD
                  zmmreg|mask|z,zmmreg,zmmrm512|b64|er AVX512
VFMSUBADD132PS
                  xmmreg|mask|z,xmmreg,xmmrm128|b32 AVX512VL
VFMSUBADD132PS
                  ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
VFMSUBADD132PS
                  zmmreg|mask|z,zmmreg,zmmrm512|b32|er AVX512
                  \verb|xmmreg|| mask|| \verb|z|, \verb|xmmreg|, \verb|xmmrm128|| b64 AVX512VL|
VFMSUBADD213PD
VFMSUBADD213PD
                  ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
VFMSUBADD213PD
                  zmmreg|mask|z,zmmreg,zmmrm512|b64|er AVX512
VFMSUBADD213PS
                  xmmreg|mask|z,xmmreg,xmmrm128|b32 AVX512VL
                  ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
VFMSUBADD213PS
VFMSUBADD213PS
                  zmmreg|mask|z,zmmreg,zmmrm512|b32|er AVX512
VFMSUBADD231PD
                  xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
VFMSUBADD231PD
                  ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
VFMSUBADD231PD
                  {\tt zmmreg|mask|z,zmmreg,zmmrm512|b64|er~AVX512}
VFMSUBADD231PS
                  xmmreg|mask|z,xmmreg,xmmrm128|b32 AVX512VL
VFMSUBADD231PS
                  ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
                  zmmreg \mid mask \mid z, zmmreg, zmmrm512 \mid b32 \mid er AVX512
VFMSUBADD231PS
VFNMADD132PD
                  xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
```

```
VFNMADD132PD
                 ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
VENMADD132PD
                 zmmreg|mask|z,zmmreg,zmmrm512|b64|er AVX512
VFNMADD132PS
                 xmmreg|mask|z,xmmreg,xmmrm128|b32 AVX512VL
VFNMADD132PS
                 ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
VFNMADD132PS
                 zmmreg|mask|z,zmmreg,zmmrm512|b32|er AVX512
VFNMADD132SD
                 xmmreg|mask|z,xmmreg,xmmrm64|er AVX512
VFNMADD132SS
                 xmmreg|mask|z,xmmreg,xmmrm32|er AVX512
VFNMADD213PD
                 xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
VFNMADD213PD
                 ymmreg | mask | z, ymmreg, ymmrm256 | b64 AVX512VL
VENMADD213PD
                 zmmreg|mask|z,zmmreg,zmmrm512|b64|er AVX512
VFNMADD213PS
                 xmmreg|mask|z,xmmreg,xmmrm128|b32 AVX512VL
VFNMADD213PS
                 ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
                 zmmreg|mask|z,zmmreg,zmmrm512|b32|er AVX512
VENMADD213PS
VFNMADD213SD
                 xmmreg|mask|z,xmmreg,xmmrm64|er AVX512
VFNMADD213SS
                 xmmreg|mask|z,xmmreg,xmmrm32|er AVX512
VENMADD231PD
                 xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
VFNMADD231PD
                 ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
VFNMADD231PD
                 zmmreg|mask|z,zmmreg,zmmrm512|b64|er AVX512
VFNMADD231PS
                 xmmreg | mask | z, xmmreg, xmmrm128 | b32 AVX512VL
VFNMADD231PS
                 ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
VENMADD231PS
                 zmmreg|mask|z,zmmreg,zmmrm512|b32|er AVX512
VFNMADD231SD
                 xmmreg | mask | z, xmmreg, xmmrm64 | er AVX512
VFNMADD231SS
                 xmmreg | mask | z, xmmreg, xmmrm32 | er AVX512
VFNMSUB132PD
                 xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
VFNMSUB132PD
                 ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
VFNMSUB132PD
                 zmmreg|mask|z,zmmreg,zmmrm512|b64|er AVX512
VFNMSUB132PS
                 xmmreg | mask | z, xmmreg, xmmrm128 | b32 AVX512VL
VFNMSUB132PS
                 ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
VFNMSUB132PS
                 zmmreg|mask|z,zmmreg,zmmrm512|b32|er AVX512
VFNMSUB132SD
                 xmmreg|mask|z,xmmreg,xmmrm64|er AVX512
VFNMSUB132SS
                 xmmreg|mask|z,xmmreg,xmmrm32|er AVX512
VFNMSUB213PD
                 xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
VFNMSUB213PD
                 ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
VFNMSUB213PD
                 zmmreg mask z, zmmreg, zmmrm512 b64 er AVX512
                 xmmreg|mask|z,xmmreg,xmmrm128|b32 AVX512VL
VENMSHR213PS
VFNMSUB213PS
                 ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
VFNMSUB213PS
                 zmmreg|mask|z,zmmreg,zmmrm512|b32|er AVX512
VFNMSUB213SD
                 xmmreg|mask|z,xmmreg,xmmrm64|er AVX512
VFNMSUB213SS
                 xmmreg|mask|z,xmmreg,xmmrm32|er AVX512
VFNMSUB231PD
                 xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
VFNMSUB231PD
                 ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
VFNMSUB231PD
                 zmmreg|mask|z,zmmreg,zmmrm512|b64|er AVX512
VFNMSUB231PS
                 xmmreg|mask|z,xmmreg,xmmrm128|b32 AVX512VL
VFNMSUB231PS
                 ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
VFNMSUB231PS
                 zmmreg|mask|z,zmmreg,zmmrm512|b32|er AVX512
VENMSUB231SD
                 xmmreg|mask|z,xmmreg,xmmrm64|er AVX512
VFNMSUB231SS
                 xmmreg|mask|z,xmmreg,xmmrm32|er AVX512
VFPCLASSPD
                 kreg|mask,xmmrm128|b64,imm8 AVX512VL/DQ
VFPCLASSPD
                 kreg|mask,ymmrm256|b64,imm8 AVX512VL/DQ
VFPCLASSPD
                 kreg | mask, zmmrm512 | b64, imm8 AVX512DQ
VFPCLASSPS
                 kreg|mask,xmmrm128|b32,imm8 AVX512VL/DQ
VFPCLASSPS
                 kreg | mask, ymmrm256 | b32, imm8 AVX512VL/D0
VFPCLASSPS
                 kreg | mask, zmmrm512 | b32, imm8 AVX512DQ
VFPCLASSSD
                 kreg|mask,xmmrm64,imm8
                                           AVX512D0
VFPCLASSSS
                 kreg|mask,xmmrm32,imm8
                                           AVX512D0
VGATHERDPD
                 xmmreg|mask,xmem64
                                           AVX512VL
VGATHERDPD
                                           AVX512VL
                 ymmreg|mask,xmem64
VGATHERDPD
                 zmmreg | mask, ymem64
                                           AVX512
VGATHERDPS
                 xmmreg|mask,xmem32
                                           AVX512VI
VGATHERDPS
                                           AVX512VL
                 ymmreg|mask,ymem32
VGATHERDPS
                                           AVX512
                 zmmreg|mask,zmem32
VGATHERPF0DPD
                                           AVX512PF
                 vmem64|mask
VGATHERPF0DPS
                 zmem32|mask
                                           AVX512PF
VGATHERPF0QPD
                 zmem64 mask
                                           AVX512PF
VGATHERPF0QPS
                 zmem32|mask
                                           AVX512PF
VGATHERPF1DPD
                 vmem64 mask
                                           AVX512PF
VGATHERPF1DPS
                 zmem32|mask
                                           AVX512PF
```

```
VGATHERPF1QPD
                   zmem64|mask
                                               AVX512PF
                   zmem32|mask
VGATHERPF10PS
                                               AVX512PF
VGATHEROPD
                                               AVX512VL
                   xmmreg mask, xmem64
VGATHERQPD
                   ymmreg|mask,ymem64
                                               AVX512VL
VGATHERQPD
                   zmmreg|mask,zmem64
                                               AVX512
VGATHERQPS
                   xmmreg|mask,xmem32
                                               AVX512VL
VGATHERQPS
                                               AVX512VL
                   xmmreg|mask,ymem32
VGATHEROPS
                   ymmreg mask,zmem32
                                               AVX512
VGETEXPPD
                   xmmreg|mask|z,xmmrm128|b64 AVX512VL
                   ymmreg|mask|z,ymmrm256|b64 AVX512VL
VGFTFXPPD
VGETEXPPD
                   zmmreg|mask|z,zmmrm512|b64|sae AVX512
VGETEXPPS
                   xmmreg|mask|z,xmmrm128|b32 AVX512VL
                   ymmreg|mask|z,ymmrm256|b32 AVX512VL
VGETEXPPS
VGETEXPPS
                   zmmreg|mask|z,zmmrm512|b32|sae AVX512
VGETEXPSD
                   xmmreg|mask|z,xmmreg,xmmrm64|sae AVX512
VGETEXPSS
                   xmmreg|mask|z,xmmreg,xmmrm32|sae AVX512
VGETMANTPD
                   xmmreg|mask|z,xmmrm128|b64,imm8 AVX512VL
VGETMANTPD
                   ymmreg|mask|z,ymmrm256|b64,imm8 AVX512VL
VGETMANTPD
                   zmmreg|mask|z,zmmrm512|b64|sae,imm8 AVX512
VGETMANTPS
                   xmmreg|mask|z,xmmrm128|b32,imm8 AVX512VL
                   ymmreg|mask|z,ymmrm256|b32,imm8 AVX512VL
VGETMANTPS
VGETMANTPS
                   zmmreg|mask|z,zmmrm512|b32|sae,imm8 AVX512
VGETMANTSD
                   xmmreg|mask|z,xmmreg,xmmrm64|sae,imm8 AVX512
VGETMANTSS
                   xmmreg|mask|z,xmmreg,xmmrm32|sae,imm8 AVX512
VINSERTF32X4
                   ymmreg|mask|z,ymmreg*,xmmrm128,imm8 AVX512VL
VINSERTF32X4
                   zmmreg|mask|z,zmmreg*,xmmrm128,imm8 AVX512
VINSERTF32X8
                   zmmreg|mask|z,zmmreg*,ymmrm256,imm8 AVX512DQ
                   ymmreg|mask|z,ymmreg*,xmmrm128,imm8 AVX512VL/DQ
zmmreg|mask|z,zmmreg*,xmmrm128,imm8 AVX512DQ
VINSERTF64X2
VINSERTF64X2
                   zmmreg|mask|z,zmmreg*,ymmrm256,imm8 AVX512
VINSERTF64X4
VTNSFRTT32X4
                   ymmreg|mask|z,ymmreg*,xmmrm128,imm8 AVX512VL
VINSERTI32X4
                   zmmreg|mask|z,zmmreg*,xmmrm128,imm8 AVX512
                   zmmreg|mask|z,zmmreg*,ymmrm256,imm8 AVX512DQ
ymmreg|mask|z,ymmreg*,xmmrm128,imm8 AVX512VL/DQ
zmmreg|mask|z,zmmreg*,xmmrm128,imm8 AVX512DQ
VINSERTI32X8
VINSERTI64X2
VTNSFRTT64X2
                   zmmreg|mask|z,zmmreg*,ymmrm256,imm8 AVX512
VINSERTI64X4
                   xmmreg,xmmreg*,xmmrm32,imm8 AVX512
VINSERTPS
                   \verb|xmmreg|| mask|z, \verb|xmmreg*|, \verb|xmmrm128|| b64 AVX512VL|
VMAXPD
                   ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b64|sae AVX512
VMAXPD
VMAXPD
                   xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
VMAXPS
VMAXPS
                   ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
VMAXPS
                   zmmreg|mask|z,zmmreg*,zmmrm512|b32|sae AVX512
                   xmmreg|mask|z,xmmreg*,xmmrm64|sae AVX512
xmmreg|mask|z,xmmreg*,xmmrm32|sae AVX512
VMAXSD
VMAXSS
                   xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
VMTNPD
VMINPD
                   ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
VMINPD
                   zmmreg|mask|z,zmmreg*,zmmrm512|b64|sae AVX512
VMINPS
                   xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
                   ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b32|sae AVX512
xmmreg|mask|z,xmmreg*,xmmrm64|sae AVX512
VMINPS
VMTNPS
VMINSD
VMINSS
                   xmmreg|mask|z,xmmreg*,xmmrm32|sae AVX512
VMOVAPD
                   xmmreg|mask|z,xmmrm128
                                               AVX512VI
VMOVAPD
                   ymmreg|mask|z,ymmrm256
                                               AVX512VL
VMOVAPD
                   zmmreg|mask|z,zmmrm512
                                               AVX512
VMOVAPD
                   xmmreg|mask|z,xmmreg
                                               AVX512VL
VMOVAPD
                   ymmreg|mask|z,ymmreg
                                               AVX512VL
VMOVAPD
                   zmmreg|mask|z,zmmreg
                                               AVX512
                   mem128 | mask, xmmreg
                                               AVX512VL
VMOVAPD
                   mem256 | mask, ymmreg
                                               AVX512VL
VMOVAPD
                   mem512 | mask,zmmreg
VMOVAPD
                                               AVX512
VMOVAPS
                   xmmreg|mask|z,xmmrm128
                                               AVX512VL
VMOVAPS
                   ymmreg|mask|z,ymmrm256
                                               AVX512VL
VMOVAPS
                   zmmreg|mask|z,zmmrm512
                                               AVX512
VMOVAPS
                   xmmreg|mask|z,xmmreg
                                               AVX512VL
VMOVAPS
                   ymmreg|mask|z,ymmreg
                                               AVX512VL
```

VMOVAPS	zmmreg mask z,zmmreg	AVX512
VMOVAPS	mem128 mask,xmmreg	AVX512VL
VMOVAPS	mem256 mask,ymmreg	AVX512VL
VMOVAPS	mem512 mask,zmmreg	AVX512
VMOVD	xmmreg,rm32	AVX512
VMOVD	rm32,xmmreg	AVX512
VMOVDDUP	xmmreg mask z,xmmrm64	AVX512VL
VMOVDDUP	ymmreg mask z,ymmrm256	AVX512VL
VMOVDDUP	zmmreg mask z,zmmrm512	AVX512
VMOVDQA32	xmmreg mask z,xmmrm128	AVX512VL
VMOVDQA32	ymmreg mask z,ymmrm256	AVX512VL
VMOVDQA32	zmmreg mask z,zmmrm512	AVX512
VMOVDQA32	xmmrm128 mask z,xmmreg	AVX512VL
VMOVDQA32	ymmrm256 mask z,ymmreg	AVX512VL
VMOVDQA32	zmmrm512 mask z,zmmreg	AVX512
VMOVDQA64	xmmreg mask z,xmmrm128	AVX512VL
VMOVDQA64	ymmreg mask z,ymmrm256	AVX512VL
-		
VMOVDQA64	zmmreg mask z,zmmrm512	AVX512
VMOVDQA64	xmmrm128 mask z,xmmreg	AVX512VL
VMOVDQA64	ymmrm256 mask z,ymmreg	AVX512VL
VMOVDQA64	zmmrm512 mask z,zmmreg	AVX512
VMOVDQU16	xmmreg mask z,xmmrm128	AVX512VL/BW
VMOVDQU16	ymmreg mask z,ymmrm256	AVX512VL/BW
VMOVDQU16	zmmreg mask z,zmmrm512	AVX512BW
VMOVDQU16	xmmrm128 mask z,xmmreg	AVX512VL/BW
VMOVDQU16	ymmrm256 mask z,ymmreg	AVX512VL/BW
•		AVX512VE/BW AVX512BW
VMOVDQU16	zmmrm512 mask z,zmmreg	
VMOVDQU32	xmmreg mask z,xmmrm128	AVX512VL
VMOVDQU32	ymmreg mask z,ymmrm256	AVX512VL
VMOVDQU32	zmmreg mask z,zmmrm512	AVX512
VMOVDQU32	xmmrm128 mask z,xmmreg	AVX512VL
VMOVDQU32	ymmrm256 mask z,ymmreg	AVX512VL
VMOVDQU32	zmmrm512 mask z,zmmreg	AVX512
VMOVDQU64	xmmreg mask z,xmmrm128	AVX512VL
VMOVDQU64	ymmreg mask z,ymmrm256	AVX512VL
VMOVDQU64	zmmreg mask z,zmmrm512	AVX512VE
-		
VMOVDQU64	xmmrm128 mask z,xmmreg	AVX512VL
VMOVDQU64	ymmrm256 mask z,ymmreg	AVX512VL
VMOVDQU64	zmmrm512 mask z,zmmreg	AVX512
VMOVDQU8	xmmreg mask z,xmmrm128	AVX512VL/BW
VMOVDQU8	ymmreg mask z,ymmrm256	AVX512VL/BW
VMOVDQU8	zmmreg mask z,zmmrm512	AVX512BW
VMOVDQU8	xmmrm128 mask z,xmmreg	AVX512VL/BW
VMOVDQU8	ymmrm256 mask z,ymmreg	AVX512VL/BW
VMOVDQU8	zmmrm512 mask z,zmmreg	AVX512BW
VMOVHLPS	xmmreg,xmmreg*,xmmreg	AVX512DW AVX512
VMOVHPD	xmmreg,xmmreg*,mem64	AVX512
VMOVHPD	mem64,xmmreg	AVX512
VMOVHPS	xmmreg,xmmreg*,mem64	AVX512
VMOVHPS	mem64,xmmreg	AVX512
VMOVLHPS	xmmreg,xmmreg*,xmmreg	AVX512
VMOVLPD	xmmreg,xmmreg*,mem64	AVX512
VMOVLPD	mem64,xmmreg	AVX512
VMOVLPS	xmmreg,xmmreg*,mem64	AVX512
VMOVLPS	mem64,xmmreg	AVX512
VMOVNTDQ	mem128,xmmreg	AVX512VL
•		
VMOVNTDO	mem256,ymmreg	AVX512VL
VMOVNTDOA	mem512,zmmreg	AVX512
VMOVNTDQA	xmmreg, mem128	AVX512VL
VMOVNTDQA	ymmreg,mem256	AVX512VL
VMOVNTDQA	zmmreg,mem512	AVX512
VMOVNTPD	mem128,xmmreg	AVX512VL
VMOVNTPD	mem256,ymmreg	AVX512VL
VMOVNTPD	mem512,zmmreg	AVX512
VMOVNTPS	mem128,xmmreg	AVX512VL
VMOVNTPS	mem256,ymmreg	AVX512VL AVX512VL
VMOVNTPS	, ,	AVX512VL AVX512
VIIOVIVIES	mem512,zmmreg	NV NJIZ

```
VMOVQ
                                                                            AVX512
                               xmmreg, rm64
VMOVO
                               rm64,xmmreg
                                                                            AVX512
VMOVO
                               xmmreg,xmmrm64
                                                                            AVX512
VMOVQ
                               xmmrm64,xmmreg
                                                                            AVX512
VMOVSD
                                                                            AVX512
                               xmmreg|mask|z,mem64
VMOVSD
                              mem64|mask,xmmreg
                                                                            AVX512
                               xmmreg|mask|z,xmmreg*,xmmreg AVX512
VMOVSD
VMOVSD
                              xmmreg|mask|z,xmmreg*,xmmreg AVX512
VMOVSHDUP
                               xmmreg|mask|z,xmmrm128
                                                                            AVX512VL
VMOVSHDUP
                               ymmreg|mask|z,ymmrm256
                                                                            AVX512VL
VMOVSHDUP
                               zmmreg|mask|z,zmmrm512
                                                                            AVX512
VMOVSLDUP
                               xmmreg|mask|z,xmmrm128
                                                                            AVX512VL
VMOVSLDUP
                               ymmreg|mask|z,ymmrm256
                                                                            AVX512VL
VMOVSLDUP
                               zmmreg|mask|z,zmmrm512
                                                                            AVX512
VMOVSS
                               xmmreg|mask|z,mem32
                                                                            AVX512
                              mem32|mask,xmmreg
VMOVSS
                                                                            AVX512
VMOVSS
                               xmmreg|mask|z,xmmreg*,xmmreg AVX512
                               xmmreg|mask|z,xmmreg*,xmmreg AVX512
VMOVSS
VMOVUPD
                              xmmreg|mask|z,xmmrm128
                                                                           AVX512VI
VMOVUPD
                              ymmreg|mask|z,ymmrm256
                                                                            AVX512VL
                                                                            AVX512
VMOVUPD
                               zmmreg|mask|z,zmmrm512
VMOVUPD
                               xmmreg | mask | z, xmmreg
                                                                            AVX512VL
VMOVUPD
                               ymmreg|mask|z,ymmreg
                                                                            AVX512VL
                              zmmreg|mask|z,zmmreg
VMOVUPD
                                                                            AVX512
VMOVUPD
                              mem128 | mask, xmmreg
                                                                            AVX512VL
VMOVUPD
                              mem256 | mask, ymmreg
                                                                            AVX512VL
VMOVUPD
                              mem512 | mask,zmmreg
                                                                            AVX512
                                                                            AVX512VL
VMOVUPS
                               xmmreg|mask|z,xmmrm128
VMOVUPS
                              ymmreg|mask|z,ymmrm256
                                                                            AVX512VL
VMOVUPS
                               zmmreg|mask|z,zmmrm512
                                                                            AVX512
VMOVUPS
                               xmmreg|mask|z,xmmreg
                                                                            AVX512VL
VMOVUPS
                                                                            AVX512VL
                               ymmreg|mask|z,ymmreg
VMOVUPS
                               zmmreg|mask|z,zmmreg
                                                                            AVX512
VMOVUPS
                              mem128 | mask, xmmreg
                                                                            AVX512VL
                              mem256 mask, ymmreg
VMOVUPS
                                                                            ΔVX512VI
VMOVUPS
                              mem512|mask.zmmreg
                                                                            AVX512
                               xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
VMULPD
VMULPD
                              ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
                              zmmreg|mask|z,zmmreg*,zmmrm512|b64|er AVX512
xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
VMULPD
VMULPS
                              vmmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
VMULPS
VMULPS
                               zmmreg|mask|z,zmmreg*,zmmrm512|b32|er AVX512
VMULSD
                               xmmreg|mask|z,xmmreg*,xmmrm64|er AVX512
                              xmmreg|mask|z,xmmreg*,xmmrm32|er AVX512
xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL/DQ
VMULSS
VORPD
                               ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL/DQ
VORPD
                               zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512DQ
VORPD
VORPS
                               xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL/DQ
                               ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL/DQ
VORPS
VORPS
                               zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512DQ
VPABSB
                               xmmreg|mask|z,xmmrm128
                                                                           AVX512VL/BW
VPABSB
                              ymmreg|mask|z,ymmrm256
                                                                           AVX512VL/BW
                               zmmreg|mask|z,zmmrm512
VPABSB
                                                                           AVX512BW
                               xmmreg|mask|z,xmmrm128|b32 AVX512VL
VPABSD
VPABSD
                               ymmreg|mask|z,ymmrm256|b32 AVX512VL
VPABSD
                               zmmreg|mask|z,zmmrm512|b32 AVX512
                               xmmreg|mask|z,xmmrm128|b64 AVX512VL
VPABS0
VPABSQ
                              ymmreg|mask|z,ymmrm256|b64 AVX512VL
VPABSQ
                               zmmreg|mask|z,zmmrm512|b64 AVX512
                               xmmreg|mask|z,xmmrm128
VPABSW
                                                                         AVX512VL/BW
VPABSW
                               ymmreg|mask|z,ymmrm256
                                                                           AVX512VL/BW
VPABSW
                               zmmreg|mask|z,zmmrm512
                                                                           AVX512BW
VPACKSSDW
                               xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL/BW
VPACKSSDW
                              ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL/BW
VPACKSSDW
                               zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512BW
                               \verb|xmmreg|| mask|| \verb|z|, \verb|xmmreg|| mask|| \verb|z|, \verb|xmmreg|| mask|| \verb|z|, \verb|xmmreg|| mask|| \verb|z|, \verb|xmmreg|| mask|| mask|
VPACKSSWB
VPACKSSWB
                               ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
```

```
VPACKSSWB
                     zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
                     xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL/BW
VPACKUSDW
VPACKUSDW
                    ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL/BW
VPACKUSDW
                     zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512BW
VPACKUSWB
                     xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
                    ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPACKUSWB
VPACKUSWB
                    xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
VPADDB
                    ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
VPADDB
VPADDB
                     zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
                    xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
VPADDD
VPADDD
VPADDD
                     xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
VPADDQ
VPADDQ
                    ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
VPADDO
                     zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
                    xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPADDSB
VPADDSB
VPADDSB
VPADDSW
                     xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
VPADDSW
                     ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
VPADDSW
                     zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
                    xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
VPADDUSB
VPADDUSB
                     zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPADDUSB
VPADDUSW
                     xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
VPADDUSW
                     ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
                    zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
VPADDUSW
VPADDW
                    ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
VPADDW
VPADDW
                     zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPALIGNR
                     xmmreg|mask|z,xmmreg*,xmmrm128,imm8 AVX512VL/BW
                    ymmreg|mask|z,ymmreg*,ymmrm256,imm8 AVX512VL/BW zmmreg|mask|z,zmmreg*,zmmrm512,imm8 AVX512BW xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
VPALIGNR
VPALIGNR
VPANDD
                    ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
VPANDD
                     zmmreg | mask | z, zmmreg*, zmmrm512 | b32 AVX512
VPANDD
VPANDND
                     xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
                    ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
VPANDND
VPANDND
                    xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
VPANDNO
VPANDNQ
                    ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
VPANDNQ
                     zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
                    xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
VPANDO
VPANDQ
VPANDO
VPAVGB
                     xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
VPAVGB
                    ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
VPAVGB
                     zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
                    xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPAVGW
VPAVGW
VPAVGW
VPBLENDMB
                     xmmreg|mask|z,xmmreg,xmmrm128 AVX512VL/BW
VPBLENDMB
                     ymmreg|mask|z,ymmreg,ymmrm256 AVX512VL/BW
VPBLENDMB
                     zmmreg|mask|z,zmmreg,zmmrm512 AVX512BW
VPBLENDMD
                     xmmreg|mask|z,xmmreg,xmmrm128|b32 AVX512VL
VPRI ENDMD
                     ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
VPBLENDMD
                     zmmreg|mask|z,zmmreg,zmmrm512|b32 AVX512
VPBLENDMQ
                     xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
VPBLENDMO
                     ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
VPBLENDMO
                     zmmreg|mask|z,zmmreg,zmmrm512|b64 AVX512
VPRI FNDMW
                     xmmreg|mask|z,xmmreg,xmmrm128 AVX512VL/BW
VPBLENDMW
                    ymmreg|mask|z,ymmreg,ymmrm256 AVX512VL/BW
VPBLENDMW
                     zmmreg mask z,zmmreg,zmmrm512 AVX512BW
VPBROADCASTB
                                                   AVX512VL/BW
                     xmmreg|mask|z,xmmrm8
VPBROADCASTB
                    ymmreg|mask|z,xmmrm8
                                                   AVX512VL/BW
VPBROADCASTB
                     zmmreg|mask|z,xmmrm8
                                                   AVX512BW
```

```
VPBROADCASTB
                 xmmreg|mask|z,reg8
                                           AVX512VL/BW
VPBROADCASTB
                 xmmreg|mask|z,reg16
                                           AVX512VL/BW
VPBROADCASTB
                 xmmreg|mask|z,reg32
                                           AVX512VL/BW
VPBROADCASTB
                 xmmreg|mask|z,reg64
                                           AVX512VL/BW
VPBROADCASTB
                 ymmreg|mask|z,reg8
                                           AVX512VL/BW
VPBROADCASTB
                 ymmreg|mask|z,reg16
                                           AVX512VL/BW
VPBROADCASTB
                 ymmreg|mask|z,reg32
                                           AVX512VL/BW
VPBROADCASTB
                 ymmreg|mask|z,reg64
                                           AVX512VL/BW
VPBROADCASTB
                 zmmreg|mask|z,reg8
                                           AVX512BW
VPBROADCASTB
                 zmmreg|mask|z,reg16
                                           AVX512BW
VPBROADCASTB
                 zmmreg|mask|z,reg32
                                           AVX512BW
VPBROADCASTB
                 zmmreg|mask|z,reg64
                                           AVX512BW
VPBROADCASTD
                 xmmreg|mask|z,mem32
                                           AVX512VL
VPBROADCASTD
                 ymmreg|mask|z,mem32
                                           AVX512VL
VPBROADCASTD
                 zmmreg|mask|z,mem32
                                           AVX512
                 xmmreg|mask|z,xmmreg
VPBROADCASTD
                                           AVX512VI
VPBROADCASTD
                 ymmreg|mask|z,xmmreg
                                           AVX512VL
VPBROADCASTD
                 zmmreg|mask|z,xmmreg
                                           AVX512
VPBROADCASTD
                 xmmreg|mask|z,reg32
                                           AVX512VL
VPBROADCASTD
                 ymmreg|mask|z,reg32
                                           AVX512VL
VPBROADCASTD
                 zmmreg|mask|z,reg32
                                           AVX512
                 xmmreg,kreg
VPBROADCASTMB20
                                           AVX512VL/CD
VPBROADCASTMB20
                 ymmreg, kreg
                                           AVX512VL/CD
VPBROADCASTMB20
                 zmmreg, kreg
                                           AVX512CD
VPBROADCASTMW2D
                 xmmreg, kreg
                                           AVX512VL/CD
VPBROADCASTMW2D
                 ymmreg, kreg
                                           AVX512VL/CD
VPBROADCASTMW2D
                                           AVX512CD
                 zmmreg, kreg
                                           AVX512VL
VPBROADCASTQ
                 xmmreg|mask|z,mem64
VPBROADCASTO
                 ymmreg|mask|z,mem64
                                           AVX512VL
VPBROADCASTO
                 zmmreg|mask|z,mem64
                                           AVX512
VPBROADCASTQ
                 xmmreg|mask|z,xmmreg
                                           AVX512VL
VPBROADCASTO
                 ymmreg|mask|z,xmmreg
                                           AVX512VL
VPBROADCASTO
                 zmmreg | mask | z, xmmreg
                                           AVX512
VPBROADCASTQ
                 xmmreg | mask | z, reg64
                                           AVX512VL
VPBROADCASTO
                 ymmreg|mask|z,reg64
                                           AVX512VI
VPBROADCASTO
                 zmmreg|mask|z.reg64
                                           AVX512
VPBROADCASTW
                 xmmreg|mask|z,xmmrm16
                                           AVX512VL/BW
VPBROADCASTW
                                           AVX512VL/BW
                 ymmreg|mask|z,xmmrm16
VPBROADCASTW
                 zmmreg|mask|z,xmmrm16
                                           AVX512BW
VPBROADCASTW
                 xmmreg|mask|z,reg16
                                           AVX512VL/BW
                                           AVX512VL/BW
VPBROADCASTW
                 xmmreg|mask|z,reg32
VPBROADCASTW
                 xmmreg|mask|z,reg64
                                           AVX512VL/BW
VPBROADCASTW
                                           AVX512VL/BW
                 ymmreg|mask|z,reg16
VPBROADCASTW
                 ymmreg mask z,reg32
                                           AVX512VL/BW
VPBROADCASTW
                 ymmreg|mask|z,reg64
                                           AVX512VL/BW
                 zmmreg|mask|z,reg16
VPBROADCASTW
                                           AVX512BW
VPBROADCASTW
                 zmmreg|mask|z,reg32
                                           AVX512BW
VPBROADCASTW
                 zmmreg|mask|z,reg64
                                           AVX512BW
                 kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPEQB
VPCMPEQB
                 kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPEQB
                 kreg|mask,zmmreg,zmmrm512 AVX512BW
                 kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VPCMPEOD
                 kreg | mask, ymmreg, ymmrm256 | b32 AVX512VL
VPCMPEOD
VPCMPEOD
                 kreg mask, zmmreg, zmmrm512 b32 AVX512
VPCMPE00
                 kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VPCMPEQQ
                 kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
                 kreg|mask,zmmreg,zmmrm512|b64 AVX512
VPCMPEQQ
VPCMPEQW
                 kreg | mask, xmmreg, xmmrm128 AVX512VL/BW
VPCMPEQW
                 kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPEQW
                 kreg|mask,zmmreg,zmmrm512 AVX512BW
VPCMPGTB
                 kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPGTB
                 kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
                 kreg|mask,zmmreg,zmmrm512 AVX512BW
VPCMPGTB
VPCMPGTD
                 kreg mask, xmmreg, xmmrm128 b32 AVX512VL
VPCMPGTD
                 kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
                 kreg|mask,zmmreg,zmmrm512|b32 AVX512
VPCMPGTD
VPCMPGTQ
                 kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
```

```
VPCMPGTQ
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VPCMPGTQ
                  kreg mask, zmmreg, zmmrm512 b64 AVX512
VPCMPGTW
                  kreg | mask, xmmreg, xmmrm128 AVX512VL/BW
VPCMPGTW
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
VPCMPGTW
VPCMPEQB
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPEQB
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPEOB
                  kreg mask, zmmreg, zmmrm512 AVX512BW
VPCMPEQD
                  kreg mask, xmmreg, xmmrm128 b32 AVX512VL
VPCMPEQD
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VPCMPEOD
                  kreg|mask,zmmreg,zmmrm512|b32 AVX512
VPCMPEQQ
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VPCMPEQQ
VPCMPEQQ
                  kreg mask, zmmreg, zmmrm512 b64 AVX512
VPCMPEQUB
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPEOUB
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPEQUB
                  kreg | mask, zmmreg, zmmrm512 AVX512BW
VPCMPEQUD
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VPCMPEOUD
VPCMPEOUD
                  kreg|mask,zmmreg,zmmrm512|b32 AVX512
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VPCMPEOUO
VPCMPEQUQ
                  kreg | mask, ymmreg, ymmrm256 | b64 AVX512VL
VPCMPEQUO
                  kreg mask, zmmreg, zmmrm512 b64 AVX512
VPCMPEOUW
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPEQUW
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPEQUW
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
                  kreg | mask, xmmreg, xmmrm128 AVX512VL/BW
VPCMPEQW
VPCMPEQW
                  kreg | mask, ymmreg, ymmrm256 AVX512VL/BW
VPCMPEQW
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
VPCMPGEB
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPGEB
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPGEB
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
VPCMPGED
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VPCMPGED
                  kreg mask, ymmreg, ymmrm256 b32 AVX512VL
                  kreg|mask,zmmreg,zmmrm512|b32 AVX512
VPCMPGED
VPCMPGEO
                  kreg|mask.xmmreg.xmmrm128|b64 AVX512VL
VPCMPGEQ
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VPCMPGEQ
                  kreg mask,zmmreg,zmmrm512 b64 AVX512
VPCMPGEUB
                  kreg | mask, xmmreg, xmmrm128 AVX512VL/BW
VPCMPGEUB
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPGEUB
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
VPCMPGEUD
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VPCMPGEUD
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VPCMPGEUD
                  kreg mask, zmmreg, zmmrm512 b32 AVX512
VPCMPGEUQ
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VPCMPGEUO
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VPCMPGEU0
                  kreg|mask,zmmreg,zmmrm512|b64 AVX512
VPCMPGEUW
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPGEUW
VPCMPGEUW
                  kreg | mask, zmmreg, zmmrm512 AVX512BW
VPCMPGEW
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
                  kreg mask, ymmreg, ymmrm256 AVX512VL/BW
VPCMPGEW
VPCMPGEW
                  kreg mask, zmmreg, zmmrm512 AVX512BW
VPCMPGTB
                  kreg mask, xmmreg, xmmrm128 AVX512VL/BW
VPCMPGTB
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPGTB
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VPCMPGTD
VPCMPGTD
                  kreg | mask, ymmreg, ymmrm256 | b32 AVX512VL
VPCMPGTD
                  kreg|mask,zmmreg,zmmrm512|b32 AVX512
VPCMPGTO
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
                  kreg | mask, ymmreg, ymmrm256 | b64 AVX512VL
VPCMPGTQ
VPCMPGTO
                  kreg|mask,zmmreg,zmmrm512|b64 AVX512
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPGTUB
VPCMPGTUB
                  kreg mask, ymmreg, ymmrm256 AVX512VL/BW
VPCMPGTUB
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
VPCMPGTUD
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VPCMPGTUD
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
```

```
VPCMPGTUD
                  kreg|mask,zmmreg,zmmrm512|b32 AVX512
VPCMPGTUO
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VPCMPGTUO
                  kreg | mask, ymmreg, ymmrm256 | b64 AVX512VL
VPCMPGTUQ
                  kreg|mask,zmmreg,zmmrm512|b64 AVX512
VPCMPGTUW
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPGTUW
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPGTUW
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
VPCMPGTW
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPGTW
                  kreg mask, ymmreg, ymmrm256 AVX512VL/BW
VPCMPGTW
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
VPCMPLEB
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPLEB
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPLEB
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
VPCMPI FD
                  kreg mask, xmmreg, xmmrm128 b32 AVX512VL
VPCMPLED
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
                  kreg|mask,zmmreg,zmmrm512|b32 AVX512
VPCMPI FD
VPCMPLEQ
                  kreg | mask, xmmreg, xmmrm128 | b64 AVX512VL
VPCMPLEO
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VPCMPLEO
                  kreg mask, zmmreg, zmmrm512 b64 AVX512
VPCMPLEUB
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPLEUB
VPCMPLEUB
                  kreg | mask, zmmreg, zmmrm512 AVX512BW
VPCMPLEUD
                  kreg | mask, xmmreg, xmmrm128 | b32 AVX512VL
VPCMPI FUD
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VPCMPLEUD
                  kreg|mask,zmmreg,zmmrm512|b32 AVX512
VPCMPLEUQ
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VPCMPLEUQ
                  kreg | mask, ymmreg, ymmrm256 | b64 AVX512VL
VPCMPLEUQ
                  kreg|mask,zmmreg,zmmrm512|b64 AVX512
VPCMPLEUW
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPLEUW
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPLEUW
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
VPCMPLEW
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPLEW
                  kreg | mask, ymmreg, ymmrm256 AVX512VL/BW
VPCMPLEW
                  kreg mask, zmmreg, zmmrm512 AVX512BW
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPI TR
VPCMPLTB
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPLTB
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
VPCMPI TD
                  kreg mask, xmmreg, xmmrm128 b32 AVX512VL
VPCMPLTD
                  kreg mask, ymmreg, ymmrm256 b32 AVX512VL
VPCMPLTD
                  kreg|mask,zmmreg,zmmrm512|b32 AVX512
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VPCMPLTO
VPCMPLTO
                  kreg | mask, ymmreg, ymmrm256 | b64 AVX512VL
                  kreg|mask,zmmreg,zmmrm512|b64 AVX512
VPCMPLTO
VPCMPLTUB
                  kreg | mask, xmmreg, xmmrm128 AVX512VL/BW
VPCMPLTUB
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPI TUB
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
VPCMPLTUD
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VPCMPLTUD
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VPCMPLTUD
                  kreg mask, zmmreg, zmmrm512 b32 AVX512
VPCMPLTUQ
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VPCMPLTUQ
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VPCMPLTUQ
                  kreg | mask, zmmreg, zmmrm512 | b64 AVX512
VPCMPLTUW
                  kreg | mask, xmmreg, xmmrm128 AVX512VL/BW
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPI TUW
VPCMPLTUW
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
VPCMPLTW
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPLTW
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPLTW
                  kreg mask, zmmreg, zmmrm512 AVX512BW
VPCMPNEQB
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPNFOB
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPNEQB
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
VPCMPNEOD
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VPCMPNEOD
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VPCMPNEQD
                  kreg mask, zmmreg, zmmrm512 b32 AVX512
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VPCMPNEQQ
VPCMPNEOO
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VPCMPNEQQ
                 kreg|mask,zmmreg,zmmrm512|b64 AVX512
```

```
VPCMPNEQUB
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPNEQUB
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPNEQUB
                  kreg mask, zmmreg, zmmrm512 AVX512BW
VPCMPNEQUD
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VPCMPNEQUD
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VPCMPNEQUD
                  kreg | mask, zmmreg, zmmrm512 | b32 AVX512
VPCMPNEQUQ
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VPCMPNEOUO
                  kreg | mask, ymmreg, ymmrm256 | b64 AVX512VL
VPCMPNEQUQ
                  kreg mask, zmmreg, zmmrm512 b64 AVX512
VPCMPNEQUW
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPNEOUW
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPNEQUW
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPNEQW
VPCMPNEQW
                  kreg mask, ymmreg, ymmrm256 AVX512VL/BW
VPCMPNEQW
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
VPCMPNGTB
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPNGTB
                  kreg | mask, ymmreg, ymmrm256 AVX512VL/BW
VPCMPNGTB
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
VPCMPNGTD
                  kreg mask, xmmreg, xmmrm128 b32 AVX512VL
VPCMPNGTD
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
                  kreg|mask,zmmreg,zmmrm512|b32 AVX512
VPCMPNGTD
VPCMPNGTQ
                  kreg | mask, xmmreg, xmmrm128 | b64 AVX512VL
VPCMPNGTO
                  kreg | mask, ymmreg, ymmrm256 | b64 AVX512VL
VPCMPNGTO
                  kreg|mask,zmmreg,zmmrm512|b64 AVX512
VPCMPNGTUB
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPNGTUB
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
VPCMPNGTUB
VPCMPNGTUD
                  kreg mask, xmmreg, xmmrm128 b32 AVX512VL
VPCMPNGTUD
                  kreg mask, ymmreg, ymmrm256 b32 AVX512VL
VPCMPNGTUD
                  kreg | mask, zmmreg, zmmrm512 | b32 AVX512
VPCMPNGTUQ
                  kreg | mask, xmmreg, xmmrm128 | b64 AVX512VL
VPCMPNGTUQ
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VPCMPNGTUQ
                  kreg mask, zmmreg, zmmrm512 b64 AVX512
VPCMPNGTUW
                  kreg | mask, xmmreg, xmmrm128 AVX512VL/BW
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPNGTHW
VPCMPNGTUW
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
VPCMPNGTW
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPNGTW
                  kreg mask, ymmreg, ymmrm256 AVX512VL/BW
VPCMPNGTW
                  kreg mask, zmmreg, zmmrm512 AVX512BW
VPCMPNLEB
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPNLEB
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPNLEB
                  kreg | mask, zmmreg, zmmrm512 AVX512BW
VPCMPNI FD
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VPCMPNLED
                  kreg mask, ymmreg, ymmrm256 b32 AVX512VL
VPCMPNLED
                  kreg|mask,zmmreg,zmmrm512|b32 AVX512
VPCMPNLEO
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VPCMPNLEQ
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VPCMPNLEQ
                  kreg|mask,zmmreg,zmmrm512|b64 AVX512
VPCMPNLEUB
                  kreg | mask, xmmreg, xmmrm128 AVX512VL/BW
VPCMPNLEUB
                  kreg | mask, ymmreg, ymmrm256 AVX512VL/BW
VPCMPNLEUB
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VPCMPNLEUD
VPCMPNLEUD
                  kreg | mask, ymmreg, ymmrm256 | b32 AVX512VL
VPCMPNI FUD
                  kreg mask, zmmreg, zmmrm512 b32 AVX512
VPCMPNLEU0
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VPCMPNLEUQ
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VPCMPNLEUQ
                  kreg mask, zmmreg, zmmrm512 b64 AVX512
VPCMPNLEUW
                  kreg | mask, xmmreg, xmmrm128 AVX512VL/BW
VPCMPNLEUW
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPNLEUW
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
VPCMPNLEW
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPNLEW
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
VPCMPNLEW
VPCMPNLTB
                  kreg mask, xmmreg, xmmrm128 AVX512VL/BW
VPCMPNLTB
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPNLTB
                  kreg | mask, zmmreg, zmmrm512 AVX512BW
VPCMPNLTD
                  kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
```

```
VPCMPNLTD
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VPCMPNI TD
                  kreg|mask,zmmreg,zmmrm512|b32 AVX512
VPCMPNLTQ
                  kreg | mask, xmmreg, xmmrm128 | b64 AVX512VL
VPCMPNLTQ
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VPCMPNLTQ
                  kreg|mask,zmmreg,zmmrm512|b64 AVX512
VPCMPNLTUB
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPNLTUB
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPNLTUB
                  kreg mask, zmmreg, zmmrm512 AVX512BW
VPCMPNLTUD
                  kreg mask, xmmreg, xmmrm128 b32 AVX512VL
VPCMPNI TUD
                  kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VPCMPNLTUD
                  kreg|mask,zmmreg,zmmrm512|b32 AVX512
VPCMPNLTUQ
                  kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VPCMPNLTUQ
                  kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VPCMPNLTUQ
                  kreg mask, zmmreg, zmmrm512 b64 AVX512
VPCMPNLTUW
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPCMPNI TUW
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPNLTUW
                  kreg | mask, zmmreg, zmmrm512 AVX512BW
VPCMPNLTW
                  kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
                  kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
VPCMPNLTW
VPCMPNLTW
                  kreg|mask,zmmreg,zmmrm512 AVX512BW
                  kreg|mask,xmmreg,xmmrm128,imm8 AVX512VL/BW
VPCMPB
VPCMPB
                  kreg mask, ymmreg, ymmrm256, imm8 AVX512VL/BW
VPCMPB
                  kreg | mask, zmmreg, zmmrm512, imm8 AVX512BW
VPCMPD
                  kreg|mask,xmmreg,xmmrm128|b32,imm8 AVX512VL
VPCMPD
                  kreg|mask,ymmreg,ymmrm256|b32,imm8 AVX512VL
VPCMPD
                  kreg|mask,zmmreg,zmmrm512|b32,imm8 AVX512
VPCMPO
                  kreg | mask, xmmreg, xmmrm128 | b64, imm8 AVX512VL
                  kreg | mask, ymmreg, ymmrm256 | b64, imm8 AVX512VL
VPCMPO
VPCMPQ
                  kreg|mask,zmmreg,zmmrm512|b64,imm8 AVX512
VPCMPUB
                  kreg|mask,xmmreg,xmmrm128,imm8 AVX512VL/BW
VPCMPUB
                  kreg|mask,ymmreg,ymmrm256,imm8 AVX512VL/BW
VPCMPUB
                  kreg|mask,zmmreg,zmmrm512,imm8 AVX512BW
VPCMPUD
                  kreg|mask,xmmreg,xmmrm128|b32,imm8 AVX512VL
VPCMPUD
                  kreg|mask,ymmreg,ymmrm256|b32,imm8 AVX512VL
VPCMPIID
                  kreg|mask,zmmreg,zmmrm512|b32,imm8 AVX512
VPCMPUO
                  kreg|mask.xmmreg.xmmrm128|b64.imm8 AVX512VL
VPCMPUQ
                  kreg|mask,ymmreg,ymmrm256|b64,imm8 AVX512VL
                  kreg|mask,zmmreg,zmmrm512|b64,imm8 AVX512
VPCMPUO
VPCMPUW
                  kreg|mask,xmmreg,xmmrm128,imm8 AVX512VL/BW
VPCMPUW
                  kreg|mask,ymmreg,ymmrm256,imm8 AVX512VL/BW
VPCMPUW
                  kreg | mask, zmmreg, zmmrm512, imm8 AVX512BW
VPCMPW
                  kreg|mask,xmmreg,xmmrm128,imm8 AVX512VL/BW
VPCMPW
                  kreg|mask,ymmreg,ymmrm256,imm8 AVX512VL/BW
VPCMPW
                  kreg | mask, zmmreg, zmmrm512, imm8 AVX512BW
VPCOMPRESSD
                 mem128 | mask, xmmreg
                                            AVX512VL
                 mem256 mask, ymmreg
VPCOMPRESSD
                                            ΔVX512VI
VPCOMPRESSD
                 mem512 | mask,zmmreg
                                            AVX512
VPCOMPRESSD
                  xmmreg|mask|z,xmmreg
                                            AVX512VL
VPCOMPRESSD
                  ymmreg mask z, ymmreg
                                            AVX512VI
VPCOMPRESSD
                                            AVX512
                  zmmreg|mask|z,zmmreg
VPCOMPRESSQ
                 mem128 | mask, xmmreg
                                            AVX512VI
                 mem256 mask, ymmreg
VPCOMPRESSO
                                            AVX512VL
VPCOMPRESSQ
                 mem512 | mask,zmmreg
                                            AVX512
VPCOMPRESSQ
                  xmmreg mask z, xmmreg
                                            AVX512VI
VPCOMPRESSO
                  ymmreg|mask|z,ymmreg
                                            AVX512VL
VPCOMPRESSQ
                  zmmreg|mask|z,zmmreg
                                            AVX512
                  xmmreg|mask|z,xmmrm128|b32 AVX512VL/CD
VPCONFLICTD
VPCONFLICTD
                 ymmreg|mask|z,ymmrm256|b32 AVX512VL/CD
VPCONFLICTD
                  zmmreg|mask|z,zmmrm512|b32 AVX512CD
                  xmmreg|mask|z,xmmrm128|b64 AVX512VL/CD
VPCONFLICTQ
                  ymmreg|mask|z,ymmrm256|b64 AVX512VL/CD
VPCONFLICTQ
VPCONFLICTO
                  zmmreg|mask|z,zmmrm512|b64 AVX512CD
VPERMB
                  xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/VBMI
VPERMB
                 ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/VBMI
VPFRMB
                  zmmreg|mask|z,zmmreg*,zmmrm512 AVX512VBMI
                 ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
VPERMD
VPERMD
```

```
VPERMI2B
                  xmmreg|mask|z,xmmreg,xmmrm128 AVX512VL/VBMI
VPFRMT2B
                  ymmreg|mask|z,ymmreg,ymmrm256 AVX512VL/VBMI
VPERMI2B
                  zmmreg|mask|z,zmmreg,zmmrm512 AVX512VBMI
VPFRMT2D
                  xmmreg|mask|z,xmmreg,xmmrm128|b32 AVX512VL
                  ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
VPERMI2D
VPERMI2D
                  zmmreg|mask|z,zmmreg,zmmrm512|b32 AVX512
VPERMI2PD
                  xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
VPERMI2PD
                  ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
VPERMI2PD
                  zmmreg|mask|z,zmmreg,zmmrm512|b64 AVX512
VPFRMT2PS
                  xmmreg|mask|z,xmmreg,xmmrm128|b32 AVX512VL
VPERMI2PS
                  ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
VPERMI2PS
                  zmmreg|mask|z,zmmreg,zmmrm512|b32 AVX512
                  xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
VPERMI20
VPERMI2Q
                  ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
VPERMI2Q
                  zmmreg|mask|z,zmmreg,zmmrm512|b64 AVX512
                  xmmreg|mask|z,xmmreg,xmmrm128 AVX512VL/BW
VPFRMT2W
VPERMI2W
                  ymmreg|mask|z,ymmreg,ymmrm256 AVX512VL/BW
VPERMI2W
                  zmmreg|mask|z,zmmreg,zmmrm512 AVX512BW
VPERMILPD
                  xmmreg|mask|z,xmmrm128|b64,imm8 AVX512VL
VPERMILPD
                  ymmreg|mask|z,ymmrm256|b64,imm8 AVX512VL
VPFRMTI PD
                  zmmreg|mask|z,zmmrm512|b64,imm8 AVX512
VPERMILPD
                  xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
                  ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
VPERMILPD
VPFRMTI PD
                  xmmreg|mask|z,xmmrm128|b32,imm8 AVX512VL
VPERMILPS
VPERMILPS
                  ymmreg|mask|z,ymmrm256|b32,imm8 AVX512VL
VPERMILPS
                  zmmreg|mask|z,zmmrm512|b32,imm8 AVX512
                  xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
VPERMILPS
VPERMILPS
                  zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
VPERMILPS
VPFRMPD
                  ymmreg|mask|z,ymmrm256|b64,imm8 AVX512VL
VPERMPD
                  zmmreg|mask|z,zmmrm512|b64,imm8 AVX512
                  ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
VPERMPD
VPERMPD
VPFRMPS
                  zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
VPERMPS
                  ymmreg|mask|z,ymmrm256|b64,imm8 AVX512VL
VPERMQ
                  zmmreg|mask|z,zmmrm512|b64,imm8 AVX512
VPERMQ
                  ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
VPERMO
VPERMQ
VPERMT2B
                  xmmreg|mask|z,xmmreg,xmmrm128 AVX512VL/VBMI
VPERMT2B
                  ymmreg|mask|z,ymmreg,ymmrm256 AVX512VL/VBMI
VPFRMT2B
                  zmmreg|mask|z,zmmreg,zmmrm512 AVX512VBMI
VPERMT2D
                  xmmreg|mask|z,xmmreg,xmmrm128|b32 AVX512VL
VPERMT2D
                  ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
VPFRMT2D
                  zmmreg|mask|z,zmmreg,zmmrm512|b32 AVX512
VPERMT2PD
                  xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
VPERMT2PD
                  ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL
VPERMT2PD
                  zmmreg|mask|z,zmmreg,zmmrm512|b64 AVX512
VPERMT2PS
                  xmmreg|mask|z,xmmreg,xmmrm128|b32 AVX512VL
VPFRMT2PS
                  ymmreg|mask|z,ymmreg,ymmrm256|b32 AVX512VL
VPERMT2PS
                  zmmreg|mask|z,zmmreg,zmmrm512|b32 AVX512
                  xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL
VPERMT20
VPERMT2Q
                  ymmreg mask z, ymmreg, ymmrm256 b64 AVX512VL
VPERMT20
                  zmmreg|mask|z,zmmreg,zmmrm512|b64 AVX512
VPERMT2W
                  xmmreg|mask|z,xmmreg,xmmrm128 AVX512VL/BW
VPFRMT2W
                  ymmreg|mask|z,ymmreg,ymmrm256 AVX512VL/BW
VPERMT2W
                  zmmreg | mask | z,zmmreg,zmmrm512 AVX512BW
VPFRMW
                  xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
VPERMW
                  ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
                  zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPFRMW
VPEXPANDD
                  xmmreg|mask|z,mem128
                                             AVX512VL
VPEXPANDD
                  vmmreg|mask|z,mem256
                                             AVX512VL
VPEXPANDD
                  zmmreg|mask|z,mem512
                                             AVX512
VPEXPANDD
                                             AVX512VI
                  xmmreg|mask|z,xmmreg
VPEXPANDD
                  ymmreg|mask|z,ymmreg
                                             AVX512VL
VPEXPANDD
                  zmmreg|mask|z,zmmreg
                                             AVX512
```

```
VPEXPANDQ
                   xmmreg|mask|z,mem128
                                               AVX512VL
VPEXPANDQ
                   ymmreg|mask|z,mem256
                                               AVX512VL
VPEXPANDQ
                   zmmreg|mask|z,mem512
                                               AVX512
VPEXPANDQ
                   xmmreg|mask|z,xmmreg
                                               AVX512VL
VPEXPANDQ
                                               AVX512VL
                   ymmreg|mask|z,ymmreg
VPEXPANDQ
                   zmmreg|mask|z,zmmreg
                                               AVX512
VPEXTRB
                   reg8,xmmreg,imm8
                                               AVX512BW
VPEXTRB
                   reg16,xmmreg,imm8
                                               AVX512BW
VPEXTRB
                   reg32,xmmreg,imm8
                                               AVX512BW
VPEXTRB
                   reg64,xmmreg,imm8
                                               AVX512BW
VPEXTRB
                   mem8,xmmreg,imm8
                                               AVX512BW
VPEXTRD
                   rm32,xmmreg,imm8
                                               AVX512D0
VPEXTRQ
                   rm64,xmmreg,imm8
                                               AVX512DQ
VPEXTRW
                   reg16,xmmreg,imm8
                                               AVX512BW
VPEXTRW
                   reg32,xmmreg,imm8
                                               AVX512BW
VPFXTRW
                   reg64,xmmreg,imm8
                                               AVX512BW
VPEXTRW
                   mem16,xmmreg,imm8
                                               AVX512BW
VPEXTRW
                   reg16,xmmreg,imm8
                                               AVX512BW
VPFXTRW
                   reg32,xmmreg,imm8
                                               AVX512BW
VPEXTRW
                   reg64,xmmreg,imm8
                                               AVX512BW
VPGATHERDD
                   xmmreg|mask,xmem32
                                               AVX512VL
VPGATHERDD
                   ymmreg | mask, ymem32
                                               AVX512VL
VPGATHERDD
                   zmmreg|mask,zmem32
                                               AVX512
VPGATHERDO
                   xmmreg|mask,xmem64
                                               AVX512VL
VPGATHERDQ
                   ymmreg|mask,xmem64
                                               AVX512VL
VPGATHERDQ
                   zmmreg|mask,ymem64
                                               AVX512
VPGATHERQD
                                               AVX512VL
                   xmmreg|mask,xmem32
VPGATHERQD
                   xmmreg|mask,ymem32
                                               AVX512VL
VPGATHERQD
                   ymmreg|mask,zmem32
                                               AVX512
                                               AVX512VL
VPGATHERQQ
                   xmmreg|mask,xmem64
VPGATHERQQ
                   ymmreg|mask,ymem64
                                               AVX512VI
VPGATHERQO
                   zmmreg|mask,zmem64
                                               AVX512
                   xmmreg,xmmreg*,reg32,imm8 AVX512BW xmmreg,xmmreg*,mem8,imm8 AVX512BW xmmreg,xmmreg*,rm32,imm8 AVX512DQ
VPINSRB
VPINSRB
VPTNSRD
                   xmmreg,xmmreg*,rm64,imm8 AVX512DQ
VPINSRO
VPINSRW
                   xmmreg,xmmreg*,reg32,imm8 AVX512BW
                   xmmreg,xmmreg*,mem16,imm8 AVX512BW
VPINSRW
                   xmmreg|mask|z,xmmrm128|b32 AVX512VL/CD
VPLZCNTD
VPLZCNTD
                   ymmreg|mask|z,ymmrm256|b32 AVX512VL/CD
                   zmmreg|mask|z,zmmrm512|b32 AVX512CD
VPLZCNTD
VPLZCNTQ
                   xmmreg | mask | z, xmmrm128 | b64 AVX512VL/CD
                   ymmreg|mask|z,ymmrm256|b64 AVX512VL/CD
VPLZCNTQ
                   zmmreg|mask|z,zmmrm512|b64 AVX512CD
VPLZCNTQ
VPMADD52HUQ
                   xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL/IFMA
                   ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL/IFMA
VPMADD52HUQ
VPMADD52HUQ
                   zmmreg|mask|z,zmmreg,zmmrm512|b64 AVX512IFMA
VPMADD52LUQ
                   xmmreg|mask|z,xmmreg,xmmrm128|b64 AVX512VL/IFMA
VPMADD52LUQ
                   ymmreg|mask|z,ymmreg,ymmrm256|b64 AVX512VL/IFMA
VPMADD52LUQ
                   zmmreg|mask|z,zmmreg,zmmrm512|b64 AVX512IFMA
VPMADDUBSW
                   xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
                   ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
VPMADDUBSW
VPMADDUBSW
                   zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPMADDWD
                   xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
                   \verb|ymmreg|| mask|| \verb|z,ymmreg*|, \verb|ymmrm256|| AVX512VL/BW||
VPMADDWD
                   zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
VPMADDWD
VPMAXSB
VPMAXSB
                   ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
VPMAXSB
                   zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPMAXSD
                   xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
                   ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
VPMAXSD
VPMAXSD
VPMAXSQ
                   ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
VPMAXSQ
                   zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
VPMAXSQ
                   \verb|xmmreg|| \verb|mask|| \verb|z|, \verb|xmmreg|*|, \verb|xmmrm128|| AVX512VL/BW|
VPMAXSW
VPMAXSW
                   ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
```

```
VPMAXSW
                    zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
                    xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
VPMAXIIR
                    ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
VPMAXUB
VPMAXUB
                    zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
                    xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
VPMAXUD
                    ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
VPMAXUD
VPMAXUD
VPMAXUO
                    xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
                    ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
VPMAXUQ
VPMAXUQ
                    zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
                    xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPMAXUW
VPMAXUW
VPMAXIIW
VPMINSB
                    xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
VPMTNSB
                    ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
VPMTNSB
                    zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
                    xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
VPMINSD
VPMTNSD
VPMINSD
VPMINSO
                    xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
VPMINSQ
                    ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
VPMINSQ
                    zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
                    xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
VPMINSW
VPMTNSW
                    zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPMINSW
VPMINUB
                    xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
VPMINUB
                    ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
                    zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
VPMINUB
VPMTNUD
                    ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
VPMINUD
VPMINUD
                    zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
VPMINUO
                    xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
                    ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
VPMINUQ
VPMINUQ
VPMTNIIW
                    ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
VPMINUW
                    zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPMINUW
VPMOVB2M
                    kreg, xmmreg
                                                  AVX512VL/BW
VPMOVB2M
                    kreg, ymmreg
                                                  AVX512VL/BW
VPMOVB2M
                                                  AVX512BW
                    kreg, zmmreg
VPMOVD2M
                                                  AVX512VL/DO
                    kreg, xmmreg
VPMOVD2M
                                                  AVX512VL/DQ
                    kreg, ymmreg
VPM0VD2M
                    kreg, zmmreg
                                                  AVX512DQ
VPMOVDB
                    xmmreg|mask|z,xmmreg
                                                  AVX512VL
VPMOVDB
                    xmmreg|mask|z,ymmreg
                                                  AVX512VL
                    xmmreg|mask|z,zmmreg
VPMOVDR
                                                  ΔVX512
VPMOVDB
                    mem32 | mask, xmmreg
                                                  AVX512VL
VPMOVDB
                    mem64 | mask, ymmreg
                                                  AVX512VL
VPMOVDB
                    mem128|mask,zmmreg
                                                  AVX512
VPMOVDW
                                                  AVX512VL
                    xmmreg|mask|z,xmmreg
VPMOVDW
                    xmmreg|mask|z,ymmreg
                                                  AVX512VI
VPMOVDW
                    ymmreg | mask | z,zmmreg
                                                  AVX512
VPMOVDW
                    mem64|mask,xmmreg
                                                  AVX512VL
VPMOVDW
                    mem128 | mask, ymmreg
                                                  AVX512VI
VPMOVDW
                    mem256 | mask, zmmreg
                                                  AVX512
VPMOVM2B
                    xmmreg, kreg
                                                  AVX512VL/BW
                                                  AVX512VL/BW
VPMOVM2B
                    ymmreg, kreg
VPMOVM2B
                    zmmreg, kreg
                                                  AVX512BW
VPMOVM2D
                    xmmreg, kreg
                                                  AVX512VL/DQ
VPMOVM2D
                                                  AVX512VL/DQ
                    ymmreg, kreg
VPMOVM2D
                    zmmreg, kreg
                                                  AVX512DQ
VPMOVM20
                    xmmreg, kreg
                                                  AVX512VL/D0
VPMOVM20
                    ymmreg, kreg
                                                  AVX512VL/D0
VPMOVM2Q
                    zmmreg, kreg
                                                  AVX512DQ
VPM0VM2W
                                                  AVX512VL/BW
                    xmmreg, kreg
VPMOVM2W
                                                  AVX512VL/BW
                    ymmreg, kreg
VPMOVM2W
                    zmmreg, kreg
                                                  AVX512BW
```

VPMOVQ2M	kreg,xmmreg	AVX512VL/DQ
VPMOVQ2M	kreg,ymmreg	AVX512VL/DQ
VPMOVQ2M	kreg,zmmreg	AVX512DQ
VPMOVQB	xmmreg mask z,xmmreg	AVX512VL
VPMOVQB	xmmreg mask z,ymmreg	AVX512VL
VPMOVQB	xmmreg mask z,zmmreg	AVX51212
•		
VPMOVQB	mem16 mask,xmmreg	AVX512VL
VPMOVQB	mem32 mask,ymmreg	AVX512VL
VPMOVQB	mem64 mask,zmmreg	AVX512
VPMOVQD	xmmreg mask z,xmmreg	AVX512VL
VPMOVQD	xmmreg mask z,ymmreg	AVX512VL
VPMOVQD	ymmreg mask z,zmmreg	AVX512
VPMOVQD	mem64 mask,xmmreg	AVX512VL
VPMOVQD	mem128 mask,ymmreg	AVX512VL
VPMOVQD	mem256 mask,zmmreg	AVX512
VPMOVQW	xmmreg mask z,xmmreg	AVX512VL
•	9, , ,	
VPMOVQW	xmmreg mask z,ymmreg	AVX512VL
VPMOVQW	xmmreg mask z,zmmreg	AVX512
VPMOVQW	mem32 mask,xmmreg	AVX512VL
VPMOVQW	mem64 mask,ymmreg	AVX512VL
VPMOVQW	mem128 mask,zmmreg	AVX512
VPMOVSDB	xmmreg mask z,xmmreg	AVX512VL
VPMOVSDB	xmmreg mask z,ymmreg	AVX512VL
VPMOVSDB	xmmreg mask z,zmmreg	AVX512
VPMOVSDB	mem32 mask,xmmreg	AVX512VL
VPMOVSDB	, ,	AVX512VL
	mem64 mask,ymmreg	
VPMOVSDB	mem128 mask,zmmreg	AVX512
VPMOVSDW	xmmreg mask z,xmmreg	AVX512VL
VPMOVSDW	xmmreg mask z,ymmreg	AVX512VL
VPMOVSDW	ymmreg mask z,zmmreg	AVX512
VPMOVSDW	mem64 mask,xmmreg	AVX512VL
VPMOVSDW	mem128 mask,ymmreg	AVX512VL
VPMOVSDW	mem256 mask,zmmreg	AVX512
VPMOVSQB	xmmreg mask z,xmmreg	AVX512VL
VPMOVSQB	xmmreg mask z,ymmreg	AVX512VL
VPMOVSQB	xmmreg mask z,zmmreg	AVX512
VPMOVSQB	mem16 mask,xmmreg	AVX512VL
VPMOVSQB		AVX512VL AVX512VL
-	mem32 mask,ymmreg	
VPMOVSQB	mem64 mask,zmmreg	AVX512
VPMOVSQD	xmmreg mask z,xmmreg	AVX512VL
VPMOVSQD	xmmreg mask z,ymmreg	AVX512VL
VPMOVSQD	ymmreg mask z,zmmreg	AVX512
VPMOVSQD	mem64 mask,xmmreg	AVX512VL
VPMOVSQD	mem128 mask,ymmreg	AVX512VL
VPMOVSQD	mem256 mask,zmmreg	AVX512
VPMOVSQW	xmmreg mask z,xmmreg	AVX512VL
VPMOVSQW	xmmreg mask z,ymmreg	AVX512VL
VPMOVSQW	xmmreg mask z,zmmreg	AVX512
VPMOVSQW	mem32 mask,xmmreg	AVX512VL
VPMOVSQW	mem64 mask,ymmreg	AVX512VL AVX512VL
•		
VPMOVSQW	mem128 mask,zmmreg	AVX512
VPMOVSWB	xmmreg mask z,xmmreg	AVX512VL/BW
VPMOVSWB	xmmreg mask z,ymmreg	AVX512VL/BW
VPMOVSWB	ymmreg mask z,zmmreg	AVX512BW
VPMOVSWB	mem64 mask,xmmreg	AVX512VL/BW
VPMOVSWB	mem128 mask,ymmreg	AVX512VL/BW
VPMOVSWB	mem256 mask,zmmreg	AVX512BW
VPMOVSXBD	xmmreg mask z,xmmrm32	AVX512VL
VPMOVSXBD	ymmreg mask z,xmmrm64	AVX512VL
VPMOVSXBD	zmmreg mask z,xmmrm128	AVX51212 AVX512
VPMOVSXBQ	xmmreg mask z,xmmrm16	AVX512VL
VPMOVSXBQ	ymmreg mask z,xmmrm32	AVX512VL
VPMOVSXBQ	zmmreg mask z,xmmrm64	AVX512
VPMOVSXBW	xmmreg mask z,xmmrm64	AVX512VL/BW
VPMOVSXBW	ymmreg mask z,xmmrm128	AVX512VL/BW
VPMOVSXBW	zmmreg mask z,ymmrm256	AVX512BW
VPMOVSXDQ	xmmreg mask z,xmmrm64	AVX512VL
-	= • • •	

VPMOVSXDQ	ymmreg mask z,xmmrm128	AVX512VL
-		
VPMOVSXDQ	zmmreg mask z,ymmrm256	AVX512
VPMOVSXWD	xmmreg mask z,xmmrm64	AVX512VL
VPMOVSXWD	ymmreg mask z,xmmrm128	AVX512VL
VPMOVSXWD	zmmreg mask z,ymmrm256	AVX512
VPMOVSXWQ	xmmreg mask z,xmmrm32	AVX512VL
VPMOVSXWQ	ymmreg mask z,xmmrm64	AVX512VL
VPMOVSXWQ	zmmreg mask z,xmmrm128	AVX512
VPMOVUSDB	xmmreg mask z,xmmreg	AVX512VL
VPMOVUSDB	xmmreg mask z,ymmreg	AVX512VL
VPMOVUSDB	xmmreg mask z,zmmreg	AVX512
VPMOVUSDB	mem32 mask,xmmreg	AVX512VL
VPMOVUSDB	mem64 mask,ymmreg	AVX512VL
VPMOVUSDB	mem128 mask,zmmreg	AVX512
VPMOVUSDW	xmmreg mask z,xmmreg	AVX512VL
VPMOVUSDW	xmmreg mask z,ymmreg	AVX512VL
VPMOVUSDW		AVX512
	ymmreg mask z,zmmreg	
VPMOVUSDW	mem64 mask,xmmreg	AVX512VL
VPMOVUSDW	mem128 mask,ymmreg	AVX512VL
VPMOVUSDW	mem256 mask,zmmreg	AVX512
VPMOVUSQB	xmmreg mask z,xmmreg	AVX512VL
VPMOVUSQB	xmmreg mask z,ymmreg	AVX512VL
VPMOVUSOB	xmmreg mask z,zmmreg	AVX512
VPMOVUSQB	mem16 mask,xmmreg	AVX512VL
•		
VPMOVUSQB	mem32 mask,ymmreg	AVX512VL
VPMOVUSQB	mem64 mask,zmmreg	AVX512
VPMOVUSQD	xmmreg mask z,xmmreg	AVX512VL
VPMOVUSQD	xmmreg mask z,ymmreg	AVX512VL
•	-	
VPMOVUSQD	ymmreg mask z,zmmreg	AVX512
VPMOVUSQD	mem64 mask,xmmreg	AVX512VL
VPMOVUSQD	mem128 mask,ymmreg	AVX512VL
VPMOVUSQD	mem256 mask,zmmreg	AVX512
•		
VPMOVUSQW	xmmreg mask z,xmmreg	AVX512VL
VPMOVUSQW	xmmreg mask z,ymmreg	AVX512VL
VPMOVUSQW	xmmreg mask z,zmmreg	AVX512
VPMOVUSQW	mem32 mask,xmmreg	AVX512VL
VPMOVUSQW	mem64 mask,ymmreg	AVX512VL
•		
VPMOVUSQW	mem128 mask,zmmreg	AVX512
VPMOVUSWB	xmmreg mask z,xmmreg	AVX512VL/BW
VPMOVUSWB	xmmreg mask z,ymmreg	AVX512VL/BW
VPMOVUSWB	ymmreg mask z,zmmreg	AVX512BW
	, , ,	
VPMOVUSWB	mem64 mask,xmmreg	AVX512VL/BW
VPMOVUSWB	mem128 mask,ymmreg	AVX512VL/BW
VPMOVUSWB	mem256 mask,zmmreg	AVX512BW
VPMOVW2M	kreg,xmmreg	AVX512VL/BW
	0,	
VPMOVW2M	kreg,ymmreg	AVX512VL/BW
VPMOVW2M	kreg,zmmreg	AVX512BW
VPMOVWB	xmmreg mask z,xmmreg	AVX512VL/BW
VPMOVWB	xmmreg mask z,ymmreg	AVX512VL/BW
		•
VPMOVWB	ymmreg mask z,zmmreg	AVX512BW
VPMOVWB	mem64 mask,xmmreg	AVX512VL/BW
VPMOVWB	mem128 mask,ymmreg	AVX512VL/BW
VPMOVWB	mem256 mask,zmmreg	AVX512BW
	, , ,	
VPMOVZXBD	xmmreg mask z,xmmrm32	AVX512VL
VPMOVZXBD	ymmreg mask z,xmmrm64	AVX512VL
VPMOVZXBD	zmmreg mask z,xmmrm128	AVX512
VPMOVZXBQ	xmmreg mask z,xmmrm16	AVX512VL
-		
VPMOVZXBQ	ymmreg mask z,xmmrm32	AVX512VL
VPMOVZXBQ	zmmreg mask z,xmmrm64	AVX512
VPMOVZXBW	xmmreg mask z,xmmrm64	AVX512VL/BW
VPMOVZXBW	ymmreg mask z,xmmrm128	AVX512VL/BW
VPMOVZXBW	zmmreg mask z,ymmrm256	AVX512VE/BW
VPMOVZXDQ	xmmreg mask z,xmmrm64	AVX512VL
VPMOVZXDQ	ymmreg mask z,xmmrm128	AVX512VL
VPMOVZXDQ	zmmreg mask z,ymmrm256	AVX512
VPMOVZXWD	xmmreg mask z,xmmrm64	AVX512VL
VPMOVZXWD	ymmreg mask z,xmmrm128	AVX512VL

```
VPMOVZXWD
                    zmmreg|mask|z,ymmrm256
                                                 AVX512
VPMOV7XW0
                    xmmreg|mask|z,xmmrm32
                                                 AVX512VI
VPMOVZXWQ
                   ymmreg|mask|z,xmmrm64
                                                 AVX512VL
VPMOVZXWQ
                    zmmreg|mask|z,xmmrm128
                                                 AVX512
                    xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
VPMULDQ
                   ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
VPMULDQ
VPMULDQ
VPMULHRSW
                   xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
                   ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
VPMULHRSW
VPMUI HRSW
                    zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
                   xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPMULHUW
VPMULHUW
VPMULHUW
                    xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
VPMUI HW
VPMULHW
                    ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
                    zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPMUI HW
                   xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
VPMULLD
VPMULLD
VPMULLD
VPMULLO
                    xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL/DQ
VPMULLQ
                    ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL/DQ
VPMULLQ
                    zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512DQ
                   xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
VPMULLW
VPMULLW
                    zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPMULLW
VPMULTISHIFTQB
                    xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL/VBMI
VPMULTISHIFTOB
                    ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL/VBMI
                   zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512VBMI
xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
VPMULTISHIFTQB
VPMULUDQ
                   ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
VPMULUDO
VPMULUDQ
                    zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
VPORD
                    xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
                   ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
VPORD
VPORD
VPORO
                   ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
VPORO
                    zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
VPORQ
                    xmmreg|mask|z,xmmrm128|b32*,imm8 AVX512VL
VPROLD
                   ymmreg|mask|z,ymmrm256|b32*,imm8 AVX512VL
zmmreg|mask|z,zmmrm512|b32*,imm8 AVX512
VPROLD
VPROLD
                   xmmreg|mask|z,xmmrm128|b64*,imm8 AVX512VL
VPROLO
VPROLQ
                   ymmreg|mask|z,ymmrm256|b64*,imm8 AVX512VL
                    zmmreg|mask|z,zmmrm512|b64*,imm8 AVX512
VPROLQ
VPROLVD
                    xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
                    ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
VPROLVD
                    zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
VPROLVD
VPROLVQ
                    xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
VPROLVQ
                    ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
VPROLVO
                    zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
VPRORD
                    xmmreg|mask|z,xmmrm128|b32*,imm8 AVX512VL
VPRORD
                    ymmreg|mask|z,ymmrm256|b32*,imm8 AVX512VL
                    zmmreg|mask|z,zmmrm512|b32*,imm8 AVX512
VPRORD
VPRORQ
                    xmmreg|mask|z,xmmrm128|b64*,imm8 AVX512VL
VPRORQ
                    ymmreg|mask|z,ymmrm256|b64*,imm8 AVX512VL
VPRORO
                    zmmreg|mask|z,zmmrm512|b64*,imm8 AVX512
VPRORVD
                    xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
                    ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
VPRORVD
VPRORVD
                    zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
                    xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
VPRORVQ
                    ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
VPRORVO
                    zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
VPRORVO
VPSADBW
                    xmmreg,xmmreg*,xmmrm128 AVX512VL/BW
                   ymmreg,ymmreg*,ymmrm256 AVX512VL/BW
zmmreg,zmmreg*,zmmrm512 AVX512BW
VPSADBW
VPSADBW
VPSCATTERDD
                                                 AVX512VI
                    xmem32|mask,xmmreg
                    vmem32 mask, ymmreg
VPSCATTERDD
                                                 AVX512VL
VPSCATTERDD
                    zmem32|mask,zmmreg
                                                 AVX512
```

```
VPSCATTERDQ
                   xmem64 | mask, xmmreg
                                               AVX512VL
                   xmem64 mask,ymmreg
VPSCATTERDO
                                               AVX512VL
VPSCATTERDO
                   ymem64 | mask,zmmreg
                                               AVX512
VPSCATTERQD
                   xmem32 | mask, xmmreg
                                               AVX512VL
VPSCATTERQD
                   ymem32 | mask, xmmreg
                                               AVX512VL
VPSCATTEROD
                   zmem32 | mask, ymmreg
                                               AVX512
VPSCATTERQO
                   xmem64 | mask, xmmreg
                                               AVX512VL
VPSCATTER00
                   ymem64 mask, ymmreg
                                               AVX512VL
VPSCATTERQQ
                   zmem64 mask,zmmreg
                                               AVX512
                   xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
VPSHUFB
                   ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPSHUFB
VPSHUFB
                   xmmreg|mask|z,xmmrm128|b32,imm8 AVX512VL
VPSHUED
VPSHUFD
                   ymmreg|mask|z,ymmrm256|b32,imm8 AVX512VL
VPSHUFD
                   zmmreg|mask|z,zmmrm512|b32,imm8 AVX512
VPSHUFHW
                   xmmreg|mask|z,xmmrm128,imm8 AVX512VL/BW
VPSHUFHW
                   ymmreg|mask|z,ymmrm256,imm8 AVX512VL/BW
VPSHUFHW
                   zmmreg|mask|z,zmmrm512,imm8 AVX512BW
VPSHUFLW
                   xmmreg|mask|z,xmmrm128,imm8 AVX512VL/BW
VPSHUFLW
                   ymmreg|mask|z,ymmrm256,imm8 AVX512VL/BW
                   zmmreg|mask|z,zmmrm512,imm8 AVX512BW
VPSHUFLW
VPSLLD
                   xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL
                   ymmreg|mask|z,ymmreg*,xmmrm128 AVX512VL
zmmreg|mask|z,zmmreg*,xmmrm128 AVX512
VPSLLD
VPSLLD
VPSLLD
                   xmmreg|mask|z,xmmrm128|b32*,imm8 AVX512VL
                   ymmreg|mask|z,ymmrm256|b32*,imm8 AVX512VL
VPSLLD
VPSLLD
                   zmmreg | mask | z,zmmrm512 | b32*,imm8 AVX512
VPSLLD0
                   xmmreg,xmmrm128*,imm8
                                              AVX512VL/BW
                   ymmreg,ymmrm256*,imm8
VPSLLDQ
                                              AVX512VI /BW
                   zmmreg,zmmrm512*,imm8
VPSLLD0
                                              AVX512BW
VPSI I O
                   xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL
VPSLLQ
                   ymmreg|mask|z,ymmreg*,xmmrm128 AVX512VL
VPSLLQ
                   zmmreg|mask|z,zmmreg*,xmmrm128 AVX512
VPSLLQ
                   xmmreg|mask|z,xmmrm128|b64*,imm8 AVX512VL
                   ymmreg|mask|z,ymmrm256|b64*,imm8 AVX512VL
VPSLLO
                   zmmreg|mask|z.zmmrm512|b64*.imm8 AVX512
VPSLLO
                   xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
VPSLLVD
VPSLLVD
                   ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
                   zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
VPSLLVD
VPSLLVQ
                   ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
VPSLLVO
VPSLLVQ
                   zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
                   xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
VPSLLVW
                   ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPSLLVW
VPSLLVW
                   xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
VPSLLW
VPSLLW
                   ymmreg|mask|z,ymmreg*,xmmrm128 AVX512VL/BW
VPSLLW
                   zmmreg|mask|z,zmmreg*,xmmrm128 AVX512BW
                   xmmreg|mask|z,xmmrm128*,imm8 AVX512VL/BW
VPSLLW
                   ymmreg|mask|z,ymmrm256*,imm8 AVX512VL/BW
zmmreg|mask|z,zmmrm512*,imm8 AVX512BW
VPSLLW
VPSLLW
VPSRAD
                   xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL
VPSRAD
                   ymmreg | mask | z,ymmreg*,xmmrm128 AVX512VL
VPSRAD
                   zmmreg|mask|z,zmmreg*,xmmrm128 AVX512
                   xmmreg|mask|z,xmmrm128|b32*,imm8 AVX512VL
VPSRAD
                   ymmreg|mask|z,ymmrm256|b32*,imm8 AVX512VL
zmmreg|mask|z,zmmrm512|b32*,imm8 AVX512
VPSRAD
VPSRAD
VPSRAQ
                   xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL
                   ymmreg|mask|z,ymmreg*,xmmrm128 AVX512VL
VPSRAQ
VPSRAO
                   zmmreg|mask|z,zmmreg*,xmmrm128 AVX512
VPSRAO
                   xmmreg|mask|z,xmmrm128|b64*,imm8 AVX512VL
VPSRAQ
                   ymmreg|mask|z,ymmrm256|b64*,imm8 AVX512VL
                   zmmreg|mask|z,zmmrm512|b64*,imm8 AVX512
VPSRAO
VPSRAVD
                   xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
VPSRAVD
                   ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
                   zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
VPSRAVD
VPSRAVQ
```

```
VPSRAVQ
                     ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
                     zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
VPSRAVO
                     xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
VPSRAVW
VPSRAVW
                     ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
                     {\tt zmmreg|mask|z,zmmreg^{\star},zmmrm512~AVX512BW}
VPSRAVW
                     xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
ymmreg|mask|z,ymmreg*,xmmrm128 AVX512VL/BW
zmmreg|mask|z,zmmreg*,xmmrm128 AVX512BW
VPSRAW
VPSRAW
VPSRAW
                     xmmreg|mask|z,xmmrm128*,imm8 AVX512VL/BW
VPSRAW
                     ymmreg|mask|z,ymmrm256*,imm8 AVX512VL/BW
VPSRAW
VPSRAW
                     zmmreg|mask|z,zmmrm512*,imm8 AVX512BW
                     xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL
ymmreg|mask|z,ymmreg*,xmmrm128 AVX512VL
VPSRLD
VPSRLD
                     zmmreg|mask|z,zmmreg*,xmmrm128 AVX512
VPSRLD
VPSRLD
                     xmmreg|mask|z,xmmrm128|b32*,imm8 AVX512VL
VPSRLD
                     ymmreg|mask|z,ymmrm256|b32*,imm8 AVX512VL
                     zmmreg|mask|z,zmmrm512|b32*,imm8 AVX512
VPSRLD
                     xmmreg,xmmrm128*,imm8
VPSRLDQ
                                                    AVX512VL/BW
                     ymmreg,ymmrm256*,imm8
VPSRLD0
                                                    AVX512VL/BW
VPSRLDO
                     zmmreg,zmmrm512*,imm8
                                                    AVX512BW
                     xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL
VPSRLQ
VPSRLQ
                     ymmreg|mask|z,ymmreg*,xmmrm128 AVX512VL
VPSRLQ
                     zmmreg|mask|z,zmmreg*,xmmrm128 AVX512
                     xmmreg|mask|z,xmmrm128|b64*,imm8~AVX512VL\\
VPSRLO
                     ymmreg|mask|z,ymmrm256|b64*,imm8 AVX512VL
VPSRLQ
VPSRLQ
                     zmmreg|mask|z,zmmrm512|b64*,imm8 AVX512
                     xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
VPSRLVD
                     ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
VPSRLVD
VPSRLVD
                     xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
VPSRL VO
VPSRLVQ
                     ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
                     zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
VPSRLVQ
                     xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPSRLVW
VPSRLVW
VPSRI VW
                     xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
VPSRLW
VPSRLW
                     ymmreg|mask|z,ymmreg*,xmmrm128 AVX512VL/BW
                     zmmreg|mask|z,zmmreg*,xmmrm128 AVX512BW
VPSRI W
                     xmmreg|mask|z,xmmrm128*,imm8 AVX512VL/BW
VPSRLW
                     ymmreg|mask|z,ymmrm256*,imm8 AVX512VL/BW
VPSRLW
                     zmmreg|mask|z,zmmrm512*,imm8 AVX512BW
VPSRIW
VPSUBB
                     xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
                     ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
VPSUBB
VPSUBB
                     zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPSUBD
                     xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
                     ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
VPSUBD
                     zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
VPSUBD
VPSUBO
                     xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
VPSUBQ
                     \verb|ymmreg|| mask|| \verb|z|, \verb|ymmreg|| *, \verb|ymmrm256|| b64 | AVX512VL|
                     zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
VPSUBQ
VPSUBSB
VPSUBSB
                     zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPSUBSB
VPSUBSW
                     xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
                     \verb|ymmreg|| mask|| \verb|z,ymmreg*|, \verb|ymmrm256|| AVX512VL/BW|
VPSUBSW
                     zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
VPSUBSW
VPSUBUSB
VPSUBUSB
                     ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
VPSUBUSB
                     zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
                     \verb|xmmreg|| mask|| \verb|z|, \verb|xmmreg|*, \verb|xmmrm128|| AVX512VL/BW|
VPSUBUSW
                     ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
VPSUBUSW
VPSUBUSW
VPSUBW
                     ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
VPSUBW
VPSUBW
                     zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
                     \verb|xmmreg|| \verb|mask|| \verb|z|, \verb|xmmreg|, \verb|xmmrm128|| \verb|b32|, \verb|imm8|| AVX512VL|
VPTERNLOGD
VPTERNLOGD
                     ymmreg|mask|z,ymmreg,ymmrm256|b32,imm8 AVX512VL
```

```
VPTERNLOGD
                   zmmreg|mask|z,zmmreg,zmmrm512|b32,imm8 AVX512
VPTFRNI OGO
                   xmmreg|mask|z,xmmreg,xmmrm128|b64,imm8 AVX512VL
                   ymmreg|mask|z,ymmreg,ymmrm256|b64,imm8 AVX512VL
VPTERNLOGQ
VPTERNLOGQ
                   zmmreg|mask|z,zmmreg,zmmrm512|b64,imm8 AVX512
                   kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPTESTMB
VPTESTMB
                   kreg | mask, ymmreg, ymmrm256 AVX512VL/BW
VPTFSTMR
                   kreg|mask,zmmreg,zmmrm512 AVX512BW
VPTESTMD
                   kreg mask, xmmreg, xmmrm128 b32 AVX512VL
VPTESTMD
                   kreg mask, ymmreg, ymmrm256 b32 AVX512VL
                   kreg|mask,zmmreg,zmmrm512|b32 AVX512
VPTESTMD
VPTESTMO
                   kreg|mask,xmmreg,xmmrm128|b64 AVX512VL
VPTESTMQ
                   kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
                   kreg|mask,zmmreg,zmmrm512|b64 AVX512
VPTESTMQ
VPTESTMW
                   kreg | mask, xmmreg, xmmrm128 AVX512VL/BW
VPTESTMW
                   kreg|mask,ymmreg,ymmrm256 AVX512VL/BW
                   kreg|mask,zmmreg,zmmrm512 AVX512BW
VPTFSTMW
VPTESTNMB
                   kreg | mask, xmmreg, xmmrm128 AVX512VL/BW
VPTFSTNMB
                   kreg | mask, ymmreg, ymmrm256 AVX512VL/BW
VPTESTNMB
                   kreg mask, zmmreg, zmmrm512 AVX512BW
VPTESTNMD
                   kreg|mask,xmmreg,xmmrm128|b32 AVX512VL
VPTFSTNMD
                   kreg|mask,ymmreg,ymmrm256|b32 AVX512VL
VPTESTNMD
                   kreg | mask, zmmreg, zmmrm512 | b32 AVX512
VPTESTNMQ
                   kreg | mask, xmmreg, xmmrm128 | b64 AVX512VL
                   kreg|mask,ymmreg,ymmrm256|b64 AVX512VL
VPTFSTNMO
VPTESTNMQ
                   kreg|mask,zmmreg,zmmrm512|b64 AVX512
VPTESTNMW
                   kreg|mask,xmmreg,xmmrm128 AVX512VL/BW
VPTESTNMW
                   kreg | mask, ymmreg, ymmrm256 AVX512VL/BW
                   kreg|mask,zmmreg,zmmrm512 AVX512BW
VPTESTNMW
VPUNPCKHBW
                   xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
                   ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
VPUNPCKHBW
VPUNPCKHBW
                   zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPUNPCKHDQ
                   xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
                   ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
VPUNPCKHDQ
VPUNPCKHDQ
VPUNPCKHQDQ
VPUNPCKHODO
                   ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
VPUNPCKHQDQ
                   zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
VPUNPCKHWD
                   xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
                   ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPUNPCKHWD
VPUNPCKHWD
                   xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
VPUNPCKLBW
VPUNPCKLBW
                   ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
VPUNPCKLBW
                   zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
                   xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
VPUNPCKLDQ
VPUNPCKLDQ
VPUNPCKLDO
VPUNPCKLQDQ
                   xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
VPUNPCKLODO
                   ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
VPUNPCKLQDQ
                   zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
                   xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL/BW
ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL/BW
zmmreg|mask|z,zmmreg*,zmmrm512 AVX512BW
VPUNPCKLWD
VPUNPCKLWD
VPUNPCKLWD
VPXORD
                   xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
VPXORD
                   ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
VPXORD
                   zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
                   xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
VPXORQ
VPXORO
VPXORQ
                   zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
                   xmmreg|mask|z,xmmreg*,xmmrm128|b64,imm8 AVX512VL/DQ
VRANGEPD
VRANGEPD
                   ymmreg|mask|z,ymmreg*,ymmrm256|b64,imm8 AVX512VL/DQ
                   zmmreg|mask|z,zmmreg*,zmmrm512|b64|sae,imm8 AVX512DQ
xmmreg|mask|z,xmmreg*,xmmrm128|b32,imm8 AVX512VL/DQ
VRANGEPD
VRANGEPS
                   ymmreg|mask|z,ymmreg*,ymmrm256|b32,imm8 AVX512VL/DQ
VRANGEPS
                   zmmreg|mask|z,zmmreg*,zmmrm512|b32|sae,imm8 AVX512DQ
VRANGEPS
VRANGESD
                   xmmreg|mask|z,xmmreg*,xmmrm64|sae,imm8 AVX512DQ
VRANGESS
                   xmmreg|mask|z,xmmreg*,xmmrm32|sae,imm8 AVX512DQ
VRCP14PD
                   xmmreg|mask|z,xmmrm128|b64 AVX512VL
```

```
VRCP14PD
                  ymmreg|mask|z,ymmrm256|b64 AVX512VL
VRCP14PD
                  zmmreg|mask|z,zmmrm512|b64 AVX512
VRCP14PS
                  xmmreg|mask|z,xmmrm128|b32 AVX512VL
VRCP14PS
                  ymmreg|mask|z,ymmrm256|b32 AVX512VL
VRCP14PS
                  zmmreg|mask|z,zmmrm512|b32 AVX512
VRCP14SD
                  xmmreg|mask|z,xmmreg*,xmmrm64 AVX512
                  xmmreg|mask|z,xmmreg*,xmmrm32 AVX512
zmmreg|mask|z,zmmrm512|b64|sae AVX512ER
VRCP14SS
VRCP28PD
VRCP28PS
                  zmmreg | mask | z, zmmrm512 | b32 | sae AVX512ER
                  xmmreg|mask|z,xmmreg*,xmmrm64|sae AVX512ER
VRCP28SD
VRCP28SS
                  xmmreg|mask|z,xmmreg*,xmmrm32|sae AVX512ER
VREDUCEPD
                  xmmreg|mask|z,xmmrm128|b64,imm8 AVX512VL/DQ
                  ymmreg|mask|z,ymmrm256|b64,imm8 AVX512VL/DQ
VREDUCEPD
VREDUCEPD
                  zmmreg|mask|z,zmmrm512|b64|sae,imm8 AVX512DQ
VREDUCEPS
                  xmmreg|mask|z,xmmrm128|b32,imm8 AVX512VL/DQ
VREDUCEPS
                  ymmreg|mask|z,ymmrm256|b32,imm8 AVX512VL/DQ
VREDUCEPS
                  zmmreg | mask | z, zmmrm512 | b32 | sae, imm8 AVX512DQ
                  xmmreg|mask|z,xmmreg*,xmmrm64|sae,imm8 AVX512DQ
VREDUCESD
                  xmmreg|mask|z,xmmreg*,xmmrm32|sae,imm8 AVX512DQ
VREDUCESS
                  xmmreg|mask|z,xmmrm128|b64,imm8 AVX512VL
VRNDSCALEPD
                  ymmreg|mask|z,ymmrm256|b64,imm8 AVX512VL
VRNDSCALEPD
VRNDSCALEPD
                  zmmreg|mask|z,zmmrm512|b64|sae,imm8 AVX512
VRNDSCALEPS
                  xmmreg|mask|z,xmmrm128|b32,imm8 AVX512VL
VRNDSCALEPS
                  ymmreg|mask|z,ymmrm256|b32,imm8 AVX512VL
VRNDSCALEPS
                  zmmreg|mask|z,zmmrm512|b32|sae,imm8 AVX512
VRNDSCALESD
                  xmmreg|mask|z,xmmreg*,xmmrm64|sae,imm8 AVX512
VRNDSCALESS
                  xmmreg|mask|z,xmmreg*,xmmrm32|sae,imm8 AVX512
                  xmmreg|mask|z,xmmrm128|b64 AVX512VL
VRSQRT14PD
VRSQRT14PD
                  ymmreg|mask|z,ymmrm256|b64 AVX512VL
VRSORT14PD
                  zmmreg|mask|z,zmmrm512|b64 AVX512
VRSQRT14PS
                  xmmreg|mask|z,xmmrm128|b32 AVX512VL
VRSQRT14PS
                  ymmreg|mask|z,ymmrm256|b32 AVX512VL
VRSQRT14PS
                  zmmreg|mask|z,zmmrm512|b32 AVX512
VRSQRT14SD
                  xmmreg|mask|z,xmmreg*,xmmrm64 AVX512
                  xmmreg|mask|z,xmmreg*,xmmrm32 AVX512
VRSORT14SS
                  zmmreg|mask|z.zmmrm512|b64|sae AVX512ER
VRSORT28PD
VRSQRT28PS
                  zmmreg|mask|z,zmmrm512|b32|sae AVX512ER
                  xmmreg|mask|z,xmmreg*,xmmrm64|sae AVX512ER
VRSQRT28SD
                  xmmreg|mask|z,xmmreg*,xmmrm32|sae AVX512ER
xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
VRSQRT28SS
VSCALEFPD
                  ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
VSCALEFPD
VSCALEFPD
                  zmmreg|mask|z,zmmreg*,zmmrm512|b64|er AVX512
VSCALEFPS
                  xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
                  ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b32|er AVX512
xmmreg|mask|z,xmmreg*,xmmrm64|er AVX512
VSCALEFPS
VSCALEFPS
VSCALEFSD
VSCALEFSS
                  xmmreg|mask|z,xmmreg*,xmmrm32|er AVX512
VSCATTERDPD
                  xmem64|mask,xmmreg
                                            AVX512VL
                  xmem64 mask, ymmreg
VSCATTERDPD
                                             AVX512VL
VSCATTERDPD
                  ymem64 | mask,zmmreg
                                             AVX512
VSCATTERDPS
                  xmem32|mask,xmmreg
                                             AVX512VI
                  ymem32 mask,ymmreg
VSCATTERDPS
                                             AVX512VL
VSCATTERDPS
                  zmem32 mask,zmmreg
                                             AVX512
VSCATTERPF0DPD
                  ymem64 mask
                                             AVX512PF
VSCATTERPF0DPS
                  zmem32|mask
                                             AVX512PF
VSCATTERPF0QPD
                  zmem64|mask
                                             AVX512PF
VSCATTERPF00PS
                  zmem32 mask
                                             AVX512PF
VSCATTERPF1DPD
                  vmem64 mask
                                             AVX512PF
                  zmem32 mask
VSCATTERPF1DPS
                                             AVX512PF
                  zmem64 mask
                                             AVX512PF
VSCATTERPF1QPD
                                             AVX512PF
                  zmem32 mask
VSCATTERPF1QPS
                  xmem64 | mask, xmmreg
VSCATTERQPD
                                             AVX512VL
                  ymem64 mask, ymmreg
VSCATTEROPD
                                             AVX512VL
VSCATTERQPD
                  zmem64 mask,zmmreg
                                             AVX512
VSCATTERQPS
                  xmem32|mask,xmmreg
                                             AVX512VL
VSCATTEROPS
                  ymem32 | mask,xmmreg
                                             AVX512VL
VSCATTEROPS
                  zmem32|mask,ymmreg
                                             AVX512
```

```
VSHUFF32X4
                    ymmreg|mask|z,ymmreg*,ymmrm256|b32,imm8 AVX512VL
                    zmmreg|mask|z,zmmreg*,zmmrm512|b32,imm8 AVX512
VSHUFF32X4
VSHUFF64X2
                    ymmreg|mask|z,ymmreg*,ymmrm256|b64,imm8 AVX512VL
VSHUFF64X2
                     zmmreg|mask|z,zmmreg*,zmmrm512|b64,imm8 AVX512
VSHUFI32X4
                    ymmreg|mask|z,ymmreg*,ymmrm256|b32,imm8 AVX512VL
                    zmmreg|mask|z,zmmreg*,zmmrm512|b32,imm8 AVX512
ymmreg|mask|z,ymmreg*,ymmrm256|b64,imm8 AVX512VL
VSHUFI32X4
VSHUFI64X2
                    zmmreg|mask|z,zmmreg*,zmmrm512|b64,imm8 AVX512
VSHUFI64X2
                    xmmreg|mask|z,xmmreg*,xmmrm128|b64,imm8 AVX512VL
VSHUFPD
VSHUFPD
                    ymmreg|mask|z,ymmreg*,ymmrm256|b64,imm8 AVX512VL
                    zmmreg|mask|z,zmmreg*,zmmrm512|b64,imm8 AVX512
xmmreg|mask|z,xmmreg*,xmmrm128|b32,imm8 AVX512VL
ymmreg|mask|z,ymmreg*,ymmrm256|b32,imm8 AVX512VL
VSHUFPD
VSHUFPS
VSHUFPS
VSHUFPS
                    zmmreg|mask|z,zmmreg*,zmmrm512|b32,imm8 AVX512
VSQRTPD
                    xmmreg|mask|z,xmmrm128|b64 AVX512VL
                    ymmreg|mask|z,ymmrm256|b64 AVX512VL
VSORTPD
VSQRTPD
                     zmmreg|mask|z,zmmrm512|b64|er AVX512
VSORTPS
                    xmmreg|mask|z,xmmrm128|b32 AVX512VL
VSORTPS
                    ymmreg | mask | z, ymmrm256 | b32 AVX512VL
VSORTPS
                    zmmreg|mask|z,zmmrm512|b32|er AVX512
VSQRTSD
                    xmmreg|mask|z,xmmreg*,xmmrm64|er AVX512
                    xmmreg|mask|z,xmmreg*,xmmrm32|er AVX512
xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
VSQRTSS
VSUBPD
VSUBPD
VSUBPD
                    zmmreg|mask|z,zmmreg*,zmmrm512|b64|er AVX512
VSUBPS
                    xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
VSUBPS
                    ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
                    zmmreg|mask|z,zmmreg*,zmmrm512|b32|er AVX512
xmmreg|mask|z,xmmreg*,xmmrm64|er AVX512
VSUBPS
VSUBSD
                    xmmreg|mask|z,xmmreg*,xmmrm32|er AVX512
VSUBSS
VUCOMISD
                    xmmreg,xmmrm64|sae
                                                   AVX512
VUCOMISS
                    xmmreg,xmmrm32|sae
                                                   AVX512
                    xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
VUNPCKHPD
VUNPCKHPD
VUNPCKHPD
VUNPCKHPS
                    xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
VUNPCKHPS
                    ymmreg | mask | z,ymmreg*,ymmrm256 | b32 AVX512VL
VUNPCKHPS
                     zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
                    xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL
ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL
VUNPCKLPD
VUNPCKI PD
                    zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512
VUNPCKLPD
VUNPCKLPS
                    xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL
                    ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL
VUNPCKLPS
                    zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512
xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VL/DQ
VUNPCKLPS
VXORPD
VXORPD
                    ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VL/DQ
                    zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512DQ
VXORPD
VXORPS
                    xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VL/DQ
VXORPS
                    ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VL/DQ
VXORPS
                     zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512DQ
```

B.1.42 Intel memory protection keys for userspace (PKU aka PKEYs)

RDPKRU LONG WRPKRU LONG

B.1.43 Read Processor ID

 RDPID
 reg32
 NOLONG

 RDPID
 reg64
 LONG

 RDPID
 reg32
 LONG,UNDOC

B.1.44 New memory instructions

CLFLUSHOPT mem CLWB mem

PCOMMIT NEVER, NOP CLZERO AMD

CLZERO	reg_ax	AMD, ND, NOLONG
CLZERO	reg_eax	AMD, ND
CLZERO	reg_rax	AMD, ND, LONG

LONG

B.1.45 Processor trace write

PTWRITE rm32
PTWRITE rm64

B.1.46 Instructions from the Intel Instruction Set Extensions,

B.1.47 doc 319433-034 May 2018

CLDEMOTE	mem	
MOVDIRI	mem32,reg32	SD
MOVDIRI	mem64,reg64	LONG
MOVDIR64B	reg16,mem512	NOLONG
MOVDIR64B	reg32,mem512	
MOVDIR64B	reg64,mem512	LONG
PCONFIG		
TPAUSE	reg32	
TPAUSE	reg32,reg_edx,reg_eax	ND
UMONITOR	reg16	NOLONG
UMONITOR	reg32	
UMONITOR	reg64	LONG
UMWAIT	reg32	
UMWAIT	reg32,reg_edx,reg_eax	ND
WBNOTNVD		

B.1.48 Galois field operations (GFNI)

```
GF2P8AFFINEINVQB xmmreg,xmmrm128,imm8
                                            GFNI,SSE
VGF2P8AFFINEINVQB xmmreg,xmmreg*,xmmrm128,imm8 GFNI,AVX VGF2P8AFFINEINVQB ymmreg,ymmreg*,ymmrm256,imm8 GFNI,AVX
VGF2P8AFFINEINVQB xmmreg|mask|z,xmmreg*,xmmrm128|b64,imm8 AVX512VL,GFNI
VGF2P8AFFINEINVQB ymmreg|mask|z,ymmreg*,ymmrm256|b64,imm8 AVX512VL,GFNI
VGF2P8AFFINEINVQB zmmreg|mask|z,zmmreg*,zmmrm512|b64,imm8 AVX512,GFNI
GF2P8AFFINEQB
                xmmreg,xmmrm128,imm8 GFNI,SSE xmmreg,xmmreg*,xmmrm128,imm8 GFNI,AVX
VGF2P8AFFINEQB
VGF2P8AFFINEQB ymmreg,ymmreg*,ymmrm256,imm8 GFNI,AVX
VGF2P8AFFINEQB xmmreg|mask|z,xmmreg*,xmmrm128|b64,imm8 AVX512VL,GFNI
VGF2P8AFFINEQB ymmreg|mask|z,ymmreg*,ymmrm256|b64,imm8 AVX512VL,GFNI
VGF2P8AFFINEQB zmmreg|mask|z,zmmreg*,zmmrm512|b64,imm8 AVX512,GFNI
GF2P8MULB
                  xmmreg,xmmrm128
                                          GFNI,SSE
                  xmmreg,xmmreg*,xmmrm128 GFNI,AVX
VGF2P8MULB
VGF2P8MULB
                 ymmreg,ymmreg*,ymmrm256 GFNI,AVX
VGF2P8MULB
                 xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VL,GFNI
VGF2P8MULB
                  ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VL,GFNI
VGF2P8MULB
                  zmmreg|mask|z,zmmreg*,zmmrm512 AVX512,GFNI
```

B.1.49 AVX512 Vector Bit Manipulation Instructions 2

VPCOMPRESSB	mem128 mask,xmmreg	AVX512VBMI2/VL
VPCOMPRESSB	mem256 mask,ymmreg	AVX512VBMI2/VL
VPCOMPRESSB	mem512 mask,zmmreg	AVX512VBMI2
VPCOMPRESSB	xmmreg mask z,xmmreg	AVX512VBMI2/VL
VPCOMPRESSB	ymmreg mask z,ymmreg	AVX512VBMI2/VL
VPCOMPRESSB	zmmreg mask z,zmmreg	AVX512VBMI2
VPCOMPRESSW	mem128 mask,xmmreg	AVX512VBMI2/VL
VPCOMPRESSW	mem256 mask,ymmreg	AVX512VBMI2/VL
VPCOMPRESSW	mem512 mask,zmmreg	AVX512VBMI2
VPCOMPRESSW	xmmreg mask z,xmmreg	AVX512VBMI2/VL
VPCOMPRESSW	ymmreg mask z,ymmreg	AVX512VBMI2/VL
VPCOMPRESSW	zmmreg mask z,zmmreg	AVX512VBMI2
VPEXPANDB	mem128 mask,xmmreg	AVX512VBMI2/VL
VPEXPANDB	mem256 mask,ymmreg	AVX512VBMI2/VL
VPEXPANDB	mem512 mask,zmmreg	AVX512VBMI2
VPEXPANDB	xmmreg mask z,xmmreg	AVX512VBMI2/VL

```
VPEXPANDB
                     ymmreg|mask|z,ymmreg
                                                     AVX512VBMI2/VL
                     zmmreg|mask|z,zmmreg
VPEXPANDS
                                                     AVX512VBMI2
VPEXPANDW
                     mem128 mask,xmmreg
                                                     AVX512VBMI2/VL
                     mem256 | mask, ymmreg
VPEXPANDW
                                                     AVX512VBMI2/VL
VPEXPANDW
                     mem512 | mask,zmmreg
                                                     AVX512VBMI2
VPEXPANDW
                     xmmreg|mask|z,xmmreg
                                                     AVX512VBMI2/VL
VPFXPANDW
                                                     AVX512VBMI2/VL
                     ymmreg|mask|z,ymmreg
VPEXPANDW
                     zmmreg|mask|z,zmmreg
                                                     AVX512VBMI2
VPSHLDW
                     xmmreg|mask|z,xmmreg*,xmmrm128,imm8 AVX512VBMI2/VL
VPSHLDW
                     ymmreg|mask|z,ymmreg*,ymmrm256,imm8 AVX512VBMI2/VL
                     zmmreg|mask|z,zmmreg*,zmmrm512,imm8 AVX512VBMI2
xmmreg|mask|z,xmmreg*,xmmrm128|b32,imm8 AVX512VBMI2/VL
ymmreg|mask|z,ymmreg*,ymmrm256|b32,imm8 AVX512VBMI2/VL
VPSHLDW
VPSHLDD
VPSHI DD
VPSHLDD
                     zmmreg|mask|z,zmmreg*,zmmrm512|b32,imm8 AVX512VBMI2
VPSHLDQ
                     xmmreg|mask|z,xmmreg*,xmmrm128|b64,imm8 AVX512VBMI2/VL
                     ymmreg|mask|z,ymmreg*,ymmrm256|b64,imm8 AVX512VBMI2/VL
VPSHLDO
                     zmmreg|mask|z,zmmreg*,zmmrm512|b64,imm8 AVX512VBMI2
xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VBMI2/VL
ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VBMI2/VL
VPSHLDQ
VPSHLDVW
VPSHLDVW
                     zmmreg|mask|z,zmmreg*,zmmrm512 AVX512VBMI2
VPSHLDVW
VPSHLDVD
                     xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VBMI2/VL
                     ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VBMI2/VL
zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512VBMI2
xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VBMI2/VL
VPSHLDVD
VPSHLDVD
VPSHLDV0
                     ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VBMI2/VL
VPSHLDVQ
                     zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512VBMI2
VPSHLDVQ
VPSHRDW
                     xmmreg|mask|z,xmmreg*,xmmrm128,imm8 AVX512VBMI2/VL
                     ymmreg|mask|z,ymmreg*,ymmrm256,imm8 AVX512VBMI2/VL
zmmreg|mask|z,zmmreg*,zmmrm512,imm8 AVX512VBMI2
VPSHRDW
VPSHRDW
                     xmmreg|mask|z,xmmreg*,xmmrm128|b32,imm8 AVX512VBMI2/VL
VPSHRDD
VPSHRDD
                     ymmreg|mask|z,ymmreg*,ymmrm256|b32,imm8 AVX512VBMI2/VL
                     zmmreg|mask|z,zmmreg*,zmmrm512|b32,imm8 AVX512VBMI2
VPSHRDD
                     xmmreg|mask|z,xmmreg*,xmmrm128|b64,imm8 AVX512VBMI2/VL
ymmreg|mask|z,ymmreg*,ymmrm256|b64,imm8 AVX512VBMI2/VL
zmmreg|mask|z,zmmreg*,zmmrm512|b64,imm8 AVX512VBMI2
VPSHRDQ
VPSHRDQ
VPSHRDO
                     xmmreg|mask|z,xmmreg*,xmmrm128 AVX512VBMI2/VL
VPSHRDVW
VPSHRDVW
                     ymmreg|mask|z,ymmreg*,ymmrm256 AVX512VBMI2/VL
VPSHRDVW
                     zmmreg|mask|z,zmmreg*,zmmrm512 AVX512VBMI2
                     xmmreg|mask|z,xmmreg*,xmmrm128|b32 AVX512VBMI2/VL
ymmreg|mask|z,ymmreg*,ymmrm256|b32 AVX512VBMI2/VL
VPSHRDVD
VPSHRDVD
                     zmmreg|mask|z,zmmreg*,zmmrm512|b32 AVX512VBMI2
VPSHRDVD
VPSHRDVQ
                     xmmreg|mask|z,xmmreg*,xmmrm128|b64 AVX512VBMI2/VL
                     ymmreg|mask|z,ymmreg*,ymmrm256|b64 AVX512VBMI2/VL
VPSHRDVQ
                     zmmreg|mask|z,zmmreg*,zmmrm512|b64 AVX512VBMI2
VPSHRDVQ
```

B.1.50 AVX512 VNNI

VPDPBUSD	<pre>xmmreg mask z,xmmreg*,xmmrm128 b32 AVX512VNNI/VL</pre>
VPDPBUSD	ymmreg mask z,ymmreg*,ymmrm256 b32 AVX512VNNI/VL
VPDPBUSD	zmmreg mask z,zmmreg*,zmmrm512 b32 AVX512VNNI
VPDPBUSDS	xmmreg mask z,xmmreg*,xmmrm128 b32 AVX512VNNI/VL
VPDPBUSDS	<pre>ymmreg mask z,ymmreg*,ymmrm256 b32 AVX512VNNI/VL</pre>
VPDPBUSDS	<pre>zmmreg mask z,zmmreg*,zmmrm512 b32 AVX512VNNI</pre>
VPDPWSSD	xmmreg mask z,xmmreg*,xmmrm128 b32 AVX512VNNI/VL
VPDPWSSD	<pre>ymmreg mask z,ymmreg*,ymmrm256 b32 AVX512VNNI/VL</pre>
VPDPWSSD	zmmreg mask z,zmmreg*,zmmrm512 b32 AVX512VNNI
VPDPWSSDS	xmmreg mask z,xmmreg*,xmmrm128 b32 AVX512VNNI/VL
VPDPWSSDS	<pre>ymmreg mask z,ymmreg*,ymmrm256 b32 AVX512VNNI/VL</pre>
VPDPWSSDS	zmmreg mask z,zmmreg*,zmmrm512 b32 AVX512VNNI

B.1.51 AVX512 Bit Algorithms

VPOPCNTB	xmmreg mask z,xmmrm128	AVX512BITALG/VL
VPOPCNTB	ymmreg mask z,ymmrm256	AVX512BITALG/VL
VPOPCNTB	zmmreg mask z,zmmrm512	AVX512BITALG
VPOPCNTW	xmmreg mask z,xmmrm128	AVX512BITALG/VL
VPOPCNTW	ymmreg mask z,ymmrm256	AVX512BITALG/VL

VPOPCNTW	zmmreg mask z,zmmrm512	AVX512BITALG
VPOPCNTD	xmmreg mask z,xmmrm128	AVX512VPOPCNTDQ/VL
VPOPCNTD	ymmreg mask z,ymmrm256	AVX512VPOPCNTDQ/VL
VPOPCNTD	zmmreg mask z,zmmrm512	AVX512VPOPCNTDQ
VPOPCNTQ	xmmreg mask z,xmmrm128	AVX512VPOPCNTDQ/VL
VPOPCNTQ	ymmreg mask z,ymmrm256	AVX512VPOPCNTDQ/VL
VPOPCNTQ	zmmreg mask z,zmmrm512	AVX512VPOPCNTDQ
VPSHUFBITQMB	<pre>kreg mask,xmmreg,xmmrm128</pre>	3 AVX512BITALG/VL
VPSHUFBITQMB	kreg mask,ymmreg,ymmrm256	6 AVX512BITALG/VL
VPSHUFBITQMB	kreg mask,zmmreg,zmmrm512	2 AVX512BITALG

B.1.52 AVX512 4-iteration Multiply-Add

V4FMADDPS	<pre>zmmreg mask z,zmmreg rs4,mem</pre>	AVX5124FMAPS,S0
V4FNMADDPS	<pre>zmmreg mask z,zmmreg rs4,mem</pre>	AVX5124FMAPS,SO
V4FMADDSS	zmmreg mask z,zmmreg rs4,mem	AVX5124FMAPS,S0
V4FNMADDSS	zmmreg mask z,zmmreg rs4,mem	AVX5124FMAPS,S0

B.1.53 AVX512 4-iteration Dot Product

V4DPWSSDS	<pre>zmmreg mask z,zmmreg rs4,mem</pre>	AVX5124VNNIW,SO
V4DPWSSD	zmmreg mask z,zmmreg rs4,mem	AVX5124VNNIW,SO

B.1.54 Intel Software Guard Extensions (SGX)

ENCLS	SGX
ENCLU	SGX
ENCLV	SGX

B.1.55 Intel Control-Flow Enforcement Technology (CET)

mem64	CET
	CET
	CET
reg32	CET
reg64	CET,LONG
reg32	CET
reg64	CET,LONG
mem64	CET
	CET
	CET
mem32,reg32	CET
mem64,reg64	CET,LONG
mem32,reg32	CET
mem64,reg64	CET,LONG
	reg32 reg64 reg32 reg64 mem64 mem32,reg32 mem64,reg64 mem32,reg32

B.1.56 Instructions from ISE doc 319433-040, June 2020

ENQCMD	reg16,mem512	ENQCMD
ENQCMD	reg32,mem512	ENQCMD, ND
ENQCMD	reg32,mem512	ENQCMD
ENQCMD	reg64,mem512	ENQCMD, LONG
ENQCMDS	reg16,mem512	ENQCMD, PRIV
ENQCMDS	reg32,mem512	ENQCMD, PRIV, ND
ENQCMDS	reg32,mem512	ENQCMD, PRIV
ENQCMDS	reg64,mem512	ENQCMD, PRIV, LONG
PCONFIG		PCONFIG, PRIV
SERIALIZE		SERIALIZE
WBNOINVD		WBNOINVD, PRIV
XRESLDTRK		TSXLDTRK
XSUSLDTRK		TSXLDTRK

B.1.57 AVX512 Bfloat16 instructions

VCVTNE2PS2BF16	xmmreg mask z,xmmreg*,xmmrm128 b32	AVX512BF16
VCVTNE2PS2BF16	ymmreg mask z,ymmreg*,ymmrm256 b32	AVX512BF16
VCVTNE2PS2BF16	<pre>zmmreg mask z,zmmreg*,zmmrm512 b32</pre>	AVX512BF16
VCVTNE2PS2BF16	xmmreg mask z,xmmreg*,xmmrm128 b32	AVX512BF16

VCVTNE2PS2BF16	<pre>ymmreg mask z,ymmreg*,ymmrm256 b32 AVX512BF16</pre>
VCVTNE2PS2BF16	zmmreg mask z,zmmreg*,zmmrm512 b32 AVX512BF16
VDPBF16PS	xmmreg mask z,xmmreg*,xmmrm128 b32 AVX512BF16
VDPBF16PS	ymmreg mask z,ymmreg*,ymmrm128 b32 AVX512BF16
VDPBF16PS	<pre>zmmreg mask z,zmmreg*,zmmrm128 b32 AVX512BF16</pre>

B.1.58 AVX512 mask intersect instructions

VP2INTERSECTD	kreg rs2,xmmreg,xmmrm128 b32	AVX512BF16
VP2INTERSECTD	kreg rs2,ymmreg,ymmrm128 b32	AVX512BF16
VP2INTERSECTD	kreg rs2,zmmreg,zmmrm128 b32	AVX512BF16

B.1.59 Intel Advanced Matrix Extensions (AMX)

LDTILECFG	mem512	AMXTILE, SZ, LONG
STTILECFG	mem512	AMXTILE, SZ, LONG
TDPBF16PS	tmmreg,tmmreg,tmmreg	AMXBF16,LONG
TDPBSSD	tmmreg,tmmreg,tmmreg	AMXINT8,LONG
TDPBSUD	tmmreg,tmmreg,tmmreg	AMXINT8,LONG
TDPBUSD	tmmreg,tmmreg,tmmreg	AMXINT8,LONG
TDPBUUD	tmmreg,tmmreg,tmmreg	AMXINT8,LONG
TILELOADD	tmmreg, mem	AMXTILE, MIB, SIB, SX, LONG
TILELOADDT1	tmmreg, mem	AMXTILE, MIB, SIB, SX, LONG
TILERELEASE		AMXTILE,LONG
TILESTORED	mem,tmmreg	AMXTILE, MIB, SIB, SX, LONG
TILEZERO	tmmreg	AMXTILE,LONG

B.1.60 Systematic names for the hinting nop instructions

HINT_NOP0	rm16	P6,UNDOC
HINT_NOP0	rm32	P6,UNDOC
HINT_NOP0	rm64	X86_64,LONG,UNDOC
HINT_NOP1	rm16	P6,UNDOC
HINT_NOP1	rm32	P6,UNDOC
HINT_NOP1	rm64	X86_64,LONG,UNDOC
HINT_NOP2	rm16	P6,UNDOC
HINT_NOP2	rm32	P6,UNDOC
HINT_NOP2	rm64	X86_64,LONG,UNDOC
HINT_NOP3	rm16	P6,UNDOC
HINT_NOP3	rm32	P6,UNDOC
HINT_NOP3	rm64	X86_64,LONG,UNDOC
HINT_NOP4	rm16	P6,UNDOC
HINT_NOP4	rm32	P6,UNDOC
HINT_NOP4	rm64	X86_64,LONG,UNDOC
HINT_NOP5	rm16	P6,UNDOC
HINT_NOP5	rm32	P6,UNDOC
HINT_NOP5	rm64	X86_64,LONG,UNDOC
HINT_NOP6	rm16	P6,UNDOC
HINT_NOP6	rm32	P6,UNDOC
HINT_NOP6	rm64	X86_64,LONG,UNDOC
HINT_NOP7	rm16	P6,UNDOC
HINT_NOP7	rm32	P6,UNDOC
HINT_NOP7	rm64	X86_64,LONG,UNDOC
HINT_NOP8	rm16	P6,UNDOC
HINT_NOP8	rm32	P6,UNDOC
HINT_NOP8	rm64	X86_64,LONG,UNDOC
HINT_NOP9	rm16	P6,UNDOC
HINT_NOP9	rm32	P6,UNDOC
HINT_NOP9	rm64	X86_64,LONG,UNDOC
HINT_NOP10	rm16	P6,UNDOC
HINT_NOP10	rm32	P6,UNDOC
HINT_NOP10	rm64	X86_64,LONG,UNDOC
HINT_NOP11	rm16	P6,UNDOC
HINT_NOP11	rm32	P6,UNDOC
HINT_NOP11	rm64	X86_64,LONG,UNDOC
HINT_NOP12	rm16	P6,UNDOC
HINT_NOP12	rm32	P6,UNDOC
HINT_NOP12	rm64	X86_64,LONG,UNDOC

HINT NOP13			
HINT NOP13	HINT NOP13	rm16	P6,UNDOC
HINT_NOP14			· · · · · · · · · · · · · · · · · · ·
HINT_NOP14	_		· · · · · · · · · · · · · · · · · · ·
HINT_NOP14			
HINT_NOP15			•
HINT_NOP15			•
HINT_NOP15		rm64	X86_64,LONG,UNDOC
HINT_NOP16 rm64 X86_64,LONG,UNDOC HINT_NOP16 rm32 P6,UNDOC HINT_NOP16 rm32 P6,UNDOC HINT_NOP16 rm64 X86_64,LONG,UNDOC HINT_NOP17 rm16 P6,UNDOC HINT_NOP17 rm32 P6,UNDOC HINT_NOP17 rm32 P6,UNDOC HINT_NOP17 rm64 X86_64,LONG,UNDOC HINT_NOP18 rm16 P6,UNDOC HINT_NOP18 rm32 P6,UNDOC HINT_NOP18 rm32 P6,UNDOC HINT_NOP19 rm32 P6,UNDOC HINT_NOP20 rm64 X86_64,LONG,UNDOC P6,UNDOC HINT_NOP20 rm64 X86_64,LONG,UNDOC HINT_NOP20 rm64 X86_64,LONG,UNDOC HINT_NOP20 rm64 X86_64,LONG,UNDOC HINT_NOP21 rm64 X86_64,LONG,UNDOC HINT_NOP21 rm64 X86_64,LONG,UNDOC HINT_NOP22 rm16 P6,UNDOC HINT_NOP22 rm16 P6,UNDOC HINT_NOP22 rm64 X86_64,LONG,UNDOC HINT_NOP22 rm64 X86_64,LONG,UNDOC HINT_NOP22 rm64 X86_64,LONG,UNDOC HINT_NOP23 rm64 X86_64,LONG,UNDOC HINT_NOP23 rm64 X86_64,LONG,UNDOC HINT_NOP24 rm64 X86_64,LONG,UNDOC HINT_NOP25 rm64 X86_64,LONG,UNDOC HINT_NOP25 rm64 X86_64,LONG,UNDOC HINT_NOP24 rm64 X86_64,LONG,UNDOC HINT_NOP25 rm32 P6,UNDOC HINT_NOP25 rm32 P6,UNDOC HINT_NOP26 rm32 P6,UNDOC HINT_NOP27 rm64 X86_64,LONG,UNDOC P6,UNDOC HINT_NOP28 rm64 X86_64,LONG,UNDOC P6,UNDOC HINT_NOP29 rm64 X86_64,LONG,UNDOC P6,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC P6,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC P6,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC P6,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC P6,UNDOC P6,U	HINT_NOP15	rm16	P6,UNDOC
HINT_NOP16 rm64 X86_64,LONG,UNDOC HINT_NOP16 rm32 P6,UNDOC HINT_NOP16 rm32 P6,UNDOC HINT_NOP16 rm64 X86_64,LONG,UNDOC HINT_NOP17 rm16 P6,UNDOC HINT_NOP17 rm32 P6,UNDOC HINT_NOP17 rm32 P6,UNDOC HINT_NOP17 rm64 X86_64,LONG,UNDOC HINT_NOP18 rm16 P6,UNDOC HINT_NOP18 rm32 P6,UNDOC HINT_NOP18 rm32 P6,UNDOC HINT_NOP19 rm32 P6,UNDOC HINT_NOP20 rm64 X86_64,LONG,UNDOC P6,UNDOC HINT_NOP20 rm64 X86_64,LONG,UNDOC HINT_NOP20 rm64 X86_64,LONG,UNDOC HINT_NOP20 rm64 X86_64,LONG,UNDOC HINT_NOP21 rm64 X86_64,LONG,UNDOC HINT_NOP21 rm64 X86_64,LONG,UNDOC HINT_NOP22 rm16 P6,UNDOC HINT_NOP22 rm16 P6,UNDOC HINT_NOP22 rm64 X86_64,LONG,UNDOC HINT_NOP22 rm64 X86_64,LONG,UNDOC HINT_NOP22 rm64 X86_64,LONG,UNDOC HINT_NOP23 rm64 X86_64,LONG,UNDOC HINT_NOP23 rm64 X86_64,LONG,UNDOC HINT_NOP24 rm64 X86_64,LONG,UNDOC HINT_NOP25 rm64 X86_64,LONG,UNDOC HINT_NOP25 rm64 X86_64,LONG,UNDOC HINT_NOP24 rm64 X86_64,LONG,UNDOC HINT_NOP25 rm32 P6,UNDOC HINT_NOP25 rm32 P6,UNDOC HINT_NOP26 rm32 P6,UNDOC HINT_NOP27 rm64 X86_64,LONG,UNDOC P6,UNDOC HINT_NOP28 rm64 X86_64,LONG,UNDOC P6,UNDOC HINT_NOP29 rm64 X86_64,LONG,UNDOC P6,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC P6,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC P6,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC P6,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC P6,UNDOC P6,U	HINT_NOP15	rm32	P6,UNDOC
HINT_NOP16		rm64	· · · · · · · · · · · · · · · · · · ·
HINT_NOP16			
HINT_NOP16 rm64			•
HINT_NOP17			· · · · · · · · · · · · · · · · · · ·
HINT_NOP17			
HINT_NOP18	HINT_NOP17	rm16	•
HINT_NOP18	HINT_NOP17	rm32	P6,UNDOC
HINT_NOP18	HINT_NOP17	rm64	X86_64,LONG,UNDOC
HINT_NOP18	HINT NOP18	rm16	
HINT_NOP18			· · · · · · · · · · · · · · · · · · ·
HINT_NOP19			· · · · · · · · · · · · · · · · · · ·
HINT_NOP19			
HINT_NOP19			•
HINT_NOP20			· · · · · · · · · · · · · · · · · · ·
HINT_NOP20 rm64		rm64	X86_64,LONG,UNDOC
HINT_NOP20	HINT_NOP20	rm16	P6,UNDOC
HINT_NOP20	HINT_NOP20	rm32	P6,UNDOC
HINT_NOP21 rm32 P6,UNDOC HINT_NOP21 rm32 P6,UNDOC HINT_NOP21 rm64 X86_64,LONG,UNDOC HINT_NOP22 rm16 P6,UNDOC HINT_NOP22 rm32 P6,UNDOC HINT_NOP22 rm32 P6,UNDOC HINT_NOP22 rm64 X86_64,LONG,UNDOC HINT_NOP23 rm16 P6,UNDOC HINT_NOP23 rm32 P6,UNDOC HINT_NOP23 rm32 P6,UNDOC HINT_NOP24 rm16 P6,UNDOC HINT_NOP24 rm32 P6,UNDOC HINT_NOP25 rm16 P6,UNDOC HINT_NOP25 rm16 P6,UNDOC HINT_NOP26 rm32 P6,UNDOC HINT_NOP25 rm64 X86_64,LONG,UNDOC HINT_NOP26 rm32 P6,UNDOC HINT_NOP26 rm32 P6,UNDOC HINT_NOP26 rm32 P6,UNDOC HINT_NOP27 rm64 X86_64,LONG,UNDOC HINT_NOP28 rm64 X86_64,LONG,UNDOC HINT_NOP29 rm64 X86_64,LONG,UNDOC HINT_NOP30 rm16 P6,UNDOC HINT_NOP31 rm32 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC			•
HINT_NOP21 rm64			
HINT_NOP21			
HINT_NOP22			•
HINT_NOP22			
HINT_NOP22	HINT_NOP22	rm16	P6,UNDOC
HINT_NOP23	HINT_NOP22	rm32	P6,UNDOC
HINT_NOP23	HINT_NOP22	rm64	X86_64,LONG,UNDOC
HINT_NOP23		rm16	
HINT_NOP23			· · · · · · · · · · · · · · · · · · ·
HINT_NOP24			· · · · · · · · · · · · · · · · · · ·
HINT_NOP24 rm32 P6,UNDOC HINT_NOP25 rm64 X86_64,LONG,UNDOC HINT_NOP25 rm16 P6,UNDOC HINT_NOP25 rm32 P6,UNDOC HINT_NOP25 rm64 X86_64,LONG,UNDOC HINT_NOP26 rm16 P6,UNDOC HINT_NOP26 rm32 P6,UNDOC HINT_NOP27 rm16 P6,UNDOC HINT_NOP27 rm32 P6,UNDOC HINT_NOP27 rm32 P6,UNDOC HINT_NOP27 rm64 X86_64,LONG,UNDOC HINT_NOP28 rm16 P6,UNDOC HINT_NOP28 rm32 P6,UNDOC HINT_NOP28 rm64 X86_64,LONG,UNDOC HINT_NOP29 rm16 P6,UNDOC HINT_NOP29 rm64 X86_64,LONG,UNDOC HINT_NOP30 rm32 P6,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm16 P			
HINT_NOP24 rm64 X86_64,LONG,UNDOC HINT_NOP25 rm16 P6,UNDOC HINT_NOP25 rm32 P6,UNDOC HINT_NOP25 rm64 X86_64,LONG,UNDOC HINT_NOP26 rm16 P6,UNDOC HINT_NOP26 rm32 P6,UNDOC HINT_NOP27 rm16 P6,UNDOC HINT_NOP27 rm32 P6,UNDOC HINT_NOP27 rm32 P6,UNDOC HINT_NOP27 rm32 P6,UNDOC HINT_NOP28 rm32 P6,UNDOC HINT_NOP28 rm32 P6,UNDOC HINT_NOP28 rm32 P6,UNDOC HINT_NOP28 rm64 X86_64,LONG,UNDOC HINT_NOP29 rm64 X86_64,LONG,UNDOC HINT_NOP29 rm64 X86_64,LONG,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm32			•
HINT_NOP25 rm32 P6,UNDOC HINT_NOP25 rm32 P6,UNDOC HINT_NOP25 rm64 X86_64,LONG,UNDOC HINT_NOP26 rm16 P6,UNDOC HINT_NOP26 rm32 P6,UNDOC HINT_NOP26 rm64 X86_64,LONG,UNDOC HINT_NOP27 rm16 P6,UNDOC HINT_NOP27 rm32 P6,UNDOC HINT_NOP27 rm64 X86_64,LONG,UNDOC HINT_NOP28 rm16 P6,UNDOC HINT_NOP28 rm32 P6,UNDOC HINT_NOP28 rm64 X86_64,LONG,UNDOC HINT_NOP29 rm16 P6,UNDOC HINT_NOP29 rm32 P6,UNDOC HINT_NOP30 rm16 P6,UNDOC HINT_NOP30 rm32 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm32 P6,UNDOC </td <td></td> <td>rm32</td> <td>· · · · · · · · · · · · · · · · · · ·</td>		rm32	· · · · · · · · · · · · · · · · · · ·
HINT_NOP25 rm32 P6,UNDOC HINT_NOP25 rm64 X86_64,LONG,UNDOC HINT_NOP26 rm16 P6,UNDOC HINT_NOP26 rm32 P6,UNDOC HINT_NOP26 rm64 X86_64,LONG,UNDOC HINT_NOP27 rm16 P6,UNDOC HINT_NOP27 rm32 P6,UNDOC HINT_NOP28 rm64 X86_64,LONG,UNDOC HINT_NOP28 rm32 P6,UNDOC HINT_NOP28 rm32 P6,UNDOC HINT_NOP28 rm64 X86_64,LONG,UNDOC HINT_NOP29 rm16 P6,UNDOC HINT_NOP29 rm64 X86_64,LONG,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm16 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP34 rm64	HINT_NOP24	rm64	X86_64,LONG,UNDOC
HINT_NOP25 rm64 X86_64,LONG,UNDOC HINT_NOP26 rm16 P6,UNDOC HINT_NOP26 rm32 P6,UNDOC HINT_NOP26 rm64 X86_64,LONG,UNDOC HINT_NOP27 rm16 P6,UNDOC HINT_NOP27 rm32 P6,UNDOC HINT_NOP28 rm64 X86_64,LONG,UNDOC HINT_NOP28 rm32 P6,UNDOC HINT_NOP28 rm64 X86_64,LONG,UNDOC HINT_NOP29 rm16 P6,UNDOC HINT_NOP29 rm32 P6,UNDOC HINT_NOP29 rm64 X86_64,LONG,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP34	HINT_NOP25	rm16	P6,UNDOC
HINT_NOP25 rm64 X86_64,LONG,UNDOC HINT_NOP26 rm16 P6,UNDOC HINT_NOP26 rm32 P6,UNDOC HINT_NOP26 rm64 X86_64,LONG,UNDOC HINT_NOP27 rm16 P6,UNDOC HINT_NOP27 rm32 P6,UNDOC HINT_NOP28 rm64 X86_64,LONG,UNDOC HINT_NOP28 rm32 P6,UNDOC HINT_NOP28 rm64 X86_64,LONG,UNDOC HINT_NOP29 rm16 P6,UNDOC HINT_NOP29 rm32 P6,UNDOC HINT_NOP29 rm64 X86_64,LONG,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP34		rm32	•
HINT_NOP26 rm16 P6,UNDOC HINT_NOP26 rm32 P6,UNDOC HINT_NOP26 rm64 X86_64,LONG,UNDOC HINT_NOP27 rm16 P6,UNDOC HINT_NOP27 rm32 P6,UNDOC HINT_NOP28 rm16 P6,UNDOC HINT_NOP28 rm32 P6,UNDOC HINT_NOP28 rm32 P6,UNDOC HINT_NOP28 rm64 X86_64,LONG,UNDOC HINT_NOP29 rm32 P6,UNDOC HINT_NOP29 rm32 P6,UNDOC HINT_NOP30 rm16 P6,UNDOC HINT_NOP30 rm32 P6,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm16 P6,UNDOC HINT_NOP31 rm32 P6,UNDOC HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP34 rm16 P6,UNDOC <			· · · · · · · · · · · · · · · · · · ·
HINT_NOP26 rm32 P6,UNDOC HINT_NOP26 rm64 X86_64,LONG,UNDOC HINT_NOP27 rm16 P6,UNDOC HINT_NOP27 rm32 P6,UNDOC HINT_NOP27 rm64 X86_64,LONG,UNDOC HINT_NOP28 rm16 P6,UNDOC HINT_NOP28 rm32 P6,UNDOC HINT_NOP28 rm64 X86_64,LONG,UNDOC HINT_NOP29 rm16 P6,UNDOC HINT_NOP29 rm32 P6,UNDOC HINT_NOP30 rm16 P6,UNDOC HINT_NOP30 rm32 P6,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm16 P6,UNDOC HINT_NOP31 rm32 P6,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm32 P6,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP34 rm16 P			
HINT_NOP26 rm64 X86_64,LONG,UNDOC HINT_NOP27 rm16 P6,UNDOC HINT_NOP27 rm32 P6,UNDOC HINT_NOP27 rm64 X86_64,LONG,UNDOC HINT_NOP28 rm16 P6,UNDOC HINT_NOP28 rm32 P6,UNDOC HINT_NOP28 rm64 X86_64,LONG,UNDOC HINT_NOP29 rm16 P6,UNDOC HINT_NOP29 rm32 P6,UNDOC HINT_NOP30 rm16 P6,UNDOC HINT_NOP30 rm32 P6,UNDOC HINT_NOP30 rm32 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm32 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm16 P6,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC </td <td></td> <td></td> <td>· · · · · · · · · · · · · · · · · · ·</td>			· · · · · · · · · · · · · · · · · · ·
HINT_NOP27 rm16 P6,UNDOC HINT_NOP27 rm32 P6,UNDOC HINT_NOP27 rm64 X86_64,LONG,UNDOC HINT_NOP28 rm16 P6,UNDOC HINT_NOP28 rm32 P6,UNDOC HINT_NOP28 rm64 X86_64,LONG,UNDOC HINT_NOP29 rm16 P6,UNDOC HINT_NOP29 rm32 P6,UNDOC HINT_NOP30 rm16 P6,UNDOC HINT_NOP30 rm32 P6,UNDOC HINT_NOP30 rm32 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm32 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm32 P6,UNDOC HINT_NOP33 rm44 X86_64,LONG,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC <td></td> <td></td> <td>· · · · · · · · · · · · · · · · · · ·</td>			· · · · · · · · · · · · · · · · · · ·
HINT_NOP27 rm32 P6,UNDOC HINT_NOP27 rm64 X86_64,LONG,UNDOC HINT_NOP28 rm16 P6,UNDOC HINT_NOP28 rm32 P6,UNDOC HINT_NOP28 rm64 X86_64,LONG,UNDOC HINT_NOP29 rm16 P6,UNDOC HINT_NOP29 rm32 P6,UNDOC HINT_NOP30 rm16 P6,UNDOC HINT_NOP30 rm32 P6,UNDOC HINT_NOP30 rm32 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm32 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm32 P6,UNDOC HINT_NOP33 rm16 P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC <td></td> <td></td> <td></td>			
HINT_NOP27 rm64 X86_64,LONG,UNDOC HINT_NOP28 rm16 P6,UNDOC HINT_NOP28 rm32 P6,UNDOC HINT_NOP28 rm64 X86_64,LONG,UNDOC HINT_NOP29 rm16 P6,UNDOC HINT_NOP29 rm32 P6,UNDOC HINT_NOP30 rm16 P6,UNDOC HINT_NOP30 rm32 P6,UNDOC HINT_NOP30 rm32 P6,UNDOC HINT_NOP31 rm16 P6,UNDOC HINT_NOP31 rm32 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm32 P6,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC	HINT_NOP27	rm16	P6,UNDOC
HINT_NOP28 rm16 P6,UNDOC HINT_NOP28 rm32 P6,UNDOC HINT_NOP28 rm64 X86_64,LONG,UNDOC HINT_NOP29 rm16 P6,UNDOC HINT_NOP29 rm32 P6,UNDOC HINT_NOP30 rm16 P6,UNDOC HINT_NOP30 rm32 P6,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm16 P6,UNDOC HINT_NOP31 rm32 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm32 P6,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm16 P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC	HINT_NOP27	rm32	P6,UNDOC
HINT_NOP28 rm16 P6,UNDOC HINT_NOP28 rm32 P6,UNDOC HINT_NOP28 rm64 X86_64,LONG,UNDOC HINT_NOP29 rm16 P6,UNDOC HINT_NOP29 rm32 P6,UNDOC HINT_NOP30 rm16 P6,UNDOC HINT_NOP30 rm32 P6,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm16 P6,UNDOC HINT_NOP31 rm32 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm32 P6,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm16 P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC	HINT NOP27	rm64	X86 64,LONG,UNDOC
HINT_NOP28 rm32 P6,UNDOC HINT_NOP28 rm64 X86_64,LONG,UNDOC HINT_NOP29 rm16 P6,UNDOC HINT_NOP29 rm32 P6,UNDOC HINT_NOP29 rm64 X86_64,LONG,UNDOC HINT_NOP30 rm16 P6,UNDOC HINT_NOP30 rm32 P6,UNDOC HINT_NOP31 rm16 P6,UNDOC HINT_NOP31 rm32 P6,UNDOC HINT_NOP31 rm32 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm32 P6,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC		rm16	
HINT_NOP28 rm64 X86_64,LONG,UNDOC HINT_NOP29 rm16 P6,UNDOC HINT_NOP29 rm32 P6,UNDOC HINT_NOP29 rm64 X86_64,LONG,UNDOC HINT_NOP30 rm16 P6,UNDOC HINT_NOP30 rm32 P6,UNDOC HINT_NOP31 rm16 P6,UNDOC HINT_NOP31 rm32 P6,UNDOC HINT_NOP31 rm32 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm32 P6,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC	_		,
HINT_NOP29 rm16 P6,UNDOC HINT_NOP29 rm32 P6,UNDOC HINT_NOP29 rm64 X86_64,LONG,UNDOC HINT_NOP30 rm16 P6,UNDOC HINT_NOP30 rm32 P6,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm16 P6,UNDOC HINT_NOP31 rm32 P6,UNDOC HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm32 P6,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm16 P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC			
HINT_NOP29 rm32 P6,UNDOC HINT_NOP29 rm64 X86_64,LONG,UNDOC HINT_NOP30 rm16 P6,UNDOC HINT_NOP30 rm32 P6,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm16 P6,UNDOC HINT_NOP31 rm32 P6,UNDOC HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm32 P6,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm16 P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC			- , ,
HINT_NOP29 rm64 X86_64,LONG,UNDOC HINT_NOP30 rm16 P6,UNDOC HINT_NOP30 rm32 P6,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm16 P6,UNDOC HINT_NOP31 rm32 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm16 P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC			•
HINT_NOP30 rm16 P6,UNDOC HINT_NOP30 rm32 P6,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm16 P6,UNDOC HINT_NOP31 rm32 P6,UNDOC HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm32 P6,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm16 P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC			•
HINT_NOP30 rm32 P6,UNDOC HINT_NOP30 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm16 P6,UNDOC HINT_NOP31 rm32 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm32 P6,UNDOC HINT_NOP33 rm16 P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC		rm64	X86_64,LONG,UNDOC
HINT_NOP30 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm16 P6,UNDOC HINT_NOP31 rm32 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm32 P6,UNDOC HINT_NOP33 rm16 P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC	HINT_NOP30	rm16	P6,UNDOC
HINT_NOP30 rm64 X86_64,LONG,UNDOC HINT_NOP31 rm16 P6,UNDOC HINT_NOP31 rm32 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm32 P6,UNDOC HINT_NOP33 rm16 P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC	HINT NOP30	rm32	P6.UNDOC
HINT_NOP31 rm16 P6,UNDOC HINT_NOP31 rm32 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm32 P6,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm16 P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC	_		· · · · · · · · · · · · · · · · · · ·
HINT_NOP31 rm32 P6,UNDOC HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm32 P6,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm16 P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC	_		
HINT_NOP31 rm64 X86_64,LONG,UNDOC HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm32 P6,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm16 P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC			
HINT_NOP32 rm16 P6,UNDOC HINT_NOP32 rm32 P6,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm16 P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC			
HINT_NOP32 rm32 P6,UNDOC HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm16 P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC			
HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm16 P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC	_	rm16	· · · · · · · · · · · · · · · · · · ·
HINT_NOP32 rm64 X86_64,LONG,UNDOC HINT_NOP33 rm16 P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC	HINT_NOP32	rm32	P6,UNDOC
HINT_NOP33 rm16 P6,UNDOC HINT_NOP33 rm32 P6,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC	HINT_NOP32	rm64	
HINT_NOP33 rm32 P6,UNDOC HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC			
HINT_NOP33 rm64 X86_64,LONG,UNDOC HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC			
HINT_NOP34 rm16 P6,UNDOC HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC			· · · · · · · · · · · · · · · · · · ·
HINT_NOP34 rm32 P6,UNDOC HINT_NOP34 rm64 X86_64,LONG,UNDOC			· · · · · · · · · · · · · · · · · · ·
HINT_NOP34 rm64 X86_64,LONG,UNDOC			· · · · · · · · · · · · · · · · · · ·
	HINT_NOP34	rm32	P6,UNDOC
	HINT_NOP34	rm64	X86_64,LONG,UNDOC
		rm16	
			•

HINT_NOP35	rm32	P6,UNDOC
HINT_NOP35	rm64	X86_64,LONG,UNDOC
HINT_NOP36	rm16	P6,UNDOC
_		· · · · · · · · · · · · · · · · · · ·
HINT_NOP36	rm32	P6,UNDOC
HINT_NOP36	rm64	X86_64,LONG,UNDOC
HINT_NOP37	rm16	P6,UNDOC
	rm32	•
HINT_NOP37		P6,UNDOC
HINT_NOP37	rm64	X86_64,LONG,UNDOC
HINT_NOP38	rm16	P6,UNDOC
HINT_NOP38	rm32	P6,UNDOC
HINT_NOP38	rm64	X86_64,LONG,UNDOC
HINT_NOP39	rm16	P6,UNDOC
HINT_NOP39	rm32	P6,UNDOC
HINT_NOP39	rm64	X86_64,LONG,UNDOC
HINT_NOP40	rm16	P6,UNDOC
HINT_NOP40	rm32	P6,UNDOC
HINT_NOP40	rm64	X86_64,LONG,UNDOC
HINT_NOP41	rm16	P6,UNDOC
_		· · · · · · · · · · · · · · · · · · ·
HINT_NOP41	rm32	P6,UNDOC
HINT_NOP41	rm64	X86_64,LONG,UNDOC
HINT_NOP42	rm16	P6,UNDOC
HINT_NOP42	rm32	P6,UNDOC
HINT_NOP42	rm64	X86_64,LONG,UNDOC
HINT_NOP43	rm16	P6,UNDOC
HINT_NOP43	rm32	P6,UNDOC
_	rm64	
HINT_NOP43		X86_64,LONG,UNDOC
HINT_NOP44	rm16	P6,UNDOC
HINT_NOP44	rm32	P6,UNDOC
HINT_NOP44	rm64	X86_64,LONG,UNDOC
HINT_NOP45	rm16	P6,UNDOC
HINT_NOP45	rm32	P6,UNDOC
HINT_NOP45	rm64	X86_64,LONG,UNDOC
HINT_NOP46	rm16	P6,UNDOC
	rm32	P6,UNDOC
HINT_NOP46		· · · · · · · · · · · · · · · · · · ·
HINT_NOP46	rm64	X86_64,LONG,UNDOC
HINT_NOP47	rm16	P6,UNDOC
HINT_NOP47	rm32	P6,UNDOC
HINT_NOP47	rm64	X86_64,LONG,UNDOC
HINT_NOP48	rm16	P6,UNDOC
HINT_NOP48	rm32	P6,UNDOC
HINT_NOP48	rm64	X86_64,LONG,UNDOC
HINT_NOP49	rm16	P6,UNDOC
HINT_NOP49	rm32	P6,UNDOC
HINT_NOP49	rm64	X86_64,LONG,UNDOC
HINT_NOP50	rm16	P6,UNDOC
		,
HINT_NOP50	rm32	P6,UNDOC
HINT_NOP50	rm64	X86_64,LONG,UNDOC
HINT_NOP51	rm16	P6,UNDOC
HINT_NOP51	rm32	P6,UNDOC
		· · · · · · · · · · · · · · · · · · ·
HINT_NOP51	rm64	X86_64,LONG,UNDOC
HINT_NOP52	rm16	P6,UNDOC
HINT_NOP52	rm32	P6,UNDOC
HINT_NOP52	rm64	X86_64,LONG,UNDOC
_		
HINT_NOP53	rm16	P6,UNDOC
HINT_NOP53	rm32	P6,UNDOC
HINT_NOP53	rm64	X86_64,LONG,UNDOC
HINT_NOP54	rm16	P6,UNDOC
		· · · · · · · · · · · · · · · · · · ·
HINT_NOP54	rm32	P6,UNDOC
HINT_NOP54	rm64	X86_64,LONG,UNDOC
HINT_NOP55	rm16	P6,UNDOC
HINT_NOP55	rm32	P6,UNDOC
		· · · · · · · · · · · · · · · · · · ·
HINT_NOP55	rm64	X86_64,LONG,UNDOC
HINT_NOP56	rm16	P6,UNDOC
HINT_NOP56	rm32	P6,UNDOC
HINT_NOP56	rm64	X86_64,LONG,UNDOC
		· · · · · · · · · · · · · · · · · · ·
HINT_NOP57	rm16	P6,UNDOC
HINT_NOP57	rm32	P6,UNDOC

HINT_NOP57	rm64	X86_64,LONG,UNDOC
HINT_NOP58	rm16	P6,UNDOC
HINT_NOP58	rm32	P6,UNDOC
HINT_NOP58	rm64	X86_64,LONG,UNDOC
HINT_NOP59	rm16	P6,UNDOC
HINT_NOP59	rm32	P6,UNDOC
HINT_NOP59	rm64	X86_64,LONG,UNDOC
HINT_NOP60	rm16	P6,UNDOC
HINT_NOP60	rm32	P6,UNDOC
HINT_NOP60	rm64	X86_64,LONG,UNDOC
HINT_NOP61	rm16	P6,UNDOC
HINT_NOP61	rm32	P6,UNDOC
HINT_NOP61	rm64	X86_64,LONG,UNDOC
HINT_NOP62	rm16	P6,UNDOC
HINT_NOP62	rm32	P6,UNDOC
HINT_NOP62	rm64	X86_64,LONG,UNDOC
HINT_NOP63	rm16	P6,UNDOC
HINT_NOP63	rm32	P6,UNDOC
HINT_NOP63	rm64	X86_64,LONG,UNDOC

Appendix C: NASM Version History

C.1 NASM 2 Series

The NASM 2 series supports x86-64, and is the production version of NASM since 2007.

C.1.1 Version 2.15.05

- Correct %ifid \$ and %ifid \$\$ being treated as true. See section 4.4.6.
- Add --reproducible option to suppress NASM version numbers and timestamps in output files. See section 2.1.34.

C.1.2 Version 2.15.04

- More sensible handling of the case where one single-line macro definition will shadow another. A
 warning will be issued, but the additional definition will be allowed. For the existing error case
 where both a parameterless and parametered macro are created, that warning is promoted to an
 error by default.
- Add special preprocessor tokens **? and **?? that expand like **? and **?? in single-line macros only. See section 4.1.6.
- Correct the encoding of the ENQCMDS and TILELOADT1 instructions.
- Fix case where the COFF backend (the coff, win32 and win64 output formats) would add padding bytes in the middle of a section if a SECTION/SEGMENT directive was provided which repeated an ALIGN= attribute. This neither matched legacy behavior, other backends, or user expectations.
- Fix SSE instructions not being recognized with an explicit memory operation size (e.g. movsd qword [eax],xmm0).
- The -L+ option no longer enables -Lw, which is mainly useful to debug NASM crashes. See section 2.1.4.
- Document long-standing hazards in the use of \$ in Dx statements, see section 3.2.1.
- The NASM-only RDOFF output format backend, which has been broken since at least NASM 2.14, has been disabled. The RDOFF tools are scheduled to be removed from the NASM distribution in NASM 2.16. If you have a concrete use case for RDOFF, please file a NASM bug report at https://bugs.nasm.us/assoon as possible. See section 8.13.

C.1.3 Version 2.15.03

- Add instructions from the Intel Instruction Set Extensions and Future Features Programming Reference, June 2020. This includes AVX5512 bfloat16, AVX512 mask intersect, and Intel Advanced Matrix Extensions (AMX).
- Support for bfloat16 floating-point constants. See section 3.4.6 and section 6.3.
- Properly display warnings in preprocess-only mode.
- Fix copy-and-paste of examples from the PDF documentation.
- Debug information now properly reflect the line numbers of macro invocations (unless declared .nolist).
- Fix excessive alignment of sections in the coff/win32/win64 output formats when the user-specified alignment is less than the default alignment for the section or section type.

- Fix explicit token pasting (%+, section 4.1.4) for the cases where one or more parts result from empty token expansion, resulting in %+ tokens at the beginning or end, or multiple ones in a row.
- Fix macro label capture (%00, section 4.3.7).
- Much better documentation for the MASM compatiblity package, %use masm (see section 6.5).
- Fix LEA without square brackets, for MASM compatibility.
- · Portability fixes.

C.1.4 Version 2.15.02

- Fix miscompilation when building with clang.
- Add db-empty warning class, see section 2.1.26.
- Fix the dependencies in the MSVC NMAKE makefile (Mkfiles/msvc.mak).
- Some documentation improvements and cleanups.
- Fix the handling of macro parameter ranges (%{:}), including with brace-enclosed original arguments.

C.1.5 Version 2.15.01

- Fix building the documentation from the release archive. For 2.15, the user has to do make warnings
 manually in the main directory in order to be able to build the documentation, which means Perl
 needs to be installed on the system.
- Add instructions for Intel Control Flow Enforcement Technology (CET).

C.1.6 Version 2.15

- The comparison and booleanizing operators can now be used in any expression context, not just %if. See section 3.5.
- New operator ? ... :. See section 3.5.1.
- Signed shift operators <<< and >>>. See section 3.5.9.
- The MASM DUP syntax for data definitions is now supported, in a somewhat enhanced form. See section 3.2.1.
- Warn for strange legacy behavior regarding empty arguments in multi-line macro expansion, but try to match legacy behavior in most cases. Legacy behavior can be disabled with the directive %pragma preproc sane_empty_expansion, see section 4.3 and section 4.10.1.
- A much more sensible limit to expression evaluation depth. The previously defined limit would rarely trigger before NASM died with a stack overrun error on most systems. See section 2.1.31.
- The state of warnings can now be saved and restored via the [WARNING PUSH] and [WARNING POP] directives. See section 7.13.
- The sectalign on off switch does not affect an explicit directive. See section 5.10.2.
- Added configure option to enable building with profiling (--enable-profiling).
- Attempt to support of long path names, up to 32767 of UTF-16 characters, on Windows.
- Fixed 'mismatch in operand sizes' error in the MOVDDUP, CMPXCHG8B and CMPXCHG16B instructions.
- Improved error messages in the string transformation routine.
- Removed obsolete gnu-elf-extensions warning about 8- and 16-bit relocation generation. See section 8.9.8

- Added group aliases for all prefixed warnings. See section 2.1.26.
- Allowed building with MSVC versions older than 1700.
- Added implicitly sized versions of the $\kappa...$ instructions, which allows the $\kappa...$ instructions to be specified without a size suffix as long as the operands are sized.
- Added -L option for additional listing information. See section 2.1.4.
- Added some warnings for obsolete instructions for a specified CPU.
- Deprecated -hf and -y options. Use -h instead.
- Made DWARF as the default debug format for ELF.
- Added %pragma list options... to set or clear listing options (see opt-L).
- Allowed immediate syntax for LEA instruction (ignore operand size completely).
- Added limited functionality MASM compatibility package. See section 6.5.
- Add single-line macros aliases using %defalias or %idefalias. These behave like a kind of "symbolic links" for single-line macros. See section 4.1.11 and clear.
- Added support for stringify, nostrip, evaluating, and greedy single-line macro arguments. See section 4.1.1.
- Unused single-line macro arguments no longer need to have a specified name. See section 4.1.1.
- Added conditional comma operator %,. See section 4.1.12.
- Changed private namespace from __foo__ to __?foo?__, so a user namespace starting from underscore is now clean from symbols. For backwards compatibility, the previous names are defined as aliases; see section 4.1.11, section 4.11.3 and chapter 5.
- Added support of ELF weak symbols and external references. See section 8.9.5.
- Changed the behavior of the EXTERN keyword and introduced REQUIRED keyword. See section 7.6.
- Added %ifusable and %ifusing directives. See chapter 6.
- Made various performance improvements and stability fixes in macro preprocessor engine.
- Improved NASM error handling and cleaned up error messages.
- · Many, many bug fixes.

C.1.7 Version 2.14.03

- Suppress nuisance "label changed during code generation" messages after a real error.
- Add support for the merge and strings attributes on ELF sections. See section 8.9.2.
- Add support for the note, preinit_array, init_array, and fini_array sections type in ELF. See section 8.9.2.
- Handle more than 32,633 sections in ELF.

C.1.8 Version 2.14.02

• Fix crash due to multiple errors or warnings during the code generation pass if a list file is specified.

C.1.9 Version 2.14.01

- Create all system-defined macros defore processing command-line given preprocessing directives (-p, -d, -u, --pragma, --before).
- If debugging is enabled, define a __DEBUG_FORMAT__ predefined macro. See section 5.5.

- Fix an assert for the case in the obj format when a SEG operator refers to an EXTERN symbol declared further down in the code.
- Fix a corner case in the floating-point code where a binary, octal or hexadecimal floating-point having at least 32, 11, or 8 mantissa digits could produce slightly incorrect results under very specific conditions.
- Support -MD without a filename, for gcc compatibility. -MF can be used to set the dependencies output filename. See section 2.1.8.
- Fix -E in combination with -MD. See section 2.1.22.
- Fix missing errors on redefined labels; would cause convergence failure instead which is very slow and not easy to debug.
- Duplicate definitions of the same label *with the same value* is now explicitly permitted (2.14 would allow it in some circumstances.)
- Add the option --no-line to ignore %line directives in the source. See section 2.1.33 and section 4.11.1.

C.1.10 Version 2.14

- Changed -I option semantics by adding a trailing path separator unconditionally.
- Fixed null dereference in corrupted invalid single line macros.
- Fixed division by zero which may happen if source code is malformed.
- Fixed out of bound access in processing of malformed segment override.
- Fixed out of bound access in certain EQU parsing.
- Fixed buffer underflow in float parsing.
- Added sgx (Intel Software Guard Extensions) instructions.
- Added +n syntax for multiple contiguous registers.
- Fixed subsections_via_symbols for macho object format.
- Added the --gprefix, --gpostfix, --lprefix, and --lpostfix command line options, to allow command line base symbol renaming. See section 2.1.28.
- Allow label renaming to be specified by %pragma in addition to from the command line. See section 7 10
- Supported generic %pragma namespaces, output and debug. See section 4.10.
- Added the --pragma command line option to inject a %pragma directive. See section 2.1.29.
- Added the --before command line option to accept preprocess statement before input. See section 2.1.30.
- Added AVX512 VBMI2 (Additional Bit Manipulation), VNNI (Vector Neural Network), BITALG (Bit Algorithm), and GFNI (Galois Field New Instruction) instructions.
- Added the STATIC directive for local symbols that should be renamed using global-symbol rules. See section 7.9.
- Allow a symbol to be defined as EXTERN and then later overridden as GLOBAL or COMMON. Furthermore, a symbol declared EXTERN and then defined will be treated as GLOBAL. See section 7.5.
- The GLOBAL directive no longer is required to precede the definition of the symbol.
- Support private_extern as macho specific extension to the GLOBAL directive. See section 8.8.5.

- Updated UD0 encoding to match with the specification
- Added the --limit-x command line option to set execution limits. See section 2.1.31.
- Updated the Codeview version number to be aligned with MASM.
- Added the --keep-all command line option to preserve output files. See section 2.1.32.
- Added the --include command line option, an alias to -P (section 2.1.19).
- Added the --help command line option as an alias to -h (section 3.1).
- Added -W, -D, and -Q suffix aliases for RET instructions so the operand sizes of these instructions can be encoded without using o16, o32 or o64.

C.1.11 Version 2.13.03

- Added AVX and AVX512 VAES* and VPCLMULQDQ instructions.
- Fixed missing dwarf record in x32 ELF output format.

C.1.12 Version 2.13.02

- Fix false positive in testing of numeric overflows.
- Fix generation of PEXTRW instruction.
- Fix smartalign package which could trigger an error during optimization if the alignment code expanded too much due to optimization of the previous code.
- Fix a case where negative value in TIMES directive causes panic instead of an error.
- Always finalize . debug_abbrev section with a null in dwarf output format.
- Support debug flag in section attributes for macho output format. See section 8.8.1.
- Support up to 16 characters in section names for macho output format.
- Fix missing update of global BITS setting if SECTION directive specified a bit size using output format-specific extensions (e.g. USE32 for the obj output format.)
- Fix the incorrect generation of VEX-encoded instruction when static mode decorators are specified on scalar instructions, losing the decorators as they require EVEX encoding.
- Option -MW to quote dependency outputs according to Watcom Make conventions instead of POSIX Make conventions. See section 2.1.12.
- The obj output format now contains embedded dependency file information, unless disabled with %pragma obj nodepend. See section 8.4.9.
- Fix generation of dependency lists.
- Fix a number of null pointer reference and memory allocation errors.
- Always generate symbol-relative relocations for the macho64 output format; at least some versions of the XCode/LLVM linker fails for section-relative relocations.

C.1.13 Version 2.13.01

- Fix incorrect output for some types of FAR or SEG references in the obj output format, and possibly other 16-bit output formats.
- Fix the address in the list file for an instruction containing a TIMES directive.
- Fix error with TIMES used together with an instruction which can vary in size, e.g. JMP.
- Fix breakage on some uses of the DZ pseudo-op.

C.1.14 Version 2.13

- Support the official forms of the UDO and UD1 instructions.
- Allow self-segment-relative expressions in immediates and displacements, even when combined with an external or otherwise out-of-segment special symbol, e.g.:

```
extern foo
mov eax,[foo - $ + ebx] ; Now legal
```

- Handle a 64-bit origin in NDISASM.
- NASM can now generate sparse output files for relevant output formats, if the underlying operating system supports them.
- The macho object format now supports the subsections_via_symbols and no_dead_strip directives, see section 8.8.4.
- The macho object format now supports the no_dead_strip, live_support and strip_static_syms section flags, see section 8.8.1.
- The macho object format now supports the dwarf debugging format, as required by newer toolchains.
- All warnings can now be suppressed if desired; warnings not otherwise part of any warning class are now considered its own warning class called other (e.g. -w-other). Furthermore, warning-as-error can now be controlled on a per warning class basis, using the syntax -w+error=warning-class and its equivalent for all other warning control options. See section 2.1.26 for the command-line options and warning classes and section 7.13 for the [WARNING] directive.
- Fix a number of bugs related to AVX-512 decorators.
- Significant improvements to building NASM with Microsoft Visual Studio via Mkfiles/msvc.mak. It is now possible to build the full Windows installer binary as long as the necessary prerequisites are installed; see Mkfiles/README
- To build NASM with custom modifications (table changes) or from the git tree now requires Perl 5.8 at the very minimum, quite possibly a higher version (Perl 5.24.1 tested.) There is no requirement to have Perl on your system at all if all you want to do is build unmodified NASM from source archives.
- Fix the {z} decorator on AVX-512 VMOVDQ* instructions.
- Add new warnings for certain dangerous constructs which never ought to have been allowed. In particular, the RESB family of instructions should have been taking a critical expression all along.
- Fix the EVEX (AVX-512) versions of the VPBROADCAST, VPEXTR, and VPINSR instructions.
- Support contracted forms of additional instructions. As a general rule, if an instruction has a non-destructive source immediately after a destination register that isn't used as an input, NASM supports omitting that source register, using the destination register as that value. This among other things makes it easier to convert SSE code to the equivalent AVX code:

```
addps xmm1,xmm0 ; SSE instruction vaddps ymm1,ymm0,ymm0 ; AVX official long form vaddps ymm1,ymm0 ; AVX contracted form
```

- Fix Codeview malformed compiler version record.
- Add the CLWB and PCOMMIT instructions. Note that the PCOMMIT instruction has been deprecated and will never be included in a shipping product; it is included for completeness only.
- Add the %pragma preprocessor directive for soft-error directives.
- Add the RDPID instruction.

C.1.15 Version 2.12.02

- Fix preprocessor errors, especially %error and %warning, inside %if statements.
- Fix relative relocations in 32-bit Mach-O.
- More Codeview debug format fixes.
- If the MASM PTR keyword is encountered, issue a warning. This is much more likely to indicate a MASM-ism encountered in NASM than it is a valid label. This warning can be suppressed with -w-ptr, the [warning] directive (see section 2.1.26) or by the macro definition %idefine ptr \$%? (see section 4.1.5).
- When an error or a warning comes from the expansion of a multi-line macro, display the file and line numbers for the expanded macros. Macros defined with .nolist do not get displayed.
- Add macros ilog2fw() and ilog2cw() to the ifunc macro package. See section 6.4.1.

C.1.16 Version 2.12.01

- Portability fixes for some platforms.
- Fix error when not specifying a list file.
- Correct the handling of macro-local labels in the Codeview debugging format.
- Add CLZERO, MONITORX and MWAITX instructions.

C.1.17 Version 2.12

- Major fixes to the macho backend (section 8.8); earlier versions would produce invalid symbols and relocations on a regular basis.
- Support for thread-local storage in Mach-O.
- Support for arbitrary sections in Mach-O.
- Fix wrong negative size treated as a big positive value passed into backend causing NASM to crash.
- Fix handling of zero-extending unsigned relocations, we have been printing wrong message and forgot to assign segment with predefined value before passing it into output format.
- Fix potential write of oversized (with size greater than allowed in output format) relative relocations.
- Portability fixes for building NASM with the LLVM compiler.
- Add support of Codeview version 8 (cv8) debug format for win32 and win64 formats in the COFF backend, see section 8.5.3.
- Allow 64-bit outputs in 16/32-bit only backends. Unsigned 64-bit relocations are zero-extended from 32-bits with a warning (suppressible via -w-zext-reloc); signed 64-bit relocations are an error.
- Line numbers in list files now correspond to the lines in the source files, instead of simply being sequential.
- There is now an official 64-bit (x64 a.k.a. x86-64) build for Windows.

C.1.18 Version 2.11.09

- Fix potential stack overwrite in macho32 backend.
- Fix relocation records in macho64 backend.
- Fix symbol lookup computation in macho64 backend.
- Adjust .symtab and .rela.text sections alignments to 8 bytes in elf64 backed.

• Fix section length computation in bin backend which leaded in incorrect relocation records.

C.1.19 Version 2.11.08

- Fix section length computation in bin backend which leaded in incorrect relocation records.
- Add a warning for numeric preprocessor definitions passed via command line which might have unexpected results otherwise.
- Add ability to specify a module name record in rdoff linker with -mn option.
- Increase label length capacity up to 256 bytes in rdoff backend for FreePascal sake, which tends to generate very long labels for procedures.
- Fix segmentation failure when rip addressing is used in macho64 backend.
- Fix access on out of memory when handling strings with a single grave. We have sixed similar problem in previous release but not all cases were covered.
- Fix NULL dereference in disassembled on BND instruction.

C.1.20 Version 2.11.07

- Fix 256 bit VMOVNTPS instruction.
- Fix -MD option handling, which was rather broken in previous release changing command line api.
- Fix access to unitialized space when handling strings with a single grave.
- Fix nil dereference in handling memory reference parsing.

C.1.21 Version 2.11.06

- Update AVX512 instructions based on the Extension Reference (319433-021 Sept 2014).
- Fix the behavior of -MF and -MD options (Bugzilla 3392280)
- Updated Win32 Makefile to fix issue with build

C.1.22 Version 2.11.05

- Add --v as an alias for -v (see section 2.1.27), for command-line compatibility with Yasm.
- Fix a bug introduced in 2.11.03 whereby certain instructions would contain multiple REX prefixes, and thus be corrupt.

C.1.23 Version 2.11.04

• Removed an invalid error checking code. Sometimes a memref only with a displacement can also set an evex flag. For example:

```
vmovdqu32 [0xabcd]{k1}, zmm0
```

• Fixed a bug in disassembler that EVEX.L'L vector length was not matched when EVEX.b was set because it was simply considered as EVEC.RC. Separated EVEX.L'L case from EVEX.RC which is ignored in matching.

C.1.24 Version 2.11.03

• Fix a bug there REX prefixes were missing on instructions inside a TIMES statement.

C.1.25 Version 2.11.02

- Add the XSAVEC, XSAVES and XRSTORS family instructions.
- Add the CLFLUSHOPT instruction.

C.1.26 Version 2.11.01

• Allow instructions which implicitly uses XMM0 (VBLENDVPD, VBLENDVPS, PBLENDVB and SHA256RNDS2) to be specified without an explicit xmm0 on the assembly line. In other words, the following two lines produce the same output:

• In the ELF backends, don't crash the assembler if section align is specified without a value.

C.1.27 Version 2.11

- Add support for the Intel AVX-512 instruction set:
- 16 new, 512-bit SIMD registers. Total 32 (ZMM0 ~ ZMM31)
- 8 new opmask registers (K0 ~ K7). One of 7 registers (K1 ~ K7) can be used as an opmask for conditional execution.
- A new EVEX encoding prefix. EVEX is based on VEX and provides more capabilities: opmasks, broadcasting, embedded rounding and compressed displacements.

- Add support for zword (512 bits), Dz and RESZ.
- Add support for the MPX and SHA instruction sets.
- Better handling of section redefinition.
- Generate manpages when running 'make dist'.
- Handle all token chains in mmacro params range.
- Support split [base,index] effective address:

```
mov eax,[eax+8,ecx*4] ; eax=base, ecx=index, 4=scale, 8=disp
```

This is expected to be most useful for the MPX instructions.

- Support BND prefix for branch instructions (for MPX).
- The DEFAULT directive can now take BND and NOBND options to indicate whether all relevant branches should be getting BND prefixes. This is expected to be the normal for use in MPX code.
- Add {evex}, {vex3} and {vex2} instruction prefixes to have NASM encode the corresponding instruction, if possible, with an EVEX, 3-byte VEX, or 2-byte VEX prefix, respectively.
- Support for section names longer than 8 bytes in Win32/Win64 COFF.
- The NOSPLIT directive by itself no longer forces a single register to become an index register, unless it has an explicit multiplier.

```
mov eax,[nosplit eax] ; eax as base register
mov eax,[nosplit eax*1] ; eax as index register
```

C.1.28 Version 2.10.09

· Pregenerate man pages.

C.1.29 Version 2.10.08

- Fix VMOVNTDOA, MOVNTDOA and MOVLPD instructions.
- Fix collision for VGATHERQPS, VPGATHERQD instructions.
- Fix VPMOVSXBQ, VGATHERQPD, VSPLLW instructions.
- Add a bunch of AMD TBM instructions.
- Fix potential stack overwrite in numbers conversion.
- Allow byte size in PREFETCHTx instructions.
- Make manual pages up to date.
- Make F3 and F2 SSE prefixes to override 66.
- Support of AMD SVM instructions in 32 bit mode.
- Fix near offsets code generation for JMP, CALL instrictions in long mode.
- Fix preprocessor parse regression when id is expanding to a whitespace.

C.1.30 Version 2.10.07

• Fix line continuation parsing being broken in previous version.

C.1.31 Version 2.10.06

- Always quote the dependency source names when using the automatic dependency generation options.
- If no dependency target name is specified via the -MT or -MQ options, quote the default output name.
- Fix assembly of shift operations in CPU 8086 mode.
- Fix incorrect generation of explicit immediate byte for shift by 1 under certain circumstances.
- Fix assembly of the VPCMPGTQ instruction.
- Fix RIP-relative relocations in the macho64 backend.

C.1.32 Version 2.10.05

Add the CLAC and STAC instructions.

C.1.33 Version 2.10.04

- Add back the inadvertently deleted 256-bit version of the VORPD instruction.
- Correct disassembly of instructions starting with byte 82 hex.
- Fix corner cases in token pasting, for example:

```
%define N 1e%++%+ 5
dd N, 1e+5
```

C.1.34 Version 2.10.03

• Correct the assembly of the instruction:

```
XRELEASE MOV [absolute],AL
```

Previous versions would incorrectly generate F3 A2 for this instruction and issue a warning; correct behavior is to emit F3 88 05.

C.1.35 Version 2.10.02

- Add the ifunc macro package with integer functions, currently only integer logarithms. See section 6.4.
- Add the RDSEED, ADCX and ADOX instructions.

C.1.36 Version 2.10.01

• Add missing VPMOVMSKB instruction with reg32, ymmreg operands.

C.1.37 Version 2.10

• When optimization is enabled, mov r64, imm now optimizes to the shortest form possible between:

```
mov r32,imm32 ; 5 bytes
mov r64,imm32 ; 7 bytes
mov r64,imm64 ; 10 bytes
```

To force a specific form, use the STRICT keyword, see section 3.7.

- Add support for the Intel AVX2 instruction set.
- Add support for Bit Manipulation Instructions 1 and 2.
- Add support for Intel Transactional Synchronization Extensions (TSX).
- Add support for x32 ELF (32-bit ELF with the CPU in 64-bit mode.) See section 8.9.
- Add support for bigendian UTF-16 and UTF-32. See section 3.4.5.

C.1.38 Version 2.09.10

• Fix up NSIS script to protect uninstaller against registry keys absence or corruption. It brings in a few additional questions to a user during deinstallation procedure but still it is better than unpredictable file removal.

C.1.39 Version 2.09.09

- Fix initialization of section attributes of bin output format.
- Fix mach64 output format bug that crashes NASM due to NULL symbols.

C.1.40 Version 2.09.08

• Fix __OUTPUT_FORMAT__ assignment when output driver alias is used. For example when -f elf is used __OUTPUT_FORMAT__ must be set to elf, if -f elf32 is used __OUTPUT_FORMAT__ must be assigned accordingly, i.e. to elf32. The rule applies to all output driver aliases. See section 5.4.

C.1.41 Version 2.09.07

- Fix attempts to close same file several times when -a option is used.
- Fixes for VEXTRACTF128, VMASKMOVPS encoding.

C.1.42 Version 2.09.06

• Fix missed section attribute initialization in bin output target.

C.1.43 Version 2.09.05

- Fix arguments encoding for VPEXTRW instruction.
- Remove invalid form of VPEXTRW instruction.

Add VLDDQU as alias for VLDQQU to match specification.

C.1.44 Version 2.09.04

- Fix incorrect labels offset for VEX intructions.
- Eliminate bogus warning on implicit operand size override.
- %if term could not handle 64 bit numbers.
- The COFF backend was limiting relocations number to 16 bits even if in real there were a way more relocations.

C.1.45 Version 2.09.03

- Print %macro name inside %rep blocks on error.
- Fix preprocessor expansion behaviour. It happened sometime too early and sometime simply wrong, Move behaviour back to the origins (down to NASM 2.05.01).
- Fix unitialized data dereference on OMF output format.
- Issue warning on unterminated %{ construct.
- Fix for documentation typo.

C.1.46 Version 2.09.02

- Fix reversed tokens when %deftok produces more than one output token.
- Fix segmentation fault on disassembling some VEX instructions.
- Missing %endif did not always cause error.
- Fix typo in documentation.
- Compound context local preprocessor single line macro identifiers were not expanded early enough and as result lead to unresolved symbols.

C.1.47 Version 2.09.01

- Fix NULL dereference on missed %deftok second parameter.
- Fix NULL dereference on invalid %substr parameters.

C.1.48 Version 2.09

- Fixed assignment the magnitude of <code>%rep</code> counter. It is limited to 62 bits now.
- Fixed NULL dereference if argument of %strlen resolves to whitespace. For example if nonexistent macro parameter is used.
- %ifenv, %elifenv, %ifnenv, and %elifnenv directives introduced. See section 4.4.9.
- Fixed NULL dereference if environment variable is missed.
- Updates of new AVX v7 Intel instructions.
- PUSH imm32 is now officially documented.
- Fix for encoding the LFS, LGS and LSS in 64-bit mode.
- Fixes for compatibility with OpenWatcom compiler and DOS 8.3 file format limitation.
- Macros parameters range expansion introduced. See section 4.3.4.
- Backward compatibility on expanging of local sigle macros restored.
- 8 bit relocations for elf and bin output formats are introduced.

- Short intersegment jumps are permitted now.
- An alignment more than 64 bytes are allowed for win32, win64 output formats.
- SECTALIGN directive introduced. See section 5.10.2.
- nojmp option introduced in smartalign package. See section 6.2.
- Short aliases win, elf and macho for output formats are introduced. Each stands for win32, elf32 and macho32 accordingly.
- Faster handling of missing directives implemented.
- Various small improvements in documentation.
- No hang anymore if unable to open malloc.log file.
- The environments without vsnprintf function are able to build nasm again.
- AMD LWP instructions updated.
- Tighten EA checks. We warn a user if there overflow in EA addressing.
- Make -0x the default optimization level. For the legacy behavior, specify -00 explicitly. See section 2.1.24.
- Environment variables read with %! or tested with %i fenv can now contain non-identifier characters if surrounded by quotes. See section 4.11.2.
- Add a new standard macro package %use fp for floating-point convenience macros. See section 6.3.

C.1.49 Version 2.08.02

• Fix crash under certain circumstances when using the %+ operator.

C.1.50 Version 2.08.01

• Fix the %use statement, which was broken in 2.08.

C.1.51 Version 2.08

- A number of enhancements/fixes in macros area.
- Support for converting strings to tokens. See section 4.1.10.
- Fuzzy operand size logic introduced.
- Fix COFF stack overrun on too long export identifiers.
- Fix Macho-O alignment bug.
- Fix crashes with -fwin32 on file with many exports.
- Fix stack overrun for too long [DEBUG id].
- Fix incorrect sbyte usage in IMUL (hit only if optimization flag passed).
- Append ending token for .stabs records in the ELF output format.
- New NSIS script which uses ModernUI and MultiUser approach.
- Visual Studio 2008 NASM integration (rules file).
- Warn a user if a constant is too long (and as result will be stripped).
- The obsoleted pre-XOP AMD SSE5 instruction set which was never actualized was removed.
- Fix stack overrun on too long error file name passed from the command line.

- Bind symbols to the .text section by default (ie in case if SECTION directive was omitted) in the ELF output format.
- Fix sync points array index wrapping.
- A few fixes for FMA4 and XOP instruction templates.
- Add AMD Lightweight Profiling (LWP) instructions.
- Fix the offset for %arg in 64-bit mode.
- An undefined local macro (%\$) no longer matches a global macro with the same name.
- Fix NULL dereference on too long local labels.

C.1.52 Version 2.07

- NASM is now under the 2-clause BSD license. See section 1.1.1.
- Fix the section type for the .strtab section in the elf64 output format.
- Fix the handling of COMMON directives in the obj output format.
- New ith and srec output formats; these are variants of the bin output format which output Intel hex and Motorola S-records, respectively. See section 8.2 and section 8.3.
- rdf2ihx replaced with an enhanced rdf2bin, which can output binary, COM, Intel hex or Motorola S-records.
- The Windows installer now puts the NASM directory first in the PATH of the "NASM Shell".
- Revert the early expansion behavior of %+ to pre-2.06 behavior: %+ is only expanded late.
- Yet another Mach-O alignment fix.
- Don't delete the list file on errors. Also, include error and warning information in the list file.
- Support for 64-bit Mach-O output, see section 8.8.
- Fix assert failure on certain operations that involve strings with high-bit bytes.

C.1.53 Version 2.06

- This release is dedicated to the memory of Charles A. Crayne, long time NASM developer as well as moderator of comp.lang.asm.x86 and author of the book *Serious Assembler*. We miss you, Chuck.
- Support for indirect macro expansion (%[...]). See section 4.1.3.
- %pop can now take an argument, see section 4.7.1.
- The argument to <code>%use</code> is no longer macro-expanded. Use <code>%[...]</code> if macro expansion is desired.
- Support for thread-local storage in ELF32 and ELF64. See section 8.9.4.
- Fix crash on %i fmacro without an argument.
- Correct the arguments to the POPCNT instruction.
- Fix section alignment in the Mach-O format.
- Update AVX support to version 5 of the Intel specification.
- Fix the handling of accesses to context-local macros from higher levels in the context stack.
- Treat WAIT as a prefix rather than as an instruction, thereby allowing constructs like 016 FSAVE to work correctly.
- Support for structures with a non-zero base offset. See section 5.9.1.

- Correctly handle preprocessor token concatenation (see section 4.3.9) involving floating-point numbers.
- The PINSR series of instructions have been corrected and rationalized.
- Removed AMD SSE5, replaced with the new XOP/FMA4/CVT16 (rev 3.03) spec.
- The ELF backends no longer automatically generate a .comment section.
- Add additional "well-known" ELF sections with default attributes. See section 8.9.2.

C.1.54 Version 2.05.01

• Fix the -w/-w option parsing, which was broken in NASM 2.05.

C.1.55 Version 2.05

- Fix redundant REX.W prefix on JMP reg64.
- Make the behaviour of -00 match NASM 0.98 legacy behavior. See section 2.1.24.
- -w-user can be used to suppress the output of %warning directives. See section 2.1.26.
- Fix bug where ALIGN would issue a full alignment datum instead of zero bytes.
- Fix offsets in list files.
- Fix %include inside multi-line macros or loops.
- Fix error where NASM would generate a spurious warning on valid optimizations of immediate values.
- Fix arguments to a number of the CVT SSE instructions.
- Fix RIP-relative offsets when the instruction carries an immediate.
- Massive overhaul of the ELF64 backend for spec compliance.
- Fix the Geode PFRCPV and PFRSORTV instruction.
- Fix the SSE 4.2 cRC32 instruction.

C.1.56 Version 2.04

- Sanitize macro handing in the %error directive.
- New %warning directive to issue user-controlled warnings.
- %error directives are now deferred to the final assembly phase.
- New %fatal directive to immediately terminate assembly.
- New %strcat directive to join quoted strings together.
- New %use macro directive to support standard macro directives. See section 4.6.4.
- Excess default parameters to %macro now issues a warning by default. See section 4.3.
- Fix %ifn and %elifn.
- Fix nested %else clauses.
- Correct the handling of nested %reps.
- New %unmacro directive to undeclare a multi-line macro. See section 4.3.12.
- Builtin macro __PASS__ which expands to the current assembly pass. See section 5.8.
- __utf16__ and __utf32__ operators to generate UTF-16 and UTF-32 strings. See section 3.4.5.

- Fix bug in case-insensitive matching when compiled on platforms that don't use the configure script. Of the official release binaries, that only affected the OS/2 binary.
- Support for x87 packed BCD constants. See section 3.4.7.
- Correct the LTR and SLDT instructions in 64-bit mode.
- Fix unnecessary REX.W prefix on indirect jumps in 64-bit mode.
- Add AVX versions of the AES instructions (VAES...).
- Fix the 256-bit FMA instructions.
- Add 256-bit AVX stores per the latest AVX spec.
- VIA XCRYPT instructions can now be written either with or without REP, apparently different versions of the VIA spec wrote them differently.
- Add missing 64-bit MOVNTI instruction.
- Fix the operand size of VMREAD and VMWRITE.
- Numerous bug fixes, especially to the AES, AVX and VTX instructions.
- The optimizer now always runs until it converges. It also runs even when disabled, but doesn't optimize. This allows most forward references to be resolved properly.
- %push no longer needs a context identifier; omitting the context identifier results in an anonymous context.

C.1.57 Version 2.03.01

- Fix buffer overflow in the listing module.
- Fix the handling of hexadecimal escape codes in '...' strings.
- The Postscript/PDF documentation has been reformatted.
- The -F option now implies -g.

C.1.58 Version 2.03

- Add support for Intel AVX, CLMUL and FMA instructions, including YMM registers.
- dy, resy and yword for 32-byte operands.
- Fix some SSE5 instructions.
- Intel INVEPT, INVVPID and MOVBE instructions.
- Fix checking for critical expressions when the optimizer is enabled.
- Support the DWARF debugging format for ELF targets.
- Fix optimizations of signed bytes.
- Fix operation on bigendian machines.
- Fix buffer overflow in the preprocessor.
- SAFESEH support for Win32, IMAGEREL for Win64 (SEH).
- %? and %?? to refer to the name of a macro itself. In particular, %idefine keyword \$%? can be used to make a keyword "disappear".
- New options for dependency generation: -MD, -MF, -MP, -MT, -MQ.
- New preprocessor directives %pathsearch and %depend; INCBIN reimplemented as a macro.

- %include now resolves macros in a sane manner.
- %substr can now be used to get other than one-character substrings.
- New type of character/string constants, using backquotes ('...'), which support C-style escape sequences.
- %defstr and %idefstr to stringize macro definitions before creation.
- Fix forward references used in EQU statements.

C.1.59 Version 2.02

- Additional fixes for MMX operands with explicit qword, as well as (hopefully) SSE operands with oword.
- Fix handling of truncated strings with DO.
- Fix segfaults due to memory overwrites when floating-point constants were used.
- Fix segfaults due to missing include files.
- Fix OpenWatcom Makefiles for DOS and OS/2.
- Add autogenerated instruction list back into the documentation.
- ELF: Fix segfault when generating stabs, and no symbols have been defined.
- ELF: Experimental support for DWARF debugging information.
- New compile date and time standard macros.
- %ifnum now returns true for negative numbers.
- New %iftoken test for a single token.
- New %ifempty test for empty expansion.
- Add support for the XSAVE instruction group.
- Makefile for Netware/gcc.
- Fix issue with some warnings getting emitted way too many times.
- Autogenerated instruction list added to the documentation.

C.1.60 Version 2.01

- Fix the handling of MMX registers with explicit qword tags on memory (broken in 2.00 due to 64-bit changes.)
- Fix the PREFETCH instructions.
- Fix the documentation.
- Fix debugging info when using -f elf (backwards compatibility alias for -f elf32).
- Man pages for rdoff tools (from the Debian project.)
- ELF: handle large numbers of sections.
- Fix corrupt output when the optimizer runs out of passes.

C.1.61 Version 2.00

- Added c99 data-type compliance.
- Added general x86-64 support.
- Added win64 (x86-64 COFF) output format.

- Added __BITS__ standard macro.
- Renamed the elf output format to elf32 for clarity.
- Added elf64 and macho (MacOS X) output formats.
- Added Numeric constants in dg directive.
- Added oword, do and reso pseudo operands.
- Allow underscores in numbers.
- Added 8-, 16- and 128-bit floating-point formats.
- Added binary, octal and hexadecimal floating-point.
- Correct the generation of floating-point constants.
- Added floating-point option control.
- Added Infinity and NaN floating point support.
- Added ELF Symbol Visibility support.
- Added setting OSABI value in ELF header directive.
- Added Generate Makefile Dependencies option.
- Added Unlimited Optimization Passes option.
- Added %IFN and %ELIFN support.
- Added Logical Negation Operator.
- Enhanced Stack Relative Preprocessor Directives.
- Enhanced ELF Debug Formats.
- Enhanced Send Errors to a File option.
- Added SSSE3, SSE4.1, SSE4.2, SSE5 support.
- Added a large number of additional instructions.
- Significant performance improvements.
- -w+warning and -w-warning can now be written as -Wwarning and -Wno-warning, respectively. See section 2.1.26.
- Add -w+error to treat warnings as errors. See section 2.1.26.
- Add -w+all and -w-all to enable or disable all suppressible warnings. See section 2.1.26.

C.2 NASM 0.98 Series

The 0.98 series was the production versions of NASM from 1999 to 2007.

C.2.1 Version 0.98.39

- · fix buffer overflow
- fix outas86's .bss handling
- "make spotless" no longer deletes config.h.in.
- %(el)if(n)idn insensitivity to string quotes difference (#809300).
- (nasm.c)__OUTPUT_FORMAT__ changed to string value instead of symbol.

C.2.2 Version 0.98.38

- Add Makefile for 16-bit DOS binaries under OpenWatcom, and modify mkdep.pl to be able to generate completely pathless dependencies, as required by OpenWatcom wmake (it supports path searches, but not explicit paths.)
- Fix the STR instruction.
- Fix the ELF output format, which was broken under certain circumstances due to the addition of stabs support.
- Quick-fix Borland format debug-info for -f obj
- Fix for %rep with no arguments (#560568)
- Fix concatenation of preprocessor function call (#794686)
- Fix long label causes coredump (#677841)
- Use autoheader as well as autoconf to keep configure from generating ridiculously long command lines.
- Make sure that all of the formats which support debugging output actually will suppress debugging output when -g not specified.

C.2.3 Version 0.98.37

- Paths given in -I switch searched for incbin-ed as well as %include-ed files.
- Added stabs debugging for the ELF output format, patch from Martin Wawro.
- Fix output/outbin.c to allow origin > 80000000h.
- Make -u switch work.
- Fix the use of relative offsets with explicit prefixes, e.g. a32 loop foo.
- Remove backslash().
- Fix the SMSW and SLDT instructions.
- -02 and -03 are no longer aliases for -010 and -015. If you mean the latter, please say so!:)

C.2.4 Version 0.98.36

- Update rdoff librarian/archiver common rec docs!
- Fix signed/unsigned problems.
- Fix JMP FAR label and CALL FAR label.
- Add new multisection support map files fix align bug
- Fix sysexit, movhps/movlps reg,reg bugs in insns.dat
- Q or 0 suffixes indicate octal
- Support Prescott new instructions (PNI).
- Cyrix XSTORE instruction.

C.2.5 Version 0.98.35

- Fix build failure on 16-bit DOS (Makefile.bc3 workaround for compiler bug.)
- Fix dependencies and compiler warnings.
- Add "const" in a number of places.

- Add –X option to specify error reporting format (use –Xvc to integrate with Microsoft Visual Studio.)
- Minor changes for code legibility.
- Drop use of tmpnam() in rdoff (security fix.)

C.2.6 Version 0.98.34

- Correct additional address-size vs. operand-size confusions.
- Generate dependencies for all Makefiles automatically.
- Add support for unimplemented (but theoretically available) registers such as tr0 and cr5. Segment registers 6 and 7 are called segr6 and segr7 for the operations which they can be represented.
- Correct some disassembler bugs related to redundant address-size prefixes. Some work still remains in this area.
- Correctly generate an error for things like "SEG eax".
- Add the JMPE instruction, enabled by "CPU IA64".
- Correct compilation on newer gcc/glibc platforms.
- Issue an error on things like "jmp far eax".

C.2.7 Version 0.98.33

- New __NASM_PATCHLEVEL__ and __NASM_VERSION_ID__ standard macros to round out the
 version-query macros. version.pl now understands X.YYplWW or X.YY.ZZplWW as a version number,
 equivalent to X.YY.ZZ.WW (or X.YY.0.WW, as appropriate).
- New keyword "strict" to disable the optimization of specific operands.
- Fix the handing of size overrides with JMP instructions (instructions such as "imp dword foo".)
- Fix the handling of "ABSOLUTE label", where "label" points into a relocatable segment.
- Fix OBJ output format with lots of externs.
- More documentation updates.
- Add –Ov option to get verbose information about optimizations.
- Undo a braindead change which broke %elif directives.
- Makefile updates.

C.2.8 Version 0.98.32

- Fix NASM crashing when %macro directives were left unterminated.
- · Lots of documentation updates.
- Complete rewrite of the PostScript/PDF documentation generator.
- The MS Visual C++ Makefile was updated and corrected.
- Recognize .rodata as a standard section name in ELF.
- Fix some obsolete Perl4-isms in Perl scripts.
- Fix configure.in to work with autoconf 2.5x.
- Fix a couple of "make cleaner" misses.
- Make the normal "./configure && make" work with Cygwin.

C.2.9 Version 0.98.31

- Correctly build in a separate object directory again.
- Derive all references to the version number from the version file.
- New standard macros __NASM_SUBMINOR__ and __NASM_VER__ macros.
- Lots of Makefile updates and bug fixes.
- New %ifmacro directive to test for multiline macros.
- Documentation updates.
- Fixes for 16-bit OBJ format output.
- Changed the NASM environment variable to NASMENV.

C.2.10 Version 0.98.30

- Changed doc files a lot: completely removed old READMExx and Wishlist files, incorporating all information in CHANGES and TODO.
- I waited a long time to rename zoutieee.c to (original) outieee.c
- moved all output modules to output/ subdirectory.
- Added 'make strip' target to strip debug info from nasm & ndisasm.
- Added INSTALL file with installation instructions.
- Added -v option description to nasm man.
- Added dist makefile target to produce source distributions.
- 16-bit support for ELF output format (GNU extension, but useful.)

C.2.11 Version 0.98.28

• Fastcooked this for Debian's Woody release: Frank applied the INCBIN bug patch to 0.98.25alt and called it 0.98.28 to not confuse poor little apt-get.

C.2.12 Version 0.98.26

• Reorganised files even better from 0.98.25alt

C.2.13 Version 0.98.25alt

- Prettified the source tree. Moved files to more reasonable places.
- Added findleak.pl script to misc/ directory.
- Attempted to fix doc.

C.2.14 Version 0.98.25

- Line continuation character \.
- Docs inadvertantly reverted "dos packaging".

C.2.15 Version 0.98.24p1

• FIXME: Someone, document this please.

C.2.16 Version 0.98.24

• Documentation – Ndisasm doc added to Nasm.doc.

C.2.17 Version 0.98.23

- Attempted to remove rdoff version1
- Lino Mastrodomenico's patches to preproc.c (%\$\$ bug?).

C.2.18 Version 0.98.22

• Update rdoff2 – attempt to remove v1.

C.2.19 Version 0.98.21

• Optimization fixes.

C.2.20 Version 0.98.20

• Optimization fixes.

C.2.21 Version 0.98.19

• H. J. Lu's patch back out.

C.2.22 Version 0.98.18

• Added ".rdata" to "-f win32".

C.2.23 Version 0.98.17

• H. J. Lu's "bogus elf" patch. (Red Hat problem?)

C.2.24 Version 0.98.16

• Fix whitespace before "[section ..." bug.

C.2.25 Version 0.98.15

- Rdoff changes (?).
- Fix fixes to memory leaks.

C.2.26 Version 0.98.14

• Fix memory leaks.

C.2.27 Version 0.98.13

• There was no 0.98.13

C.2.28 Version 0.98.12

- Update optimization (new function of "-O1")
- Changes to test/bintest.asm (?).

C.2.29 Version 0.98.11

- Optimization changes.
- · Ndisasm fixed.

C.2.30 Version 0.98.10

• There was no 0.98.10

C.2.31 Version 0.98.09

• Add multiple sections support to "-f bin".

- Changed GLOBAL_TEMP_BASE in outelf.c from 6 to 15.
- Add "-v" as an alias to the "-r" switch.
- Remove "#ifdef" from Tasm compatibility options.
- Remove redundant size-overrides on "mov ds, ex", etc.
- Fixes to SSE2, other insns.dat (?).
- Enable uppercase "I" and "P" switches.
- · Case insinsitive "seg" and "wrt".
- Update install.sh (?).
- · Allocate tokens in blocks.
- Improve "invalid effective address" messages.

C.2.32 Version 0.98.08

- Add "%strlen" and "%substr" macro operators
- Fixed broken c16.mac.
- Unterminated string error reported.
- · Fixed bugs as per 0.98bf

C.2.33 Version 0.98.09b with John Coffman patches released 28-Oct-2001

Changes from 0.98.07 release to 98.09b as of 28-Oct-2001

- More closely compatible with 0.98 when -O0 is implied or specified. Not strictly identical, since backward branches in range of short offsets are recognized, and signed byte values with no explicit size specification will be assembled as a single byte.
- More forgiving with the PUSH instruction. 0.98 requires a size to be specified always. 0.98.09b will imply the size from the current BITS setting (16 or 32).
- Changed definition of the optimization flag:
 - -00 strict two-pass assembly, JMP and Jcc are handled more like 0.98, except that backward JMPs are short, if possible.
 - -01 strict two-pass assembly, but forward branches are assembled with code guaranteed to reach; may produce larger code than -00, but will produce successful assembly more often if branch offset sizes are not specified.
 - -02 multi-pass optimization, minimize branch offsets; also will minimize signed immediate bytes, overriding size specification.
 - -03 like -02, but more passes taken, if needed

C.2.34 Version 0.98.07 released 01/28/01

- Added Stepane Denis' SSE2 instructions to a *working* version of the code some earlier versions were based on broken code sorry 'bout that. version "0.98.07"
- · Cosmetic modifications to nasm.c, nasm.h, AUTHORS, MODIFIED

C.2.35 Version 0.98.06f released 01/18/01

- Add "metalbrain"s jecxz bug fix in insns.dat
- Alter nasmdoc.src to match version "0.98.06f"

C.2.36 Version 0.98.06e released 01/09/01

- Removed the "outforms.h" file it appears to be someone's old backup of "outform.h". version "0.98.06e"
- fbk finally added the fix for the "multiple %includes bug", known since 7/27/99 reported originally (?) and sent to us by Austin Lunnen he reports that John Fine had a fix within the day. Here it is...
- Nelson Rush resigns from the group. Big thanks to Nelson for his leadership and enthusiasm in getting these changes incorporated into Nasm!
- fbk [list +], [list –] directives ineptly implemented, should be re-written or removed, perhaps.
- Brian Raiter / fbk "elfso bug" fix applied to aoutb format as well testing might be desirable...
- James Seter –postfix, –prefix command line switches.
- Yuri Zaporozhets rdoff utility changes.

C.2.37 Version 0.98p1

- GAS-like palign (Panos Minos)
- FIXME: Someone, fill this in with details

C.2.38 Version 0.98bf (bug-fixed)

• Fixed – elf and aoutb bug – shared libraries – multiple "%include" bug in "-f obj" – jcxz, jecxz bug – unrecognized option bug in ndisasm

C.2.39 Version 0.98.03 with John Coffman's changes released 27-Jul-2000

- Added signed byte optimizations for the 0x81/0x83 class of instructions: ADC, ADD, AND, CMP, OR, SBB, SUB, XOR: when used as 'ADD reg16,imm' or 'ADD reg32,imm.' Also optimization of signed byte form of 'PUSH imm' and 'IMUL reg,imm'/IMUL reg,reg,imm.' No size specification is needed.
- Added multi-pass JMP and Jcc offset optimization. Offsets on forward references will preferentially use the short form, without the need to code a specific size (short or near) for the branch. Added instructions for 'Jcc label' to use the form 'Jnotcc \$+3/JMP label', in cases where a short offset is out of bounds. If compiling for a 386 or higher CPU, then the 386 form of Jcc will be used instead.
 - This feature is controlled by a new command-line switch: "O", (upper case letter O). "-O0" reverts the assembler to no extra optimization passes, "-O1" allows up to 5 extra passes, and "-O2" (default), allows up to 10 extra optimization passes.
- Added a new directive: 'cpu XXX', where XXX is any of: 8086, 186, 286, 386, 486, 586, pentium, 686, PPro, P2, P3 or Katmai. All are case insensitive. All instructions will be selected only if they apply to the selected cpu or lower. Corrected a couple of bugs in cpu-dependence in 'insns.dat'.
- Added to 'standard.mac', the "use16" and "use32" forms of the "bits 16/32" directive. This is nothing new, just conforms to a lot of other assemblers. (minor)
- Changed label allocation from 320/32 (10000 labels @ 200K+) to 32/37 (1000 labels); makes running under DOS much easier. Since additional label space is allocated dynamically, this should have no effect on large programs with lots of labels. The 37 is a prime, believed to be better for hashing. (minor)

C.2.40 Version 0.98.03

"Integrated patchfile 0.98-0.98.01. I call this version 0.98.03 for historical reasons: 0.98.02 was trashed." --John Coffman <johninsd@san.rr.com>, 27-Jul-2000

- Kendall Bennett's SciTech MGL changes
- Note that you must define "TASM_COMPAT" at compile-time to get the Tasm Ideal Mode compatibility.
- All changes can be compiled in and out using the TASM_COMPAT macros, and when compiled without TASM_COMPAT defined we get the exact same binary as the unmodified 0.98 sources.
- standard.mac, macros.c: Added macros to ignore TASM directives before first include
- nasm.h: Added extern declaration for tasm_compatible_mode
- nasm.c: Added global variable tasm_compatible_mode
- Added command line switch for TASM compatible mode (-t)
- Changed version command line to reflect when compiled with TASM additions
- Added response file processing to allow all arguments on a single line (response file is @resp rather than –@resp for NASM format).
- labels.c: Changes islocal() macro to support TASM style @@local labels.
- Added islocalchar() macro to support TASM style @@local labels.
- parser.c: Added support for TASM style memory references (ie: mov [DWORD eax],10 rather than the NASM style mov DWORD [eax],10).
- preproc.c: Added new directives, %arg, %local, %stacksize to directives table
- Added support for TASM style directives without a leading % symbol.
- Integrated a block of changes from Andrew Zabolotny

 bit@eltech.ru:
- A new keyword %xdefine and its case-insensitive counterpart %ixdefine. They work almost the same way as %define and %idefine but expand the definition immediately, not on the invocation. Something like a cross between %define and %assign. The "x" suffix stands for "eXpand", so "xdefine" can be deciphered as "expand-and-define". Thus you can do things like this:

• Changed the place where the expansion of %\$name macros are expanded. Now they are converted into ..@ctxnum.name form when detokenizing, so there are no quirks as before when using %\$name arguments to macros, in macros etc. For example:

Now last line will be expanded into "hello" as expected. This also allows for lots of goodies, a good example are extended "proc" macros included in this archive.

Added a check for "cstk" in smacro_defined() before calling get_ctx() – this allows for things like:

```
%ifdef %$abc
%endif
```

to work without warnings even in no context.

- Added a check for "cstk" in %if*ctx and %elif*ctx directives this allows to use %ifctx without excessive warnings. If there is no active context, %ifctx goes through "false" branch.
- Removed "user error: " prefix with %error directive: it just clobbers the output and has absolutely no functionality. Besides, this allows to write macros that does not differ from built-in functions in any way.
- Added expansion of string that is output by %error directive. Now you can do things like:

```
%define hello(x) Hello, x!
%define %$name andy
%error "hello(%$name)"
```

Same happened with %include directive.

• Now all directives that expect an identifier will try to expand and concatenate everything without whitespaces in between before usage. For example, with "unfixed" nasm the commands

```
%define %$abc hello
%define __%$abc goodbye
__%$abc
```

would produce "incorrect" output: last line will expand to

```
hello goodbyehello
```

Not quite what you expected, eh? :-) The answer is that preprocessor treats the %define construct as if it would be

```
%define __ %$abc goodbye
```

(note the white space between __ and %\$abc). After my "fix" it will "correctly" expand into goodbye

as expected. Note that I use quotes around words "correct", "incorrect" etc because this is rather a feature not a bug; however current behaviour is more logical (and allows more advanced macro usage:-).

Same change was applied to: %push,%macro,%imacro,%define,%idefine,%xdefine,%ixdefine,%assign,%iassign,%undef

- A new directive [WARNING {+|-}warning-id] have been added. It works only if the assembly phase is enabled (i.e. it doesn't work with nasm -e).
- A new warning type: macro-selfref. By default this warning is disabled; when enabled NASM warns when a macro self-references itself; for example the following source:

will produce a warning, but if we remove the first line we won't see it anymore (which is The Right Thing To Do {tm} IMHO since C preprocessor eats such constructs without warnings at all).

- Added a "error" routine to preprocessor which always will set ERR_PASS1 bit in severity_code. This removes annoying repeated errors on first and second passes from preprocessor.
- Added the %+ operator in single-line macros for concatenating two identifiers. Usage example:

```
%define _myfunc _otherfunc
%define cextern(x) _ %+ x
cextern (myfunc)
```

After first expansion, third line will become "_myfunc". After this expansion is performed again so it becomes "_otherunc".

• Now if preprocessor is in a non-emitting state, no warning or error will be emitted. Example:

```
%if 1
    mov eax,ebx
%else
put anything you want between these two brackets,
    even macro-parameter references %1 or local
    labels %$zz or macro-local labels %%zz - no
    warning will be emitted.
%endif
```

 Context-local variables on expansion as a last resort are looked up in outer contexts. For example, the following piece:

will expand correctly the fourth line to [esp]; if we'll define another %\$a inside the "inner" context, it will take precedence over outer definition. However, this modification has been applied only to expand_smacro and not to smacro_define: as a consequence expansion looks in outer contexts, but %ifdef won't look in outer contexts.

This behaviour is needed because we don't want nested contexts to act on already defined local macros. Example:

```
%define %$arg1 [esp+4]
test eax,eax
if nz
    mov eax,%$arg1
endif
```

In this example the "if" mmacro enters into the "if" context, so %\$arg1 is not valid anymore inside "if". Of course it could be worked around by using explicitely %\$\$arg1 but this is ugly IMHO.

- Fixed memory leak in <code>%undef</code>. The origline wasn't freed before exiting on success.
- Fixed trap in preprocessor when line expanded to empty set of tokens. This happens, for example, in the following case:

```
#define SOMETHING SOMETHING
```

C.2.41 Version 0.98

All changes since NASM 0.98p3 have been produced by H. Peter Anvin <hpa@zytor.com>.

- The documentation comment delimiter is
- Allow EQU definitions to refer to external labels; reported by Pedro Gimeno.
- Re-enable support for RDOFF v1; reported by Pedro Gimeno.

• Updated License file per OK from Simon and Julian.

C.2.42 Version 0.98p9

- Update documentation (although the instruction set reference will have to wait; I don't want to hold up the 0.98 release for it.)
- Verified that the NASM implementation of the PEXTRW and PMOVMSKB instructions is correct. The encoding differs from what the Intel manuals document, but the Pentium III behaviour matches NASM, not the Intel manuals.
- Fix handling of implicit sizes in PSHUFW and PINSRW, reported by Stefan Hoffmeister.
- Resurrect the -s option, which was removed when changing the diagnostic output to stdout.

C.2.43 Version 0.98p8

- Fix for "DB" when NASM is running on a bigendian machine.
- Invoke insns.pl once for each output script, making Makefile.in legal for "make -j".
- Improve the Unix configure-based makefiles to make package creation easier.
- Included an RPM .spec file for building RPM (RedHat Package Manager) packages on Linux or Unix systems.
- Fix Makefile dependency problems.
- Change src/rdsrc.pl to include sectioning information in info output; required for install-info to work.
- Updated the RDOFF distribution to version 2 from Jules; minor massaging to make it compile in my environment.
- Split doc files that can be built by anyone with a Perl interpreter off into a separate archive.
- "Dress rehearsal" release!

C.2.44 Version 0.98p7

- Fixed opcodes with a third byte-sized immediate argument to not complain if given "byte" on the immediate.
- Allow %undef to remove single-line macros with arguments. This matches the behaviour of #undef in the C preprocessor.
- Allow –d, –u, –i and –p to be specified as –D, –U, –I and –P for compatibility with most C compilers and preprocessors. This allows Makefile options to be shared between cc and nasm, for example.
- · Minor cleanups.
- · Went through the list of Katmai instructions and hopefully fixed the (rather few) mistakes in it.
- (Hopefully) fixed a number of disassembler bugs related to ambiguous instructions (disambiguated by –p) and SSE instructions with REP.
- Fix for bug reported by Mark Junger: "call dword 0x12345678" should work and may add an OSP (affected CALL, JMP, Jcc).
- Fix for environments when "stderr" isn't a compile-time constant.

C.2.45 Version 0.98p6

• Took officially over coordination of the 0.98 release; so drop the p3.x notation. Skipped p4 and p5 to avoid confusion with John Fine's J4 and J5 releases.

- Update the documentation; however, it still doesn't include documentation for the various new instructions. I somehow wonder if it makes sense to have an instruction set reference in the assembler manual when Intel et al have PDF versions of their manuals online.
- Recognize "idt" or "centaur" for the -p option to ndisasm.
- Changed error messages back to stderr where they belong, but add an -E option to redirect them elsewhere (the DOS shell cannot redirect stderr.)
- -M option to generate Makefile dependencies (based on code from Alex Verstak.)
- %undef preprocessor directive, and –u option, that undefines a single-line macro.
- OS/2 Makefile (Mkfiles/Makefile.os2) for Borland under OS/2; from Chuck Crayne.
- Various minor bugfixes (reported by): Dangling %s in preproc.c (Martin Junker)
- THERE ARE KNOWN BUGS IN SSE AND THE OTHER KATMAI INSTRUCTIONS. I am on a trip and didn't bring the Katmai instruction reference, so I can't work on them right now.
- Updated the License file per agreement with Simon and Jules to include a GPL distribution clause.

C.2.46 Version 0.98p3.7

- (Hopefully) fixed the canned Makefiles to include the outrdf2 and zoutieee modules.
- · Renamed changes.asm to changed.asm.

C.2.47 Version 0.98p3.6

• Fixed a bunch of instructions that were added in 0.98p3.5 which had memory operands, and the address-size prefix was missing from the instruction pattern.

C.2.48 Version 0.98p3.5

- Merged in changes from John S. Fine's 0.98-J5 release. John's based 0.98-J5 on my 0.98p3.3 release; this merges the changes.
- Expanded the instructions flag field to a long so we can fit more flags; mark SSE (KNI) and AMD or Katmai-specific instructions as such.
- Fix the "PRIV" flag on a bunch of instructions, and create new "PROT" flag for protected-mode-only instructions (orthogonal to if the instruction is privileged!) and new "SMM" flag for SMM-only instructions.
- Added AMD-only SYSCALL and SYSRET instructions.
- Make SSE actually work, and add new Katmai MMX instructions.
- Added a -p (preferred vendor) option to ndisasm so that it can distinguish e.g. Cyrix opcodes also used in SSE. For example:

```
      ndisasm -p cyrix aliased.bin

      00000000 670F514310 paddsiw mm0,[ebx+0x10]

      00000005 670F514320 paddsiw mm0,[ebx+0x20]

      ndisasm -p intel aliased.bin

      00000000 670F514310 sqrtps xmm0,[ebx+0x10]

      00000005 670F514320 sqrtps xmm0,[ebx+0x20]
```

• Added a bunch of Cyrix-specific instructions.

C.2.49 Version 0.98p3.4

• Made at least an attempt to modify all the additional Makefiles (in the Mkfiles directory). I can't test it, but this was the best I could do.

- DOS DJGPP+"Opus Make" Makefile from John S. Fine.
- · changes.asm changes from John S. Fine.

C.2.50 Version 0.98p3.3

- Patch from Conan Brink to allow nesting of %rep directives.
- If we're going to allow INT01 as an alias for INT1/ICEBP (one of Jules 0.98p3 changes), then we should allow INT03 as an alias for INT3 as well.
- Updated changes.asm to include the latest changes.
- Tried to clean up the <CR>s that had snuck in from a DOS/Windows environment into my Unix environment, and try to make sure than DOS/Windows users get them back.
- We would silently generate broken tools if insns.dat wasn't sorted properly. Change insns.pl so that the order doesn't matter.
- Fix bug in insns.pl (introduced by me) which would cause conditional instructions to have an extra "cc" in disassembly, e.g. "jnz" disassembled as "jccnz".

C.2.51 Version 0.98p3.2

- Merged in John S. Fine's changes from his 0.98-J4 prerelease; see http://www.csoft.net/cz/johnfine/
- Changed previous "spotless" Makefile target (appropriate for distribution) to "distclean", and added "cleaner" target which is same as "clean" except deletes files generated by Perl scripts; "spotless" is union.
- Removed BASIC programs from distribution. Get a Perl interpreter instead (see below.)
- Calling this "pre-release 3.2" rather than "p3-hpa2" because of John's contributions.
- Actually link in the IEEE output format (zoutieee.c); fix a bunch of compiler warnings in that file. Note I don't know what IEEE output is supposed to look like, so these changes were made "blind".

C.2.52 Version 0.98p3-hpa

- Merged nasm098p3.zip with nasm-0.97.tar.gz to create a fully buildable version for Unix systems (Makefile.in updates, etc.)
- Changed insns.pl to create the instruction tables in nasm.h and names.c, so that a new instruction can be added by adding it *only* to insns.dat.
- Added the following new instructions: SYSENTER, SYSEXIT, FXSAVE, FXRSTOR, UD1, UD2 (the latter
 two are two opcodes that Intel guarantee will never be used; one of them is documented as UD2 in
 Intel documentation, the other one just as "Undefined Opcode" -- calling it UD1 seemed to make
 sense.)
- MAX_SYMBOL was defined to be 9, but LOADALL286 and LOADALL386 are 10 characters long. Now MAX_SYMBOL is derived from insns.dat.
- A note on the BASIC programs included: forget them. insns.bas is already out of date. Get yourself a Perl interpreter for your platform of choice at http://www.cpan.org/ports/index.html.

C.2.53 Version 0.98 pre-release 3

- added response file support, improved command line handling, new layout help screen
- fixed limit checking bug, 'OUT byte nn, reg' bug, and a couple of rdoff related bugs, updated Wishlist; 0.98 Prerelease 3.

C.2.54 Version 0.98 pre-release 2

• fixed bug in outcoff.c to do with truncating section names longer than 8 characters, referencing beyond end of string; 0.98 pre-release 2

C.2.55 Version 0.98 pre-release 1

- Fixed a bug whereby STRUC didn't work at all in RDF.
- Fixed a problem with group specification in PUBDEFs in OBJ.
- Improved ease of adding new output formats. Contribution due to Fox Cutter.
- Fixed a bug in relocations in the 'bin' format: was showing up when a relocatable reference crossed an 8192-byte boundary in any output section.
- Fixed a bug in local labels: local-label lookups were inconsistent between passes one and two if an EQU occurred between the definition of a global label and the subsequent use of a local label local to that global.
- Fixed a seg-fault in the preprocessor (again) which happened when you use a blank line as the first line of a multi-line macro definition and then defined a label on the same line as a call to that macro.
- Fixed a stale-pointer bug in the handling of the NASM environment variable. Thanks to Thomas McWilliams.
- ELF had a hard limit on the number of sections which caused segfaults when transgressed. Fixed.
- Added ability for ndisasm to read from stdin by using '-' as the filename.
- ndisasm wasn't outputting the TO keyword. Fixed.
- Fixed error cascade on bogus expression in %if an error in evaluation was causing the entire %if to be discarded, thus creating trouble later when the %else or %endif was encountered.
- Forward reference tracking was instruction-granular not operand- granular, which was causing 286-specific code to be generated needlessly on code of the form 'shr word [forwardref],1'. Thanks to Jim Hague for sending a patch.
- All messages now appear on stdout, as sending them to stderr serves no useful purpose other than to make redirection difficult.
- Fixed the problem with EQUs pointing to an external symbol this now generates an error message.
- Allowed multiple size prefixes to an operand, of which only the first is taken into account.
- Incorporated John Fine's changes, including fixes of a large number of preprocessor bugs, some small problems in OBJ, and a reworking of label handling to define labels before their line is assembled, rather than after.
- Reformatted a lot of the source code to be more readable. Included 'coding.txt' as a guideline for how to format code for contributors.
- Stopped nested %reps causing a panic they now cause a slightly more friendly error message instead.
- Fixed floating point constant problems (patch by Pedro Gimeno)
- Fixed the return value of insn_size() not being checked for -1, indicating an error.
- · Incorporated 3Dnow! instructions.
- Fixed the 'mov eax, eax + ebx' bug.
- Fixed the GLOBAL EQU bug in ELF. Released developers release 3.

- Incorporated John Fine's command line parsing changes
- Incorporated David Lindauer's OMF debug support
- Made changes for LCC 4.0 support (__NASM_CDecl__, removed register size specification warning when sizes agree).

C.3 NASM 0.9 Series

Revisions before 0.98.

C.3.1 Version 0.97 released December 1997

- This was entirely a bug-fix release to 0.96, which seems to have got cursed. Silly me.
- Fixed stupid mistake in OBJ which caused 'MOV EAX, <constant>' to fail. Caused by an error in the 'MOV EAX, <segment>' support.
- ndisasm hung at EOF when compiled with lcc on Linux because lcc on Linux somehow breaks feof(). ndisasm now does not rely on feof().
- A heading in the documentation was missing due to a markup error in the indexing. Fixed.
- Fixed failure to update all pointers on realloc() within extended- operand code in parser.c. Was causing wrong behaviour and seg faults on lines such as 'dd 0.0,0.0,0.0,0.0,...'
- Fixed a subtle preprocessor bug whereby invoking one multi-line macro on the first line of the expansion of another, when the second had been invoked with a label defined before it, didn't expand the inner macro.
- Added internal.doc back in to the distribution archives it was missing in 0.96 *blush*
- Fixed bug causing 0.96 to be unable to assemble its own test files, specifically objtest.asm. *blush again*
- Fixed seg-faults and bogus error messages caused by mismatching <code>%rep</code> and <code>%endrep</code> within multi-line macro definitions.
- Fixed a problem with buffer overrun in OBJ, which was causing corruption at ends of long PUBDEF records.
- Separated DOS archives into main-program and documentation to reduce download size.

C.3.2 Version 0.96 released November 1997

- Fixed a bug whereby, if 'nasm sourcefile' would cause a filename collision warning and put output into 'nasm.out', then 'nasm sourcefile –o outputfile' still gave the warning even though the '-o' was honoured. Fixed name pollution under Digital UNIX: one of its header files defined R_SP, which broke the enum in nasm.h.
- Fixed minor instruction table problems: FUCOM and FUCOMP didn't have two-operand forms; NDISASM didn't recognise the longer register forms of PUSH and POP (eg FF F3 for PUSH BX); TEST mem,imm32 was flagged as undocumented; the 32-bit forms of CMOV had 16-bit operand size prefixes; 'AAD imm' and 'AAM imm' are no longer flagged as undocumented because the Intel Architecture reference documents them.
- Fixed a problem with the local-label mechanism, whereby strange types of symbol (EQUs, auto-defined OBJ segment base symbols) interfered with the 'previous global label' value and screwed up local labels.
- Fixed a bug whereby the stub preprocessor didn't communicate with the listing file generator, so that the –a and –l options in conjunction would produce a useless listing file.

- Merged 'os2' object file format back into 'obj', after discovering that 'obj' _also_ shouldn't have a link pass separator in a module containing a non-trivial MODEND. Flat segments are now declared using the FLAT attribute. 'os2' is no longer a valid object format name: use 'obj'.
- Removed the fixed-size temporary storage in the evaluator. Very very long expressions (like 'mov ax,1+1+1+1+...' for two hundred 1s or so) should now no longer crash NASM.
- Fixed a bug involving segfaults on disassembly of MMX instructions, by changing the meaning of one of the operand-type flags in nasm.h. This may cause other apparently unrelated MMX problems; it needs to be tested thoroughly.
- Fixed some buffer overrun problems with large OBJ output files. Thanks to DJ Delorie for the bug report and fix.
- Made preprocess-only mode actually listen to the %line markers as it prints them, so that it can report errors more sanely.
- Re-designed the evaluator to keep more sensible track of expressions involving forward references: can now cope with previously-nightmare situations such as:

```
mov ax,foo | bar
foo equ 1
bar equ 2
```

- · Added the ALIGN and ALIGNB standard macros.
- Added PIC support in ELF: use of WRT to obtain the four extra relocation types needed.
- Added the ability for output file formats to define their own extensions to the GLOBAL, COMMON and EXTERN directives.
- Implemented common-variable alignment, and global-symbol type and size declarations, in ELF.
- Implemented NEAR and FAR keywords for common variables, plus far-common element size specification, in OBJ.
- Added a feature whereby EXTERNs and COMMONs in OBJ can be given a default WRT specification (either a segment or a group).
- Transformed the Unix NASM archive into an auto-configuring package.
- Added a sanity-check for people applying SEG to things which are already segment bases: this previously went unnoticed by the SEG processing and caused OBJ-driver panics later.
- Added the ability, in OBJ format, to deal with 'MOV EAX, < segment>' type references: OBJ doesn't directly support dword-size segment base fixups, but as long as the low two bytes of the constant term are zero, a word-size fixup can be generated instead and it will work.
- Added the ability to specify sections' alignment requirements in Win32 object files and pure binary files.
- Added preprocess-time expression evaluation: the %assign (and %iassign) directive and the bare %if (and %elif) conditional. Added relational operators to the evaluator, for use only in %if constructs: the standard relationals = < > <= >= <> (and C-like synonyms == and !=) plus low-precedence logical operators &&, ^^ and ||.
- Added a preprocessor repeat construct: %rep / %exitrep / %endrep.
- Added the __FILE__ and __LINE__ standard macros.
- Added a sanity check for number constants being greater than 0xFFFFFFF. The warning can be disabled.
- Added the %0 token whereby a variadic multi-line macro can tell how many parameters it's been given in a specific invocation.

- Added %rotate, allowing multi-line macro parameters to be cycled.
- Added the '*' option for the maximum parameter count on multi-line macros, allowing them to take arbitrarily many parameters.
- Added the ability for the user-level forms of EXTERN, GLOBAL and COMMON to take more than one
 argument.
- Added the IMPORT and EXPORT directives in OBJ format, to deal with Windows DLLs.
- Added some more preprocessor %if constructs: %ifidn / %ifidni (exact textual identity), and %ifid / %ifnum / %ifstr (token type testing).
- Added the ability to distinguish SHL AX,1 (the 8086 version) from SHL AX,BYTE 1 (the 286-and-upwards version whose constant happens to be 1).
- Added NetBSD/FreeBSD/OpenBSD's variant of a.out format, complete with PIC shared library features.
- Changed NASM's idiosyncratic handling of FCLEX, FDISI, FENI, FINIT, FSAVE, FSTCW, FSTENV, and FSTSW to bring it into line with the otherwise accepted standard. The previous behaviour, though it was a deliberate feature, was a deliberate feature based on a misunderstanding. Apologies for the inconvenience.
- Improved the flexibility of ABSOLUTE: you can now give it an expression rather than being restricted to a constant, and it can take relocatable arguments as well.
- Added the ability for a variable to be declared as EXTERN multiple times, and the subsequent definitions are just ignored.
- We now allow instruction prefixes (CS, DS, LOCK, REPZ etc) to be alone on a line (without a following instruction).
- Improved sanity checks on whether the arguments to EXTERN, GLOBAL and COMMON are valid identifiers.
- Added misc/exebin.mac to allow direct generation of .EXE files by hacking up an EXE header using DB and DW; also added test/binexe.asm to demonstrate the use of this. Thanks to Yann Guidon for contributing the EXE header code.
- ndisasm forgot to check whether the input file had been successfully opened. Now it does. Doh!
- Added the Cyrix extensions to the MMX instruction set.
- Added a hinting mechanism to allow [EAX+EBX] and [EBX+EAX] to be assembled differently. This is important since [ESI+EBP] and [EBP+ESI] have different default base segment registers.
- Added support for the PharLap OMF extension for 4096-byte segment alignment.

C.3.3 Version 0.95 released July 1997

- Fixed yet another ELF bug. This one manifested if the user relied on the default segment, and attempted to define global symbols without first explicitly declaring the target segment.
- Added makefiles (for NASM and the RDF tools) to build Win32 console apps under Symantec C++. Donated by Mark Junker.
- Added 'macros.bas' and 'insns.bas', QBasic versions of the Perl scripts that convert 'standard.mac' to 'macros.c' and convert 'insns.dat' to 'insnsa.c' and 'insnsd.c'. Also thanks to Mark Junker.
- Changed the diassembled forms of the conditional instructions so that JB is now emitted as JC, and other similar changes. Suggested list by Ulrich Doewich.
- Added '@' to the list of valid characters to begin an identifier with.

- Documentary changes, notably the addition of the 'Common Problems' section in nasm.doc.
- Fixed a bug relating to 32-bit PC-relative fixups in OBJ.
- Fixed a bug in perm_copy() in labels.c which was causing exceptions in cleanup_labels() on some systems.
- Positivity sanity check in TIMES argument changed from a warning to an error following a further complaint.
- Changed the acceptable limits on byte and word operands to allow things like '~10111001b' to work.
- Fixed a major problem in the preprocessor which caused seg-faults if macro definitions contained blank lines or comment-only lines.
- Fixed inadequate error checking on the commas separating the arguments to 'db', 'dw' etc.
- Fixed a crippling bug in the handling of macros with operand counts defined with a '+' modifier.
- Fixed a bug whereby object file formats which stored the input file name in the output file (such as OBJ and COFF) weren't doing so correctly when the output file name was specified on the command line.
- Removed [INC] and [INCLUDE] support for good, since they were obsolete anyway.
- Fixed a bug in OBJ which caused all fixups to be output in 16-bit (old-format) FIXUPP records, rather than putting the 32-bit ones in FIXUPP32 (new-format) records.
- Added, tentatively, OS/2 object file support (as a minor variant on OBJ).
- Updates to Fox Cutter's Borland C makefile, Makefile.bc2.
- Removed a spurious second fclose() on the output file.
- Added the '-s' command line option to redirect all messages which would go to stderr (errors, help text) to stdout instead.
- Added the '-w' command line option to selectively suppress some classes of assembly warning messages.
- Added the '-p' pre-include and '-d' pre-define command-line options.
- Added an include file search path: the '-i' command line option.
- Fixed a silly little preprocessor bug whereby starting a line with a '%!' environment-variable reference caused an 'unknown directive' error.
- Added the long-awaited listing file support: the '-l' command line option.
- Fixed a problem with OBJ format whereby, in the absence of any explicit segment definition, non-global symbols declared in the implicit default segment generated spurious EXTDEF records in the output.
- Added the NASM environment variable.
- From this version forward, Win32 console-mode binaries will be included in the DOS distribution in addition to the 16-bit binaries. Added Makefile.vc for this purpose.
- Added 'return 0;' to test/objlink.c to prevent compiler warnings.
- Added the __NASM_MAJOR__ and __NASM_MINOR__ standard defines.
- Added an alternative memory-reference syntax in which prefixing an operand with '&' is equivalent to enclosing it in square brackets, at the request of Fox Cutter.
- Errors in pass two now cause the program to return a non-zero error code, which they didn't before.

- Fixed the single-line macro cycle detection, which didn't work at all on macros with no parameters (caused an infinite loop). Also changed the behaviour of single-line macro cycle detection to work like cpp, so that macros like 'extrn' as given in the documentation can be implemented.
- Fixed the implementation of WRT, which was too restrictive in that you couldn't do 'mov ax,[di+abc wrt dgroup]' because (di+abc) wasn't a relocatable reference.

C.3.4 Version 0.94 released April 1997

- Major item: added the macro processor.
- Added undocumented instructions SMI, IBTS, XBTS and LOADALL286. Also reorganised CMPXCHG instruction into early-486 and Pentium forms. Thanks to Thobias Jones for the information.
- Fixed two more stupid bugs in ELF, which were causing 'ld' to continue to seg-fault in a lot of non-trivial cases.
- Fixed a seg-fault in the label manager.
- Stopped FBLD and FBSTP from _requiring_ the TWORD keyword, which is the only option for BCD loads/stores in any case.
- Ensured FLDCW, FSTCW and FSTSW can cope with the WORD keyword, if anyone bothers to provide it. Previously they complained unless no keyword at all was present.
- Some forms of FDIV/FDIVR and FSUB/FSUBR were still inverted: a vestige of a bug that I thought had been fixed in 0.92. This was fixed, hopefully for good this time...
- Another minor phase error (insofar as a phase error can _ever_ be minor) fixed, this one occurring in code of the form

```
rol ax,forward_reference
forward_reference equ 1
```

- The number supplied to TIMES is now sanity-checked for positivity, and also may be greater than 64K (which previously didn't work on 16-bit systems).
- Added Watcom C makefiles, and misc/pmw.bat, donated by Dominik Behr.
- Added the INCBIN pseudo-opcode.
- Due to the advent of the preprocessor, the [INCLUDE] and [INC] directives have become obsolete. They are still supported in this version, with a warning, but won't be in the next.
- Fixed a bug in OBJ format, which caused incorrect object records to be output when absolute labels were made global.
- Updates to RDOFF subdirectory, and changes to outrdf.c.

C.3.5 Version 0.93 released January 1997

This release went out in a great hurry after semi-crippling bugs were found in 0.92.

- Really did fix the stack overflows this time. *blush*
- Had problems with EA instruction sizes changing between passes, when an offset contained a
 forward reference and so 4 bytes were allocated for the offset in pass one; by pass two the symbol
 had been defined and happened to be a small absolute value, so only 1 byte got allocated, causing
 instruction size mismatch between passes and hence incorrect address calculations. Fixed.
- Stupid bug in the revised ELF section generation fixed (associated string-table section for .symtab was hard-coded as 7, even when this didn't fit with the real section table). Was causing 'ld' to seg-fault under Linux.
- Included a new Borland C makefile, Makefile.bc2, donated by Fox Cutter < lmb@comtch.iea.com>.

C.3.6 Version 0.92 released January 1997

- The FDIVP/FDIVRP and FSUBP/FSUBRP pairs had been inverted: this was fixed. This also affected the LCC driver.
- Fixed a bug regarding 32-bit effective addresses of the form [other_register+ESP].
- Documentary changes, notably documentation of the fact that Borland Win32 compilers use 'obj' rather than 'win32' object format.
- Fixed the COMENT record in OBJ files, which was formatted incorrectly.
- Fixed a bug causing segfaults in large RDF files.
- OBJ format now strips initial periods from segment and group definitions, in order to avoid complications with the local label syntax.
- Fixed a bug in disassembling far calls and jumps in NDISASM.
- Added support for user-defined sections in COFF and ELF files.
- Compiled the DOS binaries with a sensible amount of stack, to prevent stack overflows on any arithmetic expression containing parentheses.
- Fixed a bug in handling of files that do not terminate in a newline.

C.3.7 Version 0.91 released November 1996

- · Loads of bug fixes.
- · Support for RDF added.
- Support for DBG debugging format added.
- Support for 32-bit extensions to Microsoft OBJ format added.
- Revised for Borland C: some variable names changed, makefile added.
- LCC support revised to actually work.
- JMP/CALL NEAR/FAR notation added.
- 'a16', 'o16', 'a32' and 'o32' prefixes added.
- Range checking on short jumps implemented.
- MMX instruction support added.
- Negative floating point constant support added.
- Memory handling improved to bypass 64K barrier under DOS.
- \$ prefix to force treatment of reserved words as identifiers added.
- Default-size mechanism for object formats added.
- · Compile-time configurability added.
- #, @, ~ and c{?} are now valid characters in labels.
- -e and -k options in NDISASM added.

C.3.8 Version 0.90 released October 1996

First release version. First support for object file output. Other changes from previous version (0.3x) too numerous to document.

Appendix D: Building NASM from Source

The source code for NASM is available from our website, http://wwww.nasm.us/, see section E.1.

D.1 Building from a Source Archive

The source archives available on the web site should be capable of building on a number of platforms. This is the recommended method for building NASM to support platforms for which executables are not available.

On a system which has Unix shell (sh), run:

```
sh configure make everything
```

A number of options can be passed to configure; see sh configure --help.

A set of Makefiles for some other environments are also available; please see the file Mkfiles/README.

To build the installer for the Windows platform, you will need the *Nullsoft Scriptable Installer*, NSIS, installed.

To build the documentation, you will need a set of additional tools. The documentation is not likely to be able to build on non-Unix systems.

D.2 Building from the git Repository

The NASM development tree is kept in a source code repository using the git distributed source control system. The link is available on the website. This is recommended only to participate in the development of NASM or to assist with testing the development code.

To build NASM from the git repository you will need a Perl interpreter and, if building on a Unix system, GNU autoconf installed on your system.

To build on a Unix system, run:

```
sh autogen.sh
```

to create the configure script and then build as listed above.

D.3 Building the documentation

To build the documentation, you will need a Perl interpreter, a Postscript to PDF converter such as Ghostscript, and suitable fonts installed on your system. The recommended (and default) fonts are Adobe's Source Sans and Source Code fonts, which are freely available under the SIL Open Font License.

Appendix E: Contact Information

E.1 Website

NASM has a website at http://www.nasm.us/.

New releases, release candidates, and daily development snapshots of NASM are available from the official web site in source form as well as binaries for a number of common platforms.

E.1.1 User Forums

Users of NASM may find the Forums on the website useful. These are, however, not frequented much by the developers of NASM, so they are not suitable for reporting bugs.

E.1.2 Development Community

The development of NASM is coordinated primarily though the nasm-devel mailing list. If you wish to participate in development of NASM, please join this mailing list. Subscription links and archives of past posts are available on the website.

E.2 Reporting Bugs

To report bugs in NASM, please use the bug tracker at http://www.nasm.us/ (click on "Bug Tracker"), or if that fails then through one of the contacts in section E.1.

Please read section 2.2 first, and don't report the bug if it's listed in there as a deliberate feature. (If you think the feature is badly thought out, feel free to send us reasons why you think it should be changed, but don't just send us mail saying 'This is a bug' if the documentation says we did it on purpose.) Then read section 13.1, and don't bother reporting the bug if it's listed there.

If you do report a bug, *please* make sure your bug report includes the following information:

- What operating system you're running NASM under. Linux, FreeBSD, NetBSD, MacOS X, Win16, Win32, Win64, MS-DOS, OS/2, VMS, whatever.
- If you compiled your own executable from a source archive, compiled your own executable from git, used the standard distribution binaries from the website, or got an executable from somewhere else (e.g. a Linux distribution.) If you were using a locally built executable, try to reproduce the problem using one of the standard binaries, as this will make it easier for us to reproduce your problem prior to fixing it.
- Which version of NASM you're using, and exactly how you invoked it. Give us the precise command line, and the contents of the NASMENV environment variable if any.
- Which versions of any supplementary programs you're using, and how you invoked them. If the
 problem only becomes visible at link time, tell us what linker you're using, what version of it you've
 got, and the exact linker command line. If the problem involves linking against object files generated
 by a compiler, tell us what compiler, what version, and what command line or options you used. (If
 you're compiling in an IDE, please try to reproduce the problem with the command-line version of
 the compiler.)
- If at all possible, send us a NASM source file which exhibits the problem. If this causes copyright problems (e.g. you can only reproduce the bug in restricted-distribution code) then bear in mind the following two points: firstly, we guarantee that any source code sent to us for the purposes of debugging NASM will be used *only* for the purposes of debugging NASM, and that we will delete all our copies of it as soon as we have found and fixed the bug or bugs in question; and secondly, we would prefer *not* to be mailed large chunks of code anyway. The smaller the file, the better. A three-line sample file that does nothing useful *except* demonstrate the problem is much easier to

- work with than a fully fledged ten-thousand-line program. (Of course, some errors *do* only crop up in large files, so this may not be possible.)
- A description of what the problem actually *is*. 'It doesn't work' is *not* a helpful description! Please describe exactly what is happening that shouldn't be, or what isn't happening that should. Examples might be: 'NASM generates an error message saying Line 3 for an error that's actually on Line 5'; 'NASM generates an error message that I believe it shouldn't be generating at all'; 'NASM fails to generate an error message that I believe it *should* be generating'; 'the object file produced from this source code crashes my linker'; 'the ninth byte of the output file is 66 and I think it should be 77 instead'.
- If you believe the output file from NASM to be faulty, send it to us. That allows us to determine whether our own copy of NASM generates the same file, or whether the problem is related to portability issues between our development platforms and yours. We can handle binary files mailed to us as MIME attachments, uuencoded, and even BinHex. Alternatively, we may be able to provide an FTP site you can upload the suspect files to; but mailing them is easier for us.
- Any other information or data files that might be helpful. If, for example, the problem involves NASM failing to generate an object file while TASM can generate an equivalent file without trouble, then send us *both* object files, so we can see what TASM is doing differently from us.

Index

! operator	42	~ operator	
!= operator	41	~ opunary	42
\$\$ token	41, 105	%0 parameter count	57
\$		%00	57
Here token	41	%+1 and %-1 syntax	59
prefix	33, 37, 108	16-bit mode, versus 32-bit mode	83
% operator	42	1's complement	42
%!	72	2's complement	42
%\$ and %\$\$ prefixes	65, 66	64-bit displacement	134
‰ operator	42, 55	64-bit immediate	133
%*?	50	-a option	24, 140
%*??	50	A16	33, 132
%+	49	A32	33, 132
%,	52	A64	33, 132
%?	50	a86	30, 31
%??	50	ABS	37, 84
%[49	ABSOLUTE	85, 94
% prefix to DB lists	34	addition	42
& operator	42	addressing, mixed-size	131
&& operator	41	address-size prefixes	33
* operator	42	algebra	36
+ modifier	55	ALIGN	77, 79, 91, 93
+ operator		smart	79
binary	42	align, elf attribute	104
unary	42	ALIGNB	77
- operator	40	alignment	77
binary	42	in bin sections	91
unary	42	in ELF sections	104
@ symbol prefix	45, 55	in obj sections	94
/ operator	42	in win32 sections	97
// operator	42	of ELF common variables	107
< operator	41	ALIGNMODE	79 70
<< operator	42	?ALIGNMODE?	79
<< operator	42	ALINK	111
<= operator	41	alink.sourceforge.net	111
<=> operator	42	all	25
<> operator	41	alloc	104
= operator	41	alternate register names	79 70
== operator	41 42	altreg	79
> operator	42	ambiguity	31
>= operator	42	a.out BSD version	107
>> operator	42	Linux version	107 107
>>> operator	42		107
?	24.25	aout	107, 126
data syntax	34, 35 41	aoutb	•
operator	41	%arg	68 118 125
^ operator	42	arg	118, 125
^^ operator	41	as86 assembler directives	108 83
operator			
operator	41	assembly-time options	23

%assign	51	coff	102
ASSUME	31	colon	33
AT	76	.COM	91, 113
	140	comma	56
auto-sync -b	139	command-line	19, 91
baddb	35	commas in macro parameters	19, 91
	25	·	105
bad-pragma		.comment	
before	29	COMMON	87, 93
bf16	80	ELF extensions to	107
?bfloat16?	39	obj extensions to	96
bfloat16	40	Common Object File Format	102
bin output format	20, 91	common variables	87
bin, multisection	92	alignment in ELF	107
binary	37	element size	96
binary files	35	comparison operators	41
bit shift	42	comp.os.msdos.programmer	114
BITS	83, 91	concatenating macro parameters	58
?BITS?	74	concatenating strings	53
bitwise AND	42	condition codes as macro parame	ters 59
bitwise OR	42	conditional assembly	60
bitwise XOR	42	conditional comma operator	52
block IFs	67	conditional jumps	137
BND	84	conditional-return macro	59
bnd	25	constants	37
boolean		context fall-through lookup	66
AND	41	context stack	65, 67
OR	41	context-local labels	65
XOR	41	context-local single-line macros	66
boot loader	91	counting macro parameters	57
boot sector	137	CPU	88
Borland		CPUID	39
Pascal	119	creating contexts	65
Win32 compilers	93	critical expression	35, 44, 51, 85
braces	33	section	91
after % sign	59	cv8	99
around macro para		-D option	23
BSD	126	-d option	23
_	105, 107, 108	daily development snapshots	275
.bss bug tracker	275	.data	
•	275		105, 107, 108 115
bugs	137	_DATA	
BYTE		data	106, 109
C calling convention	115, 123	data structure	117, 125
C symbol names	114	?DATE?	74
c16.mac	118, 120	?DATE_NUM?	74
c32.mac	125	DB	34, 39
CALL FAR	43	db-empty	25
case sensitivity	30, 47, 48, 51, 54, 61, 94	dbg	109
changing sections	84	DD	34, 39
character constant	34, 39	debug information	22
character strings	38	debug information format	22
circular references	47	?DEBUG_FORMAT?	74
CLASS	94	decimal	37
%clear	72, 73	declaring structures	75
CodeView debugging for	mat 99	%defalias	52

DEFAULT	84	Nalifornatio	63
DEFAULT	106	<pre>%elifnempty %elifneny</pre>	63
default macro parameters	56		62
default macro parameters default name	91	%elifnid	62
default-wrt mechanism	96	%elifnidn	62
%define	23, 47	%elifnidni	61
	23,41	%elifnmacro	62
defining sections	51	%elifnnum %elifnstr	62
%defstr %deftok	52	%elifntoken	63
	64	%elifnum	62
%depend	30		62
design goals DevPac	30 44	%elifstr	63
	59	%eliftoken	60
disabling listing expansion division	59 42	%else	
	42 42	endproc	118, 125
signed	42 42	%endrep	63 75.05
unsigned		ENDSTRUC	75, 85
DJGPP	102, 123	environment	25, 30
djlink	111	EQU	34, 35
DLL symbols	0.5	%error	70
exporting	95	error messages	22
importing	95	error reporting format	22
DO	34, 39	escape sequences	38
DOS	22	EVEN	77
DQ	34, 39	exact matches	60
.drectve	97	. EXE	93, 111
DT	34, 39	EXE2BIN	113
DUP	34, 35, 36	EXE_begin	112
DW	34, 39	exebin.mac	112
DWORD	34	exec	104
DY	34, 39	Executable and Linkable Format	104
DZ	34	EXE_end	112
-E option	24	EXE_stack	112
-e option	24, 140	%exitrep	63
effective addresses	33, 36	EXPORT	95
element size, in common variables	96	export	108
ELF	104	exporting symbols	86
shared libraries	106	expressions	24, 41
16-bit code	107	extension	19, 91
debug formats	107	EXTERN	86
elf32	104	elf extensions to	107
elf64	104	obj extensions to	96
elfx32	104	rdf extensions to	109
%elif	60, 61	extracting substrings	53
%elifctx	61	-F option	22
%elifdef	60	-f option	20, 91
%elifempty	63	far call	31
%elifenv	63	far common variables	96
%elifid	62	far pointer	43
%elifidn	62	FARCODE	118, 120
%elifidni	62	%fatal	70 72
%elifmacro	61	?FILE?	73
%elifn	60, 61	fini_array	104
%elifnctx	61	FLAT	94
%elifndef	60	flat memory model	123

flat-form binary	91	greedy macro parameters	55
FLOAT	88	GROUP	94
?FLOAT?	89	groups	43
float	25	-h	139
?float128h?	39	hexadecimal	37
?float128l?	39	hidden	106
?float16?	39	hle	25
?float32?	39	hybrid syntaxes	31
?float64?	39	-I option	23
?float8?	39	-i option	23, 140
?float80e?	39	%iassign	51
?float80m?	39	%idefalias	52
?FLOAT_DAZ?	89	%idefine	47
float-denorm	25	%idefstr	51
floating-point	25	%ideftok	52
constants	39, 88	IEND	76
packed BCD constants	41	%if	60, 61
floating-point	31, 33, 34, 39	%ifctx	61, 67
float-overflow	25	%ifdef	60
?FLOAT_ROUND?	89	%ifempty	63
float-toolong	25	%ifenv	63
float-underflow	25	%ifid	62
follows=	92	%ifidn	61
format-specific directives	83	%ifidni	61
fp	80	%ifmacro	61
frame pointer	116, 119, 123	%ifn	60, 61
FreeBSD	107, 126	%ifnctx	61
FreeLink	107, 120	%ifndef	60
ftp.simtel.net	111	%ifnempty	63
function	106, 109	%ifnempty %ifnenv	63
functions	100, 103	%ifnid	62
C calling convention	115, 123	%ifnidn	62
PASCAL calling convention	119, 129	%ifnidni	62
-g option	22	%ifnmacro	61
git	273	%ifnnum	62
GLOBAL	86	%ifnstr	62
aoutb extensions to	106	%ifntoken	63
ELF extensions to	106	%ifnum	62
rdf extensions to	108	%ifstr	62
global offset table	126	%iftoken	62
_GLOBAL_OFFSET_TABLE_	105	ifunc	80
(G L)POSTFIX	87	ilog2()	80
(g l)postfix	29	ilog2c()	80
(G L)PREFIX	87	ilog2cw()	80
(g l)prefix	29	ilog2e()	80
got	105	ilog2f()	80
GOT relocations	127	ilog2fw()	80
GOT	105, 126	ilog2w()	80
gotoff	105, 126	%imacro	53
GOTOFF relocations	127	IMPORT	95
gotpc	105	import library	95
GOTPC relocations	126	importing symbols	86
gottpoff	106	unconditionally	86
graphics	35	INCBIN	34, 35, 39
0. 27	33	11100111	54,55,55

	22.64	March alchert Clare	100
%include	23, 64	Mach, object file format	102
include search path	23	Mach-O, object file format	102
including other files	64	macho32	102
inefficient code	137	macho64	102
infinite loop	41	MacOS X	102
?Infinity?	40	%macro	53
infinity	40	macro	26
informational section	97	macro indirection	49
init_array	104	macro library	23
instances of structures	76	macro parameters range	56
instruction list	143	macro processor	47
integer functions	80	macro-def	26
integer logarithms	80	macro-defaults	26
intel hex	92	macro-def-case-single	26
Intel number formats	40	macro-def-greedy-single	26
internal	106	macro-def-param-single	26
ISTRUC	76	macro-local labels	55
iterating over macro parameters	57	macro-params	26
ith	92	macro-params-legacy	26
%ixdefine	48	macro-params-multi	27
Jcc NEAR	137	macro-params-single	27
JMP DWORD	131	macros	36
jumps, mixed-size	131	makefile dependencies	21
-k	140	map files	92
keep-all	30	MASM	30, 34, 36, 80, 93
-L option	20	masm compatibility	80
-1 option	20	DB syntax	34, 35
label	25	-MD option	21
label preceeding macro	57	memory models	31, 115
label prefix	45	memory operand	34
label-orphan	26, 33	memory references	30, 36
label-redef	26	merge	105
label-redef-late	26	-MF option	21
last	56	-MG option	21
.lbss	105	Microsoft OMF	93
ld86	108	minifloat	40
.ldata	105	Minix	108
LIBRARY	108	misc subdirectory	112, 118, 125
license	17	mixed-language program	114
limit-X	29	mixed-size addressing	131
%line	30, 71	mixed-size instruction	131
?LINE?	73	MODULE	108
linker, free	111	modulo	42
Linux		signed	42
a.out	107	unsigned	42
as86	108	motorola s-records	92
ELF	104	-MP option	21
listing file	20	-MQ option	21
little-endian	39	MS-DOS	91
%local	69	MS-DOS device drivers	114
local labels	44	-мт option	21
lock	26	multi-line macros	26, 27, 53
.lrodata	105	multipass optimization	24
-M option	21	multiple section names	91

multiplication	42	032	33, 132
multiplier	105	064	33
multipush macro	58	.obj	111
multisection	92	obj	93
-MW option	21	object	106, 109
?NaN?	40	obsolete	27
NaN	40	obsolete-nop	27
NASM version		obsolete-removed	27
history	235	obsolete-valid	27
ID macro	73	octal	37
macros	73	OF_DEFAULT	20
string macro	73	OFFSET	31
NASMDEFSEG	93	OMF	93
nasm-devel	275	omitted parameters	56
NASMENV	30	OpenBSD	107, 126
nasm -h	20	operands	33
?NASM_MAJOR?	73	operand-size prefixes	33
?NASM_MINOR?	73	operating system	91
nasm.out	19	writing	131
?NASM_PATCHLEVEL?	73	operators	41
?NASM_SNAPSHOT?	73	unary	42
?NASM_SUBMINOR?	73	ORG	91, 113, 137
?NASM_VER?	73	orphan-labels	27
?NASM_VERSION_ID?	73	OS/2	93, 94
ndisasm	139	osabi	104
near call	31	other	27
near common variables	96	other preprocessor directives	71
negation	30	out of range, jumps	137
arithmetic	42	output file format	20
bitwise	42	output formats	91
boolean	42	?OUTPUT_FORMAT?	74
bitwise	42	overlapping segments	43
boolean	42	OVERLAY	94
	27	overloading	9-
negative-rep NetBSD	107, 126	multi-line macros	54
	•	single-line macros	47
new releases	275	•	
noalloc	104	-P option	23
nobits	92, 104	-p option	23, 64
NOBND	84	paradox	44
no_dead_strip	103	PASCAL	120
noexec	104	Pascal calling convention	119
no-line	30, 71	?PASS?	75
.nolist	59	%pathsearch	23, 64
note	104	period	44
not-my-pragma	27	PharLap	94
nowait'	32	phase	27
nowrite	104	PIC	105, 107, 126
NSIS	273	plt	105
Nullsoft Scriptable Installer	273	PLT relocations	106, 127, 128
number-overflow	27	plt relocations	128
numeric constants	34, 37	pointer, elf attribute	105
-o option	24	%рор	65
-o option	19, 139	position-independent code	105, 107, 126
016	33, 132	%pragma	70

pragma	29	RESO	34, 35
pragma	27	RESQ	34, 35
pragma-bad	27	REST	34, 35
pragma-empty	27	RESW	34, 35
pragma-na	28	RESY	34, 35
pragma-unknown	28	RESZ	34, 35
precedence	41	.rodata	105
pre-defining macros	23, 48	%rotate	57
preferred	43	rotating macro parameters	57
pre-including files	23	-s option	22, 140
preinit_array	104	searching for include files	64
preprocess-only mode	24	?SECT?	84, 85
preprocessor	24, 36, 42, 47	SECTALIGN	78
preprocessor expressions	24	SECTION	84
preprocessor loops	63	ELF extensions to	104
preprocessor variables	51	macho extensions to	103
primitive directives	83	Windows extensions to	97
PRIVATE	93	section alignment	
private_extern	104	in bin	91
proc	109, 118, 125	in ELF	104
procedure linkage table	106, 127, 128	in obj	94
processor mode	83	in win32	97
progbits	92, 104	SEG	43, 93
program entry point	95, 111	SEGMENT	84
program origin	91	obj extensions to	93
protected	106	segment address	42, 43
pseudo-instructions	34	segment alignment	
ptr	28	in bin	91
PUBLIC	86, 93	in obj	94
pure binary	91	segment names, Borland Pascal	120
%push	65	segment override	31, 33
	40	segments	43
quick start	30	groups of	94
QWORD	34	separator character	30
-r	139	shared libraries	107, 126
rdf	108	shift command	57
rdoff subdirectory	108	signed	
redirecting errors	22	bit shift	42
regsize	28	division	42
REL	37, 84	modulo	42
release candidates	275	single-line macros	27, 47
Relocatable Dynamic Object File		size, of symbols	106
Format	108	smartalign	79
relocations, PIC-specific	105	?SNaN?	40
removing contexts	65	snapshots, daily development	275
renaming contexts	67	Solaris x86	104
%rep	36, 63	-soname	129
repeating	36, 63	sound	35
%repl	67	source-listing file	20
reporting bugs	275	square brackets	30, 36
reproducible	30	srec	92
REQUIRED	86	STACK	93
RESB	34, 35	stack relative preprocessor directives	68
RESD	34, 35	%stacksize	69
NEOD .	54,55	705 COCKS 12C	03

standard macro packages	79	?TIME_NUM?	74
standard macros	73	TIMES	34, 36, 44, 137, 138
standardized section names	84, 97, 104,	TLINK	113
0.00.00.00.00.00.00.00.00.00.00.00.00.0	107, 108	tls	103, 105, 106
start	95, 111	tlsie	106
start=	92	trailing colon	33
STATIC	87	TWORD	32, 34
stderr	22	type, of symbols	106
stdout	22	-u option	23
%strcat	53	-u option	23, 139
STRICT	43	unary operators	42
string	38	%undef	23, 51
constants	34, 38, 39	undefining macros	23
length	53	underscore, in C symbols	114
manipulation in macros	52	Unicode	38, 39
strings, elf attribute	105	uninitialized storage	32, 34
%strlen	53	uninitialized	34, 35
strong	106	Unix	
STRUC	75, 85, 117, 125	SCO	104
structure data types	75	System V	104
stub preprocessor	24	UnixWare	104
subsections_via_symbols	103	unknown-pragma	28
%substr	53	unknown-warning	28
subtraction	42	%unmacro	60
suppressing preprocessing	24	unrolled loops	36
switching between sections	84	unsigned	
sym	105	bit shift	42
symbols		division	42
exporting from DLLs	95	modulo	42
importing from DLLs	95	UPPERCASE	30, 94
specifying sizes	106	%use	65, 79
specifying types	106	?USE_*?	75
synchronization	140	USE16	84, 94
.SYS	91, 114	USE32	84, 94
-t	24	user	28
TASM	24	user-defined errors	70
tasm	30, 93	user-level directives	73, 83
.tbss	105	?UTC_DATE?	74
TBYTE	32	?UTC_DATE_NUM?	74
.tdata	105	?UTC_TIME?	74
test subdirectory	111	?UTC_TIME_NUM?	74
testing		UTF-16	39
arbitrary numeric express		UTF-32	39
context stack	61	UTF-8	38
exact text identity	61	?utf16?	39
multi-line macro existenc		?utf16be?	39
single-line macro existend		?utf16le?	39
token types	62	?utf32?	39
.text	105, 107, 108	?utf32be?	39
_TEXT	115	?utf32le?	39
thread local storage	100	v	29
in ELF	106	-v option	29
in macho	103 74	VAL valid characters	111
?TIME?	14	valiu ciidi actei S	33

variable types	31
version number of nasm	73
version	29
vfollows=	92
Visual C++	97
vstart=	92
-w option	25
-w option	25
%warning	70
[WARNING]	29, 89
warning classes	25
warnings	25
warn-stack-empty	28
weak	106, 107
website	275
-Werror option	28
Win32	93, 97, 123
Win64	99, 133
Windows	111
debugging formats	99
-Wno-error option	28
write	104
writing operating systems	131
WRT 43, 93	3, 103, 105, 106, 107
WRTgot	127
WRTgotoff	127
WRTgotpc	126
WRTplt	128
WRTsym	128
www.delorie.com	111
www.pcorner.com	111
-x option	22
x2ftp.oulu.fi	111
x32	104
%xdefine	48
-z option	22
zeroing	28
zext-reloc	28