
C++ Course 8 : Classes 2

2020 by Oleksiy Grechnyev

Operator overloading

```
Operator +:
int a = 3 + 2; // int + int : built-in, no questions
string s1 = "Hello "s + "World"s; // string + string, how does it work?
string s2 = string("Hello ") + "World"; // string + const char[] ???
Suppose we have created our own class MyClass.
How can we implement operator + for it?
MyClass m1(1), m2(2);
MyClass m3 = m1 + m2; // How to do this?
MyClass m4 = MyClass(1) + MyClass(2); // Or like this
Solution C++ operator overloading: m1 + m2 is a shortcut for either
MyClass m = operator+(m1, m2); // Overloaded function, a "non-member operator:
OR
MyClass m = m1.operator+(m2); // Method, a "member operator"
```

Operators that can be overloaded



Cannot create new operators!

Operators are often **inline**. **noexcept** is a good idea.

Non-member operators are usually **friend**.

Operator parameter types, return type, behavior

??? operator+ (??? lhs, ??? rhs) { ... }

Beware of ambiguity!

```
Operator parameter types and return type can be (almost) anything.
But usually we want it to behave like + for primitive types.
Typically parameters and the return type are of the same type:
MyClass operator+ (const MyClass & Ihs, const MyClass & rhs) { ... }
Note: Overloaded operators often include versions for implicit type conversion.
For example, for string, there are several overloaded versions of operator+:
string operator+ (const string & lhs, const string & rhs);
string operator+ (const string & lhs, const char * rhs);
string operator+ (const char * lhs, const string & rhs);
```

You can add a **std::string** to a C-string (but not two C-strings!)

Remember, functions **operator+** are all overloads of the same name!

Example 1: Vec2 : 2-dimensional vector (x, y)

```
Let us design our own class: a 2D vector.


Let us overload various operators (+, == etc.).

Two private fields: x, y.

Getters and setters are not shown (see the full example in the repo).

Note: No custom copy/move operation in this class! Standard copy behavior is OK.
```

```
class Vec2{
public: //==== Methods
     Vec2(double x, double y) : x(x), y(y) {}
                                                 /// xy ctor
     Vec2() = default;
                                     /// Default (no-par) ctor
private: //==== Data
  double x = std::nan(""); // Two private fields
  double y = std::nan("");
};
```



Operators: Members or Non-Members:

```
Operators can be members (methods) or non-members (friend functions):

class Vec2 { ...

Vec2 operator+(const Vec2 & rhs); // Member

friend Vec2 operator-(const Vec2 & lhs, const Vec2 & rhs); // Declare as friend
}; // End of class Vec2

Vec2 operator-(const Vec2 & lhs, const Vec2 & rhs); // Non-Member

1. Must be members: =, [], (), ->
```

- 2. Usually members: special assignment and unary: +=, ++, unary *, ...
- 3. Usually non-members: regular binary: +, <, ==, ...

Comparison : operator == , operator! =

```
Non-member:
class Vec2 { ... // Binary operators are usually non-members (friend functions)
   friend bool operator==(const Vec2 & lhs, const Vec2 & rhs) noexcept; // Returns bool
  // End of class Vec2
inline bool operator==(const Vec2 & lhs, const Vec2 & rhs) noexcept {
  if (& lhs == & rhs)
                             // Optional, check if it is the same object
     return true:
  else // Compare all fields
     return (lhs.x == rhs.x) && (lhs.y == rhs.y);
} // reflexive, symmetric and transitive
inline bool operator!=(const Vec2 & lhs, const Vec2 & rhs) noexcept {
  return !(lhs == rhs); // The proper way to define operator!= is via operator==
} // Now operator== and operator!= are consistent!
Note: inheritance and operator== is a bad combination!
```

Comparison: operator<

```
Non-member binary operators: should be consistent with each other!
inline bool operator<(const Vec2 & lhs, const Vec2 & rhs) noexcept {
    if (lhs.x == rhs.x) // The only comparison actually implemented!
         return lhs.y < rhs.y; // In our example, x is more important that y
    else
         return lhs.x < rhs.x ;
} // I know 2D vectors cannot be compared, just an example!
inline bool operator>(const Vec2 & Ihs, const Vec2 & rhs) noexcept {
  return rhs < lhs; // Use existing operator<
inline bool operator<=(const Vec2 & lhs, const Vec2 & rhs) noexcept {
  return !(lhs > rhs); // Use existing operator>
inline bool operator>=(const Vec2 & lhs, const Vec2 & rhs) noexcept {
  return !(lhs < rhs); // Use existing operator<
```

istream input, ostream output: overload bit shifts

Write a vector to a stream. Note: Non-member function with different argument types. inline std::ostream & operator<< (std::ostream & os, const Vec2 & v){ os << std::setw(10) << v.x << " " << std::setw(10) << v.y; // No endl! return os; Read a vector from a stream. inline std::istream & operator>> (std::istream & is, Vec2 & v) { is $\gg v.x \gg v.y$; if (!is) v = Vec2(); // Default (NaN) vector on IO error return is; Do this for all your classes, if you want to read/write them!

operator+=, operator-=, operator*=, operator/=

Binary + assign operators, member operators by convention. Add two vectors: Vec2 & operator+= (const Vec2 & rhs) noexcept { x += rhs.x;y += rhs.y;**return *this**; // Return the object by reference! Multiply vector by a number: Vec2 & operator*= (double rhs) noexcept { x *= rhs; y *= rhs; **return *this**; // Return the object by reference! Note: Always return *this, so that assignments can be chained (a=b=c=d+=Vec2(3, 4)).

operator+, operator-, operator*, operator/

```
Non-member binary operators. Use existing operator+= etc.
inline Vec2 operator+(const Vec2 & lhs, const Vec2 & rhs) noexcept {
  Vec2 temp = lhs; // Make a copy of lhs
  temp += rhs; // Based on the existing operator+! Add rhs to it.
  return temp; // Return the result by value
} // Better pass lhs by value and avoid the copy!
inline Vec2 operator-(Vec2 lhs, const Vec2 & rhs) noexcept {
  lhs -= rhs; // DO like this!
  return lhs;
inline Vec2 operator*(Vec2 lhs, double rhs) noexcept {
  Ihs *= rhs; // Multiply vector by double: different types
  return lhs;
inline Vec2 operator*(double lhs, const Vec2 & rhs) noexcept { return rhs*lhs; }
```

operator++, operator--

Member operators (Note: Not a proper vector operation!): Prefix version (++v): Vec2 & operator++() noexcept { // Increase both x, y by 1 ++**X**; ++**y**; **return *this**; // Return self by reference Postfix version (v++): Dummy (int) argument signifies postfix! Vec2 operator++(int) noexcept { **Vec2 temp{*this}**; // Make a copy of self ++*this; // Call prefix like this return temp; // Return the copy by value. Less efficient!

operator[]: Index vector components !

```
Member operator:
Non-const version:
double & operator[] (int i) {
     switch (i) {
     case 0:
       return x;
    case 1:
       return y;
     default:
       throw std::out_of_range("Vec2::operator[]");
const version, needed for indexing const objects!
const double & operator[] (int i) const { ... }
```

operator()

```
Member operator, prints the vector to console:
void operator()(const std::string &s) noexcept {
    std::cout << s << *this << std::endl;
}

Now we can use Vec2 as a function:
Vec2 a{1.0, 2.5};
a("Terrible Vector");</pre>
```

Any better uses for **operator()**? OpenCV and Eigen use it often.

operator double (Cast operator to double)

```
Member operator (of class Vec2): Casts Vec2 to double, "inverse constructor".
double len() { // A regular method: Norm of the vector
    return std::sqrt(x*x + y*y);
explicit operator double() noexcept {
    return len();
explicit version can only be used in explicit casts:
Vec2 a{1.0, 2.5};
double d1 = (double) a;
                                      // OK
double d2 = static cast<double>( a ); // OK
double d3 = a;
                                  // ERROR! Forbidden by explicit!
                                  // ERROR! Forbidden by explicit!
double d4 = sqrt(a);
Without explicit: can be used for implicit type conversions! Dangerous!
```

operator bool

```
Member operator (of class Vec2 ): Casts Vec2 to bool.
explicit operator bool() noexcept {
    return x || y; // false is x == y == 0
Usage:
Vec2 a{1.0, 2.5};
bool b1 = (bool) a;
                                  // OK
bool b2 = static cast<bool>(a); // OK
bool b3 = a;
                              // ERROR! Forbidden by explicit!
Principle function of operator bool: use in if statements.
if and ?: work fine even with explicit:
if (a) ... // OK
int z = a ? 13 : 25; // OK
```

Vec2 is now complete! Hurray!

The rule of five (previously "three")

Normally, a class has the following default methods (auto-created by the compiler)

- copy constructor (copy all fields)
- move constructor (move all fields)
- copy assignment (copy all fields)
- move assignment (move all fields)
- destructor (empty)

Rule of five: If you implement *any* of these methods, the defaults are no longer generated, you will have to implement *all* of them. Idea: you might have custom memory management, or some external resources (streams, sockets), thus default behavior is wrong.

Use **default** + **delete** to override this behavior if needed.

Note: This has nothing to do with the default (no-param) Ctor, like **Warrior()**. It is generated if and only if there are no other (explicitly defined) constructors. Nothing like this in our **Vec2**! Only default copy behavior which copies two fields!

Copy and move constructors and assignment operators

```
Tjej(const Tjej & rhs) : name(rhs.name) {}  // Copy Ctor
Tjej(Tjej && rhs): name(std::move(rhs.name)){} // Move Ctor
Tjej & operator= (const Tjej & rhs) { // Copy assignment
   if (this != &rhs) // Check for self-assignment
       name = rhs.name;
   return *this;
Tjej & operator= (Tjej && rhs) { // Move assignment
   if (this != &rhs) // Check for self-assignment
    name = std::move(rhs.name);
   return *this;
```

Tjej && is an *rvalue* reference, e.g. ref to temp object, e.g. Tjej("Bettan")

Terminology comes from C: Ivalue = rvalue;

For example: w = Tjej("Bettan");

Classes with custom memory usage?

Our first example **Vec2** had no custom memory management. Many classes do though. How to create one?

sizeof(C) is determined at compile time for every C++ class C!
You cannot change the size of the object or set it at runtime!
But dynamic data size is possible with the heap, new[] and delete[] (or malloc/free).

Warning: For your data it is better to use existing **vector** or **cv::Mat** something!

Just make a **vector** field in your class. Don't reinvent the wheel!


Example 2 below (**IntBox**) is just for better understanding!

Don't try to reproduce it in real life!

Classes which use the heap. How do they behave when copied? Value behaviour: **vector** and other C++ containers. Copies data. Pointer behavior: **cv::Mat**, **shared ptr**. Copies reference, not data.


Unique behavior: unique_ptr, istream, ostream. Cannot be copied.

Class with heap resources:



What happens to the heap data when we copy an object?


Unique object: Copying is forbidden



unique_ptr, istream, ostream

If you have a **unique_ptr** field, object of your class cannot be copied!


Value behavior: Copy resources



std::vector and most containers behave like this.

You can use container (e.g. **std::vector**) fields in your class for value behavior.

Pointer behavior: Do not copy resources



shared_ptr and cv::Mat (from OpenCV) behave like this. You have to count references !
Use shared_ptr fields in your class for pointer behavior !

Example 2: Implementing value behavior with raw pointers.


Let us design our own class: a trivial container for an int value.

But it uses heap memory. Can be empty (nullptr).

Let us manage heap with raw pointers (reinventing the wheel!).

```
class IntBox{
public:
    IntBox() { } // Empty Ctor
    IntBox(int n): data(new int(n)) { } // Ctor, creates new heap object
                 // Dtor
    ~IntBox(){
           if (data) // nullptr check
              delete data;
private:
    int * data = nullptr; // Pointer to data, nullptr if empty
```

Can we copy InBox using default copy ctor+assignment?



Two pointers to a heap object! Double **delete** by the destructor!!! And we wanted to COPY the heap data! Pointer is copied instead!

clear() method makes IntBox empty

```
class IntBox{
public:
     void clear(){
          if (data) { // nullptr check
                delete data; // Free the heap memory
                data = nullptr; // Don't forget to set data to nullptr
private:
     int * data = nullptr; // Pointer to data, nullptr if empty
```

Copy and move constructors:

```
Copy constructor: clone a heap object
IntBox(const IntBox & rhs) { // Copy Ctor : Deep Clone
    if (rhs.data) { // If rhs is not empty
       data = new int(*rhs. data); // Deep clone the heap object
    } // Otherwise data stays nullptr
Move constructor, move heap block from rhs to *this:
IntBox(IntBox && rhs) {
    data = rhs. data:
                                  // Copy the pointer from rhs to *this!
    rhs. data = nullptr;
                                  // Set rhs to empty without delete!
```

Copy assignment (operator=)

```
IntBox & operator=(const IntBox & rhs) {
    if (this != &rhs) { // Check for self-assign
                // Clear self first! Before any copy/move!
       clear();
      if (rhs.data) { // If rhs is not empty
         data = new int(*rhs.data); // Deep clone the heap object
       } // Otherwise data stays nullptr
    return *this; // As usual, return self by ref
```

Self - assignment: **a = a**; We must always check for this stupid possibility!

Otherwise something will always go wrong.

For example, **clear()** will screw up things!

Move assignment (operator=)

Extra slides: Implementing efficient swap(

C++ numerics : special algorithms

```
Sum all numbers in a container:
vector<double> v{1., 2., 4., 7., 10.};
double res = accumulate(cbegin(v), cend(v), 0.);
Product of all numbers in a container: use lambda, start with 1:
accumulate(cbegin(v), cend(v), 1., [](double x, double y) {return x*y;});
Product of all numbers in a container: use std::multiplies (wrapper of *):
accumulate(cbegin(v), cend(v), 1., multiplies<int>());
Range : create vector {2., 3., .. , 11.}:
iota(v.begin(), v.end(), 2.);
```

Scalar product of two vectors: inner_product(cbegin(v1), cend(v1), cbegin(v2), 0.)

Read yourself: more numerics, complex, cmath. But use Eigen for linear algebra!

Technology of the day: Profiling

- Profiling = Run your code and examine CPU time usage.
- !!! Profiling takes skills !!! It is easy to misunderstand the results !!!
- Flat profile = CPU time used by each function + number of calls.
- Call tree = All function calls (number+time) in each function.
- Self time = Time spent by the function itself (excluding other function).
- Inclusive (cumulative) time = Time spent by the function, including function it calls.

Profiling is typically done in Release:

cmake -DCMAKE BUILD TYPE=Release ..

But with debug symbols!

set(CMAKE_CXX_FLAGS_RELEASE "\${CMAKE_CXX_FLAGS_RELEASE} -g")

Pitfalls:

- 1. C++ names (labdas, templates, namespaces etc.)
- 2. Threads
- 3. Calling functions from external .so libraries (e.g. OpenCV), gprof has problems with that

Using gprof (Built-in profiler for gcc, probably not the best)

1. Set compiler flags "-pg" in CMakeLists.txt:

```
set(CMAKE_CXX_FLAGS_RELEASE "${CMAKE_CXX_FLAGS_RELEASE} -pg")
```

2. Run the program (generates file gmon.out):

./demo

3. Run the profiler:

gprof ./demo gmon.out > analysis.txt

Result: flat profile and call tree (Note: C++ names hurt!):

Flat profile:

```
Each sample counts as 0.01 seconds.
% cumulative self self total
time seconds seconds calls ms/call ms/call name
55.56 1.30 1.30 4002 0.32 0.32 std::_Function_handler<std::unique_ptr<std::__future_base::_Result_base,
std::__future_base::_Result_base::_Deleter> (),
std::__future_base::_Task_setter<std::unique_ptr<std::__future_base::_Result<unsigned long>,
std::__future_base::_Result_base::_Deleter>, std::__future_base::_Task_statelinelib::mcmlsd::findMax(double*, unsigned long*,
unsigned long, ctpl::thread_pool&)::{lambda(int)#1}, std::allocator<int>, unsigned long (int)>::_M_run(int&&)::{lambda()#1},
unsigned long> >::_M_invoke(std::_Any_data const&)
```

Using google profiler (gperftools)

1. Set compiler flags "-g" in CMakeLists.txt (no -p!):

set(CMAKE_CXX_FLAGS_RELEASE "\${CMAKE_CXX_FLAGS_RELEASE} -g")

2. Run the program with the profiler, generate file main.prof:


LD_PRELOAD=/usr/lib/x86_64-linux-gnu/libprofiler.so.0 CPUPROFILE=main.prof demo

3. Output the profile info in callgrind format (also available : text, PS etc.):

google-pprof --callgrind ./demo main.prof > demo.callgrind

4. View the callgrind profile using KCacheGrind (nice interactive GUI):

kcachegrind demo.callgrind &



Using valgrind

Valgrind runs programs in a x64 emulator (20-30 times slower). It has many tools:

Look for memory leaks (memcheck, the default tool): valgrind demo 2>result.txt

CPU usage profiling (callgrind):

valgrind --tool=callgrind demo

kcachegrind callgrind.out.12653

CPU cache profiling (cachegrind):

valgrind --tool=cachegrind demo

kcachegrind cachegrind.out.13200

Other GUI tools: Valkyrie, Alleyoop for memcheck.

Thank you for your attention!



Implementing efficient swap()

```
void swap(IntBox &lhs, IntBox &rhs) noexcept {
  using std::swap;
  swap(lhs.data, rhs.data);
                                 // Swap pointers, uses std::swap
Usage:
using std::swap; // Or using namespace std;
IntBox a(17), b(42);
swap(a, b); // NOT std::swap() !!!
std::swap() is not very efficient.
We use swap() for a class specific version of swap.
```

We fall back to **std::swap()** if no class-specific version exists.