Guía de como recuperar datos de un servidor dedicado con Centos en modo rescate

1.- Conectarnos por consola ssh

```
rescue on 82.165.194.211:/mnt

login as: root
root@_______info's password:
Linux rescue 3.16.48 #2 SMP Fri Sep 29 13:37:50 UTC 2017 x86_64

The programs included with the Debian GNU/Linux system are free software; the exact distribution terms for each program are described in the individual files in /usr/share/doc/*/copyright.

Debian GNU/Linux comes with ABSOLUTELY NO WARRANTY, to the extent permitted by applicable law.
```

2.- Obtenemos información Conectarnos por consola ssh

rescue on xxx.yyy.zzz.rrr:/\$ lshw -short

system D2721-H1 /0 bus D2721-H1 /0/0 memory 109KiB BIOS /0/3 processor Dual-Core AMD Opteron(tm) Processor 1218 HE /0/3/5 memory 256KiB L1 cache /0/3/6 memory 2MiB L2 cache /0/22 memory 4GiB System Memory /0/22/0 memory 1GiB DIMM DDR2 Synchronous /0/22/1 memory 1GiB DIMM DDR2 /0/22/2 memory 1GiB DIMM DDR2 /0/22/3 memory 1GiB DIMM DDR2 /0/22/3 memory 1GiB DIMM DDR2 /0/4 memory RAM memory /0/1 bridge MCP78S [GeForce 8200] LPC Bridge /0/1.1 bus MCP78S [GeForce 8200] SMBus /0/1.2 memory RAM memory
/0/0 memory 109KiB BIOS /0/3 processor Dual-Core AMD Opteron(tm) Processor 1218 HE /0/3/5 memory 256KiB L1 cache /0/3/6 memory 2MiB L2 cache /0/22 memory 4GiB System Memory /0/22/0 memory 1GiB DIMM DDR2 Synchronous /0/22/1 memory 1GiB DIMM DDR2 /0/22/2 memory 1GiB DIMM DDR2 /0/22/3 memory 1GiB DIMM DDR2 Synchronous /0/22/3 memory 1GiB DIMM DDR2 /0/4 memory RAM memory /0/1 bridge MCP78S [GeForce 8200] LPC Bridge /0/1.1 bus MCP78S [GeForce 8200] SMBus
processor Dual-Core AMD Opteron(tm) Processor 1218 HE /0/3/5 memory 256KiB L1 cache /0/3/6 memory 2MiB L2 cache /0/22 memory 4GiB System Memory /0/22/0 memory 1GiB DIMM DDR2 Synchronous /0/22/1 memory 1GiB DIMM DDR2 /0/22/2 memory 1GiB DIMM DDR2 /0/22/2 memory 1GiB DIMM DDR2 /0/22/3 memory 1GiB DIMM DDR2 /0/4 memory RAM memory /0/1 bridge MCP78S [GeForce 8200] LPC Bridge /0/1.1 bus MCP78S [GeForce 8200] SMBus
/0/3/5 memory 256KiB L1 cache /0/3/6 memory 2MiB L2 cache /0/22 memory 4GiB System Memory /0/22/0 memory 1GiB DIMM DDR2 Synchronous /0/22/1 memory 1GiB DIMM DDR2 /0/22/2 memory 1GiB DIMM DDR2 Synchronous /0/22/3 memory 1GiB DIMM DDR2 Synchronous /0/22/3 memory 1GiB DIMM DDR2 /0/4 memory RAM memory /0/1 bridge MCP78S [GeForce 8200] LPC Bridge /0/1.1 bus MCP78S [GeForce 8200] SMBus
/0/3/6 memory 2MiB L2 cache /0/22 memory 4GiB System Memory /0/22/0 memory 1GiB DIMM DDR2 Synchronous /0/22/1 memory 1GiB DIMM DDR2 /0/22/2 memory 1GiB DIMM DDR2 Synchronous /0/22/3 memory 1GiB DIMM DDR2 /0/4 memory RAM memory /0/1 bridge MCP78S [GeForce 8200] LPC Bridge /0/1.1 bus MCP78S [GeForce 8200] SMBus
/0/22 memory 4GiB System Memory /0/22/0 memory 1GiB DIMM DDR2 Synchronous /0/22/1 memory 1GiB DIMM DDR2 /0/22/2 memory 1GiB DIMM DDR2 Synchronous /0/22/3 memory 1GiB DIMM DDR2 /0/4 memory RAM memory /0/1 bridge MCP78S [GeForce 8200] LPC Bridge /0/1.1 bus MCP78S [GeForce 8200] SMBus
/0/22/0 memory 1GiB DIMM DDR2 Synchronous /0/22/1 memory 1GiB DIMM DDR2 /0/22/2 memory 1GiB DIMM DDR2 Synchronous /0/22/3 memory 1GiB DIMM DDR2 /0/4 memory RAM memory /0/1 bridge MCP78S [GeForce 8200] LPC Bridge /0/1.1 bus MCP78S [GeForce 8200] SMBus
/0/22/1 memory 1GiB DIMM DDR2 /0/22/2 memory 1GiB DIMM DDR2 Synchronous /0/22/3 memory 1GiB DIMM DDR2 /0/4 memory RAM memory /0/1 bridge MCP78S [GeForce 8200] LPC Bridge /0/1.1 bus MCP78S [GeForce 8200] SMBus
/0/22/2 memory 1GiB DIMM DDR2 Synchronous /0/22/3 memory 1GiB DIMM DDR2 /0/4 memory RAM memory /0/1 bridge MCP78S [GeForce 8200] LPC Bridge /0/1.1 bus MCP78S [GeForce 8200] SMBus
/0/22/3 memory 1GiB DIMM DDR2 /0/4 memory RAM memory /0/1 bridge MCP78S [GeForce 8200] LPC Bridge /0/1.1 bus MCP78S [GeForce 8200] SMBus
/0/4 memory RAM memory /0/1 bridge MCP78S [GeForce 8200] LPC Bridge /0/1.1 bus MCP78S [GeForce 8200] SMBus
/0/1 bridge MCP78S [GeForce 8200] LPC Bridge /0/1.1 bus MCP78S [GeForce 8200] SMBus
/0/1.1 bus MCP78S [GeForce 8200] SMBus
/0/1.2 memory RAM memory
/0/1.4 memory RAM memory
/0/2 bus MCP78S [GeForce 8200] OHCI USB 1.1 Controll
/0/2/1 usb3 bus OHCI PCI host controller
/0/2.1 bus MCP78S [GeForce 8200] EHCI USB 2.0 Controll
/0/2.1/1 usb1 bus EHCI Host Controller
/0/5 bus MCP78S [GeForce 8200] OHCI USB 1.1 Controll
/0/5/1 usb4 bus OHCI PCI host controller
/0/4.1 bus MCP78S [GeForce 8200] EHCI USB 2.0 Controll
/0/4.1/1 usb2 bus EHCI Host Controller
/0/7 multimedia MCP72XE/MCP72P/MCP78U/MCP78S High Defini
/0/8 bridge MCP78S [GeForce 8200] PCI Bridge

/0/9	storage	MCP78S [GeForce 8200] SATA Controller (non-	
/0/b	bridge	MCP78S [GeForce 8200] PCI Express Bridge	
/0/b/0	display	C77 [GeForce 8200]	
/0/10	bridge	MCP78S [GeForce 8200] PCI Express Bridge	
/0/12	bridge	MCP78S [GeForce 8200] PCI Express Bridge	
/0/13	bridge	MCP78S [GeForce 8200] PCI Bridge	
/0/13/0 eth0	netwo	rk NetLink BCM5787 Gigabit Ethernet PCI Expres	
/0/100	bridge	K8 [Athlon64/Opteron] HyperTransport Techno	
/0/101	bridge	K8 [Athlon64/Opteron] Address Map	
/0/102	bridge	K8 [Athlon64/Opteron] DRAM Controller	
/0/103	bridge	K8 [Athlon64/Opteron] Miscellaneous Control	
/0/6 scsi0	storage		
/0/6/0.0.0 /dev/sda disk 500GB ST3500418AS			
/0/6/0.0.0/1 /de	v/sda1 vo	olume 4GiB EXT3 volume	
/0/6/0.0.0/2 /dev/sda2 volume 2GiB Linux swap volume			
/0/6/0.0.0/3 /dev/sda3 volume 459GiB Linux raid autodetect partition			
/0/a scsi1 storage			
/0/a/0.0.0 /dev/sdb disk 500GB ST3500418AS			
/0/a/0.0.0/1 /dev/sdb1 volume 4GiB EXT3 volume			
/0/a/0.0.0/2 /dev/sdb2 volume 2GiB Linux swap volume			
/0/a/0.0.0/3 /dev/sdb3 volume 459GiB Linux raid autodetect partition			

Tenemos dos discos duro de 500 Gb

3.- Comprobar el estado del software RAID

\$ cat /proc/mdstat

\$ lsblk

```
:~$ lsblk
rescue on
NAME
                MAJ:MIN RM
                              SIZE RO TYPE
                                             MOUNTPOINT
sda
                   8:0
                          0 465.8G
                                       disk
  sdal
                   8:1
                                 4G
                                     0 part
                   9:1
                                 4G
                                    0 raidl
  L_md1
  sda2
                   8:2
                                2G
                                    0 part
  sda3
                   8:3
                          0 459.8G
                                     0 part
  L_md3
                   9:3
                          0 459.8G
                                     0 raidl
                               21G
     -vg00-usr
                252:0
                                     0 lvm
                              230G
      vg00-var
               252:1
                                       lvm
      vg00-home 252:2
                                10G
                                     0 lvm
                          0 465.8G
sdb
                   8:16
                                     0 disk
                  8:17
                                4G
                                     0 part
  -sdbl
  ∟md1
                  9:1
                                4G
                                     0 raidl
  sdb2
                  8:18
                                2G
                                     0 part
  sdb3
                   8:19
                          0 459.8G
                                     0 part
   -md3
                   9:3
                          0 459.8G
      vg00-usr
                252:0
                          0
                               21G
                                       lvm
                 252:1
                              230G
      vg00-var
                                     0 lvm
      -vg00-home 252:2
                                10G
                                     0 lvm
```

Dos discos duros de 500 Gb montados en raid1

4.- Mostrar particiones

rescue on xx.yyy.zzz.rrr:~\$ fdisk -l

Disk /dev/sdb: 465.8 GiB, 500107862016 bytes, 976773168 sectors

Units: sectors of 1 * 512 = 512 bytes

Sector size (logical/physical): 512 bytes / 512 bytes

I/O size (minimum/optimal): 512 bytes / 512 bytes

Disklabel type: dos

Disk identifier: 0xa7f4baa4

Device Boot Start End Sectors Size Id Type

/dev/sdb1 2048 8390655 8388608 4G fd Linux raid autodetect

/dev/sdb2 8390656 12584959 4194304 2G 82 Linux swap / Solaris

/dev/sdb3 12584960 976773167 964188208 459.8G fd Linux raid autodetect

Disk /dev/sda: 465.8 GiB, 500107862016 bytes, 976773168 sectors

Units: sectors of 1 * 512 = 512 bytes

Sector size (logical/physical): 512 bytes / 512 bytes

I/O size (minimum/optimal): 512 bytes / 512 bytes

Disklabel type: dos

Disk identifier: 0xc201ef99

Device Boot Start End Sectors Size Id Type

/dev/sda1 2048 8390655 8388608 4G fd Linux raid autodetect

/dev/sda2 8390656 12584959 4194304 2G 82 Linux swap / Solaris

/dev/sda3 12584960 976773167 964188208 459.8G fd Linux raid autodetect

Disk /dev/md3: 459.8 GiB, 493664272384 bytes, 964188032 sectors

Units: sectors of 1 * 512 = 512 bytes

Sector size (logical/physical): 512 bytes / 512 bytes

I/O size (minimum/optimal): 512 bytes / 512 bytes

Disk /dev/md1: 4 GiB, 4294901760 bytes, 8388480 sectors

Units: sectors of 1 * 512 = 512 bytes

Sector size (logical/physical): 512 bytes / 512 bytes

I/O size (minimum/optimal): 512 bytes / 512 bytes

Disk /dev/mapper/vg00-usr: 21 GiB, 22548578304 bytes, 44040192 sectors

Units: sectors of 1 * 512 = 512 bytes

Sector size (logical/physical): 512 bytes / 512 bytes

I/O size (minimum/optimal): 512 bytes / 512 bytes

Disk /dev/mapper/vg00-var: 230 GiB, 246960619520 bytes, 482344960 sectors

Units: sectors of 1 * 512 = 512 bytes

Sector size (logical/physical): 512 bytes / 512 bytes

I/O size (minimum/optimal): 512 bytes / 512 bytes

Disk /dev/mapper/vg00-home: 10 GiB, 10737418240 bytes, 20971520 sectors

Units: sectors of 1 * 512 = 512 bytes

Sector size (logical/physical): 512 bytes / 512 bytes

I/O size (minimum/optimal): 512 bytes / 512 bytes

En el Sistema hay dos discos duros de 500 Gb en raid 1 y sobre este hay montado 1 unidades lógicas vg00

Listado de los volúmenes

\$ pvscan

\$ vgs

\$ pvs

\$ pvdisplay

```
PV /dev/md3 VG vq00
                                  lvm2 [459.76 GiB / 198.76 GiB free]
 Total: 1 [459.76 GiB] / in use: 1 [459.76 GiB] / in no VG: 0 [0
escue on
                       :~$ pvs
            VG Fmt Attr PSize
                                   PFree
            vg00 lvm2 a-- 459.76g 198.76g
 /dev/md3
                       :~$ pvdisplay
rescue on
 --- Physical volume --
 PV Name
                       /dev/md3
 VG Name
                       vg00
 PV Size
                       459.76 GiB / not usable 2.94 MiB
 Allocatable
                       yes
 PE Size
                       4.00 MiB
 Total PE
                       117698
 Free PE
                       50882
 Allocated PE
                       66816
 PV UUID
                       smuDeL-XAPd-DKjj-i90B-J13d-1Xyp-RXk0Uw
```

Mostrar físicamente la ubicación de la partición lógica

```
rescue on :~$ 1s /dev/vg00 -al

total 0

drwxr-xr-x 2 root root 100 May 18 02:41 .

drwxr-xr-x 15 root root 13720 May 18 02:41 ..

lrwxrwxrwx 1 root root 7 May 18 02:41 home -> ../dm-2

lrwxrwxrwx 1 root root 7 May 18 02:41 usr -> ../dm-0

lrwxrwxrwx 1 root root 7 May 18 02:41 var -> ../dm-1
```

El volumen lógico vg00 tienes las siguientes particiones /home /usr y /var

5.- Mostrar volúmenes y montarlos

\$ lvm vgscan -v

Escanear los volúmennes que hay disponibles

```
rescue on :~$ lvm vgscan -v
Wiping cache of LVM-capable devices
Wiping internal VG cache
Reading volume groups from cache.
Found volume group "vg00" using metadata type lvm2
```

\$ vgchange -a y "vg00"

Activar los grupos creados

```
rescue on :~$ vgchange -a y "vg00"

3 logical volume(s) in volume group "vg00" now active
```

Listar los volúmenes lógicos

\$ lvm lvs -all

```
rescue on :~$ lvm lvs --all

LV VG Attr LSize Pool Origin Data% Meta% Move Log Cpy%Sync Convert
home vg00 -wi-a---- 10.00g
usr vg00 -wi-a---- 21.00g
var vg00 -wi-a---- 230.00g
```

Crear las carpetas donde se colocará las particiones

```
rescue on :~$ ls /mnt -al
total 24
drwxr-xr-x 6 root root 4096 May 20 10:44 .
drwxr-xr-x 20 root root 4096 May 18 02:41 ..
drwxr-xr-x 2 root root 4096 May 20 10:44 home
drwxr-xr-x 2 root root 4096 May 20 10:37 root
drwxr-xr-x 2 root root 4096 May 20 10:44 usr
drwxr-xr-x 2 root root 4096 May 20 10:44 var
```

Montaje de los volúmenes lógicos

```
rescue on f :~$ mount /dev/vg00/usr /mnt/usr
rescue on :~$ mount /dev/vg00/home /mnt/home
rescue on ; :~$ mount /dev/vg00/var /mnt/var
```

6.- Accedemos al servidor por sftp con winscp

