

Chapter 1. INTRODUCTION

The cuBLAS library is an implementation of BLAS (Basic Linear Algebra Subprograms) on top of the NVIDIA $^{\mathbb{R}}$ CUDA $^{\mathbb{T}^{\mathbb{M}}}$ runtime. It allows the user to access the computational resources of NVIDIA Graphics Processing Unit (GPU).

Starting with CUDA 6.0, the cuBLAS Library now exposes two sets of API, the regular cuBLAS API which is simply called cuBLAS API in this document and the CUBLASXT API.

To use the cuBLAS API, the application must allocate the required matrices and vectors in the GPU memory space, fill them with data, call the sequence of desired cuBLAS functions, and then upload the results from the GPU memory space back to the host. The cuBLAS API also provides helper functions for writing and retrieving data from the GPU.

To use the CUBLASXT API, the application must keep the data on the Host and the Library will take care of dispatching the operation to one or multiple GPUS present in the system, depending on the user request.

1.1. Data layout

For maximum compatibility with existing Fortran environments, the cuBLAS library uses column-major storage, and 1-based indexing. Since C and C++ use row-major storage, applications written in these languages can not use the native array semantics for two-dimensional arrays. Instead, macros or inline functions should be defined to implement matrices on top of one-dimensional arrays. For Fortran code ported to C in mechanical fashion, one may chose to retain 1-based indexing to avoid the need to transform loops. In this case, the array index of a matrix element in row "i" and column "j" can be computed via the following macro

```
#define IDX2F(i,j,ld) ((((j)-1)*(ld))+((i)-1))
```

Here, ld refers to the leading dimension of the matrix, which in the case of column-major storage is the number of rows of the allocated matrix (even if only a submatrix of it is being used). For natively written C and C++ code, one would most likely choose 0-based

indexing, in which case the array index of a matrix element in row "i" and column "j" can be computed via the following macro

#define IDX2C(i,j,ld) (((j)*(ld))+(i))

1.2. New and Legacy cuBLAS API

Starting with version 4.0, the cuBLAS Library provides a new updated API, in addition to the existing legacy API. This section discusses why a new API is provided, the advantages of using it, and the differences with the existing legacy API.

The new cuBLAS library API can be used by including the header file "cublas_v2.h". It has the following features that the legacy cuBLAS API does not have:

- the handle to the cuBLAS library context is initialized using the function and is explicitly passed to every subsequent library function call. This allows the user to have more control over the library setup when using multiple host threads and multiple GPUs. This also allows the cuBLAS APIs to be reentrant.
- the scalars α and β can be passed by reference on the host or the device, instead of only being allowed to be passed by value on the host. This change allows library functions to execute asynchronously using streams even when α and β are generated by a previous kernel.
- when a library routine returns a scalar result, it can be returned by reference on the host or the device, instead of only being allowed to be returned by value only on the host. This change allows library routines to be called asynchronously when the scalar result is generated and returned by reference on the device resulting in maximum parallelism.
- the error status cublasStatus_t is returned by all cuBLAS library function calls. This change facilitates debugging and simplifies software development. Note that cublasStatus was renamed cublasStatus_t to be more consistent with other types in the cuBLAS library.
- the cublasAlloc() and cublasFree() functions have been deprecated.
 This change removes these unnecessary wrappers around cudaMalloc() and cudaFree(), respectively.
- the function cublasSetKernelStream() was renamed cublasSetStream() to be more consistent with the other CUDA libraries.

The legacy cuBLAS API, explained in more detail in the Appendix A, can be used by including the header file "cublas.h". Since the legacy API is identical to the previously released cuBLAS library API, existing applications will work out of the box and automatically use this legacy API without any source code changes. In general, new applications should not use the legacy cuBLAS API, and existing existing applications should convert to using the new API if it requires sophisticated and optimal stream parallelism or if it calls cuBLAS routines concurrently from multiple threads. For the rest of the document, the new cuBLAS Library API will simply be referred to as the cuBLAS Library API.

As mentioned earlier the interfaces to the legacy and the cuBLAS library APIs are the header file "cublas.h" and "cublas_v2.h", respectively. In addition, applications using the cuBLAS library need to link against the DSO cublas.so (Linux), the DLL cublas.dll

(Windows), or the dynamic library cublas.dylib (Mac OS X). Note: the same dynamic library implements both the new and legacy cuBLAS APIs.

1.3. Example code

Example 1. Application Using C and CUBLAS: 1-based indexing.

```
//Example 1. Application Using C and CUBLAS: 1-based indexing
#include <stdio.h>
#include <stdlib.h>
#include <math.h>
#include <cuda runtime.h>
#include "cublas v2.h"
#define M 6
#define N 5
#define IDX2F(i,j,ld) ((((j)-1)*(ld))+((i)-1))
        __inline__ void modify (cublasHandle_t handle, float *m, int ldm, int
n, int p, int q, float alpha, float beta) {
   cublasSscal (handle, n-p+1, &alpha, &m[IDX2F(p,q,ldm)], ldm);
    cublasSscal (handle, ldm-p+1, &beta, &m[IDX2F(p,q,ldm)], 1);
int main (void) {
   cudaError_t cudaStat;
   cublasStatus_t stat;
   cublasHandle t handle;
   int i, j;
   float* devPtrA;
   float* a = 0;
   a = (float *)malloc (M * N * sizeof (*a));
    if (!a) {
       printf ("host memory allocation failed");
       return EXIT FAILURE;
    for (j = 1; j <= N; j++) {</pre>
        for (i = 1; i <= M; i++) {</pre>
            a[IDX2F(i,j,M)] = (float)((i-1) * M + j);
   cudaStat = cudaMalloc ((void**)&devPtrA, M*N*sizeof(*a));
    if (cudaStat != cudaSuccess) {
        printf ("device memory allocation failed");
        return EXIT FAILURE;
   stat = cublasCreate(&handle);
    if (stat != CUBLAS_STATUS_SUCCESS) {
        printf ("CUBLAS initialization failed\n");
        return EXIT FAILURE;
   stat = cublasSetMatrix (M, N, sizeof(*a), a, M, devPtrA, M);
    if (stat != CUBLAS_STATUS_SUCCESS) {
        printf ("data download failed");
        cudaFree (devPtrA);
       cublasDestroy(handle);
       return EXIT FAILURE;
   modify (handle, devPtrA, M, N, 2, 3, 16.0f, 12.0f);
    stat = cublasGetMatrix (M, N, sizeof(*a), devPtrA, M, a, M);
    if (stat != CUBLAS STATUS SUCCESS) {
       printf ("data upload failed");
        cudaFree (devPtrA);
        cublasDestroy(handle);
        return EXIT FAILURE;
   cudaFree (devPtrA);
   cublasDestroy(handle);
   for (j = 1; j <= N; j++) {
   for (i = 1; i <= M; i++) {</pre>
            printf ("%7.0f", a[IDX2F(i,j,M)]);
        printf ("\n");
    free(a);
```

1.4. Example code

Example 2. Application Using C and CUBLAS: 0-based Indexing.

```
//Example 2. Application Using C and CUBLAS: 0-based indexing
#include <stdio.h>
#include <stdlib.h>
#include <math.h>
#include <cuda runtime.h>
#include "cublas v2.h"
#define M 6
#define N 5
#define IDX2C(i,j,ld) (((j)*(ld))+(i))
static __inline__ void modify (cublasHandle_t handle, float *m, int ldm, int
n, int p, int q, float alpha, float beta) {
    cublasSscal (handle, n-p, &alpha, &m[IDX2C(p,q,ldm)], ldm);
    cublasSscal (handle, ldm-p, &beta, &m[IDX2C(p,q,ldm)], 1);
int main (void) {
    cudaError t cudaStat;
    cublasStatus t stat;
    cublasHandle_t handle;
    int i, j;
    float* devPtrA;
    float* a = 0;
    a = (float *)malloc (M * N * sizeof (*a));
    if (!a) {
        printf ("host memory allocation failed");
        return EXIT FAILURE;
    for (j = 0; j < N; j++) {
        for (i = 0; i < M; i++) {
            a[IDX2C(i,j,M)] = (float)(i * M + j + 1);
    cudaStat = cudaMalloc ((void**)&devPtrA, M*N*sizeof(*a));
    if (cudaStat != cudaSuccess) {
       printf ("device memory allocation failed");
        return EXIT FAILURE;
    stat = cublasCreate(&handle);
    if (stat != CUBLAS_STATUS_SUCCESS) {
        printf ("CUBLAS initialization failed\n");
        return EXIT FAILURE;
    stat = cublasSetMatrix (M, N, sizeof(*a), a, M, devPtrA, M);
    if (stat != CUBLAS STATUS SUCCESS) {
       printf ("data download failed");
        cudaFree (devPtrA);
        cublasDestroy(handle);
        return EXIT FAILURE;
    modify (handle, devPtrA, M, N, 1, 2, 16.0f, 12.0f);
    stat = cublasGetMatrix (M, N, sizeof(*a), devPtrA, M, a, M);
    if (stat != CUBLAS STATUS SUCCESS) {
        printf ("data upload failed");
        cudaFree (devPtrA);
        cublasDestroy(handle);
        return EXIT FAILURE;
    cudaFree (devPtrA);
    cublasDestroy(handle);
    for (j = 0; j < N; j++) {
        for (i = 0; i < M; i++) {</pre>
            printf ("%7.0f", a[IDX2C(i,j,M)]);
        printf ("\n");
    free(a);
    return EXIT SUCCESS;
```

Chapter 2. USING THE CUBLAS API

2.1. General description

This section describes how to use the cuBLAS library API. It does not contain a detailed reference for all API datatypes and functions—those are provided in subsequent chapters. The Legacy cuBLAS API is also not covered in this section—that is handled in an Appendix.

2.1.1. Error status

All cuBLAS library function calls return the error status cublasStatus t.

2.1.2. cuBLAS context

The application must initialize the **handle** to the cuBLAS library context by calling the **cublasCreate()** function. Then, the is explicitly passed to every subsequent library function call. Once the application finishes using the library, it must call the function **cublasDestory()** to release the resources associated with the cuBLAS library context.

This approach allows the user to explicitly control the library setup when using multiple host threads and multiple GPUs. For example, the application can use <code>cudaSetDevice()</code> to associate different devices with different host threads and in each of those host threads it can initialize a unique <code>handle</code> to the cuBLAS library context, which will use the particular device associated with that host thread. Then, the cuBLAS library function calls made with different <code>handle</code> will automatically dispatch the computation to different devices.

The device associated with a particular cuBLAS context is assumed to remain unchanged between the corresponding cublasCreate() and cublasDestory() calls. In order for the cuBLAS library to use a different device in the same host thread, the application must set the new device to be used by calling cudaSetDevice() and then create another cuBLAS context, which will be associated with the new device, by calling cublasCreate().

2.1.3. Thread Safety

The library is thread safe and its functions can be called from multiple host threads, even with the same handle. When multiple threads share the same handle, extreme care needs to be taken when the handle configuration is changed because that change will affect potentially subsequent CUBLAS calls in all threads. It is even more true for the destruction of the handle. So it is not recommended that multiple thread share the same CUBLAS handle.

2.1.4. Results reproducibility

By design, all CUBLAS API routines from a given toolkit version, generate the same bitwise results at every run when executed on GPUs with the same architecture and the same number of SMs. However, bit-wise reproducibility is not guaranteed across toolkit version because the implementation might differ due to some implementation changes.

For some routines such as **cublas<t>symv** and **cublas<t>hemv**, an alternate significantly faster routines can be chosen using the routine **cublasSetAtomicsMode()**. In that case, the results are not guaranteed to be bit-wise reproducible because atomics are used for the computation.

2.1.5. Scalar Parameters

There are two categories of the functions that use scalar parameters:

- functions that take alpha and/or beta parameters by reference on the host or the device as scaling factors, such as gemm
- functions that return a scalar result on the host or the device such as amax(), amin, asum(), rotg(), rotmg(), dot() and nrm2().

For the functions of the first category, when the pointer mode is set to <code>CUBLAS_POINTER_MODE_HOST</code>, the scalar parameters <code>alpha</code> and/or <code>beta</code> can be on the stack or allocated on the heap. Underneath the CUDA kernels related to that functions will be launched with the value of <code>alpha</code> and/or <code>beta</code>. Therefore if they were allocated on the heap, they can be freed just after the return of the call even though the kernel launch is asynchronous. When the pointer mode is set to <code>CUBLAS_POINTER_MODE_DEVICE</code>, <code>alpha</code> and/or <code>beta</code> must be accessible on the device and their values should not be modified until the kernel is done. Note that since <code>cudaFree()</code> does an implicit <code>cudaDeviceSynchronize()</code>, <code>cudaFree()</code> can still be called on <code>alpha</code> and/or <code>beta</code> just after the call but it would defeat the purpose of using this pointer mode in that case.

For the functions of the second category, when the pointer mode is set to <code>CUBLAS_POINTER_MODE_HOST</code>, these functions blocks the CPU, until the GPU has completed its computation and the results has been copied back to the Host. When the pointer mode is set to <code>CUBLAS_POINTER_MODE_DEVICE</code>, these functions return immediately. In this case, similarly to matrix and vector results, the scalar result is ready only when execution of the routine on the GPU has completed. This requires proper synchronization in order to read the result from the host.

In either case, the pointer mode <code>CUBLAS_POINTER_MODE_DEVICE</code> allows the library functions to execute completely asynchronously from the Host even when <code>alpha</code> and/or <code>beta</code> are generated by a previous kernel. For example, this situation can arise when iterative methods for solution of linear systems and eigenvalue problems are implemented using the cuBLAS library.

2.1.6. Parallelism with Streams

If the application uses the results computed by multiple independent tasks, CUDATM streams can be used to overlap the computation performed in these tasks.

The application can conceptually associate each stream with each task. In order to achieve the overlap of computation between the tasks, the user should create CUDATM streams using the function <code>cudaStreamCreate()</code> and set the stream to be used by each individual cuBLAS library routine by calling <code>cublasSetStream()</code> just before calling the actual cuBLAS routine. Then, the computation performed in separate streams would be overlapped automatically when possible on the GPU. This approach is especially useful when the computation performed by a single task is relatively small and is not enough to fill the GPU with work.

We recommend using the new cuBLAS API with scalar parameters and results passed by reference in the device memory to achieve maximum overlap of the computation when using streams.

A particular application of streams, batching of multiple small kernels, is described below.

2.1.7. Batching Kernels

In this section we will explain how to use streams to batch the execution of small kernels. For instance, suppose that we have an application where we need to make many small independent matrix-matrix multiplications with dense matrices.

It is clear that even with millions of small independent matrices we will not be able to achieve the same *GFLOPS* rate as with a one large matrix. For example, a single $n \times n$ large matrix-matrix multiplication performs n^3 operations for n^2 input size, while 1024

 $\frac{n}{32} \times \frac{n}{32}$ small matrix-matrix multiplications perform $1024 \left(\frac{n}{32}\right)^3 = \frac{n^3}{32}$ operations for the same input size. However, it is also clear that we can achieve a significantly better performance with many small independent matrices compared with a single small matrix.

The architecture family of GPUs allows us to execute multiple kernels simultaneously. Hence, in order to batch the execution of independent kernels, we can run each of them in a separate stream. In particular, in the above example we could create 1024 CUDATM streams using the function cudaStreamCreate(), then preface each call to cublas<t>gemm() with a call to cublasSetStream() with a different stream for each of the matrix-matrix multiplications. This will ensure that when possible the different computations will be executed concurrently. Although the user can create many streams, in practice it is not possible to have more than 16 concurrent kernels executing at the same time.

2.1.8. Cache configuration

On some devices, L1 cache and shared memory use the same hardware resources. The cache configuration can be set directly with the CUDA Runtime function cudaDeviceSetCacheConfig. The cache configuration can also be set specifically for some functions using the routine cudaFuncSetCacheConfig. Please refer to the CUDA Runtime API documentation for details about the cache configuration settings.

Because switching from one configuration to another can affect kernels concurrency, the cuBLAS Library does not set any cache configuration preference and relies on the current setting. However, some cuBLAS routines, especially Level-3 routines, rely heavily on shared memory. Thus the cache preference setting might affect adversely their performance.

2.1.9. Device API Library

Starting with release 5.0, the CUDA Toolkit now provides a static cuBLAS Library cublas_device.a that contains device routines with the same API as the regular cuBLAS Library. Those routines use internally the Dynamic Parallelism feature to launch kernel from within and thus is only available for device with compute capability at least equal to 3.5.

In order to use those library routines from the device the user must include the header file "cublas_v2.h" corresponding to the new cuBLAS API and link against the static cuBLAS library cublas_device.a.

Those device cuBLAS library routines are called from the device in exactly the same way they are called from the host, with the following exceptions:

- ► The legacy cuBLAS API is not supported on the device.
- ▶ The pointer mode is not supported on the device, in other words, scalar input and output parameters must be allocated on the device memory.

Furthermore, the input and output scalar parameters must be allocated and released on the device using the cudaMalloc and cudaFree routines from the Host respectively or malloc and free routines from the device, in other words, they can not be passed by reference from the local memory to the routines.

2.1.10. Static Library support

Starting with release 6.5, the cuBLAS Library is also delivered in a static form as libcublas_static.a on Linux and Mac OSes. The static cuBLAS library and all others static maths libraries depend on a common thread abstraction layer library called libculibos.a.

For example, on Linux, to compile a small application using cuBLAS, against the dynamic library, the following command can be used:

nvcc myCublasApp.c -lcublas -o myCublasApp

Whereas to compile against the static cuBLAS library, the following command has to be used:

```
nvcc myCublasApp.c -lcublas_static -lculibos -o myCublasApp
```

It is also possible to use the native Host C++ compiler. Depending on the Host Operating system, some additional libraries like **pthread** or **d1** might be needed on the linking line. The following command on Linux is suggested:

```
g++ myCublasApp.c -lcublas_static -lculibos -lcudart_static -lpthread -ldl -I <cuda-toolkit-path>/include -L <cuda-toolkit-path>/lib64 -o myCublasApp
```

Note that in the latter case, the library **cuda** is not needed. The CUDA Runtime will try to open explicitly the **cuda** library if needed. In the case of a system which does not have the CUDA driver installed, this allows the application to gracefully manage this issue and potentially run if a CPU-only path is available.

2.2. cuBLAS Datatypes Reference

2.2.1. cublasHandle_t

The **cublasHandle_t** type is a pointer type to an opaque structure holding the cuBLAS library context. The cuBLAS library context must be initialized using **cublasCreate()** and the returned handle must be passed to all subsequent library function calls. The context should be destroyed at the end using **cublasDestroy()**.

2.2.2. cublasStatus_t

The type is used for function status returns. All cuBLAS library functions return their status, which can have the following values.

Value	Meaning
CUBLAS_STATUS_SUCCESS	The operation completed successfully.
CUBLAS_STATUS_NOT_INITIALIZED	The cuBLAS library was not initialized. This is usually caused by the lack of a prior cublasCreate() call, an error in the CUDA Runtime API called by the cuBLAS routine, or an error in the hardware setup. To correct: call cublasCreate() prior to the
	function call; and check that the hardware, an appropriate version of the driver, and the cuBLAS library are correctly installed.
CUBLAS_STATUS_ALLOC_FAILED	Resource allocation failed inside the cuBLAS library. This is usually caused by a cudaMalloc() failure.
	To correct: prior to the function call, deallocate previously allocated memory as much as possible.

Value	Meaning
CUBLAS_STATUS_INVALID_VALUE	An unsupported value or parameter was passed to the function (a negative vector size, for example).
	To correct: ensure that all the parameters being passed have valid values.
CUBLAS_STATUS_ARCH_MISMATCH	The function requires a feature absent from the device architecture; usually caused by the lack of support for double precision.
	To correct: compile and run the application on a device with appropriate compute capability, which is 1.3 for double precision.
CUBLAS_STATUS_MAPPING_ERROR	An access to GPU memory space failed, which is usually caused by a failure to bind a texture.
	To correct: prior to the function call, unbind any previously bound textures.
CUBLAS_STATUS_EXECUTION_FAILED	The GPU program failed to execute. This is often caused by a launch failure of the kernel on the GPU, which can be caused by multiple reasons.
	To correct: check that the hardware, an appropriate version of the driver, and the cuBLAS library are correctly installed.
CUBLAS_STATUS_INTERNAL_ERROR	An internal cuBLAS operation failed. This error is usually caused by a cudaMemcpyAsync() failure.
	To correct: check that the hardware, an appropriate version of the driver, and the cuBLAS library are correctly installed. Also, check that the memory passed as a parameter to the routine is not being deallocated prior to the routine's completion.
CUBLAS_STATUS_NOT_SUPPORTED	The functionnality requested is not supported
CUBLAS_STATUS_LICENSE_ERROR	The functionnality requested requires some license and an error was detected when trying to check the current licensing. This error can happen if the license is not present or is expired or if the environment variable NVIDIA_LICENSE_FILE is not set properly.

2.2.3. cublasOperation_t

The cublasOperation_t type indicates which operation needs to be performed with the dense matrix. Its values correspond to Fortran characters 'N' or 'n' (non-transpose), 'T' or 't' (transpose) and 'C' or 'c' (conjugate transpose) that are often used as parameters to legacy BLAS implementations.

Value	Meaning
CUBLAS_OP_N	the non-transpose operation is selected
CUBLAS_OP_T	the transpose operation is selected

Value	Meaning
CUBLAS_OP_C	the conjugate transpose operation is selected

2.2.4. cublasFillMode_t

The type indicates which part (lower or upper) of the dense matrix was filled and consequently should be used by the function. Its values correspond to Fortran characters <code>'L'</code> or <code>'l'</code> (lower) and <code>'U'</code> or <code>'u'</code> (upper) that are often used as parameters to legacy BLAS implementations.

Value	Meaning
CUBLAS_FILL_MODE_LOWER	the lower part of the matrix is filled
CUBLAS_FILL_MODE_UPPER	the upper part of the matrix is filled

2.2.5. cublasDiagType_t

The type indicates whether the main diagonal of the dense matrix is unity and consequently should not be touched or modified by the function. Its values correspond to Fortran characters 'N' or 'n' (non-unit) and 'U' or 'u' (unit) that are often used as parameters to legacy BLAS implementations.

Value	Meaning
CUBLAS_DIAG_NON_UNIT	the matrix diagonal has non-unit elements
CUBLAS_DIAG_UNIT	the matrix diagonal has unit elements

2.2.6. cublasSideMode_t

The type indicates whether the dense matrix is on the left or right side in the matrix equation solved by a particular function. Its values correspond to Fortran characters 'L' or 'l' (left) and 'R' or 'r' (right) that are often used as parameters to legacy BLAS implementations.

Value	Meaning
CUBLAS_SIDE_LEFT	the matrix is on the left side in the equation
CUBLAS_SIDE_RIGHT	the matrix is on the right side in the equation

2.2.7. cublasPointerMode_t

The cublasPointerMode_t type indicates whether the scalar values are passed by reference on the host or device. It is important to point out that if several scalar values are present in the function call, all of them must conform to the same single pointer mode. The pointer mode can be set and retrieved using cublasSetPointerMode() and cublasGetPointerMode() routines, respectively.

Value	Meaning
CUBLAS_POINTER_MODE_HOST	the scalars are passed by reference on the host
CUBLAS_POINTER_MODE_DEVICE	the scalars are passed by reference on the device

2.2.8. cublasAtomicsMode_t

The type indicates whether cuBLAS routines which has an alternate implementation using atomics can be used. The atomics mode can be set and queried using and routines, respectively.

Value	Meaning
CUBLAS_ATOMICS_NOT_ALLOWED	the usage of atomics is not allowed
CUBLAS_ATOMICS_ALLOWED	the usage of atomics is allowed

2.3. CUDA Datatypes Reference

The chapter describes types shared by multiple CUDA Libraries and defined in the header file library_types.h.

2.3.1. cudaDataType_t

The **cudaDataType_t** type is an enumerant to specify the data precision. It is used when the data reference does not carry the type itself (e.g void *)

For example, it is used in the routine **cublasSgemmEx**.

Value	Meaning
CUDA_R_16F	the data type is 16-bit floating-point
CUDA_C_16F	the data type is 16-bit complex floating-point
CUDA_R_32F	the data type is 32-bit floating-point
CUDA_C_32F	the data type is 32-bit complex floating-point
CUDA_R_64F	the data type is 64-bit floating-point
CUDA_C_64F	the data type is 64-bit complex floating-point
CUDA_R_8I	the data type is 8-bit signed integer
CUDA_C_8I	the data type is 8-bit complex signed integer
CUDA_R_8U	the data type is 8-bit unsigned integer
CUDA_C_8U	the data type is 8-bit complex unsigned integer

2.3.2. libraryPropertyType_t

The libraryPropertyType_t is used as a parameter to specify which property is requested when using the routine cublasGetProperty

Value	Meaning
MAJOR_VERSION	enumerant to query the major version
MINOR_VERSION	enumerant to query the minor version
PATCH_LEVEL	number to identify the patch level

2.4. cuBLAS Helper Function Reference

2.4.1. cublasCreate()

```
cublasStatus_t
cublasCreate(cublasHandle t *handle)
```

This function initializes the CUBLAS library and creates a handle to an opaque structure holding the CUBLAS library context. It allocates hardware resources on the host and device and must be called prior to making any other CUBLAS library calls. The CUBLAS library context is tied to the current CUDA device. To use the library on multiple devices, one CUBLAS handle needs to be created for each device. Furthermore, for a given device, multiple CUBLAS handles with different configuration can be created. Because cublasCreate allocates some internal resources and the release of those resources by calling cublasDestroy will implicitly call cublasDeviceSynchronize, it is recommended to minimize the number of cublasCreate/cublasDestroy occurences. For multi-threaded applications that use the same device from different threads, the recommended programming model is to create one CUBLAS handle per thread and use that CUBLAS handle for the entire life of the thread.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the initialization succeeded
CUBLAS_STATUS_NOT_INITIALIZED	the CUDA™ Runtime initialization failed
CUBLAS_STATUS_ALLOC_FAILED	the resources could not be allocated

2.4.2. cublasDestroy()

```
cublasStatus_t
cublasDestroy(cublasHandle t handle)
```

This function releases hardware resources used by the CUBLAS library. This function is usually the last call with a particular handle to the CUBLAS library. Because **cublasCreate** allocates some internal resources and the release of those resources by calling **cublasDestroy** will implicitly call **cublasDeviceSynchronize**, it is recommended to minimize the number of **cublasCreate/cublasDestroy** occurences.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the shut down succeeded
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized

2.4.3. cublasGetVersion()

```
cublasStatus_t
cublasGetVersion(cublasHandle_t handle, int *version)
```

This function returns the version number of the cuBLAS library.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized

2.4.4. cublasSetStream()

```
cublasStatus_t
cublasSetStream(cublasHandle t handle, cudaStream t streamId)
```

This function sets the cuBLAS library stream, which will be used to execute all subsequent calls to the cuBLAS library functions. If the cuBLAS library stream is not set, all kernels use the *default* **NULL** stream. In particular, this routine can be used to change the stream between kernel launches and then to reset the cuBLAS library stream back to **NULL**.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the stream was set successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized

2.4.5. cublasGetStream()

```
cublasStatus_t
cublasGetStream(cublasHandle t handle, cudaStream t *streamId)
```

This function gets the cuBLAS library stream, which is being used to execute all calls to the cuBLAS library functions. If the cuBLAS library stream is not set, all kernels use the *default* **NULL** stream.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the stream was returned successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized

2.4.6. cublasGetPointerMode()

```
cublasStatus_t
cublasGetPointerMode(cublasHandle t handle, cublasPointerMode t *mode)
```

This function obtains the pointer mode used by the cuBLAS library. Please see the section on the cublasPointerMode_t type for more details.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the pointer mode was obtained successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized

2.4.7. cublasSetPointerMode()

```
cublasStatus_t
cublasSetPointerMode(cublasHandle_t handle, cublasPointerMode_t mode)
```

This function sets the pointer mode used by the cuBLAS library. The *default* is for the values to be passed by reference on the host. Please see the section on the **cublasPointerMode_t** type for more details.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the pointer mode was set successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized

2.4.8. cublasSetVector()

This function copies **n** elements from a vector **x** in host memory space to a vector **y** in GPU memory space. Elements in both vectors are assumed to have a size of **elemSize** bytes. The storage spacing between consecutive elements is given by **incx** for the source vector **x** and by **incy** for the destination vector **y**.

In general, y points to an object, or part of an object, that was allocated via cublasAlloc(). Since column-major format for two-dimensional matrices is assumed, if a vector is part of a matrix, a vector increment equal to 1 accesses a (partial) column of that matrix. Similarly, using an increment equal to the leading dimension of the matrix results in accesses to a (partial) row of that matrix.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters incx, incy, elemSize<=0
CUBLAS_STATUS_MAPPING_ERROR	there was an error accessing GPU memory

2.4.9. cublasGetVector()

This function copies **n** elements from a vector **x** in GPU memory space to a vector **y** in host memory space. Elements in both vectors are assumed to have a size of **elemSize** bytes. The storage spacing between consecutive elements is given by **incx** for the source vector and **incy** for the destination vector **y**.

In general, **x** points to an object, or part of an object, that was allocated via **cublasAlloc()**. Since column-major format for two-dimensional matrices is assumed, if a vector is part of a matrix, a vector increment equal to **1** accesses a (partial) column of that matrix. Similarly, using an increment equal to the leading dimension of the matrix results in accesses to a (partial) row of that matrix.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters incx, incy, elemSize<=0
CUBLAS_STATUS_MAPPING_ERROR	there was an error accessing GPU memory

2.4.10. cublasSetMatrix()

This function copies a tile of rows x cols elements from a matrix A in host memory space to a matrix B in GPU memory space. It is assumed that each element requires storage of elemSize bytes and that both matrices are stored in column-major format, with the leading dimension of the source matrix A and destination matrix B given in lda and ldb, respectively. The leading dimension indicates the number of rows of the allocated matrix, even if only a submatrix of it is being used. In general, B is a device pointer that points to an object, or part of an object, that was allocated in GPU memory space via cublasAlloc().

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters rows, cols<0 Or elemSize, lda, ldb<=0
CUBLAS_STATUS_MAPPING_ERROR	there was an error accessing GPU memory

2.4.11. cublasGetMatrix()

This function copies a tile of **rows x cols** elements from a matrix **A** in GPU memory space to a matrix **B** in host memory space. It is assumed that each element requires storage of **elemSize** bytes and that both matrices are stored in column-major format,

with the leading dimension of the source matrix **A** and destination matrix **B** given in **1da** and **1db**, respectively. The leading dimension indicates the number of rows of the allocated matrix, even if only a submatrix of it is being used. In general, **A** is a device pointer that points to an object, or part of an object, that was allocated in GPU memory space via **cublasAlloc()**.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters rows, cols<0 or elemSize, lda, ldb<=0
CUBLAS_STATUS_MAPPING_ERROR	there was an error accessing GPU memory

2.4.12. cublasSetVectorAsync()

This function has the same functionality as **cublasSetVector()**, with the exception that the data transfer is done asynchronously (with respect to the host) using the given CUDATM stream parameter.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters incx, incy, elemSize<=0
CUBLAS_STATUS_MAPPING_ERROR	there was an error accessing GPU memory

2.4.13. cublasGetVectorAsync()

This function has the same functionality as ${\tt cublasGetVector}$ (), with the exception that the data transfer is done asynchronously (with respect to the host) using the given ${\tt CUDA}^{\tt TM}$ stream parameter.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters incx, incy, elemSize<=0
CUBLAS_STATUS_MAPPING_ERROR	there was an error accessing GPU memory

2.4.14. cublasSetMatrixAsync()

This function has the same functionality as **cublasSetMatrix()**, with the exception that the data transfer is done asynchronously (with respect to the host) using the given CUDATM stream parameter.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters rows, cols<0 Or elemSize, lda, ldb<=0
CUBLAS_STATUS_MAPPING_ERROR	there was an error accessing GPU memory

2.4.15. cublasGetMatrixAsync()

This function has the same functionality as cublasGetMatrix(), with the exception that the data transfer is done asynchronously (with respect to the host) using the given $CUDA^{TM}$ stream parameter.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters rows, cols<0 Or elemSize, lda, ldb<=0
CUBLAS_STATUS_MAPPING_ERROR	there was an error accessing GPU memory

2.4.16. cublasSetAtomicsMode()

cublasStatust cublasSetAtomicsMode(cublasHandlet handle, cublasAtomicsModet mode)

Some routines like cublas<t>symv and cublas<t>hemv have an alternate implementation that use atomics to cumulate results. This implementation is generally significantly faster but can generate results that are not strictly identical from one run to the others. Mathematically, those different results are not significant but when debugging those differences can be prejudicial.

This function allows or disallows the usage of atomics in the cuBLAS library for all routines which have an alternate implementation. When not explicitly specified in the documentation of any cuBLAS routine, it means that this routine does not have an alternate implementation that use atomics. When atomics mode is disabled, each

cuBLAS routine should produce the same results from one run to the other when called with identical parameters on the same Hardware.

The value of the atomics mode is CUBLASATOMICSNOTALLOWED. Please see the section on the type for more details.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the atomics mode was set successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized

2.4.17. cublasGetAtomicsMode()

cublasStatust cublasGetAtomicsMode(cublasHandlet handle, cublasAtomicsModet *mode)

This function queries the atomic mode of a specific cuBLAS context.

The value of the atomics mode is CUBLASATOMICSNOTALLOWED. Please see the section on the type for more details.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the atomics mode was queried successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized

2.5. cuBLAS Level-1 Function Reference

In this chapter we describe the Level-1 Basic Linear Algebra Subprograms (BLAS1) functions that perform scalar and vector based operations. We will use abbreviations <type> for type and <t> for the corresponding short type to make a more concise and clear presentation of the implemented functions. Unless otherwise specified <type> and <t> have the following meanings:

<type></type>	<t></t>	Meaning
float	's' or 'S'	real single-precision
double	'd' or 'D'	real double-precision
cuComplex	'c' or 'C'	complex single-precision
cuDoubleComplex	ʻz' or ʻZ'	complex double-precision

When the parameters and returned values of the function differ, which sometimes happens for complex input, the <t> can also have the following meanings 'Sc', 'Cs', 'Dz' and 'Zd'.

The abbreviation $\mathbf{Re}(.)$ and $\mathbf{Im}(.)$ will stand for the real and imaginary part of a number, respectively. Since imaginary part of a real number does not exist, we will consider it to be zero and can usually simply discard it from the equation where it is being used. Also, the $\bar{\alpha}$ will denote the complex conjugate of α .

In general throughout the documentation, the lower case Greek symbols α and β will denote scalars, lower case English letters in bold type \mathbf{x} and \mathbf{y} will denote vectors and capital English letters A, B and C will denote matrices.

2.5.1. cublasI<t>amax()

This function finds the (smallest) index of the element of the maximum magnitude. Hence, the result is the first i such that $|\mathbf{Im}(x[j])| + |\mathbf{Re}(x[j])|$ is maximum for i = 1, ..., n and $j = 1 + (i - 1)^*$ incx. Notice that the last equation reflects 1-based indexing used for compatibility with Fortran.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
n		input	number of elements in the vector \mathbf{x} .
х	device	input	<type> vector with elements.</type>
incx		input	stride between consecutive elements of ${f x}$.
result	host or device	output	the resulting index, which is 0 if n,inex<=0.

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	the reduction buffer could not be allocated
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

isamax, idamax, icamax, izamax

2.5.2. cublasI<t>amin()

This function finds the (smallest) index of the element of the minimum magnitude. Hence, the result is the first i such that $|\mathbf{Im}(x[j])| + |\mathbf{Re}(x[j])|$ is minimum for i = 1, ..., n and $j = 1 + (i - 1)^*$ incx Notice that the last equation reflects 1-based indexing used for compatibility with Fortran.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
n		input	number of elements in the vector \mathbf{x} .
х	device	input	<type> vector with elements.</type>
incx		input	stride between consecutive elements of ${f x}$.
result	host or device	output	the resulting index, which is 0 if n,inex<=0.

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	the reduction buffer could not be allocated
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

isamin

2.5.3. cublas<t>asum()

This function computes the sum of the absolute values of the elements of vector \mathbf{x} . Hence, the result is $\sum_{i=1}^{n} |\mathbf{Im}(x[j])| + |\mathbf{Re}(x[j])|$ where $j = 1 + (i-1)^*$ incx. Notice that the last equation reflects 1-based indexing used for compatibility with Fortran.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
n		input	number of elements in the vector ${f x}$.
х	device	input	<type> vector with elements.</type>

Param.	Memory	In/out	Meaning
incx		input	stride between consecutive elements of ${f x}$.
result	host or device	output	the resulting index, which is 0.0 if n,incx<=0.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	the reduction buffer could not be allocated
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

sasum, dasum, scasum, dzasum

2.5.4. cublas<t>axpy()

This function multiplies the vector \mathbf{x} by the scalar α and adds it to the vector \mathbf{y} overwriting the latest vector with the result. Hence, the performed operation is $\mathbf{y}[j] = \alpha \times \mathbf{x}[k] + \mathbf{y}[j]$ for i = 1, ..., n, $k = 1 + (i-1)^*$ incx and $j = 1 + (i-1)^*$ incy. Notice that the last two equations reflect 1-based indexing used for compatibility with Fortran.

Param.	Memory	In/out	Meaning	
handle		input	handle to the cuBLAS library context.	
alpha	host or device	input	<type> scalar used for multiplication.</type>	
n		input	nput number of elements in the vector \mathbf{x} and \mathbf{y} .	
х	device	input	<type> vector with \mathbf{n} elements.</type>	
incx		input	stride between consecutive elements of ${f x}$.	

Param.	Memory	In/out	Meaning	
у	device	in/out	<type> vector with n elements.</type>	
incy		input	stride between consecutive elements of y.	

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

saxpy, daxpy, caxpy, zaxpy

2.5.5. cublas<t>copy()

This function copies the vector \mathbf{x} into the vector \mathbf{y} . Hence, the performed operation is $\mathbf{y}[j] = \mathbf{x}[k]$ for i = 1, ..., n, $k = 1 + (i - 1)^*$ incx and $j = 1 + (i - 1)^*$ incy. Notice that the last two equations reflect 1-based indexing used for compatibility with Fortran.

Param.	Memory	In/out	Meaning	
handle		input	handle to the cuBLAS library context.	
n		input	number of elements in the vector \mathbf{x} and \mathbf{y} .	
х	device	input	<type> vector with \mathbf{n} elements.</type>	
incx		input	stride between consecutive elements of \mathbf{x} .	
у	device	output	<type> vector with \mathbf{n} elements.</type>	
incy		input	stride between consecutive elements of y.	

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning	
CUBLAS_STATUS_SUCCESS	the operation completed successfully	

Error Value	Meaning
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

scopy, dcopy, ccopy, zcopy

2.5.6. cublas<t>dot()

This function computes the dot product of vectors \mathbf{x} and \mathbf{y} . Hence, the result is $\sum_{i=1}^{n} (\mathbf{x}[k] \times \mathbf{y}[j])$ where $k = 1 + (i-1)^*$ incx and $j = 1 + (i-1)^*$ incy. Notice that in the first equation the conjugate of the element of vector should be used if the function name ends in character 'c' and that the last two equations reflect 1-based indexing used for compatibility with Fortran.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
n		input	number of elements in the vectors ${f x}$ and ${f y}$.
x	device	input	<type> vector with $\mathbf n$ elements.</type>
incx		input	stride between consecutive elements of ${f x}$.
у	device	input	<type> vector with n elements.</type>
incy		input	stride between consecutive elements of y.
result	host or device	output	the resulting dot product, which is 0.0 if $n \le 0$.

The possible error va	lues returned bv	this f	unction ar	ıd the	eir meanings	are listed	below.
F							

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	the reduction buffer could not be allocated
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

sdot, ddot, cdotu, cdotc, zdotu, zdotc

2.5.7. cublas<t>nrm2()

This function computes the Euclidean norm of the vector \mathbf{x} . The code uses a multiphase model of accumulation to avoid intermediate underflow and overflow, with the result

being equivalent to $\sqrt{\sum_{i=1}^{n} (\mathbf{x}[j] \times \mathbf{x}[j])}$ where $j = 1 + (i-1)^*$ incx in exact arithmetic. Notice that the last equation reflects 1-based indexing used for compatibility with Fortran.

Param.	Memory	In/out	Meaning	
handle		input handle to the cuBLAS library context.		
n		input number of elements in the vector x .		
х	device	input	pput <type> vector with n elements.</type>	
incx		input	stride between consecutive elements of ${f x}$.	
result	host or device	output	the resulting norm, which is 0.0 if n,incx<=0.	

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	the reduction buffer could not be allocated
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

snrm2, snrm2, dnrm2, dnrm2, scnrm2, scnrm2, dznrm2

2.5.8. cublas<t>rot()

```
cublasStatus t cublasSrot(cublasHandle t handle, int n,
                          *s)
cublasStatus_t cublasDrot(cublasHandle_t handle, int n,
                          const double *c, const double
                                                                 *s)
cublasStatus t cublasCrot(cublasHandle_t handle, int n,
                          const float *c, const cuComplex
                                                                 *s)
cublasStatus_t cublasCsrot(cublasHandle_t handle, int n,
                         cuComplex *x, int incx, cuComplex *y, int incy, const float *c, const float
                                                                 *s)
cublasStatus t cublasZrot(cublasHandle t handle, int n,
                          cuDoubleComplex *x, int incx,
                          cuDoubleComplex *y, int incy,
const double *c, const cuDoubleComplex *s)
cublasStatus_t cublasZdrot(cublasHandle_t handle, int n,
                          cuDoubleComplex *x, int incx,
                          cuDoubleComplex *y, int incy,
                          const double *c, const double
                                                                 *s)
```

This function applies Givens rotation matrix

$$G = \begin{pmatrix} C & S \\ -S & C \end{pmatrix}$$

to vectors **x** and **y**.

Hence, the result is $\mathbf{x}[k] = c \times \mathbf{x}[k] + s \times \mathbf{y}[j]$ and $\mathbf{y}[j] = -s \times \mathbf{x}[k] + c \times \mathbf{y}[j]$ where $k = 1 + (i-1)^*$ incx and $j = 1 + (i-1)^*$ incy. Notice that the last two equations reflect 1-based indexing used for compatibility with Fortran.

Param.	Memory	In/out	Meaning	
handle		input	handle to the cuBLAS library context.	
n		input	number of elements in the vectors \mathbf{x} and \mathbf{y} .	
х	device	in/out	<type> vector with ${\tt n}$ elements.</type>	
incx		input	stride between consecutive elements of ${f x}$.	
у	device	in/out	<type> vector with \mathbf{n} elements.</type>	
incy		input	stride between consecutive elements of y .	
С	host or device	input	cosine element of the rotation matrix.	
s	host or device	input	sine element of the rotation matrix.	

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

srot, drot, crot, csrot, zrot, zdrot

2.5.9. cublas<t>rotg()

This function constructs the Givens rotation matrix

$$G = \begin{pmatrix} C & S \\ -S & C \end{pmatrix}$$

that zeros out the second entry of a 2×1 vector $(a, b)^T$.

Then, for real numbers we can write

$$\begin{pmatrix} c & s \\ -s & c \end{pmatrix} \begin{pmatrix} a \\ b \end{pmatrix} = \begin{pmatrix} r \\ 0 \end{pmatrix}$$

where $c^2 + s^2 = 1$ and $r = a^2 + b^2$. The parameters a and b are overwritten with r and z, respectively. The value of z is such that c and s may be recovered using the following rules:

$$(c, s) = \begin{cases} (\sqrt{1 - z^2}, z) & \text{if } |z| < 1\\ (0.0, 1.0) & \text{if } |z| = 1\\ (1/z, \sqrt{1 - z^2}) & \text{if } |z| > 1 \end{cases}$$

For complex numbers we can write

$$\begin{pmatrix} c & s \\ -\overline{s} & c \end{pmatrix} \begin{pmatrix} a \\ b \end{pmatrix} = \begin{pmatrix} r \\ 0 \end{pmatrix}$$

where $c^2 + (\bar{s} \times s) = 1$ and $r = \frac{a}{|a|} \times \|(a, b)^T\|_2$ with $\|(a, b)^T\|_2 = \sqrt{|a|^2 + |b|^2}$ for $a \neq 0$ and r = b for a = 0. Finally, the parameter a is overwritten with r on exit.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
a	host or device	in/out	<type> scalar that is overwritten with \emph{r} .</type>
b	host or device	in/out	<type> scalar that is overwritten with \emph{z} .</type>
с	host or device	output	cosine element of the rotation matrix.
s	host or device	output	sine element of the rotation matrix.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

srotg, drotg, crotg, zrotg

2.5.10. cublas<t>rotm()

This function applies the modified Givens transformation

$$H = \begin{pmatrix} h_{11} & h_{12} \\ h_{21} & h_{22} \end{pmatrix}$$

to vectors \mathbf{x} and \mathbf{y} .

Hence, the result is $\mathbf{x}[k] = h_{11} \times \mathbf{x}[k] + h_{12} \times \mathbf{y}[j]$ and $\mathbf{y}[j] = h_{21} \times \mathbf{x}[k] + h_{22} \times \mathbf{y}[j]$ where $k = 1 + (i-1)^*$ incx and $j = 1 + (i-1)^*$ incy . Notice that the last two equations reflect 1-based indexing used for compatibility with Fortran.

The elements , , and of matrix H are stored in param[1], param[2], param[3] and param[4], respectively. The flag=param[0] defines the following predefined values for the matrix H entries

flag=-1.0	flag= 0.0	flag= 1.0	flag=-2.0
$ \begin{pmatrix} h_{11} & h_{12} \\ h_{21} & h_{22} \end{pmatrix} $	$\begin{pmatrix} 1.0 & h_{12} \\ h_{21} & 1.0 \end{pmatrix}$	$\begin{pmatrix} h_{11} & 1.0 \\ -1.0 & h_{22} \end{pmatrix}$	$\begin{pmatrix} 1.0 & 0.0 \\ 0.0 & 1.0 \end{pmatrix}$

Notice that the values -1.0, 0.0 and 1.0 implied by the flag are not stored in param.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
n		input number of elements in the vectors \mathbf{x} and \mathbf{y} .	
x	device	in/out	<type> vector with n elements.</type>
incx		input	stride between consecutive elements of ${f x}$.
у	device	in/out	<type> vector with \mathbf{n} elements.</type>
incy		input	stride between consecutive elements of y .
param	host or device	input	<pre><type> vector of 5 elements, where $param[0]$ and $param[1-4]$ contain the flag and matrix H.</type></pre>

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

srotm, drotm

2.5.11. cublas<t>rotmg()

This function constructs the modified Givens transformation

$$H = \begin{pmatrix} h_{11} & h_{12} \\ h_{21} & h_{22} \end{pmatrix}$$

that zeros out the second entry of a $2 \times 1 \operatorname{vector} \left(\sqrt{d1} * x \mathbf{1}, \sqrt{d2} * y \mathbf{1} \right)^T$.

The flag=param[0] defines the following predefined values for the matrix H entries

flag=-1.0	flag= 0.0	flag= 1.0	flag=-2.0
$\begin{pmatrix} h_{11} & h_{12} \\ h_{21} & h_{22} \end{pmatrix}$	$\begin{pmatrix} 1.0 & h_{12} \\ h_{21} & 1.0 \end{pmatrix}$	$\begin{pmatrix} h_{11} & 1.0 \\ -1.0 & h_{22} \end{pmatrix}$	$\begin{pmatrix} 1.0 & 0.0 \\ 0.0 & 1.0 \end{pmatrix}$

Notice that the values -1.0, 0.0 and 1.0 implied by the flag are not stored in param.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
d1	host or device	in/out	<type> scalar that is overwritten on exit.</type>
d2	host or device	in/out	<type> scalar that is overwritten on exit.</type>
x1	host or device	in/out	<type> scalar that is overwritten on exit.</type>
y1	host or device	input	<type> scalar.</type>
param	host or device	output	<pre><type> vector of 5 elements, where $param[0]$ and $param[1-4]$ contain the flag and matrix H.</type></pre>

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

srotmg, drotmg

2.5.12. cublas<t>scal()

This function scales the vector \mathbf{x} by the scalar α and overwrites it with the result. Hence, the performed operation is $\mathbf{x}[j] = \alpha \times \mathbf{x}[j]$ for i = 1, ..., n and $j = 1 + (i - 1)^*$ incx. Notice that the last two equations reflect 1-based indexing used for compatibility with Fortran.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
alpha	host or device	input	<type> scalar used for multiplication.</type>

Param.	Memory	In/out	Meaning
n		input	number of elements in the vector ${f x}$.
х	device	in/out	<type> vector with $\mathbf n$ elements.</type>
incx		input	stride between consecutive elements of ${f x}$.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

sscal, dscal, cscal, cscal, zdscal, zscal

2.5.13. cublas<t>swap()

This function interchanges the elements of vector \mathbf{x} and \mathbf{y} . Hence, the performed operation is $\mathbf{y}[j] \Leftrightarrow \mathbf{x}[k]$ for i = 1, ..., n, $k = 1 + (i - 1)^*$ incx and $j = 1 + (i - 1)^*$ incy. Notice that the last two equations reflect 1-based indexing used for compatibility with Fortran.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
n		input	number of elements in the vector ${f x}$ and ${f y}$.
х	device	in/out	<type> vector with \mathbf{n} elements.</type>
incx		input	stride between consecutive elements of ${f x}$.
у	device	in/out	<type> vector with n elements.</type>
incy		input	stride between consecutive elements of \mathbf{y} .

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully

Error Value	Meaning
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

sswap, dswap, cswap, zswap

2.6. cuBLAS Level-2 Function Reference

In this chapter we describe the Level-2 Basic Linear Algebra Subprograms (BLAS2) functions that perform matrix-vector operations.

2.6.1. cublas<t>gbmv()

This function performs the banded matrix-vector multiplication

$$\mathbf{y} = \alpha \operatorname{op}(A)\mathbf{x} + \beta \mathbf{y}$$

where A is a banded matrix with kl subdiagonals and ku superdiagonals, \mathbf{x} and \mathbf{y} are vectors, and α and β are scalars. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == \text{CUBLAS_OP_N} \\ A^T & \text{if transa} == \text{CUBLAS_OP_T} \\ A^H & \text{if transa} == \text{CUBLAS_OP_H} \end{cases}$$

The banded matrix A is stored column by column, with the main diagonal stored in row ku+1 (starting in first position), the first superdiagonal stored in row ku (starting in second position), the first subdiagonal stored in row ku+2 (starting in first position), etc. So that in general, the element A(i, j) is stored in the memory location \mathbf{A} ($\mathbf{ku+1+i-j}$, \mathbf{j}) for $j=1,\ldots,n$ and $i\in[\max(1,j-ku),\min(m,j+kl)]$. Also, the elements in the array A that do not conceptually correspond to the elements in the banded matrix (the top left $ku\times ku$ and bottom right $kl\times kl$ triangles) are not referenced.

Param.	Memory	In/out	Meaning	
handle		input	handle to the cuBLAS library context.	
trans		input	operation op(A) that is non- or (conj.) transpose.	
m		input	number of rows of matrix A.	
n		input	number of columns of matrix A.	
kl		input	number of subdiagonals of matrix A.	
ku		input	number of superdiagonals of matrix A.	
alpha	host or device	input	<type> scalar used for multiplication.</type>	
А	device	input	<pre><type> array of dimension lda x n with lda>=kl+ku+1.</type></pre>	
lda		input	leading dimension of two-dimensional array used to store matrix A .	
x	device	input	<pre><type> vector with n elements if transa == CUBLAS_OP_N and m elements otherwise.</type></pre>	
incx		input	stride between consecutive elements of x.	
beta	host or device	input	<pre><type> scalar used for multiplication, if beta == 0 then y does not have to be a valid input.</type></pre>	
у	device	in/out	<pre><type> vector with m elements if transa == CUBLAS_OP_N and n elements otherwise.</type></pre>	
incy		input	stride between consecutive elements of y.	

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters or
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

sgbmv, dgbmv, cgbmv, zgbmv

2.6.2. cublas<t>gemv()

```
cublasStatus_t cublasSgemv(cublasHandle_t handle, cublasOperation_t trans,
                                                          *A, int lda,
                                                           *x, int incx,
cublasStatus_t cublasDgemv(cublasHandle_t handle, cublasOperation_t trans,
                                 int m, int n,
                                 const double
                                                            *alpha,
                                const double
const double
const double
const double
const double
const double
double

*A, int
*x, int
*the const
*y, int incy)
                                                           *A, int lda,
                                                            *x, int incx,
cublasStatus_t cublasCgemv(cublasHandle_t handle, cublasOperation_t trans,
                                 int m, int n,
                                const cuComplex *alpha,
const cuComplex *A, int lda,
const cuComplex *x, int incx,
const cuComplex *beta,
cuComplex *y, int incy)
cublasStatus_t cublasZgemv(cublasHandle_t handle, cublasOperation_t trans,
                                 int m, int n,
                                 const cuDoubleComplex *alpha,
                                 const cuDoubleComplex *A, int lda,
                                 const cuDoubleComplex *x, int incx,
                                 const cuDoubleComplex *beta,
                                 cuDoubleComplex *y, int incy)
```

This function performs the matrix-vector multiplication

$$\mathbf{y} = \alpha \operatorname{op}(A)\mathbf{x} + \beta \mathbf{y}$$

where A is a $m \times n$ matrix stored in column-major format, \mathbf{x} and \mathbf{y} are vectors, and α and β are scalars. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == \text{CUBLAS_OP_N} \\ A^T & \text{if transa} == \text{CUBLAS_OP_T} \\ A^H & \text{if transa} == \text{CUBLAS_OP_H} \end{cases}$$

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
trans		input	operation op(A) that is non- or (conj.) transpose.
m		input	number of rows of matrix A.
n		input	number of columns of matrix A.
alpha	host or device	input	<type> scalar used for multiplication.</type>
A	device	input	<pre><type> array of dimension lda x n with lda >= max(1,m). Before entry, the leading m by n part of the array A must contain the matrix of coefficients. Unchanged on exit.</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A. 1da must be at least max (1,m).

Param.	Memory	In/out	Meaning
x	device	input	<pre><type> vector at least (1+(n-1)*abs(incx)) elements if transa==CUBLAS_OP_N and at least (1+(m-1)*abs(incx)) elements otherwise.</type></pre>
incx		input	stride between consecutive elements of x.
beta	host or device	input	<pre><type> scalar used for multiplication, if beta==0 then y does not have to be a valid input.</type></pre>
У	device	in/out	<pre><type> vector at least (1+(m-1)*abs(incy)) elements if transa==CUBLAS_OP_N and at least (1+(n-1)*abs(incy)) elements otherwise.</type></pre>
incy		input	stride between consecutive elements of y

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters m,n<0 or incx,incy=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

sgemv, dgemv, cgemv, zgemv

2.6.3. cublas<t>ger()

```
cublasStatus t cublasSger(cublasHandle t handle, int m, int n,
                              const float const float
                                                       *x, int incx,
                              const float *y, infloat *A, int lda)
                                                      *y, int incy,
cublasStatus_t cublasDger(cublasHandle_t handle, int m, int n,
                              const double *alpha, const double *x, int incx,
                              *y, int incy,
cublasStatus t cublasCgeru(cublasHandle_t handle, int m, int n,
                              *y, int incy,
                              const cuComplex *y, int cuComplex *A, int lda)
cublasStatus t cublasCgerc(cublasHandle t handle, int m, int n,
                              const cuComplex *alpha,
const cuComplex *x, int incx,
const cuComplex *y, int incy,
cuComplex *A, int lda)
cublasStatus t cublasZgeru(cublasHandle t handle, int m, int n,
                              const cuDoubleComplex *alpha,
                              const cuDoubleComplex *x, int incx,
const cuDoubleComplex *y, int incy,
                              cuDoubleComplex *A, int lda)
cublasStatus t cublasZgerc(cublasHandle t handle, int m, int n,
                              const cuDoubleComplex *alpha,
                              const cuDoubleComplex *x, int incx,
const cuDoubleComplex *y, int incy,
                              cuDoubleComplex *A, int lda)
```

This function performs the rank-1 update

$$A = \begin{cases} \alpha \mathbf{x} \mathbf{y}^T + A & \text{if ger(),geru() is called} \\ \alpha \mathbf{x} \mathbf{y}^H + A & \text{if gerc() is called} \end{cases}$$

where *A* is a $m \times n$ matrix stored in column-major format, **x** and **y** are vectors, and α is a scalar.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
m		input	number of rows of matrix A.
n		input	number of columns of matrix A .
alpha	host or device	input	<type> scalar used for multiplication.</type>
х	device	input	<type $>$ vector with m elements.
incx		input	stride between consecutive elements of x.
у	device	input	<type> vector with n elements.</type>
incy		input	stride between consecutive elements of y.
А	device	in/out	<pre><type> array of dimension lda x n With lda >= max(1,m).</type></pre>

Param.	Memory	In/out	Meaning
lda		input	leading dimension of two-dimensional array used to store matrix A.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters m,n<0 or incx,incy=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

sger, dger, cgeru, cgerc, zgeru, zgerc

2.6.4. cublas<t>sbmv()

This function performs the symmetric banded matrix-vector multiplication

$$\mathbf{y} = \alpha A \mathbf{x} + \beta \mathbf{y}$$

where *A* is a $n \times n$ symmetric banded matrix with *k* subdiagonals and superdiagonals, **x** and **y** are vectors, and α and β are scalars.

If $uplo == CUBLAS_FILL_MODE_LOWER$ then the symmetric banded matrix A is stored column by column, with the main diagonal of the matrix stored in row 1, the first subdiagonal in row 2 (starting at first position), the second subdiagonal in row 3 (starting at first position), etc. So that in general, the element A(i, j) is stored in the memory location A(1+i-j,j) for $j=1,\ldots,n$ and $i\in[j,\min(m,j+k)]$. Also, the elements in the array A that do not conceptually correspond to the elements in the banded matrix (the bottom right $k \times k$ triangle) are not referenced.

If **uplo == CUBLAS_FILL_MODE_UPPER** then the symmetric banded matrix A is stored column by column, with the main diagonal of the matrix stored in row **k+1**, the first superdiagonal in row **k** (starting at second position), the second superdiagonal in row **k-1** (starting at third position), etc. So that in general, the element A(i, j) is stored in the memory location **A** (**1+k+i-j**, **j**) for j = 1, ..., n and $i \in [\max(1, j - k), j]$. Also,

the elements in the array \mathbf{A} that do not conceptually correspond to the elements in the banded matrix (the top left $k \times k$ triangle) are not referenced.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix A lower or upper part is stored, the other symmetric part is not referenced and is inferred from the stored elements.
n		input	number of rows and columns of matrix A.
k		input	number of sub- and super-diagonals of matrix ${f A}$.
alpha	host or device	input	<type> scalar used for multiplication.</type>
А	device	input	<pre><type> array of dimension lda x n with \lda >= k+1.</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A .
х	device	input	<type> vector with n elements.</type>
incx		input	stride between consecutive elements of x.
beta	host or device	input	<pre><type> scalar used for multiplication, if beta==0 then y does not have to be a valid input.</type></pre>
у	device	in/out	<type> vector with n elements.</type>
incy		input	stride between consecutive elements of y.

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,k<0 or incx,incy=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

ssbmv, dsbmv

2.6.5. cublas<t>spmv()

This function performs the symmetric packed matrix-vector multiplication

$$\mathbf{y} = \alpha A \mathbf{x} + \beta \mathbf{y}$$

where *A* is a $n \times n$ symmetric matrix stored in packed format, **x** and **y** are vectors, and α and β are scalars.

If **uplo == CUBLAS_FILL_MODE_LOWER** then the elements in the lower triangular part of the symmetric matrix A are packed together column by column without gaps, so that the element A(i, j) is stored in the memory location AP[i+((2*n-j+1)*j)/2] for j=1, ..., n and $i \ge j$. Consequently, the packed format requires only $\frac{n(n+1)}{2}$ elements for storage.

If **uplo == CUBLAS_FILL_MODE_UPPER** then the elements in the upper triangular part of the symmetric matrix A are packed together column by column without gaps, so that the element A(i, j) is stored in the memory location AP[i+(j*(j+1))/2] for j=1, ..., n and $i \le j$. Consequently, the packed format requires only $\frac{n(n+1)}{2}$ elements for storage.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix ${\cal A}$ lower or upper part is stored, the other symmetric part is not referenced and is inferred from the stored elements.
n		input	number of rows and columns of matrix \boldsymbol{A} .
alpha	host or device	input	<type> scalar used for multiplication.</type>
AP	device	input	<type> array with A stored in packed format.</type>
x	device	input	<type> vector with n elements.</type>
incx		input	stride between consecutive elements of ${f x}$.
beta	host or device	input	<pre><type> scalar used for multiplication, if beta==0 then y does not have to be a valid input.</type></pre>
у	device	input	<type> vector with n elements.</type>
incy		input	stride between consecutive elements of y.

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n<0 or incx,incy=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

sspmv, dspmv

2.6.6. cublas<t>spr()

This function performs the packed symmetric rank-1 update

```
A = \alpha \mathbf{x} \mathbf{x}^T + A
```

where *A* is a $n \times n$ symmetric matrix stored in packed format, **x** is a vector, and α is a scalar.

If **uplo == CUBLAS_FILL_MODE_LOWER** then the elements in the lower triangular part of the symmetric matrix A are packed together column by column without gaps, so that the element A(i, j) is stored in the memory location AP[i+((2*n-j+1)*j)/2] for j=1, ..., n and $i \ge j$. Consequently, the packed format requires only $\frac{n(n+1)}{2}$ elements for storage.

If **uplo == CUBLAS_FILL_MODE_UPPER** then the elements in the upper triangular part of the symmetric matrix A are packed together column by column without gaps, so that the element A(i, j) is stored in the memory location AP[i+(j*(j+1))/2] for j=1, ..., n and $i \le j$. Consequently, the packed format requires only $\frac{n(n+1)}{2}$ elements for storage.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix ${\cal A}$ lower or upper part is stored, the other symmetric part is not referenced and is inferred from the stored elements.
n		input	number of rows and columns of matrix \boldsymbol{A} .
alpha	host or device	input	<type> scalar used for multiplication.</type>
x	device	input	<type> vector with \mathbf{n} elements.</type>
incx		input	stride between consecutive elements of x.
AP	device	in/out	<type $>$ array with A stored in packed format.

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized

Error Value	Meaning
CUBLAS_STATUS_INVALID_VALUE	the parameters n<0 or incx,incy=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

sspr, dspr

2.6.7. cublas<t>spr2()

This function performs the packed symmetric rank-2 update

$$A = \alpha(\mathbf{x}\mathbf{y}^T + \mathbf{y}\mathbf{x}^T) + A$$

where *A* is a $n \times n$ symmetric matrix stored in packed format, **x** is a vector, and α is a scalar.

If **uplo == CUBLAS_FILL_MODE_LOWER** then the elements in the lower triangular part of the symmetric matrix A are packed together column by column without gaps, so that the element A(i, j) is stored in the memory location AP[i+((2*n-j+1)*j)/2] for j=1, ..., n and $i \ge j$. Consequently, the packed format requires only $\frac{n(n+1)}{2}$ elements for storage.

If uplo == CUBLAS_FILL_MODE_UPPER then the elements in the upper triangular part of the symmetric matrix A are packed together column by column without gaps, so that the element A(i, j) is stored in the memory location AP[i+(j*(j+1))/2] for j=1, ..., n and $i \le j$. Consequently, the packed format requires only $\frac{n(n+1)}{2}$ elements for storage.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix ${\cal A}$ lower or upper part is stored, the other symmetric part is not referenced and is inferred from the stored elements.
n		input	number of rows and columns of matrix \boldsymbol{A} .
alpha	host or device	input	<type> scalar used for multiplication.</type>
x	device	input	<type> vector with n elements.</type>
incx		input	stride between consecutive elements of x.

Param.	Memory	In/out	Meaning
у	device	input	<type> vector with \mathbf{n} elements.</type>
incy		input	stride between consecutive elements of y.
AP	device	in/out	<type> array with A stored in packed format.</type>

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n<0 or incx,incy=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

sspr2, dspr2

2.6.8. cublas<t>symv()

```
cublasStatus_t cublasSsymv(cublasHandle_t handle, cublasFillMode_t uplo,
                          int n, const float *alpha,
const float *A, int lda,
const float *x, int incx, const float
     *beta,
                          float
                                        *y, int incy)
cublasStatus_t cublasDsymv(cublasHandle_t handle, cublasFillMode_t uplo,
                         int n, const double *A, int lda, const double *x, int incx, const double
     *beta,
                                   *y, int incy)
                        double
cublasStatus_t cublasCsymv(cublasHandle_t handle, cublasFillMode_t uplo,
                         device pointer */
                         *beta,
                          cuComplex
                                        *y, int incy)
cublasStatus_t cublasZsymv(cublasHandle_t handle, cublasFillMode_t uplo,
                          int n, const cuDoubleComplex *alpha,
                          const cuDoubleComplex *A, int lda,
const cuDoubleComplex *x, int incx, const
cuDoubleComplex *beta,
                        cuDoubleComplex *y, int incy)
```

This function performs the symmetric matrix-vector multiplication.

$$\mathbf{y} = \alpha A \mathbf{x} + \beta \mathbf{y}$$

where *A* is a $n \times n$ symmetric matrix stored in lower or upper mode, **x** and **x** are vectors, and α and β are scalars.

This function has an alternate faster implementation using atomics that can be enabled with cublasSetAtomicsMode().

Please see the section on the function **cublasSetAtomicsMode()** for more details about the usage of atomics.

Param.	Memory	In/out	Meaning	
handle		input	handle to the cuBLAS library context.	
uplo		input	indicates if matrix lower or upper part is stored, the other symmetric part is not referenced and is inferred from the stored elements.	
n		input	number of rows and columns of matrix A.	
alpha	host or device	input	<type> scalar used for multiplication.</type>	
Α	device	input	<pre><type> array of dimension lda x n with lda>=max(1,n).</type></pre>	
lda		input	leading dimension of two-dimensional array used to store matrix A .	
х	device	input	<type> vector with n elements.</type>	
incx		input	stride between consecutive elements of x.	
beta	host or device	input	<type> scalar used for multiplication, if beta==0 then y does not have to be a valid input.</type>	
у	device	in/out	<type> vector with n elements.</type>	
incy		input	stride between consecutive elements of y.	

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n<0 or incx,incy=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

ssymv, dsymv

2.6.9. cublas<t>syr()

This function performs the symmetric rank-1 update

$$A = \alpha \mathbf{x} \mathbf{x}^T + A$$

where *A* is a $n \times n$ symmetric matrix stored in column-major format, **x** is a vector, and α is a scalar.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix A lower or upper part is stored, the other symmetric part is not referenced and is inferred from the stored elements.
n		input	number of rows and columns of matrix A.
alpha	host or device	input	<type> scalar used for multiplication.</type>
х	device	input	<type> vector with \mathbf{n} elements.</type>
incx		input	stride between consecutive elements of ${f x}$.
Α	device	in/out	<pre><type> array of dimensions lda x n, with lda>=max(1,n).</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A.

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n<0 or incx=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

ssyr, dsyr

2.6.10. cublas<t>syr2()

```
cublasStatus_t cublasSsyr2(cublasHandle_t handle, cublasFillMode_t uplo, int n,
                        const float *alpha, const float
*x, int incx,
                    const float *y, int incy, float
*A, int lda
cublasStatus_t cublasDsyr2(cublasHandle_t handle, cublasFillMode_t uplo, int n,
                        const double *alpha, const double
*x, int incx,
                                             *y, int incy, double
                       const double
*A, int lda
cublasStatus_t cublasCsyr2(cublasHandle_t handle, cublasFillMode_t uplo, int n,
                        const cuComplex *alpha, const cuComplex
*x, int incx,
                       const cuComplex *y, int incy, cuComplex
*A, int lda
cublasStatus t cublasZsyr2(cublasHandle t handle, cublasFillMode t uplo, int n,
                        const cuDoubleComplex *alpha, const cuDoubleComplex
*x, int incx,
                       const cuDoubleComplex *y, int incy, cuDoubleComplex
*A, int lda
```

This function performs the symmetric rank-2 update

$$A = \alpha(\mathbf{x}\mathbf{y}^T + \mathbf{y}\mathbf{x}^T) + A$$

where *A* is a $n \times n$ symmetric matrix stored in column-major format, **x** and **y** are vectors, and α is a scalar.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input indicates if matrix A lower or upper part is stored, the other symmetric part is not referenced and is inferred from the stored elements.	
n		input	number of rows and columns of matrix A.
alpha	host or device	input	<type> scalar used for multiplication.</type>
х	device	input	<type> vector with n elements.</type>
incx		input	stride between consecutive elements of x.
у	device	input	<type> vector with n elements.</type>
incy		input	stride between consecutive elements of y.
А	device	in/out	<pre><type> array of dimensions lda x n, with lda>=max(1,n).</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A .

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n<0 or incx,incy=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

ssyr2, dsyr2

2.6.11. cublas<t>tbmv()

This function performs the triangular banded matrix-vector multiplication

$$\mathbf{x} = \mathrm{op}(A)\mathbf{x}$$

where A is a triangular banded matrix, and \mathbf{x} is a vector. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == \text{CUBLAS_OP_N} \\ A^T & \text{if transa} == \text{CUBLAS_OP_T} \\ A^H & \text{if transa} == \text{CUBLAS_OP_C} \end{cases}$$

If **uplo == CUBLAS_FILL_MODE_LOWER** then the triangular banded matrix A is stored column by column, with the main diagonal of the matrix stored in row **1**, the first subdiagonal in row **2** (starting at first position), the second subdiagonal in row **3** (starting at first position), etc. So that in general, the element A(i, j) is stored in the memory location A(1+i-j,j) for $j=1,\ldots,n$ and $i\in[j,\min(m,j+k)]$. Also, the elements in the array **A** that do not conceptually correspond to the elements in the banded matrix (the bottom right $k \times k$ triangle) are not referenced.

If **uplo == CUBLAS_FILL_MODE_UPPER** then the triangular banded matrix A is stored column by column, with the main diagonal of the matrix stored in row **k+1**, the first superdiagonal in row **k** (starting at second position), the second superdiagonal in row **k-1** (starting at third position), etc. So that in general, the element A(i, j) is stored in the memory location **A**(1+**k**+**i**-**j**,**j**) for j = 1, ..., n and $i \in [\max(1, j-k, j)]$. Also, the

elements in the array \mathbf{A} that do not conceptually correspond to the elements in the banded matrix (the top left $k \times k$ triangle) are not referenced.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix ${\bf A}$ lower or upper part is stored, the other part is not referenced and is inferred from the stored elements.
trans		input	operation op(A) that is non- or (conj.) transpose.
diag		input	indicates if the elements on the main diagonal of matrix ${\bf A}$ are unity and should not be accessed.
n		input	number of rows and columns of matrix A.
k		input	number of sub- and super-diagonals of matrix .
Α	device	input	<type> array of dimension lda x n, with lda>=k+1.</type>
lda		input	leading dimension of two-dimensional array used to store matrix A.
х	device	in/out	<type> vector with \mathbf{n} elements.</type>
incx		input	stride between consecutive elements of x.

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,k<0 or incx=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_ALLOC_FAILED	the allocation of internal scratch memory failed
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

stbmv, dtbmv, ctbmv, ztbmv

2.6.12. cublas<t>tbsv()

```
cublasStatus t cublasStbsv(cublasHandle t handle, cublasFillMode t uplo,
                       cublasOperation t trans, cublasDiagType t diag,
                                     *x, int incx)
                       int n, int k, const float
                       float
cublasStatus t cublasDtbsv(cublasHandle t handle, cublasFillMode t uplo,
                       cublasOperation_t trans, cublasDiagType_t diag,
                                                *A, int lda,
                       int n, int k, const double
                                    *x, int incx)
                       double
cublasStatus t cublasCtbsv(cublasHandle t handle, cublasFillMode t uplo,
                      cublasOperation_t trans, cublasDiagType_t diag,
                       int n, int k, const cuComplex *A, int lda,
cublasOperation t trans, cublasDiagType t diag,
                       int n, int k, const cuDoubleComplex *A, int lda,
                       cuDoubleComplex *x, int incx)
```

This function solves the triangular banded linear system with a single right-hand-side $op(A)\mathbf{x} = \mathbf{b}$

where A is a triangular banded matrix, and \mathbf{x} and \mathbf{b} are vectors. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == \text{CUBLAS_OP_N} \\ A^T & \text{if transa} == \text{CUBLAS_OP_T} \\ A^H & \text{if transa} == \text{CUBLAS_OP_C} \end{cases}$$

The solution **x** overwrites the right-hand-sides **b** on exit.

No test for singularity or near-singularity is included in this function.

If **uplo == CUBLAS_FILL_MODE_LOWER** then the triangular banded matrix A is stored column by column, with the main diagonal of the matrix stored in row **1**, the first subdiagonal in row **2** (starting at first position), the second subdiagonal in row **3** (starting at first position), etc. So that in general, the element A(i, j) is stored in the memory location A(1+i-j,j) for $j=1,\ldots,n$ and $i\in[j,\min(m,j+k)]$. Also, the elements in the array **A** that do not conceptually correspond to the elements in the banded matrix (the bottom right $k \times k$ triangle) are not referenced.

If **uplo == CUBLAS_FILL_MODE_UPPER** then the triangular banded matrix A is stored column by column, with the main diagonal of the matrix stored in row **k+1**, the first superdiagonal in row **k** (starting at second position), the second superdiagonal in row **k-1** (starting at third position), etc. So that in general, the element A(i, j) is stored in the memory location **A(1+k+i-j,j)** for j = 1, ..., n and $i \in [\max(1, j-k, j)]$. Also, the elements in the array **A** that do not conceptually correspond to the elements in the banded matrix (the top left $k \times k$ triangle) are not referenced.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix ${\bf A}$ lower or upper part is stored, the other part is not referenced and is inferred from the stored elements.
trans		input	operation op(A) that is non- or (conj.) transpose.

Param.	Memory	In/out	Meaning
diag		input	indicates if the elements on the main diagonal of matrix ${\tt A}$ are unity and should not be accessed.
n		input	number of rows and columns of matrix A.
k		input	number of sub- and super-diagonals of matrix A.
А	device	input	<pre><type> array of dimension lda x n, with lda >= k+1.</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A.
x	device	in/out	<type> vector with \mathbf{n} elements.</type>
incx		input	stride between consecutive elements of \mathbf{x} .

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,k<0 or incx=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

stbsv, dtbsv, ctbsv, ztbsv

2.6.13. cublas<t>tpmv()

```
cublasStatus_t cublasStpmv(cublasHandle_t handle, cublasFillMode_t uplo,
                          cublasOperation_t trans, cublasDiagType_t diag,
                          int n, const float
                          float
                                         *x, int incx)
cublasStatus t cublasDtpmv(cublasHandle t handle, cublasFillMode t uplo,
                          cublasOperation_t trans, cublasDiagType_t diag,
                          int n, const double
                          double
                                          *x, int incx)
cublasStatus t cublasCtpmv(cublasHandle t handle, cublasFillMode t uplo,
                          cublasOperation_t trans, cublasDiagType_t diag,
                          int n, const cuComplex
                          cuComplex
                                     *x, int incx)
cublasStatus t cublasZtpmv(cublasHandle t handle, cublasFillMode t uplo,
                          cublasOperation t trans, cublasDiagType t diag,
                          int n, const cuDoubleComplex *AP,
                          cuDoubleComplex *x, int incx)
```

This function performs the triangular packed matrix-vector multiplication

$$\mathbf{x} = \mathrm{op}(A)\mathbf{x}$$

where A is a triangular matrix stored in packed format, and \mathbf{x} is a vector. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == \text{CUBLAS_OP_N} \\ A^T & \text{if transa} == \text{CUBLAS_OP_T} \\ A^H & \text{if transa} == \text{CUBLAS_OP_C} \end{cases}$$

If **uplo == CUBLAS_FILL_MODE_LOWER** then the elements in the lower triangular part of the triangular matrix A are packed together column by column without gaps, so that the element A(i, j) is stored in the memory location AP[i+((2*n-j+1)*j)/2] for j=1, ..., n and $i \ge j$. Consequently, the packed format requires only $\frac{n(n+1)}{2}$ elements for storage.

If **uplo == CUBLAS_FILL_MODE_UPPER** then the elements in the upper triangular part of the triangular matrix A are packed together column by column without gaps, so that the element A(i, j) is stored in the memory location AP[i+(j*(j+1))/2] for A(i, j) and $i \le j$. Consequently, the packed format requires only $\frac{n(n+1)}{2}$ elements for storage.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix ${\bf A}$ lower or upper part is stored, the other part is not referenced and is inferred from the stored elements.
trans		input	operation op(A) that is non- or (conj.) transpose.
diag		input	indicates if the elements on the main diagonal of matrix ${\tt A}$ are unity and should not be accessed.
n		input	number of rows and columns of matrix ${f a}$.
AP	device	input	<type> array with A stored in packed format.</type>
x	device	in/out	<type> vector with n elements.</type>
incx		input	stride between consecutive elements of ${f x}$.

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters \$n<0 or incx=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_ALLOC_FAILED	the allocation of internal scratch memory failed
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

stpmv, dtpmv, ctpmv, ztpmv

2.6.14. cublas<t>tpsv()

```
cublasStatus t cublasStpsv(cublasHandle t handle, cublasFillMode t uplo,
                          cublasOperation t trans, cublasDiagType t diag,
                          int n, const float
                                          *x, int incx)
                          float
cublasStatus t cublasDtpsv(cublasHandle t handle, cublasFillMode t uplo,
                          cublasOperation_t trans, cublasDiagType_t diag,
                          int n, const double
                                        *x, int incx)
                          double
cublasStatus t cublasCtpsv(cublasHandle t handle, cublasFillMode t uplo,
                          cublasOperation_t trans, cublasDiagType_t diag,
                          int n, const cuComplex
                          cuComplex *x, int incx)
cublasStatus t cublasZtpsv(cublasHandle t handle, cublasFillMode t uplo,
                          cublasOperation_t trans, cublasDiagType_t diag,
                          int n, const cuDoubleComplex *AP,
                          cuDoubleComplex *x, int incx)
```

This function solves the packed triangular linear system with a single right-hand-side $op(A)\mathbf{x} = \mathbf{b}$

where A is a triangular matrix stored in packed format, and ${\bf x}$ and ${\bf b}$ are vectors. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == \text{CUBLAS_OP_N} \\ A^T & \text{if transa} == \text{CUBLAS_OP_T} \\ A^H & \text{if transa} == \text{CUBLAS_OP_C} \end{cases}$$

The solution **x** overwrites the right-hand-sides **b** on exit.

No test for singularity or near-singularity is included in this function.

If **uplo == CUBLAS_FILL_MODE_LOWER** then the elements in the lower triangular part of the triangular matrix A are packed together column by column without gaps, so that the element A(i, j) is stored in the memory location AP[i+((2*n-j+1)*j)/2] for j=1, ..., n and $i \ge j$. Consequently, the packed format requires only $\frac{n(n+1)}{2}$ elements for storage.

If **uplo == CUBLAS_FILL_MODE_UPPER** then the elements in the upper triangular part of the triangular matrix A are packed together column by column without gaps, so that the element A(i, j) is stored in the memory location AP[i+(j*(j+1))/2] for j=1, ..., n and $i \le j$. Consequently, the packed format requires only $\frac{n(n+1)}{2}$ elements for storage.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix ${\bf A}$ lower or upper part is stored, the other part is not referenced and is inferred from the stored elements.
trans		input	operation op(A) that is non- or (conj.) transpose.
diag		input	indicates if the elements on the main diagonal of matrix are unity and should not be accessed.

Param.	Memory	In/out	Meaning
n		input	number of rows and columns of matrix ${\tt A}$.
AP	device	input	<type> array with A stored in packed format.</type>
х	device	in/out	<type> vector with \mathbf{n} elements.</type>
incx		input	stride between consecutive elements of \mathbf{x} .

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n<0 or incx=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

stpsv, dtpsv, ctpsv, ztpsv

2.6.15. cublas<t>trmv()

```
cublasStatus t cublasStrmv(cublasHandle t handle, cublasFillMode t uplo,
                          cublasOperation_t trans, cublasDiagType_t diag,
                          int n, const float
                          float
                                         *x, int incx)
cublasStatus t cublasDtrmv(cublasHandle t handle, cublasFillMode t uplo,
                          cublasOperation_t trans, cublasDiagType_t diag,
                                                       *A, int lda,
                          int n, const double
                          double *x, int incx)
cublasStatus t cublasCtrmv(cublasHandle t handle, cublasFillMode t uplo,
                          cublasOperation_t trans, cublasDiagType_t diag,
                          int n, const cuComplex
                                                       *A, int lda,
                          cuComplex *x, int incx)
cublasStatus t cublasZtrmv(cublasHandle t handle, cublasFillMode t uplo,
                          cublasOperation_t trans, cublasDiagType_t diag,
                          int n, const cuDoubleComplex *A, int lda,
                          cuDoubleComplex *x, int incx)
```

This function performs the triangular matrix-vector multiplication

$$\mathbf{x} = \mathrm{op}(A)\mathbf{x}$$

where A is a triangular matrix stored in lower or upper mode with or without the main diagonal, and \mathbf{x} is a vector. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == \text{CUBLAS_OP_N} \\ A^T & \text{if transa} == \text{CUBLAS_OP_T} \\ A^H & \text{if transa} == \text{CUBLAS_OP_C} \end{cases}$$

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix ${\bf A}$ lower or upper part is stored, the other part is not referenced and is inferred from the stored elements.
trans		input	operation op(A) that is non- or (conj.) transpose.
diag		input	indicates if the elements on the main diagonal of matrix ${\bf A}$ are unity and should not be accessed.
n		input	number of rows and columns of matrix ${f A}$.
Α	device	input	<pre><type> array of dimensions lda $x n$, with lda>=max(1,n).</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A.
x	device	in/out	<type> vector with n elements.</type>
incx		input	stride between consecutive elements of \mathbf{x} .

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n<0 or incx=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_ALLOC_FAILED	the allocation of internal scratch memory failed
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

strmv, dtrmv, ctrmv, ztrmv

2.6.16. cublas<t>trsv()

```
cublasStatus t cublasStrsv(cublasHandle t handle, cublasFillMode t uplo,
                           cublasOperation_t trans, cublasDiagType_t diag,
                                                        *A, int lda,
                           int n, const float
                                           *x, int incx)
                           float
cublasStatus_t cublasDtrsv(cublasHandle_t handle, cublasFillMode_t uplo,
                           cublasOperation t trans, cublasDiagType t diag,
                           int n, const double
                                                         *A, int lda,
                                           *x, int incx)
                           double
cublasStatus_t cublasCtrsv(cublasHandle_t handle, cublasFillMode_t uplo,
                           cublasOperation_t trans, cublasDiagType_t diag,
                           int n, const cuComplex
                                                         *A, int lda,
                           cuComplex
                                           *x, int incx)
cublasStatus t cublasZtrsv(cublasHandle t handle, cublasFillMode t uplo,
                           cublasOperation t trans, cublasDiagType t diag,
                           int n, const cuDoubleComplex *A, int lda,
                           cuDoubleComplex *x, int incx)
```

This function solves the triangular linear system with a single right-hand-side

$$op(A)\mathbf{x} = \mathbf{b}$$

where A is a triangular matrix stored in lower or upper mode with or without the main diagonal, and \mathbf{x} and \mathbf{b} are vectors. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == \texttt{CUBLAS_OP_N} \\ A^T & \text{if transa} == \texttt{CUBLAS_OP_T} \\ A^H & \text{if transa} == \texttt{CUBLAS_OP_C} \end{cases}$$

The solution \mathbf{x} overwrites the right-hand-sides \mathbf{b} on exit.

No test for singularity or near-singularity is included in this function.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix ${\bf A}$ lower or upper part is stored, the other part is not referenced and is inferred from the stored elements.
trans		input	operation op(A) that is non- or (conj.) transpose.
diag		input	indicates if the elements on the main diagonal of matrix ${\bf A}$ are unity and should not be accessed.
n		input	number of rows and columns of matrix A.
А	device	input	<pre><type> array of dimension lda x n, With lda>=max(1,n).</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A.
х	device	in/out	<type> vector with n elements.</type>
incx		input	stride between consecutive elements of x.

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n<0 or incx=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

strsv, dtrsv, ctrsv, ztrsv

2.6.17. cublas<t>hemv()

This function performs the Hermitian matrix-vector multiplication

$$\mathbf{y} = \alpha A \mathbf{x} + \beta \mathbf{y}$$

where *A* is a $n \times n$ Hermitian matrix stored in lower or upper mode, **x** and **y** are vectors, and α and β are scalars.

This function has an alternate faster implementation using atomics that can be enabled with

Please see the section on the for more details about the usage of atomics

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix A lower or upper part is stored, the other Hermitian part is not referenced and is inferred from the stored elements.
n		input	number of rows and columns of matrix A.
alpha	host or device	input	<type> scalar used for multiplication.</type>
А	device	input	<pre><type> array of dimension lda x n, with lda>=max(1,n). The imaginary parts of the diagonal elements are assumed to be zero.</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A .
х	device	input	<type> vector with n elements.</type>
incx		input	stride between consecutive elements of x.
beta	host or device	input	<pre><type> scalar used for multiplication, if beta==0 then y does not have to be a valid input.</type></pre>
у	device	in/out	<type> vector with n elements.</type>
incy		input	stride between consecutive elements of y.

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n<0 or incx,incy=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

chemy, zhemy

2.6.18. cublas<t>hbmv()

This function performs the Hermitian banded matrix-vector multiplication

$$\mathbf{y} = \alpha A \mathbf{x} + \beta \mathbf{y}$$

where *A* is a $n \times n$ Hermitian banded matrix with *k* subdiagonals and superdiagonals, **x** and **y** are vectors, and α and β are scalars.

If **uplo == CUBLAS_FILL_MODE_LOWER** then the Hermitian banded matrix A is stored column by column, with the main diagonal of the matrix stored in row **1**, the first subdiagonal in row **2** (starting at first position), the second subdiagonal in row **3** (starting at first position), etc. So that in general, the element A(i, j) is stored in the memory location A(1+i-j,j) for $j=1,\ldots,n$ and $i\in[j,\min(m,j+k)]$. Also, the elements in the array **A** that do not conceptually correspond to the elements in the banded matrix (the bottom right $k \times k$ triangle) are not referenced.

If $\mathtt{uplo} == \mathtt{CUBLAS_FILL_MODE_UPPER}$ then the Hermitian banded matrix A is stored column by column, with the main diagonal of the matrix stored in row $\mathtt{k+1}$, the first superdiagonal in row \mathtt{k} (starting at second position), the second superdiagonal in row $\mathtt{k-1}$ (starting at third position), etc. So that in general, the element A(i, j) is stored in the memory location $\mathtt{A}(\mathtt{1+k+i-j},\mathtt{j})$ for $j=1,\ldots,n$ and $i\in[\max(1,j-k),j]$. Also, the elements in the array \mathtt{A} that do not conceptually correspond to the elements in the banded matrix (the top left $k\times k$ triangle) are not referenced.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.

Param.	Memory	In/out	Meaning
uplo		input	indicates if matrix A lower or upper part is stored, the other Hermitian part is not referenced and is inferred from the stored elements.
n		input	number of rows and columns of matrix A.
k		input	number of sub- and super-diagonals of matrix A.
alpha	host or device	input	<type> scalar used for multiplication.</type>
A	device	input	<pre><type> array of dimensions lda x n, with lda>=k+1. The imaginary parts of the diagonal elements are assumed to be zero.</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A.
×	device	input	<type> vector with n elements.</type>
incx		input	stride between consecutive elements of x.
beta	host or device	input	<pre><type> scalar used for multiplication, if beta==0 then does not have to be a valid input.</type></pre>
у	device	in/out	<type> vector with n elements.</type>
incy		input	stride between consecutive elements of y.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,k<0 or incx,incy=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

chbmv, zhbmv

2.6.19. cublas<t>hpmv()

This function performs the Hermitian packed matrix-vector multiplication

$$\mathbf{y} = \alpha A \mathbf{x} + \beta \mathbf{y}$$

where *A* is a $n \times n$ Hermitian matrix stored in packed format, **x** and **y** are vectors, and α and β are scalars.

If **uplo == CUBLAS_FILL_MODE_LOWER** then the elements in the lower triangular part of the Hermitian matrix A are packed together column by column without gaps, so that the element A(i, j) is stored in the memory location AP[i+((2*n-j+1)*j)/2] for j=1, ..., n and $i \ge j$. Consequently, the packed format requires only $\frac{n(n+1)}{2}$ elements for storage.

If uplo == CUBLAS_FILL_MODE_UPPER then the elements in the upper triangular part of the Hermitian matrix A are packed together column by column without gaps, so that the element A(i,j) is stored in the memory location AP[i+(j*(j+1))/2] for $j=1,\ldots,n$ and $i \le j$. Consequently, the packed format requires only $\frac{n(n+1)}{2}$ elements for storage.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix A lower or upper part is stored, the other Hermitian part is not referenced and is inferred from the stored elements.
n		input	number of rows and columns of matrix A.
alpha	host or device	input	<type> scalar used for multiplication.</type>
AP	device	input	<type> array with A stored in packed format. The imaginary parts of the diagonal elements are assumed to be zero.</type>
x	device	input	<type> vector with n elements.</type>
incx		input	stride between consecutive elements of x.
beta	host or device	input	<pre><type> scalar used for multiplication, if beta==0 then y does not have to be a valid input.</type></pre>
у	device	in/out	<type> vector with n elements.</type>

Param.	Memory	In/out	Meaning
incy		input	stride between consecutive elements of y.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n<0 or incx,incy=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

chpmv, zhpmv

2.6.20. cublas<t>her()

This function performs the Hermitian rank-1 update

$$A = \alpha \mathbf{x} \mathbf{x}^H + A$$

where *A* is a $n \times n$ Hermitian matrix stored in column-major format, **x** is a vector, and α is a scalar.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix A lower or upper part is stored, the other Hermitian part is not referenced and is inferred from the stored elements.
n		input	number of rows and columns of matrix A.
alpha	host or device	input	<type> scalar used for multiplication.</type>
x	device	input	<type> vector with \mathbf{n} elements.</type>
incx		input	stride between consecutive elements of ${f x}$.
A	device	in/out	<pre><type> array of dimensions lda x n, with lda>=max(1,n). The imaginary parts of the diagonal elements are assumed and set to zero.</type></pre>

Param.	Memory	In/out	Meaning
lda		input	leading dimension of two-dimensional array used to store matrix A.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n<0 or incx=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

cher, zher

2.6.21. cublas<t>her2()

This function performs the Hermitian rank-2 update

$$A = \alpha \mathbf{X} \mathbf{Y}^H + \bar{\alpha} \mathbf{Y} \mathbf{X}^H + A$$

where *A* is a $n \times n$ Hermitian matrix stored in column-major format, **x** and **y** are vectors, and α is a scalar.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix A lower or upper part is stored, the other Hermitian part is not referenced and is inferred from the stored elements.
n		input	number of rows and columns of matrix A.
alpha	host or device	input	<type> scalar used for multiplication.</type>
x	device	input	<type> vector with $\mathbf n$ elements.</type>
incx		input	stride between consecutive elements of ${f x}$.
у	device	input	<type> vector with $\mathbf n$ elements.</type>

Param.	Memory	In/out	Meaning
incy		input	stride between consecutive elements of \mathbf{y} .
A	device	in/out	<pre><type> array of dimension lda x n with lda>=max(1,n). The imaginary parts of the diagonal elements are assumed and set to zero.</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n<0 or incx,incy=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

cher2, zher2

2.6.22. cublas<t>hpr()

This function performs the packed Hermitian rank-1 update

$$A = \alpha \mathbf{x} \mathbf{x}^H + A$$

where *A* is a $n \times n$ Hermitian matrix stored in packed format, **x** is a vector, and α is a scalar.

If **uplo == CULBAS_FILL_MODE_LOWER** then the elements in the lower triangular part of the Hermitian matrix A are packed together column by column without gaps, so that the element A(i, j) is stored in the memory location AP[i+((2*n-j+1)*j)/2] for j=1, ..., n and $i \ge j$. Consequently, the packed format requires only $\frac{n(n+1)}{2}$ elements for storage.

If $uplo == CULBAS_FILL_MODE_UPPER$ then the elements in the upper triangular part of the Hermitian matrix A are packed together column by column without gaps, so that

the element A(i, j) is stored in the memory location **AP[i+(j*(j+1))/2]** for j = 1, ..., n and $i \le j$. Consequently, the packed format requires only $\frac{n(n+1)}{2}$ elements for storage.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix ${\bf A}$ lower or upper part is stored, the other Hermitian part is not referenced and is inferred from the stored elements.
n		input	number of rows and columns of matrix A.
alpha	host or device	input	<type> scalar used for multiplication.</type>
x	device	input	<type> vector with \mathbf{n} elements.</type>
incx		input	stride between consecutive elements of ${f x}$.
AP	device	in/out	<type> array with A stored in packed format. The imaginary parts of the diagonal elements are assumed and set to zero.</type>

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n<0 or incx=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

chpr, zhpr

2.6.23. cublas<t>hpr2()

This function performs the packed Hermitian rank-2 update

$$A = \alpha \mathbf{x} \mathbf{y}^H + \bar{\alpha} \mathbf{y} \mathbf{x}^H + A$$

where *A* is a $n \times n$ Hermitian matrix stored in packed format, **x** and **y** are vectors, and α is a scalar.

If **uplo == CULBAS_FILL_MODE_LOWER** then the elements in the lower triangular part of the Hermitian matrix A are packed together column by column without gaps, so that the element A(i, j) is stored in the memory location AP[i+((2*n-j+1)*j)/2] for j=1, ..., n and $i \ge j$. Consequently, the packed format requires only $\frac{n(n+1)}{2}$ elements for storage.

If uplo == CULBAS_FILL_MODE_UPPER then the elements in the upper triangular part of the Hermitian matrix A are packed together column by column without gaps, so that the element A(i, j) is stored in the memory location AP[i+(j*(j+1))/2] for j=1, ..., n and $i \le j$. Consequently, the packed format requires only $\frac{n(n+1)}{2}$ elements for storage.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix A lower or upper part is stored, the other Hermitian part is not referenced and is inferred from the stored elements.
n		input	number of rows and columns of matrix A.
alpha	host or device	input	<type> scalar used for multiplication.</type>
х	device	input	<type> vector with n elements.</type>
incx		input	stride between consecutive elements of ${f x}$.
у	device	input	<type> vector with n elements.</type>
incy		input	stride between consecutive elements of y.
АР	device	in/out	<type> array with a stored in packed format. The imaginary parts of the diagonal elements are assumed and set to zero.</type>

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n<0 or incx,incy=0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

chpr2, zhpr2

2.7. cuBLAS Level-3 Function Reference

In this chapter we describe the Level-3 Basic Linear Algebra Subprograms (BLAS3) functions that perform matrix-matrix operations.

2.7.1. cublas<t>gemm()

```
cublasStatus t cublasSgemm(cublasHandle t handle,
                                                                                 cublasOperation_t transa, cublasOperation_t transb,
                                                                                 int m, int n, int k,
                                                                                 const float
                                                                                                                                                    *alpha,
                                                                                const float
                                                                                                                                                   *A, int lda,
                                                                                const float
                                                                                                                                                  *B, int ldb,
                                                                                const float *beta, float *C, int ldc)
                                                                                                                                                    *beta,
cublasStatus t cublasDgemm(cublasHandle t handle,
                                                                                cublasOperation t transa, cublasOperation t transb,
                                                                                int m, int n, int k,
                                                                               const double const
cublasStatus t cublasCgemm(cublasHandle t handle,
                                                                                cublasOperation_t transa, cublasOperation_t transb,
                                                                                int m, int n, int k,
                                                                               const cuComplex *A, int lda, const cuComplex *B, int ldb, *beta,
                                                                                cublasStatus t cublasZgemm(cublasHandle t handle,
                                                                                cublasOperation t transa, cublasOperation t transb,
                                                                                int m, int n, int k,
                                                                                const cuDoubleComplex *alpha,
                                                                                const cuDoubleComplex *A, int lda,
const cuDoubleComplex *B, int ldb,
                                                                                const cuDoubleComplex *beta,
                                                                                cuDoubleComplex *C, int ldc)
cublasStatus t cublasHgemm(cublasHandle t handle,
                                                                                cublasOperation_t transa, cublasOperation_t transb,
                                                                                 int m, int n, int k,
                                                                                const __half *alpha,
const __half *A, int lda,
                                                                                const half *B, int ldb,
                                                                                const
                                                                                                        _
half *beta,
                                                                                 half *C, int ldc)
```

This function performs the matrix-matrix multiplication

$$C = \alpha op(A)op(B) + \beta C$$

where α and β are scalars, and A, B and C are matrices stored in column-major format with dimensions op(A) $m \times k$, op(B) $k \times n$ and C $m \times n$, respectively. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == \text{CUBLAS_OP_N} \\ A^T & \text{if transa} == \text{CUBLAS_OP_T} \\ A^H & \text{if transa} == \text{CUBLAS_OP_C} \end{cases}$$

and op(B) is defined similarly for matrix B.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
transa		input	operation op(A) that is non- or (conj.) transpose.
transb		input	operation op(B) that is non- or (conj.) transpose.
m		input	number of rows of matrix op(A) and C.
n		input	number of columns of matrix op(B) and c.
k		input	number of columns of $op(a)$ and rows of $op(b)$.
alpha	host or device	input	<type> scalar used for multiplication.</type>
A	device	input	<pre><type> array of dimensions lda x k With lda>=max(1,m) if transa == CUBLAS_OP_N and lda x m With lda>=max(1,k) otherwise.</type></pre>
lda		input	leading dimension of two-dimensional array used to store the matrix ${\bf A}$.
В	device	input	<pre><type> array of dimension ldb x n with ldb>=max(1,k) if transa == CUBLAS_OP_N and ldb x k with ldb>=max(1,n) otherwise.</type></pre>
ldb		input	leading dimension of two-dimensional array used to store matrix B.
beta	host or device	input	<pre><type> scalar used for multiplication. If beta==0, c does not have to be a valid input.</type></pre>
С	device	in/out	<pre><type> array of dimensions ldc x n With ldc>=max(1,m).</type></pre>
ldc		input	leading dimension of a two-dimensional array used to store the matrix c.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters m,n,k<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision or in the case of cublasHgemm the device does not support math in half precision.
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

sgemm, dgemm, cgemm, zgemm

2.7.2. cublas<t>gemm3m()

This function performs the complex matrix-matrix multiplication, using Gauss complexity reduction algorithm. This can lead to an increase in performance up to 25%

$$C = \alpha \operatorname{op}(A) \operatorname{op}(B) + \beta C$$

where α and β are scalars, and A, B and C are matrices stored in column-major format with dimensions op(A) $m \times k$, op(B) $k \times n$ and C $m \times n$, respectively. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == \text{CUBLAS_OP_N} \\ A^T & \text{if transa} == \text{CUBLAS_OP_T} \\ A^H & \text{if transa} == \text{CUBLAS_OP_C} \end{cases}$$

and op(B) is defined similarly for matrix B.



These 2 routines are only supported on GPUs with architecture capabilities equal or greater than $5.0\,$

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
transa		input	operation op(A) that is non- or (conj.) transpose.
transb		input	operation op(B) that is non- or (conj.) transpose.
m		input	number of rows of matrix op(A) and c.
n		input	number of columns of matrix op(B) and c.
k		input	number of columns of op(A) and rows of op(B).
alpha	host or device	input	<type> scalar used for multiplication.</type>
A	device	input	<pre><type> array of dimensions lda x k With lda>=max(1,m) if transa == CUBLAS_OP_N and lda x m With lda>=max(1,k) otherwise.</type></pre>
lda		input	leading dimension of two-dimensional array used to store the matrix A.

Param.	Memory	In/out	Meaning
В	device	input	<pre><type> array of dimension ldb x n with ldb>=max(1,k) if transa == CUBLAS_OP_N and ldb x k with ldb>=max(1,n) otherwise.</type></pre>
ldb		input	leading dimension of two-dimensional array used to store matrix B .
beta	host or device	input	<pre><type> scalar used for multiplication. If beta==0, C does not have to be a valid input.</type></pre>
С	device	in/out	<pre><type> array of dimensions ldc x n With ldc>=max(1,m).</type></pre>
ldc		input	leading dimension of a two-dimensional array used to store the matrix c.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters m,n,k<0
CUBLAS_STATUS_ARCH_MISMATCH	the device has a compute capabilites lower than 5.0
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

cgemm, zgemm

2.7.3. cublas<t>gemmBatched()

```
cublasStatus t cublasSgemmBatched(cublasHandle t handle,
                                      cublasOperation t transa, cublasOperation t
                                      transb,
                                      const float *alpha,
const float *Aarray[], int lda,
const float *Barray[], int ldb,
const float *beta,
float *Carray[], int ldc, int
batchCount)
cublasStatus t cublasDgemmBatched(cublasHandle t handle,
                                      cublasOperation t transa, cublasOperation t
                                      int m, int n, int k,
                                      const double *alpha,
const double *Aarray[], int lda,
const double *Barray[], int ldb,
const double *beta,
double *Carray[], int ldc, int
batchCount)
cublasStatus t cublasCgemmBatched(cublasHandle t handle,
                                      cublasOperation_t transa, cublasOperation_t
transb,
                                      batchCount)
cublasStatus t cublasZgemmBatched(cublasHandle t handle,
                                      cublasOperation_t transa, cublasOperation_t
 transb,
                                      int m, int n, int k,
                                      const cuDoubleComplex *alpha,
                                      const cuDoubleComplex *Aarray[], int lda,
                                      const cuDoubleComplex *Barray[], int ldb,
                                      const cuDoubleComplex *beta,
                                      cuDoubleComplex *Carray[], int ldc, int
batchCount)
```

This function performs the matrix-matrix multiplications of an array of matrices.

```
C[i] = \alpha \operatorname{op}(A[i]) \operatorname{op}(B[i]) + \beta C[i], \text{ for } i \in [0, batchCount - 1]
```

where α and β are scalars, and A, B and C are arrays of pointers to matrices stored in column-major format with dimensions op(A[i]) $m \times k$, op(B[i]) $k \times n$ and C[i] $m \times n$, respectively. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == \text{CUBLAS_OP_N} \\ A^T & \text{if transa} == \text{CUBLAS_OP_T} \\ A^H & \text{if transa} == \text{CUBLAS_OP_C} \end{cases}$$

and op(B[i]) is defined similarly for matrix B[i].

This function is intended to be used for matrices of small sizes where the launch overhead is a significant factor. For small sizes, typically smaller than 100x100, this function improves significantly performance compared to making calls to its corresponding cublas<t>gemm routine. However, on GPU architectures that support

concurrent kernels, it might be advantageous to make multiple calls to **cublas<t>gemm** into different streams as the matrix sizes increase.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
transa		input	operation op(A[i]) that is non- or (conj.) transpose.
transb		input	operation op(B[i]) that is non- or (conj.) transpose.
m		input	number of rows of matrix op(A[i]) and C[i].
n		input	number of columns of $op(B[i])$ and $c[i]$.
k		input	number of columns of $op(A[i])$ and rows of $op(B[i])$.
alpha	host or device	input	<type> scalar used for multiplication.</type>
Aarray	device	input	array of pointers to <type> array, with each array of dim. lda x k With lda>=max(1,m) if transa==CUBLAS_OP_N and lda x m with lda>=max(1,k) otherwise.</type>
lda		input	leading dimension of two-dimensional array used to store each matrix ${\tt A[i]}$.
Barray	device	input	array of pointers to <type> array, with each array of dim. ldb x n With ldb>=max(1,k) if transa==CUBLAS_OP_N and ldb x k with ldb>=max(1,n) max(1,) otherwise.</type>
ldb		input	leading dimension of two-dimensional array used to store each matrix B[i].
beta	host or device	input	<pre><type> scalar used for multiplication. If beta == 0, C does not have to be a valid input.</type></pre>
Carray	device	in/out	array of pointers to <type> array. It has dimensions ldc x n with ldc>=max(1,m).</type>
ldc		input	leading dimension of two-dimensional array used to store each matrix c[i].
batchCount		input	number of pointers contained in Aarray, Barray and Carray.

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters m, n, k, batchCount<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

2.7.4. cublas<t>symm()

```
cublasStatus t cublasSsymm(cublasHandle t handle,
                                cublasSideMode_t side, cublasFillMode t uplo,
                                int m, int n,
                                const float
                                                          *alpha,
                                const float *A, in const float *B, in the const float the const float *C, int ldc)
                                                          *A, int lda,
                                                          *B, int ldb,
cublasStatus_t cublasDsymm(cublasHandle_t handle,
                                cublasSideMode_t side, cublasFillMode_t uplo,
                                int m, int n,
                               const double const double const double
                                const double
                                                          *alpha,
                                                         *A, int lda, *B, int ldb,
                                                          *beta,
                                                 *C, int ldc)
cublasStatus t cublasCsymm(cublasHandle t handle,
                                cublasSideMode_t side, cublasFillMode_t uplo,
                                int m, int n,
                                const cuComplex *alpha,
const cuComplex *A, int lda,
const cuComplex *B, int ldb,
const cuComplex *beta,
                                cublasStatus t cublasZsymm(cublasHandle t handle,
                                cublasSideMode t side, cublasFillMode t uplo,
                                int m, int n,
                                const cuDoubleComplex *alpha,
const cuDoubleComplex *A, int lda,
                                const cuDoubleComplex *B, int ldb,
                                const cuDoubleComplex *beta,
                                cuDoubleComplex *C, int ldc)
```

This function performs the symmetric matrix-matrix multiplication

$$C = \begin{cases} \alpha AB + \beta C & \text{if side} == \text{CUBLAS_SIDE_LEFT} \\ \alpha BA + \beta C & \text{if side} == \text{CUBLAS_SIDE_RIGHT} \end{cases}$$

where *A* is a symmetric matrix stored in lower or upper mode, *B* and *C* are $m \times n$ matrices, and α and β are scalars.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
side		input	indicates if matrix A is on the left or right of B.
uplo		input	indicates if matrix A lower or upper part is stored, the other symmetric part is not referenced and is inferred from the stored elements.
m		input	number of rows of matrix с and в, with matrix а sized accordingly.
n		input	number of columns of matrix с and в, with matrix а sized accordingly.
alpha	host or device	input	<type> scalar used for multiplication.</type>

Param.	Memory	In/out	Meaning	
A	device	input	<pre><type> array of dimension lda x m with lda>=max(1,m) if side == CUBLAS_SIDE_LEFT and lda x n with lda>=max(1,n) otherwise.</type></pre>	
lda		input	nput leading dimension of two-dimensional array used to store matrix A .	
В	device	input	<pre><type> array of dimension ldb x n with ldb>=max(1,m).</type></pre>	
ldb		input	leading dimension of two-dimensional array used to store matrix в.	
beta	host or device	input	<pre><type> scalar used for multiplication, if beta == 0 then c does not have to be a valid input.</type></pre>	
С	device	in/out	<pre><type> array of dimension ldc x n with ldc>=max(1,m).</type></pre>	
ldc		input	leading dimension of two-dimensional array used to store matrix c.	

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters m, n<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

ssymm, dsymm, csymm, zsymm

2.7.5. cublas<t>syrk()

```
cublasStatus t cublasSsyrk(cublasHandle t handle,
                                                                                                          cublasFillMode_t uplo, cublasOperation t trans,
                                                                                                          int n, int k,
const float
                                                                                                        *alpha,
                                                                                                                                                                                            *A, int lda,
cublasStatus t cublasDsyrk(cublasHandle t handle,
                                                                                                          cublasFillMode_t uplo, cublasOperation_t trans,
                                                                                                         int n, int k,
                                                                                                        const double const double const double to the const double const double to the const d
                                                                                                                                                                                               *alpha,
                                                                                                                                                                                           *A, int lda, *beta,
cublasStatus t cublasCsyrk(cublasHandle t handle,
                                                                                                          cublasFillMode t uplo, cublasOperation t trans,
                                                                                                          int n, int k,
                                                                                                        const cuComplex *alpha,
const cuComplex *A, int lda,
const cuComplex *beta,
cuComplex *C, int ldc)
cublasStatus_t cublasZsyrk(cublasHandle_t handle,
                                                                                                          cublasFillMode t uplo, cublasOperation t trans,
                                                                                                          int n, int k,
                                                                                                          const cuDoubleComplex *alpha,
                                                                                                          const cuDoubleComplex *A, int lda,
                                                                                                          const cuDoubleComplex *beta,
                                                                                                          cuDoubleComplex *C, int ldc)
```

This function performs the symmetric rank- *k* update

$$C = \alpha \operatorname{op}(A) \operatorname{op}(A)^{T} + \beta C$$

where α and β are scalars, C is a symmetric matrix stored in lower or upper mode, and A is a matrix with dimensions op(A) $n \times k$. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == CUBLAS_OP_N \\ A^T & \text{if transa} == CUBLAS_OP_T \end{cases}$$

Param.	Memory	In/out	Meaning	
handle		input	handle to the cuBLAS library context.	
uplo		input indicates if matrix c lower or upper part is stored, the other symmetric part is not referenced and is inferred from the stored elements.		
trans		input	operation op(A) that is non- or transpose.	
n		input	nput number of rows of matrix op(A) and c.	
k		input	number of columns of matrix op(A).	
alpha	host or device	input	<type> scalar used for multiplication.</type>	
А	device	input	<pre><type> array of dimension lda x k with lda>=max(1,n) if trans == CUBLAS_OP_N and lda x n with lda>=max(1,k) otherwise.</type></pre>	

Param.	Memory	In/out	Meaning
lda		input	leading dimension of two-dimensional array used to store matrix A.
beta	host or device	input	<pre><type> scalar used for multiplication, if beta==0 then c does not have to be a valid input.</type></pre>
С	device	in/out	<pre><type> array of dimension ldc x n, with ldc>=max(1,n).</type></pre>
ldc		input	leading dimension of two-dimensional array used to store matrix c.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,k<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

ssyrk, dsyrk, csyrk, zsyrk

2.7.6. cublas<t>syr2k()

```
cublasStatus t cublasSsyr2k(cublasHandle t handle,
                                                                                                                                                                                 cublasFillMode_t uplo, cublasOperation t trans,
                                                                                                                                                                                 int n, int k,
                                                                                                                                                                             const float
*C, int ldc)
                                                                                                                                                                                                                                                                                                                        *alpha,
                                                                                                                                                                                                                                                                                                                       *A, int lda,
                                                                                                                                                                                                                                                                                                                          *B, int ldb,
cublasStatus t cublasDsyr2k(cublasHandle t handle,
                                                                                                                                                                              cublasFillMode_t uplo, cublasOperation_t trans,
                                                                                                                                                                               int n, int k,
                                                                                                                                                                            const double const double const double const double const double const double double const doubl
                                                                                                                                                                                                                                                                                                                          *alpha,
                                                                                                                                                                                                                                                                                                                    *A, int lda,
*B, int ldb,
cublasStatus t cublasCsyr2k(cublasHandle t handle,
                                                                                                                                                                               cublasFillMode_t uplo, cublasOperation_t trans,
                                                                                                                                                                               int n, int k,
                                                                                                                                                                               const cuComplex
                                                                                                                                                                              const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex cuComp
                                                                                                                                                                                                                                                                                                                        *alpha,
                                                                                                                                                                               cublasStatus t cublasZsyr2k(cublasHandle t handle,
                                                                                                                                                                                cublasFillMode t uplo, cublasOperation t trans,
                                                                                                                                                                               int n, int k,
                                                                                                                                                                               const cuDoubleComplex *alpha,
const cuDoubleComplex *A, int lda,
                                                                                                                                                                                const cuDoubleComplex *B, int ldb,
                                                                                                                                                                                const cuDoubleComplex *beta,
                                                                                                                                                                                cuDoubleComplex *C, int ldc)
```

This function performs the symmetric rank- 2k update

$$C = \alpha(\operatorname{op}(A)\operatorname{op}(B)^{T} + \operatorname{op}(B)\operatorname{op}(A)^{T}) + \beta C$$

where α and β are scalars, C is a symmetric matrix stored in lower or upper mode, and A and B are matrices with dimensions op(A) $n \times k$ and op(B) $n \times k$, respectively. Also, for matrix A and B

$$op(A)$$
 and $op(B) = \begin{cases} A \text{ and } B \\ A^T \text{ and } B^T \end{cases}$ if trans == CUBLAS_OP_N

Param.	Memory	In/out	Meaning	
handle		input	handle to the cuBLAS library context.	
uplo		input	indicates if matrix c lower or upper part, is stored, the other symmetric part is not referenced and is inferred from the stored elements.	
trans		input	input operation op(A) that is non- or transpose.	
n		input	number of rows of matrix op(A), op(B) and C.	
k		input	number of columns of matrix $op(A)$ and $op(B)$.	
alpha	host or device	input	<type> scalar used for multiplication.</type>	

Param.	Memory	In/out	Meaning	
A	device	input	<pre><type> array of dimension lda x k with lda>=max(1,n) if transa == CUBLAS_OP_N and lda x n with lda>=max(1,k) otherwise.</type></pre>	
lda		input	leading dimension of two-dimensional array used to store matrix A.	
В	device	input	<pre><type> array of dimensions ldb x k with ldb>=max(1,n) if transa == CUBLAS_OP_N and ldb x n with ldb>=max(1,k) otherwise.</type></pre>	
ldb		input	leading dimension of two-dimensional array used to store matrix в.	
beta	host or device	input	<pre><type> scalar used for multiplication, if beta==0, then c does not have to be a valid input.</type></pre>	
С	device	in/out	<pre><type> array of dimensions ldc x n with ldc>=max(1,n).</type></pre>	
ldc		input	leading dimension of two-dimensional array used to store matrix c.	

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,k<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

ssyr2k, dsyr2k, csyr2k, zsyr2k

2.7.7. cublas<t>syrkx()

```
cublasStatus t cublasSsyrkx(cublasHandle t handle,
                                     cublasFillMode t uplo, cublasOperation t trans,
                                     int n, int k,
                                    const float *alpha
const float *A, in
const float *B, in
const float *beta,
float *C, int ldc)
                                                                  *alpha,
                                                                 *A, int lda,
*B, int ldb,
                                                                  *beta,
cublasStatus t cublasDsyrkx(cublasHandle_t handle,
                                     cublasFillMode_t uplo, cublasOperation_t trans,
                                    int n, int k,

const double

*C, int ldc)
cublasStatus t cublasCsyrkx(cublasHandle t handle,
                                    cublasFillMode_t uplo, cublasOperation_t trans,
                                    int n, int k,
                                    const cuComplex
const cuComplex
const cuComplex
const cuComplex
*A, int lda,
*B, int ldb,
                                                                 *beta,
                                    const cuComplex
                                    cuComplex *C, int ldc)
cublasStatus t cublasZsyrkx(cublasHandle t handle,
                                     cublasFillMode_t uplo, cublasOperation_t trans,
                                     int n, int k,
                                     const cuDoubleComplex *alpha,
                                     const cuDoubleComplex *A, int lda,
                                     const cuDoubleComplex *B, int ldb,
                                     const cuDoubleComplex *beta,
                                     cuDoubleComplex *C, int ldc)
```

This function performs a variation of the symmetric rank- *k* update

$$C = \alpha(\operatorname{op}(A)\operatorname{op}(B)^T + \beta C$$

where α and β are scalars, C is a symmetric matrix stored in lower or upper mode, and A and B are matrices with dimensions op(A) $n \times k$ and op(B) $n \times k$, respectively. Also, for matrix A and B

op(A) and op(B) =
$$\begin{cases} A \text{ and } B & \text{if trans} == \text{CUBLAS_OP_N} \\ A^T \text{ and } B^T & \text{if trans} == \text{CUBLAS_OP_T} \end{cases}$$

This routine can be used when B is in such way that the result is garanteed to be symmetric. An usual example is when the matrix B is a scaled form of the matrix A: this is equivalent to B being the product of the matrix A and a diagonal matrix. For an efficient computation of the product of a regular matrix with a diagonal matrix, refer to the routine cublas<t>dgmm.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix c lower or upper part, is stored, the other symmetric part is not referenced and is inferred from the stored elements.

Param.	Memory	In/out	Meaning
trans		input	operation op(A) that is non- or transpose.
n		input	number of rows of matrix op(A), op(B) and C.
k		input	number of columns of matrix op(A) and op(B).
alpha	host or device	input	<type> scalar used for multiplication.</type>
A	device	input	<pre><type> array of dimension lda x k with lda>=max(1,n) if transa == CUBLAS_OP_N and lda x n with lda>=max(1,k) otherwise.</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A.
В	device	input	<pre><type> array of dimensions ldb x k with ldb>=max(1,n) if transa == CUBLAS_OP_N and ldb x n with ldb>=max(1,k) otherwise.</type></pre>
ldb		input	leading dimension of two-dimensional array used to store matrix B.
beta	host or device	input	<pre><type> scalar used for multiplication, if beta==0, then c does not have to be a valid input.</type></pre>
С	device	in/out	<pre><type> array of dimensions ldc $x n$ with ldc>=max(1,n).</type></pre>
ldc		input	leading dimension of two-dimensional array used to store matrix c.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,k<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to: ssyrk, dsyrk, csyrk, zsyrk and ssyr2k, dsyr2k, csyr2k, zsyr2k

2.7.8. cublas<t>trmm()

```
cublasStatus t cublasStrmm(cublasHandle t handle,
                             cublasSideMode t side, cublasFillMode t uplo,
                             cublasOperation t trans, cublasDiagType t diag,
                             int m, int n,
                             const float
                                                     *alpha,
                             const float
                                                     *A, int lda,
*B, int ldb,
*C, int ldc)
                             float
cublasStatus t cublasDtrmm(cublasHandle t handle,
                             cublasSideMode t side, cublasFillMode t uplo,
                             cublasOperation_t trans, cublasDiagType_t diag,
                             int m, int n,
                             const double const double const double
                                                     *alpha,
                                                    *A, int lda,
                                                    *B, int ldb,
                                                     *C, int ldc)
                             double
cublasStatus t cublasCtrmm(cublasHandle_t handle,
                             cublasSideMode t side, cublasFillMode t uplo,
                             cublasOperation_t trans, cublasDiagType_t diag,
                             int m, int n,
                                                  *alpha,
                             const cuComplex
const cuComplex
const cuComplex
cuComplex
                                                     *A, int lda, *B, int ldb,
                                                     *C, int ldc)
                             cuComplex
cublasStatus t cublasZtrmm(cublasHandle t handle,
                             cublasSideMode t side, cublasFillMode t uplo,
                             cublasOperation t trans, cublasDiagType t diag,
                             int m, int n,
                             const cuDoubleComplex *alpha,
                             const cuDoubleComplex *A, int lda,
                             const cuDoubleComplex *B, int ldb,
                             cuDoubleComplex
                                                   *C, int ldc)
```

This function performs the triangular matrix-matrix multiplication

$$C = \begin{cases} \alpha \operatorname{op}(A)B & \text{if side} == \mathsf{CUBLAS_SIDE_LEFT} \\ \alpha B \operatorname{op}(A) & \text{if side} == \mathsf{CUBLAS_SIDE_RIGHT} \end{cases}$$

where A is a triangular matrix stored in lower or upper mode with or without the main diagonal, B and C are $m \times n$ matrix, and α is a scalar. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == \text{CUBLAS_OP_N} \\ A^T & \text{if transa} == \text{CUBLAS_OP_T} \\ A^H & \text{if transa} == \text{CUBLAS_OP_C} \end{cases}$$

Notice that in order to achieve better parallelism cuBLAS differs from the BLAS API only for this routine. The BLAS API assumes an in-place implementation (with results written back to B), while the cuBLAS API assumes an out-of-place implementation (with results written into C). The application can obtain the in-place functionality of BLAS in the cuBLAS API by passing the address of the matrix B in place of the matrix C. No other overlapping in the input parameters is supported.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
side		input	indicates if matrix A is on the left or right of в.

Param.	Memory	In/out	Meaning
uplo		input	indicates if matrix A lower or upper part is stored, the other part is not referenced and is inferred from the stored elements.
trans		input	operation op(A) that is non- or (conj.) transpose.
diag		input	indicates if the elements on the main diagonal of matrix ${\tt A}$ are unity and should not be accessed.
m		input	number of rows of matrix ${f B}$, with matrix ${f A}$ sized accordingly.
n		input	number of columns of matrix ${\bf B}$, with matrix ${\bf A}$ sized accordingly.
alpha	host or device	input	<pre><type> scalar used for multiplication, if alpha==0 then ${\tt A}$ is not referenced and ${\tt B}$ does not have to be a valid input.</type></pre>
A	device	input	<pre><type> array of dimension lda x m With lda>=max(1,m) if side == CUBLAS_SIDE_LEFT and lda x n With lda>=max(1,n) otherwise.</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A .
В	device	input	<pre><type> array of dimension ldb x n with ldb>=max(1,m).</type></pre>
ldb		input	leading dimension of two-dimensional array used to store matrix в.
С	device	in/out	<pre><type> array of dimension ldc x n With ldc>=max(1,m).</type></pre>
ldc		input	leading dimension of two-dimensional array used to store matrix c.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters m, n<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

strmm, dtrmm, ctrmm, ztrmm

2.7.9. cublas<t>trsm()

```
cublasStatus t cublasStrsm(cublasHandle t handle,
                           cublasSideMode_t side, cublasFillMode t uplo,
                           cublasOperation t trans, cublasDiagType t diag,
                           int m, int n,
                           const float *A, int ldb)
                                                 *alpha,
                                                 *A, int lda,
cublasStatus t cublasDtrsm(cublasHandle t handle,
                           cublasSideMode t side, cublasFillMode t uplo,
                           cublasOperation_t trans, cublasDiagType_t diag,
                           int m, int n,
                           const double
                                                 *alpha,
                                                *A, int lda,
                           const double *A, in double *B, int ldb)
cublasStatus t cublasCtrsm(cublasHandle t handle,
                           cublasSideMode t side, cublasFillMode t uplo,
                           cublasOperation_t trans, cublasDiagType_t diag,
                           int m, int n,
                           const cuComplex
                                                 *alpha,
                                               *A, int lda,
                           const cuComplex *A, in cuComplex *B, int ldb)
cublasStatus t cublasZtrsm(cublasHandle_t handle,
                           cublasSideMode_t side, cublasFillMode t uplo,
                           cublasOperation t trans, cublasDiagType t diag,
                           int m, int n,
                           const cuDoubleComplex *alpha,
                           const cuDoubleComplex *A, int lda,
                           cuDoubleComplex *B, int ldb)
```

This function solves the triangular linear system with multiple right-hand-sides

```
 \begin{cases} op(A)X = \alpha B & \text{if side} == CUBLAS\_SIDE\_LEFT \\ Xop(A) = \alpha B & \text{if side} == CUBLAS\_SIDE\_RIGHT \end{cases}
```

where A is a triangular matrix stored in lower or upper mode with or without the main diagonal, X and B are $m \times n$ matrices, and α is a scalar. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == \text{CUBLAS_OP_N} \\ A^T & \text{if transa} == \text{CUBLAS_OP_T} \\ A^H & \text{if transa} == \text{CUBLAS_OP_C} \end{cases}$$

The solution *X* overwrites the right-hand-sides *B* on exit.

No test for singularity or near-singularity is included in this function.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
side		input	indicates if matrix ${f a}$ is on the left or right of ${f x}$.
uplo		input	indicates if matrix A lower or upper part is stored, the other part is not referenced and is inferred from the stored elements.
trans		input	operation op(A) that is non- or (conj.) transpose.
diag		input	indicates if the elements on the main diagonal of matrix A are unity and should not be accessed.

Param.	Memory	In/out	Meaning	
m		input	number of rows of matrix B, with matrix A sized accordingly.	
n		input	nput number of columns of matrix ${f B}$, with matrix ${f A}$ is sized accordingly.	
alpha	host or device	input	<type> scalar used for multiplication, if alpha==0 then A is not referenced and в does not have to be a valid input.</type>	
A	device	input	<pre><type> array of dimension lda x m With lda>=max(1,m) if side == CUBLAS_SIDE_LEFT and lda x n With lda>=max(1,n) otherwise.</type></pre>	
lda		input	leading dimension of two-dimensional array used to store matrix ${\bf A}$.	
В	device	in/out	<type> array. It has dimensions ldb x n with ldb>=max(1,m).</type>	
ldb		input	leading dimension of two-dimensional array used to store matrix в.	

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters m, n<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

strsm, dtrsm, ctrsm, ztrsm

2.7.10. cublas<t>trsmBatched()

```
cublasStatus t cublasStrsmBatched( cublasHandle t handle,
                                     cublasSideMode_t side,
cublasFillMode_t uplo,
                                    cublasOperation t trans,
                                     cublasDiagType t diag,
                                     int m,
                                     int n,
                                     const float *alpha,
                                    float *A[],
                                    int lda,
                                    float *B[],
                                    int ldb,
                                     int batchCount);
cublasStatus t cublasDtrsmBatched( cublasHandle t
                                                       handle,
                                    cublasSideMode t side,
                                     cublasFillMode t uplo,
                                     cublasOperation t trans,
                                     cublasDiagType t diag,
                                     int m,
                                    int n,
                                     const double *alpha,
                                     double *A[],
                                    int lda,
double *B[],
                                    int ldb,
                                    int batchCount);
                                                       handle,
cublasStatus t cublasCtrsmBatched( cublasHandle t
                                    cublasSideMode_t side,
cublasFillMode_t uplo,
                                    cublasOperation t trans,
                                    cublasDiagType t diag,
                                    int m,
                                     int n,
                                     const cuComplex *alpha,
                                    cuComplex *A[],
                                    int lda,
                                    cuComplex *B[],
                                     int ldb,
                                     int batchCount);
cublasStatus_t cublasZtrsmBatched( cublasHandle_t
                                                       handle,
                                    cublasSideMode t side,
                                    cublasFillMode_t uplo,
                                     cublasOperation_t trans,
                                     cublasDiagType t diag,
                                     int m,
                                     const cuDoubleComplex *alpha,
                                     cuDoubleComplex *A[],
                                     int lda,
                                     cuDoubleComplex *B[],
                                     int ldb,
                                     int batchCount);
```

This function solves an array of triangular linear systems with multiple right-hand-sides

```
 \begin{cases} op(A[i]X[i] = \alpha B[i] & \text{if side} == \text{CUBLAS\_SIDE\_LEFT} \\ X[i]op(A[i]) = \alpha B[i] & \text{if side} == \text{CUBLAS\_SIDE\_RIGHT} \end{cases}
```

where A[i] is a triangular matrix stored in lower or upper mode with or without the main diagonal, X[i] and B[i] are $m \times n$ matrices, and α is a scalar. Also, for matrix A

$$op(A[i]) = \begin{cases} A[i] & \text{if transa} == \text{CUBLAS_OP_N} \\ A^T[i] & \text{if transa} == \text{CUBLAS_OP_T} \\ A^H[i] & \text{if transa} == \text{CUBLAS_OP_C} \end{cases}$$

The solution X[i] overwrites the right-hand-sides B[i] on exit.

No test for singularity or near-singularity is included in this function.

This function works for any sizes but is intended to be used for matrices of small sizes where the launch overhead is a significant factor. For bigger sizes, it might be advantageous to call **batchCount** times the regular **cublas<t>trsm** within a set of CUDA streams.

The current implementation is limited to devices with compute capability above or equal 2.0.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
side		input	indicates if matrix $A[i]$ is on the left or right of $x[i]$.
uplo		input	indicates if matrix A[i] lower or upper part is stored, the other part is not referenced and is inferred from the stored elements.
trans		input	operation op(A[i]) that is non- or (conj.) transpose.
diag		input	indicates if the elements on the main diagonal of matrix <code>a[i]</code> are unity and should not be accessed.
m		input	number of rows of matrix B[i], with matrix A[i] sized accordingly.
n		input	number of columns of matrix B[i], with matrix A[i] is sized accordingly.
alpha	host or device	input	<pre><type> scalar used for multiplication, if alpha==0 then a[i] is not referenced and B[i] does not have to be a valid input.</type></pre>
A	device	input	array of pointers to <type> array, with each array of dim. lda x m With lda>=max(1,m) if transa==CUBLAS_OP_N and lda x n with lda>=max(1,n) otherwise.</type>
lda		input	leading dimension of two-dimensional array used to store matrix A[i].
В	device	in/out	array of pointers to <type> array, with each array of dim. ldb x n With ldb>=max(1,m)</type>
ldb		input	leading dimension of two-dimensional array used to store matrix B[i].
batchCount		input	number of pointers contained in A and B.

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters m, n<0.
CUBLAS_STATUS_ARCH_MISMATCH	the device is below compute capability 2.0.
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

strsm, dtrsm, ctrsm, ztrsm

2.7.11. cublas<t>hemm()

This function performs the Hermitian matrix-matrix multiplication

$$C = \begin{cases} \alpha AB + \beta C & \text{if side} == \text{CUBLAS_SIDE_LEFT} \\ \alpha BA + \beta C & \text{if side} == \text{CUBLAS_SIDE_RIGHT} \end{cases}$$

where *A* is a Hermitian matrix stored in lower or upper mode, *B* and *C* are $m \times n$ matrices, and α and β are scalars.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
side		input	indicates if matrix ${f A}$ is on the left or right of ${f B}$.
uplo		input	indicates if matrix A lower or upper part is stored, the other Hermitian part is not referenced and is inferred from the stored elements.
m		input	number of rows of matrix ${\tt c}$ and ${\tt B}$, with matrix ${\tt A}$ sized accordingly.
n		input	number of columns of matrix c and B, with matrix A sized accordingly.
alpha	host or device	input	<type> scalar used for multiplication.</type>

Param.	Memory	In/out	Meaning
A	device	input	<pre><type> array of dimension lda x m with lda>=max(1,m) if side==CUBLAS_SIDE_LEFT and lda x n with lda>=max(1,n) otherwise. The imaginary parts of the diagonal elements are assumed to be zero.</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A.
В	device	input	<pre><type> array of dimension ldb x n with ldb>=max(1,m).</type></pre>
ldb		input	leading dimension of two-dimensional array used to store matrix в.
beta		input	<pre><type> scalar used for multiplication, if beta==0 then c does not have to be a valid input.</type></pre>
С	device	in/out	<pre><type> array of dimensions ldc x n with ldc>=max(1,m).</type></pre>
ldc		input	leading dimension of two-dimensional array used to store matrix c.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters m, n<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

chemm, zhemm

2.7.12. cublas<t>herk()

This function performs the Hermitian rank- *k* update

$$C = \alpha \operatorname{op}(A) \operatorname{op}(A)^H + \beta C$$

where α and β are scalars, C is a Hermitian matrix stored in lower or upper mode, and A is a matrix with dimensions op(A) $n \times k$. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == \text{CUBLAS_OP_N} \\ A^H & \text{if transa} == \text{CUBLAS_OP_C} \end{cases}$$

Param.	Memory	In/out	Meaning	
handle		input	handle to the cuBLAS library context.	
uplo		input	indicates if matrix ${\bf A}$ lower or upper part is stored, the other Hermitian part is not referenced and is inferred from the stored elements.	
trans		input	operation op(A) that is non- or (conj.) transpose.	
n		input	number of rows of matrix op(A) and C.	
k		input	number of columns of matrix op(A).	
alpha	host or device	input	<type> scalar used for multiplication.</type>	
A	device	input	<pre><type> array of dimension lda x k with lda>=max(1,n) if transa == CUBLAS_OP_N and lda x n with lda>=max(1,k) otherwise.</type></pre>	
lda		input	leading dimension of two-dimensional array used to store matrix A .	
beta		input	<pre><type> scalar used for multiplication, if beta==0 then c does not have to be a valid input.</type></pre>	
С	device	in/out	<pre><type> array of dimension ldc x n, with ldc>=max(1,n). The imaginary parts of the diagonal elements are assumed and set to zero.</type></pre>	
ldc		input	leading dimension of two-dimensional array used to store matrix c.	

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,k<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

cherk, zherk

2.7.13. cublas<t>her2k()

This function performs the Hermitian rank- 2k update

$$C = \alpha \operatorname{op}(A) \operatorname{op}(B)^{H} + \bar{\alpha} \operatorname{op}(B) \operatorname{op}(A)^{H} + \beta C$$

where α and β are scalars, C is a Hermitian matrix stored in lower or upper mode, and A and B are matrices with dimensions op(A) $n \times k$ and op(B) $n \times k$, respectively. Also, for matrix A and B

$$op(A)$$
 and $op(B) = \begin{cases} A \text{ and } B & \text{if trans} == CUBLAS_OP_N \\ A^H \text{ and } B^H & \text{if trans} == CUBLAS_OP_C \end{cases}$

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix A lower or upper part is stored, the other Hermitian part is not referenced and is inferred from the stored elements.
trans		input	operation op(A) that is non- or (conj.) transpose.
n		input	number of rows of matrix op(A), op(B) and c.
k		input	number of columns of matrix op(A) and op(B).
alpha	host or device	input	<type> scalar used for multiplication.</type>
A	device	input	<pre><type> array of dimension lda x k with lda>=max(1,n) if transa == CUBLAS_OP_N and lda x n with lda>=max(1,k) otherwise.</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A.
В	device	input	<pre><type> array of dimension ldb x k with ldb>=max(1,n) if transa == CUBLAS_OP_N and ldb x n with ldb>=max(1,k) otherwise.</type></pre>
ldb		input	leading dimension of two-dimensional array used to store matrix в.

Param.	Memory	In/out	Meaning
beta	host or device	input	<pre><type> scalar used for multiplication, if beta==0 then c does not have to be a valid input.</type></pre>
С	device	in/out	<pre><type> array of dimension ldc x n, with ldc>=max(1,n). The imaginary parts of the diagonal elements are assumed and set to zero.</type></pre>
ldc		input	leading dimension of two-dimensional array used to store matrix c.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,k<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

cher2k, zher2k

2.7.14. cublas<t>herkx()

This function performs a variation of the Hermitian rank- *k* update

$$C = \alpha \operatorname{op}(A) \operatorname{op}(B)^H + \beta C$$

where α and β are scalars, C is a Hermitian matrix stored in lower or upper mode, and A and B are matrices with dimensions op(A) $n \times k$ and op(B) $n \times k$, respectively. Also, for matrix A and B

$$op(A)$$
 and $op(B) = \begin{cases} A \text{ and } B & \text{if trans} == CUBLAS_OP_N \\ A^H \text{ and } B^H & \text{if trans} == CUBLAS_OP_C \end{cases}$

This routine can be used when the matrix B is in such way that the result is garanteed to be hermitian. An usual example is when the matrix B is a scaled form of the matrix A: this is equivalent to B being the product of the matrix A and a diagonal matrix. For an efficient computation of the product of a regular matrix with a diagonal matrix, refer to the routine cublas<t>dgmm.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix A lower or upper part is stored, the other Hermitian part is not referenced and is inferred from the stored elements.
trans		input	operation op(A) that is non- or (conj.) transpose.
n		input	number of rows of matrix op(A), op(B) and c.
k		input	number of columns of matrix op(A) and op(B).
alpha	host or device	input	<type> scalar used for multiplication.</type>
A	device	input	<pre><type> array of dimension lda x k with lda>=max(1,n) if transa == CUBLAS_OP_N and lda x n with lda>=max(1,k) otherwise.</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A.
В	device	input	<pre><type> array of dimension ldb x k with ldb>=max(1,n) if transa == CUBLAS_OP_N and ldb x n with ldb>=max(1,k) otherwise.</type></pre>
ldb		input	leading dimension of two-dimensional array used to store matrix в.
beta	host or device	input	real scalar used for multiplication, if beta==0 then c does not have to be a valid input.
С	device	in/out	<pre><type> array of dimension ldc x n, with ldc>=max(1,n). The imaginary parts of the diagonal elements are assumed and set to zero.</type></pre>
ldc		input	leading dimension of two-dimensional array used to store matrix c.

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,k<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

cherk, zherk and

cher2k, zher2k

2.8. BLAS-like Extension

In this chapter we describe the BLAS-extension functions that perform matrix-matrix operations.

2.8.1. cublas<t>geam()

```
cublasStatus t cublasSgeam(cublasHandle t handle,
                                                                                                                                                                                                                                                         cublasOperation t transa, cublasOperation t transb,
                                                                                                                                                                                                                                                  int m, int n,
const float
cons
cublasStatus t cublasDgeam(cublasHandle t handle,
                                                                                                                                                                                                                                                     cublasOperation_t transa, cublasOperation_t transb,
                                                                                                                                                                                                                                                      int m, int n,
                                                                                                                                                                                                                                                 const double const
                                                                                                                                                                                                                                                                                                                                                                                                                                                                        *alpha,
                                                                                                                                                                                                                                                                                                                                                                                                                                                                        *A, int lda,
                                                                                                                                                                                                                                                                                                                                                                                                                                                                      *B, int ldb,
cublasStatus t cublasCgeam(cublasHandle t handle,
                                                                                                                                                                                                                                                     cublasOperation_t transa, cublasOperation_t transb,
                                                                                                                                                                                                                                                        int m, int n,
                                                                                                                                                                                                                                                  const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex const cuComplex 
cublasStatus_t cublasZgeam(cublasHandle_t handle,
                                                                                                                                                                                                                                                    cublasOperation_t transa, cublasOperation_t transb,
                                                                                                                                                                                                                                                      int m, int n,
                                                                                                                                                                                                                                                      const cuDoubleComplex *alpha,
                                                                                                                                                                                                                                                      const cuDoubleComplex *A, int lda,
const cuDoubleComplex *beta,
                                                                                                                                                                                                                                                        const cuDoubleComplex *B, int ldb,
                                                                                                                                                                                                                                                        cuDoubleComplex *C, int ldc)
```

This function performs the matrix-matrix addition/transposition

```
C = \alpha \operatorname{op}(A) + \beta \operatorname{op}(B)
```

where α and β are scalars, and A, B and C are matrices stored in column-major format with dimensions op(A) $m \times n$, op(B) $m \times n$ and C $m \times n$, respectively. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == \text{CUBLAS_OP_N} \\ A^T & \text{if transa} == \text{CUBLAS_OP_T} \\ A^H & \text{if transa} == \text{CUBLAS_OP_C} \end{cases}$$

and op(B) is defined similarly for matrix B.

The operation is out-of-place if C does not overlap A or B.

The in-place mode supports the following two operations,

$$C = \alpha^* C + \beta op(B)$$

$$C = \alpha \operatorname{op}(A) + \beta * C$$

For in-place mode, if C = A, ldc = lda and transa = CUBLAS_OP_N. If C = B, ldc = ldb and transb = CUBLAS_OP_N. If the user does not meet above requirements, CUBLAS_STATUS_INVALID_VALUE is returned.

The operation includes the following special cases:

the user can reset matrix C to zero by setting *alpha=*beta=0.

the user can transpose matrix A by setting *alpha=1 and *beta=0.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
transa		input	operation op(A) that is non- or (conj.) transpose.
transb		input	operation op(B) that is non- or (conj.) transpose.
m		input	number of rows of matrix op(A) and c.
n		input	number of columns of matrix op(B) and c.
alpha	host or device	input	<pre><type> scalar used for multiplication. If *alpha == 0, A does not have to be a valid input.</type></pre>
A	device	input	<pre><type> array of dimensions lda x n With lda>=max(1,m) if transa == CUBLAS_OP_N and lda x m With lda>=max(1,n) otherwise.</type></pre>
lda		input	leading dimension of two-dimensional array used to store the matrix A.
В	device	input	<pre><type> array of dimension ldb x n with ldb>=max(1,m) if transa == CUBLAS_OP_N and ldb x m with ldb>=max(1,n) otherwise.</type></pre>
ldb		input	leading dimension of two-dimensional array used to store matrix в.
beta	host or device	input	<type> scalar used for multiplication. If *beta == 0, в does not have to be a valid input.</type>
С	device	output	<pre><type> array of dimensions ldc x n With ldc>=max(1,m).</type></pre>
ldc		input	leading dimension of a two-dimensional array used to store the matrix c.

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized

Error Value	Meaning
CUBLAS_STATUS_INVALID_VALUE	the parameters m,n<0, alpha,beta=NULL or improper settings of in-place mode
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

2.8.2. cublas<t>dgmm()

This function performs the matrix-matrix multiplication

$$C = \begin{cases} A \times diag(X) & \text{if mode} == \text{CUBLAS_SIDE_RIGHT} \\ diag(X) \times A & \text{if mode} == \text{CUBLAS_SIDE_LEFT} \end{cases}$$

where A and C are matrices stored in column-major format with dimensions $m \times n$. X is a vector of size n if $mode == CUBLAS_SIDE_RIGHT$ and of size m if $mode == CUBLAS_SIDE_LEFT$. X is gathered from one-dimensional array x with stride incx. The absolute value of incx is the stride and the sign of incx is direction of the stride. If incx is positive, then we forward x from the first element. Otherwise, we backward x from the last element. The formula of X is

$$X[j] = \begin{cases} x[j \times incx] & \text{if } incx \ge 0 \\ x[(\chi - 1) \times |incx| - j \times |incx|] & \text{if } incx < 0 \end{cases}$$

where $\chi = m$ if mode == CUBLAS_SIDE_LEFT and $\chi = n$ if mode == CUBLAS_SIDE_RIGHT.

Example 1: if the user wants to perform $diag(diag(B)) \times A$, then incx = ldb + 1 where ldb is leading dimension of matrix **B**, either row-major or column-major.

Example 2: if the user wants to perform $\alpha \times A$, then there are two choices, either cublasgeam with *beta=0 and transa == CUBLAS_OP_N or cublasdgmm with incx=0 and x[0]=alpha.

The operation is out-of-place. The in-place only works if lda = ldc.

Param.	Memory	In/out	Meaning	
handle		input	handle to the cuBLAS library context.	
mode		input	left multiply if mode == CUBLAS_SIDE_LEFT or right multiply if mode == CUBLAS_SIDE_RIGHT	
m		input	number of rows of matrix A and C.	
n		input	number of columns of matrix A and C .	
А	device	input	<type> array of dimensions lda x n with lda>=max(1,m)</type>	
lda		input	leading dimension of two-dimensional array used to store the matrix ${\bf A}$.	
x	device	input	one-dimensional <type> array of size $inc \times m$ if mode == CUBLAS_SIDE_LEFT and $inc \times n$ if mode == CUBLAS_SIDE_RIGHT</type>	
incx		input	stride of one-dimensional array x.	
С	device	in/out	<type> array of dimensions ldc x n with ldc>=max(1,m).</type>	
ldc		input	leading dimension of a two-dimensional array used to store the matrix c.	

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters m, n<0 or mode != CUBLAS_SIDE_LEFT, CUBLAS_SIDE_RIGHT
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

2.8.3. cublas<t>getrfBatched()

```
cublasStatus t cublasSgetrfBatched(cublasHandle t handle,
                                    int n,
float *Aarray[],
                                   int lda,
                                   int *PivotArray,
                                   int *infoArray,
                                   int batchSize);
cublasStatus t cublasDgetrfBatched(cublasHandle t handle,
                                   int n,
                                   double *Aarray[],
                                   int lda,
                                   int *PivotArray,
                                   int *infoArray,
                                   int batchSize);
cublasStatus t cublasCgetrfBatched(cublasHandle t handle,
                                    int n,
                                   cuComplex *Aarray[],
                                   int lda,
                                   int *PivotArray,
                                   int *infoArray,
                                    int batchSize);
cublasStatus t cublasZgetrfBatched(cublasHandle t handle,
                                   cuDoubleComplex *Aarray[],
                                    int lda,
                                   int *PivotArray,
                                   int *infoArray,
                                   int batchSize);
```

Aarray is an array of pointers to matrices stored in column-major format with dimensions **nxn** and leading dimension **lda**.

This function performs the LU factorization of each Aarray[i] for i = 0, ..., batchSize-1 by the following equation

```
P*Aarray[i] = L*U
```

where \mathbf{P} is a permutation matrix which represents partial pivoting with row interchanges. \mathbf{L} is a lower triangular matrix with unit diagonal and \mathbf{U} is an upper triangular matrix.

Formally P is written by a product of permutation matrices Pj, for j = 1,2,...,n, say P = P1 * P2 * P3 * * Pn. Pj is a permutation matrix which interchanges two rows of vector x when performing Pj*x. Pj can be constructed by j element of PivotArray[i] by the following matlab code

```
// In Matlab PivotArray[i] is an array of base-1.
// In C, PivotArray[i] is base-0.
Pj = eye(n);
swap Pj(j,:) and Pj(PivotArray[i][j] ,:)
```

 ${\tt L}$ and ${\tt U}$ are written back to original matrix ${\tt A}$, and diagonal elements of ${\tt L}$ are discarded. The ${\tt L}$ and ${\tt U}$ can be constructed by the following matlab code

```
// A is a matrix of nxn after getrf.
L = eye(n);
for j = 1:n
    L(:,j+1:n) = A(:,j+1:n)
end
U = zeros(n);
for i = 1:n
    U(i,i:n) = A(i,i:n)
end
```

If matrix A (=Aarray[i]) is singular, getrf still works and the value of info(=infoArray[i]) reports first row index that LU factorization cannot proceed. If info is k, U(k,k) is zero. The equation P*A=L*U still holds, however L and U are from the following matlab code

```
// A is a matrix of nxn after getrf.
// info is k, which means U(k,k) is zero.
L = eye(n);
for j = 1:k-1
    L(:,j+1:n) = A(:,j+1:n)
end
U = zeros(n);
for i = 1:k-1
    U(i,i:n) = A(i,i:n)
end
for i = k:n
    U(i,k:n) = A(i,k:n)
end
```

This function is intended to be used for matrices of small sizes where the launch overhead is a significant factor.

cublas<t>getrfBatched supports non-pivot LU factorization if PivotArray is nil.

cublas<t>getrfBatched supports arbitrary dimension.

cublas<t>getrfBatched only supports compute capability 2.0 or above.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
n		input	number of rows and columns of Aarray[i].
Aarray	device	input	array of pointers to <type> array, with each array of dim. n $x \in \mathbb{N}$ n with lda>=max(1,n).</type>
lda		input	leading dimension of two-dimensional array used to store each matrix ${\tt Aarray[i]}$.
PivotArray	device	output	array of size n x batchSize that contains the pivoting sequence of each factorization of Aarray[i] stored in a linear fashion. If PivotArray is nil, pivoting is disabled.
infoArray	device	output	array of size batchSize that info(=infoArray[i]) contains the information of factorization of Aarray[i].
			If info=0, the execution is successful.
			If info = -j, the j-th parameter had an illegal value.

Param.	Memory	In/out	Meaning
			If info = k, U(k,k) is 0. The factorization has been completed, but U is exactly singular.
batchSize		input	number of pointers contained in A

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,batchSize,lda <0
CUBLAS_STATUS_ARCH_MISMATCH	the device has a compute capability < 200
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

sgeqrf, dgeqrf, cgeqrf, zgeqrf

2.8.4. cublas<t>getrsBatched()

```
cublasStatus t cublasSgetrsBatched(cublasHandle t handle,
                                    cublasOperation t trans,
                                    int n,
                                    int nrhs,
                                    const float *Aarray[],
                                    int lda,
                                    const int *devIpiv,
                                   float *Barray[],
                                   int ldb,
                                    int *info,
                                   int batchSize);
cublasStatus t cublasDgetrsBatched(cublasHandle t handle,
                                    cublasOperation t trans,
                                    int n,
                                   int nrhs,
                                    const double *Aarray[],
                                    int lda,
                                   const int *devIpiv,
                                    double *Barray[],
                                    int ldb,
                                    int *info,
                                    int batchSize);
cublasStatus t cublasCgetrsBatched(cublasHandle t handle,
                                    cublasOperation t trans,
                                    int n,
                                    int nrhs,
                                    const cuComplex *Aarray[],
                                   int lda,
                                   const int *devIpiv,
                                    cuComplex *Barray[],
                                    int ldb,
                                   int *info,
                                   int batchSize);
cublasStatus t cublasZgetrsBatched(cublasHandle t handle,
                                   cublasOperation t trans,
                                    int n,
                                   int nrhs,
                                    const cuDoubleComplex *Aarray[],
                                    int lda,
                                    const int *devIpiv,
                                    cuDoubleComplex *Barray[],
                                   int ldb,
                                    int *info,
                                   int batchSize);
```

This function solves an array of systems of linear equations of the form:

$$op(A[i])X[i] = \alpha B[i]$$

where A[i] is a matrix which has been LU factorized with pivoting , X[i] and B[i] are $n \times n$ rhs matrices. Also, for matrix A

$$op(A[i]) = \begin{cases} A[i] & \text{if trans} == \text{CUBLAS_OP_N} \\ A^T[i] & \text{if trans} == \text{CUBLAS_OP_T} \\ A^H[i] & \text{if trans} == \text{CUBLAS_OP_C} \end{cases}$$

This function is intended to be used for matrices of small sizes where the launch overhead is a significant factor.

cublas<t>getrsBatched supports non-pivot LU factorization if **devIpiv** is nil. cublas<t>getrsBatched supports arbitrary dimension.

cublas<t>getrsBatched only supports compute capability 2.0 or above.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
trans		input	operation op(A) that is non- or (conj.) transpose.
n		input	number of rows and columns of Aarray[i].
nrhs		input	number of columns of Barray[i].
Aarray	device	input	array of pointers to <type> array, with each array of dim. $n \times n$ with lda>=max(1,n).</type>
lda		input	leading dimension of two-dimensional array used to store each matrix Aarray[i].
devlpiv	device	input	array of size n x batchSize that contains the pivoting sequence of each factorization of Aarray[i] stored in a linear fashion. If devIpiv is nil, pivoting for all Aarray[i] is ignored.
Barray	device	input/ output	array of pointers to <type> array, with each array of dim. $n \times nrhs$ with ldb>=max(1,n).</type>
ldb		input	leading dimension of two-dimensional array used to store each solution matrix Barray[i].
info	host	output	If info=0, the execution is successful.
			If info = -j, the j-th parameter had an illegal value.
batchSize		input	number of pointers contained in A

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,batchSize,lda <0
CUBLAS_STATUS_ARCH_MISMATCH	the device has a compute capability < 200
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

sgeqrs, dgeqrs, cgeqrs, zgeqrs

2.8.5. cublas<t>getriBatched()

```
cublasStatus t cublasSgetriBatched(cublasHandle t handle,
                                   int n,
float *Aarray[],
                                   int lda,
                                   int *PivotArray,
                                   float *Carray[],
                                   int ldc,
                                   int *infoArray,
                                   int batchSize);
cublasStatus t cublasDgetriBatched(cublasHandle t handle,
                                   int n,
                                   double *Aarray[],
                                   int lda,
                                   int *PivotArray,
                                   double *Carray[],
                                   int ldc,
                                   int *infoArray,
                                   int batchSize);
cublasStatus t cublasCgetriBatched(cublasHandle t handle,
                                   int n,
                                   cuComplex *Aarray[],
                                   int lda,
                                   int *PivotArray,
                                   cuComplex *Carray[],
                                   int ldc,
                                   int *infoArray,
                                   int batchSize);
cublasStatus t cublasZgetriBatched(cublasHandle t handle,
                                   int n,
                                   cuDoubleComplex *Aarray[],
                                   int lda,
                                   int *PivotArray,
                                   cuDoubleComplex *Carray[],
                                   int ldc,
                                   int *infoArray,
                                   int batchSize);
```

Aarray and **Carray** are arrays of pointers to matrices stored in column-major format with dimensions **n*****n** and leading dimension **1da** and **1dc** respectively.

This function performs the inversion of matrices A[i] for i = 0, ..., batchSize-1.

Prior to calling cublas<t>getriBatched, the matrix A[i] must be factorized first using the routine cublas<t>getrfBatched. After the call of cublas<t>getrfBatched, the matrix pointing by Aarray[i] will contain the LU factors of the matrix A[i] and the vector pointing by (PivotArray+i) will contain the pivoting sequence.

Following the LU factorization, cublas<t>getriBatched uses forward and backward triangular solvers to complete inversion of matrices A[i] for i = 0, ..., batchSize-1. The inversion is out-of-place, so memory space of Carray[i] cannot overlap memory space of Array[i].

Typically all parameters in cublas<t>getrfBatched would be passed into cublas<t>getriBatched. For example,

```
// step 1: perform in-place LU decomposition, P*A = L*U.
// Aarray[i] is n*n matrix A[i]
  cublasDgetrfBatched(handle, n, Aarray, lda, PivotArray, infoArray,
batchSize);
// check infoArray[i] to see if factorization of A[i] is successful or not.
  Array[i] contains LU factorization of A[i]

// step 2: perform out-of-place inversion, Carray[i] = inv(A[i])
  cublasDgetriBatched(handle, n, Aarray, lda, PivotArray, Carray, ldc,
infoArray, batchSize);
// check infoArray[i] to see if inversion of A[i] is successful or not.
```

The user can check singularity from either cublas<t>getrfBatched or cublas<t>getriBatched.

This function is intended to be used for matrices of small sizes where the launch overhead is a significant factor.

If cublas<t>getrfBatched is performed by non-pivoting, **PivotArray** of cublas<t>getriBatched should be nil.

cublas<t>getriBatched supports arbitrary dimension.

cublas<t>getriBatched only supports compute capability 2.0 or above.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
n		input	number of rows and columns of Aarray[i].
Aarray	device	input	array of pointers to <type> array, with each array of dimension $n*n$ with $1da>=max(1,n)$.</type>
lda		input	leading dimension of two-dimensional array used to store each matrix ${\tt Aarray[i]}$.
PivotArray	device	output	array of size n*batchSize that contains the pivoting sequence of each factorization of Aarray[i] stored in a linear fashion. If PivotArray is nil, pivoting is disabled.
Carray	device	output	array of pointers to <type> array, with each array of dimension $n*n$ with $1dc>=max(1,n)$.</type>
ldc		input	leading dimension of two-dimensional array used to store each matrix Carray[i].
infoArray	device	output	array of size $batchSize$ that $info(=infoArray[i])$ contains the information of $inversion$ of $A[i]$.
			If info=0, the execution is successful.
			If info = k , $U(k,k)$ is 0. The U is exactly singular and the inversion failed.
batchSize		input	number of pointers contained in A

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,batchSize,lda,ldc <0
CUBLAS_STATUS_ARCH_MISMATCH	the device has a compute capability < 200
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

2.8.6. cublas<t>matinvBatched()

```
cublasStatus t cublasSmatinvBatched(cublasHandle t handle,
                                     int n,
const float *A[],
                                     int lda,
                                     float *Ainv[],
                                     int lda inv,
                                     int *info,
                                     int batchSize);
cublasStatus_t cublasDmatinvBatched(cublasHandle_t handle,
                                     int n,
const double *A[],
                                     int lda,
                                    double *Ainv[],
                                     int lda inv,
                                     int *info,
                                     int batchSize);
cublasStatus t cublasCmatinvBatched(cublasHandle t handle,
                                     const cuComplex *A[],
                                     int lda,
                                     cuComplex *Ainv[],
                                     int lda inv,
                                     int *info,
                                     int batchSize);
cublasStatus t cublasZmatinvBatched(cublasHandle t handle,
                                     int n,
                                     const cuDoubleComplex *A[],
                                     int lda,
                                     cuDoubleComplex *Ainv[],
                                     int lda inv,
                                    int *info,
                                     int batchSize);
```

A and Ainv are arrays of pointers to matrices stored in column-major format with dimensions n*n and leading dimension lda and lda inv respectively.

This function performs the inversion of matrices A[i] for i = 0, ..., batchSize-1.

This function is a short cut of **cublas<t>getrfBatched** plus **cublas<t>getriBatched**. However it only works if **n** is less than 32. If not, the user has to go through **cublas<t>getrfBatched** and **cublas<t>getriBatched**.

If the matrix A[i] is singular, then info[i] reports singularity, the same as cublas<t>getrfBatched.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
n		input	number of rows and columns of A[i].
A	device	input	array of pointers to <type> array, with each array of dimension n*n with lda>=max(1,n).</type>
lda		input	leading dimension of two-dimensional array used to store each matrix $\mathbf{A}[\mathbf{i}]$.
Ainv	device	output	array of pointers to <type> array, with each array of dimension n*n with lda_inv>=max(1,n).</type>
lda_inv		input	leading dimension of two-dimensional array used to store each matrix Ainv[i].
info	device	output	array of size $batchSize$ that $info[i]$ contains the information of inversion of $A[i]$.
			If info[i]=0, the execution is successful.
			If info[i]=k, U(k,k) is 0. The U is exactly singular and the inversion failed.
batchSize		input	number of pointers contained in A.

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	<pre>the parameters n,batchSize,lda,lda_inv <0; or n >32</pre>
CUBLAS_STATUS_ARCH_MISMATCH	the device has a compute capability < 200
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

2.8.7. cublas<t>geqrfBatched()

```
cublasStatus t cublasSgeqrfBatched( cublasHandle t handle,
                                     int m,
                                     int n,
                                     float *Aarray[],
                                     int lda,
                                     float *TauArray[],
                                     int *info,
                                     int batchSize);
cublasStatus t cublasDgeqrfBatched( cublasHandle t handle,
                                     int n,
                                    double *Aarray[],
                                    int lda,
                                    double *TauArray[],
                                    int *info,
                                    int batchSize);
cublasStatus t cublasCgeqrfBatched( cublasHandle_t handle,
                                     int m,
                                     int n,
                                     cuComplex *Aarray[],
                                    int lda,
                                    cuComplex *TauArray[],
                                     int *info,
                                    int batchSize);
cublasStatus t cublasZgeqrfBatched( cublasHandle t handle,
                                     int m,
                                     int n,
                                     cuDoubleComplex *Aarray[],
                                     cuDoubleComplex *TauArray[],
                                     int *info,
                                     int batchSize);
```

Aarray is an array of pointers to matrices stored in column-major format with dimensions $m \times n$ and leading dimension lda. **TauArray** is an array of pointers to vectors of dimension of at least max (1, min(m, n)).

This function performs the QR factorization of each <code>Aarray[i]</code> for <code>i = 0, ...,batchSize-1</code> using Householder reflections. Each matrix <code>Q[i]</code> is represented as a product of elementary reflectors and is stored in the lower part of each <code>Aarray[i]</code> as follows:

This function is intended to be used for matrices of small sizes where the launch overhead is a significant factor.

cublas<t>geqrfBatched supports arbitrary dimension.

cublas<t>geqrfBatched only supports compute capability 2.0 or above.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
m		input	number of rows Aarray[i].
n		input	number of columns of Aarray[i].
Aarray	device	input	array of pointers to <type> array, with each array of dim. m x n with lda>=max(1,m).</type>
lda		input	leading dimension of two-dimensional array used to store each matrix Aarray[i].
TauArray	device	output	array of pointers to <type> vector, with each vector of dim. max(1,min(m,n)).</type>
info	host	output	If info=0, the parameters passed to the function are valid If info<0, the parameter in postion -info is invalid
batchSize		input	number of pointers contained in A

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	<pre>the parameters m,n,batchSize <0 or lda < imax(1,m)</pre>
CUBLAS_STATUS_ARCH_MISMATCH	the device has a compute capability < 200
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

sgeqrf, dgeqrf, cgeqrf, zgeqrf

2.8.8. cublas<t>gelsBatched()

```
cublasStatus t cublasSgelsBatched( cublasHandle t handle,
                                     cublasOperation t trans,
                                    int m,
                                    int n,
                                    int nrhs,
                                    float *Aarray[],
                                    int lda,
                                    float *Carray[],
                                    int ldc,
                                    int *info,
int *devInfoArray,
                                    int batchSize );
cublasStatus t cublasDgelsBatched( cublasHandle t handle,
                                    cublasOperation_t trans,
                                    int m,
                                    int n,
                                    int nrhs,
                                    double *Aarray[],
                                    int lda,
double *Carray[],
                                    int ldc,
                                    int *info,
                                    int *devInfoArray,
                                    int batchSize );
cublasStatus_t cublasCgelsBatched( cublasHandle_t handle,
                                    cublasOperation t trans,
                                    int m,
                                    int n,
                                    int nrhs,
                                    cuComplex *Aarray[],
                                    int lda,
                                    cuComplex *Carray[],
                                    int ldc,
                                    int *info,
                                    int *devInfoArray,
                                    int batchSize );
cublasStatus t cublasZgelsBatched( cublasHandle t handle,
                                    cublasOperation t trans,
                                    int m,
                                    int n,
                                    int nrhs,
                                    cuDoubleComplex *Aarray[],
                                    int lda,
                                    cuDoubleComplex *Carray[],
                                    int ldc,
                                    int *info,
                                    int *devInfoArray,
                                    int batchSize );
```

Aarray is an array of pointers to matrices stored in column-major format with dimensions $\mathbf{m} \times \mathbf{n}$ and leading dimension \mathbf{lda} . Carray is an array of pointers to matrices stored in column-major format with dimensions $\mathbf{n} \times \mathbf{nrhs}$ and leading dimension \mathbf{ldc} .

This function find the least squares solution of a batch of overdetermined systems : it solves the least squares problem described as follows :

```
minimize || Carray[i] - Aarray[i]*Xarray[i] || , with i =
0, ...,batchSize-1
```

On exit, each <code>Aarray[i]</code> is overwritten with their QR factorization and each <code>Carray[i]</code> is overwritten with the least square solution

cublas<t>gelsBatched supports only the non-transpose operation and only solves over-determined systems ($m \ge n$).

cublas<t>gelsBatched only supports compute capability 2.0 or above.

This function is intended to be used for matrices of small sizes where the launch overhead is a significant factor.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
trans		input	operation op(Aarray[i]) that is non- or (conj.) transpose. Only non-transpose operation is currently supported.
m		input	number of rows Aarray[i].
n		input	number of columns of each Aarray[i] and rows of each Carray[i].
nrhs		input	number of columns of each Carray[i].
Aarray	device	input/ output	array of pointers to <type> array, with each array of dim. m x n with lda>=max(1,m).</type>
lda		input	leading dimension of two-dimensional array used to store each matrix Aarray[i].
Carray	device	input/ output	array of pointers to <type> array, with each array of dim. n x nrhs with ldc>=max(1,m).</type>
ldc		input	leading dimension of two-dimensional array used to store each matrix Carray[i].
info	host	output	If info=0, the parameters passed to the function are valid If info<0, the parameter in position -info is invalid
devInfoArray	device	output	optional array of integers of dimension batchsize. If non-null, every element devInfoArray[i] contain a value V with the following meaning: V = 0: the i-th problem was sucessfully solved V > 0: the V-th diagonal element of the Aarray[i] is zero. Aarray[i] does not have full rank.
batchSize		input	number of pointers contained in Aarray and Carray

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	<pre>the parameters m,n,batchSize <0 , lda < imax(1,m) Or ldc < imax(1,m)</pre>
CUBLAS_STATUS_NOT_SUPPORTED	the parameters ${\tt m}$ < ${\tt n}$ or ${\tt trans}$ is different from non-transpose.
CUBLAS_STATUS_ARCH_MISMATCH	the device has a compute capability < 200
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

sgels, dgels, cgels, zgels

2.8.9. cublas<t>tpttr()

```
cublasStatus t cublasStpttr ( cublasHandle t handle,
                              cublasFillMode t uplo,
                              int n,
                              const float *AP,
                              float *A,
                              int lda );
cublasStatus t cublasDtpttr ( cublasHandle t handle,
                              cublasFillMode t uplo,
                              int n,
                              const double *AP,
                              double *A,
                              int lda );
cublasStatus_t cublasCtpttr ( cublasHandle_t handle,
                              cublasFillMode t uplo,
                              int n,
                              const cuComplex *AP,
                             cuComplex *A,
                             int lda );
cublasStatus_t cublasZtpttr ( cublasHandle_t handle,
                              cublasFillMode t uplo
                              int n,
                              const cuDoubleComplex *AP,
                              cuDoubleComplex *A,
                              int lda );
```

This function performs the conversion from the triangular packed format to the triangular format

If uplo == CUBLAS_FILL_MODE_LOWER then the elements of AP are copied into the lower triangular part of the triangular matrix A and the upper part of A is left untouched. If uplo == CUBLAS_FILL_MODE_UPPER then the elements of AP are copied into the upper triangular part of the triangular matrix A and the lower part of A is left untouched.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.

Param.	Memory	In/out	Meaning	
uplo		input	indicates if matrix AP contains lower or upper part of matrix A.	
n		input	number of rows and columns of matrix ${f a}$.	
AP	device	input	<type> array with A stored in packed format.</type>	
А	device	output	<pre><type> array of dimensions lda $x n$, with lda>=max(1,n). The opposite side of A is left untouched.</type></pre>	
lda		input	leading dimension of two-dimensional array used to store matrix A.	

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

stpttr, dtpttr, ctpttr, ztpttr

2.8.10. cublas<t>trttp()

```
cublasStatus_t cublasStrttp ( cublasHandle_t handle,
                               cublasFillMode t uplo,
                               int n, const float *A,
                               int lda,
                               float *AP );
cublasStatus_t cublasDtrttp ( cublasHandle_t handle,
                               cublasFillMode t uplo,
                               int n,
                               const double *A,
                               int lda,
                               double *AP );
cublasStatus_t cublasCtrttp ( cublasHandle_t handle,
                               cublasFillMode_t uplo,
                               int n,
                               const cuComplex *A,
                               int lda,
                               cuComplex *AP );
cublasStatus t cublasZtrttp ( cublasHandle t handle,
                               cublasFillMode t uplo,
                               int n,
                               const cuDoubleComplex *A,
                               int lda,
                               cuDoubleComplex *AP );
```

This function performs the conversion from the triangular format to the triangular packed format

If uplo == CUBLAS_FILL_MODE_LOWER then the lower triangular part of the triangular matrix **A** is copied into the array **AP**. If uplo == CUBLAS_FILL_MODE_UPPER then then the upper triangular part of the triangular matrix **A** is copied into the array **AP**.

Param.	Memory	In/out	Meaning	
handle		input	handle to the cuBLAS library context.	
uplo		input	indicates which matrix A lower or upper part is referenced.	
n		input	number of rows and columns of matrix A.	
А	device	input	<pre><type> array of dimensions lda $x n$, with lda>=max(1,n).</type></pre>	
lda		input	leading dimension of two-dimensional array used to store matrix A.	
AP	device	output	<type> array with A stored in packed format.</type>	

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

strttp, dtrttp, ctrttp, ztrttp

2.8.11. cublas<t>gemmEx()

```
cublasStatus t cublasSgemmEx(cublasHandle t handle,
                          cublasOperation_t transa,
                          cublasOperation t transb,
                          int m,
                          int n,
                          int k,
                          const float     *alpha,
const void     *A,
                          cudaDataType t Atype,
                          int lda,
                          const void *B,
                          cudaDataType_t Btype,
                          int ldb,
                          const float *beta,
                          cudaDataType t Ctype,
                          int ldc)
cublasStatus t cublasCgemmEx(cublasHandle t handle,
                          cublasOperation t transa,
                          cublasOperation t transb,
                          int m,
                          int n,
                          int k,
                          const cuComplex *alpha,
                          const void *A,
                          cudaDataType_t Atype,
                          int lda,
                                         *B,
                          const void
                          cudaDataType_t Btype,
                          int ldb,
                          const cuComplex *beta,
                          void *C,
                          cudaDataType_t Ctype,
                          int ldc)
```

This function is an extension of **cublas<t>gemm** where the input matrices and output matrices can have a lower precision but the computation is still done in the type **<t>**, e.g in **float** for **cublasSgemmEx** and **cuComplex** for **cublasSgemmEx**

$$C = \alpha \operatorname{op}(A)\operatorname{op}(B) + \beta C$$

where α and β are scalars, and A, B and C are matrices stored in column-major format with dimensions op(A) $m \times k$, op(B) $k \times n$ and C $m \times n$, respectively. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == \text{CUBLAS_OP_N} \\ A^T & \text{if transa} == \text{CUBLAS_OP_T} \\ A^H & \text{if transa} == \text{CUBLAS_OP_C} \end{cases}$$

and op(B) is defined similarly for matrix B.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
transa		input	operation op(A) that is non- or (conj.) transpose.
transb		input	operation op(B) that is non- or (conj.) transpose.
m		input	number of rows of matrix op(A) and c.

Param.	Memory	In/out	Meaning	
n		input	number of columns of matrix $op(B)$ and c .	
k		input	number of columns of op(A) and rows of op(B).	
alpha	host or device	input	<type> scalar used for multiplication.</type>	
A	device	input	<pre><type> array of dimensions lda x k With lda>=max(1,m) if transa == CUBLAS_OP_N and lda x m With lda>=max(1,k) otherwise.</type></pre>	
Atype		input	enumerant specifying the datatype of matrix ${f a}$.	
lda		input	leading dimension of two-dimensional array used to store the matrix ${\bf A}$.	
В	device	input	<pre><type> array of dimension ldb x n with ldb>=max(1,k) if transa == CUBLAS_OP_N and ldb x k with ldb>=max(1,n) otherwise.</type></pre>	
Btype		input	enumerant specifying the datatype of matrix B.	
ldb		input	leading dimension of two-dimensional array used to store matrix в.	
beta	host or device	input	<pre><type> scalar used for multiplication. If beta==0, c does not have to be a valid input.</type></pre>	
С	device	in/out	<type> array of dimensions ldc x n With ldc>=max(1,m).</type>	
Ctype		input	enumerant specifying the datatype of matrix c.	
ldc		input	leading dimension of a two-dimensional array used to store the matrix c.	

The matrix types combinations supported for ${\tt cublasSgemmEx}$ are listed below :

A	В	С
CUDA_R_16F	CUDA_R_16F	CUDA_R_16F
CUDA_R_16F	CUDA_R_16F	CUDA_R_32F
CUDA_R_8I	CUDA_R_8I	CUDA_R_32F
CUDA_R_32F	CUDA_R_32F	CUDA_R_32F

The matrix types combinations supported for ${\tt cublasCgemmEx}$ are listed below :

Α	В	С
CUDA_C_8I	CUDA_C_8I	CUDA_C_32F
CUDA_C_32F	CUDA_C_32F	CUDA_C_32F

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_ARCH_MISMATCH	cublasCgemmEx is only supported for GPU with architecture capabilities equal or greater than 5.0
CUBLAS_STATUS_NOT_SUPPORTED	the combination of the parameters Atype,Btype and Ctype is not supported
CUBLAS_STATUS_INVALID_VALUE	the parameters m,n,k<0
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

sgemm

2.8.12. cublasCsyrkEx()

This function is an extension of **cublasCsyrk** where the input matrix and output matrix can have a lower precision but the computation is still done in the type **cuComplex**

This function performs the symmetric rank- *k* update

$$C = \alpha \operatorname{op}(A) \operatorname{op}(A)^T + \beta C$$

where α and β are scalars, C is a symmetric matrix stored in lower or upper mode, and A is a matrix with dimensions op(A) $n \times k$. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == CUBLAS_OP_N \\ A^T & \text{if transa} == CUBLAS_OP_T \end{cases}$$



This routine is only supported on GPUs with architecture capabilities equal or greater than 5.0

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.

Param.	Memory	In/out	Meaning
uplo		input	indicates if matrix c lower or upper part is stored, the other symmetric part is not referenced and is inferred from the stored elements.
trans		input	operation op(A) that is non- or transpose.
n		input	number of rows of matrix op(A) and C.
k		input	number of columns of matrix op(A).
alpha	host or device	input	<type> scalar used for multiplication.</type>
A	device	input	<pre><type> array of dimension lda x k with lda>=max(1,n) if trans == CUBLAS_OP_N and lda x n with lda>=max(1,k) otherwise.</type></pre>
Atype		input	enumerant specifying the datatype of matrix A.
lda		input	leading dimension of two-dimensional array used to store matrix A.
beta	host or device	input	<type> scalar used for multiplication, if beta==0 then c does not have to be a valid input.</type>
С	device	in/out	<type> array of dimension ldc x n, with ldc>=max(1,n).</type>
Ctype		input	enumerant specifying the datatype of matrix c.
ldc		input	leading dimension of two-dimensional array used to store matrix c.

The matrix types combinations supported for ${\tt cublasCsyrkEx}$ are listed below :

Α	С
CUDA_C_8I	CUDA_C_32F
CUDA_C_32F	CUDA_C_32F

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,k<0
CUBLAS_STATUS_NOT_SUPPORTED	the combination of the parameters Atype and Ctype is not supported
CUBLAS_STATUS_ARCH_MISMATCH	the device has a compute capabilites lower than 5.0
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

ssyrk, dsyrk, csyrk, zsyrk

2.8.13. cublasCsyrk3mEx()

This function is an extension of **cublasCsyrk** where the input matrix and output matrix can have a lower precision but the computation is still done in the type **cuComplex**. This routine is implemented using the Gauss complexity reduction algorithm which can lead to an increase in performance up to 25%

This function performs the symmetric rank- *k* update

$$C = \alpha \operatorname{op}(A) \operatorname{op}(A)^T + \beta C$$

where α and β are scalars, C is a symmetric matrix stored in lower or upper mode, and A is a matrix with dimensions op(A) $n \times k$. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == CUBLAS_OP_N \\ A^T & \text{if transa} == CUBLAS_OP_T \end{cases}$$



This routine is only supported on GPUs with architecture capabilities equal or greater than 5.0

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix c lower or upper part is stored, the other symmetric part is not referenced and is inferred from the stored elements.
trans		input	operation op(A) that is non- or transpose.
n		input	number of rows of matrix op(A) and C.
k		input	number of columns of matrix op(A).
alpha	host or device	input	<type> scalar used for multiplication.</type>
A	device	input	<pre><type> array of dimension lda x k with lda>=max(1,n) if trans == CUBLAS_OP_N and lda x n with lda>=max(1,k) otherwise.</type></pre>
Atype		input	enumerant specifying the datatype of matrix A.

Param.	Memory	In/out	Meaning
lda		input	leading dimension of two-dimensional array used to store matrix A.
beta	host or device	input	<pre><type> scalar used for multiplication, if beta==0 then c does not have to be a valid input.</type></pre>
С	device	in/out	<pre><type> array of dimension ldc x n, with ldc>=max(1,n).</type></pre>
Ctype		input	enumerant specifying the datatype of matrix c.
ldc		input	leading dimension of two-dimensional array used to store matrix c.

The matrix types combinations supported for **cublasCsyrk3mEx** are listed below:

Α	С
CUDA_C_8I	CUDA_C_32F
CUDA_C_32F	CUDA_C_32F

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,k<0
CUBLAS_STATUS_NOT_SUPPORTED	the combination of the parameters Atype and Ctype is not supported
CUBLAS_STATUS_ARCH_MISMATCH	the device has a compute capabilites lower than 5.0
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

ssyrk, dsyrk, csyrk, zsyrk

2.8.14. cublasCherkEx()

This function is an extension of **cublasCherk** where the input matrix and output matrix can have a lower precision but the computation is still done in the type **cuComplex**

This function performs the Hermitian rank- *k* update

$$C = \alpha \operatorname{op}(A) \operatorname{op}(A)^H + \beta C$$

where α and β are scalars, C is a Hermitian matrix stored in lower or upper mode, and A is a matrix with dimensions op(A) $n \times k$. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == CUBLAS_OP_N \\ A^H & \text{if transa} == CUBLAS_OP_C \end{cases}$$



This routine is only supported on GPUs with architecture capabilities equal or greater than 5.0

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix A lower or upper part is stored, the other Hermitian part is not referenced and is inferred from the stored elements.
trans		input	operation op(A) that is non- or (conj.) transpose.
n		input	number of rows of matrix op(A) and C.
k		input	number of columns of matrix op(A).
alpha	host or device	input	<type> scalar used for multiplication.</type>
A	device	input	<pre><type> array of dimension lda x k with lda>=max(1,n) if transa == CUBLAS_OP_N and lda x n with lda>=max(1,k) otherwise.</type></pre>
Atype		input	enumerant specifying the datatype of matrix A.
lda		input	leading dimension of two-dimensional array used to store matrix A.
beta		input	<pre><type> scalar used for multiplication, if beta==0 then c does not have to be a valid input.</type></pre>
С	device	in/out	<pre><type> array of dimension ldc x n, with ldc>=max(1,n). The imaginary parts of the diagonal elements are assumed and set to zero.</type></pre>
Ctype		input	enumerant specifying the datatype of matrix c.
ldc		input	leading dimension of two-dimensional array used to store matrix c.

The matrix types combinations supported for **cublasCherkEx** are listed below:

Α	С
CUDA_C_8I	CUDA_C_32F

Α	С
CUDA_C_32F	CUDA_C_32F

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,k<0
CUBLAS_STATUS_NOT_SUPPORTED	the combination of the parameters Atype and Ctype is not supported
CUBLAS_STATUS_ARCH_MISMATCH	the device has a compute capabilites lower than 5.0
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

cherk

2.8.15. cublasCherk3mEx()

This function is an extension of **cublasCherk** where the input matrix and output matrix can have a lower precision but the computation is still done in the type **cuComplex**. This routine is implemented using the Gauss complexity reduction algorithm which can lead to an increase in performance up to 25%

This function performs the Hermitian rank- *k* update

$$C = \alpha \operatorname{op}(A) \operatorname{op}(A)^{H} + \beta C$$

where α and β are scalars, C is a Hermitian matrix stored in lower or upper mode, and A is a matrix with dimensions op(A) $n \times k$. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == CUBLAS_OP_N \\ A^H & \text{if transa} == CUBLAS_OP_C \end{cases}$$



This routine is only supported on GPUs with architecture capabilities equal or greater than $5.0\,$

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
uplo		input	indicates if matrix A lower or upper part is stored, the other Hermitian part is not referenced and is inferred from the stored elements.
trans		input	operation op(A) that is non- or (conj.) transpose.
n		input	number of rows of matrix op(A) and C.
k		input	number of columns of matrix op(A).
alpha	host or device	input	<type> scalar used for multiplication.</type>
A	device	input	<pre><type> array of dimension lda x k with lda>=max(1,n) if transa == CUBLAS_OP_N and lda x n with lda>=max(1,k) otherwise.</type></pre>
Atype		input	enumerant specifying the datatype of matrix A.
lda		input	leading dimension of two-dimensional array used to store matrix A.
beta		input	<pre><type> scalar used for multiplication, if beta==0 then c does not have to be a valid input.</type></pre>
С	device	in/out	<pre><type> array of dimension ldc x n, with ldc>=max(1,n). The imaginary parts of the diagonal elements are assumed and set to zero.</type></pre>
Ctype		input	enumerant specifying the datatype of matrix c.
ldc		input	leading dimension of two-dimensional array used to store matrix c.

The matrix types combinations supported for ${\tt cublasCherk3mEx}$ are listed below :

Α	С
CUDA_C_8I	CUDA_C_32F
CUDA_C_32F	CUDA_C_32F

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized

Error Value	Meaning
CUBLAS_STATUS_INVALID_VALUE	the parameters n,k<0
CUBLAS_STATUS_NOT_SUPPORTED	the combination of the parameters Atype and Ctype is not supported
CUBLAS_STATUS_ARCH_MISMATCH	the device has a compute capabilites lower than 5.0
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

cherk

2.8.16. cublasNrm2Ex()

This function is an API generalization of the routine **cublas<t>nrm2** where input data, output data and compute type can be specified independently.

This function computes the Euclidean norm of the vector \mathbf{x} . The code uses a multiphase model of accumulation to avoid intermediate underflow and overflow, with the result

being equivalent to $\sqrt{\sum_{i=1}^{n} (\mathbf{x}[j] \times \mathbf{x}[j])}$ where $j = 1 + (i - 1)^*$ incx in exact arithmetic. Notice that the last equation reflects 1-based indexing used for compatibility with Fortran.

Param.	Memory	In/out	Meaning	
handle		input	handle to the cuBLAS library context.	
n		input	number of elements in the vector \mathbf{x} .	
х	device	input	<type> vector with n elements.</type>	
хТуре		input	enumerant specifying the datatype of vector \mathbf{x} .	
incx		input	stride between consecutive elements of \mathbf{x} .	
result	host or device	output	the resulting norm, which is 0.0 if n,incx<=0.	
resultType		input	enumerant specifying the datatype of the result.	
executionType		input	enumerant specifying the datatype in which the computation is executed.	

The datatypes combinations currrently supported for **cublasNrm2Ex** are listed below:

х	result	execution
CUDA_R_16F	CUDA_R_16F	CUDA_R_32F
CUDA_R_32F	CUDA_R_32F	CUDA_R_32F
CUDA_R_64F	CUDA_R_64F	CUDA_R_64F
CUDA_C_32F	CUDA_C_32F	CUDA_C_32F
CUDA_C_64F	CUDA_C_64F	CUDA_C_64F

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	the reduction buffer could not be allocated
CUBLAS_STATUS_NOT_SUPPORTED	the combination of the parameters xType, resultType and executionType is not supported
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

snrm2, snrm2, dnrm2, dnrm2, scnrm2, scnrm2, dznrm2

2.8.17. cublasAxpyEx()

This function is an API generalization of the routine **cublas<t>axpy** where input data, output data and compute type can be specified independently.

This function multiplies the vector \mathbf{x} by the scalar α and adds it to the vector \mathbf{y} overwriting the latest vector with the result. Hence, the performed operation is $\mathbf{y}[j] = \alpha \times \mathbf{x}[k] + \mathbf{y}[j]$ for i = 1, ..., n, $k = 1 + (i - 1)^*$ incx and $j = 1 + (i - 1)^*$ incy. Notice that the last two equations reflect 1-based indexing used for compatibility with Fortran.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
alpha	host or device	input	<type> scalar used for multiplication.</type>

Param.	Memory	In/out	Meaning
n		input	number of elements in the vector ${\bf x}$ and ${\bf y}$.
x	device	input	<type> vector with n elements.</type>
хТуре		input	enumerant specifying the datatype of vector \mathbf{x} .
incx		input	stride between consecutive elements of ${f x}$.
у	device	in/out	<type> vector with n elements.</type>
уТуре		input	enumerant specifying the datatype of vector \mathbf{y} .
incy		input	stride between consecutive elements of y.
executionTy	ре	input	enumerant specifying the datatype in which the computation is executed.

The datatypes combinations currrently supported for **cublasAxpyEx** are listed below:

х	у	
CUDA_R_16F	CUDA_R_16F	CUDA_R_32F
CUDA_R_32F	CUDA_R_32F	CUDA_R_32F
CUDA_R_64F	CUDA_R_64F	CUDA_R_64F
CUDA_C_32F	CUDA_C_32F	CUDA_C_32F
CUDA_C_64F	CUDA_C_64F	CUDA_C_64F

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_NOT_SUPPORTED	the combination of the parameters xType,yType, and executionType is not supported
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

saxpy, daxpy, caxpy, zaxpy

2.8.18. cublasDotEx()

```
cublasStatus t cublasDotEx (cublasHandle t handle,
                            int n,
                            const void *x,
                           cudaDataType xType,
                           int incx,
                           const void *y,
                            cudaDataType yType,
                            int incy,
                            void *result,
                            cudaDataType resultType,
                            cudaDataType executionType);
cublasStatus t cublasDotcEx (cublasHandle t handle,
                             int n,
                            const void *x,
                             cudaDataType xType,
                             int incx,
                            const void *y,
                            cudaDataType yType,
                             int incy,
                             void *result,
                             cudaDataType resultType,
                             cudaDataType executionType);
```

These functions are an API generalization of the routines **cublas<t>dot** and **cublas<t>dotc** where input data, output data and compute type can be specified independently.

This function computes the dot product of vectors \mathbf{x} and \mathbf{y} . Hence, the result is $\sum_{i=1}^{n} (\mathbf{x}[k] \times \mathbf{y}[j])$ where $k = 1 + (i-1)^*$ incx and $j = 1 + (i-1)^*$ incy. Notice that in the first equation the conjugate of the element of vector should be used if the function name ends in character 'c' and that the last two equations reflect 1-based indexing used for compatibility with Fortran.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.
n		input	number of elements in the vectors ${f x}$ and ${f y}$.
x	device	input	<type> vector with n elements.</type>
хТуре		input	enumerant specifying the datatype of vector \mathbf{x} .
incx		input	stride between consecutive elements of x.
у	device	input	<type> vector with n elements.</type>
уТуре		input	enumerant specifying the datatype of vector \mathbf{y} .
incy		input	stride between consecutive elements of y.
result	host or device	output	the resulting dot product, which is 0.0 if $n \le 0$.
resultType		input	enumerant specifying the datatype of the result.

Param.	Memory	In/out	Meaning
executionT	ype	input	enumerant specifying the datatype in which the computation is executed.

The datatypes combinations currrently supported for **cublasDotEx** and **cublasDotcEx** are listed below:

х	у	result	execution
CUDA_R_16F	CUDA_R_16F	CUDA_R_16F	CUDA_R_32F
CUDA_R_32F	CUDA_R_32F	CUDA_R_32F	CUDA_R_32F
CUDA_R_64F	CUDA_R_64F	CUDA_R_64F	CUDA_R_64F
CUDA_C_32F	CUDA_C_32F	CUDA_C_32F	CUDA_C_32F
CUDA_C_64F	CUDA_C_64F	CUDA_C_64F	CUDA_C_64F

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	the reduction buffer could not be allocated
CUBLAS_STATUS_NOT_SUPPORTED	the combination of the parameters xType,yType, resultType and executionType is not supported
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

sdot, ddot, cdotu, cdotc, zdotu, zdotc

2.8.19. cublasScalEx()

This function scales the vector \mathbf{x} by the scalar α and overwrites it with the result. Hence, the performed operation is $\mathbf{x}[j] = \alpha \times \mathbf{x}[j]$ for i = 1, ..., n and $j = 1 + (i - 1)^*$ incx. Notice that the last two equations reflect 1-based indexing used for compatibility with Fortran.

Param.	Memory	In/out	Meaning
handle		input	handle to the cuBLAS library context.

Param.	Memory	In/out	Meaning
alpha	host or device	input	<type> scalar used for multiplication.</type>
n		input	number of elements in the vector ${f x}$.
x	device	in/out	<type> vector with n elements.</type>
хТуре		input	enumerant specifying the datatype of vector \mathbf{x} .
incx		input	stride between consecutive elements of ${\bf x}$.
executionTy	ре	input	enumerant specifying the datatype in which the computation is executed.

The datatypes combinations currrently supported for ${\tt cublasScalEx}$ are listed below :

х	execution
CUDA_R_16F	CUDA_R_32F
CUDA_R_32F	CUDA_R_32F
CUDA_R_64F	CUDA_R_64F
CUDA_C_32F	CUDA_C_32F
CUDA_C_64F	CUDA_C_64F

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_NOT_SUPPORTED	the combination of the parameters *Type and executionType is not supported
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

sscal, dscal, cscal, zdscal, zscal

Chapter 3. USING THE CUBLASXT API

3.1. General description

The cublasXt API of cuBLAS exposes a multi-GPU capable Host interface: when using this API the application only needs to allocate the required matrices on the Host memory space. There are no restriction on the sizes of the matrices as long as they can fit into the Host memory. The cublasXt API takes care of allocating the memory across the designated GPUs and dispatched the workload between them and finally retrieves the results back to the Host. The cublasXt API supports only the compute-intensive BLAS3 routines (e.g matrix-matrix operations) where the PCI transfers back and forth from the GPU can be amortized. The cublasXt API has its own header file cublasXt.h.

Starting with release 8.0, cublasXt API allows any of the matrices to be located on a GPU device.

Note: The cublasXt API is only supported on 64-bit platforms.

3.1.1. Tiling design approach

To be able to share the workload between multiples GPUs, the cublasXt API uses a tiling strategy: every matrix is divided in square tiles of user-controllable dimension BlockDim x BlockDim. The resulting matrix tiling defines the static scheduling policy: each resulting tile is affected to a GPU in a round robin fashion One CPU thread is created per GPU and is responsible to do the proper memory transfers and cuBLAS operations to compute all the tiles that it is responsible for. From a performance point of view, due to this static scheduling strategy, it is better that compute capabilites and PCI bandwidth are the same for every GPU. The figure below illustrates the tiles distribution between 3 GPUs. To compute the first tile G0 from C, the CPU thread 0 responsible of GPU0, have to load 3 tiles from the first row of A and tiles from the first column of B in a pipeline fashion in order to overlap memory transfer and computations and sum the results into the first tile G0 of C before to move on to the next tile G0.




Figure 1 Example of cublasXt<t>gemm() tiling for 3 Gpus

When the tile dimension is not an exact multiple of the dimensions of *C*, some tiles are partially filled on the right border or/and the bottom border. The current implementation does not pad the incomplete tiles but simply keep track of those incomplete tiles by doing the right reduced cuBLAS opearations: this way, no extra computation is done. However it still can lead to some load unbalance when all GPUS do not have the same number of incomplete tiles to work on.

When one or more matrices are located on some GPU devices, the same tiling approach and workload sharing is applied. The memory transfers are in this case done between devices. However, when the computation of a tile and some data are located on the same GPU device, the memory transfer to/from the local data into tiles is bypassed and the GPU operates directly on the local data. This can lead to a significant performance increase, especially when only one GPU is used for the computation.

The matrices can be located on any GPU device, and do not have to be located on the same GPU device. Furthermore, the matrices can even be located on a GPU device that do not participate to the computation.

On the contrary of the cuBLAS API, even if all matrices are located on the same device, the cublasXt API is still a blocking API from the Host point of view: the data results wherever located will be valid on the call return and no device synchronization is required.

3.1.2. Hybrid CPU-GPU computation

In the case of very large problems, the cublasXt API offers the possibility to offload some of the computation to the Host CPU. This feature can be setup with the routines <code>cublasXtSetCpuRoutine()</code> and <code>cublasXtSetCpuRatio()</code> The workload affected to the CPU is put aside: it is simply a percentage of the resulting matrix taken from the bottom and the right side whichever dimension is bigger. The GPU tiling is done after that on the reduced resulting matrix.

If any of the matrices is located on a GPU device, the feature is ignored and all computation will be done only on the GPUs

This feature should be used with caution because it could interfere with the CPU threads responsible of feeding the GPUs.

Currenty, only the routine **cublasXt<t>gemm()** supports this feature.

3.1.3. Results reproducibility

Currently all CUBLAS XT API routines from a given toolkit version, generate the same bit-wise results when the following conditions are respected :

- all GPUs particating to the computation have the same compute-capabilities and the same number of SMs.
- the tiles size is kept the same between run.
- either the CPU hybrid computation is not used or the CPU Blas provided is also guaranteed to produce reproducible results.

3.2. cublasXt API Datatypes Reference

3.2.1. cublasXtHandle t

The cublasXtHandle_t type is a pointer type to an opaque structure holding the cublasXt API context. The cublasXt API context must be initialized using cublasXtCreate() and the returned handle must be passed to all subsequent cublasXt API function calls. The context should be destroyed at the end using cublasXtDestroy().

3.2.2. cublasXtOpType_t

The cublasOpType_t enumerates the four possible types supported by BLAS routines. This enum is used as parameters of the routines cublasXtSetCpuRoutine and cublasXtSetCpuRatio to setup the hybrid configuration.

Value	Meaning
CUBLASXT_FLOAT	float or single precision type

Value	Meaning
CUBLASXT_DOUBLE	double precision type
CUBLASXT_COMPLEX	single precision complex
CUBLASXT_DOUBLECOMPLEX	double precision complex

3.2.3. cublasXtBlasOp_t

The **cublasXtBlasOp_t** type enumerates the BLAS3 or BLAS-like routine supported by cublasXt API. This enum is used as parameters of the routines **cublasXtSetCpuRoutine** and **cublasXtSetCpuRatio** to setup the hybrid configuration.

Value	Meaning
CUBLASXT_GEMM	GEMM routine
CUBLASXT_SYRK	SYRK routine
CUBLASXT_HERK	HERK routine
CUBLASXT_SYMM	SYMM routine
CUBLASXT_HEMM	HEMM routine
CUBLASXT_TRSM	TRSM routine
CUBLASXT_SYR2K	SYR2K routine
CUBLASXT_HER2K	HER2K routine
CUBLASXT_SPMM	SPMM routine
CUBLASXT_SYRKX	SYRKX routine
CUBLASXT_HERKX	HERKX routine

3.2.4. cublasXtPinningMemMode_t

The type is used to enable or disable the Pinning Memory mode through the routine cubasMgSetPinningMemMode

Value	Meaning
CUBLASXT_PINNING_DISABLED	the Pinning Memory mode is disabled
CUBLASXT_PINNING_ENABLED	the Pinning Memory mode is enabled

3.3. cublasXt API Helper Function Reference

3.3.1. cublasXtCreate()

```
cublasStatus_t
cublasXtCreate(cublasXtHandle t *handle)
```

This function initializes the cublasXt API and creates a handle to an opaque structure holding the cublasXt API context. It allocates hardware resources on the host and device and must be called prior to making any other cublasXt API calls.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the initialization succeeded
CUBLAS_STATUS_ALLOC_FAILED	the resources could not be allocated
CUBLAS_STATUS_NOT_SUPPORTED	cublasXt API is only supported on 64-bit platform

3.3.2. cublasXtDestroy()

```
cublasStatus_t
cublasXtDestroy(cublasXtHandle t handle)
```

This function releases hardware resources used by the cublasXt API context. The release of GPU resources may be deferred until the application exits. This function is usually the last call with a particular handle to the cublasXt API.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the shut down succeeded
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized

3.3.3. cublasXtDeviceSelect()

```
cublasXtDeviceSelect(cublasXtHandle t handle, int nbDevices, int deviceId[])
```

This function allows the user to provide the number of GPU devices and their respective Ids that will participate to the subsequent cublasXt API Math function calls. This function will create a cuBLAS context for every GPU provided in that list. Currently the device configuration is static and cannot be changed between Math function calls. In that regard, this function should be called only once after cublasXtCreate. To be able to run multiple configurations, multiple cublasXt API contexts should be created.

Note: In the current release of cuBLAS, the CUBLASXT API supports two GPUs if they are on the same board such as Tesla K10 or GeForce GTX690 and one GPU otherwise. If access to more GPUs devices is needed, details of the licensing are described at cublasXt.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	user call was sucessful

Return Value	Meaning
CUBLAS_STATUS_INVALID_VALUE	Access to at least one of the device could not be done or a cuBLAS context could not be created on at least one of the device
CUBLAS_STATUS_ALLOC_FAILED	some resources could not be allocated.
CUBLAS_STATUS_LICENSE_ERROR	The number of GPUs requested exceeds the maximum number authorized by the current licensing.

3.3.4. cublasXtSetBlockDim()

cublasXtSetBlockDim(cublasXtHandle_t handle, int blockDim)

This function allows the user to set the block dimension used for the tiling of the matrices for the subsequent Math function calls. Matrices are split in square tiles of blockDim x blockDim dimension. This function can be called anytime and will take effect for the following Math function calls. The block dimension should be chosen in a way to optimize the math operation and to make sure that the PCI transfers are well overlapped with the computation.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the call has been successful
CUBLAS_STATUS_INVALID_VALUE	blockDim <= 0

3.3.5. cublasXtGetBlockDim()

cublasXtGetBlockDim(cublasXtHandle_t handle, int *blockDim)

This function allows the user to query the block dimension used for the tiling of the matrices.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the call has been successful

3.3.6. cublasXtSetCpuRoutine()

cublasXtSetCpuRoutine(cublasXtHandle_t handle, cublasXtBlasOp_t blasOp, cublasXtOpType_t type, void *blasFunctor)

This function allows the user to provide a CPU implementation of the corresponding BLAS routine. This function can be used with the function cublasXtSetCpuRatio() to define an hybrid computation between the CPU and the GPUs. Currently the hybrid feature is only supported for the xGEMM routines.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the call has been successful
CUBLAS_STATUS_INVALID_VALUE	blasOp or type define an invalid combination

Return Value	Meaning
CUBLAS_STATUS_NOT_SUPPORTED	CPU-GPU Hybridization for that routine is not supported

3.3.7. cublasXtSetCpuRatio()

```
cublasXtSetCpuRatio(cublasXtHandle_t handle, cublasXtBlasOp_t blasOp,
  cublasXtOpType_t type, float ratio )
```

This function allows the user to define the percentage of workload that should be done on a CPU in the context of an hybrid computation. This function can be used with the function cublasXtSetCpuRoutine() to define an hybrid computation between the CPU and the GPUs. Currently the hybrid feature is only supported for the xGEMM routines.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the call has been successful
CUBLAS_STATUS_INVALID_VALUE	blasOp or type define an invalid combination
CUBLAS_STATUS_NOT_SUPPORTED	CPU-GPU Hybridization for that routine is not supported

3.3.8. cublasXtSetPinningMemMode()

cublasXtSetPinningMemMode(cublasXtHandle_t handle, cublasXtPinningMemMode_t
 mode)

This function allows the user to enable or disable the Pinning Memory mode. When enabled, the matrices passed in subsequent cublasXt API calls will be pinned/ unpinned using the CUDART routine <code>cudaHostRegister</code> and <code>cudaHostUnregister</code> respectively if the matrices are not already pinned. If a matrix happened to be pinned partially, it will also not be pinned. Pinning the memory improve PCI transfer performace and allows to overlap PCI memory transfer with computation. However pinning/unpinning the memory take some time which might not be amortized. It is advised that the user pins the memory on its own using <code>cudaMallocHost</code> or <code>cudaHostRegister</code> and unpin it when the computation sequence is completed. By default, the Pinning Memory mode is disabled.



The Pinning Memory mode should not enabled when matrices used for different calls to cublasXt API overlap. CublasXt determines that a matrix is pinned or not if the first address of that matrix is pinned using cudaHostGetFlags, thus cannot know if the matrix is already partially pinned or not. This is especially true in multi-threaded application where memory could be partially or totally pinned or unpinned while another thread is accessing that memory.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the call has been successful
CUBLAS_STATUS_INVALID_VALUE	the mode value is different from CUBLASXT_PINNING_DISABLED and CUBLASXT_PINNING_ENABLED

3.3.9. cublasXtGetPinningMemMode()

cublasXtGetPinningMemMode(cublasXtHandle_t handle, cublasXtPinningMemMode_t *mode)

This function allows the user to query the Pinning Memory mode. By default, the Pinning Memory mode is disabled.

Return Value	Meaning
CUBLAS_STATUS_SUCCESS	the call has been successful

3.4. cublasXt API Math Functions Reference

In this chapter we describe the actual Linear Agebra routines that cublasXt API supports. We will use abbreviations <type> for type and <t> for the corresponding short type to make a more concise and clear presentation of the implemented functions. Unless otherwise specified <type> and <t> have the following meanings:

<type></type>	<t></t>	Meaning
float	's' or 'S'	real single-precision
double	'd' or 'D'	real double-precision
cuComplex	'c' or 'C'	complex single-precision
cuDoubleComplex	ʻz' or ʻZ'	complex double-precision

The abbreviation $\mathbf{Re}(.)$ and $\mathbf{Im}(.)$ will stand for the real and imaginary part of a number, respectively. Since imaginary part of a real number does not exist, we will consider it to be zero and can usually simply discard it from the equation where it is being used. Also, the α will denote the complex conjugate of α .

In general throughout the documentation, the lower case Greek symbols α and β will denote scalars, lower case English letters in bold type \mathbf{x} and \mathbf{y} will denote vectors and capital English letters A, B and C will denote matrices.

3.4.1. cublasXt<t>gemm()

```
cublasStatus t cublasXtSgemm(cublasXtHandle_t handle,
                               cublasOperation_t transa, cublasOperation_t transb,
                               size t m, size t n, size t k,
                               const float
                              const float *alpha
const float *A, in
const float *B, in
const float *beta,
float *C, int ldc)
                                                        *alpha,
                                                       *A, int lda,
                                                        *B, int ldb,
cublasStatus_t cublasXtDgemm(cublasXtHandle_t handle,
                              cublasOperation t transa, cublasOperation t transb,
                               int m, int n, int k,
                               const double
                                                        *alpha,
                                                        *A, int lda, *B, int ldb,
                               const double
                              const double const double *B, in the const double *C, int ldc)
cublasStatus_t cublasXtCgemm(cublasXtHandle_t handle,
                              cublasOperation_t transa, cublasOperation_t transb,
                               int m, int n, int k,
                              const cuComplex const cuComplex
                                                        *alpha,
                                                      *A, int lda,
                              const cuComplex *B, int ldb,
                               const cuComplex
                               cuComplex *C, int ldc)
cublasStatus t cublasXtZgemm(cublasXtHandle t handle,
                               cublasOperation t transa, cublasOperation t transb,
                               int m, int n, int k,
                               const cuDoubleComplex *alpha,
const cuDoubleComplex *A, int lda,
                               const cuDoubleComplex *B, int ldb,
                               const cuDoubleComplex *beta,
                               cuDoubleComplex *C, int ldc)
```

This function performs the matrix-matrix multiplication

$$C = \alpha \operatorname{op}(A)\operatorname{op}(B) + \beta C$$

where α and β are scalars, and A, B and C are matrices stored in column-major format with dimensions op(A) $m \times k$, op(B) $k \times n$ and C $m \times n$, respectively. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == \text{CUBLAS_OP_N} \\ A^T & \text{if transa} == \text{CUBLAS_OP_T} \\ A^H & \text{if transa} == \text{CUBLAS_OP_C} \end{cases}$$

and op(B) is defined similarly for matrix B.

Param.	Memory	In/out	Meaning
handle		input	handle to the cublasXt API context.
transa		input	operation op(A) that is non- or (conj.) transpose.
transb		input	operation op(B) that is non- or (conj.) transpose.
m		input	number of rows of matrix op(A) and C.
n		input	number of columns of matrix op(в) and с.
k		input	number of columns of $op(A)$ and rows of $op(B)$.

Param.	Memory	In/out	Meaning
alpha	host	input	<type> scalar used for multiplication.</type>
A	host or device	input	<pre><type> array of dimensions lda x k with lda>=max(1,m) if transa == CUBLAS_OP_N and lda x m with lda>=max(1,k) otherwise.</type></pre>
lda		input	leading dimension of two-dimensional array used to store the matrix ${\bf A}$.
В	host or device	input	<pre><type> array of dimension ldb x n with ldb>=max(1,k) if transa == CUBLAS_OP_N and ldb x k with ldb>=max(1,n) otherwise.</type></pre>
ldb		input	leading dimension of two-dimensional array used to store matrix B .
beta	host	input	<pre><type> scalar used for multiplication. If beta==0, C does not have to be a valid input.</type></pre>
С	host or device	in/out	<pre><type> array of dimensions ldc x n With ldc>=max(1,m).</type></pre>
ldc		input	leading dimension of a two-dimensional array used to store the matrix c.

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters m, n, k<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

sgemm, dgemm, cgemm, zgemm

3.4.2. cublasXt<t>hemm()

This function performs the Hermitian matrix-matrix multiplication

```
C = \begin{cases} \alpha AB + \beta C & \text{if side} == \text{CUBLAS\_SIDE\_LEFT} \\ \alpha BA + \beta C & \text{if side} == \text{CUBLAS\_SIDE\_RIGHT} \end{cases}
```

where *A* is a Hermitian matrix stored in lower or upper mode, *B* and *C* are $m \times n$ matrices, and α and β are scalars.

Param.	Memory	In/out	Meaning
handle		input	handle to the cublasXt API context.
side		input	indicates if matrix A is on the left or right of B.
uplo		input	indicates if matrix A lower or upper part is stored, the other Hermitian part is not referenced and is inferred from the stored elements.
m		input	number of rows of matrix c and B, with matrix A sized accordingly.
n		input	number of columns of matrix c and B, with matrix A sized accordingly.
alpha	host	input	<type> scalar used for multiplication.</type>
A	host or device	input	<pre><type> array of dimension lda x m with lda>=max(1,m) if side==CUBLAS_SIDE_LEFT and lda x n with lda>=max(1,n) otherwise. The imaginary parts of the diagonal elements are assumed to be zero.</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A.
В	host or device	input	<pre><type> array of dimension ldb \times n with ldb>=max(1,m).</type></pre>
ldb		input	leading dimension of two-dimensional array used to store matrix в.
beta	host	input	<pre><type> scalar used for multiplication, if beta==0 then c does not have to be a valid input.</type></pre>

Param.	Memory	In/out	Meaning
С	host or device	in/out	<type> array of dimensions ldc x n with ldc>=max(1,m).</type>
ldc		input	leading dimension of two-dimensional array used to store matrix c.

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters m, n<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

chemm, zhemm

3.4.3. cublasXt<t>symm()

```
cublasStatus_t cublasXtSsymm(cublasXtHandle_t handle,
                             cublasSideMode_t side, cublasFillMode_t uplo,
                             size_t m, size_t n,
cublasStatus t cublasXtDsymm(cublasXtHandle t handle,
                             cublasSideMode t side, cublasFillMode t uplo,
                             size_t m, size_t n,
                             const double *A, size_const double *B, size_const double *beta,
double *C, size_t ldc)
                                                    *A, size_t lda,
                                                    *B, size_t ldb,
cublasStatus_t cublasXtCsymm(cublasXtHandle_t handle,
                             cublasSideMode t side, cublasFillMode t uplo,
                             size_t m, size_t n,
                             const cuComplex *alpha,
const cuComplex *A, size t lda,
const cuComplex *B, size t ldb,
const cuComplex *beta,
                             cuComplex *C, size_t ldc)
cublasStatus_t cublasXtZsymm(cublasXtHandle_t handle,
                             cublasSideMode_t side, cublasFillMode_t uplo,
                             size_t m, size_t n,
                             const cuDoubleComplex *alpha,
                             const cuDoubleComplex *A, size t lda,
                             const cuDoubleComplex *B, size t ldb,
                             const cuDoubleComplex *beta,
                             cuDoubleComplex *C, size_t ldc)
```

This function performs the symmetric matrix-matrix multiplication

$$C = \begin{cases} \alpha AB + \beta C & \text{if side} == \text{CUBLAS_SIDE_LEFT} \\ \alpha BA + \beta C & \text{if side} == \text{CUBLAS_SIDE_RIGHT} \end{cases}$$

where A is a symmetric matrix stored in lower or upper mode, A and A are $m \times n$ matrices, and α and β are scalars.

Param.	Memory	In/out	Meaning
handle		input	handle to the cublasXt API context.
side		input	indicates if matrix ${f a}$ is on the left or right of ${f B}$.
uplo		input	indicates if matrix ${\bf A}$ lower or upper part is stored, the other symmetric part is not referenced and is inferred from the stored elements.
m		input	number of rows of matrix A and B , with matrix A sized accordingly.
n		input	number of columns of matrix c and A, with matrix A sized accordingly.
alpha	host	input	<type> scalar used for multiplication.</type>
А	host or device	input	<pre><type> array of dimension lda x m with lda>=max(1,m) if side == CUBLAS_SIDE_LEFT and lda x n with lda>=max(1,n) otherwise.</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A.
В	host or device	input	<type> array of dimension ldb x n with ldb>=max(1,m).</type>
ldb		input	leading dimension of two-dimensional array used to store matrix в.
beta	host	input	<pre><type> scalar used for multiplication, if beta == 0 then c does not have to be a valid input.</type></pre>
С	host or device	in/out	<pre><type> array of dimension ldc x n with ldc>=max(1,m).</type></pre>
ldc		input	leading dimension of two-dimensional array used to store matrix c.

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters m, n<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

ssymm, dsymm, csymm, zsymm

3.4.4. cublasXt<t>syrk()

```
cublasStatus t cublasXtSsyrk(cublasXtHandle t handle,
                              cublasFillMode_t uplo, cublasOperation_t trans,
                              int n, int k,
const float *A, in
const float *beta,
float *C, int ldc)
                                                     *alpha,
*A, int lda,
*beta,
cublasStatus t cublasXtDsyrk(cublasXtHandle t handle,
                              cublasFillMode_t uplo, cublasOperation_t trans,
                               int n, int k,
                              const double
                                                       *alpha,
                              const double const double const double *A, int lda, the const double double *C, int ldc)
cublasStatus_t cublasXtCsyrk(cublasXtHandle_t handle,
                              cublasFillMode t uplo, cublasOperation t trans,
                              int n, int k,
                              cublasStatus t cublasXtZsyrk(cublasXtHandle t handle,
                              cublasFillMode_t uplo, cublasOperation_t trans,
                              int n, int k,
                              const cuDoubleComplex *alpha,
                              const cuDoubleComplex *A, int lda,
const cuDoubleComplex *beta,
                              cuDoubleComplex *C, int ldc)
```

This function performs the symmetric rank- *k* update

$$C = \alpha \operatorname{op}(A) \operatorname{op}(A)^T + \beta C$$

where α and β are scalars, C is a symmetric matrix stored in lower or upper mode, and A is a matrix with dimensions op(A) $n \times k$. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == CUBLAS_OP_N \\ A^T & \text{if transa} == CUBLAS_OP_T \end{cases}$$

Param.	Memory	In/out	Meaning
handle		input	handle to the cublasXt API context.
uplo		input	indicates if matrix c lower or upper part is stored, the other symmetric part is not referenced and is inferred from the stored elements.
trans		input	operation op(A) that is non- or transpose.
n		input	number of rows of matrix op(A) and C.
k		input	number of columns of matrix $op(a)$.
alpha	host	input	<type> scalar used for multiplication.</type>
А	host or device	input	<pre><type> array of dimension lda x k with lda>=max(1,n) if trans == CUBLAS_OP_N and lda x n with lda>=max(1,k) otherwise.</type></pre>

Param.	Memory	In/out	Meaning
lda		input	leading dimension of two-dimensional array used to store matrix A.
beta	host	input	<pre><type> scalar used for multiplication, if beta==0 then c does not have to be a valid input.</type></pre>
С	host or device	in/out	<pre><type> array of dimension ldc x n, with ldc>=max(1,n).</type></pre>
ldc		input	leading dimension of two-dimensional array used to store matrix c.

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,k<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

ssyrk, dsyrk, csyrk, zsyrk

3.4.5. cublasXt<t>syr2k()

```
cublasStatus_t cublasXtSsyr2k(cublasXtHandle_t handle,
                                       cublasFillMode_t uplo, cublasOperation t trans,
                                       size t n, size t k,
                                      const float *A, size const float *A, size const float *B, size const float *beta, float *C, size t ldc)
                                                                     *A, size_t lda,
                                                                     *B, size_t ldb,
cublasStatus_t cublasXtDsyr2k(cublasXtHandle_t handle,
                                      cublasFillMode_t uplo, cublasOperation_t trans,
                                      size_t n, size_t k,
                                      const double *alpha,
const double *A, size
const double *B, size
const double *beta,
double *C, size t ldc)
                                                                     *A, size_t lda,
                                                                    *B, size t ldb,
cublasStatus_t cublasXtCsyr2k(cublasXtHandle_t handle,
                                      cublasFillMode_t uplo, cublasOperation_t trans,
                                      size_t n, size_t k,
                                      const cuComplex *A, size_t lda,
const cuComplex *B, size_t ldb,
const cuComplex *beta,
cuComplex *C, size_t ldc)
cublasStatus_t cublasXtZsyr2k(cublasXtHandle_t handle,
                                       cublasFillMode t uplo, cublasOperation t trans,
                                       size_t n, size_t k,
                                      const cuDoubleComplex *alpha,
const cuDoubleComplex *A, size_t lda,
const cuDoubleComplex *B, size_t ldb,
                                       const cuDoubleComplex *beta,
                                       cuDoubleComplex *C, size_t ldc)
```

This function performs the symmetric rank- 2k update

$$C = \alpha(\operatorname{op}(A)\operatorname{op}(B)^{T} + \operatorname{op}(B)\operatorname{op}(A)^{T}) + \beta C$$

where α and β are scalars, C is a symmetric matrix stored in lower or upper mode, and A and B are matrices with dimensions op(A) $n \times k$ and op(B) $n \times k$, respectively. Also, for matrix A and B

$$op(A)$$
 and $op(B) = \begin{cases} A \text{ and } B \\ A^T \text{ and } B^T \end{cases}$ if trans == CUBLAS_OP_N

Param.	Memory	In/out	Meaning
handle		input	handle to the cublasXt API context.
uplo		input	indicates if matrix c lower or upper part, is stored, the other symmetric part is not referenced and is inferred from the stored elements.
trans		input	operation op(A) that is non- or transpose.
n		input	number of rows of matrix $op(A)$, $op(B)$ and C .
k		input	number of columns of matrix $op(A)$ and $op(B)$.
alpha	host	input	<type> scalar used for multiplication.</type>

Param.	Memory	In/out	Meaning
А	host or device	input	<pre><type> array of dimension lda x k with lda>=max(1,n) if transa == CUBLAS_OP_N and lda x n with lda>=max(1,k) otherwise.</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix ${f a}$.
В	host or device	input	<pre><type> array of dimensions ldb x k with ldb>=max(1,n) if transa == CUBLAS_OP_N and ldb x n with ldb>=max(1,k) otherwise.</type></pre>
ldb		input	leading dimension of two-dimensional array used to store matrix B .
beta	host	input	<pre><type> scalar used for multiplication, if beta==0, then c does not have to be a valid input.</type></pre>
С	host or device	in/out	<pre><type> array of dimensions ldc x n With ldc>=max(1,n).</type></pre>
ldc		input	leading dimension of two-dimensional array used to store matrix c.

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,k<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

ssyr2k, dsyr2k, csyr2k, zsyr2k

3.4.6. cublasXt<t>syrkx()

```
cublasStatus t cublasXtSsyrkx(cublasXtHandle t handle,
                                    cublasFillMode t uplo, cublasOperation t trans,
                                    size t n, size t k,
                                   const float *A, size_t lda,
const float *B, size_t ldb,
const float *beta,
float *C, size_t ldc)
cublasStatus t cublasXtDsyrkx(cublasXtHandle_t handle,
                                   cublasFillMode_t uplo, cublasOperation_t trans,
                                    size t n, size t k,
                                   const double const double
                                                                *alpha,
                                   const double *alpna,
const double *A, size_t lda,
const double *B, size_t ldb,
const double *C, size_t ldc)
cublasStatus_t cublasXtCsyrkx(cublasXtHandle_t handle,
                                   cublasFillMode t uplo, cublasOperation t trans,
                                   size t n, size t k,
                                   const cuComplex *A, size_t lda,
const cuComplex *B, size_t ldb,
const cuComplex *b, size_t ldb,
const cuComplex *cucomplex *c, size_t ldc)
cublasStatus_t cublasXtZsyrkx(cublasXtHandle_t handle,
                                   cublasFillMode_t uplo, cublasOperation_t trans,
                                    size_t n, size_t k,
                                    const cuDoubleComplex *alpha,
                                    const cuDoubleComplex *A, size_t lda,
                                    const cuDoubleComplex *B, size_t ldb,
                                    const cuDoubleComplex *beta,
                                    cuDoubleComplex *C, size t ldc)
```

This function performs a variation of the symmetric rank- *k* update

$$C = \alpha(\operatorname{op}(A)\operatorname{op}(B)^T + \beta C$$

where α and β are scalars, C is a symmetric matrix stored in lower or upper mode, and A and B are matrices with dimensions op(A) $n \times k$ and op(B) $n \times k$, respectively. Also, for matrix A and B

op(A) and op(B) =
$$\begin{cases} A \text{ and } B & \text{if trans} == \text{CUBLAS_OP_N} \\ A^T \text{ and } B^T & \text{if trans} == \text{CUBLAS_OP_T} \end{cases}$$

This routine can be used when B is in such way that the result is garanteed to be symmetric. An usual example is when the matrix B is a scaled form of the matrix A: this is equivalent to B being the product of the matrix A and a diagonal matrix.

Param.	Memory	In/out	Meaning
handle		input	handle to the cublasXt API context.
uplo		input	indicates if matrix c lower or upper part, is stored, the other symmetric part is not referenced and is inferred from the stored elements.
trans		input	operation op(A) that is non- or transpose.

Param.	Memory	In/out	Meaning
n		input	number of rows of matrix $op(A)$, $op(B)$ and c .
k		input	number of columns of matrix $op(a)$ and $op(b)$.
alpha	host	input	<type> scalar used for multiplication.</type>
A	host or device	input	<pre><type> array of dimension lda x k with lda>=max(1,n) if transa == CUBLAS_OP_N and lda x n with lda>=max(1,k) otherwise.</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A.
В	host or device	input	<pre><type> array of dimensions ldb x k with ldb>=max(1,n) if transa == CUBLAS_OP_N and ldb x n with ldb>=max(1,k) otherwise.</type></pre>
ldb		input	leading dimension of two-dimensional array used to store matrix в.
beta	host	input	<pre><type> scalar used for multiplication, if beta==0, then c does not have to be a valid input.</type></pre>
С	host or device	in/out	<pre><type> array of dimensions ldc x n With ldc>=max(1,n).</type></pre>
ldc		input	leading dimension of two-dimensional array used to store matrix c.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,k<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to: ssyrk, dsyrk, csyrk, zsyrk and ssyr2k, dsyr2k, csyr2k, zsyr2k

3.4.7. cublasXt<t>herk()

This function performs the Hermitian rank- k update

$$C = \alpha \operatorname{op}(A) \operatorname{op}(A)^H + \beta C$$

where α and β are scalars, C is a Hermitian matrix stored in lower or upper mode, and A is a matrix with dimensions op(A) $n \times k$. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == CUBLAS_OP_N \\ A^H & \text{if transa} == CUBLAS_OP_C \end{cases}$$

			1	
Param.	Memory	In/out	Meaning	
handle		input	handle to the cublasXt API context.	
uplo		input	indicates if matrix $\bf A$ lower or upper part is stored, the other Hermitian part is not referenced and is inferred from the stored elements.	
trans		input	operation op(A) that is non- or (conj.) transpose.	
n		input	number of rows of matrix op(A) and C.	
k		input	number of columns of matrix $op(A)$.	
alpha	host	input	<type> scalar used for multiplication.</type>	
A	host or device	input	<pre><type> array of dimension lda x k with lda>=max(1,n) if transa == CUBLAS_OP_N and lda x n with lda>=max(1,k) otherwise.</type></pre>	
lda		input	leading dimension of two-dimensional array used to store matrix A.	
beta	host	input	<pre><type> scalar used for multiplication, if beta==0 then c does not have to be a valid input.</type></pre>	
С	host or device	in/out	<pre><type> array of dimension ldc x n, with ldc>=max(1,n). The imaginary parts of the diagonal elements are assumed and set to zero.</type></pre>	
ldc		input	leading dimension of two-dimensional array used to store matrix c.	

•	· ·
Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,k<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

cherk, zherk

3.4.8. cublasXt<t>her2k()

This function performs the Hermitian rank- 2k update

$$C = \alpha \operatorname{op}(A) \operatorname{op}(B)^{H} + \bar{\alpha} \operatorname{op}(B) \operatorname{op}(A)^{H} + \beta C$$

where α and β are scalars, C is a Hermitian matrix stored in lower or upper mode, and A and B are matrices with dimensions op(A) $n \times k$ and op(B) $n \times k$, respectively. Also, for matrix A and B

$$op(A)$$
 and $op(B) = \begin{cases} A \text{ and } B & \text{if trans} == CUBLAS_OP_N \\ A^H \text{ and } B^H & \text{if trans} == CUBLAS_OP_C \end{cases}$

Param.	Memory	In/out	Meaning
handle		input	handle to the cublasXt API context.
uplo		input	indicates if matrix A lower or upper part is stored, the other Hermitian part is not referenced and is inferred from the stored elements.
trans		input	operation op(A) that is non- or (conj.) transpose.
n		input	number of rows of matrix $op(A)$, $op(B)$ and c .
k		input	number of columns of matrix $op(a)$ and $op(b)$.

Param.	Memory	In/out	Meaning
alpha	host	input	<type> scalar used for multiplication.</type>
A	host or device	input	<pre><type> array of dimension lda x k With lda>=max(1,n) if transa == CUBLAS_OP_N and lda x n With lda>=max(1,k) otherwise.</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A.
В	host or device	input	<pre><type> array of dimension ldb x k with ldb>=max(1,n) if transa == CUBLAS_OP_N and ldb x n with ldb>=max(1,k) otherwise.</type></pre>
ldb		input	leading dimension of two-dimensional array used to store matrix B .
beta	host	input	<pre><type> scalar used for multiplication, if beta==0 then c does not have to be a valid input.</type></pre>
С	host or device	in/out	<pre><type> array of dimension ldc x n, with ldc>=max(1,n). The imaginary parts of the diagonal elements are assumed and set to zero.</type></pre>
ldc		input	leading dimension of two-dimensional array used to store matrix c.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,k<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

cher2k, zher2k

3.4.9. cublasXt<t>herkx()

This function performs a variation of the Hermitian rank- k update

$$C = \alpha \operatorname{op}(A) \operatorname{op}(B)^{H} + \beta C$$

where α and β are scalars, C is a Hermitian matrix stored in lower or upper mode, and A and B are matrices with dimensions op(A) $n \times k$ and op(B) $n \times k$, respectively. Also, for matrix A and B

$$op(A)$$
 and $op(B) = \begin{cases} A \text{ and } B & \text{if trans} == CUBLAS_OP_N \\ A^H \text{ and } B^H & \text{if trans} == CUBLAS_OP_C \end{cases}$

This routine can be used when the matrix B is in such way that the result is garanteed to be hermitian. An usual example is when the matrix B is a scaled form of the matrix A: this is equivalent to B being the product of the matrix A and a diagonal matrix. For an efficient computation of the product of a regular matrix with a diagonal matrix, refer to the routine cublasXt<t>dgmm.

Param.	Memory	In/out	Meaning
handle		input	handle to the cublasXt API context.
uplo		input indicates if matrix A lower or upper part is stored, the other Hermitian part is not referenced and is inferred from the stored elements.	
trans		input	operation op(A) that is non- or (conj.) transpose.
n		input	number of rows of matrix $op(A)$, $op(B)$ and C .
k		input	number of columns of matrix $op(a)$ and $op(b)$.
alpha	host	input	<type> scalar used for multiplication.</type>
А	host or device	input	<pre><type> array of dimension lda x k with lda>=max(1,n) if transa == CUBLAS_OP_N and lda x n with lda>=max(1,k) otherwise.</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A.

Param.	Memory	In/out	Meaning
В	host or device	input	<pre><type> array of dimension ldb x k with ldb>=max(1,n) if transa == CUBLAS_OP_N and ldb x n with ldb>=max(1,k) otherwise.</type></pre>
ldb		input	leading dimension of two-dimensional array used to store matrix B.
beta	host	input	real scalar used for multiplication, if beta==0 then c does not have to be a valid input.
С	host or device	in/out	<type> array of dimension ldc \times n, with ldc>=max(1,n). The imaginary parts of the diagonal elements are assumed and set to zero.</type>
ldc		input	leading dimension of two-dimensional array used to store matrix c.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters n,k<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

cherk, zherk and

cher2k, zher2k

3.4.10. cublasXt<t>trsm()

```
cublasStatus t cublasXtStrsm(cublasXtHandle t handle,
                           cublasSideMode_t side, cublasFillMode t uplo,
                           cublasOperation t trans, cublasXtDiagType t diag,
                           size_t m, size_t n,
                           const float
                                                  *alpha,
                           const float

const float

*B, size t ldb)
                                               *A, size_t lda,
cublasStatus t cublasXtDtrsm(cublasXtHandle t handle,
                           cublasSideMode t side, cublasFillMode t uplo,
                           cublasOperation t trans, cublasXtDiagType t diag,
                           size_t m, size_t n,
                           const double
                                                  *alpha,
                           const double *A, size_double *B, size_t ldb)
                                                 *A, size t lda,
cublasStatus t cublasXtCtrsm(cublasXtHandle t handle,
                           cublasSideMode t side, cublasFillMode t uplo,
                           cublasOperation_t trans, cublasXtDiagType_t diag,
                           size_t m, size_t n,
                                                  *alpha,
                           const cuComplex
                                               *A, size_t lda,
                           const cuComplex *A, size_
cuComplex *B, size_t ldb)
cublasStatus_t cublasXtZtrsm(cublasXtHandle_t handle,
                           cublasSideMode t side, cublasFillMode t uplo,
                           cublasOperation t trans, cublasXtDiagType t diag,
                           size_t m, size_t n,
                           const cuDoubleComplex *alpha,
                           const cuDoubleComplex *A, size_t lda,
                           cuDoubleComplex *B, size t ldb)
```

This function solves the triangular linear system with multiple right-hand-sides

```
 \begin{cases} op(A)X = \alpha B & \text{if side} == CUBLAS\_SIDE\_LEFT \\ Xop(A) = \alpha B & \text{if side} == CUBLAS\_SIDE\_RIGHT \end{cases}
```

where A is a triangular matrix stored in lower or upper mode with or without the main diagonal, X and B are $m \times n$ matrices, and α is a scalar. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == \text{CUBLAS_OP_N} \\ A^T & \text{if transa} == \text{CUBLAS_OP_T} \\ A^H & \text{if transa} == \text{CUBLAS_OP_C} \end{cases}$$

The solution *X* overwrites the right-hand-sides *B* on exit.

No test for singularity or near-singularity is included in this function.

Param.	Memory	In/out	Meaning
handle		input	handle to the cublasXt API context.
side		input	indicates if matrix ${f a}$ is on the left or right of ${f x}$.
uplo		input	indicates if matrix A lower or upper part is stored, the other part is not referenced and is inferred from the stored elements.
trans		input	operation op(A) that is non- or (conj.) transpose.
diag		input	indicates if the elements on the main diagonal of matrix ${\bf A}$ are unity and should not be accessed.

Param.	Memory	In/out	Meaning
m		input	number of rows of matrix ${f B}$, with matrix ${f A}$ sized accordingly.
n		input	number of columns of matrix ${\bf B}$, with matrix ${\bf A}$ is sized accordingly.
alpha	host	input	<type> scalar used for multiplication, if alpha==0 then A is not referenced and B does not have to be a valid input.</type>
A	host or device	input	<pre><type> array of dimension lda x m With lda>=max(1,m) if side == CUBLAS_SIDE_LEFT and lda x n With lda>=max(1,n) otherwise.</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A.
В	host or device	in/out	<type> array. It has dimensions ldb x n with ldb>=max(1,m).</type>
ldb		input	leading dimension of two-dimensional array used to store matrix в.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters m, n<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

strsm, dtrsm, ctrsm, ztrsm

3.4.11. cublasXt<t>trmm()

```
cublasStatus t cublasXtStrmm(cublasXtHandle t handle,
                                                                                    cublasSideMode_t side, cublasFillMode t uplo,
                                                                                    cublasOperation t trans, cublasDiagType t diag,
                                                                                    size_t m, size_t n,
                                                                                  const float
const float
float
                                                                                                                                                        *alpha,
                                                                                                                                                       *A, size_t lda,
                                                                                                                                                     *B, size_t ldb, *C, size_t ldc)
cublasStatus t cublasXtDtrmm(cublasXtHandle t handle,
                                                                                  cublasSideMode t side, cublasFillMode t uplo,
                                                                                   cublasOperation_t trans, cublasDiagType t diag,
                                                                                   size_t m, size_t n,
                                                                                  const double const double const double
                                                                                                                                                        *alpha,
                                                                                                                                                       *A, size_t lda,
                                                                                                                                                       *B, size t ldb,
                                                                                                                                                       *C, size_t ldc)
                                                                                  double
cublasStatus_t cublasXtCtrmm(cublasXtHandle_t handle,
                                                                                  cublasSideMode t side, cublasFillMode t uplo,
                                                                                   cublasOperation_t trans, cublasDiagType_t diag,
                                                                                   size t \overline{m}, size \overline{t} n,
                                                                                  const cuComplex
const cuComplex
const cuComplex
const cuComplex
cu
cublasStatus_t cublasXtZtrmm(cublasXtHandle_t handle,
                                                                                   cublasSideMode t side, cublasFillMode t uplo,
                                                                                   cublasOperation_t trans, cublasDiagType_t diag,
                                                                                   size_t m, size_t n,
                                                                                    const cuDoubleComplex *alpha,
                                                                                   const cuDoubleComplex *A, size_t lda,
                                                                                    const cuDoubleComplex *B, size t ldb,
                                                                                    cuDoubleComplex
                                                                                                                                                        *C, size_t ldc)
```

This function performs the triangular matrix-matrix multiplication

$$C = \begin{cases} \alpha \operatorname{op}(A)B & \text{if side} == \mathsf{CUBLAS_SIDE_LEFT} \\ \alpha B \operatorname{op}(A) & \text{if side} == \mathsf{CUBLAS_SIDE_RIGHT} \end{cases}$$

where A is a triangular matrix stored in lower or upper mode with or without the main diagonal, B and C are $m \times n$ matrix, and α is a scalar. Also, for matrix A

$$op(A) = \begin{cases} A & \text{if transa} == \text{CUBLAS_OP_N} \\ A^T & \text{if transa} == \text{CUBLAS_OP_T} \\ A^H & \text{if transa} == \text{CUBLAS_OP_C} \end{cases}$$

Notice that in order to achieve better parallelism, similarly to the cublas API, cublasXT API differs from the BLAS API for this routine. The BLAS API assumes an in-place implementation (with results written back to B), while the cublasXt API assumes an out-of-place implementation (with results written into C). The application can still obtain the in-place functionality of BLAS in the cublasXT API by passing the address of the matrix B in place of the matrix C. No other overlapping in the input parameters is supported.

Param.	Memory	In/out	Meaning
handle		input	handle to the cublasXt API context.
side		input	indicates if matrix ${f a}$ is on the left or right of ${f B}$.

Param.	Memory	In/out	Meaning
uplo		input	indicates if matrix A lower or upper part is stored, the other part is not referenced and is inferred from the stored elements.
trans		input	operation op(A) that is non- or (conj.) transpose.
diag		input	indicates if the elements on the main diagonal of matrix ${\tt A}$ are unity and should not be accessed.
m		input	number of rows of matrix B, with matrix A sized accordingly.
n		input	number of columns of matrix ${\tt B}$, with matrix ${\tt A}$ sized accordingly.
alpha	host	input	<type> scalar used for multiplication, if alpha==0 then A is not referenced and в does not have to be a valid input.</type>
A	host or device	input	<pre><type> array of dimension lda x m With lda>=max(1,m) if side == CUBLAS_SIDE_LEFT and lda x n With lda>=max(1,n) otherwise.</type></pre>
lda		input	leading dimension of two-dimensional array used to store matrix A .
В	host or device	input	<pre><type> array of dimension ldb x n with ldb>=max(1,m).</type></pre>
ldb		input	leading dimension of two-dimensional array used to store matrix в.
С	host or device	in/out	<pre><type> array of dimension ldc x n With ldc>=max(1,m).</type></pre>
ldc		input	leading dimension of two-dimensional array used to store matrix c.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_INVALID_VALUE	the parameters m, n<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

strmm, dtrmm, ctrmm, ztrmm

3.4.12. cublasXt<t>spmm()

```
cublasStatus_t cublasXtSspmm( cublasXtHandle_t handle,
                                 cublasSideMode t side,
                                 cublasFillMode t uplo,
                                 size t m,
                                 size t n,
                                 const float *alpha,
                                 const float *AP,
                                 const float *B,
                                 size t ldb,
                                 const float *beta,
                                 float *C,
                                 size t ldc );
cublasStatus t cublasXtDspmm( cublasXtHandle t handle,
                                 cublasSideMode t side,
                                 cublasFillMode t uplo,
                                 size_t m,
                                 size_t n,
const double *alpha,
                                 const double *AP,
                                 const double *B,
                                 size_t ldb,
                                 const double *beta,
                                 double *C,
                                 size_t ldc );
cublasStatus t cublasXtCspmm( cublasXtHandle t handle,
                                 cublasSideMode t side,
                                 cublasFillMode t uplo,
                                 size t m,
                                 size t n,
                                 const cuComplex *alpha,
                                 const cuComplex *AP,
                                 const cuComplex *B,
                                 size t ldb,
                                 const cuComplex *beta,
                                 cuComplex *C,
                                 size t ldc );
cublasStatus_t cublasXtZspmm( cublasXtHandle_t handle,
                                 cublasSideMode t side,
                                 cublasFillMode t uplo,
                                 size_t m,
                                 size_t n,
const cuDoubleComplex *alpha,
                                 const cuDoubleComplex *AP,
                                 const cuDoubleComplex *B,
                                 size t ldb,
                                 const cuDoubleComplex *beta,
                                 cuDoubleComplex *C,
                                 size t ldc );
```

This function performs the symmetric packed matrix-matrix multiplication

$$C = \begin{cases} \alpha AB + \beta C & \text{if side} == \text{CUBLAS_SIDE_LEFT} \\ \alpha BA + \beta C & \text{if side} == \text{CUBLAS_SIDE_RIGHT} \end{cases}$$

where *A* is a $n \times n$ symmetric matrix stored in packed format, *B* and *C* are $m \times n$ matrices, and α and β are scalars.

If **uplo == CUBLAS_FILL_MODE_LOWER** then the elements in the lower triangular part of the symmetric matrix A are packed together column by column without gaps, so that the element A(i, j) is stored in the memory location AP[i+((2*n-j+1)*j)/2] for j=1, ..., n and $i \ge j$. Consequently, the packed format requires only $\frac{n(n+1)}{2}$ elements for storage.

If **uplo == CUBLAS_FILL_MODE_UPPER** then the elements in the upper triangular part of the symmetric matrix A are packed together column by column without gaps, so that the element A(i, j) is stored in the memory location AP[i+(j*(j+1))/2] for j=1, ..., n and $i \le j$. Consequently, the packed format requires only $\frac{n(n+1)}{2}$ elements for storage.



The packed matrix AP must be located on the Host whereas the other matrices can be located on the Host or any GPU device

Param.	Memory	In/out	Meaning
handle		input	handle to the cublasXt API context.
side		input	indicates if matrix A is on the left or right of B .
uplo		input	indicates if matrix A lower or upper part is stored, the other symmetric part is not referenced and is inferred from the stored elements.
m		input	number of rows of matrix A and B, with matrix A sized accordingly.
n		input	number of columns of matrix c and A, with matrix A sized accordingly.
alpha	host	input	<type> scalar used for multiplication.</type>
AP	host	input	<type> array with A stored in packed format.</type>
В	host or device	input	<pre><type> array of dimension ldb x n with ldb>=max(1,m).</type></pre>
ldb		input	leading dimension of two-dimensional array used to store matrix в.
beta	host	input	<pre><type> scalar used for multiplication, if beta == 0 then c does not have to be a valid input.</type></pre>
С	host or device	in/out	<pre><type> array of dimension ldc x n with ldc>=max(1,m).</type></pre>
ldc		input	leading dimension of two-dimensional array used to store matrix c.

The possible error values returned by this function and their meanings are listed below.

Error Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized

Error Value	Meaning
CUBLAS_STATUS_INVALID_VALUE	the parameters m, n<0
CUBLAS_STATUS_ARCH_MISMATCH	the device does not support double-precision
CUBLAS_STATUS_NOT_SUPPORTED	the matrix AP is located on a GPU device
CUBLAS_STATUS_EXECUTION_FAILED	the function failed to launch on the GPU

For references please refer to:

ssymm, dsymm, csymm, zsymm

Appendix A. USING THE CUBLAS LEGACY API

This appendix does not provide a full reference of each Legacy API datatype and entry point. Instead, it describes how to use the API, especially where this is different from the regular cuBLAS API.

Note that in this section, all references to the "cuBLAS Library" refer to the Legacy cuBLAS API only.

A.1. Error Status

The cublasStatus type is used for function status returns. The cuBLAS Library helper functions return status directly, while the status of core functions can be retrieved using cublasGetError(). Notice that reading the error status via cublasGetError(), resets the internal error state to CUBLAS_STATUS_SUCCESS. Currently, the following values for are defined:

Value	Meaning
CUBLAS_STATUS_SUCCESS	the operation completed successfully
CUBLAS_STATUS_NOT_INITIALIZED	the library was not initialized
CUBLAS_STATUS_ALLOC_FAILED	the resource allocation failed
CUBLAS_STATUS_INVALID_VALUE	an invalid numerical value was used as an argument
CUBLAS_STATUS_ARCH_MISMATCH	an absent device architectural feature is required
CUBLAS_STATUS_MAPPING_ERROR	an access to GPU memory space failed
CUBLAS_STATUS_EXECUTION_FAILED	the GPU program failed to execute
CUBLAS_STATUS_INTERNAL_ERROR	an internal operation failed
CUBLAS_STATUS_NOT_SUPPORTED	the feature required is not supported

This legacy type corresponds to type cublasStatus_t in the cuBLAS library API.

A.2. Initialization and Shutdown

The functions <code>cublasInit()</code> and <code>cublasShutdown()</code> are used to initialize and shutdown the <code>cuBLAS</code> library. It is recommended for <code>cublasInit()</code> to be called before any other function is invoked. It allocates hardware resources on the GPU device that is currently bound to the host thread from which it was invoked.

The legacy initialization and shutdown functions are similar to the cuBLAS library API routines cublasCreate() and cublasDestroy().

A.3. Thread Safety

The legacy API is not thread safe when used with multiple host threads and devices. It is recommended to be used only when utmost compatibility with Fortran is required and when a single host thread is used to setup the library and make all the functions calls.

A.4. Memory Management

The memory used by the legacy cuBLAS library API is allocated and released using functions cublasAlloc() and cublasFree(), respectively. These functions create and destroy an object in the GPU memory space capable of holding an array of n elements, where each element requires elemSize bytes of storage. Please see the legacy cuBLAS API header file "cublas.h" for the prototypes of these functions.

The function **cublasAlloc()** is a wrapper around the function **cudaMalloc()**, therefore device pointers returned by **cublasAlloc()** can be passed to any CUDATM device kernel functions. However, these device pointers can not be dereferenced in the host code. The function **cublasFree()** is a wrapper around the function **cudaFree()**.

A.5. Scalar Parameters

There are two categories of the functions that use scalar parameters:

- functions that take alpha and/or beta parameters by reference on the host or the device as scaling factors, such as gemm
- functions that return a scalar result on the host or the device such as amax(), amin, asum(), rotg(), rotmg(), dot() and nrm2().

For the functions of the first category, when the pointer mode is set to CUBLAS_POINTER_MODE_HOST, the scalar parameters alpha and/or beta can be on the stack or allocated on the heap. Underneath the CUDA kernels related to that functions will be launched with the value of alpha and/or beta. Therefore if they were allocated on the heap, they can be freed just after the return of the call even though the kernel launch is asynchronous. When the pointer mode is set to CUBLAS POINTER MODE DEVICE, alpha and/or beta must be accessible on the

device and their values should not be modified until the kernel is done. Note that since cudaFree() does an implicit cudaDeviceSynchronize(), cudaFree() can still be called on alpha and/or beta just after the call but it would defeat the purpose of using this pointer mode in that case.

For the functions of the second category, when the pointer mode is set to <code>CUBLAS_POINTER_MODE_HOST</code>, these functions blocks the CPU, until the GPU has completed its computation and the results has been copied back to the Host. When the pointer mode is set to <code>CUBLAS_POINTER_MODE_DEVICE</code>, these functions return immediately. In this case, similarly to matrix and vector results, the scalar result is ready only when execution of the routine on the GPU has completed. This requires proper synchronization in order to read the result from the host.

In either case, the pointer mode <code>CUBLAS_POINTER_MODE_DEVICE</code> allows the library functions to execute completely asynchronously from the Host even when <code>alpha</code> and/or <code>beta</code> are generated by a previous kernel. For example, this situation can arise when iterative methods for solution of linear systems and eigenvalue problems are implemented using the cuBLAS library.

A.6. Helper Functions

In this section we list the helper functions provided by the legacy cuBLAS API and their functionality. For the exact prototypes of these functions please refer to the legacy cuBLAS API header file "cublas.h".

Helper function	Meaning
cublasInit()	initialize the library
cublasShutdown()	shuts down the library
cublasGetError()	retrieves the error status of the library
cublasSetKernelStream()	sets the stream to be used by the library
cublasAlloc()	allocates the device memory for the library
cublasFree()	releases the device memory allocated for the library
cublasSetVector()	copies a vector \mathbf{x} on the host to a vector on the GPU
cublasGetVector()	copies a vector x on the GPU to a vector on the host
cublasSetMatrix()	copies a $m \times n$ tile from a matrix on the host to the GPU
cublasGetMatrix()	copies a $m \times n$ tile from a matrix on the GPU to the host
cublasSetVectorAsync()	similar to cublasSetVector(), but the copy is asynchronous

Helper function	Meaning
cublasGetVectorAsync()	similar to cublasGetVector(), but the copy is asynchronous
cublasSetMatrixAsync()	similar to cublasSetMatrix(), but the copy is asynchronous
cublasGetMatrixAsync()	similar to cublasGetMatrix(), but the copy is asynchronous

A.7. Level-1,2,3 Functions

The Level-1,2,3 cuBLAS functions (also called core functions) have the same name and behavior as the ones listed in the chapters 3, 4 and 5 in this document. Please refer to the legacy cuBLAS API header file "cublas.h" for their exact prototype. Also, the next section talks a bit more about the differences between the legacy and the cuBLAS API prototypes, more specifically how to convert the function calls from one API to another.

A.8. Converting Legacy to the cuBLAS API

There are a few general rules that can be used to convert from legacy to the cuBLAS API.

Exchange the header file "cublas.h" for "cublas_v2.h".

Exchange the type cublasStatus for cublasStatus t.

Exchange the function cublasSetKernelStream() for cublasSetStream().

Exchange the function cublasAlloc() and cublasFree() for cudaMalloc() and cudaFree(), respectively. Notice that cudaMalloc() expects the size of the allocated memory to be provided in bytes (usually simply provide n x elemSize to allocate n elements, each of size elemSize bytes).

Declare the **cublasHandle** t cuBLAS library handle.

Initialize the handle using **cublasCreate()**. Also, release the handle once finished using **cublasDestroy()**.

Add the handle as the first parameter to all the cuBLAS library function calls.

Change the scalar parameters to be passed by reference, instead of by value (usually simply adding "&" symbol in C/C++ is enough, because the parameters are passed by reference on the host by *default*). However, note that if the routine is running asynchronously, then the variable holding the scalar parameter cannot be changed until the kernels that the routine dispatches are completed. See the CUDA C Programming Guide for a detailed discussion of how to use streams.

Change the parameter characters 'N' or 'n' (non-transpose operation), 'T' or 't' (transpose operation) and 'C' or 'c' (conjugate transpose operation) to CUBLAS_OP_N, CUBLAS_OP_T and CUBLAS_OP_C, respectively.

Change the parameter characters 'L' or 'l' (lower part filled) and 'U' or 'u' (upper part filled) to CUBLAS_FILL_MODE_LOWER and CUBLAS_FILL_MODE_UPPER, respectively.

Change the parameter characters 'N' or 'n' (non-unit diagonal) and 'U' or 'u' (unit diagonal) to CUBLAS_DIAG_NON_UNIT and CUBLAS_DIAG_UNIT, respectively.

Change the parameter characters 'L' or 'l' (left side) and 'R' or 'r' (right side) to CUBLAS_SIDE_LEFT and CUBLAS_SIDE_RIGHT, respectively.

If the legacy API function returns a scalar value, add an extra scalar parameter of the same type passed by reference, as the last parameter to the same function.

Instead of using **cublasGetError**, use the return value of the function itself to check for errors.

Finally, please use the function prototypes in the header files "cublas.h" and "cublas_v2.h" to check the code for correctness.

A.9. Examples

For sample code references that use the legacy cuBLAS API please see the two examples below. They show an application written in C using the legacy cuBLAS library API with two indexing styles (Example A.1. "Application Using C and cuBLAS: 1-based indexing" and Example A.2. "Application Using C and cuBLAS: 0-based Indexing"). This application is analogous to the one using the cuBLAS library API that is shown in the Introduction chapter.

Example A.1. Application Using C and cuBLAS: 1-based indexing

```
#include <stdio.h>
#include <stdlib.h>
#include <math.h>
#include "cublas.h"
#define M 6
#define N 5
#define IDX2F(i,j,ld) ((((j)-1)*(ld))+((i)-1))
                void modify (float *m, int ldm, int n, int p, int q, float
        inline
alpha, float beta) {
   cublasSscal (n-p+1, alpha, &m[IDX2F(p,q,ldm)], ldm);
   cublasSscal (ldm-p+1, beta, &m[IDX2F(p,q,ldm)], 1);
int main (void) {
   int i, j;
   cublasStatus stat;
   float* devPtrA;
float* a = 0;
   a = (float *)malloc (M * N * sizeof (*a));
   if (!a) {
       printf ("host memory allocation failed");
       return EXIT FAILURE;
    for (j = 1; j <= N; j++) {
       for (i = 1; i <= M; i++) {
           a[IDX2F(i,j,M)] = (float)((i-1) * M + j);
   cublasInit();
   stat = cublasAlloc (M*N, sizeof(*a), (void**)&devPtrA);
    if (stat != cuBLAS_STATUS_SUCCESS) {
       printf ("device memory allocation failed");
        cublasShutdown();
       return EXIT FAILURE;
   stat = cublasSetMatrix (M, N, sizeof(*a), a, M, devPtrA, M);
    if (stat != cuBLAS_STATUS_SUCCESS) {
       printf ("data download failed");
       cublasFree (devPtrA);
       cublasShutdown();
       return EXIT FAILURE;
    }
   modify (devPtrA, M, N, 2, 3, 16.0f, 12.0f);
   stat = cublasGetMatrix (M, N, sizeof(*a), devPtrA, M, a, M);
    if (stat != cuBLAS STATUS SUCCESS) {
       printf ("data upload failed");
       cublasFree (devPtrA);
        cublasShutdown();
       return EXIT FAILURE;
   }
   cublasFree (devPtrA);
   cublasShutdown();
    for (j = 1; j \le N; j++) {
        for (i = 1; i <= M; i++) {
            printf ("%7.0f", a[IDX2F(i,j,M)]);
       printf ("\n");
   free(a);
   return EXIT SUCCESS;
```

Example A.2. Application Using C and cuBLAS: 0-based indexing

```
#include <stdio.h>
#include <stdlib.h>
#include <math.h>
#include "cublas.h"
#define M 6
#define N 5
#define IDX2C(i,j,ld) (((j)*(ld))+(i))
                 void modify (float *m, int ldm, int n, int p, int q, float
        inline
alpha, float beta) {
   cublasSscal (n-p, alpha, &m[IDX2C(p,q,ldm)], ldm);
   cublasSscal (ldm-p, beta, &m[IDX2C(p,q,ldm)], 1);
int main (void) {
   int i, j;
   cublasStatus stat;
   float* devPtrA;
float* a = 0;
   a = (float *)malloc (M * N * sizeof (*a));
   if (!a) {
       printf ("host memory allocation failed");
        return EXIT FAILURE;
    for (j = 0; j < N; j++) {
        for (i = 0; i < M; i++) {</pre>
            a[IDX2C(i,j,M)] = (float)(i * M + j + 1);
   cublasInit();
   stat = cublasAlloc (M*N, sizeof(*a), (void**)&devPtrA);
    if (stat != cuBLAS_STATUS_SUCCESS) {
       printf ("device memory allocation failed");
        cublasShutdown();
       return EXIT FAILURE;
   stat = cublasSetMatrix (M, N, sizeof(*a), a, M, devPtrA, M);
    if (stat != cuBLAS_STATUS_SUCCESS) {
       printf ("data download failed");
        cublasFree (devPtrA);
       cublasShutdown();
       return EXIT FAILURE;
    }
   modify (devPtrA, M, N, 1, 2, 16.0f, 12.0f);
   stat = cublasGetMatrix (M, N, sizeof(*a), devPtrA, M, a, M);
    if (stat != cuBLAS STATUS SUCCESS) {
       printf ("data upload failed");
        cublasFree (devPtrA);
        cublasShutdown();
        return EXIT FAILURE;
   }
   cublasFree (devPtrA);
   cublasShutdown();
    for (j = 0; j < N; j++) {
   for (i = 0; i < M; i++) {</pre>
            printf ("%7.0f", a[IDX2C(i,j,M)]);
       printf ("\n");
   free(a);
   return EXIT SUCCESS;
```

Using the cuBLAS Legacy API

Appendix B. CUBLAS FORTRAN BINDINGS

The cuBLAS library is implemented using the C-based CUDA toolchain, and thus provides a C-style API. This makes interfacing to applications written in C and C++ trivial, but the library can also be used by applications written in Fortran. In particular, the cuBLAS library uses 1-based indexing and Fortran-style column-major storage for multidimensional data to simplify interfacing to Fortran applications. Unfortunately, Fortran-to-C calling conventions are not standardized and differ by platform and toolchain. In particular, differences may exist in the following areas:

- symbol names (capitalization, name decoration)
- argument passing (by value or reference)
- passing of string arguments (length information)
- passing of pointer arguments (size of the pointer)
- returning floating-point or compound data types (for example single-precision or complex data types)

To provide maximum flexibility in addressing those differences, the cuBLAS Fortran interface is provided in the form of wrapper functions and is part of the Toolkit delivery. The C source code of those wrapper functions is located in the **src** directory and provided in two different forms:

- the thunking wrapper interface located in the file fortran_thunking.c
- the direct wrapper interface located in the file fortran.c

The code of one of those 2 files needs to be compiled into an application for it to call the cuBLAS API functions. Providing source code allows users to make any changes necessary for a particular platform and toolchain.

The code in those two C files has been used to demonstrate interoperability with the compilers g77 3.2.3 and g95 0.91 on 32-bit Linux, g77 3.4.5 and g95 0.91 on 64-bit Linux, Intel Fortran 9.0 and Intel Fortran 10.0 on 32-bit and 64-bit Microsoft Windows XP, and g77 3.4.0 and g95 0.92 on Mac OS X.

Note that for g77, use of the compiler flag -fno-second-underscore is required to use these wrappers as provided. Also, the use of the default calling conventions with regard to argument and return value passing is expected. Using the flag -fno-f2c changes the default calling convention with respect to these two items.

The thunking wrappers allow interfacing to existing Fortran applications without any changes to the application. During each call, the wrappers allocate GPU memory, copy source data from CPU memory space to GPU memory space, call cuBLAS, and finally copy back the results to CPU memory space and deallocate the GPU memory. As this process causes very significant call overhead, these wrappers are intended for light testing, not for production code. To use the thunking wrappers, the application needs to be compiled with the file fortran_thunking.c

The direct wrappers, intended for production code, substitute device pointers for vector and matrix arguments in all BLAS functions. To use these interfaces, existing applications need to be modified slightly to allocate and deallocate data structures in GPU memory space (using cuBLAS_ALLOC and cuBLAS_FREE) and to copy data between GPU and CPU memory spaces (using cuBLAS_SET_VECTOR, cuBLAS_GET_VECTOR, cuBLAS_GET_VECTOR, cuBLAS_GET_MATRIX). The sample wrappers provided in fortran.c map device pointers to the OS-dependent type size_t, which is 32-bit wide on 32-bit platforms and 64-bit wide on a 64-bit platforms.

One approach to deal with index arithmetic on device pointers in Fortran code is to use C-style macros, and use the C preprocessor to expand these, as shown in the example below. On Linux and Mac OS X, one way of pre-processing is to use the option '-E -x f77-cpp-input' when using g77 compiler, or simply the option '-cpp' when using g95 or

gfortran. On Windows platforms with Microsoft Visual C/C++, using 'cl -EP' achieves similar results.

```
! Example B.1. Fortran 77 Application Executing on the Host
! -----
   subroutine modify ( m, ldm, n, p, q, alpha, beta )
   implicit none
   integer ldm, n, p, q
real*4 m (ldm, *) , alpha , beta
external cublas_sscal
   call cublas sscal (n-p+1, alpha , m(p,q), ldm)
   call cublas sscal (ldm-p+1, beta, m(p,q), 1)
   end
   program matrixmod
   implicit none
   integer M, N
   parameter (M=6, N=5)
   real*4 a(M,N)
   integer i, j
   external cublas init
   external cublas shutdown
   do j = 1, N
      do i = 1, M
          a(i, j) = (i-1)*M + j
      enddo
   enddo
   call cublas init
   call modify (a, M, N, 2, 3, 16.0, 12.0)
   call cublas shutdown
   do j = 1 , \overline{N}
      do i = 1 , M
           write(*,"(F7.0$)") a(i,j)
      enddo
       write (*,*) ""
   enddo
   stop
```

When traditional fixed-form Fortran 77 code is ported to use the cuBLAS library, line length often increases when the BLAS calls are exchanged for cuBLAS calls. Longer function names and possible macro expansion are contributing factors. Inadvertently exceeding the maximum line length can lead to run-time errors that are difficult to find, so care should be taken not to exceed the 72-column limit if fixed form is retained.

The examples in this chapter show a small application implemented in Fortran 77 on the host and the same application with the non-thunking wrappers after it has been ported to use the cuBLAS library.

The second example should be compiled with ARCH_64 defined as 1 on 64-bit OS system and as 0 on 32-bit OS system. For example for g95 or gfortran, this can be done directly on the command line by using the option '-cpp -DARCH_64=1'.

```
! Example B.2. Same Application Using Non-thunking cuBLAS Calls
#define IDX2F (i,j,ld) ((((j)-1)*(ld))+((i)-1))
    subroutine modify ( devPtrM, ldm, n, p, q, alpha, beta )
    implicit none
   integer sizeof real
   parameter (sizeof real=4)
    integer ldm, n, p, q
#if ARCH 64
    integer*8 devPtrM
    integer*4 devPtrM
#endif
   real*4 alpha, beta
    call cublas sscal ( n-p+1, alpha,
                         devPtrM+IDX2F(p, q, ldm) *sizeof_real,
                         ldm)
    call cublas_sscal(ldm-p+1, beta,
                       devPtrM+IDX2F(p, q, ldm)*sizeof real,
                       1)
   return
    end
    program matrixmod
    implicit none
    integer M, N, sizeof real
#if ARCH 64
    integer*8 devPtrA
#else
    integer*4 devPtrA
#endif
    parameter(M=6, N=5, sizeof real=4)
   real*4 a(M,N)
    integer i,j,stat
    external cublas_init, cublas_set_matrix, cublas_get_matrix
    external cublas_shutdown, cublas_alloc
    integer cublas alloc, cublas set matrix, cublas get matrix
    do j=1,N
        do i=1, M
            a(i,j) = (i-1)*M+j
        enddo
    enddo
    call cublas init
    stat= cublas alloc(M*N, sizeof_real, devPtrA)
    if (stat.NE.0) then
        write(*,*) "device memory allocation failed"
        call cublas shutdown
        stop
    endif
    stat = cublas_set_matrix(M,N,sizeof_real,a,M,devPtrA,M)
    if (stat.NE.0) then
        call cublas_free( devPtrA )
write(*,*) "data download failed"
        call cublas shutdown
        stop
    endif
    call modify(devPtrA, M, N, 2, 3, 16.0, 12.0)
    stat = cublas get matrix(M, N, sizeof real, devPtrA, M, a, M)
    if (stat.NE.0) then
    call cublas_free ( devPtrA )
write(*,*) "data upload failed"
    call cublas shutdown
    stop
    endif
    call cublas_free ( devPtrA )
    call cublas shutdown
    do j = 1 , N
        do i = 1 , M
            write (*,"(F7.0\$)") a(i,j)
        enddo
        write (*,*) ""
```

Appendix C. ACKNOWLEDGEMENTS

NVIDIA would like to thank the following individuals and institutions for their contributions:

- ▶ Portions of the SGEMM, DGEMM, CGEMM and ZGEMM library routines were written by Vasily Volkov of the University of California.
- ▶ Portions of the SGEMM, DGEMM and ZGEMM library routines were written by Davide Barbieri of the University of Rome Tor Vergata.
- ▶ Portions of the DGEMM and SGEMM library routines optimized for Fermi architecture were developed by the University of Tennessee. Subsequently, several other routines that are optimized for the Fermi architecture have been derived from these initial DGEMM and SGEMM implementations.
- ► The substantial optimizations of the STRSV, DTRSV, CTRSV and ZTRSV library routines were developed by Jonathan Hogg of The Science and Technology Facilities Council (STFC). Subsequently, some optimizations of the STRSM, DTRSM, CTRSM and ZTRSM have been derived from these TRSV implementations.
- Substantial optimizations of the SYMV and HEMV library routines were developed by Ahmad Abdelfattah, David Keyes and Hatem Ltaief of King Abdullah University of Science and Technology (KAUST).

Notice

ALL NVIDIA DESIGN SPECIFICATIONS, REFERENCE BOARDS, FILES, DRAWINGS, DIAGNOSTICS, LISTS, AND OTHER DOCUMENTS (TOGETHER AND SEPARATELY, "MATERIALS") ARE BEING PROVIDED "AS IS." NVIDIA MAKES NO WARRANTIES, EXPRESSED, IMPLIED, STATUTORY, OR OTHERWISE WITH RESPECT TO THE MATERIALS, AND EXPRESSLY DISCLAIMS ALL IMPLIED WARRANTIES OF NONINFRINGEMENT, MERCHANTABILITY, AND FITNESS FOR A PARTICULAR PURPOSE.

Information furnished is believed to be accurate and reliable. However, NVIDIA Corporation assumes no responsibility for the consequences of use of such information or for any infringement of patents or other rights of third parties that may result from its use. No license is granted by implication of otherwise under any patent rights of NVIDIA Corporation. Specifications mentioned in this publication are subject to change without notice. This publication supersedes and replaces all other information previously supplied. NVIDIA Corporation products are not authorized as critical components in life support devices or systems without express written approval of NVIDIA Corporation.

Trademarks

NVIDIA and the NVIDIA logo are trademarks or registered trademarks of NVIDIA Corporation in the U.S. and other countries. Other company and product names may be trademarks of the respective companies with which they are associated.

Copyright

© 2007-2016 NVIDIA Corporation. All rights reserved.

