Potext Developer Guide 0.2.0

Chris Ahlstrom (ahlstromcj@gmail.com)

April 14, 2024



Pseudo-Greek Transliteration

Contents

1	Intr	Introduction 3						
	1.1	Additions to Tinygettext	3					
	1.2	Unused GNU Gettext Features	4					
	1.3	Code Changes	4					
	1.4	Future Work	4					
	1.5	Naming Conventions	5					
	1.6	Home Potext Configuration	6					
2	Potext Usage in Applications 6							
	2.1	Main Module Using Potext	7					
	2.2	Marking a Module for Translation	8					
	2.3	Creating the .po Files	9					
	2.4	Installing the .po Files	10					
3	Pote	ext Architecture	١0					
	3.1		12					
	3.2		13					
	3.3		14					
	3.4		15					
	3.5		16					
	3.6		17					
	3.7	Dictionary Class	17					
	3.8	·	19					
	3.9		19					
	3.10		20					
	3.11	Gettext Module	21					
4	GN	GNU Gettext and Its Potext Replacements 21						
	4.1		22					
	4.2		22					
5	Pote	ext Tests	24					
•	5.1		 25					
	5.2		26					
	5.3		26					
	5.4		-0 27					
	5.5		 27					
	0.0		- · 27					
			 27					
		· · · · · · · · · · · · · · · · · · ·	- · 28					
		, , , , , , , , , , , , , , , , , , , ,	-0 29					
		9	29					
		, 0 ,	- 0 30					
		v	30					
			30					
			30					

6	Sun	nmary	30							
7	7 References									
\mathbf{L}^{i}	List of Figures									
	1	Potext "Big Picture" Architecture	11							
	2	Log Stream (po::logstream)	12							
	3	Dictionary Manager (po::dictionarymgr)	13							
	4	PO/MO Parser Base (po::pomoparserbase)	14							
	5	PO Parser (po::poparser)	15							
	6	MO Parser (po::moparser)	16							
	7	Binary Data Extractor (po::extractor)	17							
	8	Dictionary (po::dictionary)	18							
	9	Language (po::language)	20							
	10	NLS Bindings (po::nlsbindings)	21							
	11	Getteyt Module (namespace po)	23							

1 Introduction

The potext libraries adopt, refactor, and greatly extend the tinygettext library ([6]). The purpose of that library is to provide a lightweight mechanism to do translations using the Portable Object translation files, *.po, directly. Also incorporated are some elements of the simple-gettext library ([5]) to support handling Machine Object files, *.mo.

The purpose of the *Potext* library is to provide C++ functions that mirror the many functions of gettext, including textdomain(), bind_textdomain(), bind_textdomain_codeset(), gettext(), dgettext(), ngettext(), and others, for translations made via GNU PO files and GNU MO files. In addition, some of the details of tinygettext are wrapped so that, other than marking the text to be translated, the translation setup is done by calling a single function in main().

Our main goal is to make it easy and lightweight to internationalize an application while sticking with *GNU Gettext* conventions. The *GNU Gettext* manual ([2]) is an important resource used in writing *Potext*. Also important is the source code at savannah.gnu.org ([1]).

Note that *Potext* requires the usage of C++17 and above. It support builds using the *GNU* and *Clang* compilers. It also requires the use of *Meson 1.1* and above. See the INSTALL file. *Windows* support (apart from *Mingw* and *Cygwin* will be provided, but it is not ready yet.

1.1 Additions to Tinygettext

- Re-implementations of gettext/libintl functions as a module (collection of functions) in the po namespace.
- Integration of the functions above with the dictionary-manager class.
- Support for selecting a domain during the run.
- Support for selecting a .po/.mo file directly and getting domain information from it.

- A new class, nlsbindings, to supplement the language class.
- Full documentation of architecture and usage.
- Meson .wrap files to use Potext as a subproject. A sample application project is stored in the tar-file noted below.
- With version 0.2, Potext can also read GNU .mo files for more complete compatibility with GNU Gettext.
- Additional test programs, test .po files, test .mo files, and upgrades to existing tests.

With these additions, *Potext* should be relatively straightforward to use in a new C++ application. The tar-ball extras/code/mini-potext-test.tar.xz contains a simple application using *Potext* as a sub-project stored in *GitHub*. Unpack the tar-ball into its own directory and build it by running its work.sh script.

1.2 Unused GNU Gettext Features

For ease of use, some features of GNU Gettext are not implemented:

- Thread locks in gettext()-like functions; locking can be added if testing reveals it necessary for the use-cases that *Potext* supports.
- Determining if the binary is running SUID root.
- All kinds of C macros to choose build options.
- Detecting changes to localization and character conversion environment variables.

Currently *Potext* is meant to be set up once at the start of the run of an application. It assumes that once the setup is made, no localization changes will be made. Keeps it simple.

1.3 Code Changes

- Changed the coding style and naming conventions for (perhaps) easier reading.
- Use of initializer lists, rather than brute-force assignment statements, for initializing various containers.
- Use of the auto keyword in declarations and for-loops.
- Many additional using directives, most hidden in the po namespace or in a class declaration.
- A few additional helper classes have been added to provide new features.

These changes are meant to make the code easier to read, understand, and modify.

1.4 Future Work

- Hammer on this code in Windows.
- Work out the installation process; including .po and .mo file installation and copying (if desired) to the user's configuration directory. Add support to assist a *Potext*-using project with the installation of the .po files.

- Handle capitals, punctuation, etc. without additional .po/.mo entries.
- Get the handling of categories (e.g. LC_TIME) to work. However, note that the category is almost always LC_MESSAGES, so this is a low priority.
- Allow for the user to override the character set via the OUTPUT_CHARSET environment variable.
- Analyze the translation file to determine if the actual character-set matches the specified character-set.
- Support the "//IGNORE" and "//TRANSLIT" flags for character-set conversions.
- Handle the "C" locale as discussed below.

Ignore LANGUAGE and its system-dependent analog if the locale is set to "C" because:

- 1. "C" locale uses the ASCII encoding; most international messages use non-ASCII characters, which get displayed as question marks or as invalid 8-bit characters.
- 2. The precise output of some programs in the "C" locale is specified by POSIX and should not depend on environment variables like LANGUAGE. Such programs can use gettext().

Also ignore LANGUAGE and its system-dependent analog if the locale is C.UTF-8 or C.<encoding>; that's the by-design behaviour for glibc, see https://sourceware.org/glibc/wiki/Proposals/C.UTF-8. Also look in /usr/lib/locale/C.utf8.

1.5 Naming Conventions

Potext uses some conventions for naming things in this document.

- **\$prefix**. The base location for installation of the application and its ancillary data files on *UNIX/Linux/BSD*:
 - /usr/
 - /usr/local/
- \$winprefix. The base location for installation of the application and its ancillary data files on Windows.
 - C:/Program Files/
 - C:/Program Files (x86)/
- \$podir. The installed location of the *.po files. The directory share (Linux) or data (Windows), the package-name of the application (PACKAGE), and po are concatenated, and again the conventions differ between operating systems.
 - /usr/share/PACKAGE/po/
 - /usr/local/share/PACKAGE/po/
 - C:/Program Files/PACKAGE/data/po/
 - C:/Program Files (x86)/PACKAGE/data/po/
- \$home. The alternate installed location of the *.po files. Not to be confused with \$HOME, this is the standard location for configuration files. On a UNIX-style system, it would be \$HOME/.config/appname. The files would be put into a po subdirectory here.
- \$localedir. The installed location of the *.mo files. The directory share (Linux) or data (Windows), the package-name of the application (PACKAGE), and locale are concatenated. The conventions for Linux versus Windows differ as a matter of historical interest:

- /usr/share/PACKAGE/locale/
- /usr/local/share/PACKAGE/locale/
- C:/Program Files/PACKAGE/data/locale/
- C:/Program Files (x86)/PACKAGE/data/locale/

At present, Potext does not support directories of .mo files. It might, in the future.

- \$modir and LC_MESSAGES. A more common convention for *.mo files on UNIX is to put them in
 - /usr/share/locale/<language>/LC_MESSAGES/PACKAGE.mo
 - /usr/local/share/locale/<language>/LC_MESSAGES/PACKAGE.mo.

Currently, the *Potext* library uses only the *.po files. In the future it might also handle *.mo files. Also note that various applications differ in the exact location of their translation files.

1.6 Home Potext Configuration

The *Potext* library also supports installing the *.po and *.mo translation files in the user's configuration area. The conventions we use are:

- \$home. The location where PACKAGE installs, creates, or copies its configuration files. Do not confuse it with \$HOME, although \$home is in \$HOME/.config/PACKAGE. The *.po files are stored in \$HOME/.config/PACKAGE/po.
- \$winhome. This location is different for Windows: C:/Users/user/AppData/Local/PACKAGE. Again, the *.po files are in a subdirectory called po, and the *.mo files are in a subdirectory called mo. or locale.

We are still working out details of how best to manage translations for an application.

Also, for reference, we mention some of the files used by GNU Gettext.

- PACKAGE.pot, created by xgettext.
- LANG.po, created by msgmerge, copying PACKAGE.pot, or by editing.
- LANG.gmo, created by msgfmt.
- For installed packages, see \$prefix/locale/LANG/PACKAGE.mo.
- Or see \$prefix/locale-langpack. LC_category (e.g. LC_NUMERIC).
- LANG/PACKAGE.po, reverse engineered from PACKAGE.mo by msgunfmt.

Also refer to the Python packages polib ([4]) and poedit ([3]).

2 Potext Usage in Applications

This section briefly covers the usage of *Potext* in an application. A real sample is included in library/tests/hellopotext.cpp (see section 5.2 "Hello Potext" on page 26). A small sample application showing the usage of *Potext* as a *Meson subproject* in a completely separate application project is contained in:

```
extras/code/mini-potext-test.tar.xz
```

Unpack this file in its own directory and check it out.

2.1 Main Module Using Potext

The first thing is to add the following header file to the module defining the main() function.

```
#include "po/potext.hpp" // includes "po/gettext.hpp"
```

For clarity, potext.hpp is better, but it does include an extra header file.

If *Potext* support is optional for the project, then do something like this; PROJECT_USE_POTEXT is a macro optionally defined when configuring the project build.

```
#if defined PROJECT_USE_POTEXT
#include "po/potext.hpp" // includes "po/gettext.hpp"
else
#define _(str) (str)
#define N_(str) str
#endif
```

An application using "gettext" internationalization generally needs to call setlocale(), textdomain(), and bindtextdomain(). The following function declared in the gettext.hpp header file wraps up these functions in one call.

```
std::string init_app_locale
(
    const std::string & arg0,
    const std::string & pkgname,
    const std::string & domainname,
    const std::string & dirname,
    const std::wstring & wdirname = L"",
    int category = (-1)
)
```

arg0. The path-name by which the program was called. This information can determine more precisely where installed .po files might be stored.

pkgname. The name of the PACKAGE, which can be the short name for the program, such as "helloworld".

domainname. The base name of a message catalog, such as "en_US". It must consist of characters legal in filenames. An application might want to use its package name, such as "helloworld", for the domain name. If empty, then the environment variable TEXTDOMAIN is used. If that's empty, then LC_ALL is used. If that's empty, then LC_MESSAGE is used. Lastly, if that's empty, then LANG is used.

dirname. Provides the name of the LOCALEDIR. The standard search directory is /user/share/locale. If empty, then the environment variable TEXTDOMAINDIR is used. If the name is "user", then the .po files are searched for in /home/user/.config/package/ or C:/Users/user/AppData/Local, instead of some place in the system.

wdirname. The wide-string version of the locale directory name, most useful in Windows. The use of the wide-string parameter is optional, and not well tested yet.

category. The area that is covered, such as LC_ALL, LC_MONETARY, and LC_NUMERIC. The default value selects LC_ALL.

The following calls are made for the setup:

- 1. std::setlocale() sets the application's current category and locale. The category is LC_ALL by default, and the locale is empty, so that the locale parts are modified according to environment variables.
- 2. po::set_locale_info() sets up the domain name and the locale directory name. If empty, the environment variables discussed above are used. In addition, it is determined if the locale directory is a system directory, the user's configuration directory, or some arbitrary directory containing .po files.
- 3. po::init_lib_locale() first asks the dictionary-manager (see section 3 "Potext Architecture" on page 10) to add all of the dictionaries (po files) in that directory to the list of selectable dictionaries, making one of them the default dictionary. Then the reimplementation of the bindtextdomain() is called to create a new domain-to-directory binding, and it is inserted into a container. This container supports looking up the locale directory associated with a domain.
- 4. po::textdomain() This function sets the current domain for the dictionary manager to use.

2.2 Marking a Module for Translation

The basic usage to *Potext* is essentially identical to that of *GNU Gettext*, except that (currently) only .po files are used directly.

Add the following header file.

```
#include "po/potext.hpp" // includes "po/gettext.hpp"
```

Mark each translatable string as usual, using the _() macro:

```
std::string errmsg = _("Unknown system error");
```

That macro hides a call to po::gettext(). Additional "get-text" functions are listed in the table in the following section: section 4.2 "Gettext Module" on page 22.

2.3 Creating the .po Files

After marking the files that will provide translations, they must be processed to extract the marked strings for translation. For example:

```
$ xgettext test_helpers.cpp --keyword="_" --output="es.po"
```

The result is an untranslated template, es.po.

```
# SOME DESCRIPTIVE TITLE.
      # Copyright (C) YEAR THE PACKAGE'S COPYRIGHT HOLDER
      # This file is distributed under the same license as the PACKAGE package.
      # FIRST AUTHOR <EMAIL@ADDRESS>, YEAR.
      #, fuzzy
      msgid ""
      msgstr ""
      "Project-Id-Version: PACKAGE VERSION\n"
      "Report-Msgid-Bugs-To: \n"
      "POT-Creation-Date: 2024-03-20 06:53-0400\n"
      "PO-Revision-Date: YEAR-MO-DA HO:MI+ZONE\n"
      "Last-Translator: FULL NAME <EMAIL@ADDRESS>\n"
      "Language-Team: LANGUAGE <LL@li.org>\n"
      "Language: \n"
      "MIME-Version: 1.0\n"
      "Content-Type: text/plain; charset=CHARSET\n"
      "Content-Transfer-Encoding: 8bit\n"
#: test_helpers.cpp:79
      msgid "output"
      msgstr ""
       . . .
```

The next step is to edit this file appropriately, as in the following snippet:

```
# Mensajes en español para test_helpers.
# Copyright (C) 2024 Potext Software Foundation Inc.
# This file is distributed under the same license as the test_helpers package.
# Chris Ahlstrom <ahlstromcj@gmail.com>, 2024.
msgid ""
msgstr ""
"Project-Id-Version: Potext test_helpers 0.1.0\n"
"Report-Msgid-Bugs-To: ahlstromcj@gmail.com\n"
"POT-Creation-Date: 2023-09-18 22:55+0200\n"
"PO-Revision-Date: 2024-03-20 17:08+0200\n"
"Last-Translator: Google Translate <translate.google.com>\n"
"Language-Team: Spanish <es@tp.org.es>\n"
"Language: es\n"
"MIME-Version: 1.0\n"
"Content-Type: text/plain; charset=UTF-8\n"
"Content-Transfer-Encoding: 8-bit\n"
"X-Bugs: Report translation errors to the Language-Team address.\n"
"Plural-Forms: nplurals=2; plural=(n != 1);\n"
```

```
#: test_helpers.cpp:79
msgid "output"
msgstr "producción"
```

In the project tree, create a po directory and move the .po file to it.

Note that the *GNU Gettext* manual ([2]) (in chapter 6) describes many more facets (heh heh) to the creation and manipulation of .po files.

2.4 Installing the .po Files

The installation process for the project should include installing the .po files. Where to install them in the system, if desired? It does not quite make sense to store them in a place like

```
/usr/local/share/locale/LL/LC\_MESSAGES}
```

because that contains .mo files (and some Qt .qm files!).

We would suggest something like /usr/local/share/po/PACKAGE. We should provide support in *Potext* for that. Once *Potext* supports parsing .mo files, the usual processes and location can be used. Future stuff.

The project, once installed, can also, if desired, copy the relevant language file to the user's configuration directory, /home/user/.config/package/ or C:/Users/user/AppData/Local at the first run, and use it there.

3 Potext Architecture

This section provides a walk-through of the architecture of the *Potext* library. Much of the architecture is similar to *Tinygettext* ([6]), but there are some important changes and additions. Some notes about the classes and documentation:

- All classes and free functions are wrapped in the po namespace.
- The macro _() that normally wraps *GNU* function gettext() here wraps the *Potext* function po::gettext().
- The related "gettext" functions are redefined in terms of *Potext* functions.
- In the diagrams, for the function parameters, we use "std::string", rather than "const std::string &" for brevity in the diagrams.
- Not every attribute or function is described. Some groups of items include <code>_xxxx_</code> to represent a number of similar functions.
- The copy constructors, principal assignment operators, and destructors are not described. See the header files to see if they are default, delete, or defined.

First, the big picture.




Figure 1: Potext "Big Picture" Architecture

The most important part of *Potext* is the dictionary class. It is filled by the po::poparser::parse() function, which takes a .po file and fills a dictionary object with a set of message strings and their translations. It also includes plural forms from the .po file to translate plural messages using "plural" functions. Each dictionary includes the message entries and context entries. For a description of the .po file, see the *GNU Gettext* manual ([2]).

The dictionarymgr class handles one or more dictionaries. It has been augmented to hold a new nlsbindings class toion provided support for bindtextdomain and textdomain, which are not provided by *Tinygettext*.

The dictionarymgr's additional member functions are used to implement the free functions in the gettext module, such as gettext() and dgettext(), etc. The gettext module is an addition to Potext to make it easy to switch from Gettext to Potext.

The language class supports the various parts of a domain name: language, country, modifier, long name, and the long name localized.

Parsing .po files is facilitated by the various file-system classes. Each .po file results in the creation of a dictionary.

The poparser class supports reading and parsing a .po file to create a dictionary. It inherits some common code from the pomoparserbase class.

The moparser class supports reading and parsing a .mo file to create a dictionary. It also inherits

some common code from the pomoparserbase class.

The iconvert class supports converting the translations to another codeset (besides UTF-8) when creating the dictionaries.

The logstream class supports internal error logging, but can also be used by an application.

These classes are discussed in more detail in the following sections.

3.1 Logstream Class

The po::logstream class is a reimplementation of the tinygettext::Log class.

logstream.dia

```
po::logstream

-sm_enable_testing: bool
-sm_test_error: bool
-sm_info_callback: po::logstream::callback
-sm_warning_callback: po::logstream::callback
-sm_error_callback: po::logstream::callback
+logstream(): po::logstream::callback
void (*) (const std::string &)
+info(): std::ostream &
+warning(): std::ostream &
-def_xxxx_callback(str:std::string): void
-callbacks_reset(): void
-get(): std::ostream &
```

logstream.dia

Figure 2: Log Stream (po::logstream)

The po::logstream class provides std::ostream objects for emitting errors, warnings, and information messages. It also provides the ability to set a callback function to change how the messages are emitted. It is used internally for writing status to the console. It can also be used by an application, but ...

... An interesting issue that we have not yet figured out is illustrated by the test application hellopotext. When run, all of the messages written to std::cout appear first, including the final message "SUCCESS". Then all of the messages logged during setup and translation in the *Potext* library appear when hellopotext is exiting.

3.2 Dictionary Manager Class

The po::dictionarymgr class is a reimplementation of the tinygettext::dictionary_manager class. It contains an std::unordered_map of shared pointers to dictionary objects, keyed by language objects which are searched using operator () hash function in a po::langhash structure.

Currently, Potext does not do anything special with the searchpath deque.




Figure 3: Dictionary Manager (po::dictionarymgr)

In *Tinygettext*, the dictionary_manager class coordinated multiple locale directories and the selection of a particular dictionary for a translation.

Potext's dictionarymgr currently handles only one directory, but it adds support for domain-binding and for actually using translation functions that accept a domain parameter. The new functions are

described next.

- get_bindings(). This function returns an nlsbindings class reference that contains a list of domain names with the names of the directory and the character-set for each domain. The nlsbindings class provides the set-binding functions needed by the following new functions.
- add_dictionaries(). This function scans a directory for .po files and creates a dictionary for each one.
- make_dictionary(). This helper function opens a file using the std::filesystem class function open_file. It then creates an std::shared_ptr for a new dictionary and calls the static function po::poparser::parse_po_file(). Then it calls the member function po::nlsbindings::set_binding_values() to create a corresponding binding object.
- textdomain(). This function sets the current domain to the given domain name. It is used in the gettext module to implement the textdomain() function.
- bindtextdomain(). This function associates a domain name with a locale directory in which to find the .po file. It is used in the gettext module to implement the bindtextdomain() function.
- bind_textdomain_codeset(). This function associates a domain name with a characterset to use in converting messages. It is used in the gettext module to implement the bind_textdomain_codeset() function.
- get_dictionary(). This function returns a reference to the current dictionary object. It is used in the gettext module to access the main dictionary to use it in the various gettext-like functions.

3.3 Pomoparserbase Class

As of version 0.2, some common functionality has been moved into this base class.




Figure 4: PO/MO Parser Base (po::pomoparserbase)

For version 0.2, we have moved the file-reading support, dictionary class, and iconvert class into a base class common to the moparser and poparser classes.

Other than that commonality, the two parser class are somewhat different in how they parse, since the .po file is text, and the .mo file is binary.

3.4 Poparser Class

The po::poparser class is a serious reimplementation of the tinygettext::POParser class.




Figure 5: PO Parser (po::poparser)

The poparser "connects" a .po file, an input stream, and a dictionary object in order to populate the dictionary with plural forms, set the character-set, and use it (if needed) to convert the translated message string to the character-set, The static function po::poparser::parse_po_file() is called to create a temporary poparser and use it to read a file and fill in an empty dictionary.

The po::poparser::get_string_line() function handles the main task of parsing a line from the .po file and deciding what to do with it.

The po::poparser::get_msgstr function adds a message (which might be converted to a specified character-set) to the dictionary.

The po::poparser::get_msgid_plural() adds a plural form (see section 3.8 "Pluralforms Class" on page 19) or a contextual translation to the dictionary.

The po::poparser class uses the po::iconvert class to convert the string translation to the desired character-set. The po::iconvert class is a reimplementation of the tinygettext::IConv class. Note that it defines the po::iconv_t type.

3.5 Moparser Class

The po::moparser class is based on pomoparserbase, and adds the ability to parse .mo files. tinygettext::POParser class.




Figure 6: MO Parser (po::moparser)

The moparser "connects" a .mo file, an input stream, and a dictionary object in order to populate the dictionary with plural forms, set the character-set, and use it (if needed) to convert the translated message string to the character-set, The static function po::moparser::parse_mo_file() is called to create a temporary moparser and use it to read a file and fill in an empty dictionary.

The format of the .mo file is described in the moparser module's top banner. The format is dissected and described further in these files:

```
library/tests/mo/es/newt.hex
library/tests/mo/de/helloworld.hex
```

Note the moparser::header structure, which provides the layout of the first few words in the .mo file. Each translation structure holds the "original" message ID, the "original plural" message ID, the context (if specified), the translated singular string, and a list of plural forms (if specified).

The moparser class gets the character-set name and the plural-forms description by searching for

the key strings to find them. It then searches for original singular strings, original plural strings, context strings, and the list of plural translations. These items are stored in a vector of translations, which is later used to populate a dictionary.

The process of the binary data is facilitated by the extractor class discussed in the next section.

3.6 Extractor Class

This new class is used internally in the parsing of .mo files. It encapsulates some tricky binary data extraction so that the moparser class is less complex than otherwise. The binary data is represented by a string, which is loaded by the constructor.




Figure 7: Binary Data Extractor (po::extractor)

For the most part, the data in the string is accessed by position and length. Offsets and pointers for string or character targets can be found using a starting offset, a length, and perhaps a character delimiter such as a newline, null byte, and the EOT (ASCII 4) character.

Note the data types of byte and word, here hidden in the extractor class.

Also included is the offset structure, which is the pair of data items the .mo format uses.

3.7 Dictionary Class

The po::dictionary class is a reimplementation of the tinygettext::Dictionary class.




Figure 8: Dictionary (po::dictionary)

The dictionary class holds a set of conversions of strings to a list of possible conversions, and another set of lists to support various message contexts.

The dictionary contains entries, an std::unordered_map of phrases keyed by a message ID string as used in *GNU* gettext(). A phraselist is simply an std::vector<std::string>.

The dictionary also contains ctxtentries, an std::unordered_map of entries keyed by a context string.

The dictionary also contains a pluralforms object that can be used to look up the proper plural translation. These functions provide the desired lookups:

- translate().
- translate_plural().
- translate_ctxt().
- translate_ctxt_plural().

Note that there are no functions that use the name of a domain as a parameter. Instead, the domain-using functions in the gettext module look up the dictionary associated with the desired domain, and use the appropriate translate function.

A new function <code>create_po_dump()</code> generates a string the is a reasonable representation of a .po file. It can be used to convert a .mo file to a .po file. An example is its usage in the <code>potext_test_list-msgstrs</code> command.

If one does not need this functionality, undefine this macro in the po_build_macros.h header file:

POTEXT_DICTIONARY_CREATE_PO_DUMP

3.8 Pluralforms Class

The po::pluralforms class is a reimplementation of the tinygettext::PluralForms class. Each .po file contains a line describing how the translation of plurals is to be handled for each language:

```
Plural-Forms: nplurals=2; plural=n != 1;
```


The pluralforms class provides a static function for each possible plural form (and there are quite a number of them). These functions are inserted into an std::unordered_map which is keyed by strings like the one shown above. Some of these strings are extremely long. (We could shorten the keys by ignoring the redundant part of the plural-forms string.)

The po::pluralforms::from_string() function strips the spaces from a string parameter and does a fast lookup to return the appropriate pluralforms object.

3.9 Language Class

The po::language class is a reimplementation of the tinygettext::Language class.

The po::languagespec structure is a reimplementation of the tinygettext::LanguageSpec structure. This structure now uses std::string instead of character pointers.



language.dia

Figure 9: Language (po::language)

The language class is a wrapper for a languagespec structure. As shown in the figure, it provides functions to get and set the components of a language specification, to make comparisons, and converted the specification to a string.


The dictionarymgr uses the language as a key to look up the desired dictionary, and if not found, to make a new dictionary and add it to the dictionary container.

We still need to understand a little more about this class and its usage.

3.10 NLS Bindings Class

The nlsbindings class is an addition for the *Potext* library to support adding text-domain functions akin to those in *GNU Gettext*, but wrapped in the po namespace.

nlsbindings.dia



nlsbindings.dia

Figure 10: NLS Bindings (po::nlsbindings)

It provides some simplified implementations of *GNU Gettext* functions that lack such niceties as locking and checking for SUID root applications. These can be added later as the need becomes apparent. For details, see the code in the *GNU Gettext* project in it's gettext-runtime/intl directory.

3.11 Gettext Module

The *Potext* gettext module is discussed in the next section. (See section 4.2 "Gettext Module" on page 22.)

4 GNU Gettext and Its Potext Replacements

This section briefly covers the public functions and macros of *GNU Gettext* and our replacements for them. Here are the main differences:

- All implementations are functions; no macros are used.
- All functions are inside the po namespace.
- All character pointers are replaced by std::string.
- Lookups are done via .po files, at present.
- None of the functions with a "category" parameter are implemented at this time. Those function would seem to need to find an load up another dictionary object. Also, by far the most common translation files on a *UNIX* system are in the LC_MESSAGE subdirectories.

4.1 GNU Gettext Header File

This section provides a walkthrough of the gettext.h header file of the *Potext* library. This is useful in understanding *Gettext* versus *Potext*.

Let us survey the important functions and macros that are used in the gettext.h header file (see /usr/include/libintl.h):

- ENABLE_NLS. If defined in a GNU automake project, this includes the libintl.h header file, which is not needed in an application using the *Potext* library for translation. NLS can be disabled via -disable-nls.
- DEFAULT_TEXT_DOMAIN. If ENABLE_NLS is defined, this macro causes gettext to be defined as dgettext, and ngettext to be defined as dngettext. If ENABLE_NLS is not defined, then the following "functions" are "voided":
 - gettext
 - dgettext
 - dcgettext
 - ngettext
 - dngettext
 - dcngettext
 - textdomain
 - bindtextdomain
 - bind_textdomain_codeset
- DEFAULT_TEXT_DOMAIN revisited. If defined, more macros are defined, for message-context support. These call pgettext_aux or npgettext_aux
 - pgettext
 - dpgettext
 - dcpgettext
 - npgettext
 - dnpgettext
 - dcnpgettext
- GNULIB_defined_setlocal. If defined, uses the rpl_setlocale from gnulib as setlocale.
- gettext_noop. A pseudo function that marks code for extraction of messages, but does not call gettext.
- pgettext_expr. Calls dcpgettext_expr().
- dpgettext_expr. Calls dcnpgettext_expr().

Do we want potext to be a drop-in replacement for all this stuff? We shall try!

4.2 Gettext Module

The gettext module provides a reimplementation of *GNU Gettext* "gettext" functions in the po namespace.

Here, we use the term "module" to describe a set of related functions that are not members of

a class. All functions in this module are in the po namespace, or are static and internal to the module.




Figure 11: Gettext Module (namespace po)

We are slowly implement the various "gettext" functions shown in that figure, plus some others that are not shown. See the next section for a brief discussion of our copy of the GNU Gettext header file.

The following table lists the functions/macros and their purpose and status. The implementations are member functions of po::dictionary or po::dictionarymgr (*); all dictionaries are contained and referenced in po::dictionarymgr, either as the main dictionary or a dictionary selected based on domain. Fall-back functions are noted for some "none" implementations.

Table 1: Gettext Functions

Function	Implementation	Purpose
<pre>textdomain()</pre>	textdomain() *	Set or change the current global domain
bindtextdomain()	bindtextdomain() *	for the LC_MESSAGE category. Set or change the locale directory for the given domain. LC_MESSAGE category. The wide-character UTF-16 version for Windows is not yet implemented.
<pre>bind_textdomain_codeset()</pre>	partial *	Set or change the character-set for the given domain. LC_MESSAGE category.
gettext()	translate()	Single message ID translation.
dgettext()	$\operatorname{translate}(\r)$	Single message ID translation in a specific domain.
<pre>dcgettext()</pre>	none: dgettext()	Single message ID translation in a specific domain and specific language category. For all get-text functions with a category parameter, there is currently no implementation, just a fall-back to the non-category version.
ngettext()	$translate_plural()$	Message ID translation using a specific singular or plural form.
<pre>dngettext()</pre>	$translate_plural()$	Message ID translation using a specific singular or plural form for a given domain.
dcngettext()	$none: \ translate_plural()$	Message ID translation using a specific singular or plural form for a given domain and a given locale category.
pgettext()	${\rm translate_ctxt}()$	Single message ID translation for a given context (e.g. "console" versus "gui". The 'p' stands for 'particular'.
<pre>dpgettext()</pre>	$translate_ctxt()$	Single message ID translation for a given context and the given domain.
<pre>dpcgettext()</pre>	none: dpgettext()	Single message ID translation for a given context, given domain, and category other than LC_Messages.
npggettext()	no	Probaby worth doing.
dnpggettext()	no	Probaby worth doing.
dcnpggettext()	no	Probaby not worth doing.

5 Potext Tests

This section provides a useful walkthrough of the testing of the *potext* library. They illustrate the various way in which the *Potext* library can be used by a developer.

These tests are not installed; they are in the transitory directory potext/build/library/tests. The test *.po files are in the directory potext/library/tests and its subdirectories. The shell script library/tests/tests.sh runs all of the potext_test tests listed in the following file, plus a couple more.

library/tests/testlines.list

It specifies the tests described here, but using only single-word phrases. The reason is that we have not yet figured out how to deal with phrases enclosed in double-quotes in a shell script.

Let us survey the main features of all of the test po files:

- po directory. This directory contains a small sampling of .po files from the *GNU Gettext* project. They have been pared down a bit just to save a few bytes, and a few extra translations have bee added for testing. They are used in the new hellopotext test program to test the functions in the gettext C++ module.
- library/tests/de.po. A basic po file with just msgid keys and msgstr translations in Deutsche (German, Alemania).
- library/tests/broken.po. This file has an entry msgstr[10], obviously bad.
- library/tests/helloworld/de.po. It has some msgctxt sections with msgid_plural, msgstr[0] for a singular translation and msgstr[1] for a plural translation for each context (none, "gui", and "console").
- library/tests/level/de.po. Contains basic entries plus a number of entries with a blank message-ID followed by a long description and a message-string with a blank value followed by a long translation. NEED TO FIGURE THAT OUT. Also includes a couple of printf() format statements.
- library/tests/po/de.po. Another basic file with a number of translations and a weird message-ID called "umlaut".
- library/tests/po/de_AT.po. A short file with "umlaut" and a couple of plurals.
- library/tests/po/fr.po. Contains one German translation. Wtf?

One thing to watch for in running the tests. The test programs write output to std::cout or std::cerr, while the *Potext* library internals use the po::logstream class functions. What happen is the all of the application output comes first, while the log-stream message are not emitted until test program exit. Not sure why the latter aren't "flushed" immediately.

Here are the tests provided:

- helloworld
- hellopotext
- po_parser_test
- mo_parser_test
- potext_test

The code is in the library/tests directory, and the executables are written to build/library/tests directory.

5.1 Hello World

helloworld. This test is the original from the tinygettext project. Not much done with it; it includes a copy of the gettext.h header file and calls some of the stock GNU Gettext functions.

5.2 Hello Potext

hellopotext. This application is a good test of *potext* from the perspective of a developer wanting to use it in an application. Without arguments, this test runs through basic tests of the following functions. The main domain is provided to po::init_app_locale() which should normally be called in the applications's main() entry point function.

- _() and gettext(). This function does a message translation lookup using the current domain, which is logged in the init_app_locale() function. This smoke test illustrates the most common case we want to cover, which is the translation of a phrase according to the main (or only) domain and locale directory loaded. Also included is a test where the original message is not present in the .po file.
- dgettext. This function looks up a domain's dictionary and uses it for the translation. This test runs through all of the domains (i.e. .po files) in the po project directory. Currently tested are the es, fr, de, and a bogus domain named xx, which should just return the input message ID.
- dcgettext. This test does not do anything. Currently *Potext* does not handle locale categories. The reasons? First, the most common use case is looking up message translations in the LC_MESSAGES locale category. Second, this translation would require loading additional locale directories and their dictionaries. With this complication, we will sit on this problem for awhile.
- ngettext. This test handles plural forms in the current domain. It deals only the main domain, es, It tests translating the plurals of the following singulars: "File" and "Person". The translations are likely not accurate, as they were provided by *Google Translate*. But they adequately test the process.
- dngettext. This test handles plural forms in a specified domain. Currently tested are the es, fr, de, and a bogus domain named xx, which should just return the input message ID.
- dcngettext. This function is not yet implemented, due to difficulties with selecting the category directory, as discussed above.
- pgettext. This test applies only to the domain specified in the init_app_locale() function.

Some functions not yet tested because of the implementation difficulties noted above.

- dcgettext().
- dcngettext().

Additional arguments can change the default domain. We will document these real soon now.

5.3 PO Parser Test

po_parser_test This small application tests the ability to parse some sample .mo files.

To run this test, simply supply the name of a .po file and examine the results. Any .po file can be provided.

Without arguments, this application lists some options and stock test .po files to run.

5.4 MO Parser Test

mo_parser_test This small application tests the ability to parse some sample .mo files.

To run this test, simply supply the name of a .mo file and examine the results. Any .mo file can be provided.

Without arguments, this application lists some options and stock test .mo files to run.

In progress. We need to add some more files to be able to test all of the most important aspects of .mo files.

5.5 Potext Test

potext_test This application is another good test of *potext* from the perspective of a developer wanting to use it in an application. Running it without any arguments shows a list of 8 tests. These tests are run by supplying the appropriate command-line arguments. These are reflected in the following sections.

5.5.1 Potext Test 'Translate'

These tests are run using a command like the following:

```
$ ./build/library/tests/potext_test translate <...options...>
```

By running potext_test without any options, one sees four "translate" commands. The four variations on the "translate" test are described in the following sub-sections.

5.5.1.1 Translate Basic: Po File and Sample Message

This test is a simple translation of a word. The basic "translate" test is run by the following form, which has an argument count of 4.

\$./build/library/tests/potext_test translate <file> <msg>

The file is a test .po file in the tests directory. The message is a phrase present in that file, such as "F1 - show/hide this help screen", translated in de.po as "F1 - Hilfe anzeigen/verstecken".

Here is the run:

\$./build/library/tests/potext_test translate \
library/tests/de.po "F1 - show/hide this help screen"

The output is

```
Translation: "F1 - Hilfe anzeigen/verstecken"
```

If only a part of the message is provided, of course there is no match, and the message is

```
Translation: "F1 - Hilfe"
[potext] Couldn't translate: "F1 - Hilfe"
```

This second test shows that any deviation from a supported message causes an warning, and returns the original message. These deviations include missing letters, missing punctuation, additional spaces. We wonder if we can work around such issues in this library. We shall see.

5.5.1.2 Translate: Po File, Context, and Sample Message

This test is run by the following form, which has an argument count of 5.

```
$ ./build/library/tests/potext_test translate <file> <context> <msg>
```

This test requires a po file with message-context entries such as these three different entries found in library/test/helloworld/de.po for the phrase "Hello World":

```
msgctxt ""
msgid "Hello World"
msgctxt "console"
msgid "Hello World"
msgctxt "gui"
msgid "Hello World"
```

Please note that the *GNU* gettext() documentation says that an empty message context (msgctxt "") is not the same as a missing message context. In the "helloworld" test program, these contexts are provided by the following lines:

```
pgettext("", "Hello World")
pgettext("console", "Hello World")
pgettext("gui", "Hello World")
```

The macros ngettext and npgettext are also used to provide access to the various plural forms in that po file. In any case, we need to use library/test/helloworld/de.po for this test. An actual test run:

The output is

```
Context 'console' translation: "Hallo Welt (singular) in der Console"
```

If the **<context>** parameter is not found in the **po** file, a message is emitted to indicate the error.

5.5.1.3 Translate: Po File with Singular and Plurals

This test is run by the following form, which has an argument count of 6.

The singular and plural parameters are message IDs, such as "Hello World". This command is a bit tricky; the N value is not a C index, but an index that starts at 1. The N parameter ranges from 1 to the last array value in the po file. The number of singular/plural translations depends on the language and is specified in the specific .po file using a header declaration such as "Plural-Forms: nplurals=2; plural=(n != 1);". Look at pluralforms.cpp to see all the plural-forms settings and "callbacks" that are support. Some of these forms support Slavic and Arabic languages, and we are not able to test them.

An actual test run:

The output is

TODO

5.5.1.4 Translate: Po File with Context, Singular, and Plurals

This test is run by the following form, which has an argument count of 7.

An actual test run:

The output is

TODO

5.5.2 Potext Test 'Directory'

These tests are run using a command like the following:

\$./build/library/tests/potext_test directory <dir> <msg> [<lang>]

5.5.3 Potext Test 'Language'

These tests are run using a command like the following:

\$./build/library/tests/potext_test language <lang>

5.5.4 Potext Test 'Language Directory'

These tests are run using a command like the following:

\$./build/library/tests/potext_test language-dir <dir>

5.5.5 Potext Test 'List Message Strings'

These tests are run using a command like the following:

\$./build/library/tests/potext_test list-msgstrs <file>

The "file" parameter can be a .po file or a .mo file. This test takes the dictionary read in from that file and basically writes a .po file to the console.

6 Summary

Contact: If you have ideas about *Potext* or a bug report, please email us (at mailto:ahlstromcj@gmail.com).

Remaining issues:

The *.po files "msgid" and "msgstr" entries have punctuation marks and trailing spaces that are significant. CAN WE GET AROUND THIS ISSUE? We need to trim these trailing characters in both specifications, and also when translating, and restore them in the translation.

7 References

The *Potext* reference list.

References

- [1] GNU Translation Team. GNU Gettext Code https://git.savannah.gnu.org/git/gettext.git. 2023.
- [2] GNU Translation Team. GNU Gettext Tools manual, version 0.22. https://www.gnu.org/software/gettext/manual/gettext.pdf. 2023.
- [3] Poedit Team. Gettext translation for PHP, Python, etc. https://poedit.net/. 2023.
- [4] Polib Team. Gettext file creation, manipulation, etc. for Python https://pypi.org/project/polib/. 2023.
- [5] Laurent Cozic Simple Gettext on GitHub. https://github.com/laurent22/simple-gettext. 2017.
- [6] Tinygettext Team. Tinygettext on GitHub. https://github.com/tinygettext/tinygettext. 2023