

Seq66 User Manual 0.92.0

Chris Ahlstrom
(ahlstromcj@gmail.com)

February 7, 2021



Button-Grid User Interface, Qt 5

Contents

1	Introduction	8
1.1	Seq66: What?	9
1.2	Seq66: Why?	9
1.3	Improvements	9
1.4	Document Structure	9
1.5	Let's Go!	9
1.5.1	Main Top Controls (Condensed View)	11
1.5.1.1	PPQN Selection	11
1.5.1.2	Set's Buss Override	11
1.5.1.3	Global Beats Per Measure	12
1.5.1.4	Global Beat Width	12
1.5.1.5	BBT or HMS Time Display	12
1.5.1.6	Beat Indicator	12
1.5.2	Main Bottom Controls, First Row	12
1.5.2.1	Set Name	12
1.5.2.2	Set Master Button	12
1.5.2.3	Active Set Indicator	12
1.5.2.4	Set Changer	13
1.5.3	Main Bottom Controls, Second Row	13
1.5.3.1	Panic Button	13
1.5.3.2	Stop Button	13
1.5.3.3	Pause Button	13
1.5.3.4	Play Button	14
1.5.3.5	Live Record Button	14
1.5.3.6	Keep Queue Button	14
1.5.3.7	Mute Group Learn Button	14
1.5.3.8	Developer Test Button	14
1.5.3.9	Song Editor Button	15
1.5.3.10	Live/Song Mode Button	15
1.5.3.11	PPQN Indicator	15
1.5.3.12	BBT/HMS Toggle Button	15
1.5.3.13	Tap BPM Button	15
1.5.3.14	Beats Per Minute Control	15
2	Menu	15
2.1	Menu / File	16
2.2	Menu / File / New	16
2.2.1	Menu / File / Open	16
2.2.2	Menu / File / Open Playlist	17
2.2.3	Menu / File / Recent MIDI files	17
2.2.4	Menu / File / Save and Save As	18
2.2.5	Menu / File / Import MIDI	19
2.2.6	Menu / File / Export Song as MIDI	19
2.2.7	Menu / File / Export MIDI Only	20
2.3	Menu / Edit	20
2.3.1	Menu / Edit / Preferences	21

2.3.1.1	Menu / Edit / Preferences / MIDI Clock	21
2.3.1.2	Menu / Edit / Preferences / MIDI Input	24
2.3.1.3	Menu / Edit / Preferences / Keyboard (Removed)	25
2.3.1.4	Menu / Edit / Preferences / Mouse (Removed)	25
2.3.1.5	Menu / Edit / Preferences / Display	25
2.3.1.6	Menu / Edit / Preferences / JACK	26
2.3.1.7	Menu / Edit / Preferences / Play Options	27
2.4	Menu / Help / About...	27
2.5	Menu / Help / Build Info...	28
3	Patterns Panel	28
3.1	Patterns / Set Handling	28
3.2	Patterns / Main Panel	28
3.2.1	Pattern Slot	30
3.2.2	Pattern	31
3.2.3	Pattern Keys and Click	34
3.2.3.1	Pattern Keys	34
3.2.3.2	Pattern Clicks	37
3.3	Patterns / Bottom Panel	37
3.4	Patterns / Multiple Panels	38
3.5	Patterns / Variable Set Size	38
4	Pattern Editor	39
4.1	Pattern Editor / First Row	41
4.2	Pattern Editor / Second Row	42
4.3	Pattern Editor / Piano Roll	45
4.3.1	Pattern Editor / Piano Roll Items	46
4.3.2	Pattern Editor / Note Painting	46
4.3.3	Pattern Editor / Note Editing	47
4.3.4	Pattern Editor / Zoom Keys	48
4.4	Events Editor	49
4.5	Data View	49
4.6	Pattern Editor / Bottom Row	50
4.7	Pattern Editor / Common Actions	53
4.7.1	Pattern Editor / Common Actions / Scrolling	53
4.7.2	Pattern Editor / Common Actions / Close	54
5	Song Editor	54
5.1	Song Editor / Top Panel	55
5.2	Song Editor / Measures Ruler	57
5.3	Song Editor / Patterns (Names) Panel	57
5.4	Song Editor / Song Roll	58
5.4.1	Song Editor / Song Roll / Layout	58
5.4.2	Song Editor / Song Roll / Keystrokes	59
5.5	Song Editor / Bottom Panel	60

6 Event Editor	60
6.1 Event Editor / Event Frame	61
6.1.1 Event Frame / Data Items	62
6.1.2 Event Frame / Navigation	63
6.2 Event Editor / Info Panel	63
6.3 Event Editor / Edit Fields	63
6.4 Event Editor / Bottom Buttons	64
7 Seq66 Session Management	65
7.1 Seq66 Session Management / NSM	65
7.1.1 Seq66 Session Management / NSM / First Run Without NSM	66
7.1.2 Seq66 Session Management / NSM / Run in NSM	67
7.1.3 Seq66 Session Management / NSM / Run with Remote NSM	68
7.1.4 Seq66 Session Management / Sessions Tab	69
7.1.5 Seq66 Session Management / File Menu	70
7.2 Seq66 Session Management / Signals	72
7.3 Seq66 Session Management / LASH	72
8 Import/Export	72
8.1 Import MIDI	72
8.2 Export Song as MIDI	73
8.3 Export MIDI Only	73
9 Seq66 Keyboard and Mouse Actions	73
9.1 Keyboard Control	74
9.2 Main Window	76
9.3 Performance Editor Window	77
9.3.1 Performance Editor Piano Roll	77
9.3.2 Performance Editor Time Section	78
9.3.3 Performance Editor Names Section	79
9.4 Pattern Editor	79
9.4.1 Pattern Editor Piano Roll	79
9.4.2 Pattern Editor Event Panel	80
9.4.3 Pattern Editor Data Panel	81
9.4.4 Pattern Editor Virtual Keyboard	81
9.5 Event Editor	81
10 Seq66 JACK Support	81
10.1 Seq66 JACK Transport	82
10.2 Seq66 Native JACK MIDI	82
10.2.1 Seq66 JACK MIDI Output	82
10.2.2 Seq66 JACK MIDI Input	83
10.2.3 Seq66 JACK MIDI Virtual Ports	83
10.2.4 Seq66 JACK MIDI and a2jmidid	83
11 Port Mapping	84
11.1 Output Port Mapping	84
11.2 Input Port Mapping	85

12 Seq66 Configuration	86
12.1 Configuration File Commonalities	87
12.1.1 [Seq66] Section	88
12.1.2 [comments] Section	88
12.1.3 Numeric Settings	88
12.1.4 Boolean Settings	88
12.1.5 Variables	88
12.1.6 Stanzas	89
12.2 Command Line	89
12.3 'rc' File	91
12.3.1 'rc' File / MIDI Control	91
12.3.2 'rc' File / Mute Groups	92
12.3.3 'rc' File / Color Palette	92
12.3.4 'rc' File / Note Mapper	92
12.3.5 'rc' File / MIDI-Clock Section	92
12.3.6 'rc' File / MIDI Clock Mod Ticks	93
12.3.7 'rc' File / MIDI-Meta-Events Section	93
12.3.8 'rc' File / Keyboard Control Section	93
12.3.9 'rc' File / JACK Transport	93
12.3.10 'rc' File / MIDI Input	94
12.3.11 'rc' File / Manual ALSA Ports	94
12.3.12 'rc' File / Reveal ALSA Ports	95
12.3.13 'rc' File / Interaction Method	95
12.3.14 'rc' File / Auto Option Save	95
12.3.15 'rc' File / Last Used Directory	96
12.3.16 'rc' File / Recent Files	96
12.3.17 'rc' File / Play-List	96
12.4 'usr' File	96
12.4.1 'usr' File / MIDI Bus Definitions	99
12.4.2 'usr' File / MIDI Instrument Definitions	100
12.4.3 'usr' File / User Interface Settings	101
12.4.4 'usr' File / User MIDI Settings	102
12.4.5 'usr' File / User Options	102
12.5 'ctrl' File	103
12.5.1 'ctrl' File / MIDI Control Settings	103
12.5.2 'ctrl' File / Loop Control	103
12.5.3 'ctrl' File / Mute-Group Control	105
12.5.4 'ctrl' File / Automation Control	105
12.5.4.1 Automation / BPM Up and Down	105
12.5.4.2 Automation / Screen-Set Up and Down	105
12.5.4.3 Automation / Mod Replace	105
12.5.4.4 Automation / Mod Snapshot	106
12.5.4.5 Automation / Mod Queue	106
12.5.4.6 Automation / Mute Group	106
12.5.4.7 Automation / Screen-Set Play	106
12.5.5 Automation / More MIDI Control	106
12.5.6 'ctrl' File / MIDI Control Output	107
12.6 'mutes' File	108

12.7 'drums' File	108
12.8 'palette' File	109
12.9 'playlist' File	109
13 Seq66 Play-Lists	109
13.1 Seq66 Play-Lists / 'playlist' File Format	109
13.2 Seq66 Play-Lists / 'rc' File	111
13.3 Seq66 Play-Lists / 'ctrl' File / [midi-control]	111
13.4 Seq66 Play-Lists / Command Line Invocation	111
13.5 Seq66 Play-Lists / Verification	112
13.6 Seq66 Play-Lists / User Interface	112
13.6.0.1 Seq66 Play-Lists / User Interfaces / Playlist Buttons	114
13.6.0.2 Seq66 Play-Lists / User Interfaces / Info Fields	115
14 Seq66 Set Master	115
15 Seq66 Mutes Master	116
16 Palettes for Coloring	118
16.1 Palettes Setup	118
16.1.1 Palettes Setup / Pattern	119
16.1.2 Palettes Setup / Ui and Inverse Ui	119
16.1.3 Palettes Setup / Brushes	119
16.2 Palettes Summary	120
17 Seq66 Headless Version	120
17.1 Seq66 Headless Setup	120
18 Launchpad Mini	122
18.1 Launchpad Mini Basics	122
18.2 System Survey, ALSA	124
18.3 Control Setup	124
18.3.1 Input Control Setup	124
18.3.1.1 [loop-control]	125
18.3.1.2 [mute-group-control]	125
18.3.1.3 [automation-control]	125
18.3.2 Output Control Setup	126
18.3.2.1 [midi-control-out]	126
18.3.2.2 [mute-control-out]	126
18.3.2.3 [automation-control-out]	127
18.4 Test Run, ALSA	127
18.5 System Survey, JACK	128
19 Concepts	129
19.1 Concepts / Terms	129
19.1.1 Concepts / Terms / loop, pattern, track, sequence	130
19.1.2 Concepts / Terms / armed, muted	130
19.1.3 Concepts / Terms / bank, screenset	130
19.1.4 Concepts / Terms / buss, bus, port	130

19.1.5 Concepts / Terms / performance, song, trigger	130
19.1.6 Concepts / Terms / export	131
19.1.7 Concepts / Terms / group, mute-group	131
19.1.8 Concepts / Terms / PPQN, pulses ticks, clocks, divisions	131
19.1.9 Concepts / Terms / queue, keep queue, snapshot, one-shot	131
19.2 Concepts / Sound Subsystems	132
19.2.1 Concepts / Sound Subsystems / ALSA	132
19.2.2 Concepts / Sound Subsystems / PortMIDI	132
19.2.3 Concepts / Sound Subsystems / JACK	132
20 MIDI Format and Other MIDI Notes	132
20.1 Standard MIDI Format 0	132
20.2 Proprietary Track Format	133
20.3 MIDI Information	134
20.3.1 MIDI Variable-Length Value	135
20.3.2 MIDI Track Chunk	135
20.3.3 MIDI Meta Events	135
20.4 More MIDI Information	135
20.4.1 MIDI File Header, MThd	136
20.4.2 MIDI Track, MTrk	137
20.4.3 Channel Events	137
20.4.4 Meta Events Revisited	138
20.5 Meta Events	138
20.5.1 Sequence Number (0x00)	139
20.5.2 Track/Sequence Name (0x03)	139
20.5.3 End of Track (0x2F)	139
20.5.4 Set Tempo Event (0x51)	139
20.5.5 Time Signature Event (0x58)	140
20.5.6 SysEx Event (0xF0)	141
20.5.7 Sequencer Specific (0x7F)	141
20.5.8 Non-Specific End of Sequence	142
21 Kudos	142
22 Summary	143
23 References	144

List of Figures

1 Seq66 Main Screen	10
2 Main Screen Controls	11
3 Seq66 Menu File Items	16
4 File / Open	17
5 File / Open Playlist	17
6 Seq66 Menu File Recent Files	18
7 File / Save As	19
8 MIDI Clock Tab, ALSA Devices	22

9	MIDI Input, ALSA View	24
10	Display Options	25
11	File / Options / JACK	26
12	Patterns Panel Pop-up Menu	29
13	External Pattern Editor Window	39
14	Pattern Editor Window, Annotated	41
15	Virtual Keyboard Number and Note Views	46
16	Pattern Editor Event Button Context Menu	51
17	Pattern Editor LFO	52
18	Song Editor Window, Annotated	55
19	Event Editor Window	61
20	MIDI File Unexportable	73
21	JACK MIDI Ports and Auto-Connect	82
22	Seq66 Composite View of Native Devices	97
23	Seq66 Composite View of Devices As Set in "sample.usr"	101
24	Sets Tab	115
25	Mtes Tab	116
26	Sample nanoKEY2 Control Setup	121
27	Launchpad Minu Running with Seq66	128

List of Tables

1	Main Window Support	76
2	Performance Window Piano Roll	77
3	Performance Editor Time Section	78
4	Performance Editor Names Section	79
5	Pattern Editor Piano Roll	80
6	Pattern Editor Virtual Piano Keyboard	81
7	All SeqSpec Items	133
8	MIDI Meta Event Types	136
9	Application Support for MIDI Files	136

1 Introduction

This document describes "Seq66", a reboot of *Seq24* and a rewrite of *Sequencer64*, through version 0.92.0. The following project supports *Seq66* and documentation:

- <https://github.com/ahlstromcj/seq66.git>

Seq66 is *Sequencer64* refactored for newer versions of *C++* with cruft cleanup. It drops the *Gtkmm* user-interface in favor of *Qt 5*, and has better handling of sets, mute-groups, and configuration files. It includes support for the *Non Session Manager* and the ability to modify the color palette. Be prepared to note some significant differences (as well as similarities) between *Seq66* and *textslSequencer64*.

We have many contributors to acknowledge. Please see section 21 "Kudos" on page 142.

1.1 Seq66: What?

Sq66 is an ongoing reboot of *Seq24*, a live-looping sequencer with an interface similar to a hardware sequencer. *Sq66* is not a synthesizer. It requires a hardware synthesizer or a software synthesizer.

1.2 Seq66: Why?

The first reason to refactor *Sequencer64* is to take advantage of things learned in responding to user reports. The second reason is to use the new code as an opportunity to add new functionality such as *Non Session Manager* support. The last reason is to tighten the code by using newer features of *C++11* and beyond.

1.3 Improvements

The following improvements are some that have been made in *Sq66* versus *Sequencer64*.

- Qt 5 as the standard user-interface.
- A mutes editor tab, improve mutes handling, control, and status display.
- A playlist editor tab, with improved flexibility and automation.
- A sets editor tab (still in progress).
- A better live frame (main window and external windows) using buttons (and a fallback to the earlier style).
- Non Session Manager support.
- Repartitioning of the configuration files into separate files for flexibility.

For developers, a *Sq66* build is customizable via C macros, by enabling/disabling options at 'configure' time, and by many command-line arguments. We cannot show all permutations of settings in this document, so don't be surprised if some screenshots don't quite match one's setup. Distro maintainers might create their own build configurations.

1.4 Document Structure

The structure of this document follows the user-interface of *Sq66*. To help the reader jump around this document, it provides multiple links, references, and index entries.

1.5 Let's Go!

Make sure no other sound application is running, for the first run. Start *Sq66* to use JACK for MIDI, or on Windows, just run it (`qseq66`, or `qpseq66.exe` on Windows); for better trouble-shooting, run it from the command-line at first. The port settings will depend on your system. Provide a MIDI file. On our system, the synthesizer (*Yoshimi*) comes up on MIDI buss 5; on Windows, buss 0 is the "MIDI Mapper", while buss 1 is the built-in wavetable synthesizer. The `--buss` option remaps all events to the desired buss:

```
$ qseq66 --jack-midi --buss 5 data/midi/b4uacuse-gm-patchless.midi
C:\> qpseq66 --buss 1 data/midi/b4uacuse-gm-patchless.midi
```

The "data" directory is a installation directory:

/usr/share/seq66-0.90/ C:/Program Files (x86)/Seq66	(Linux) (Windows)
--	----------------------

The configuration directory is:

/home/user/.config/seq66 C:/Users/user/AppData/Local/seq66	(Linux) (Windows)
---	----------------------

These are created after the first run of *Seq66*.

If the `--alsa` option is used instead of `--jack-midi`, then the *ALSA* subsystem is used (Linux only). The following figure shows the main window using a light desktop theme and green labels.



Figure 1: Seq66 Main Screen

The *Seq66* main window appears, as shown above. This figure has many differences from the *Seq24* main window, but the functionality is similar. Most features, including the "look" of the application, can be configured via the 'rc', 'usr', 'ctrl', 'drums', 'playlist', 'mutes', and 'palette' configuration files, or via command-line options, and via desktop themes. There are many new front-panel items in *Seq66*. Many of these buttons have configurable keystrokes and configurable MIDI controls.

We break the discussion into sections for the following groups shown in the figure above:

- Center Tabs
- Application Menu
- Main Screen Controls

The **Live** tab is foremost in the application. It provides a grid of patterns (also called loops, tracks, or sequences) that display recorded MIDI data, status information, and provide popup-menus for each pattern. The buttons can be colored via a palette, and that the status of being armed is easy to see from the theme's coloring of activated buttons. In addition, the buttons can be toggled by a keystroke, shown in the lower right corner of the button. Another name for the **Live** tab is the **Patterns Panel**; it can be replicated in an external window. This tab and all the other tabs will be discussed in more detail, each in its own section. The **Menu** is also described later (see section 2 "Menu" on page 15).

Here, we first discuss the top and bottom **Main** controls, as shown in the following collapsed figure:




Figure 2: Main Screen Controls

See the following section and section 1.5.2 "Main Bottom Controls, First Row" on page 12.

1.5.1 Main Top Controls (Condensed View)

The top panel of the Pattern window is simple, consisting of the name of the program and a few controls. The top main control items are, from left to right:

- **PPQN Selection**
- **Set's Buss Override**
- **Global Beats Per Measure**
- **Global Beat Width**
- **BBT or HMS Time Display**
- **Beat Indicator**

1.5.1.1 PPQN Selection

This dropdown allows one to change the pulses-per-quarter-note (PPQN) of the loaded tune. As with Seq24, the default PPQN is 192. This can be changed to match the PPQN read from the file, or to other values: File, 32, 48, 96, 192, 384, 768, 960, 1920, 3840, 7680, 9600, 19200

1.5.1.2 Set's Buss Override

This dropdown allows for overriding the buss (port) number used by all of the patterns in the current set. This modifies the song and will lead to a prompt to save. The list of output busses is either the existing MIDI ports on the system, or, if port-mapping (see section 11 "Port Mapping" on page 84) is active, the list of mapped output ports. This is an easy way to redirect the set to a different output device.

1.5.1.3 Global Beats Per Measure

This dropdown changes the global beats/measure for the song.

Values: 1 to 16

1.5.1.4 Global Beat Width

This dropdown changes the global beat width (time-signature denominator) for the song.

Values: 1, 2, 4, 8, 16

1.5.1.5 BBT or HMS Time Display

This text simply shows the current time during playback. It can be shown in BBT (bars:beats:ticks) or HMS (hours:minutes:seconds).

1.5.1.6 Beat Indicator

The beat indicator is inspired by the *Kepler34* implementation. It shows the first beat in color, and the rest of the beats in white. It does not adapt to changes in the time-signature until playback is stopped.

1.5.2 Main Bottom Controls, First Row

The bottom main control items take up two rows. The first row contains:

- Set Name
- Set Master Button
- Active Set Indicator
- Set Changer

1.5.2.1 Set Name

This text field shows the name of the current set, and also allows editing the set name.

1.5.2.2 Set Master Button

This button brings up an external window showing the **Set Master** panel. This panel is also available in a center tab. It is a work in progress, and doesn't have a whole lot of functionality yet. It can currently show existing sets in one view, and allow reordering the sets.

1.5.2.3 Active Set Indicator

This read-only text field shows the set number of the currently active set. One can open a number of external *Live Frames* by Shift-left-clicking on pattern slots. The currently active set is then the set that has the mouse focus. This allows for working with multiple sets without a lot of mouse/keyboard navigation.

1.5.2.4 Set Changer

This spin-box allows showing a different set in the main windows. This set can be modified by adding new patterns, changing its name, or importing other MIDI files into the current set.

1.5.3 Main Bottom Controls, Second Row

On to the next section of the main bottom buttons, the second row contains:

- **Panic Button**
- **Stop Button**
- **Pause Button**
- **Play Button**
- **Live Record**
- **Keep Queue Button**
- **Mute Group Learn Button**
- **Developer Test Button**
- **Song Editor Button**
- **Song Mode Button**
- **PPQN Indicator**
- **BBT/HMS Toggle Button**
- **Tap BPM Button**
- **Beats Per Minute Control**

Many of these controls have keystrokes and MIDI-control slots that can be set up in the 'ctrl' file.

1.5.3.1 Panic Button

This button causes playback to stop, all patterns to mute, and flushes the MIDI buss. There is currently no keystroke, MIDI control, or MIDI-announcement (output) slot for this automation operation.

1.5.3.2 Stop Button

This button stops playback and rewinds to the beginning of the song. By default, the **Esc** key operates this function, and there is both a MIDI-control slot and a MIDI-announcement slot available for it.

1.5.3.3 Pause Button

This button stops playback, but does not rewind to the beginning of the song. It also resumes playback at the same point as the pause. By default, the **Period** key operates this function, and there is a MIDI-control slot and a MIDI-announcement slot available for it. This key is also hardwired to pause and start playback in the pattern editor and the song editor.

1.5.3.4 Play Button

This button starts playback, either at the beginning or at the pause point. Also called the "start button". By default, the **Space** key operates this function, and there is both a MIDI-control slot and a MIDI-announcement slot available for it. This key is also hardwired to toggle playback in the pattern editor and the song editor.

1.5.3.5 Live Record Button

This button causes a live playing session to be recorded. That is, triggers are added to the song automatically as the musician mutes and unmutes patterns, and the triggers can then be seen as layouts in the *Song* editor. By default, the **P** key operates this function,

1.5.3.6 Keep Queue Button

Puts the application into a "sticky" queue mode. In this mode, pressing a pattern key does not do a mute/unmute function, but instead turns on queuing for the selected pattern. By default, the **Backslash** key operates this function, and there is a MIDI-control slot available for it.

1.5.3.7 Mute Group Learn Button

Also called the "L" button. Sets up to learn the current set of active patterns ("mute group") into a mute-group. When in group-learn mode, the **Shift** key cannot be hit, so the group-learn mode automatically converts the keys to their shifted versions. This feature known as *shift-lock* or *auto-shift*. After pressing the "L" button, the user can then press a keystroke, which is automatically shifted, and the pattern set is saved, and can be recalled by that button (shifted) later. It can be saved in a 'mutes' file, as part of the MIDI tune, or in both places.

Example: We have 5 patterns armed in the current set. Press the "L" button, and then press the "s" key. These pattern statuses are saved and can be recalled later by the "S" ("s"-shifted) key.

By default, the **e1** (lower-case "l") key also sets this function, and there is a MIDI-control slot available for it, as well as a MIDI-announcement slot. In addition to that, one can also press the **Ctrl-L** key. The "e1" with it!

Remember that groups work with the playing ("in-view") screen-set. One must change the screenset and give it the command to make it the playing one. By default, the **Home** key is configured for this purpose.

There is also a setting in the 'mutes' file called **mute-group-selected**. If this value is set to a value from 0 to 31, then that mute group will be automatically applied when *Seq66* starts up. This is useful with the loading of the most-recent MIDI file (which is also a feature of *Seq66*).

1.5.3.8 Developer Test Button

This button is always disabled. Functionality is added temporarily when testing new features. Ignore this button.

1.5.3.9 Song Editor Button

This button (with a "pencil" icon) brings up an external window for editing the Song/Performance information. If already up, it closes it. Works the same as the **Edit / Song Editor** menu or the hard-wired **Ctrl-E** key.

1.5.3.10 Live/Song Mode Button

This button toggles between the *Live* and *Song* performance mode. In the *Live* mode, the musician controls are muting/unmuting of each pattern. In the *Song* mode, the triggers layed out in the **Song Editor** control the playback. By default, the **F10** key operates this function, There is currently no automation control for this button.

1.5.3.11 PPQN Indicator

This read-only field displays the current PPQN for the current tune.

```
qseq66.usr: [user-midi-settings] midi_ppqn
```

1.5.3.12 BBT/HMS Toggle Button

Toggles the format of the current time displayed during playback. It can be shown in B:B:T (bars:beats:ticks) or H:M:S (hours:minutes:seconds).

1.5.3.13 Tap BPM Button

Tap this button with a regular beat to determine the beats-per-minute of the tapping. With each tap, the counter on the button increments and the BPM is recalculated. Stop tapping for a few seconds to reset the counter. By default, the **F9** key operates this function, but it STILL NEEDS WORK to show the results in the BPM control. There is also a MIDI-control slot for this function.

1.5.3.14 Beats Per Minute Control

This control can be text-edited or spun to change the beats/minute value used in playing back the current song. This value is also saved to the file.

2 Menu

The *Seq66* menu structure is more complex than that of *Seq24*. In particular, the *File* menu has two variants: a normal file menu, and a file menu when *Seq66* is running under the *Non Session Manager*.

2.1 Menu / File

The **File** menu is used to save and load files in Standard MIDI Format 0 or 1, *Cakewalk "WRK"*, and *Seq66* MIDI files. The *Seq66* menu entry contains the sub-items shown below. The next few sub-sections discuss the sub-items in the **File** menu. Please note that these entries are different if *Seq66* is start under the control of the *Non Session Manager*.




Figure 3: Seq66 Menu File Items

1. **New**
2. **Open**
3. **Open Playlist**
4. **Recent MIDI files**
5. **Save**
6. **Save As**
7. **Export Song as MIDI**
8. **Export MIDI Only**
9. **Import MIDI to Current Set**
10. **Quit (Exit in Windows)**

For information on the **File** menu when *Seq66* is running under the *Non Session Manager*, see section [7.1.5 "Seq66 Session Management / File Menu"](#) on page [70](#).

2.2 Menu / File / New

The **New** menu entry clears the current song. (A play-list or mute-groups setup, if loaded, are not affected.) If unsaved changes are pending, the user is prompted to save the changes. Prompting for changes is more comprehensive than *Seq24*. However, when in doubt, save! Keep backups of your tunes and configuration files!

2.2.1 Menu / File / Open

The **Open** menu entry opens a song (MIDI file or *Cakewalk WRK* file), replacing the current song (after a prompt if the song was modified). It opens up a standard file dialog:




Figure 4: File / Open

This dialog lets one type a file-name, highlighting the first file that matches the characters typed. *Seq66* can open *Seq66*, regular MIDI files, and Cakewalk "WRK" files.

2.2.2 Menu / File / Open Playlist

The **Open Playlist...** menu entry opens a *Seq66* play-list file.




Figure 5: File / Open Playlist

The playlist file contains a list of "playlist sections", each listing a number of MIDI songs. These playlists and songs can be selected by the arrow keys or by MIDI control, and are displayed and editable in the *Playlist* tab in the main window. See section [13 "Seq66 Play-Lists"](#) on page [109](#).

2.2.3 Menu / File / Recent MIDI files

This menu entry provides a list of the last few MIDI files created or opened; play-list selections are not included in this list.




Figure 6: Seq66 Menu File Recent Files

This list is saved in the [recent-files] section of the 'rc' configuration file. In the menu, only the last part of the file-name is shown, but in the 'rc' file, the full path to the file-name is stored. This path is in "UNIX" format, using the forward slash, or solidus, as the path separator, even in Windows. Only unique entries are included in the recent-files list. The limit is 10 recent-file entries. This is a feature from Kepler34 [6]. One can also set *Seq66* to load the most-recent file at startup. Here is an example from an 'rc' file. Note the startup option.

```
[recent-files]
# Holds a list of the last few recently-loaded MIDI files.
# The first number is the number of items in the list. The second value
# indicates if to load the most recent file (the top of the list)
# at startup (1 == load it).
3 1
/home/chris/git/seq66/data/b4uacuse-gm-patchless.midi
/home/chris/git/seq66/data/midi/colours.midi
/home/chris/git/Julian-data/TestBeeps.midi
```

2.2.4 Menu / File / Save and Save As

The **Save** menu entry saves the song under its current file-name. If there is no current file-name, it opens up a standard file dialog to name and save the file. The **Save As** menu entry saves a song under a different name. It opens up the following standard file dialog, very similar to the **File Open** dialog, with an additional **Name** text-edit field.




Figure 7: File / Save As

To save a new file or save the current file to a new name, enter the name in the name field, without an extension. *Seq66* will append a `.midi` extension to the filename. The file will be saved in a format that the Linux `file` command will tag as something like:

```
colours.midi: Standard MIDI data (format 1) using 16 tracks at 1/192
```

It looks like a simple MIDI file, and yet, if one re-opens it in *Seq66*, one sees that the mute-groups, labeling, pattern information, and song layout have been preserved in this file. This information is saved in a way that MIDI-compliant software should be able to use or ignore without failure. After the last track in the file, a number of sequencer-specific (SeqSpec) items are saved, to preserve the extra information that *Seq66* adds to the song. There is no way to save a *Cakewalk* "WRK" file. *Seq66* can only read them, and then save them as *Seq66* files.

Meta events are now partially handled by *Seq66*. Meta events **Set Tempo** and **Time Signature** are now fully supported. Other meta events, such as **Meta MIDI Channel** and **Meta MIDI Port** are now read as events, and are saved back when the file is saved. They cannot be edited in *Seq66*, but they are not lost. (Channel and port meta events are considered *obsolete* in the MIDI standard.)

2.2.5 Menu / File / Import MIDI

The **Import** menu entry imports an SMF 0 or SMF 1 MIDI file as one or more patterns, one pattern per track, into the specified screen-set. This functionality is explained in detail in section [8.1 "Import MIDI"](#) on page [72](#).

2.2.6 Menu / File / Export Song as MIDI

Thanks to the *Seq32* project, the ability to export songs to MIDI format has been added. In this export, a complete song performance is recoded so that other MIDI sequencers can play the performance properly. This functionality is explained in detail in section [8.2 "Export Song as MIDI"](#) on page [73](#).

2.2.7 Menu / File / Export MIDI Only

Sometimes it might be useful to export only the non-vendor-specific (non-SeqSpec) data from a Seq66 song, in order to reduce the size of the file or to accomodate non-compliant sequencers. This functionality is explained in detail in section [8.3 "Export MIDI Only" on page 73](#).

2.3 Menu / Edit

The **Edit** menu has undergone some expansion in Seq66.

1. Preferences...
2. Song Editor
3. Apply Song Transpose
4. Clear Mute Groups
5. Reload Mute Groups
6. Mute All Tracks
7. Unmute All Tracks
8. Toggle All Tracks

1. Preferences. This entry brings up a **Preferences** menu entry, to allow viewing and tweaking MIDI I/O ports, displays options, JACK options, and more. It can also be brought up by **Ctrl-P**. It is discussed in detail in a later section.

2. Song Editor. This item toggles the presence of the main song / performance editor. Note that the song editor is also available in the **Song** center tab in the main window. The song editor allows specifying exact numbers of loop replays; this provides a canned rendition of the MIDI tune.

3. Apply Song Transpose. Selecting this item applies the song transposition value to all sequences / patterns marked as transposable. (Normally, drum tracks are *not* transposable). This actively changes the note / pitch value of all note and aftertouch events in the pattern. For the setting of song transpose, see section [5 "Song Editor" on page 54](#). Note that transpose can be enabled in the in the sequence editor (see section [4 "Pattern Editor" on page 39](#)).

4. Clear Mute Groups. A feature of Seq66 is that the mute groups are saved in both the 'rc' file and in the "MIDI" file. This menu entry clears them. If this resulted in any mute-group sequences status being set to false, then the user is prompted to save the MIDI file, so that it will no longer have any mute-group information. And then, if the application exits, the cleared mute-group information is also saved to the 'rc' file.

5. Reload Mute Groups. This menu entry reloads the mute-groups from the 'rc' file. So, if one loads a MIDI file that has its own mute groups that one does not like, this command will restore one's favorite mute-grouping from the 'rc' file.

6. Mute All Tracks. This menu entry, useful mostly in **Live** mode, immediately mutes *all* patterns in the entire song. The hard-wired keyboard short-cut for this action is **Ctrl-M**.

7. Unmute All Tracks. This menu entry, useful mostly in **Live** mode, immediately unmutes *all* patterns in the entire song. The hard-wired keyboard short-cut for this action is **Ctrl-U**.

8. Toggle All Tracks. This option toggles the mute/armed status of **all** tracks. It is useful mostly **Live** mode, which overrides **Song** mode even if the Song Editor is focussed. The hard-wired keyboard short-cut for this action is **Ctrl-T**.

2.3.1 Menu / Edit / Preferences

Preferences provides a number of settings in one tabbed dialog, shown in the figures that follow. It allows one to set MIDI clocking, MIDI Input, display tweaks, minor playback options, and some JACK parameters.

Missing in this new dialog are: incoming MIDI events to control the sequencer; what keys are mapped to functions; how the mouse works. The MIDI and Key controls, far more numerous than in *Seq24*, have been consolidated into a 'ctrl' file and are fairly easy to edit with a text editor. *Sq66* does not support the 'fruity' mouse mode at this time.

2.3.1.1 Menu / Edit / Preferences / MIDI Clock

The **MIDI Clock** tab provides a way to set MIDI clocking for the available MIDI output busses. It configures the output busses for MIDI clock and data. It shows the devices that can play music. The items that appear in this tab depend on:

- What MIDI devices are connected to the computer. MIDI controllers, USB MIDI cables, applications with virtual ports, and other connected devices will add MIDI output devices (ports) to the system. This list will generally match the output of `aplaymidi -l` or `aconnect -lio`.
- The setting of the "manual-ports" option, which tells *Sq66* to set up virtual MIDI ports. It is enabled by the `--manual-ports` command-line option or the `[manual-ports]` section of the `qseq66.rc` configuration file.
- The setting of the *Sq66*-specific "reveal ALSA ports" option, `--reveal-ports` command-line option or the `[reveal-ports]` section of the `qseq66.rc` configuration file.

If `--manual-ports` is on, this list shows the virtual MIDI output busses that *Sq66* can drive. One needs to use a JACK or ALSA MIDI connection application to connect a device on each of those outputs. The fact that the buss names can start with different numbers, depending on the system setup, can complicate the playing of MIDI in this manner. Also, the 'usr' configuration file can change the visible names of the ports to match specific equipment attached to the ports.




Figure 8: MIDI Clock Tab, ALSA Devices

The following elements are present in this tab:

1. **Ports and Clocks Table**
2. **Clock Start Modulo**
3. **Save Clock/Input Maps**
4. **Meta Events**
5. **Client ID**

The **Ports and Clocks** table contains the following elements, although some can be removed by specifying the `port-naming = short` option in the 'rc' file.

1. **Index Number**
2. **Client Number**
3. **Port Number**
4. **Buss Name**
5. **Port Disabled**
6. **Off**
7. **On (Pos)**
8. **On (Mod)**
9. **Clock Start Modulo**

The format of the left side of the entry listing is like the following:

```
[5] 128:4 yoshimi:input
^ ^ ^ ^
| | |
| | | ----- Buss name
| | | ----- Port number
| | | ----- Client number
----- Index number
```

1. Index Number. The number in square brackets is an ordinal indicating the position of the output buss in the list. For all practical purposes in *Seq66*, it is the buss/port number. This

number can be stored in a pattern in order to have the pattern's output go to that buss. This is true even if port-mapping is in place. It can be used with the `-b`, `--buss`, or `--bus` options to redirect all pattern output to that buss, useful if only one buss is active or the *Seq66* patterns route to non-existent busses.

2. Client Number. The number that precedes the colon is the "client number". It is useful mainly in ALSA, where clients can have numbers like "14", "128", "129", etc. For native JACK mode, it matches the index number or is the name of the client (e.g. "seq66").

3. Port Number. The number that follows the colon is the "port number". It is useful mainly in ALSA. For native JACK mode, it matches the index number.

4. Buss Name. These labels indicate the output busses (ports) available. *Seq66* does not access devices by name, but by port number. However, a port-map can be created to make it possible to find the correct buss / port number by name lookup.

5. Port Disabled. The **Port Disabled** clock choice marks an output port that the user does not want to use or that the operating system (Windows [®]) is locking or disabling. Normally, this inaccessible port would cause *Seq66* to exit. With the port disabled, the inaccessible port is ignored. This feature also shows when a port-map cannot find a device in the system's device list. When the Windows version of *Seq66* (`qpseq66.exe`) is first started, it may error out. It will then write `erroneous.rc` and `erroneous.usr` configuration files, which can be examined to find the offending buss, which can then be marked in the normal 'rc' file as disabled.

6. Off. Disables the MIDI *clock* for the given output buss. MIDI output is still sent to those ports, and each port that has a device connected to it will play music. Some synthesizers may require this setting.

7. On (Pos). MIDI clock will be sent to this buss. MIDI Song Position and MIDI Continue will be sent if playback starts at greater than tick 0 in Song mode. Otherwise, MIDI Start will be sent.

8. On (Mod). MIDI clock will be sent to this buss. MIDI Start will be sent, and clocking will begin once the Song Position has reached the start modulo of the specified size (see the next item's description). This setting is used for gear that does not respond to Song Position.

Below the **Ports and Clocks Table** are more configuration elements.

1. Clock Start Modulo. Clock Start Modulo (1/16 Notes). This value starts at 1 and ranges up to 16384, and defaults to 64. It is used by the **On (Mod)** setting discussed above. It is the `[midi-clock-mod-ticks]` option in the *Seq66* 'rc' file.

2. Save Clock/Input Maps. Pressing this button saves the current set of MIDI I/O ports to sections in the 'rc' file. These sections can be enabled in order to support port-mapping in subsequent runs of *Seq66*.

3. Meta Events. This section consists of one item, the Tempo Track number. It allows the user to move the tempo track from pattern 0 to another pattern. Changing this option is not recommended, since track 1 (0) is the official track for tempo events, but *Seq66* allows the user to record tempo events to another track. *Seq66* will process tempo events in any pattern. *The "Set as Tempo Track" button to the right is not yet functional.*

4. Seq66 Client ID. This read-only text field shows the client ID number assigned to *Seq66* by the ALSA MIDI subsystem.

5. Output Ports Mapped. This read-only check-box shows if the port-mapper is active for the output ports. This item can only be edited by closing the application, editing the 'rc' file, and restarting the application.

There is currently no user-interface item corresponding to the "manual-ports" command-line and 'rc' configuration file option. We should rename this option to "virtual" eventually.

2.3.1.2 Menu / Edit / Preferences / MIDI Input

To set up *Seq66* to record MIDI from devices such as controllers and keyboards, the output of the ALSA MIDI recording command-line `arecordmidi -l` is relevant. Something like that listing appears in the Input tab:




Figure 9: MIDI Input, ALSA View

Any item checked allows *Seq66* to record MIDI from that source, which must be connected to this input port.

Warning: If the `[user-midi-bus-definitions]` value in the 'usr' configuration file is non-zero, and the corresponding number of `[user-midi-bus-N]` settings are provided, then the list of existing hardware will be ignored, and those values will be shown instead. This feature can be overridden with the `--reveal-ports (-r)` option. If you define these sections, they should match your hardware exactly, and your hardware should not change from session to session.

If the "auto ALSA ports" option is turned on, via the `-a` or `--auto-ports` option, then the input ports from the system are shown.

1. **Input Buses.** **Input Buses** delineates the MIDI input devices as noted above.
2. **Input Options.** **Input Options** adds further refinements to MIDI input. Currently it has only one setting, for recording input into patterns by the channel in each event.
3. **Input Ports Mapped.** This stand-alone read-only check-box shows if the port-mapper is active for the input ports. This item can only be modified by closing the application, editing the 'rc' file, and restarting the application.
4. **Input Option.** **Record input into sequence according to channel** causes MIDI input with multiple channels to be distributed to each sequence according to MIDI channel number. When disabled, the normal recording behavior dumps all data into the current sequence, regardless of channel.

2.3.1.3 Menu / Edit / Preferences / Keyboard (Removed)

The default keyboard mappings follow *Sq24* fairly well, but add a large number of additional controls. *Seq66* does not provide a user-interface to edit control keystrokes; around 96 keystroke slots would need to be provided! The keystroke and MIDI controls are consolidated, and are easy to change by editing the appropriate 'ctrl' configuration file, stored in one of the following directories, depending on the operating system:

```
/home/username/.config/seq66/qseq66.ctrl          (Linux)
C:/Users/username/AppData/Local/seq66/qseq66.ctrl (Windows)
```

There are also some extended example present in the *Seq66* data/linux directory.

For more information on keystrokes, see section [9.1 "Keyboard Control"](#) on page [74](#).

2.3.1.4 Menu / Edit / Preferences / Mouse (Removed)

This item selected the mouse-interaction method. It is not supported in *Seq66*... the "Fruity" interaction method is not available.

2.3.1.5 Menu / Edit / Preferences / Display

This dialog provides a few odds and ends to enhance the user-interface. Some of these items (plus a few more) can be configured by editing the 'usr' file.




Figure 10: Display Options

1. Editor Key Height. This option affects the pattern editor's piano roll. Smaller means a wider range of notes can be shown. It might be a good idea at some point to implement a vertical zoom.

2. Scaling of User Interface. These two items set scale factor for width and height of the main window. The lowest scale factor is 0.5, and the largest scale factor is 3.0. For the smallest window, the smallest practical values are 0.85 x 0.60.

3. Palette File Base Name. This text edit holds the base name of a 'palette' file, which is always stored in the *Seq66* configuration directory.

4. Save Current Palette. Normally, there is no palette file. Pushing this button creates one, which can then be modified and configured as the palette-file to use in the 'rc' file.

2.3.1.6 Menu / Edit / Preferences / JACK

This tab sets up JACK transport, if *Seq66* was built with JACK support. This tab also sets up options for using LASH session management, if *Seq66* was built with LASH support, which is no longer the default, even though it is shown in the figure below.




Figure 11: File / Options / JACK

The main sections in this dialog are:

1. **JACK Transport/MIDI**
2. **JACK Start Mode**
3. **JACK Transport Connect and Disconnect**
4. **LASH Options**

1. Transport/MIDI. These settings are stored in the 'rc' file settings group [jack-transport]. This items collects the following settings:

- **Jack Transport.** Enables slave synchronization with JACK Transport. The command-line option is `--jack-transport`. The behavior of this mode of operation is perhaps not quite correct. Even as a slave, *Seq66* can start and stop playback. Note that this option cannot be disabled via the mouse if the **Transport Master** option is enabled. Disable that one first.
- **Transport Master.** *Seq66* will attempt to serve as the JACK Master. The command-line option is `--jack-master`. **Tip:** *Seq66* generally works better as JACK Master. If this option is enabled the **JACK Transport** option is automatically enabled as well.
- **Master Conditional.** *Seq66* will fail to serve as the JACK Master if there is already a Master. The command-line option is `--jack-master-cond`. If this option is enabled the **JACK Transport** option is automatically enabled as well.

- **Native JACK MIDI.** This option is for the `seq66` version of *Seq66*. If set, MIDI input and output use native JACK MIDI, rather than ALSA. However, if JACK is not running on the system, then `seq66` will fall back to ALSA mode. The command-line option is `--jack-midi`.

If one makes a change in the JACK transport settings, it is best to then press the **JACK Transport Disconnect** button, then the **JACK Transport Connect** button. Another option is to restart *Seq66*... the settings are automatically saved when *Seq66* exits.

2. JACK Start mode. This item collects the following settings, also stored in the 'rc' file settings group [jack-transport].

- **Live Mode.** Playback will be in live mode. Use this option to allow muting and unmuting of patterns. This option might also be called "non-song mode". The command-line option is `--jack-start-mode 0`.
- **Song Mode.** Playback will use only the Song Editor's data. The command-line option is `--jack-start-mode 1`.

Seq66 also selects the playback modes according to which window started the playback. *The main window*, or pattern window, causes playback to be in live mode. The user can arm and mute patterns in the main window by clicking on sequences, using their hot-keys, and by using the group-mode and learn-mode features. The song editor causes playback to be in performance mode, also known as "playback mode", or **Song** mode.

3. Connect. Connect to JACK Sync. This button is useful to restart JACK sync when making changes to it, or when *Seq66* was started in ALSA mode.

4. Disconnect. Disconnect from JACK Sync. This button is useful to stop JACK sync when making changes to it.

5. LASH Options. Currently contains only one item, which enables the usage of LASH session management. Currently, *Seq66* needs to be restarted to complete the enabling or disabling of LASH support. Like the rest of the options, this one is written to the 'rc' configuration file. However, LASH is no longer supported in the default build.

JACK connection and disconnection are disabled during playback, but the buttons don't yet reflect that status.

2.3.1.7 Menu / Edit / Preferences / Play Options

There is currently only one setting in this tab:

Resume Note Ons at start/stop or sequence toggle. This option allows notes that had already started to be resumed when playback resumes.

2.4 Menu / Help / About...

This menu entry shows the "About" dialog. That dialog provides access to some credits for the program as well. authors and the project documentors. It also shows Git version-control information as well.

2.5 Menu / Help / Build Info...

This menu entry shows the "Build Info" dialog. This list of build options enabled in the current application is the same list that it generated via this command line:

```
$ seq66 --version
```

3 Patterns Panel

Seq66 works with patterns (also known as "loops", "tracks", or "sequences") that are repeated throughout a song. One composes and edits small patterns, and combines them to create a full song. This is a powerful way to work, and makes one productive within an hour.

The *Seq66 Patterns Panel* is in the center of the **main window** of *Seq66*. See [Figure 1 "Seq66 Main Screen"](#) on page [10](#). It is here one creates a set of patterns, manages the configuration, controls the playback rate, adds tempo events, and opens the pattern, song, event, or playlist editors.

When the Patterns Panel has the application focus, and *Seq66* is *not* running in **Song** mode, it puts *Seq66* in **Live** mode. The musician can control the playback and muting/unmuting of each pattern in the song, while it is playing, from within this window.

If the song editor (see section [5 "Song Editor"](#) on page [54](#)) has the input focus, it controls the muting/unmuting of each pattern, and *Seq66* runs in **Song** mode. (There are ways to override this behavior.)

For exposition, we break the Patterns Panel into a menu bar, a top panel, a pattern panel, and a bottom panel. The *Seq66* menu bar is discussed in section [2 "Menu"](#) on page [15](#).

3.1 Patterns / Set Handling

Let's go through an example using the **Home** key (or whatever key is configured as the **Set Playing Screenset** key.)

1. Load a song with more than one screen-set.
2. Unmute the pattern(s) in the first set and start playback.
3. Use the "**]**" (**Screenset Up**) key to move to the next set. Note that the first set is still playing. Also note that the now-current set is *not* playing.
4. Press the **Home** key. Note that the first set turns off, and the current set turns on. These steps can be repeated at will.
5. Finally, hit the **F8 (Toggle Mutes)** key. Note that all tracks on all sets toggle muting each time this key is pressed.

3.2 Patterns / Main Panel

The main panel of the Patterns window provides a grid of empty boxes. Each filled box represents a loop, track, sequence, or pattern. One sees only 32 loops at a time in the main panel (but many more than 32 loops can be supported by *Seq66*).

This group of 32 loops is called a "screen-set". One can switch between sets by using the "**[**" and "**]**" keys on the keyboard, or by using the spin-widget-driven, labelled **Set** interface item,

or by hitting the (default) Home key to make it the playing screenset, or by hitting Page-Up or Page-Down with the pattern window in keyboard focus. There are a total of 32 sets, for a total of 1024 loops/patterns. Only one screen-set can be controlled at a time, in general. But any number of screensets can be playing at the same time.

Note that the Page Up and Page Down keystrokes, and their counterparts in **File / Options / Keyboard / Control Keys / Screenset Up** and **Screenset Down**, can be used in lieu of the Set spin-button.

It is important to note that keystroke control of the screen-set will wrap-around in screen-set values (i.e. screen-set down at 0 results in screen-set 31, and screen-set up at 31 results in screen-set 0). However, the spinbuttons will stop up at 31 and stop down at 0. We consider this a feature rather than a bug, at this time.




Figure 12: Patterns Panel Pop-up Menu

The individual items annotated in this figure are described in section [3.2.2 "Pattern"](#) on page [31](#), in more detail. The slot at the bottom left of this figure shows some new features:

- The sequence number appears at the bottom left of the slot. This number ranges from 0 on up.
- The buss number (re 0) and the channel number (re 1) appears to the right of the sequence number, in the format "0-1".
- To the right of that, the time signature ("4/4") appears, at the bottom.
- The hot-key for muting/unmuting the pattern appears next, at the bottom right of the slot.

- The title of the sequence appears at the top left of the pattern slot.
- The length of the sequence, in number of measures (bars), appears at the upper right of the slot.
- The font is a *Qt* font.
- A right-click over a pattern button brings up a fairly extensive popup menu.

Observe that feature in the first figure of the next section. The two main items are the empty *pattern slot*, and the slot filled with a *MIDI pattern*:

1. **Pattern Slot**
2. **Pattern**

3.2.1 Pattern Slot

An empty box is a slot for a pattern. If a pattern is present in the slot, the top line will show the title of the pattern, and the number of measures in the pattern. A pattern can show a number of different statuses based on the coloring of elements in the pattern slot. (However, note that some of the special coloring used in *Sequencer64* is not supported in *Seq66*.

- **Empty background.** When the default button coloring for the current *Qt* theme is shown, without a pattern box, this state indicates that the slot is unused.
- **Yellow pattern box.** This color is used when a pattern is first created by double-clicking on the slot. However, this color sticks even when notes are added. But feel free to change it to another color, or no color.
- **Normal background.** Unarmed (muted) patterns show the unactivated/unchecked state of the button as per the *Qt* theme. If a color is applied, it has a slight bit of alpha in the color so that the color appears muted.
- **Active background.** An armed (unmuted) pattern shows the activated/checked state of the button as per the *Qt* theme. If a color is applied, it has no transparency, and the color appears bright.
- **Red events.** Indicates a pattern for which the new transpose feature is disabled.

The user can also apply coloring to each sequence. This feature was adopted from *Kepler34* ([6]). The pattern menu for sequence color is shown in the previous figure. We've used colors in most of the examples in this manual.

Right-clicking on an empty box one brings up a menu to create a new loop, as well as some other operations.

1. **New pattern**
2. **External live frame for set 0**

1. New. Creates a new loop or pattern. Clicking this menu entry fills in the empty box with an untitled pattern. Another way to create a new loop is to double-left-click on an empty slot.

2. External live frame for set 0. This option brings up an external **Live** frame window, which is the same as the patterns panel, but can be used to show a different set in a multi-set project. Up to 32 external live frames can be shown. More on the external live frames later.

Once a new loop is created, there are more options for that slot.

1. **New pattern**

2. External live frame for set 0

3. Edit pattern in tab
4. Edit pattern in window
5. Edit pattern in tab

- Mute All Tracks
- Unmute All Tracks
- Toggle All Tracks
- Toggle Live Tracks

The first two menu entries are the same as above. However, since there is already a pattern present in the slot, the user is prompted before erasing the current pattern and creating a new one.

1. Edit Pattern In Tab. Selecting this item activates the **Edit** tab and fills it with data from the selected pattern. Note that this editor is somewhat simplistic, useful for common operations. We want to keep it uncluttered so that the user can make the main window operation small if desired.

CONTINUE HERE!

2. Edit Pattern In Window. Selecting this item brings up the pattern in an external pattern editor that is more sophisticated than the **Edit** tab. from the selected pattern. Note that this editor is somewhat simplistic, useful for common operations.

, and brings up the Pattern Editor so that one can fill in the new pattern.

In addition to right-click and select **New**, the user can double-click on the empty slot, to bring up a new instance of the sequence editor. For the double-click, the effect can be a bit confusing at first, because it also toggles the arming/mute status of the slot quickly twice (leaving it as it was). It takes some getting used to, but we miss it when using *Seq24*.

A nice feature is hitting the equals ("=") key, then hitting a pattern shortcut key (hot-key), to bring up a new sequence or edit an existing one in a **Pattern Editor**. Another feature is hitting the minus ("−") key, then the hot-key, to bring up the **Event Editor**. The configuration file settings for the the '=' and '-' keys can be altering in the **File / Options / Keyboard** tab.

3. Paste. Pastes a loop or pattern that was previously copied. Also note that there is no **Ctrl-V** key for this operation in the main window.

4. Song. The **Song** items are described later.

3.2.2 Pattern

A filled pattern slot is referred to as a *pattern* (or *loop*, or *sequence*). A pattern is shown in the Pattern window as a filled box with the following items of information in it.

- **Name.** This line contains the name or title of the pattern, to help reference it when juggling a number of patterns.
- **Pattern Length.** If the option to show pattern hot-key is enabled, the length of the pattern, in measures, is shown in the upper right corner of the pattern slot. This feature is useful when recording tempo events that will increase the length of the tempo track.
- **Contents.** The contents of the pattern provide a fairly detailed and distinguishable representation of the notes or events in the pattern. Also, when the song is playing, a vertical bar cursor tracks the position of the playback of the pattern or loop; it returns to the beginning of the box every time that pattern starts over again. With *Seq66*, an imported empty pattern

will no longer needlessly scroll. However, if a pattern has even a single event (say, a program change), it will scroll.

- **Sequence Number.** This number is shown at the bottom left of the pattern slot.
- **Bus-Channel.** This pair of numbers shows the the MIDI buss number, a dash, and the MIDI channel number. For example, "0-2" means MIDI buss 0, channel 2.
- **Beat.** This pair of numbers is the standard time-signature of the pattern, such as "4/4" or "3/4". The first number is the beats-per-measure, and the second is the size of the beat, here, a quarter note.
- **Shortcut Key.** The key noted in the lower-right corner of the pattern is a "hot-key" that can be pressed to toggle the mute/unmute status of that pattern. This action is an alternative to left-click on the pattern.
- **Progress Cursor.** At the left of each box is a vertical line, waiting for playback to start so that it can move through the pattern, again and again.
- **Armed.** Button highlighting indicates that the pattern is armed (unmuted), and will play if playback is initiated in the pattern window in live mode. An item is armed/disarmed by a left-click on it. If the Shift key is held during a left-click on a pattern, then the armed/unarmed state of every other active pattern is toggled. This feature is useful for isolating a single track or pattern.
- **Queued.** That same pattern also shows that it is queued, which means that it will toggle its playing status when the pattern next begins again.
- **Sequence number.** Later builds of *Seq66* are now built with the option to also show the sequence number in the pattern box, if the "show sequence numbers" option is on. This option can be set in the 'usr' configuration file.

Left-click on an filled pattern box will toggle the status of the pattern between muted (white background) and unmuted (black background). If the song is playing via the main window, toggling this status makes the pattern stop playing or start playing. The armed status can also be toggled using hot-keys.

If the **Song Editor** is the active window and was used to start the playback, the pattern boxes will toggle between the muted/unmuted states as the music plays, and the pattern is active or inactive at the point of playback. (The **Song Editor** acts as a list of triggers).

A right-click on an already-filled box brings up a menu to allow one to edit it, or perform a few other actions specified in the context menu. Here is that menu:

Here one can choose to edit the pattern, cut and copy the pattern, set the MIDI bus/channel, and more. One can also clear all performance (song) data for the pattern. Here are the menu entries:

1. **New pattern**
2. **Extern live frame**
3. **Edit pattern in tab**
4. **Edit pattern in window**
5. **Edit events in tab**
6. **Set pattern color**
7. **Copy pattern**
8. **Cut pattern**
9. **Delete pattern**

1. **Edit....** Edits an existing loop or pattern. Clicking this menu entry brings up the **Pattern Editor** so that one can modify the existing pattern by click-dragging new notes in a piano roll user-interface, known as the "sequence editor".

In addition to right-click and selecting **Edit...**, the user can double-click on the slot, to bring up the **Pattern Editor**.

Another way to bring up a pattern in the **Pattern Editor** is to click the **equal** key and then the pattern's hot-key. For example, "**=q**" will open up the editor for the pattern with the hot-key **q**. The Equals key (=) is the default key that does this action. This key can be changed by modifying the **File / Options / Keyboard / Control keys / Pattern Edit** item.

2. Event Edit.... Edits an existing loop or pattern, but using a detailed **Event Editor** that shows events as text and numbers, and allows editing them as text and numbers.

Another way to bring up the **Event Editor** is to click the **minus** key and then the pattern's hot-key. For example, "**-q**" will open up the **Event Editor** for that pattern. The Minus key (-) is the default key that does this action. This key can be changed by modifying the **File / Options / Keyboard / Control keys / Event Edit** item.

The **Event Editor** is not the same as the **event** pane in the pattern editor; the **Event Editor** shows all events at once, and shows them only in text/list format. This editor is basic, meant for viewing MIDI events and making some minor edits or deletes. The **Event Editor** is most useful when trying to find events that are screwing up the performance of that pattern. See section [6 "Event Editor" on page 60](#), for more information.

To simplify the application and avoid editing a pattern in two different dialogs, if either the **Pattern Editor** or the **Event Editor** is active for a given sequence, the right-click sequence-slot menu leaves out the **Edit...** and **Event Edit...** menu entries.

The old functionality was to have the **Edit...** menu entry simply raise the existing **Pattern Editor** to the top of the windows.

3. Cut. Deletes and copies an existing loop or pattern. One can also drag-and-drop a pattern into another cell (there is no outline box during the drag, sadly). Note that there is no **Ctrl-X** key for this operation in the main window.

4. Copy. Copies an existing loop or pattern. The pattern can then be pasted elsewhere in the Patterns panel. One can also drag-and-drop a pattern into another cell (there is no outline box during the drag). See section [3.2.1 "Pattern Slot" on page 30](#). Note that there is no **Ctrl-C** key for this operation in the live (main) window.

5. Song. Clicking this menu entry brings up a small popup menu. It contains the following items:

1. **Clear This Track's Song Data**
2. **Mute All Tracks**
3. **Unmute All Tracks**
4. **Toggle All Tracks**
5. **Toggle Live Tracks**

Clear This Track's Song Data This item is not available if the pattern is empty. Selecting this filled-box right-click menu item causes that box's loop/pattern to be removed from the song editor. The triggers disappear from the Song Editor window, and so will not be played when the song plays in Song mode.

Song / Mute All Tracks Selecting this filled-box right-click menu item causes the tracks in the Song Editor to be muted. Sometime it takes a few seconds for the user-interfaces to show this big change. This item mutes all tracks (or loops/patterns). It works when one has opened the Song Editor window and started playing in playback mode by starting play using that window.

So, let us assume the song is running in live (playback) mode. The patterns that are active (unmuted) in the live window are shown with a black background in the main patterns window. If one right clicks on a pattern cell and selects **Song / Mute All Tracks**, all those patterns will become white and be silenced. Eventually, the Song Editor window catches up and shows the "M" activated for all tracks.

Unmute All Tracks Provides the opposite functionality, making all tracks armed and audible. Selecting this filled-box right-click menu item causes the tracks in the song to be unmuted.

Toggle All Tracks Toggles the armed/mute status of all tracks. It doesn't matter if Live or Song Mode is in force. By default, the F8 key will also toggle all tracks.

Note that there is also a feature where a **Shift-Left-Click** on a pattern slot toggles the mute status of the *other* tracks.

Toggle Live Tracks Toggles the mute status of only the armed/unmuted tracks when in Live mode. Works only in Live mode. This operation unmutes all tracks that are currently unmuted. The statuses of these armed tracks are saved; when this operation is performed again, those tracks are unmuted, turned back on. This menu entry provides the same function as the **Mute** button in the main window.

6. Color. This menu item allows for specifying colors for the patterns. Colors can make it easier to find a pattern while running live. Note that there are some minor issues with colors, and that this feature is still in flux.

7. Enable/Disable Transpose. This menu entry changes depending upon whether the new transpose feature is enabled or disabled for the sequence/pattern. Note that, if the events shown in the slot are red, this denotes that transpose is currently *disabled* for that pattern, which might be a drum pattern.

8. MIDI Bus. Selecting this filled-box right-click menu item brings up a list of the up to 16 MIDI output busses that *Seq66* supports. For each of these bus items, another pop-up menu allows one to specify the MIDI output channel for that bus.

Another way to specify busses is the **--buss n** command-line option. It causes every pattern in the MIDI file to be directed to that bus number, and when a new sequence/pattern is created. This option is only for convenience in testing. Save the file, and it will have that bus number as part of each track's data, which makes the song file less portable, so be careful.

3.2.3 Pattern Keys and Click

This section recapitulates all the clicks and keys that perform actions in the Pattern windows. Some additional clicks and keys are noted here as well.

3.2.3.1 Pattern Keys

Each pattern in the patterns panel can have a hot-key or shortcut-key associated with it.

For each pattern, hitting its assigned hot-key will also toggle its status between muted/unmuted (armed/unarmed). Below is the default grid that is mapped to the loops/patterns on the screen-set. This grid can be changed in the **File / Options / Keyboard** tab, and is saved in the *keyboard-control* section of the "rc" file.

```
[ 1 ][ 2 ][ 3 ][ 4 ][ 5 ][ 6 ][ 7 ][ 8 ]
[ q ][ w ][ e ][ r ][ t ][ y ][ u ][ i ]
[ a ][ s ][ d ][ f ][ g ][ h ][ j ][ k ]
[ z ][ x ][ c ][ v ][ b ][ n ][ m ][ , ]
```

These characters are shown in the lower right corner of each pattern, as an aid to memory.

A "shift" functionality is available for the mute/unmute hot-keys when a set is larger than 32 patterns. Normally, pressing the 1 key will toggle sequence 0. If preceded by one slash key (/), then sequence 32 will be toggled. If preceded by two slash keys, then sequence 64 will be toggled. This features supports using set sizes of 32, 64, and 96 patterns.

The "[" and "]" keys on the keyboard decrement or increment the set number.

The left and right **Alt** keys are, by default, set up in the **File / Options / Keyboard / Snapshot 1** and **Snapshot 2** fields to be used as "snapshot" keys. Our preference is to use something that does not trigger desktop commands, perhaps "F11" or "F12", or one of the keys in the keypad.

When a snapshot key is pressed, the state of the patterns (armed versus unarmed) is saved. While the snapshot key is held, one can then change the state of the patterns (using the keyboard, *not* the mouse) to change how the song plays. When the snapshot key is released, the original saved state of the patterns is restored.

Holding the "queue" key and then hitting a pattern hot-key will queue an on/off toggle for a pattern when the end of the loop is reached. This is the "queue" functionality. This means that the change in state of the pattern will not take hold immediately, but will kick in when the pattern restarts. This pending state is indicated by coloring the central box of the pattern grey, as shown in the figure below. Please note the "keep queue" functionality and the "one-shot queue" functionality described below.

The coloring for queuing provides dark grey event backgrounds. At the end of the pattern, the left top pattern will turn off, and the right top pattern will turn on. Light-grey coloring is used to show a "one-shot" queue. The one-shot queue can only turn a pattern on, and it will force the pattern off after one play. Queue also works for mute/unmute pattern sets ("groups"); in this case, every sequence will toggle its status after its individual loop ends.

We do **not** recommend using **Ctrl** or **Alt** keys for pattern control. They conflict with application or desktop settings. However, if one insists on such hot-key combinations, use the **Menu** button in the main window to disable the menu. One can also use normal keys to enable queuing. For example, the minus key or the keypad's slash key can be used.

Pressing the "keep queue" hot-key assigned in the "rc" file activates a "sticky" queue mode. In this mode, pressing a pattern key immediately turns on queuing, instead of mute/unmute. And multiple patterns can be handled in this way at the same time. Keep-queue persists until one clicks the normal queue function hot-key, or changes the active (viewed) screen-set. "Keep queue" mode is cancelled by pressing the normal queue hot-key. This hot-key can be changed in the **File / Options / Keyboard / Keep queue** field. There is also a **Q** button for the same purpose. Also note the "queued replace/solo" functionality, described a bit later.

Thanks to *Kepler34*, we have "one-shot queue" functionality. This one-shot setup queues a pattern up for unmuting only, and, once the pattern has played, it is automatically muted. This process is easier than having to unqueue the pattern manually before the next playback. This hot-key can be changed in the **File / Options / Ext Keys / One-shot queue** field.

The "replace" hot-key (the left **Ctrl** key by default, which should be changed to something better), sets a form of muting/unmuting. When the "replace" hot-key is pressed and held while clicking a pattern or pressing that pattern's hot-key, that sequence is unmuted, and all of the other sequences are muted. "Replace" is a form of "solo". "Replace" is also implemented via MIDI control, where the MIDI control can be activated, but then the user has to select the desired sequence.

Sq66 provides an extension to the replace/solo functionality that is called "queued-replace" or "queued-solo". In this feature, when the "keep queue" function is activated, the replace function is queued so that it does not occur until the next time the patterns loop. And queued-replace provides a form of snapshot, limited to the *current* screen-set. Here are the steps:

1. Start playback with some patterns on.
2. Press and release the "keep queue" hot-key. This puts the application into "queue" mode. It is indicated via a "**Q**" button.
3. Press and hold the "replace" hot-key.
4. Click the desired pattern hot-key. Observe that it arms or stays on, and that the other playing patterns show the "queued" color (grey). At the end of the loop, they turn off, and the "replace" pattern is now solo.
5. Click the same pattern hot-key again. Observe that the other patterns that were toggled off are now queued to be toggled on at the next loop. Steps 4 and 5 can be repeated endlessly.
6. To end the "queued-replace" mode, click the normal "queue" hot-key. Also, changing the active screen-set ends "queue-replace" mode. It does *not* end normal queue mode, to preserve the behavior found in *Sq24*. One needs to clear the queue mode in order to select another pattern to solo.

Before pressing the "keep queue" key, patterns 33 ("**q**") and 34 ("**a**") are unmuted, while the desired replace pattern, 32 ("**1**") is off. Then the user presses (and holds) the "replace" key, then clicks the "**1**" key. This puts all unmuted patterns, plus the muted replace pattern as well, into queue mode, as shown by the grey panels. When the progress bar reaches the end of the pattern, pattern 32 will go on, and patterns 33 and 34 will go off. If the replace-pattern is already on, it is not queued, as there's no need to turn it on.

If, while in queue mode, the replace key is held and "**1**" is pressed again, the other patterns will be queued, and will turn on again. Thus, the solo status of the replace pattern can be toggled at will, until queue mode is exited by pressing and releasing the normal "queue" key. If the replace key is *not* held down, and another pattern's replace hot-key is pressed, that pattern will be queued normally. If one wants to change the solo functionality to a different pattern, simple hold the replace key and click on a different pattern. The new arrangement of soloing is memorized. One can clear the queue mode by pressing the normal queue key.

There are more keys defined in the **Keyboard** dialog, and it is worth figuring out what they do, if not documented here. For a couple of short, but good, video tutorials about using arming, queuing, and snapshots, see reference [21].

There is a truer "Solo" functionality in the Patterns Panel and the Song Editor. To "solo" a pattern, move the mouse cursor over the pattern, hold the **Shift** key, and left-click the pattern. This will turn off all the other patterns, so that the selected pattern ins the only one playing. Holding the **Shift** key and clicking the same pattern again will unmute all of the other patterns.

3.2.3.2 Pattern Clicks

Left-click on a pattern-filled box will change its state from muted (white background) to playing (black background), whether the sequencer is playing or not.

Left-click-hold-drag on a pattern, drags it to a different pattern on the grid. The box disappears while dragged, and reappears in the new location when dropped. However, a pattern *cannot* be dragged if its **Pattern Editor** window is open.

Right-click on a pattern brings up the appropriate context menus, as discussed earlier, depending on whether the pattern box is empty or filled.

Middle-click does nothing when the mouse rests inside a pattern box.

3.3 Patterns / Bottom Panel

The bottom panel of the Patterns window provides way to control the overall playback of the song. It has changed quite a bit over the last few versions of *Seq66*, and we have not yet caught up with the diagrams. And the Qt user-interface adds more changes. Refer to the diagram of the whole window, for now. It has a number of items:

1. **Panic!**
2. **Stop**
3. **Play and Pause**
4. **Song Record**
5. **Song Record Snap**
6. **BPM**
7. **Tap Tempo**
8. **Log Tempo**
9. **Record Tempo**
10. **Keep-Queue Status**
11. **Name**
12. **Set**
13. **Toggle Song Editor**

1. Panic!. This new button stops the song and sends MIDI Off messages on all notes.

2. Stop. The red square button stops the playback of the song and all its patterns. The keystroke for stopping playback is the **Escape** character. It can be changed to **Space**, so that the space-bar then becomes effectively a playback toggle key.

3. Play and Pause. The green triangular button starts the playback of the whole song. The keystroke for starting playback is the **Space** character by default.

The Play button can be used as a Pause button. When the Play button is clicked, the button icon changes to a Pause icon: A Pause key (by default, the period) is also defined.

4. Song Record. Song-recording in *Seq66* is adopted from the *Kepler34* project. This feature takes live muting changes and records them as triggers in the **Song Editor**. The default hot-key for this function is P. This feature does not honor queuing... rather than waiting until the end of the pattern when the queuing takes effect, the trigger recording starts immediately.

5. Song Record Snap. This button toggles snapping the beginning and end of a recorded trigger to the nearest beat. There is no hot-key for this button at this time.

6. BPM. The spin widget adjusts the "beats per minute" (BPM) value. The range of this field is from 1 bpm to 600 bpm, with a default value of 120 bpm. Although this field looks editable, it is not. Most keystrokes that are entered actually toggle one of the pattern boxes. However, the following keys can also modify the BPM in small increments: The **semicolon** reduces the BPM; The **apostrophe** increases the BPM. Also, if one right-clicks on the Up button, the BPM advances to its largest supported value, and if one right-clicks on the Down button, the BPM advances to its lowest value. MIDI control for this value is also available.

The precision of the BPM value can be set to 0, 1, or 2 decimal places, and the increment values for the step size (small) or page size (large) of the BPM spinner can be configured in the 'usr' file.

7. Tap Tempo. This control is clicked in time with a tune, to set the tempo based on the tempo of the clicks. Once clicked, the label of this button increments with every click, and the **BPM** field updates to display the calculated tempo. If the user stops tapping for 5 seconds, the label reverts to 0, the BPM value keeps its final value, and the user can try tapping the tempo again, or accept the current value. Tapping can also be done using the keystroke defined in the 'ctrl' file. It defaults to the "F9" key.

8. Keep-Queue Status. This item is the **Q** button. It provides a visual way to know the current state of keep-queue, and is activated either by clicking on it or by pressing the assigned keep-queue key.

9. Name. Each of the 32 available screen-sets can be given a name by entering it into this field. This name is saved with the MIDI file.

10. Set. This spin widget selects the current screen-set. The values in this field range from 0 to 31 (less if the set-size is a larger value), and default to 0.

11. Toggle Song Editor. Pressing this button toggles the presence on-screen of the **Song Editor**. The **Ctrl-E** keystroke can also be used.

3.4 Patterns / Multiple Panels

Multiple patterns-panels can be created.

Note that Page Up and Page Down keystrokes, as well as their configurable counterparts in **File / Options / Keyboard / Control Keys / Screenset Up** and **Screenset Down**, apply only to the top leftmost "mainwid". Of course, if the "mainwids" are synced, then all are affected by these keystrokes.

In multi-wid mode, each "mainwid" frame shows the corresponding set number and, if present, the set notepad text for each "mainwid" set.

The **-o wid=3x2,i** option can be used to set this mode. These settings can be made permanent in the 'usr' file. In that file, the options modified are **block_rows** and **block_columns**.

3.5 Patterns / Variable Set Size

This option, informally known as "variset", allow some changes in the set size and layout from the default $4 \times 8 = 32$ sets layout. The row count can be set from 4 to 8, and the column count can be set to 8 to 12. Note that the set size can only be *increased* by these settings.

Warning: seq24 was fairly hardwired for supporting 32 patterns per set, and there are still places where that is true. Thus, consider this option to be experimental.

The `-o sets=8x8` option can be used to set this mode. These settings can be made permanent in the 'usr' file. In that file, the options modified are `mainwnd_rows` and `mainwnd_cols`.

Generally, it is recommended to stick with the 4x8 (32 patterns/set), 8x8 (64 patterns/set), and 8x12 (96 patterns/set). This works best with the existing set of 32 hot-keys.

Also note that the Qt 5 user-interface also supports "variset", whether in the main window or in the external live-frame. In addition, both Qt windows can be resized and still show good renditions of the pattern-slots.

4 Pattern Editor

The **Seq66 Pattern Editor** can edit and preview a pattern, configure its buss, channel, transpose, musical scale, and many other settings. A rudimentary version of the **Pattern Editor** appears in the **Edit** tab in the main window, and a more powerful version can be brought up in an external window.




Figure 13: External Pattern Editor Window

The **Pattern Editor** is complex, and we will discuss the external window only since its features are a superset of the **Edit** tab. For exposition, we break the window into the following sections:

1. First Row
2. Second Row
3. Time
4. Piano Roll

- 5. **Events**
- 6. **Data View**
- 7. **Bottom Row**
- 8. **Common Actions**

Before we describe this window, there are some things to recognize. First, if the pattern is empty when play is started, the progress bar will still move, so that the user can play a MIDI instrument and record new notes. Second, to add a note with the mouse, one must press the *right* mouse button (the pointer changes to a pencil) and, *while holding it*, press the left mouse button. Or click in the pattern editor, press the **p** key to select the "pencil" or "paint" mode, then left-click to add a note or left-click-drag to add multiple notes as the mouse moves. Press or release the right mouse button, or press **x** to "eXit" or "eXscape" from paint mode. Another option is to press the "hand" button to toggle between note-entry and note-selection. Third, notes are drawn only with the length selected by the "notes" button near the top of the pattern window. There are tricks to modifying the new notes that are described later.

Sq66 automatically scrolls horizontally through the sequence/pattern editor window when playback moves the progress bar outside of the current frame of data. This feature makes it easier to follow patterns that are longer than a measure or two.

One might want to print out the following figure to follow along. There is a lot of functionality in this window.




Figure 14: Pattern Editor Window, Annotated

4.1 Pattern Editor / First Row

The top bar (horizontal panel) of the Pattern (sequence) Editor lets one change the name of the pattern/loop/sequence/track, the time signature of the piece, how long the track is, and some other configuration items.

1. Track Number
2. Track Title
3. Beats Per Bar Reset and Beats Per Bar
4. Beat Width Reset and Beat Width
5. Pattern Length Reset and Pattern Length
6. Chord Types

7. Buss Reset and Buss Selection

8. Channel Reset and Channel Selection

1. Track Number. This item shows the sequence/track/pattern/loop number, to make it easier to pick it out when a lot of patterns are being edited at once.

2. Track Name. Provides the name of the pattern. This name should be short and memorable. It is displayed in the **Live Grid** (the **Patterns Panel**), on the top line of its pattern slot.

3. Beats Per Bar. Specifies the number of beat units per bar in the time signature. The possible values range from 1 to 16, if the drop-down menu is used. Arbitrary values up to 32 can be entered by typing the number. The "Reset" button resets the value to 4.

4. Beat Width. Specifies the size of the bottom beat unit of the time signature: 1 for whole notes; 2 for half notes; 4 for quarter notes; 8 for eighth notes; 16 for sixteenth notes; and 32 for thirty-second notes. The whole time signature is displayed at the bottom center of the corresponding pattern slot in the **Live Grid**. Arbitrary values up to 32 can be entered by typing the number. The "Reset" button resets the value to 4.

5. Pattern Length. Sets the length of the current pattern, in measures. The possible values range from 1 to 64. Arbitrary values up to 1024 can be entered by typing the number. However, when opening or importing a non-*Seq66* MIDI tune, the length of each track will be used, and so other values are possible.

Bringing up a pattern less than one measure or bar in length in the pattern editor will adjust the pattern to pad it to the length of one measure. *Seq66* will, when it reads such a short pattern from a MIDI file,

A feature from user *stazed* allows the pattern to expand indefinitely while the user inputs MIDI from a controller, via the **Expand** option of the **Loop Record Type**.

6. Chord Types. This setting allows one to select a chord type (e.g. "major" or "minor"). When active, a note is treated like the base note of the selected chord type, and extra notes are generated to create that chord. The **Chord Generation Reset** button is at the left of the **Data View**.

7. Chord Generation.

8. MIDI Out Device (Buss). This setting specifies a virtual MIDI output buss or a MIDI output device set up by the computer and attached MIDI equipment. The button resets it to buss 0. Note that, if the pattern's selected buss is not found, this entry will be blank. The user must select a valid buss from this dropdown.

9. MIDI Out Channel. These settings select the MIDI output channel. The possible values range from 1 to 16. If instruments are assigned in the 'usr' configuration file to that device and channel, their names will be shown in the dropdown.

4.2 Pattern Editor / Second Row

The second horizontal panel of the Pattern Editor provides a number of additional settings and functions:

1. Undo

2. Redo

3. Quantize Selection

4. Tools Popup
5. Follow Progress
6. Reset Snap and Grid Snap
7. Note Length Reset and Note Length
8. Zoom Reset and Zoom
9. Key Reset and Key of Sequence
10. Scale Reset and Musical Scale
11. Background Sequence

1. Undo. The **Undo** button rolls back any changes to the pattern from this session. It will roll back one change each time pressed. Pressing **Ctrl-Z** is the same as using the **Undo** button.

2. Redo. The **Redo** button will restore any undone changes to the pattern from this session. It will restore one change each time it is pressed. There is currently no redo key.

3. Quantize Selection. This button quantizes the selected events as per the **Grid Snap** setting.

4. Tools. This button brings up a nested menu for modifying selected events and notes:

1. **Select.** This menu provides two sets of selections for notes:

- **All Notes**, which selects all notes in the pattern; The **Ctrl-A** will also select all of the events in the pattern editor.
- **Inverse Notes**, which inverts the selection of notes.

2. **Modify Time.** This menu offers two ways to tweak the timing of the selected note:

- **Quantize Selected Notes** quantizes the selected notes, the same way as the **Quantize ("Q")** button.
- **Tighten Selected Notes**, which is merely a less strict form of quantization.
- **Modify Pitch** has only one entry by default, **Transpose Selected**. Selecting the **Transpose Selected** entry brings up a sub-menu. If the user has selected a **Musical Scale** setting other than **Off**, then **Modify Pitch** has two entries:
 - **Transpose Selected**, discussed above, plus another sub-menu,
 - **Harmonic Transpose Selected**, which makes sure that all transpositions stay on the selected scale. Again, the harmonic-transpose option will not be available unless a scale has been selected.

5. Follow Progress. This button toggles whether or not the progress bar follows progress in long patterns. Turning off this feature is useful when one wants to concentrate on the current measure without the paging to subsequent measures that occurs with the "follow progess" feature.

6. Grid Snap. Grid snap selects where the notes will snap when drawn. That is, it selects the snap-spacing for the notes. The following values are supported: **1, 1/2, 1/4, 1/8, 1/16** (*the default value*), **1/32, 1/64**, and **1/128**. Additional values are also supported: **1/3, 1/6, 1/12, 1/24, 1/48, 1/96**, and **1/192**. The button to the left of this control resets it to the default value.

7. Note Length. Note length determines the duration of inserted notes. Like the **Grid Snap** values, the following values are supported: **1, 1/2, 1/4, 1/8, 1/16** (*the default value*), **1/32, 1/64**, and **1/128**. Additional values are also supported: **1/3, 1/6, 1/12, 1/24, 1/48, 1/96**, and **1/192**. The button to the left of this control resets it to the default value.

8. Zoom. Horizontal zoom is the ratio between MIDI pixels and ticks, written as "pixels:ticks", where "ticks" is the "pulses" in "PPQN". For example, **1:4** = 4 ticks per pixel. Supported values are **1:1, 1:2** (*the default value*), **1:4, 1:8, 1:16**, and **1:32**, along with more values to support higher

PPQN tunes: **1:64**, **1:128**, **1:256**, and **1:512**. The default zoom is 2 for the standard PPQN value, 192, but it increases for higher PPQN values, so that the default zoom looks sensible. As the right number (ticks) goes higher, the effect is to zoom out, and show more of the pattern.

9. Key of Sequence. Selects the desired musical key for the pattern. The following keys are supported: **C**, **C#**, **D**, **D#**, **E**, **F**, **F#**, **G**, **G#**, **A**, **A#**, and **B**. Changing the key shifts the marked note-rows for the **Musical Scale** setting and indicates the base notes of the key in a **bold** font. The small key button resets the key to **C**.

The musical key that a sequence/pattern is set to is saved in the MIDI file along with the rest of the data for the sequence. **However**, a change made to the key, scale, or background sequence in the pattern editor can be saved in the whole song, so that opening another sequence will apply the same settings to that sequence. This is an optional feature, supported as noted below.

If the global-sequence feature is enabled, and the user selects a different key, scale, or background sequence in the pattern editor, then *all* patterns share the selected key, scale, or background sequence. Furthermore, these settings are saved in the "proprietary" section of the MIDI file, where they are available for all patterns.

If the global-sequence feature is *not* enabled, and the user selects a different key, scale, or background sequence in the pattern editor, then only that pattern will use the selected key, scale, or background. The key, scale, or background sequence change will be saved in the MIDI file only for that pattern, as a SeqSpec meta event. The global-sequence feature setting can be made in the 'usr' configuration file.

10. Musical Scale. Selects the desired background scale for the pattern; it provides a way for someone to key in notes that are only in that scale. When a scale is selected, the following features are supported:

- The notes that are *not* in the scale are shown as grey in the piano roll.
- For harmonic transposition, the notes are shifted so that they remain in the selected scale.
- The exact notes that are considered "in-scale" shift according to the value of the selected **Key of Sequence**.

The following musical scales are supported:

- **Off (Chromatic)**
- **Major (Ionian)**
- **Minor (Aeolian)**
- **Harmonic Minor**
- **Melodic Minor**
- **Whole Tone**
- **Blues**
- **Major Pentatonic**
- **Minor Pentatonic**

Please let us know of any mistakes in the new scales. Note that the **Melodic Minor** scale is supposed to descend in the same way as the natural **Minor** scale, but there is no way to support that trick in *Seq66*.

One can select which **Musical Scale** and **Key** the piece is in nominally, and *Seq66* will grey those keys on the piano-roll that are *not* in the selected scale for the selected key. This is purely

visual; a user can still add off-key notes. This feature makes it easier to stay in key while playing and recording. The scale will shift when a different **Key** is selected.

The scale that a pattern is set to is saved in the MIDI file along with the rest of the data for the pattern. A change made to the key, scale, or background pattern in the pattern editor can be saved globally, so that opening another pattern apply the same settings to that pattern. This is a configurable feature in the 'usr' file; see "global_seq_feature". This option allows applying the key/scale/background-sequence either globally (all patterns) or locally (per-pattern), with each pattern holding its key, scale, and background-sequence settings in SeqSpec meta events.

11. Background Sequence. One can select another pattern to draw on the background to help with writing corresponding parts. The button brings up a small menu with values of **Off** and **Set 0** (at a minimum). The 0 is a set number; sets are numbered from 0 to 31. Additional set numbers appear in the menu for each set that has data in it. Under the **Set 0** entry, a menu appears. Once the desired pattern is selected from that list, it appears as dark cyan note bars, along with the normal notes that are part of the pattern.

The background sequence that shows is saved in the MIDI file along with the rest of the data for the sequence/pattern. A change made to the key, scale, or background sequence in the pattern editor is saved in the editor, so that opening another sequence will apply the same settings to that sequence. This is an optional feature, as noted earlier.

12. Chord Generation. One can insert chords with one click. (This feature comes from user "stazed" and his Seq32 project [17].) Select the desired chord type first. Once a value other than **Off** is selected, drawing mode will add multiple notes representing the chord created, with the clicked note value as the base of the chord.

4.3 Pattern Editor / Piano Roll

The piano roll is the center of the pattern/loop/track/sequence editor. It is accompanied by a thin "event bar" ("event area", "event strip") just below it, and a taller "data bar" or "data area" just below that. While the pattern editor is very similar to note editors in other sequencers, it is a bit different in feel. A good mouse with at least 3 buttons is very helpful for editing. Buttons and keystrokes support enhanced editing.

When the piano roll has keyboard focus, the **Space** key starts and stops playback, rewinding to the beginning when stopped. The **.** (period) key starts and pauses playback, without rewinding. This functionality is similar to that of the main window, but these keys are not reconfigurable in the piano roll.

One can page vertically in the piano roll using the **Page Up** and **Page Down** keys. One can go to the leftmost position using the **Ctrl-Home** key, and to the rightmost position using the **Ctrl-End** key,

With the note-step feature, if one paints notes with the mouse, the note position advances with each click. If one paints notes via an external MIDI keyboard, the notes are painted and advanced. To preview notes entered via a MIDI device, click the **pass MIDI in to output** button to activate so that they will be passed to the sound generator or software synthesizer.

4.3.1 Pattern Editor / Piano Roll Items

The center of the pattern editor consists of a time panel at the top, a virtual keyboard at the left, a note grid, a vertical scrollbar, an event panel, and a data panel at the bottom.

1. Beat
2. Measure
3. Virtual Piano Keyboard
4. Notes

1. Beat. The light vertical lines represent the beats defined by the configuration for the pattern. The even lighter dotted lines between the beats are useful for snapping notes.

2. Measure. The heavy vertical lines represent the measures (bars) defined by the configuration for the pattern. Also note that the end of the pattern occurs at the end of a measure, and is marked by a blocky **END** marker.

3. Virtual Piano Keyboard. The virtual keyboard is a fairly powerful interface. It shows, by shadowing, which note on the keyboard will be drawn. It can be played with a mouse, using left-clicks, to preview a short motif. Every octave, a note letter and octave number are shown, as in "C4". If there is a difference scale in force, then the letter changes to match, as in "F#5".

A right-click in the virtual keyboard area toggles the display between octave-note letters, MIDI note-numbers, and other views. The following figure shows all views, superimposed for comparison.




Figure 15: Virtual Keyboard Number and Note Views

4. Notes. Musical notes are indicated in the piano roll by thick horizontal bars with white centers. Each bar provides a visual representation of the pitch of a note and the length of a note. The current scale and background pattern can also be shown in the piano roll.

5. Time Scroll. Allows one to pan through the whole pattern, if it is too long to fit in the window horizontally.

4.3.2 Pattern Editor / Note Painting

When we say "editing" in the context of the piano roll, in part we mean that we will "draw" or "paint" notes. Drawing, modifying, copying, and deleting notes is easy in *Seq66*.

The *Seq24* note-editing style is as expected for basic actions such as selecting and moving notes using the left mouse button. Drawing a note or event is a bit different, in that one must first enter the drawing mode ("paint mode"). One way is to *click and hold* the right mouse button, and then

click and drag the mouse to insert notes. Note that some *Seq66* windows can use the *Ctrl-left-click* as a middle click. Another way is to use the **p** key to enter the "paint" mode. To get out of the "paint" mode, press the **x** key while in the sequence editor. Also available is a "finger" button (**Note Select/Note Entry**) to click to toggle the mode.

Notes are inserted to be at the current length and grid-snap values for the sequence editor for as long as the buttons are pressed while the mouse is dragged. The length of the note will be that specified in the note-length setting (e.g. "1/16"). This is the "auto-note" feature. The auto-note feature also works with chord-generation. Notes are inserted only up to the specified sequence length. Once notes are inserted, moving the mouse with the left button still held down moves the notes to the new note value of the mouse. If one releases the left button, then presses and holds it again, more notes will be added in the same way. This is a good way to layer notes in a short sequence. The draw mode has the following features:

- Notes are continually added as the mouse is dragged ("auto-notes").
- Notes cannot be added past the "END" marker of the pattern, which marks the **Sequence Length in bars** setting.
- As the mouse is dragged while the left button is held in draw mode, notes are either added, or, if already present at that note-on time, are moved up and down.
- If the draw mode is exited, and entered again, then the original notes will not be altered. Instead, new ones will be added.
- Notes can be added while the pattern is playing, and will be heard the next time the progress bar passes over them.

Drawing/painting can also be done while the sequence is playing, and notes will be added to be played the next time the progress bar crosses them.

4.3.3 Pattern Editor / Note Editing

Once notes are in place, whether by recording or using "paint" mode, the piano roll provides a sophisticated set of note-editing actions.

1. Event Selection. There are various ways to select events using the mouse or the keyboard in the piano roll:

- **Ctrl-A.** Pressing the **Ctrl-A** key will select all of the events in the pattern editor.
- **Left Click.** Pressing the left button on a note or a event deselects all other notes or events, and selects the item clicked on. The selected note will turn orange (or the configured palette color).
- **Left Click Drag.** Pressing the left mouse button and dragging also lets one select ("lasso") multiple events and notes. The selected notes will turn orange. Adjustments can be made to one or more notes by selecting one or more notes, and then applying one or more special "selection actions" to the selection. Be careful! If you **Ctrl-left-click-drag** on an already-selected note, the drag will change the length of *all of the notes in the selection*.
- **Ctrl Left Click.** Pressing the **Ctrl** key and the left button on a note or an unselected event adds that event to the selection.
- **Left Click Drag Selection Up/Down.** To move notes in pitch, once selected, grab one of the notes in the selection and drag it upward or downward. Also, when a selection is in force,

the Up and Down arrow keys will change the pitch of every note in the selection. The smallest unit of pitch change is one MIDI note value.

- **Left Click Drag Selection Left/Right.** To move notes in time, once selected, grab one of the notes in the selection and drag it leftward or rightward. Also, since a selection is in force, the **Left** and **Right** arrow keys can also be used to change the time of every note in the selection. The smallest unit of time change is the **Grid snap** value, which might be a 16th note, for example.
- **Ctrl Left Click Drag.**
 - Pressing the **Ctrl** while left-click-dragging *on unselected events* lets one make additional selections of multiple events and notes.
 - Pressing the **Ctrl** while left-click-dragging *on an already-selected event* lets one stretch or compress the lengths of all notes in the selection. This feature is called *event stretch* or *event compression*. Notes can be shortened below the default note length by event compression. There is currently no way to change the length of the note using a keystroke.
- **Deselect Notes.** To deselect the notes, click somewhere else in the piano roll, and the notes should change back to white. There is no way to deselect a single note, with, say, a **Shift-click** or **Ctrl-click** action.

Warning: Reducing or increasing the length of a note selection by too much causes the note or notes to "wrap-around" to the end of the pattern boundary and grow more from the beginning of the sequence. If it happens, one probably ought to undo it.

The **Tools** button described in section [4.2 "Pattern Editor / Second Row"](#) on page [42](#) can also be used to modify selections. Once one or more notes are selected, they can be modified in time, pitch, or length, as described above.

Warning: If one moves the selection too low or too high in pitch, whether with the mouse or the arrow keys, any notes that go below the lowest MIDI pitch or above the highest MIDI pitch **will be lost!** If done using the mouse, the undo feature (**Ctrl-Z**) will work. If done using the arrow keys, the undo feature does not work! Be careful, especially if you have a fast keyboard repeat rate!

Note that there is no possibility of note loss with a change in time. When a note disappears at one end of the pattern boundary, it wraps around to the other end. Cool.

2. Copy/Paste. Copying, cutting, and pasting is supported by selecting a number of events or notes, and using the **Cut** (**Ctrl-X**), **Copy** (**Ctrl-C**), and **Paste** (**Ctrl-V**) keys. When the notes are selected, one can delete them with the **Delete** or **Backspace** key. If the events are *cut*, using the **Ctrl-X** key, then they can be *pasted*, using the **Ctrl-V** key, then moving the cursor to the desired place, and clicking.

One can move the selection box using the arrow keys, to the desired location, and then click to drop the notes at that location. Selected notes that are cut or copied can also be pasted into *other* pattern editor dialogs; that is, they can be pasted into other sequences.

4.3.4 Pattern Editor / Zoom Keys

After a left-click in the piano roll, the **z**, **Z**, and **0** can be used to zoom the piano-roll view *horizontally*. The **z** key zooms out (smaller), the **Z** key zooms in (larger), and the **0** key resets the zoom to the

default value. The horizontal zoom feature also affects the time-line (measures indicator) and the data area.

The note display can also be zoomed vertically. The **v** key zooms out vertically to make the notes thinner, the **V** key zooms in vertically to make the notes fatter, and the **0** key resets the zoom to the value of the "key height" setting in the 'usr' configuration file.

4.4 Events Editor

Also known as the "events pane" or "events panel". The narrow (a few pixels high) events strip shows discrete events, such as **Note On** and **Note Off**. These and other events appear as small squares in the event strip, along with a black vertical bar in the **Data View** with a height proportional to the data-value of the event and a numeric representation of that value. The event value (data) editor (directly under the event strip) is used to change note velocities, channel pressure, control codes, patch select, etc.

*We currently recommend being careful of editing or selecting events in that pane (feel free to disobey), because **more work is needed**.* Note events should not be inserted in the event strip; it is too easy to screw up. In fact, selection and editing is disabled for **Note On**, **Note Off**, and **Aftertouch**.

Other event types can be inserted via the event strip. To do that, first select the kind of event to insert using the **Event** button in the bottom panel. Then place the mouse cursor in the event strip. Right-click to make the drawing cursor appear at the exact spot where the event must go. While holding the right button, click the left button. A small square for the event will appear.

One can also left-click in that section, then hit the **p** key to go into "paint" mode, and hit the **x** key to escape that mode.

Should one want more of the same event, continue to hold both buttons and drag the mouse. One event should appear at each beat (16th note) position that is crossed.

To move the event(s) to a different spot, select it/them via the left button. Then drag the selection as desired. It is currently not possible to move them to positions smaller than the beat size; temporarily reduce the beat size if desired.

4.5 Data View

Once the events are in place, the next step is to modify the data values of the events as needed. But first, note the buttons at the left.

1. **Transpose**
2. **Drum Note Mode**
3. **Chord Generation Reset**

1. Transpose. This button toggles the ability of the sequence to be transposed. If transpose is enabled for that pattern, the button will be highlighted as per the current desktop theme. Patterns for drums should, in general, not be transposable.

2. Drum Note Mode. This button changes from normal note mode to drum note mode. In the drum mode, the notes are drawn as small red diamonds without any duration. They are also entered the same way. This is a feature adopted from *Kepler34*.

3. Chord Generation. This button resets the chord-generation feature to **Off**. It's located by the data pane in order to save space in the first row.

Now on to the **Data View** itself. Also known as the "data pane" or "data panel". **Modify Event Data** offers a way to alter the event data values in the lower pane of the pattern editor, the "data pane".

The events values for the currently selected category of events are shown in this window as vertical lines of a height proportional to the value. These values can be easily modified by left-click-dragging the mouse past each line, to chop it off at the given value. Easier to try it than explain it. Right-click-drag also works the same. When notes are selected, and the mouse is used to change the values (heights) of the lines in the event-data area, *only the events that are selected* are changed. The data-values of *unselected* events are left unchanged. A cool feature from Seq24.

Any events that are selected in the piano roll or event strip can have their values modified with the mouse wheel.

Data values can also be modified using the **LFO** pane.

4.6 Pattern Editor / Bottom Row

The bottom row of the pattern editor provides for selecting events for viewing and editing, MIDI playback, pass-through, and recording.

1. **Event Category Selector**
2. **Selector for Existing Data**
3. **Selected Event Name**
4. **LFO Panel**
5. **Armed/Muted Toggle** (Data To MIDI Buss)
6. **MIDI Thru Toggle**
7. **MIDI Record Toggle**
8. **MIDI Record Quantized**
9. **Loop Record Type** (Merge, Replace, Expand)
10. **Record Velocity and Reset**

1. Event Category Selector. This button brings up the following context menu, so that the user can select the category of events to view and edit.




Figure 16: Pattern Editor Event Button Context Menu

Note the squares. Some might be filled (black), most are empty. Filled squares indicate that the sequence has some events of that type. Otherwise, there are no such events in the sequence. Useful in deciding if it is worth selecting the event.

The sub-menus of this context menu show 128 MIDI controller messages. They also use the squares to indicate if there are any events of the type shown in the menu. These sub-menus can be modified by editing the 'usr' file:

```
$HOME/.config/seq66/seq66.usr
```

to make it match one's instrument.

2. Existing Event Menu. The existing-event selector is a small button (with a black-square icon) that brings up a menu with only existing events shown. Unlike the event-selector described above, this menu shows only the actual events existing in the track, for quicker selection.

3. Event Selection. Shows the selection event, with its event number shown in hexadecimal notation, and the name of the event shown.

4. LFO. A low-frequency oscillator allows data events can be modulated by some rudimentary wave functions. By clicking on the **LFO** button or using the **Ctrl-L** key, the following window appears, with a set of 4 vertical sliders:




Figure 17: Pattern Editor LFO

1. **DC Offset.** Provides a kind of DC offset for the data value. Starts at 64, and ranges from 1 to 127.
2. **Mod Range.** Controls the depth of modulation. Starts at 64, and ranges from 1 to 127.
3. **Periods.** Indicates the number of periods per pattern length. For long patterns, this parameter should be set high, to even show an effect. It is also subject to an 'anti-aliasing' effect, especially for short patterns. Try it! For short patterns, try a value of 1 at first. For a pattern of one measure in length, this will create one period of the wave.
4. **Phase Shift.** Provides the phase shift within a period of the LFO wave. A value of 1 is a phase shift of 360 degrees (or maybe it is one radian?).
5. **Use Measures.** If checked, a measure is used to calculate the periodicity of a change, rather than using the whole length of the sequence.
6. **Wave Type.** Selects the kind of wave to use for the LFO:
 1. **None.** This setting is useful if one wants to change only the DC offset.
 2. **Sine.**
 3. **Sawtooth.**
 4. **Reverse Sawtooth.**
 5. **Triangle.**
7. **Reset Data.** This button restores the initial event data. Useful when one applies modulation that one ultimately does not like.
8. **Close.** Closes the LFO panel.
5. **Armed/Mute Toggle.** This button causes the pattern to be output to the selected MIDI output bus, which will normally be connected to a software or hardware synthesizer, to be heard. This item performs muting/unmuting (disarming/arm) in the same way as pressing the corresponding pattern button in the **Live** frame.
6. **MIDI Thru Toggle.** This button routes incoming MIDI data through *Seq66*, which then writes it to the MIDI output bus.

7. MIDI Record Toggle. This button routes incoming MIDI data into *Seq66*, which then saves the data to its buffer, and also displays the new information (notes) in the piano roll view.

8. MIDI Record Quantized. This button will cause MIDI data to be recorded, but be quantized on the fly before recording it. The quantization is to the current snap value.

9. Loop Record Type. In *Seq24*, the pattern recording worked by merging new notes played as the pattern to be recorded was looped. This method allows a loop to be built up bit-by-bit. *Seq66* adds two more methods from Stazed's *Seq32* project. The three methods are:

1. **Merge.** This is the normal style of recording loops, where notes can accumulate.
2. **Replace.** When the loop starts over, and a note is pressed, then the existing notes in that loop are erased, and the new note is added. This provides a good way of correcting major mistakes, live. It will not work if adding notes while not recording. This mode can cause incomplete notes if one holds the note and releases it in the next iteration, leaving a partially-drawn note behind. The workaround is to try again.
3. **Expand.** Once the end of the loop is near, whether or not any notes are being input, another measure is added to the length of the loop. This continues indefinitely, whether or not any notes are being played/recorded.

10. Vol. This button allows setting the volume of the recording. The velocity of the notes will be set to the selected value upon recording. The velocity values are shown at the right side of each menu entry. These values correspond to MIDI volume levels from 127 down to 16, as shown in the figure. If the **Free** item is selected, then the incoming note velocity is preserved.

4.7 Pattern Editor / Common Actions

This section is a catch-all for actions not described above.

4.7.1 Pattern Editor / Common Actions / Scrolling

We are still trying to work whether or not to enable this feature in *Seq66*.

Let us describe the actions that can be performed with a scroll wheel, or with the scrolling features of multi-touch touchpads. There are three major scrolling actions available when using mouse scrolling, with the mouse hovering in the piano-roll area:

- **Vertical Panning (Notes Panning)** Using the vertical scroll action of a mouse or touchpad moves the view of the sequence/pattern notes up and down. One can also click in the piano roll, and then use the **Page-Up** and **Page-Down** keys to move the view up and down in pitch.
- **Horizontal Panning (Timeline Panning)** Holding the **Shift** key, and then using the vertical scroll action of a mouse or touchpad moves the view of the sequence/pattern time forward and backward. One can also click in the piano roll, and then use the **Shift Page-Up** and **Shift Page-Down** keys to move the view left and right in time.
- **Horizontal Zoom (Timeline Zoom)** Holding the **Ctrl** key, and then using the vertical scroll action of a mouse or touchpad zooms the view of the sequence/pattern time to compress it or expand it. One can also click in the piano roll, and then use the **z** , **Z** , and **0** keys to change the timeline zoom.

The actions of this scrolling are smooth and fast. If an event is selected in the piano-roll area or the (thin) event area, then the scrolling increases or decreases the value of the event. In the case of

a note, this increases or decreases the velocity of the note. For all events, this increases or decreases the length of the vertical line that represents the value of the event.

4.7.2 Pattern Editor / Common Actions / Close

There is no **Close** button in the pattern editor. One can use window-manager actions, such as clicking on the **X** button of the window frame, or pressing the exit key defined in the window manager.

5 Song Editor

The *Seq66 Song Editor* combines all patterns into a complete tune with specified repetitions of each pattern. It shows one row per pattern/loop/sequence, with the placement of each pattern at various time locations in the song. In *Seq66* parlance, the song editor creates a *performance*, and the performance is implemented by a set of triggers. Triggers are internal timing items stored with each pattern when a *Seq66* MIDI tune is saved. In **Song** mode, these triggers, not the user, control playback.

Two song editor windows can be brought onscreen, as a convenience for arranging projects with a large number of sequences/patterns. The **Song** tab and a **Song** window can be shown at the same time. The **Song** editor activates the **Song** mode of *Seq66*. Once playback is started in the song editor (using the **Space** or **.** keys), some actions in the patterns panel no longer have effect, disabling live mode. The song editor takes over the arming/unarming (unmuting/muting) shown in the patterns panel. The highlighting of armed/unarmed patterns changes according to whether the pattern is triggered in the song editor, or not. If one tries to change the muting in the patterns panel, the song editor immediately returns the pattern to the state it has in the song editor. The only way to manually change the muting then is to click the pattern's label in the song editor. Both the song editor and the patterns panel both reflect the change in muting in the user-interface (though with *opposite colors*).




Figure 18: Song Editor Window, Annotated

Note the major items shown:

1. **Top Panel**
2. **Measures Ruler**
3. **Patterns (Names) Panel**
4. **Song Roll**
5. **Bottom Panel**

Here are some of the features for the song editor:

- Toggling of the mute state of multiple patterns via the name fields of the patterns.
- Optional pattern coloring (selected in the Patterns panel)
- A configurable progress bar.
- **Undo** and **Redo** buttons.
- A **Transpose** button and transposition drop-down selector.
- Red coloring of events for patterns that are not transposable, such as drum tracks.
- Horizontal zoom via buttons and keystrokes

The song editor is not too complex, but for exposition, we break it into the sections enumerated above.

5.1 Song Editor / Top Panel

The top panel shown earlier provides quick access to actions and configuration.

1. **Undo**
2. **Redo**
3. **Follow Progress**
4. **Zoom Out and Zoom In**
5. **Toggle Section Painting**
6. **Grid Snap**
7. **Transpose**
8. **L/R Loop**
9. **L/R Collapse**
10. **L/R Expand**
11. **L/R Expand and Copy**

1. Stop. Stops the playback of the song. The keystroke for stopping playback is the **Escape** character. It can be configured to be another character (such as **Space**, which would make the space-bar toggle the playback status).

2. Play. Starts the playback of the song, starting at the **L marker**. The **L marker** serves as the start position for playback in the song editor. One can change the start position only when the performance is not playing. The default keystroke for starting playback is the **Space** character. The default keystroke for stopping playback is the **Escape** character. The default keystroke for pausing playback is the **Period** character.

Note that there are no stop, pause, and play buttons in this frame. They are supplied by the main window, and the **Song** tab can be activated in the main window.

3. Undo. The **Undo** button rolls back the last change in the layout of a pattern. Each time it is clicked, the most recent change is undone. Also implemented via **Ctrl-Z**.

4. Redo. The **Redo** button reapplies the last change undone by the **Undo** button. Also implemented via **Shift-Ctrl-Z**.

5. Zoom Out and Zoom In. These buttons change the horizontal zoom. Zoom can also be changed via the keystrokes **z**, **0**, and **Z**.

6. Follow Progress. **Follow Progress** toggles the mode of following progress for longer songs. When active, the song roll pages right to keep up with the progress bar.

7. Toggle Section Painting. **Toggle Section Painting** toggles the ability to drag the mouse along the pattern's timeline to create triggers to indicate when the pattern plays. Short patterns will be duplicated one or more times as the mouse is dragged. This mode can also be changed via the keystrokes **p** and **x**.

8. Grid Snap. Indicates the horizontal grid snap for movement actions and trigger drawing. Grid snap determine where the pattern boundaries are drawn. Unlike the **Grid Snap** of the pattern editor, the units of the song editor snap value are in fractions of a measure length. The following values are supported: 1, 1/2, 1/4, 1/8, 1/16, and 1/32.

9. Transpose. **Transpose** consists of two controls: one to apply transposition, and a drop-down menu to select the direction and amount of transposition. Transposition ranges from minus one octave to plus one octave.

10. L/R Loop. Activates loop mode. When play is activated, plays the song and loop between the **L marker** and the **R marker**. This button is a state button, and its appearance indicates when it is depressed, and thus active. If this button is deactivated during playback, then playback

continues past the **R marker**. Note that these markers can be placed using left and right mouse clicks, respectively, in the measures ruler.

11. L/R Collapse. This button collapses the song between the **L marker** and the **R marker**. What this means is that, if there is song material (patterns) before the **L marker** and after the **R marker**, and the **Collapse** button is pressed, any song material between the L and R markers is erased, and the song material after the **R marker** is moved leftward to the **L marker**. Collapsing occurs in all tracks present in the song editor.

12. L/R Expand. This button expands the song between the **L marker** and the **R marker**. It inserts blank space between these markers, moving the song material that is after the **R marker** to the right by the duration of the blank space. Expansion occurs in all tracks present in the song editor.

13. L/R Expand and Copy. This button expands the song between the **L marker** and the **R marker** much like the **Expand** button. However, it also copies the original data that is present after the **R marker**, and pastes it into the newly-available space between the L and R markers.

5.2 Song Editor / Measures Ruler

The measures ruler ("bar indicator") consists of a *timeline* at the top and the **L marker** and **R marker** mentioned above. There are some hidden details in the measures panel.

The *measures ruler* is the ruled and numbered section at the top of the arrangement panel. It provides a place to put the left and right markers. In the *Seq24* documentation, it is called the "bar indicator".

Left-click in the measures ruler to move and drop an **L marker (L anchor)** on the measures ruler. Right-click in the measures ruler to drop an **L marker (R anchor)** on the measures ruler.

These markers denote the time interval from the left of the **L marker** to the right of the **R marker**. Once these markers are in place, one can then use the *Collapse* and *Expand* buttons to modify the placement of the pattern events.

Note that the **L marker** serves as the start position for playback in the song editor. One can change the start position only when the performance is not playing.

Another way to move the "L" and "R" markers has been added. To select which marker will move, first click the upper half of the time strip (otherwise, the "L" will move, prematurely) to give it keyboard focus. Then press the lower-case **l** key or the lower-case **r** key. *There is no visual feedback that one is in the movement mode.* Then press the **Left-Arrow** or **Right-Arrow** key to move the selected marker.

5.3 Song Editor / Patterns (Names) Panel

The patterns panel is at the left of the song roll. Here are the items to note in the patterns panel:

1. **Number.** The number of the screen set.
2. **Title.** The title is the name of the pattern, for easy reference.
3. **Channel.** The channel number appears (redundantly) at the right of the title.
4. **Buss-Channel.** This pair of numbers shows the MIDI buss number used in the pattern and the channel used for the pattern.
5. **Beat/Measure.** This pair of numbers is the standard time-signature of the pattern.

6. **Mute Indicator.** The letter M is in a black box if the track/pattern is muted, and a white box if it is unmuted. Left-clicking on the "M" (or the name of the pattern) mutes/unmutes the pattern. If the Shift key is held while left-clicking on the M or the pattern name, then the mute/unmute state of every other active pattern is toggled. This feature is useful for isolating a single track or pattern.
7. **Empty Track.** Completely empty tracks (no track events or meta events) are indicated by a dark-gray filling in the pattern column. Tracks that have only meta information, but no playable event, are indicated by a yellow filling in the pattern column.

The patterns column shows a list of all of the patterns that have been created in the current song. Each pattern in this list has a track of pattern layouts associated with it in the piano roll section.

Left-clicking on the pattern name or the "M" toggles the muting (arming) status of the track. It does the same thing if the **Ctrl** key is held at the same time.

Shift-left-clicking on the pattern name or the "M" button toggles the muting (arming) status of *all other tracks* except the track that was selected. This action is useful for quickly listening to a single sequence in isolation.

Right-clicking on the pattern name or the "M" button brings up the same pattern editing menu as discussed in section [3.2.2 "Pattern" on page 31](#). Recall that this context menu has the following entries: **Edit...**, **Event Edit...**, **Cut**, **Copy**, **Song**, **Disable Transpose**, and **MIDI Bus**.

5.4 Song Editor / Song Roll

Also known as the "arrangement panel". The "Piano Roll" section of the arrangement panel is where patterns or subsections are inserted, deleted, shrunk, lengthened, or moved. Actions can be done via the mouse or keyboard.

5.4.1 Song Editor / Song Roll / Layout

Here are features to note in the annotated piano roll area:

1. **Trigger Creation.** By click-dragging the mouse in paint mode, a series of triggers can be created; they indicate where the track will be unmuted and playing. See below for more information about triggers.
2. **Selection.** Clicking inside a trigger selects it. Selection is denoted by an orange rectangle around the trigger and a dark grey color in the trigger. A pattern subsection can be moved by the mouse and deleted by keystrokes.
3. **De-selection.** Left-clicking or right-clicking in an empty area of the song roll will deselect the selection.
4. **Selection Movement.** If one grabs (left-click) inside the pattern or pattern subsection, that item can be moved horizontally, as long as there is room.
5. **Section Length ("handle").** The small squares in two corners of the patterns are the section "handles". By grabbing a handle with a left-click, the handle can be moved horizontally to either lengthen or shorten the pattern to the nearest snap position, if there is room to move in the desired direction.
6. **Pattern Subsectioning.** A middle-click (or ctrl-left-click) inside a pattern inserts a selection position marker in it, breaking the pattern into two equal pieces. We call each piece a *pattern*

subsection. This division can be done over and over. There are also options for splitting at the nearest snap point.

7. **Expansion.** Originally, all the long patterns of this sample song were continuous. But, by setting the L and R markers, and using the **Expand** button, we opened up some silent space in the song, just to be able to show it off.

The Seq24 help files refer to work in the song editor as the "Performance Editor" or "Performance Mode". Adding a pattern in this window is a bit like adding a note in the pattern editor. One clicks, holds, and drags the mouse to insert a copy or copies of the pattern associated with the row in which one is dragging. The longer one drags, the more copies of the pattern that are inserted.

Right-click on the arrangement panel (roll) to enter paint mode, and hold the button. Paint mode does not work while the sequence is playing. Another way to turn on painting is to make sure that the performance editor piano roll has the keyboard focus by left-clicking in it, then press the **p** key to enter the paint mode, and **x** escape it. See section [5.4.2 "Song Editor / Song Roll / Keystrokes](#)" on page [59](#).

The song editor supports horizontal zoom in the piano roll. This feature is accessible via the buttons, and also accessible via keystrokes. The zoom feature also modifies the time-line.

A left-click with a simultaneous right-click-hold inserts one copy of the pattern. The inserted pattern shows up as a box with a tiny representation of the notes visible inside. Some patterns can be less than a measure in length, resulting in a tiny box. To keep adding more copies of the pattern, continue to hold both buttons and drag the mouse rightward.

Middle-click **i**(or **ctrl-left-click**) on a trigger in a pattern row to splits the trigger into two triggers.

This splits the pattern into two equal *pattern subsections*. Each middle-click on the pattern adds a new selection position, halving the size of the subsections as more pattern subsections are added. The **allow_snap_split** option in the '**rc**' file allows the split to be made at the nearest snap point instead of in the middle.

When a pattern or a pattern subsection is left-clicked in the piano roll, it is marked with a dark gray filling. It can then be moved horizontally if there is room, or be deleted or copied for later pasting.

When a right-left-click action is done in this gray area, the result is to *delete* that pattern section or subsection. One can also hit the **Delete** key.

5.4.2 Song Editor / Song Roll / Keystrokes

There are a number of useful keystrokes in the song roll that can be used once it has focus, by clicking in it.

- Enter "paint" mode. The **p** key enters paint mode, where additional triggers can be added by click-dragging on a pattern row. The **x** key leaves this mode. The "finger" button and the mouse cursor both indicate the status.
- Start/Pause button functionality. When the song roll has keyboard focus, the **Space** key starts and stops playback, rewinding to the beginning when stopped. The **.** (period) key starts and pauses playback, without rewinding. This functionality is similar to that of the main window, but these keys are not reconfigurable in the song roll.
- Undo / Redo / Cut / Copy / Paste of a selected section. Provided by buttons and by these keystrokes:

- **Ctrl-Z.** Undo.
- **Shift-Ctrl-Z.** Redo.
- **Ctrl-X.** Cut. Removes the selection. Can also be done with the **Delete** and **Backspace** keys. The deletion can be undone.
- **Ctrl-C.** Copy. Copies the trigger for later usage.
- **Ctrl-V.** Paste. Puts the roll into paste mode. When inserted, each insert goes immediately after the current item or the previous insertion. The same can be done for whole patterns.
- Horizontal (Time) Zoom. Provided by buttons and by these keystrokes: **Z.** Zoom in. **z.** Zoom out. **O.** Reset zoom.
- Paging. Paging by keystroke is not yet complete. Here is what can be done. One can page up and down vertically in the arrangement panel using the **Page Up** and **Page Down** keys. One can page left and right horizontally in the arrangement panel using the **Up-Arrow** and **Down-Arrow** keys.

5.5 Song Editor / Bottom Panel

The bottom panel is simple, consisting of a stock horizontal scroll bar.

6 Event Editor

The **Seq66 Event Editor** tab is used to view and edit, in detail, the events present in a loop / sequence / pattern / track. It is accessed by right-clicking on a pattern in the **Live** frame, then selecting the **Edit pattern in tab** menu entry. The default keystroke combination for this action is to use the minus key followed by the desired pattern's hot-key.

The event editor is not very sophisticated. It is a basic editor for simple edits, viewing, and trouble-shooting. Viewing and scrolling work; editing, deleting, and inserting events work. But there are many possible interactions between event links (Note Off events linked to Note On events, for example), performance triggers, and the pattern, performance, and event editor dialogs. Surely some bugs still lurk. If anything bad happens, do *not* press the **Save to Sequence** button! If the application aborts, let us know!

Here are the major "issues":

1. It requires the user to know the details about MIDI events and data values.
2. It does not present handy dropdown lists for various items.
3. It does not detect any changes made to the sequence in the pattern editor; we will ultimately add a refresh button.
4. It does not have an undo function.
5. It cannot mark more than one event for deletion or modification. However, if one note event is deleted, the corresponding linked note event is also deleted.
6. There is no support for dragging and dropping of events.

The event editor is a good way to see the events in a sequence, and to delete or modify problematic events. Additionally, it can be used to add **Set Tempo** meta events. If an event is added that has a time-stamp beyond the current length of the sequence, then the length of the sequence

is extended. Unlike the event pane in the pattern editor, the event-editor dialog shows all types of events at once.




Figure 19: Event Editor Window

The event-editor dialog is fairly complex. For exposition, we break it down into a few sections:

1. **Event Frame**
2. **Info Panel**
3. **Edit Fields**
4. **Bottom Buttons**

The event frame is a list of events, which can be traversed, and edited. The fields in the right panel show the name of the pattern containing the events and other information about the pattern. The edit fields provide text fields for viewing and entering information about the current event, and buttons to delete, insert, and modify events. The bottom buttons allow changes to be saved and the editor to be closed. The following sections described these items in detail.

6.1 Event Editor / Event Frame

The event frame is the event-list shown on the left side of the event editor. It is accompanied by a vertical scroll-bar, for moving one line or one page at a time. Mouse or touchpad scrolling can be used to move up and down in the event list. This movement is even easier than reaching for the scrollbars. We have been trying to get this table to auto-stretch vertically when the main window is vertically maximized, but have not succeeded so far.

6.1.1 Event Frame / Data Items

The event frame shows a list of numbered events, one per line. The currently-selected event is highlighted in cyan text on a black background. Here is an example of the data line for a MIDI event:

```
17 003:3:128 Note On Ch 3 0x45:69 0x6b:107 003:4:96
```

This line consists of the following parts:

1. **Index Number**
2. **Time Stamp**
3. **Event Name**
4. **Channel Number**
5. **Data Bytes**
6. **Link**

1. Index Number. Displays the index number of the event. This number is purely for reference, and is not part of the event. Events in the pattern are numbered from 0 to the number of events in the pattern.

2. Time Stamp. Displays the time stamp of the event, which indicates the cumulative time of the event in the pattern. It is displayed in the format of "measure:beat:divisions". The measure values start from 1, and range up to the number of measures in the pattern. The beat values start from 1, and range up to the number of beats in the measure. The division values range from 0 up to one less than the PPQN (pulses per quarter note) value for the whole song. As a shortcut, one can use the dollar sign ("\$") to represent PPQN-1.

3. Event Name. Displays the name of the event. The event name indicates what kind of MIDI event it is. The following event names are supported:

1. **Note Off**
2. **Note On**
3. **Aftertouch**
4. **Control Change**
5. **Program Change**
6. **Channel Pressure**
7. **Pitch Wheel**
8. **Tempo**

4. Channel Number. Shows the channel number (for channel-events only) re 0, not 1. For the user, of course, MIDI channels always range from 1 to 16. Internally, they range from 0 to 15.

5. Data Bytes. Shows the one or two data bytes for the event. The byte is shown in two formats, hexadecimal and decimal, as in **0x6b:107** ("hex:dec").

Note Off, Note On, and Aftertouch events require a byte for the key (0 to 127) and a byte for the velocity (also 0 to 127). Control Change events require a control code and a value for that control code. Pitch wheel events require two bytes to encode the full range of pitch changes. Program change events require only a byte value to pick the patch or program (instrument) to be used for the sequence. The Channel Pressure event requires only a one-byte value. Tempo requires a number (e.g. "120.3") to be typed in.

6.1.2 Event Frame / Navigation

Moving about in the event frame is straightforward, but has some wrinkles to note. Navigation with the mouse is done by moving to the desired event and clicking on it. The event becomes highlighted, and its data items are shown in the "info panel". There is no support for dragging and dropping events in the event frame. There is no support for selecting multiple events.

The scrollbar can be used to move within the frame, either by one line at a time, or by a page at a time. A page is defined as one frame's worth of lines, minus 5 lines, for some overlap in paging.

Navigation with keystrokes is also supported, for the Up and Down arrows and the Page-Up and Page-Down keys. Note that using the Up and Down arrows by holding them down for awhile causes autorepeat to kick in. Use the scrollbar or page keys to move through multiple pages. Home and End also work.

6.2 Event Editor / Info Panel

The "info panel" is simply a read-only list of properties on the top right of the event editor. It serves to remind the user of the pattern being edited and some characteristics of the pattern and the whole song. Five items are shown:

1. **Sequence Number and Name.** A bit redundant, as the window caption or the pattern also shows the pattern name. It can be set here or in the pattern editor.
2. **Time Signature.** A pattern property, shown only as a reminder. It can be set in the pattern editor.
3. **PPQN** Shows the "parts per quarter note", or resolution of the whole song. The default PPQN of *Seq66* is 192.
4. **Sequence Channel** In *Seq66*, the channel number is a property of the pattern. All channel events in the pattern get routed to the same channel, even if somehow the event itself specifies a different channel.
5. **Sequence Count** Displays the current number of events in the pattern. This number changes as events are inserted or deleted.

6.3 Event Editor / Edit Fields

The edit fields show the values of the currently-selected event. They allow changing an event, adding a new event, or deleting the currently-selected event.

1. **Event Category** (bold-faced, read-only)
2. **Time** (event timestamp)
3. **Event** (event name)
4. **D0** (data byte 1)
5. **D1** (data byte 2)

Important: changes made in the event editor are *not* written to the sequence until the **Save to Sequence** button is clicked. If one messes up an edit field, just click on the event again; all the fields will be filled in again. That's as much "undo" as the event-editor offers at this time, other than closing without saving.

1. Event Category. Displays the event category of the event in bold-face. Currently, only channel events and a couple of meta events, can be handled, but someday we hope to handle the wide array of system events, and perhaps even system-exclusive events.

2. Time. Displays the timestamp of the event. Currently only the "measure:beat:division" format is fully supported. We allow editing (but not display) of the timestamp in pulse (divisions) format and "hour:minute:second.fraction" format, but there are bugs to work out.

If one wants to delete or modify an event, this field does not need to be modified. If this field is modified, and the **Modify** button is pressed, then the event will be moved. This field can locate a new event at a specific time. If the time is not in the current frame, the frame will move to the location of the new event and make it the current event.

3. Event. Displays the name of the event, and allows entry of an event name. The event name indicates what kind of MIDI event it is. The following event names are supported:

1. **Note Off**
2. **Note On**
3. **Aftertouch**
4. **Control Change**
5. **Program Change**
6. **Channel Pressure**
7. **Pitch Wheel**
8. **Tempo**

Typing in one of these names changes the kind of event if the event is modified. Abbreviations and case-insensitivity can be used to reduce the effort of typing. This handling of the editing of the event name is still a bit clumsy. It would be better to provide a drop-down list for more painless selection of events. Some day.

4. D0. Allows modification of the first data byte of the event. One must know what one is doing. The scanning of the digits is very simple: start with the first digit, and convert until a non-digit is encountered. The data-byte value can be entered in decimal notation, or, if prepended with "0x", in hexadecimal notation.

For a Tempo setting only this field is used; Data Byte 2 is ignored. Enter a Tempo value, such as "120", and then click **Insert**. The value is converted to the 3 bytes of a tempo event, and then added at the given timestamp. (Screen refresh is not perfect yet, but reloading the pattern shows the correct tempo.)

5. D1. Allows modification of the second data byte of the event (if applicable to the event). One must know what one is doing. The scanning of the digits is as noted above.

6. Delete. Causes the selected event to be deleted. The frame display is updated to move following events upward.

Seq66 does not support using the **Delete** and **Insert** keys to supplement the buttons; the **Delete**

6.4 Event Editor / Bottom Buttons

These are the buttons that act on the edit fields or current event selection:

1. **Delete** (selected event)
2. **Insert** (new event)
3. **Modify** (selected event)
4. **Clear** (all events)
5. **Save** (back to sequence)

6. Dump (events to console)

1. Insert. Inserts a new event, described by the **Event Timestamp**, **Event Name**, **Data Byte 1**, and **Data Byte 2** fields. The new event is placed in the appropriate location for the given timestamp. If the timestamp is at a time that is not visible in the frame, the frame moves to show the new event, so be careful.

2. Modify. Deletes the current event, and inserts the modified event, which is placed in the appropriate location for the given timestamp. (This feature does not work with linked Note Ons and Note Offs).

3. Clear. Deletes all of the events in the event table. As with all edits, does not become official until the **Save** button is clicked.

4. Save. Saves all of the events in the event table into the original sequence. There is no way to undo this action. This button does not close the dialog; further editing can be performed. The Save button is enabled only if some unsaved changes to the events exist.

Any sequence/pattern editor that is open should be reflected in the pattern editor once this button is pressed.

5. Dump. Write the events to a console, useful mostly for further troubleshooting, as it does not go through the event table.

Again, good luck with this tab. Bug reports are appreciated.

7 Seq66 Session Management

The first thing to do for session management is to make sure that the application is capable of various levels of session management, from *UNIX* signals to a complete session manager like the *Non Session Manager*. Basic session management consist of being able to properly start the application and let it run properly during its life-cyle, whether it is a command-line application or a graphical application.

Seq66 supports session management in three ways:

1. **Non Session Manager (NSM)**
2. **Signals**
3. **LASH** (not ready)

Non Session Manager provides a replacement for the *JACK Session API* (now disabled by default in a *Seq66* build). It allows control over the startup of multiple applications, the process of saving a session, and provides a way to save their patching (connections) in *JACK*. NSM support in *Seq66* is essentially finished.

Signals provide for initiating a save operation and the sudden termination of an application. This mode is useful with *nsm-proxy*, a way to script applications that don't have *NSM* support.

LASH is an earlier session protocol, supported in *Seq64*. However, it is not ready in *Seq66* and is a low priority at this time.

7.1 Seq66 Session Management / NSM

The *Non Session Manager* is an API implementation for session management for Linux audio/MIDI. NSM clients use a well-defined OSC protocol to communicate with the session management daemon.

7.1.1 Seq66 Session Management / NSM / First Run Without NSM

This section discusses what happens when *Seq66* is installed, then run outside of any session from the console or an application menu. For a discussion where *Seq66* is run for the first time under NSM, see section [7.1.2 "Seq66 Session Management / NSM / Run in NSM" on page 67](#).

Generally, after installing *Seq66*, or when creating a new setup (such as a play-list) it is good to run it normally first, to simplify trouble-shooting. This action creates the configuration files in the default location, `/home/user/.config/seq66`:

```
$ qseq66
[No 'rc' file, will create: qseq66.rc/ctrl/midi/mutes]
[No 'usr' file, will create: /home/user/.config/seq66/qseq66.usr]
[File exists: /home/user/.config/seq66/qseq66.rc]
[Saving initial config files to session directory!]
[Writing 'rc': /home/user/.config/seq66/qseq66.rc]
[Writing 'ctrl': /home/user/.config/seq66/qseq66.ctrl]
[Writing 'mutes': /home/user/.config/seq66/qseq66.mutes]
[Writing 'usr': /home/user/.config/seq66/qseq66.usr]
.
.
```

Then exit *Seq66* to ensure the configuration files are created. Optionally, in this initial setup, one can also create a 'playlist' file and a 'drums' file, or copy them from:

```
/usr/share/seq66-0.91/data/samples      (Linux)
C:/Program Files (x86)/Seq66/data/samples (Windows)
```

to

```
/home/user/.config/seq66                  (Linux)
C:/Users/user/AppData/Local/seq66          (Windows)
```

and modify them appropriately. Another first-time modification to consider is setting up *Seq66* to use the JACK audio/MIDI subsystem (on *Linux*). In the 'rc' file, look for the following line:

```
0 # with_jack_midi
```

And change it to:

```
1 # with_jack_midi
```

Another first-time modification to consider is using virtual ports (option `-manual-ports`) versus the automatic port connections *Seq66* normally makes. This setup allows the user to manually make connections between *Seq66* and other MIDI applications. In the 'rc' file, look for the following lines:

```
[manual-ports]
0 # flag for manual (virtual) ALSA or JACK ports
16 # number of manual/virtual ports
```

And change them to:

```
[manual-ports]
1 # flag for manual (virtual) ALSA or JACK ports
4 # number of manual/virtual ports
```

It is then important to start `qseq66` in the normal manner again, and verify that everything works as expected.

7.1.2 Seq66 Session Management / NSM / Run in NSM

When *Seq66* is run in *NSM* for the first time, what happens to the new configuration depends on whether or not the normal configuration files exist in the default configuration location.

If no configuration files exist, then new configuration files are created in the *NSM* session directory. If these configuration files exist, then they are replicated in the *NSM* session directory.

No existing normal configuration. Here, we have just installed *Seq66*, but have not yet run it. We start the *non-session-manager*, create a new session, and add `qseq66` to this session. This starts `qseq66`, and, after a short delay to get the session information from the daemon, a new configuration is created in the session directory.

Existing normal configuration. If there is an existing *Seq66* configuration, then running `qseq66` in a new session will cause the configuration to be recreated in the new session directory, including play-lists and MIDI files. If a play-list has been configured, it is also copied, and so are the MIDI files it requires. (Their relative directory structure is preserved.)

If *JACK* has been configured to be used by *Seq66*, be sure *JACK* is started (e.g. by running the `qjackctl` application.)

For illustration, we run *NSM* from a terminal window, which can be very helpful when problems occur.

```
$ non-session-manager
[non-session-manager] Starting daemon...
[nsmd] Session root is: /home/user/NSM Sessions
NSM_URL=osc.udp://mycomputer.mls:19625/
[nsmd] Listing sessions
```

If *NSM* refuses to start, make sure that the `liblo` library from the *OSC* project is installed. If it is installed, then check the `/etc/hosts` file to make sure that the loopback interfaces are defined. In some versions of *Linux*, it isn't defined properly, and the *NSM* daemon (`nsmd`) will not start. Here is an example for the default install in *Debian Sid*:

```
127.0.0.1 localhost
127.0.1.1 mycomputer.mls mycomputer
```

The *NSM* user-interface (not shown here) that comes up is empty at first. So create a session by clicking the *NSM* New button, and entering a session name (here, "**Seq66**") in the prompt that comes up. In the console window, a couple of `/nsm/server/new` *OSC* messages about the creation of the session appear.

```
[non-session-manager] Sending new for: Seq66
[nsmd] Creating new session "Seq66"
[non-session-manager] /nsm/server/new says Created.
[non-session-manager] /nsm/server/new says Session created
```

Next, click the *Add Client to Session*, and, since `qseq66` has been installed system-wide, it is in the `PATH` and its executable name can be entered simply: "`qseq66`". A number of console messages from *Seq66* appear, plus some messages from *NSM*.

```
[non-session-manager] Sending add for: qseq66
[nsmd] Process has pid: 2797436
[nsmd] Launching qseq66
[nsmd] Got announce from seq66
[nsmd] Client was expected.
[nsmd] Process has pid: 2797436
[nsmd] The client "seq66" at "osc.udp://127.0.0.1:13318/" informs us it's
      ready to receive commands.
```

Once *Seq66* is running under NSM, then click the **Save** button at the top of the NSM interface in order to save the session information. This is an important step. One can see what has been created to support the session; the directory that NSM creates by default is `/home/user/NSM Sessions`.

```
$ pwd
/home/user/NSM Sessions
$ lmtree Seq66
Seq66/
+-- seq66.nGJDW/
|   +-- config/
|   |   +-- qseq66.ctrl
|   |   +-- qseq66.mutes
|   |   +-- qseq66.rc
|   |   +-- qseq66.usr
|   +-- midi/
+-- session.nsm
```

So NSM has created a directory with the session name we gave it: `Seq66`. Under that directory is a file, `session.nsm`, which contains information like the following:

```
seq66:qseq66:nIRJI
```

The format of this text is `appname:exename:nXXXX`, where `XXXX` is a 4-letter randomly-generated token. Also created is a directory, `seq66.nIRJI`, which is the root of the *Seq66* session. The "IRJI" portion is randomly generated by NSM.

The rest of the directories, `config` and `midi`, are generated by *Seq66*. The `config` directory is used instead of `/home/user/.config/seq66`) and `midi` directory contains new MIDI files, imported MIDI files, or MIDI files from a play-list. The new `config` directory contains versions of the various configuration files that will always be used to start up *Seq66* during the session. One can also add valid play-list, palette, and drums/note-mapping files to that directory later.

If before running NSM, one had set up a play-list file and provided the proper "MIDI base directory" in the 'rc' file, then all the MIDI files are copied to the NSM session `midi` directory, preserving all relative directories. When the *Non Session Manager* is started the next time, and the "Seq66" session is clicked, this starts *Seq66*, and the play-list can be seen in the *Playlist* tab.

One last thing to note is that, when viewing the MIDI ports created by *Seq66*, they will be named "seq66" when not in session management, and "seq66.nIRJI" (for example) when under session management. This makes it possible to run multiple instances of *Seq66*.

7.1.3 Seq66 Session Management / NSM / Run with Remote NSM

As described in the NSM documentation, the `nsmd` daemon can be run stand-alone, and can also be ran on a remote computer. The `qseq66.usr` file can be edited to allow *Seq66* to use a pre-planned NSM and specify the URL to connect. Look for the following lines in the 'usr' file:

```
[user-session]
session = none
url = ""
```

Now assume we've run the daemon as follows:

```
$ nsmd --osc-port 9999
[nsmd] Session root is: /home/user/NSM Sessions
NSM_URL=osc.udp://mycomputer.mls:9999/
```

Change the **session** lines to allow the usage of *NSM* at that URL:

```
[user-session]
session = nsm
url = "osc.udp://mycomputer.mls:9999"
```


The **url** is not used if running *Seq66* from the *NSM* GUI... the application will get the URL from the *NSM* environment.

Note that **qseq66** can still be run outside of a session manager. It will detect the absense of the session manager and run normally.

7.1.4 Seq66 Session Management / Sessions Tab

The *Session* tab is a *read-only* tab provided to orient the user to the setup supported by the session. When not running in a session, the normal configuration directory and files are shown. When running in an *NSM* section, the configuration information received from *NSM* is displayed.

This tab is not yet fully functional and is meant to display information to help the user understand what is happening in the run. In particular, **Detach** and **Session Log** don't yet work.




Session Tab When Running Under NSM

This section describes the *Session* tab in the main *Seq66* window. At present, this tab is just informative. It displays the following bits of information that *Seq66* has received from *NSM* via the *nmsd* daemon:

- Name of the session manager.
- Session path for the session, the root directory of the session. All data goes into this directory. If not running in a session, the active configuration directory (which can be modified via command-line arguments) is shown.
- The OSC URL of the session, which includes the port number. Generally, the port number is selected at run-time, but it is also possible to configure *NSM* to use a specific port number.
- Display-name for the session.
- The generated client ID for the session.
- The log of action of the session manager. Not yet supported.

7.1.5 Seq66 Session Management / File Menu

The author of *NSM* has provided documentation for session-management which provides very strict instructions on how an application must behave under session management. *Seq66* tries very hard to stick to these instructions. One major adjustment an application must make is to adhere to the "File menu" guidelines.



File Menu When Running Under NSM

The following items describe the menu entries. Some of these may be in progress or still need to be enforced.

- **New MIDI File.** This function prompts for the name of a new MIDI file and clears the current MIDI file. The file-name must not include a full-path to the file. The path is hardwired by the session. A relative path can be included. This name is needed because there is no "Save As" option when running in an *NSM* session.
- **Import into Session.** Prompts the user for a MIDI file to be imported (copied) into the current session. The path to the file is then adjusted to use the *NSM midi* subdirectory.
- **Open Playlist.** Works the same as without session management, but gets the list from the session directory.
- **Save Session.** This function saves the main configuration files (except for the 'usr' file), saves the play-list and note-mapper files, if in use, and saves the current MIDI file, if any.
- **Export Song As MIDI.** Allows exporting the current song as a stock MIDI file, using the performance information (triggers) to write the MIDI data as it would be played in "song" mode. The default directory that comes up in the prompt is the "last-used directory" from the session 'rc' file.
- **Export MIDI Only.** Allows exporting the current song as a stock MIDI file. The "proprietary" SeqSpec data is *not* written. The default directory that comes up in the prompt is the "last-used directory" from the session 'rc' file.
- **Import MIDI to Current Set.** This item allows the user to grab a MIDI file from anywhere and import it into the current set. The default directory that comes up in the prompt is the "last-used directory" from the session 'rc' file.
- **Detach.** Allows *Seq66* to detach from session management. This process simply disconnects from *NSM* and restores the normal *File* menu. Currently, it is disabled because it causes issues that we cannot yet solve.
- **Quit.** Quits *Seq66*. There are no messages to send to *NSM* in this case. The *nsmd* daemon detects that the *Seq66* client has disappeared (and notes that on the console output, if available).

At some point we would like to present a small tutorial showing a session under *JACK*.

7.2 Seq66 Session Management / Signals

By default, the basic form of session management in *Seq66* occurs by signals. A session manager can start *Seq66*, and it can tell *Seq66* to save or stop. Starting is done by a system call to spawn the application. The save and stop actions are supported by sending the following signals to the application:

- **SIGINT.** This signal stops *Seq66*. It corresponds to using **Ctrl-C** from the command-line to stop *Seq66*. This signal should work for both the graphical and command-line application. As *Seq66* shuts down, it does its normal saving of the current state of the configuration.
- **SIGTERM.** This signal also stops *Seq66*. It can be sent by an application to exit *Seq66*.
- **SIGUSR1.** This signal tells *Seq66* to save. This action will save the current MIDI file.

One application that can control *Seq66*, to some extent, when not in session mode, is *nsm-proxy*:

<https://non.tuxfamily.org/wiki/nsm-proxy>

NSM-Proxy is a simple NSM client for wrapping non-NSM capable programs. It enables the use of programs supporting LADISH Level 0 and 1, and programs which accept their configuration via command-line arguments. There is a command-line version and a graphical version.

More to come on how to use *nsm-proxy*.

7.3 Seq66 Session Management / LASH

LASH support has not yet been fully reimplemented and retested. It is a low priority.

8 Import/Export

This section explains the details of the MIDI import and export functionality, accessed by the main menu as noted in sections [2.2.5](#), [2.2.6](#), and [2.2.7](#), on page [19](#).

8.1 Import MIDI

The **Import** menu entry imports an SMF 0 or SMF 1 MIDI file as one or more patterns, one pattern per track, and imports them into the currently-active set. Even long tracks, that aren't short loops, are imported. The difference from **File / Open** is that the destination screen-set (bank) for the import can be specified, and the existing data in the already-loaded MIDI file is preserved. If the imported file is a *Seq66* MIDI file, its proprietary sections will *not* be imported, in order to preserve the performance setup. The **Import** dialog is similar to the **Open** dialog.

When imported, each track, whether music or information, is entered into its own loop/pattern box (slot). The import operation can handle reasonably complex files. When the file is imported, the sequence number for each track is adjusted to put the track into the desired screen-set. The import can place the imported data into any of the 32 available screen-sets. Quite large songs can be built by importing patterns.

Import also handles SMF 0 MIDI files. It parcels out the SMF 0 data into sequences/patterns for each of the 16 MIDI channels. It also puts all of the MIDI data into the 17th pattern (pattern 16), in case it is needed. Note that this slot is used no matter which screen-set one imports the file into. Bug, or feature?

8.2 Export Song as MIDI

Thanks to Seq32, exporting song performances (see the **Song Editor**) to standard MIDI format has been added. The **Export Song as MIDI** operation modifies the song in the following ways:

- Only tracks (sequences, loops, or patterns) that are "exportable" are written. To be exportable, a track must be unmuted, and it must have triggers present in the **Song Editor**.
- Each trigger generates the events, including repeats and offset-play of the events. If there is a gap in the layout (e.g. due to an **Expand** operation in the **Song Editor**), then the corresponding gap in the events is exported. The result is a track that reconstructs the original playback/performance layout of that pattern. The events themselves are sufficient to play the performance exactly in any MIDI sequencer. The triggers are useful for further editing of the song/performance, so they are preserved in the triggers *SeqSpec* section.
- Empty pattern slots between tracks are removed.
- No matter what set the original track was in, it ends up in the first set.
- Other additions, such as time signature and tempo meta events, are written in the same manner as for a normal **File / Save** operation.

The export dialog is similar to the open dialog; one will likely want to change the name of the file so as not to overwrite it. If there are no exportable tracks, the following message is shown:




Figure 20: MIDI File Unexportable

Once the file is exported, reopen it to see the results of the export. Both the main window and the song editor show the results of the export. The two sets are combined into the first set, and all of the track layouts (triggers) have been exported. Had there been gaps in layouts or repeats of layouts in the song/performance data, these would have been reflected in the triggers.

8.3 Export MIDI Only

Sometimes it might be useful to export only the non-sequencer-specific (non-*SeqSpec*) data from a *Seq66* song. For example, some buggy sequencers (*hello Windows Media Player*) might balk at some *SeqSpec* item in the song, and refuse to load the MIDI file. For such cases, the **Export MIDI Only** menu item writes a file that does not contain the *SeqSpec* data for each track, and does not include all the *SeqSpec* data (such as mute groups) that is normally written to the end of the *Seq66* MIDI file.

9 Seq66 Keyboard and Mouse Actions

This section presents some tables summarizing keyboard and mouse actions available in *Seq66*. It does not cover mute keys and group keys, which are well described in the keyboard options for the

main window. It does not cover the "fruity" mouse actions, as this mode of mouse-handling is not supported in *Seq66*.

This section describes the keystrokes that are currently hardwired in *Seq66*. This description only includes items not defined in the 'ctrl' file. That is, hardwired values. "KP" stands for "keypad". The effect that keystrokes have depends upon which window has the keyboard/mouse focus.

9.1 Keyboard Control

Seq66 provides a plethora of keyboard controls for user-interface actions, note-modification, zooming, and pattern control. Most of these controls (not all) are easy to change by editing the appropriate 'ctrl' configuration file, stored in one of the following directories, depending on the operating system:

```
/home/username/.config/seq66/qseq66.ctrl  
C:/Users/username/AppData/Local/seq66/qpseq66.ctrl
```

There are also some extended examples present in the *Seq66* data/linux and data/samples directory. Note that keyboard and MIDI control settings have been consolidated into a single table in the 'ctrl' file. The [mute-group] control section has been moved to it's own 'mutes' file.

There are a number of "gotchas" to be aware of when assigning keys to the fields in the **Keyboard** tab:

- Some of the keystrokes are hard-wired, such as "arrow" keys (for controlling play-lists), "page up/down" keys, or the "zoom" keys.
- *Seq66* has appropriated the Shift key so that a Shift-left-click on a pattern slot opens up the corresponding set (based on pattern number) in an external live grid. For the group-learn feature, the Shift key is automatically enabled, using an "auto-shift" feature. Thus, using characters that require the Shift key while clicking, such as { and }, becomes surprising. Instead, look to the remaining keys: F11, F12, and the "keypad" keys if more keystrokes are wanted.

[keyboard-control]. We won't attempt to cover every key-control item, just the categories. Some items might be discussed in other parts of this manual. Remember that key and MIDI control have been consolidated. Also remember that the 'ctrl' file contains comments and an orderly layout to make it easier to understand and to edit.

An additional key definition is shown for the pause key. By default, the pause key is the period (".."), but that can be changed.

A goal of *Seq66* is being able to edit a pattern using mainly the computer keyboard. *Seq66* supports two modifier keys. The first modifier key causes the usual pattern-toggle key (hot-key) for a given slot to instead bring up the pattern editor. By default, this key is the equals ("=") key. The second modifier key causes the usual pattern-toggle key (hot-key) for a given slot to instead bring up the event editor. By default, this key is the minus ("-") key. Both of these keys are configurable.

Some of the keys have positional mnemonic value. For example, for BPM control, the semicolon is at the left (down), and the apostrophe is at the right (up).

The **slot shift** key is useful when using pattern grids larger than 8 x 4 patterns. Pressing the slot-shift key basically adds 32 to the pattern number of the slot-key that is pressed. The default key is the forward slash ("/") key.

A **snapshot** is a briefly-preserved state of the patterns. One can press a snapshot key, change the state of the patterns for live playback, and then release the snapshot key to revert to the state when the snapshot key was first pressed. The default key is the **Ins** key.

To **queue** a pattern means to ready it for playback upon the next repeat of a pattern. A pattern can be armed immediately with a hot-key, or it can be queued to play back the next time the pattern repeats. A pattern can be queued by holding the queue key (defined in **File / Options / Keyboard / queue**) and pressing a pattern-slot hot-key. Instead of the pattern turning on immediately, it turns on at the next repeat of the pattern. The default key is the "o" key.

Keep queue allows the queue to be held without holding down the queue button the whole time. First, press the keep-queue key. Next, hitting any of the slot hot-keys, no matter how many, sets up the corresponding pattern slot to be queued. Also, in keep-queue mode, clicking on the pattern slot will queue the pattern. The keep-queue mode is disabled by hitting the "queue" key again (any currently active queues remain active until finished). The default key is the backslash key, "\ key. There is also a "Q" button to toggle the keep-queue status.

One-Shot causes a slot to be queued for only a single playback. The default key is the pipe, "|" key. Currently buggy.

6. Sequence toggle keys. Each of these keys toggles the playing/muting of one of the 32 loop/pattern boxes. These keys are layed out logically on the keyboard by default, and can also be shown in each loop/pattern box. Please note that we often call them "shortcut keys" or "hot-keys" where the context makes it clear that they apply to the armed/unarmed state of a pattern.

7. Mute-group slots. There can be up to 32 mute-groups. When activated, a mute-group sets the muted/unmuted status of the current "playing set" to the pattern-muting statuses of the selected mute-group. Each of these keys operates on the mute-grouping of one of the 32 stored mute groups. These keys are layed out logically on the keyboard by default, and consist of **Shift** versions of the sequence-toggle (hot) keys. Note that a mute-group key will be memorized only when *Seq66* is in *group-learn* mode.

8. Learn.

To define the group of patterns for one mute group, press and hold the configured Learn key (the "el", "l" key by default, the hard-wired **Ctrl-L** key, or the "L" button in the user-interface. Simultaneously (not needed with the "L" button), pressing one of the mute group keys: *Seq66* will save the currently-playing pattern slots into the corresponding mute group. The default mute group keys must be the shifted version of the key, but one does not need the **Shift** key while pressing **Insert** to learn the group, only to trigger it. *Seq66* will automatically assign the corresponding key with **Shift** activated. Try pressing the **Shift** key in Learn mode and see what happens!

Group-mute can be globally enabled or disabled (with default keys apostrophe ' and igrave or grave `). So make sure it is enabled before trying to use it.

9. Disable. It is the inverse **apostrophe** key by default. This key is the *group off* key.

10. Enable. It is the **igrave** (back-tick) key by default. This key is the *group on* key.

A number of additional functions have been added to *Seq66*, and keystrokes have been provided for those new functions.

Note the **Song/Live toggle** key. The *song mode* normally is in effect only when playback is started from the **Song Editor**. Now this mode can be used from any window, if enabled by pressing this key. There is also a button in the main window for this function, which shows the current state

of this flag. Note that this flag is also stored in the 'rc' configuration file, as well as this hot-key value, which defaults to F10.

The **JACK mode** is set via the **File / Options / JACK / JACK Connect or JACK Disconnect** buttons. This keystroke will toggle between JACK connect and JACK disconnect. The **Song Editor** will also have a **JACK** button. The hot-key for this function defaults to F2.

The *menu mode* indicates if the main menu of the main window is accessible or not. It is disabled during playback so that more hot-keys can be used without triggering menu functions. It can also be disabled by the user; the default hot-key is F3. This feature is needed because the original *Seq24* had numerous conflicts between the menu key bindings and the default key bindings for the main window.

Follow JACK is a feature ported from *Seq32*. The default key is F4. It determines if *Seq66* follows JACK transport.

Fast forward is a feature ported from *Seq32*. The default key is F6. While this key is held, the song pointer will fast-forward through the song. This feature does not have a corresponding button.

Rewind is a feature ported from *Seq32*. The default key is F5. While this key is held, the song pointer will rewind. This feature does not have a corresponding button.

Pointer position is a feature ported from *Seq32*. The default key is F7. When this key is pressed, the song pointer will move to the current position of the mouse, snapped. This feature does not have a corresponding button.

Toggle mutes toggles the mute status of every pattern on every screen-set. It corresponds to the **Edit / Toggle mute all tracks** or the **Song / Toggle All Tracks** menu entries. There is also a button in the main window for this function, which shows the current state of this flag. Note that this hot-key value is stored in the 'rc' configuration file, and defaults to F8.

Tap BPM allows the user to "tap" in time with some other music, and see the tap sequence translated into beats/minute (BPM). There is also a "0" button for this function. After 5 seconds, this feature resets automatically, so the user can try again if not satisfied. At least two taps are needed for the BPM to be registered.

9.2 Main Window

The main window keystrokes are all defined via the options dialog and "rc" configuration file, or are stock window-management keystrokes. The main window has a very complete setup for live control of the MIDI tune via keystrokes. These actions are not included in table 1 "[Main Window Support](#)" on page [76](#).

Table 1: Main Window Support

Action	Normal	Double	Shift	Ctrl
e	—	—	—	Open song editor
l (el)	—	—	—	Enter Learn mode
Left-click slot	Mute/Unmute	New/Edit	Toggle other slots	—
Right-click slot	Edit menu	—	Edit menu	Edit Menu

The new mouse features of this window for *Seq66*, as noted in section 3 "[Patterns Panel](#)" on page [28](#), are:

- *Shift-left-click*: Over one pattern slot, this action toggles the mute/unmute (armed/unarmed) status of all other patterns (even the patterns in other, unseen sets).
- *Left-double-click*: Over a pattern slot, this action quickly toggles the mute/unmute status, which is confusing. But it ultimately brings up the pattern editor (sequence editor) for that pattern.

9.3 Performance Editor Window

The "performance editor" window is also known as the "song editor" window. Its main sections are the "piano roll" (perfroll) and the "performance time" (perftime) sections, discussed in the following sections. Also, some keystrokes are handled by the frame of the window.

- **Ctrl-z**. Undo.
- **Ctrl-r**. Redo.

9.3.1 Performance Editor Piano Roll

Note that the keystrokes in this table (see table 2 "Performance Window Piano Roll" on page 77) require that the focus first be assigned to the piano roll by left-clicking in an empty area within it. Otherwise, another section of the performance editor might receive the keystroke.

Table 2: Performance Window Piano Roll

Action	Normal	Double	Shift	Ctrl
Space	Start playback	—	—	—
Esc	Stop playback	—	—	—
Period (.)	Pause playback	—	—	—
Del	Cut section	—	—	—
c key	—	—	—	Copy
p key	Paint mode	—	—	—
v key	—	—	—	Paste
x key	Escape paint	—	—	Cut
z key	Zoom out	—	—	Undo
0 key	Reset zoom	—	—	—
Z key	Zoom in	—	—	Undo
Left-arrow	Move earlier	—	—	—
Right-arrow	Move later	—	—	—
Left-click	Select section	—	—	—
Right-click	Paint mode	—	Paint mode	Paint mode
Scroll-up	Scroll up	—	Scroll Left	Scroll Up
Scroll-down	Scroll down	—	Scroll Right	Scroll Down

This section of the performance editor also handles the start, stop, and pause keys. These can be modified in the **Options / Keyboard** page. A "section" in the performance editor is actually a box that specifies a trigger for the pattern in that sequence/pattern slot. Note that the "toggle other slots" action occurs only if shift-left-clicked in the "names" area of the performance editor. Left-click is used to select performance blocks if clicked within a block, or to deselect them if clicked

in an empty area of the piano roll. Also note that all scrolling is done by the internal horizontal and vertical step increments. Some features of this window for *Seq66*, as noted in section 5 "Song Editor" on page 54, are explained here:

- *p*: Enters the paint mode, until right-click is pressed or until the "x" key is pressed.
- *x*: Exits the paint mode. Think of the made-up term "x-scape".
- *z*: Zooms out the performance view. It makes the view look smaller, so that more of the performance can be seen. Opening a second performance view is another way to see more of the performance.
- *0*: Resets the zoom to its normal value.
- *Z*: Zooms in the performance view, making the view larger, so that more details of the performance can be seen.
- *Left Arrow*: Moves the selected item to the left (earlier in time) in the performance layout.
- *Right Arrow*: Moves the selected item to the right (later in time) in the performance layout.
- Once selected (rendered in grey), a pattern section (trigger) can be moved by the mouse. To move it using the left or right arrow keys, the paint mode must be entered, but only via the "p" key.

9.3.2 Performance Editor Time Section

- *l*. Set to move L marker.
- *r*. Set to move R marker.
- *x*. Escape ("x-scape") the movement mode.
- *Left*. Move the selected marker left.
- *Right*. Move the selected marker right.

This section of the performance editor is also known as the "measure ruler" or the "bar indicator".

Table 3: Performance Editor Time Section

Action	Normal	Double	Shift	Ctrl
<i>l</i>	Move L [1]	—	—	—
<i>r</i>	Move R [1]	—	—	—
<i>x</i>	Escape Move	—	—	—
Left-Click	Set L [2]	—	—	—
Middle-Click	—	—	—	—
Right-Click	Set R [2]	—	—	—

1. Activates movement of this marker using the left and right arrow keys. Movement is in increments of the snap value. This mode is exited by pressing the 'x' key. Also see note [2].
2. Controlled in the pertime section.

The features of this window for *Seq66* are:

- *l*: Enters a mode where the left and right arrow keys move the L marker, until the "x" key is pressed.

- **r:** Enters a mode where the left and right arrow keys move the R marker, until the "x" key is pressed.
- **x:** Exits the marker-movement mode.

9.3.3 Performance Editor Names Section

Table 4: Performance Editor Names Section

Action	Normal	Double	Shift	Ctrl
Left-Click	Toggle track	—	Toggle other tracks	—
Middle-Click	—	—	—	—
Right-Click	New/Edit menu	—	—	—

9.4 Pattern Editor

The pattern/sequencer editor piano roll is a complex and powerful event editor; table 5 "Pattern Editor Piano Roll" on page 80, doesn't begin to cover its functionality. Here are some keystrokes handled by the main frame of the piano roll:

- **Ctrl-L.** Bring up the LFO event modulation editor.
- **Ctrl-W.** Exit the sequence (pattern) editor.
- **Ctrl-Page Up.** Zoom in.
- **Ctrl-Page Down.** Zoom out.
- **Shift-Page Up.** Scroll leftward.
- **Shift-Page Down.** Scroll rightward.
- **Shift-Home.** Scroll leftward to the beginning.
- **Shift-End.** Scroll rightward to the end.
- **Page Down.** Scroll downward.
- **Page Up.** Scroll upward.
- **Home.** Scroll upward to the beginning.
- **End.** Scroll downward to the end.
- **Delete.** Deletes (not cuts) the currently-selected notes in the piano roll; can be undone with the **Undo** button.

9.4.1 Pattern Editor Piano Roll

Here are the keystrokes handled by the piano roll: These keystrokes require that the focus be set to the piano roll by clicking in it with the mouse.

- **Ctrl-r.** Redo.
- **Ctrl-a.** Select all.
- **Ctrl-Left.** Shrink selected notes.
- **Ctrl-Right.** Grow selected notes.
- **Delete.** Remove selected notes.
- **Backspace.** Remove selected notes.
- **Home.** Set sequence to beginning of sequence. (Verify!)
- **Enter, Return.** Paste the selected notes at the current position.

And here is the table, which includes items not described above:

Table 5: Pattern Editor Piano Roll

Action	Normal	Double	Shift	Ctrl
Del	Delete Selected	—	—	—
c	—	—	—	Copy
p	Paint mode	—	—	—
v	—	—	—	Paste
x	Escape Paint	—	—	Cut
z	Zoom Out	—	Zoom In	Undo
0	Reset Zoom	—	—	—
Left-Arrow	Move Earlier [1]	—	—	—
Right-Arrow	Move Later [1]	—	—	—
Up-Arrow	Increase Pitch	—	—	—
Down-Arrow	Decrease Pitch	—	—	—
Left-Click	Deselect	—	—	—
Right-Click	Paint mode	—	Edit Menu	Edit/Edit Menu
Left-Middle-Click	Grow Selected	—	Stretch Sel.	—
Scroll-Up	Zoom Time In	—	Scroll Left	Zoom Time In
Scroll-Down	Zoom Time Out	—	Scroll Right	Zoom Time Out

- Once selected (and thus rendered in grey), a pattern segment can be moved by the mouse. To move it using the left or right arrow keys, the paint mode must be entered, but only via the **p** key – the right mouse button deselects the greyed pattern. Too tricky, we might try fixing it later.

Features of this window section for *Seq66*, as noted in section [4.3.1 "Pattern Editor / Piano Roll Items"](#) on page [46](#), are:

- **p:** Enters the paint mode, until right-click is pressed or until the **x** key is pressed. Notes are added by clicking or click-dragging.
- **x:** Exits ("x-scapes") the paint mode.
- **z:** Zooms out.
- **0:** Resets zoom to its normal value.
- **Z:** Zooms in.
- **..**: The period (configurable) does the pause function.
- **Left Arrow:** Moves selected events to the left.
- **Right Arrow:** Moves selected events to the right.
- **Up Arrow:** Moves selected notes upward in pitch.
- **Down Arrow:** Moves selected notes downward in pitch.

9.4.2 Pattern Editor Event Panel

- **Ctrl-x.** Cut.
- **Ctrl-c.** Copy.
- **Ctrl-v.** Paste.

- **Ctrl-z.** Undo.
- **Delete.** Delete (not cut!) the selected events.
- **p.** Enter "paint" (also known as "adding") mode.
- **x.** Escape ("x-scape") the paint mode.

9.4.3 Pattern Editor Data Panel

Currently, no keystroke support is provided in the data panel. One potential upgrade would be the ability to change the value of the event with the Up and Down arrow keys.

9.4.4 Pattern Editor Virtual Keyboard

Table 6: Pattern Editor Virtual Piano Keyboard

Action	Normal	Double	Shift	Ctrl
Left-Click	Play note	—	—	—
Right-Click	Toggle labels	—	—	—

9.5 Event Editor

- **Down.** Move one slot down.
- **Up.** Move one slot up.
- **Page Down.** Move one frame down.
- **Page Up.** Move one frame up.
- **Home.** Move to top frame.
- **End.** Move to bottom frame.
- **Asterisk, KP Multiply.** Delete the currently-selected event.

10 Seq66 JACK Support

This section describes some details concerning the JACK support of *Seq66*. As with *Seq24*, *Seq66* has JACK transport support. JACK supposedly works with Windows, but we do not provide a JACK MIDI engine for that system. The JACK support is loosely based on the RtMIDI project (see [13]). This mode also supports fallback-to-ALSA if the JACK server is not running.

If one wants to use *Seq66* and USB devices with JACK MIDI, one needs to expose the USB ports to JACK using `a2jmidid --export-hw`, and connect the resultant MIDI JACK ports oneself, using *QJackCtl*, for example.

To enable the JACK transport support at run-time on *Linux*, the options `-j/--jack-transport`, `-J/--jack-master`, `-C/--jack-master-cond`, and `-t/--jack-midi` are available.

The following sections discuss the JACK transport support and the native JACK MIDI support.

10.1 Seq66 JACK Transport

JACK transport support is separate from native JACK MIDI support. The JACK transport client is an invisible client with the name "seq66-transport", while the JACK MIDI client is visible in *QJackCtl*, and the ports created are part of the "seq66" client.

Seq66 can be configured to run without JACK transport, with JACK transport as a "slave" (i.e. "client"), as JACK master, or as JACK master if there is no other master detected.

As per the rules of JACK, any client can start and stop the transport, and the other clients will follow suit. When *Seq66* is a JACK client, it will accept beats/minute (BPM) changes from another client that is running as master. When *Seq66* is master, changes to its BPM will be transmitted to the other clients.

10.2 Seq66 Native JACK MIDI

Currently, *Seq66* will connect to a JACK client automatically only at startup, where it will connect to all JACK clients that it finds. If it can't find a JACK client, then it will fail to register a JACK port, and cannot play.

The other option is to set up virtual ports using the `--manual-ports` or `--options virtual=o,i` options, and then to manually connect these ports to the desired MIDI devices or applications using *QJackCtl* (for example).

To run with JACK MIDI, just make sure JACK is running, then start *Seq66*, which will detect JACK and use it. If it instead opts to run with ALSA, edit the 'rc' file to set up `midi_jack`, or add the `-t` or `--jack-midi` option to the command-line. If *Seq66* doesn't find JACK, it will still fall back to ALSA.

The JACK (-t) and ALSA (-A) options are sticky options. That is, they are saved to the 'rc' configuration file at exit, so one does not have to specify them in subsequent *seq66* sessions.

10.2.1 Seq66 JACK MIDI Output

By default (or depending on the 'rc' configuration file), *Seq66* will automatically connect the ports that it finds to `seq66`. The following figure shows connections to a number of USB MIDI devices (purple) that have been bridged to JACK (red) by the `a2jmidid` daemon.




Figure 21: JACK MIDI Ports and Auto-Connect

Note that the ports in *Seq66* are named after the devices to which they are connected.

The output ports available are shown in *seq66*'s **Edit / Preferences / MIDI Clock** tab. If USB devices are not shown, that means that the `a2jmidid` is not running. There is a `bash` script, `data/linux/startjack` that will run `jack_control` and `a2j_control` to start JACK and the "a2j" daemon to provide full support. On our current setup, it creates devices with long names (abbreviated inside *Seq66*):

```
6 # number of MIDI clocks (output busses)
0 0 "[0] 0:0 seq66:a2j Midi Through [14] (playback): Midi Through Port-0"
1 0 "[1] 0:1 seq66:a2j Launchpad Mini [28] (playback): Launchpad Mini MIDI 1"
2 0 "[2] 0:2 seq66:a2j E-MU XMidi1X1 Tab [32] (playback): E-MU ... Tab MIDI 1"
3 0 "[3] 0:3 seq66:a2j nanoKEY2 [36] (playback): nanoKEY2 MIDI 1"
4 0 "[4] 0:4 seq66:a2j USB Midi [40] (playback): USB Midi MIDI 1"
5 0 "[5] 1:5 seq66:yoshimi-01 midi in"
```

10.2.2 Seq66 JACK MIDI Input

The input ports also end up with long names:

```
5 # number of input MIDI busses
0 1 "[0] 0:0 seq66:a2j Midi Through [14] (capture): Midi Through Port-0"
1 1 "[1] 0:1 seq66:a2j Launchpad Mini [28] (capture): Launchpad Mini MIDI 1"
2 1 "[2] 0:2 seq66:a2j E-MU XMidi1X1 Tab [32] (capture): E-MU ... Tab MIDI 1"
3 0 "[3] 0:3 a2j:nanoKEY2 [36] (capture): nanoKEY2 MIDI 1"
4 0 "[4] 0:4 a2j:USB Midi [40] (capture): USB Midi MIDI 1"
```

When the check-box for a buss is selected, that input can be captured by `seq66`.

10.2.3 Seq66 JACK MIDI Virtual Ports

The manual-versus-normal port support for JACK MIDI is essentially the same as that for ALSA. The `--manual-ports` and `--options virtual=o,i` options provide "virtual ports". These are ports that do not represent hardware, but are created by applications to allow them to connect to other applications or MIDI devices.

The difference between manual/virtual ports and normal ports is that, while normal ports are automatically connected to the remote ports that exist in the system, the manual/virtual ports are just created, and one must manually connect them via, for example, the *QJackCtl* connections dialog.

So, if one wants *seq66* to automatically connect to all existing JACK MIDI ports, *do not* use the `-m`/`--manual-ports` option... use the `-a`/`--auto-ports` option. Both options apply to both ALSA and JACK.

The **MIDI Clock** and **MIDI Input** tabs reflect what is seen in *QJackCtl*.

10.2.4 Seq66 JACK MIDI and a2jmidid

One thing we saw is that `seq66` can deal with the odd naming of JACK ports created by the `a2jmidid` application.

One can see in the input and output lists shown earlier that that the `a2j` client creates entries for "Midi Through", software clients, and bridged USB MIDI devices.

Again, if these automatic connections get in the way, run `seq66` in manual/virtual mode.

To set up *JACK*, one can use the script shipped with *Seq66*, `data/linus/startjack`. It has the following requirements and dependencies:

- `qjackctl`. Provides a way to show the connections. It also can start *JACK*, but we use `jack_control` for that in this script.
- `jack_control`. Provides a way to start *JACK* and set up a number of *JACK* parameters. Part of the *Debian jack2d* package.
- `a2j_control`. Provides a way to configure and start the *ALSA-to-JACK* bridge to create bridges for all the hardware MIDI ports on the computer. Part of the *Debian a2jmidid* package.
- `yoshimi`. Provides a software synthesizer for MIDI playback.
- `yoshimi-b4uacuse-gm.state`. Provides a "General MIDI" setup for *yoshimi*. Located in the `data/linux` directory.
- *Editing*. One must edit the script to change the value of `HWPORT`

One can also edit the script to use another software synthesizer. Once ready, Run `startjack` and wait patiently for it to set up.

11 Port Mapping

Seq66, like *Seq24*, bases its I/O port scheme on buss numbers (also called "port numbers"). This numbering scheme applies whether *ALSA*, *JACK*, or *Windows Multimedia* are used as the MIDI engine, and whether *Seq66* is running with "automatic" ports or "manual" (virtual, software-created) ports. These buss numbers range from 0 on upward based on the input or output MIDI ports active in the system. In "automatic" mode (REFERENCE) these ports represent the hardware ports and ports created by other applications. In "manual" mode, these ports represent virtual ports that can be connected through other software under *ALSA* or *JACK*.

A given pattern/loop/sequence can be assigned to output to a given port via a buss number that is saved with the pattern. Thus, when a tune is loaded, each sequence can automatically output to the desired MIDI device.

The problem is that the list of MIDI devices can change, with devices being reordered, removed, or added to the set of MIDI devices available on the system. Port mapping provides a partial solution to this issue. It allows the buss number stored with a pattern to be remapped to another buss number, based on the name of the port.

As with the normal port listings, the port-mappings are managed in the *Seq66* 'rc' file (REFERENCE).

11.1 Output Port Mapping

Assume that the system has the following set of ports. These busses are stored in the 'rc' file when *Seq66* exits.

```
[midi-clock]
6      # number of MIDI clocks (output busses)
0 0    "[0] 14:0 Midi Through Port-0"
1 0    "[1] 28:0 nanoKEY2 MIDI 1"
2 0    "[2] 36:0 E-MU XMidi1X1 Tab MIDI 1"
3 0    "[3] 40:0 USB Midi MIDI 1"
4 0    "[4] 44:0 Launchpad Mini MIDI 1"
5 0    "[5] 128:0 yoshimi:input"
```

If some items are unplugged, then this list will change, so save it. Click the **Save Clock/Input Maps** button in the **Edit / Preferences / MIDI Clock** dialog. The result is a new section in the 'rc' file:

```
[midi-clock-map]
1  # map is/not active
0  "Midi Through Port-0"
1  "nanoKEY2 MIDI 1"
2  "E-MU XMidi1X1 Tab MIDI 1"
3  "USB Midi MIDI 1"
4  "Launchpad Mini MIDI 1"
5  "input"
```

It is simpler, containing only an index number and shorter versions of the port names, called "nick-names". These index numbers can be used like buss numbers: they can be stored in a pattern, and used to direct output to a device by name. Let's say we've unplugged some devices, so that the MIDI clocks list is shorter:

```
[midi-clock]
4      # number of MIDI clocks (output busses)
0 0    "[0] 14:0 Midi Through Port-0"
1 0    "[1] 32:0 USB Midi MIDI 1"
2 0    "[2] 36:0 Launchpad Mini MIDI 1"
3 0    "[3] 128:0 yoshimi:input"
```

So, if a pattern has stored item 3 "USB Midi MIDI 1" as its output buss, and the output port map is active, the "3" is looked up in the map, the nick-name "USB Midi MIDI 1" grabbed, and looked up in the system list, which returns "1" as the buss number to use for output.

On the other hand, if a pattern has stored item 2 "E-MU XMidi1X1 MIDI 1" as its output buss, this item will not be found in the system list, so that the pattern will need to be routed to an existing port.

Note that the mapping can be disabled by setting the first value to 0. In that case, *Seq66* uses buss numbers in the normal way. In the user interface dropdowns for output buss, if a map is active, it is put into the dropdown; any missing items are noted and are shown as disabled. If the map is not active, then only the actual system output ports are shown.

11.2 Input Port Mapping

The input ports are handling somewhat similarly. Here's the initial system input setup:

```
[midi-input]
```

```
6      # number of input MIDI busses
0 1    "[0] 0:1 system:announce"
1 0    "[1] 14:0 Midi Through Port-0"
2 0    "[2] 28:0 nanoKEY2 MIDI 1"
3 0    "[3] 36:0 E-MU XMidi1X1 Tab MIDI 1"
4 0    "[4] 40:0 USB Midi MIDI 1"
5 0    "[5] 44:0 Launchpad Mini MIDI 1"
```

Note that the "system:announce" buss is always disabled, as *Seq66* does not use it. Here is the stored input port-map:

```
[midi-input-map]
0  "announce"
1  "Midi Through Port-0"
2  "nanoKEY2 MIDI 1"
3  "E-MU XMidi1X1 Tab MIDI 1"
4  "USB Midi MIDI 1"
5  "Launchpad Mini MIDI 1"
```

And here is the system input map with some devices unplugged.

```
[midi-input]
1  # map is/not active
0  "announce"
1  "Midi Through Port-0"
2  "USB Midi MIDI 1"
3  "Launchpad Mini MIDI 1"
```

Note that the mapping can be disabled by setting the first value to 0. In that case, *Seq66* uses buss numbers in the normal way. In the user interface dropdowns for input buss, if a map is active, it is put into the dropdown; any missing items are noted and are shown as disabled. If the map is not active, then only the actual system input ports are shown.

12 Seq66 Configuration

Seq66 configuration has become a lot more elaborate. Fortunately, most of the configuration is well documented with-in the *Seq66* "man" page and in the configuration files themselves. Therefore, this new discussion will be less prolix than it was for *Sequencer64*. Here are the topics to discuss:

- **Command-line Options**
- **'rc' File**
- **'usr' File**
- **'ctrl' File**
- **'mutes' File**
- **'drums' File**
- **'palette' File**
- **'playlist' File**

After the first run of *Seq66*, it will generate a set of configuration files in the default *configuration* directory, with names dependent on the version of *Seq66* being run:

```
/home/user/.config/seq66/qseq66.rc
/home/user/.config/seq66/qseq66.usr
/home/user/.config/seq66/qseq66.ctrl
/home/user/.config/seq66/qseq66.mutes
/home/user/.config/seq66/qseq66.drums
/home/user/.config/seq66/qseq66.playlist
```

The palette file is not automatically generated. It can be saved from the **Edit / Preferences** / **Display** tab.

For *Microsoft Windows*, the default base name of the files is `qpseq66`, and the default configuration directory is

```
C:/Users/user/AppData/Local/seq66/
```

When running *Seq66* from the *Non Session Manager* (see section [7 "Seq66 Session Management"](#) on page [65](#)), the configuration directory is automatically set to something like

```
/home/user/NSM Sessions/MySession/seq66.nRSIQ/config
```

There is no palette file by default, but the user can create one. The color palettes are discussed in section [16 "Palettes for Coloring"](#) on page [118](#).

These files contain the the data for remote MIDI control, computer keyboard control, MIDI clock, JACK transport, and a many other settings.

Seq66 always overwrites the most of these files upon exiting. One must therefore quit *Seq66* before making manual modifications to these files.

Some of the settings can be modified in the **Edit / Preferences** dialog, or overridden from the command line.

12.1 Configuration File Commonalities

All of the *Seq66* configuration files have the following in common:

- **[Seq66] Section**
- **[comments] Section**
- **Numeric Settings**
- **Boolean Settings**
- **Variables**
- **Stanzas**

Generally, each configuration file has its own specific set of sections, each section-name being enclosed in square brackets in a very strict format: No spaces inside the square brackets. Sections are looked up by this name, including the square brackets, and the name must be exact.

12.1.1 [Seq66] Section

This section is generally just informational. At a minimum, it holds two variables:

- **config-type**. This value indicates the type of the file, such as "ctrl" or 'rc'.
- **version**. This value indicates the version of the file. Currently, it is not used, but once *Seq66* solidifies, it can be used to make adjustments for changes in configuration when reading older versions of files.

This section may also contain additional "global" variables specific to a given **config-type**.

12.1.2 [comments] Section

This section is also informational, but the user can edit this section to include information describing the purpose of the file. For example, a 'ctrl' file for a *Novation Launchpad* might describe the purpose of this file. The comments stop at the first blank (not even spaces) line. To skip a line in the comment, put a single space character on the blank line.

12.1.3 Numeric Settings

Numeric settings consist of a line containing one or more numbers, usually preceded by an explanatory comment, and followed by a standard script comment.

```
3      # grid_style
```

12.1.4 Boolean Settings

Boolean settings are the same as numerical settings, but have only two values: "0" or "1".

```
0      # flag to record incoming data by channel
```

12.1.5 Variables

Variable are a new style of value setting, and can encompass not only booleans and numeric values, but string values, which may correspond to enumerated values in the source code. These values are specified by a section-name plus variable-name pair.

```
[mute-group-flags]
save-mutes-to = both
. . .
```

12.1.6 Stanzas

A stanza in a *Seq66* configuration file consists of some data at the beginning, a set of values bracketed by square brackets, and some optional data at the end. The values inside the square brackets are numeric, and can be in decimal format, sometimes hexadecimal format, or in binary "0/1" format.

```
0 "1" [ 0 0 0x00 0 0 0 ] [ 0 0 0x00 0 0 0 ] [ 0 0 0x00 0 0 0 ] # Loop 0
1 "q" [ 0 0 0x00 0 0 0 ] [ 0 0 0x00 0 0 0 ] [ 0 0 0x00 0 0 0 ] # Loop 1
2 "a" [ 0 0 0x00 0 0 0 ] [ 0 0 0x00 0 0 0 ] [ 0 0 0x00 0 0 0 ] # Loop 2
3 "z" [ 0 0 0x00 0 0 0 ] [ 0 0 0x00 0 0 0 ] [ 0 0 0x00 0 0 0 ] # Loop 3
. . .
```

12.2 Command Line

Command-line options are well-described in the *Seq66* "man" page. Here, we will present a brief note about each option, and, where applicable, a reference to the corresponding configuration file option. Here is the basic command line:

```
qseq66 [options list] [MIDI filename]
```

-h --help Display a list of all command-line options, then exit.

-v --version Display the program version, then exit.

-H --home [directory] Change the "home" configuration directory from \$HOME.config/seq66
The configuration files are loaded from or saved to the specified directory.

-b --bus [buss] Modifies the output buss number on *all* tracks when a MIDI file is read.
Useful for testing or quick-and-dirty setup.

-q --ppqn [ppqn] Supports modifying the PPQN value of *Seq66*, which is defaults to a value of 192. This setting is written into the MIDI file when it is saved. The PPQN value can range from 32 to 19200, or be set to 0 to use the PPQN from the loaded file.

```
qseq66.usr: [user-midi-settings] midi_ppqn .
```

-L --lash If LASH support is compiled into the program, this option enables it. Deprecated.
See **usr: [user-session] session**.

```
qseq66.usr: [user-session] session
```

-m --manual-ports *Seq66* won't attach the system's existing ALSA or JACK MIDI ports. Instead, it will create its own set of virtual input and output busses/ports. The default number of port is 1 for input, and 16 for output, but these values can be changed in the 'rc' file.

```
qseq66.rc: [manual-ports] flag for manual/virtual ports
```

-a --auto-ports *Seq66* will automatically attach to the system's existing ALSA/JACK ports.

```
qseq66.rc: [manual-ports] flag for manual/virtual ports
```

-r --reveal-ports *Seq66* will show the names of the ALSA/JACK ports that the system defines, rather than the names defined in the 'usr' configuration file.

-R --hide-ports *Seq66* will show the names of the ALSA port that the 'user' configuration file define, rather than the names defined by ALSA.

qseq66.rc: [reveal-ports] flag for reveal ports
qseq66.usr: [user-midi-bus-definitions] number of user-defined busses

-A --alsa Seq66 will run with ALSA, even if JACK is running. This option is "sticky" (they are saved).

-t --jack-midi Seq66 will run with JACK, which is the default if JACK is running.

qseq66.rc: [jack-transport] with_jack_midi

-s --show-midi Dumps incoming MIDI to the screen.

-p --priority Runs at higher priority with a FIFO scheduler.

-k --show-keys Prints pressed key value.

-K --inverse Changes the color palette for the sequence editor and performance editor piano rolls. Also note that the palette is highly configurable.

qseq66.palette: [palette] inverse

-X --playlist [filename] This option loads the given file-name as a play-list file. See section [13 "Seq66 Play-Lists" on page 109](#).

qseq66.rc: [playlist] name
qseq66.playlist: [playlist] full

-j --jack-transport Seq66 will sync to JACK transport.

qseq66.rc: [jack-transport] with_jack_transport

-J --jack-master Seq66 will try to be JACK master.

qseq66.rc: [jack-transport] with_jack_master

-C --jack-master-cond JACK master will fail if there is already a master.

qseq66.rc: [jack-transport] with_jack_cond

-M --jack-start-mode [x] When Seq66 is synced to JACK, the following play modes are available: 0 = live mode; and 1 = song mode, the default.

qseq66.rc: [jack-transport] song_start_mode

-U --jack-session-uuid [uuid] Set the UUID for the JACK session.

-u --user-save Save the 'usr' configuration file when exiting. Normally, it is saved only if not present in the configuration directory, so as not to get stuck with temporary settings such as the --bus option.

qseq66.rc: [auto-option-save] auto-save-options-on-exit

-f --rc filename Use a different 'rc' configuration file. It must be a file in the user's \$HOME/.config/seq66 directory or the directory specified by the --home option. The .rc extension is added if necessary.

-F --usr filename Use a different 'usr' configuration file. Similar to the --rc option.

-c --config basename Use a different configuration file base name for the 'rc' and 'usr' files. For example, one can specify a full configuration for "testing", for "jack", or for "alsa", to set up testing.rc and testing.usr, jack.rc and jack.usr, alsa.rc and alsa.usr.

-o --option opvalue Provides additional options, since the application is running out of single-character options. The opvalue set supported is:

- **daemonize** and **no-daemonize**. Makes the **seq66cli** application fork to the background, or makes the **seq66cli** application run in the foreground so that console output can be seen.
- **log=filename.log**. Reroutes standard error and standard output messages to the given log-file. This file is located in the configuration directory. If this file is present, additional log information is appended. The default log-file name is specified in the **[user-options]** section of the 'usr' file.
- **sets=8x8**. This option, informally known as "variset", allow some changes in the set size and layout from the default $4 \times 8 = 32$ sets layout. Consider this option to be experimental. Expect problems. To save these options to the 'usr' file, add the **--user-save** option to the command line. In that file, the options modified are **mainwnd_rows** and **mainwnd_cols**.
- **scale=WxH**. This option scales the main window by the given factors, ranging from 0.75 to 3.0.
- **mutes=value**. Specifies the saving of mute-groups to the 'mutes' file, 'midi' file, or 'both' files.
- **virtual=o,i**. Set up the manual-ports option with 'o' output ports and 'i' input ports.

Many of the above options are including in the relevant configuration files. We will point to them in the future.

12.3 'rc' File

```
/home/user/.config/seq66/qseq66.rc
```

The 'rc' configuration file has undergone a lot of changes, including off-loading the keyboard control, MIDI control, and mutes control sections into their own files, and adding a few "variable" settings. Rather than repeating information already present in the self-documenting 'rc' file, we will summarize the settings and refer the reader to the sample files for more information.

The 'rc' file adds these [Seq66] options to the common data for all configuration files:

```
verbose = false
sets-mode = normal
port-namng = short
```

verbose is the same as the **--verbose** command-line option, except that, if set to "true", it affects every invocation of Seq66.

The **sets-mode** option determines if sets are muted when going to the next play-screen ('normal'), while 'autoarm' will automatically unmute the next set. The 'additive' options keeps the previous set unmuted when moving to the next set. These are options requested by users.

The port-naming values are 'short' or 'long'. The short style just shows the port number and short port name; the long style shows all the numbers and the long port name.

12.3.1 'rc' File / MIDI Control

Seq66 offloads MIDI control to a separate file. Move or create the **[midi-control]** section to a separate file in the Seq66 configuration directory, and add the following snippet:

```
[midi-control-file]
"qseq66.ctrl"          # contains a whole [midi-control] section
```

As with the 'rc' file, the 'ctrl' file is rewritten upon exit. For the details of the 'ctrl' file, see section [12.5 "'ctrl' File"](#) on page [103](#).

12.3.2 'rc' File / Mute Groups

```
[midi-group-file]
"qseq66.mutes"          # contains a whole [mute-groups] section
```

The mutes-groups sections is written on exit dependent on the `save-mutes-to` option in the mute-groups file.

12.3.3 'rc' File / Color Palette

```
[palette-file]
1      # palette_active
"qseq66.palette"
```

The only need for a palette file is when the user is not satisfied with the default palette for the patterns, inverse colors, or hatching for some pattern piano roll items. There is a button to save the current/default palette for later modification in the **Edit / Preferences / Display** tab.

12.3.4 'rc' File / Note Mapper

```
[note-mapper]
1
"qseq66.drums"
```

This file can be used transform the existing drum (non-transposable) tracks into another set of drum tracks. A lot of work has been done in the past with non-General-MIDI instruments (particularly consumer instruments like the Yamaha *PSS-780*). This option is useful for transformation older MIDI files into GM format.

12.3.5 'rc' File / MIDI-Clock Section

The MIDI Clock fields contain the clocking state from the last time *Seq66* was run, and their status, and their names. Turn off the clock with a 0, or on with a 1 (which means to send **MIDI Song Position**, and **MIDI Continue** if starting after tick 0), or on with positioning with a 2, which sends **MIDI Start** and then begins clocking after the position reaches a modulo of the **Clock Start Modulo value**). Luckily, the user-interface makes it easy to select the desire value, and has tool-tips to instruct the user. This section has entries for each MIDI output buss.

This configuration item is represented in the **Edit / Preferences / MIDI Clock** tab.

```
[midi-clock]
5    # number of MIDI clocks (output busses)
0 0    "[0] 14:0 Midi Through Port-0"
1 0    "[1] 128:0 TiMidity port 0"
2 0    "[2] 128:1 TiMidity port 1"
```

. . .

12.3.6 'rc' File / MIDI Clock Mod Ticks

This configuration item is the same as the **Edit / Preferences / MIDI Clock / Clock Start Modulo** option.

```
[midi-clock-mod-ticks]
64
0 # flag to record incoming data by channel
```

The record-flag is kind of an outcast. Not sure why it is here, something to rectify later.

12.3.7 'rc' File / MIDI-Meta-Events Section

The new MIDI Meta events section is the start of additional options supporting meta events as normal events in *Seq66*. This section defines just one feature of MIDI meta-event handling at present. Normally, tempo events are supposed to occur in the first track (pattern 0). But one can move this track elsewhere to accomodate one's existing body of tunes. If affects where tempo events are recorded. The default value is 0, the maximum is 1023. A pattern must exist at this number for it to work.

```
[midi-meta-events]
10 # tempo_track_number
```

As per the MIDI specification, the first track (track 1 in track numbering, or pattern 0 in *Seq66* numbering) is *the official track* for certain MIDI meta events, such as **Set Tempo** and **Time Signature**. However, to accommodate existing tunes and their set arrangement, we allow the user to and change the tempo track to another pattern.

12.3.8 'rc' File / Keyboard Control Section

The keyboard control has been merged into the MIDI control and been moveed into the 'ctrl' file. There is no longer any user-interface to change the keyboard control, for two reasons: (1) It is pretty easy to read, understand, and edit the 'ctrl' file, and (2) There are many more controls in *seq66*, and creating a user-interface to edit them would not be worth the effort. We suspect most users will be happy enough with the default settings, and users of internationaly keyboards will find the 'ctrl' file easy enough to edit with a programmer's editor.

12.3.9 'rc' File / JACK Transport

This section holds the settings for both JACK transport and for native JACK MIDI mode.

The JACK Transport options are also command-line options. See section [12.2 "Command Line"](#) on page [89](#).

```
[jack-transport]
0  # with_jack_transport
0  # with_jack_master
0  # with_jack_master_cond
0  # song_start_mode
0  # with_jack_midi
```

These options are described well in the 'rc' file.

Please note that the JACK transport options are set to make sense, no matter what the user specifies. Also note that JACK transport is separately configurable from JACK MIDI, and each uses a different JACK client internally. We might combine them at some point, if necessary.

12.3.10 'rc' File / MIDI Input

This configuration item is represented in the **MIDI Input** tab in the **Edit / Preferences**. The first number is a line count, and would equal the number of supported input ports. After that, this 'rc' entry here has two variables; the first is the port number, and the second number indicates whether it is disabled (0), or enabled (1). The next lines show the input busses present on the system (normally).

```
[midi-input]
2  # number of MIDI busses
0 1    "[0] 0:1 system:announce"
1 0    "[1] 14:0 Midi Through Port-0"
```

Again, see the 'rc' file itself for more information.

12.3.11 'rc' File / Manual ALSA Ports

The name of this setting is a bit of a misnomer in a couple of ways:

1. It actually refers to the usage of *virtual* MIDI ports. These are ports that are set up by the application so that other devices, applications, or session managers can connect *manually* to the MIDI application.
2. This option is not just for ALSA. It can also be used when running in native JACK mode, to support virtual JACK ports that can be connected manually (e.g. in the *QJackCtl* application.)

```
[manual-ports]
0  # flag for manual (virtual) ALSA or JACK ports
8  # number of manual/virtual output ports
4  # number of manual/virtual input ports
```

The opposite of *--manual-ports* is *--auto-ports*, which is the normal mode of running *Seq66*. In this mode, system MIDI input/output devices are discovered and automatically connected.

It will create port names as per the settings in the 'usr' configuration file's sections:

```
[user-midi-bus-definitions]
[user-midi-bus-N]
```

These definitions can be used by JACK for connection, and these definitions can be used to specifically rename the ports that exist in the system. This option is misleading if one wants to have access to the actual ALSA/JACK ports that exist on the system. The next option gets around that issue.

12.3.12 'rc' File / Reveal ALSA Ports

This option applies to both ALSA and JACK.

```
[reveal-ports]
1 # flag for reveal ALSA ports
```

Turning on the reveal-ports option is necessary if one wants to see the actual port names defined by the system. It ignores the settings in the 'usr' configuration file's `user-midi-bus-definitions` and `user-midi-bus-N` sections. If this option is turned on, the definitions in the 'usr' configuration file are *not* read from that file.

12.3.13 'rc' File / Interaction Method

```
1 # allow_mod4_mode
1 # allow_snap_split
1 # allow_click_edit
```

The Mod4 ("Windows" key) option is still available, but no longer necessary. Also removed is the option for the "fruity" option of *Seq24*. It will be added if there is a clamor for it.

This option comes from the *seq32* project. It allows for pattern-splitting in the Song editor at snap points, rather than just at the middle of the pattern.

This option allows one to enable/disable the ability to double-click in a pattern slot in the main window to bring it up for editing. This can interfere with a live performance where muting/unmuting come fast enough to be seen as a double-click.

12.3.14 'rc' File / Auto Option Save

This item determines if the 'rc' configuration file (and other files) is saved upon exit of *Seq66*. The normal behavior is to save it, which can sometimes be inconvenient when one is just trying out some command-line options.

```
[auto-option-save]
0 # auto-save-options-on-exit support flag
```

12.3.15 'rc' File / Last Used Directory

The following item refers to the last directory in which one opened or saved a MIDI file.

```
[last-used-dir]
/home/ahlstrom/Home/ca/mls/git/seq66/contrib/midi/
```

12.3.16 'rc' File / Recent Files

The following item preserves a list of the last few MIDI files loaded. It is not filled when a MIDI file is loaded via a play-list. The first number is the count of recent-files. The second number is a boolean, set to "1" if the most-recent file should be loaded when *Seq66* starts. This option is useful as part of restoring a session.

```
[recent-files]
2 1
"/home/user/Home/ca/mls/git/seq66-alternate/contrib/midi/2Bars.midi"
"contrib/midi/b4uacuse-seq24.midi"
```

12.3.17 'rc' File / Play-List

This item provides a configured set of named play-lists in a play-list file, and a flag to activate it. Having a playlist makes it easy to load song after song from pre-determined lists.

```
[playlist]
0      # playlist_active, 1 = active, 0 = do not use it
"/home/ahlstrom/.config/seq66/sample.playlist"
```

See section [13 "Seq66 Play-Lists" on page 109](#). It describes the setup, layout, and usage of a *Seq66* playlist file containing one or more playlists.

12.4 'usr' File

This section describes the *Seq66* 'usr' (or "user") file. The *Seq66* 'usr' configuration file provides a way to give more informative names to the MIDI busses, MIDI channels, and MIDI controllers of a given system setup. This configuration overrides the default values of the **Event** drop-down list and menu items in the Pattern editor, and make them reflect the names of the MIDI Control (CC) values of one's devices.

In *Seq66* it, also includes some items that affect the user-interface's look, and many other new configuration items.

Unlike the 'rc' file, the 'usr' file is *not* written every time *Seq66* exits. If the 'usr' file does not exist, one is created, but it is normally not overwritten thereafter. To cause it to be overwritten at exit, run *Seq66* with the **-u** or **--user-save** option:

```
$ qseq66 --user-save
```

This option is recommended when one installs a new version of *Seq66*, which might add new options to the 'usr' file. One usually must edit the 'usr' file manually. There are a few items that can be tweaked in the *Seq66* application, and if they are modified, the user-save flag is turned on.

By default, the list of MIDI devices that *Seq66* shows depends on one's system setup and whether the manual-port option is specified or not. Here's our system, with the [manual-port] option turned off, shown in a composite view with all menus one can look at for MIDI settings:




Figure 22: Seq66 Composite View of Native Devices

At the top, the buss dropdown menu contains the MIDI busses/ports active on this computer. At right, the MIDI channel shows the channels numbers that can be picked for buss 0. At bottom left, we see the default controller values that *Seq66* includes. We have no idea if these correspond to any controllers that the selected MIDI buss supports. We can use this dropdown to see if any such controller events are in the loaded MIDI file, of course; a solid black square indicates that such an event was found in the pattern.

To change the defaults, we can create a 'usr' file to set them up. The discussion here relies on the reader opening the file `sample.usr`, which is included in the shared `data/samples` directory provided once *Seq66* is installed.

Assume we have 3 MIDI "buss" devices hooked to our system: two Model "2x2" MIDI port

devices, and an old PCR-30 MIDI controller keyboard. Let's number them:

1. Model 2x2 A
2. Model 2x2 B
3. PCR-30

Then assume that we have nine different MIDI instruments in our kit. Let's number them, too:

1. Waldorf Micro Q
2. SuperNova
3. DrumStation
4. TX81Z
5. WaveStation
6. ESI-2000
7. ES-1
8. ER-1
9. TB-303

The *Waldorf Micro Q*, the *SuperNova*, and the *DrumStation* all have a large number of special MIDI controller values for modifying the sound they produce. The *DrumStation* accepts MIDI controllers that change various features of the sound of each type of drum it supports.

The buss devices can be configured to route certain MIDI channels to certain MIDI devices. Assume we have them set up this way:

1. Bus 0: Model 2x2 A
 - SuperNova: channels 1 to 8
 - TX81Z: channels 9 to 11
 - Waldorf Micro Q: channels 12 to 15
 - DrumStation: channel 16
2. Bus 1: Model 2x2 B
 - WaveStation: channels 1 to 4
 - ESI-2000: channels 5 to 14
 - ES-1: channel 15
 - ER-1: channel 16
3. Bus 2: PCR-30
 - TB-303: channel 1

We use the **'usr' configuration file**. to show these items with the proper names associated with each device, channel, and controller value

The Seq24 configuration file was called `.seq24usr`, and it was stored in the user's `$HOME` directory. Seq66 uses a new file-name to take its place. After one runs Seq66 for the first time (or after deleting the configuration files), it will generate a `seq66.usr` file in one's HOME directory:

```
/home/user/.config/seq66/seq66.usr
```

It allows you to give an alias to each MIDI bus, MIDI channel, and MIDI control codes, per channel. The process for setting up the 'usr' file is to:

1. Define one or more MIDI busses, the name of each, and what instruments are on which channels. Each bus is configured in a section of the form "[user-midi-bus-X]", where "X" ranges from 0 on up. Each bus then defines up to 16 channel entries. Each entry includes the channel number and the number of a section in the user-instrument section described next.
2. Define all of the instruments and their controller names, if they have them. Each instrument is configured in a section of the form "[user-instrument-X]", where "X" ranges from 0 on up. Up to 128 controllers can be defined.

Let's walk through the structure of this setup, since it is a little bit tricky.

The first important section in the 'usr' file is [user-midi-bus-definitions]. This section contains an number of [user-midi-bus-N] sections, where "N" ranges from 0 on upward. These correspond to the MIDI *output* busses expected to be in the system (ignoring the ALSA "announce" bus if ALSA is the MIDI engine being used).

Each of the busses contains 16 (0 to 15) channel entries. These channels are referred to as "instrument numbers", and are represented as and linked to "instruments" in this section:

```
[user-instrument-definitions]
```

Each instrument contains up to 128 controller values; these controller values are available in the **Event** button in the Pattern Editor, and their names are shown.

So, each instrument is setup as a "channel" in a particular "bus". In the Pattern Editor, when a particular bus and channel is selected, the **Event** menu entries should match the controller entries set up in the 'usr' file.

The list of devices and channels shown earlier can be seen in the Seq66 sample file `sample.usr`. Deducting 1 from each device number and channel number (so that numbering starts from 0), and consulting the device manuals to determine the controller values supported, one can assemble a 'usr' configuration file that makes the setup visible in Seq66.

Peruse the next couple of sections to understand a bit about the format of this file, following along in the sample 'usr' file.

12.4.1 'usr' File / MIDI Bus Definitions

This section begins with an "INI" group marker [user-midi-bus-definitions]. It defines the number of user busses that will be configured in this file.

```
[user-midi-bus-definitions]
3      # number of user-defined MIDI busses
```

This means that the 'usr' file will have three MIDI bus sections: [user-midi-bus-0], [user-midi-bus-1], and [user-midi-bus-2]. Here's is an example of one such section:

```
[user-midi-bus-0]
2x2 A (SuperNova,Q,TX81Z,DrumStation)
16
0 1
```

```

1 1      # Instrument #1 of the [user-instrument-definitions] section
. .
8 3      # Instrument #3 of the [user-instrument-definitions] section
9 3
. .
11 0     # Instrument #0 of the [user-instrument-definitions] section
12 0     # This is the Waldorf Micro Q device
. .
15 2     # Instrument #2 of the [user-instrument-definitions] section

```

These instrument-definition sections are read from the 'usr' configuration file only if the "reveal ports" option is *off* ("0"); this option can also be specified in the [**reveal-ports**] section of the 'rc' file. Otherwise, the actual port names reported by ALSA/JACK are shown.

The **user-midi-bus-definitions** and **user-midi-bus-N** sections can be misleading if one wants to have access to the actual MIDI port names that exist on the system. It is left as an exercise for the reader to try these different combinations of show-port options. Or one can consult the *Sequencer64 User Manual* to see the figures.

- Clocks View, -m (--manual-ports)
- Inputs View, -m (--manual-ports)
- Clocks View, -m (--manual-ports) and -R (--hide-ports)
- Clocks View, -r (--reveal-ports)
- Inputs View, -r (--reveal-ports)
- Clocks View, -R (--hide-ports)

12.4.2 'usr' File / MIDI Instrument Definitions

This section begins with an "INI" group marker [**user-instrument-definitions**]. It defines the number of user instruments that will be configured in this file. This section defines characteristics, such as the meanings of MIDI controller values, of the instruments themselves, not the MIDI busses to which they attached.

```
[user-instrument-definitions]
9      # number of user instrument
```

So this 'usr' file will define 9 instruments. We provide only one section as an example. Note that items without text default to the values prescribed by the General MIDI (GM) specification.

```
[user-instrument-0]
Waldorf Micro Q          # name of instrument
128                      # number of MIDI controllers
0                        # first controller value, unnamed
1 Modulation Wheel
2 Breath Control
3
4 Foot Control
. .
123 All Notes Off (0)    # defaults to GM
124
125 Unsupported
126 Unsupported
```

127

defaults to GM

Note the unnamed control numbers above. An unnamed control number might be an unsupported control number. It is termed to be "inactive". In this case, the **Event** menu of the Pattern editor will show the default name of this controller. Again, though, the function denoted by this name might not be supported by the device. In that case, it might be better to call it "Unsupported". See the examples above. See the figure below for one example as set up using the **sample.usr** file:




Figure 23: Seq66 Composite View of Devices As Set in "sample.usr"

12.4.3 'usr' File / User Interface Settings

This section, new to *Seq66*, begins with an "INI" group marker [**user-interface-settings**].

It provides for a feature we will hopefully be able to complete some day: the complete specification of the appearance of the user-interface. There is plenty of room to change the appearance of *Seq66* already! Please try the settings and see what looks good. Refer to either the sample file or the file generated when *Seq66* first runs.

```
[user-interface-settings]
1      # grid_style
2      # grid_brackets
4      # mainwnd_rows
8      # mainwnd_cols
32     # max_sets
```

There are a number of additional user-interface options. See the generated or sample 'usr' file for descriptions. Also see the chapter on palettes.

12.4.4 'usr' File / User MIDI Settings

This section begins with an "INI" group marker [`user-midi-settings`]. It supports files with different PPQN, and allows one to specify the global defaults for tempo, beats per measure, and so on.

```
[user-midi-settings]
192    # midi_ppqn
4      # midi_beats_per_measure/bar
120    # midi_beats_per_minute
4      # midi_beat_width
-1     # midi_buss_override
80     # velocity_override (-1 = 'Free')
```

The `velocity-override` option fixes a long standing (from *Seq24*) bug where the actual incoming note velocity was always replaced by a hard-wired value.

```
1      # bpm_precision
0.1   # bpm_step_increment
5.0   # bpm_page_increment
```

The `bpm-precision`, `bpm-step-increment`, and `bpm-page-increment` values allow more precise control over tempo, which makes it easier to match the tempo of external music sources. Note that the step-increment is used by the up/down arrow buttons, the up/down arrow keys, and the MIDI BPM control values. The page-increment is used if the BPM field has focus and the Page-Up/Page-Down keys are pressed, and new MIDI control values have been added to support coarse MIDI control of tempo.

```
0      # midi_bpm_minimum
360   # midi_bpm_maximum
```

The `midi-bpm-minimum` and `midi-bpm-maximum` settings are used in scaling the display of Tempo events. By adjusting these values, one can more easily see the variations in tempo. In a main window pattern slot, or in the song editor tempo track, this range is scaled to the full range of note values, 0 to 127. Generally, one wants to select a range that keeps the main tempo line at the middle height of the pattern display.

To obtain these new settings, remember to backup the existing `seq66.usr`, then run *Seq66* with the `--user-save` option, and then do a "diff" on the new file and the original to merge any old values that need to be preserved. Then make any further tweaks to the new values.

12.4.5 'usr' File / User Options

This section begins with an "INI" group marker [`user-options`]. It provides for additional options keyed by the `-o`/`--option` options. This group of options serves to expand the options that are available, since *Seq66* is running out of single-character options. This group of options are shown below.

```
0      # option_daemonize
```

If this option is not used when running `seq66cli`, then the application stays in the console window and dumps informational output to it. If this option is in force, then the only way to affect `seq66cli` is to send a signal (e.g. SIGKILL) to it, or use MIDI control.

```
"seq66.log"
```

This log-file is written to the same directory as the 'usr' file, the *Seq66* configuration directory. If empty, then a valid file-name must be specified in the `--option log=filename.log` option. There's more to the 'usr' configuration file than we've exposed here.

12.5 'ctrl' File

Like *Seq24*, *Seq66* provides a way to control the application to some extent via a MIDI controller, such as a MIDI keyboard or a MIDI pad device. The current section describes this feature; additional resources and ideas can be found at linuxaudio.org ([9]). Also see the tutorial section [section 18 "Launchpad Mini"](#) on page [122](#).

This file provides settings for keyboard control, MIDI control, and for specifying MIDI output to reflect *automation* commands in a device such as the *LaunchPad*. The name of this file is specified in the 'rc' file as noted earlier.

12.5.1 'ctrl' File / MIDI Control Settings

```
/home/user/.config/seq66/qseq66.usr
```

This file offloads the control settings from the 'rc' file, for a more flexible setup. It starts with the sections common to all *Seq66* configuration files. The first unique section defines some useful settings using the new variables feature of the configuration. Look at the sample or generated file to see the layout of these items.

- **load-key-controls**. Generally, this should always be set to "true".
- **load-midi-controls**. This one could plausibly disabled, but for live performance will certainly be set to "true".
- **control-buss**. The control-buss value ranges from 0 to the maximum buss provided by the hardware on the system. If set, then only that buss will be allowed to send MIDI control. A value of 255 or 0xff means any buss can send MIDI control.
- **midi-enabled**. If set to "true", then the MIDI controls will be used. It can be set to "false", while keeping the configuration in place for later usage.
- **button-offset**. This item provides a way to move a set of input controls (e.g. from a *Launchpad Mini*) to a different area of the input control device. Not yet supported.
- **button-rows**. Indicates the rows of the input control grid. Still in progress.
- **button-columns**. Indicates the columns of the input control grid. Still in progress.

12.5.2 'ctrl' File / Loop Control

The loop-control group consists of 32 lines (0 to 31), one for each pattern slot shown in the patterns panel. It provides a way to control the arming/disarming (muting/unmuting) of each pattern shown in the patterns panel. It consolidates the keyboard and MIDI control settings into one table.

Note that the main window shows the *active* screen-set. These MIDI controls affect the *active* screen-set.

This block of matrix elements, numbered from 0 to 31, represent control functions (toggle, mute, unmute) for the 32 patterns of the active screen-set. These 32 rows correspond to the hot-keys assigned in the **File / Options / Keyboard / Control keys [keyboard-group]** configuration panel.

The MIDI control section begins with the following "INI"-style group marker tag, followed by one stanza-line per loop:

```
[loop-control]
0 "1" [ 0 0 0x00 0 0 0 ] [ 0 0 0x00 0 0 0 ] [ 0 0 0x00 0 0 0 ] # Loop 0
. . .
```

The first number is an index number, starting at 0. It indicates what loop the control line will affect. The numbers in the leftmost brackets define a *toggle* filter; the numbers in the middle brackets define an *on* filter; the numbers in the rightmost brackets define an *off* filter. The numbers inside each set of brackets define six values that set up the control. The layout of each filter inside the brackets is as follows:

[OPR INV STAT D1 D2min D2max]

- **OPR** = **on/off**
- **INV** = **inverse**
- **STAT** = **MIDI status byte** (channel ignored)
- **D1** = **data1**
- **D2min** = **data2 min**
- **D2max** = **data2 max**

If **OPR (on/off)** is set to 1, it will match the incoming MIDI against the **STAT (MIDI status byte)** pattern. and perform the action (on/off/toggle) if the data falls in the range specified. All values are in decimal.

The **INV (inverse)** field will make the pattern perform the opposite action (*off* for *on*, *on* for *off*) if the data falls outside the specified range. This is cool because one can map several sequences to a knob or fader.

The **STAT (MIDI status byte)** field is a MIDI status byte number in decimal or hexadecimal notation. One can look up the possible status values up in the MIDI messages tables; the relevant data can be found at [\[10\]](#).

The last three fields describe the range of data that will match. The **D1 (data1)** field provides the actual MIDI event message number to detect, in decimal. This item could be a Note On/Off event or a Control/Mode change event, for example.

The **D2min (data2 min)** field is the minimum value of the event for the filter to match. For Note On/Off events, this would be the velocity value, for example.

The **D2max (data2 max)** field is the maximum value of the event for the filter to match.

For each pattern, we can set up MIDI events to turn a pattern on, off, or to toggle it.

The MIDI control setup resembles a matrix. This matrix is divided into a number of sections depending on the overall functionality of the MIDI controls in the section:

12.5.3 'ctrl' File / Mute-Group Control

This section provides controls for 32 groups of mutes. A group is a set of patterns that can toggle their playing state together. Every group contains all 32 sequences in the active screen set. So, this part of the MIDI Control section is used for muting and unmuting (and toggling) a group of patterns using a keystroke or MIDI control. The definitions are in the same format as the loop-control section.

```
[mute-group-control]
0 "!" [ 0 0 0x00 0 0 0 ] [ 0 0 0x00 0 0 0 ] [ 0 0 0x00 0 0 0 ] # Mute 0
. . .
```

All this section does is set up the controls to be used; the actual mute-group patters are defined in a 'mutes' configuration file.

12.5.4 'ctrl' File / Automation Control

This section provides ways to control *Seq66* push-button controls from a keyboard or from a MIDI device. These entries control *Seq66* actions like changing the BPM value, screen-set, record, solo, etc.

Each item in this group consists of one line. Each line specifies a MIDI event that can cause a given *Seq66* user-interface operation to occur. These items are easy to view in the 'ctrl' configuration file, in the [automation-control] section.

```
[automation-control]
0 "" [ 0 0 0x00 0 0 0 ] [ 0 0 0x00 0 0 0 ] [ 0 0 0x00 0 0 0 ] # BPM Up
. . .
```

12.5.4.1 Automation / BPM Up and Down

These controls increment or decrement the beats-per-minute setting, as if the up- or down-arrow has been clicked in the BPM combobox, or the up- or down-arrow key pressed, in that combo-box. This increment is the "step increment" which defaults to 1, but can be modified by changing the "bpm_step_increment" value in the 'usr' configuration file.

12.5.4.2 Automation / Screen-Set Up and Down

Also abbreviated "Set Up" and "Set Down". This control increments / decrements to the next / previous screen-set. Once the screen-set has been altered, mute-groups and other actions apply to that screen set.

12.5.4.3 Automation / Mod Replace

This control the "replace" flag. Then, when the user manually clicks a pattern slot, that pattern is unmuted, and all the rest are muted. Thus, this MIDI control is kind a of "Solo" function. It works whether in "Live" or "Song" mode.

12.5.4.4 Automation / Mod Snapshot

This control causes the playing statuses of all active (i.e. having data) patterns to be saved. When turned off, the original playing status is restored. Thus, two MIDI events need to be allocated to this functionality.

12.5.4.5 Automation / Mod Queue

This control sets up the "queue" status flag. Then, when the user manually clicks a pattern slot, that pattern is queued, and will play at the next cycle of the pattern.

Here is an example from [9], which shows how to set up the "Sustain" control-change event to queue or un-queue a sequence: The *Akai MPK Mini* has a Sustain button and we can set the Sustain MIDI event (with MIDI status byte 176 [0xB0] to represent a Controller event, and control/mode change number 64 [0x40] to represent the Sustain or Pedal control) up as the queue modifier in the `mod queue` entry:

```
6 "o" [ 0 0 0x00 0 0 0 ] [ 1 0 0xB0 64 127 127 ] [ 1 0 0xB0 64 0 0 ]
#      OPR INV STA D1 mn mx   OPR INV STA D1 mn mx     OPR INV STA D1 mn mx
#          ^ ^           | |           ^ ^           | |
#          | |           | |           | |           |
#          | -----Sustain----- |           |
#          -----Control Change-----
```

So when the Sustain button is held down, and one presses one of the pads on the *MPK Mini*, the corresponding sequence gets queued.

Also included in the data directory are sample 'ctrl' files for other devices.

12.5.4.6 Automation / Mute Group

This MIDI control sets up a "group learn". This control sets two internal flags on : "mode-group" and "group-learn". The first flag indicates that we will be handling mute-groups. The second flag indicates that we are learning these mute-groups, effectively recording the current status of all the patterns in all of the screen-sets.

Note that this control corresponds to the "L" button in the main window user-interface. It can also be accessed by the hard-wired hot-key, **Ctrl-L**. and the default hot-key, 1.

12.5.4.7 Automation / Screen-Set Play

This MIDI control sets the playing screen-set.

12.5.5 Automation / More MIDI Control

Many additional control items were requested by users, to control additional features of the application. Too many to list here. See the 'ctrl' file samples for more information.

12.5.6 'ctrl' File / MIDI Control Output

This section provides a way to have a MIDI device, such as the *Novation Launchpad Mini*, show the status of the patterns that are active, as well as other information.

```
[midi-control-out-settings]
set-size = 32
output-buss = 1
enabled = false
button-offset = 0
button-rows = 8
button-columns = 8
```

The first section sets up some general settings.

- **set-size**. Provides the set size. The default is 32, in a 4 x 8 grid.
- **output-buss**. Indicates where automation-display controls are to be sent. Specify the output buss to which the display device is attached.
- **midi-enabled**. If set to "true", then the MIDI control outputs will be used. It can be set to "false", while keeping the configuration in place for later usage.
- **button-offset**. This item provides a way to move a set of output controls (e.g. from a *Launchpad Mini*) to a different area of the output control device. Not yet supported.
- **button-rows**. Indicates the rows of the output control grid. Still in progress.
- **button-columns**. Indicates the columns of the output control grid. Still in progress.

```
[midi-control-out]
0 [1 0 0x90 0 60] [1 0 0x90 0 15] [1 0 0x90 0 62] [1 0 0x90 0 12]
. . .
```

The first number is the pattern number of the pattern whose armed/muted status is to be shown. There are samples in the `data/linux` directory for some devices that one can adapt to other equipment.

There are additional automation controls whose status can be displayed:

```
# MIDI Control Out: play on/off
0 [0 0x0 0 0] [0 0x0 0 0]
# MIDI Control Out: stop on/off
0 [0 0x0 0 0] [0 0x0 0 0]
# MIDI Control Out: pause on/off
0 [0 0x0 0 0] [0 0x0 0 0]
# MIDI Control Out: queue on/off
0 [0 0x0 0 0] [0 0x0 0 0]
# MIDI Control Out: oneshot on/off
0 [0 0x0 0 0] [0 0x0 0 0]
# MIDI Control Out: replace on/off
0 [0 0x0 0 0] [0 0x0 0 0]
# MIDI Control Out: snap1 store/restore
0 [0 0x0 0 0] [0 0x0 0 0]
# MIDI Control Out: snap2 store/restore
0 [0 0x0 0 0] [0 0x0 0 0]
# MIDI Control Out: learn on/off
0 [0 0x0 0 0] [0 0x0 0 0]
```

See the sample files for more detailed descriptions.

12.6 'mutes' File

This file starts with:

```
[mute-group-flags]
save-mutes-to = both
mute-group-rows = 4
mute-group-columns = 8
mute-group-selected = -1
groups-format = bin
```

These variables are described in the sample 'mutes' file. The mute-in group consists of 32 lines (32 to 63), one for each pattern box. It provides a way to control the mute groups. A group is a set of sequences that can arm their playing state together; every group contains all 32 sequences in the *active* screen-set.

This section is delimited by the [mute-group] construct. It controls 32 groups of mutes in the same way as defined for [midi-control]. A group is set of sequences that can toggle their playing state together. Every group contains all 32 sequences in the active screen set.

```
[mute-groups]
0 [ 0 0 0 0 0 0 0 0 ] [ 0 0 0 0 0 0 0 0 ] [ . . . ] [ 0 0 0 0 0 0 0 0 ]
1 [ 0 0 0 0 0 0 0 0 ] [ 0 0 0 0 0 0 0 0 ] [ . . . ] [ 0 0 0 0 0 0 0 0 ]
.
.
.
31 [ 0 0 0 0 0 0 0 0 ] [ 0 0 0 0 0 0 0 0 ] [ . . . ] [ 0 0 0 0 0 0 0 0 ]
```

In this group are the definitions of the state of the 32 (or more, once the support for larger sets is completely worked out) sequences in the playing screen set when a group is selected. Each set of brackets defines a group.

12.7 'drums' File

The 'drums' file is based on a similar file created using the `midicvt` application (also available on [GitHub](#)). This file is also referred to as the 'note-mapper' file.

```
[notemap-flags]
map-type = drums
gm-channel = 10
reverse = false
```

These settings are explained in the sample 'drums' files. In addition, the file includes a number of sections that define the number and name of the original "drum", and the *General MIDI* device to which it corresponds.

```
[Drum 36]
dev-name = "Bass Drum Gated Reverb"
gm-name = "Bass Drum 1"
dev-note = 36
gm-note = 36
```

This file is useful mainly when obtaining drum tracks recorded with devices in the early days of MIDI, where each vendor provided their own peculiar layout of percussion sounds.

12.8 'palette' File

This file is described in the chapter on palettes, section [16 "Palettes for Coloring" on page 118](#).

12.9 'playlist' File

This file is described in the chapter on playlists, section [13 "Seq66 Play-Lists" on page 109](#).

13 Seq66 Play-Lists

Seq66 supports play-lists. A play-list is a variation on the 'rc' file, conventionally ending with the extension `.playlist`. It contains a number of "playlist" sections, each with a human-readable title, selectable via a MIDI data number, or by moving to the next or previous playlist in the list using the **Up** and **Down** arrow keys. Each playlist section contains a list of songs, also selectable via a MIDI data number, or by moving to the next or previous song in the list using the **Left** and **Right** arrow keys.

Movement between the playlists and the songs is accomplished via MIDI control or the arrow keys. It describes the general usage of the [midi-control] section. Using MIDI control makes it possible to use the `seq66cli` headless version of *Seq66* in a live setting. In the normal user-interface, play-list movement can also be done manually via the four arrow keys on the computer keyboard.

The playlist file can be specified on the command-line, in the 'rc' file, or be loaded from the **File / Open Playlist** menu. If it is specified on the command line, that playlist setup will be written to the 'rc' file. It can be removed by specifying a blank (i.e. two double-quotes, "") play-list name. The file extension is `.playlist`.

The Qt user-interface supports editing of the play-list, though not yet perfected; bugs still exist. The user can use a text editor to edit the play-list file, if careful.

The play-list format is defined in the following section. Later sections describe the user-interface.

13.1 Seq66 Play-Lists / 'playlist' File Format

The play-list file, by convention, has a file-name of the form `sample.playlist`. The play-list file starts with a hardwired top banner that the user can edit with a text editor. It can also have an optional comments section, much like the 'rc' and 'usr' files. It is *not* overwritten when *Seq66* exits.

```
[comments]
Comments added to this section are preserved....
```

A blank line (without even a space) ends the comment section. Following the comments section is a [playlist-options] section.

```
[playlist-options]
1  # If set to 1, when a new song is selected, unmute all its patterns
0  # If set to 1, every MIDI song is opened to verify it.
```

The first option allows the load of the next song to enable the patterns in that song. The second option causes each MIDI file to be opened to verify that it is an error-free play-list. This process can be time-consuming for large playlists.

Following the options section are one or more [playlist] sections. Here is the layout of a sample playlist section.

```
[playlist]

# Playlist number, arbitrary but unique. 0 to 127 recommended
# for use with MIDI playlist control.
126

# Display name of this play list.
"Music for Serious Dogs"

# Storage directory for the song-files in this play list.
contrib/midi/

# Provides the MIDI song-control number, and also the
# base file-name (tune.midi) of each song in this playlist.
# The playlist directory is used, unless the file-name contains its
# own path.
70 allofarow.mid
71 CountryStrum.midi
72 contrib/wrk/longhair.wrk
```

A play-list file can have more than one [playlist] section. This allows for partitioning songs into various groups that can be easily selected (e.g. based on the mood of the musician or the audience).

After the [playlist] tag comes the play-list number. This number can be any non-negative value. However, in order to use MIDI control to select the playlist, this number should be limited to the range 0 to 127. If there is more than one [playlist] section, they are ordered by this number, regardless of where they sit in the play-list file.

Next comes a human-readable name for the playlist, which is meant to be displayed in the user-interface. If surrounded by quotes, the quotes are removed before usage.

Next is the song-storage directory. This directory is the default location in which to find the songs. It can be an absolute directory or a relative directory. However, be wary of using relative directories, since they depend on where *Seq66* is run. Also, if a song's file-name has its own directory component, that overrides the default song-storage directory.

Lastly, there is a list of MIDI song file-names, preceded by their numbers. As with the playlist numbers, it is recommended to keep them between 0 and 127, for usage with MIDI control. And the songs are ordered by this number, rather than by their position in the list.

13.2 Seq66 Play-Lists / 'rc' File

The most consistent way to specify a play-list is to add an entry like the following to the 'rc' file:

```
[playlist]
# Provides a configured play-list and a flag to activate it.
0      # playlist_active, 1 = active, 0 = do not use it
# Provides the name of a play-list. If there is none, use """.
# Or set the flag above to 0.
"/home/ahlstrom/.config/seq66/sample.playlist"
```

This setup allows a play-list file to be specified and activated. If the name of the play-list file does *not* contain a directory, then the play-list file is search for in the user's *Seq66* configuration directory.

If the play-list file-name is empty (i.e. set to ""), then there is no play-list active.

13.3 Seq66 Play-Lists / 'ctrl' File / [midi-control]

The MIDI control stanzas for play-list and song-selection don't quite follow the toggle/on/off convention of the [midi-control] section, though the layout is the same:

Pick-by-number	Next	Previous
24 "F2" [1 0 144 2 1 127]	[1 0 144 4 1 127]	[1 0 144 0 1 127] # Play List
25 "F3" [1 0 144 5 1 127]	[1 0 144 3 1 127]	[1 0 144 1 1 127] # Play Song

Both lines specify setting the next play-list or song according to a number, or via "next" and "previous" controls. The "next" and "previous" controls can be implemented by any MIDI event, including *Note On* or *Program Change*. However, the "value" section requires a MIDI event that provides a **d1** (second data byte) value, because this value is used as the MIDI control number to select a play-list or song item. So, the following setting,

```
24 "F2" [1 0 144 2 1 127] . . .
```

specifies that a *Note On* event with channel 0 (144 = 0x90) on note #2 with a velocity between the range 1 to 127 will select a play-list. However, this selection will be made only if the velocity ranges from 1 to 127, and there exists a selection with that velocity in the play-list file. This control requires a controller device that can be configured to provide the exact *Note On* event, including the exact velocity.

13.4 Seq66 Play-Lists / Command Line Invocation

The command-line options to specify (and activate) the play-list feature are:

```
-X playlist_file
--playlist playlist_file
```

The play-list file is either a base-name (e.g. `sample.playlist`) or a name that includes the full path to the play-list file (e.g. `data/sample.playlist`). If no path is specified, the directory

is the currently set *Seq66* configuration-file directory. For session support, one must stick with the configuration directory; do not provide an explicit directory-name.

Please note that any play-list file specified on the command line, or loaded in the play-list user-interface, will be written into the 'rc' file's [playlist] section when *Seq66* exits.

13.5 Seq66 Play-Lists / Verification


When *Seq66* loads a play-list file, an option allows every song in the play-list file to be verified by loading it. If any load fails, then the playlist will fail to load. This check can be slow when there are many large MIDI files specified in the play-list file.

13.6 Seq66 Play-Lists / User Interface

Playlists and songs can be selected or moved-to via keystrokes or user-interface actions, in addition to MIDI control.

The Up and Down arrows move forward or backward through the list of play-lists, and the Right and Left arrows move forward or backward through the list of songs for the currently-selected play-list.

The Qt 5 user-interface supports the display, selection, and editing of the play-lists and the song-list for each play-list. There are still some minor issues to work out. If encountered, close *Seq66* and edit the .playlist file manually. It is self-documenting.



Qt 5 Playlist Tab

There is a lot to talk about in this tab.

1. **Playlist File.** This field displays the path to the loaded play-list file. It is not editable. Remember that a play-list file can contain multiple play-lists.
2. **Playlist Selection.** These fields display the main MIDI-file directory, the MIDI control number, and the name of the selected play-list. The **Directory** is where the MIDI files reside by default. A file-name can include a different path, however. These fields are editable, with the intent to use them to add a new play-list or modify the current one.
3. **Song Selection.** These fields display the MIDI-file directory, the MIDI control number, and the file-name of the selected play-list. Note that the directory is normally the play-list directory, but a path present in the MIDI file-name overrides that directory. These fields are editable, with the intent to use them to add a new song or modify the "meta information" of the current one.
4. **List Names.** This table shows the MIDI-control number and the name of each play-list.
5. **List Buttons.** These buttons are described below. Please note that, in some cases, the exact functionality is still being worked out or perfected.
6. **Song Files in List.** This table shows the MIDI-control number and the name of each song.
7. **Song Files in List Buttons.** These buttons are described below. Please note that, in some cases, the exact functionality is still being worked out or perfected.

13.6.0.1 Seq66 Play-Lists / User Interfaces / Playlist Buttons

This section briefly describes the "List" buttons to the right of the play-list table.

- **Load List.**
- **Add List.**
- **Modify List.**
- **Delete List.**
- **Save Lists.**

1. Load List. This button brings up the "Open play-list file" dialog, using the *Seq66* configuration directory as the default directory. It is recommended to use only this directory, especially when running in a session manager. If loaded from somewhere else, save the file back to the configuration directory.

2. Add List. This button is enabled with the editing of the **Playlist Selection** fields. Once these three fields are correct, the list can be added. The new list can then be populated with songs.

3. Modify List. This button is enabled with the editing of the **Playlist Selection** fields. Once these three fields are correct, the list can be modified. **Bug:** Currently does not work.

4. Delete List. This button removes the currently-selected play-list from the play-list file. This action doesn't take effect until the play-list file is saved or *Seq66* exits and does its normal saving.

5. Save Lists. This button bring up a file dialog to save the current play-lists and songs into a play-list file.

This section briefly describes the "Song" buttons to the right of the song-list table.

- **Load Song.**
- **Add Song.**
- **Modify Song**
- **Delete Song.**
- **Lists Active.**

1. Load Song. This button bring up a dialog to open a MIDI or WRK file from the current song-directory or from an arbitrary directory. Currently, be careful with this option; adding a file from an arbitrary directory will generally prepend that directory to the MIDI file-name, making the song list difficult to read.

2. Add Song. This button is meant to add a song already loaded in the **Live** frame into the play-list. Currently not implemented; disabled.

3. Modify Song. This button is meant to modify song information. Currently not implemented; disabled.

4. Delete Song. This button deletes the currently-selected song from the song list.

5. Lists Active. If checked, the play-list is enabled, and the arrow keys, automation keys, and MIDI controls (if configured) can be used to move between play-lists and songs.

13.6.0.2 Seq66 Play-Lists / User Interfaces / Info Fields

The following read-only fields show some information about the file-system for the play-lists.

- **MIDI Base Directory.** Provides the top-most directory where all of the files in the play-list are stored. Currently read-only, in order not to interfere with session locations.
- **Current Song Path.** Shows the exact path the the currently-selected song. Currently read-only, in order not to interfere with session locations.

These items can be modified, however, by editing the play-list file directly.

14 Seq66 Set Master

The **Set Master** is a way to get a global view of all the screensets in a *Seq66* MIDI file, and to be able to do some simple operations (movement, naming, etc.) with the sets. It is still a work in progress.




Figure 24: Sets Tab

The operations that can be done consist of viewing the sets, making a screenset active, rearranging the sets, removing sets, and getting a survey of the contents of the sets.

1. Sets Grid. The set grid is (presumably) always 4 x 8. Like the mute-groups, there's not a lot of benefit supporting more sets. The reader may wish to email us arguing for a different point of view. This grid shows the sets that are present in the MIDI file, and allows one to choose which set is currently active (i.e. which is the "play screen"). Click on it and it is active. Also remember that keystrokes ([and]) by default)

2. Set List. The table at the right shows the set numbers, how many patterns/sequences are in each set, and the set name. Eventually the set name will be editable.

3. Set Number/Name Fields. Eventually, these fields will be editable.

4. Set Up/Down Buttons. These buttons allow the user to move the sets up and down.

5. Show All Set Tracks. Clicking this button lists all the sets and their tracks in the edit box at the left. This functionality is provisional.

6. Delete Selected Set. Clicking this button deletes the set selected in the table above it. Note that the 0th set cannot be deleted. In *Seq66*, there must always be a set 0.

15 Seq66 Mutes Master

The **Mutes** tab is a way to get a global view of all the mutegroups in a *Seq66* MIDI file or global configuration, and to be able to do some simple operations with the mute groups. To learn more about mute-groups, see section 1.5.3.7 "Mute Group Learn Button" on page 14, and section 19.1.7 "Concepts / Terms / group, mute-group" on page 131.




Figure 25: Mtes Tab

This diagram show the **Mutes** tab after some mute-groups have been created. Mute-groups can be created in the main window's patterns panel, but it is difficult to know what each group consists of. This tab make it easy to see the layout of the mute-groups, and also allows for some editing of the mute-groups.

1. Group Table. At the right is a table that holds all of the assigned mute-group key and some information about them:

- **Group.** This column holds the group numbers for each group, ranging from 0 to 31. Each row corresponds to a button in the **Mute-Groups** grid.
- **Active.** This column shows the number of activated patterns in the mute-group. A zero means the mute-group is inactive.
- **Key.** Indicates the keystroke that can be used to put that mute-group in place on the patterns in the current screenset.
- **Group Name.** Provides a mnemonic name for the mute group. A feature for the future.

Currently, none of the items in this table are editable. The user must modify `qseq66.mutes` with a text editor. Also note that this table is the only way to select a mute-group for editing.

2. Mute-Groups. This grid is always of size **4 x 8**. It represents the maximum of 32 mute-groups that can be supported by *Seq66*. To start, all group buttons are *disabled* and *unchecked* (inactive). Where a mute-group exists, the button is made *checked* (active), but still disabled.

Here, the user clicked on mute-group 7, which now becomes active in the user-interface. (But it is not made active in the patterns panel). The **7** button is also enabled, and can be clicked.

Clicking once deactivates the button, which potentially flags that mute-group for removal. Clicking it again reactivates it, which also enables all of the buttons in the **Group Patterns** grid.

3. Group Patterns. Once this grid is enabled, each button can be click to add a pattern to the mute-group, or remove a pattern from the mute-group.

4. Set Mutes. When a change in the mute-group status or the status of one of its patterns is made, this button becomes enabled. Once clicked, the current mute-group is modified internally, where it will later be saved when *Seq66* exits.

5. Mutes File. The mutes-file shows the base-name of a file into which one can write the current-mute group setup, as a way to back up the setup. TO DO: We need to disable auto-save of the mutes file at exit in this case, unless the name provided is identical.

6. Save File. This button save the mute-groups. If the user has provided a path in the **Mutes File** field, the path is stripped. We do not want to write configuration information outside of the session configuration directory.

7. Write Format. This section provides the following features, which still need some work:

- **Binary.** This flag indicates to save the mute-group information in binary format, which is the normal format. Each mute-group pattern's setting is indicated by a 0 or a 1. This is the default format for writing the mute-groups.
- **Hex.** In this format, each set of mute-group is written in 8-bit hexadecimal format (e.g. "0xff"). This format is useful if the user has opted to have large set sizes such as 64 and 96 patterns. Not well-supported yet.
- **To MIDI.** When a tune is closed, as when *Seq66* exits, this option indicates to write the mute-group information to the *Seq66*-style MIDI file.
- **To Mutes.** When a tune is closed, as when *Seq66* exits, this option indicates to write the mute-group information to the normal *Seq66* configuration file (e.g. `qseq66.mutes`).

8. Clear All Mutes. This button will clear every mute group. Use it carefully!

9. Trigger Mode. When activated, this option will enable the **Mute-Groups** buttons, deactivate them all, and turn them into standard push-buttons. When clicked the mute-group will be activated during playback.

10. Pattern Offset. If the user has selected a larger set size that is a multiple of 32, this item is enabled. It then allows the user to modify patterns with a sequence number greater than 31. A future feature.

11. Up/Down Buttons. A future feature to move mute-group around without changing the keystroke for that mute group.

16 Palettes for Coloring

Many user-interface elements in *Seq66* are drawn independently of the Qt theme in force, and they have their own coloring. Also, patterns can be colored, and the color is stored (as a color number) in the pattern when the tune is saved.

There are four palettes:

- **Pattern.** This palette contains 32 color entries, and each can be used to add color to a pattern in the *Live* grid or in the *Song* editor. The color of a pattern, if used, is saved with the pattern in the MIDI file.
- **Ui.** This palette contains 16 color entries. These color entries are used in drawing text, backgrounds, grid lines, background patterns, drum notes, and more. These colors each have a counterpart that is used with the `--inverse` option is applied to a run of *Seq66*.
- **Inverse Ui.** This palette contains 16 color entries. These colors are used when the `--inverse` option is applied to a run of *Seq66*.
- **Brushes.** This "palette" provides a way to specify the fill type for the drawing of notes, the scale (if shown) in the pattern editor, and the background sequence (if shown). It allows the user to select solid fill, hatching, and some other fill patterns.

All palettes have default values built into the application. However, the user can also include 'palette' files to change the colors used. For example, the normal colored palette can be changed to a gray-scale palette. The name of the palette file is specified in the 'rc' file by lines like the following:

```
[palette-file]
1      # palette_active
qseq66-alt-gray.palette
```

If this palette file is active, it is loaded, changing all of the palettes, and thus the coloring of *Seq64*.

16.1 Palettes Setup

The palette file is a standard *Seq66* configuration file with a name something like `qseq66.palette`, plus two sections:

```
[palette]
[ui-palette]
```

The first section is the "Pattern" palette, and the second section is the "Ui" palette, which includes the inverse palette as well.

16.1.1 Palettes Setup / Pattern

The following shows the pattern palette, with some entries elided for brevity:

```
[palette]
0      "Black" [ 0xFF000000 ]      "White" [ 0xFFFFFFFF ]
1      "Red" [ 0xFFFF0000 ]      "White" [ 0xFFFFFFFF ]
2      "Green" [ 0xFF008000 ]      "White" [ 0xFFFFFFFF ]
3      "Yellow" [ 0xFFFFFFF00 ]      "Black" [ 0xFF000000 ]
4      "Blue" [ 0xFF0000FF ]      "White" [ 0xFFFFFFFF ]
...
29      ...
30      ...
31      ...
project.
```

The names are color names, and these names are what show up in the popup color menus for the pattern buttons in the *Live* grid. The colors on the left are the background colors, and the colors on the right are the foreground colors, which are chosen for contrast with the background. The colors are in #AARRGGBB format, with the "#" replaced by "0x" because "#" starts a comment in *Seq66* configuration files. Note that all the alpha values are "FF" (opqque); we have not yet experimented with changing them. Lastly, only 32 entries are accepted.

16.1.2 Palettes Setup / Ui and Inverse Ui

The following shows the pattern palette, with some entries elided for brevity:

```
[ui-palette]
0      "Foreground" [ 0xFF000000 ]      "Foreground" [ 0xFFFFFFFF ]
1      "Background" [ 0xFFFFFFFF ]      "Background" [ 0xFF000000 ]
2      "Label" [ 0xFF000000 ]      "Label" [ 0xFFFFFFFF ]
3      "Selection" [ 0xFFFFA500 ]      "Selection" [ 0xFFFF00FF ]
4      "Drum" [ 0xFFFF0000 ]      "Drum" [ 0xFF000080 ]
...
13      ...
14      ...
15      ...
project.
```

Here, the names are feature names, not color names. The first color is the normal color, and the second color is the inverse color. Only 16 entries are accepted.

16.1.3 Palettes Setup / Brushes

The last palette is small, allowing the fill-pattern of a few pattern-editor items to be changed.

```
[brushes]
empty = nobrush
note = solid
scale = dense3
backseq = dense2
```

On the left of the equals sign is the item than can be filled, and on the right side is the *Qt* brush to be used. The defaults for most are solid fill.

The entry `empty` isn't used yet. The entry `note` affects the fill of normal/selected notes. The entry `note` affects the fill for the piano roll scale. The hatching used here makes it easier to recognize that the scale is just there for orientation. The entry `note` affects the fill of the background sequence. The hatching used here helps further distinguish the real notes from the background notes.

16.2 Palettes Summary

There are some obvious enhancements to this scheme, including increasing the number of palette items, synchronizing the palette with the current desktop them semi-automatically, and providing a user interface to drag-and-drop colors. Perhaps someday we'll update *Sqtool* for this purpose?

17 Seq66 Headless Version

Sq66 can be built as a command-line application. See the `INSTALL` file provided with the source code distribution. That is, *Sq66* can be run from the command-line, with no user interface. It can also be instantiated as a Linux daemon, for totally headless usage. Because there is not a lot of visibility into a headless process, the setup for `seq66cli` is a little complex, and the musician must get used to blind MIDI control.

17.1 Seq66 Headless Setup

The first step in setting up a headless `seq66cli` session is to make sure that the GUI version (`seq66`) works as expected. The GUI and headless configurations need to do the following:

1. Access the correct inputs, especially a keyboard or pad controller that can be used for controlling the sequencer via MIDI, as well as inputting notes.
2. The MIDI input must be configured with some `[midi-control]` values, so that the headless sequencer can do things like stop and start playback, select the next playlist or song, or change other sequencer controls. Also note that an alternative is to provide a `[midi-control-file]` specified in the "rc" file.
3. Access the desired outputs, in order to play sounds. This can sometimes be tricky, because *Sq66* can route all patterns to the same output, or can let the patterns decide the outputs for themselves.
4. Use the desired play-list. The headless sequencer can only select songs to play via a pre-configured play-list.

Sometimes odd problems, such as the output synthesizer not working, not appearing in the list of outputs, can prove a real puzzle. Here are the steps used in this test; adapt them to your setup. For simplicity, JACK is not running, and so ALSA is in force.

First, after booting, plug in the MIDI keyboard or MIDI control pad. Our example here will use the *Korg nanoKEY2* keyboard.

Second, start the desired (software) synthesizer. We will use the synth *Yoshimi*, with a stock setup from our "Yoshimi Cookbook" project. The order of starting the keyboard/pad and the

synthesiser will alter the port numbers of these items. Best to do things in the same order every time... be consistent.

Third, to validate the setup, run a command from the command-line such as:

```
seq66 -b 2 -v -X data/sample.playlist
```

The buss number ("2") may need to be different on your setup to get sound routed to the correct synthesizer. Also, the path to the playlist might need to be an absolute path; normally playlists are stored in the `HOME/.config/seq66` directory and accessed from there. Verify that the main window shows the playlist name, and that the arrow keys modify the play-list or song selection. If that works, verify that the MIDI keyboard or pad controller works to change the selection. Verify that the current song plays through the synthesizer that was started. If this setup works (MIDI controls have the proper effect and the tunes play through the synthesizer), proceed to the next step.

Fourth, edit the `seq66.rc` and `seq66cli.rc` files as described below so that the former's settings of `[midi-clock]` or `[midi-clock-file]` are entered into the latter "rc" configuration. For our testing, we use a separate MIDI-control file (`nanomap.rc`), which is set up in the main "rc" file to be read via a `[midi-clock-file]` setting. The `nanomap.rc` file sets up our *nanoKEY2* as shown in this figure:




Figure 26: Sample nanoKEY2 Control Setup

In this figure, the **OCT -** button on the nanoKEY2 is pressed until it is flashing (not seen in the figure). This means that the lowest note on the nanoKEY2 is MIDI note 0, the lowest note possible. With these settings, the playlists and songs can be loaded and then played and paused. The `seq66cli.rc` file is edited so that the rather large `[midi-control]` section is replaced by the following:

```
[midi-control-file]
nanomap.rc      # (/home/ahlstrom/.config/seq66/nanomap.rc)
```

The `nanomap.rc` file is included in the "data" directory of the source-code package.

Fifth, test the command-line *Seq66* by running the following command (your setup might vary) on the command line:

```
$ ./Seq66cli/seq66cli -b 2 -v data/sample.playlist -v
```

There is a play-list option to automatically unmute the sets when a new song is selected. If set, then the first song should be ready to play. If it plays, and the play-list seems to work (as indicated by the console output and the proper playback), then run `seq66cli` as a daemon:

```
$ ./Seq66cli/seq66cli -b 2 -X data/sample.playlist -v -o daemonize
```

The keyboard controls and sound output should still work.

18 Launchpad Mini

This section discusses the configuration and usage of the *Novation Launchpad Mini* (we'll call it the "Mini") for control of patterns and for showing the status of *Seq66*. We will describe one of the 'ctrl' files provided with *Seq66*, the setup of ports and connections under ALSA and under JACK, and some related topics. A picture of the Mini appears at the end of this section.

18.1 Launchpad Mini Basics

Let's start with a guide to Mini programming. Some of this information was adopted from the PDF file `launchpad-programmers-reference.pdf`. That document notes that a Mini message is 3 bytes, and is of type Note Off (80h), Note On (90h), or a controller change (B0h). However, on our Mini, we do not receive Note Offs (in ALSA)... we receive Note Ons with velocity 0.

The Mini has a top row of circular buttons numbered from 1 to 8. The next 8 rows start with 8 unlabeled square buttons on the left side with a circular button on the right, labelled with letters A through H.

The top row's circular buttons (labeled "1" through "8") emit 0xB0 cc 0x7f on press, and 0xB0 cc 0x00 on release, where:

- **0xB0** is a Control Change on channel 0.
- **cc** is a Control Change number, ranging from 0x68 (104 decimal) to 0x6f (111 decimal) which are in the range of *undefined* MIDI controllers.

The square buttons in the 8 x 8 matrix emit 0x90 nn 0x7f on press, and 0x90 nn 0x00 on release, where:

- **0x90** is a Note On message on channel 0.
- **nn** is the hex value of the note, as shown by the two-digit hex values shown below. The first "n" is the row number (from "0" to "7"). The second "n" is the column (from "0" to "7", and "8" for the circular buttons).

The right columns's circular buttons (labeled "A" through "H"), emit the same kind of message, with note numbers of the form n8.

There are two layouts available, **X-Y** and **Drum**. In *Seq66*, the drum layout is not used; see the file `contrib/notes/launchpad.txt`.

X-Y Key Layout (mapping mode 1):

1	2	3	4	5	6	7	8
B0h: (68h)	(69h)	(6ah)	(6bh)	(6ch)	(6dh)	(6eh)	(6fh)
90h: [00h]	[01h]	[02h]	[03h]	[04h]	[05h]	[06h]	[07h]

(08h) A
[10h] [11h] [12h] [13h] [14h] [15h] [16h] [17h] (18h) B

[20h]	[21h]	[22h]	[23h]	[24h]	[25h]	[26h]	[27h]	(28h)	C
[30h]	[31h]	[32h]	[33h]	[34h]	[35h]	[36h]	[37h]	(38h)	D
[40h]	[41h]	[42h]	[43h]	[44h]	[45h]	[46h]	[47h]	(48h)	E
[50h]	[51h]	[52h]	[53h]	[54h]	[55h]	[56h]	[57h]	(58h)	F
[60h]	[61h]	[62h]	[63h]	[64h]	[65h]	[66h]	[67h]	(68h)	G
[70h]	[71h]	[72h]	[73h]	[74h]	[75h]	[76h]	[77h]	(78h)	H

The colors of the grid-buttons LED can be set via the command `90h key vel`, where:

- **0x90** is a Note On message on channel 0.
- **key** is a hex value given in the active of the two layouts shown above.
- **vel** is a bit mask of the form `00GGCKRR` where the bits have these meanings:
 - GG for Green brightness.
 - C to clear the LED setting of the other buffer. There are two buffers; see below for an explanation.
 - K to copy the data to both buffers.
 - RR for Red brightness.

The Mini has two buffers 0 and 1 which contain two separate LED states. For example, in one buffer, all LEDs can be red, and in the other buffer, all LEDs can be green. By default, buffer 0 is used for displaying and for writing. By alternating the buffers, the display can blink.

The brightness values used for green and red range from 0 (off) to 3 (full brightness). *Seq66* uses these values to provide red, green, yellow, and amber lighting.

Hex	MSB	LSB	Color	Brightness	Decimal	Vel
00GG CKRR						
0Ch	0000	1100	Off	Off	12	
0Dh	0000	1101	Red	Low	13	
0Eh	0000	1110	Red	Medium	14	
0Fh	0000	1111	Red	Full	15	
1Ch	0001	1100	Green	Low	28	
1Dh	0001	1101	Amber	Low	29	
2Ch	0010	1100	Green	Medium	44	
2Eh	0010	1110	Amber	Medium	46	
3Ch	0011	1100	Green	Full	60	
3Eh	0011	1110	Yellow	Full	62	
3Fh	0011	1111	Amber	Full	63	

There are some other commands, not used, documented in `contrib/notes/launchpad.txt`. Also shown is a decimal version of the X-Y key layout.

We use the square grid for toggling and showing pattern muting, and also for toggling mute groups. The top row of buttons are used for *Seq66*. We start with the basic controls, mapped to the top row of circular buttons (tentative):

Panic*	Stop	Pause	Play	Song*	Keep*	Group*	???
68h	69h	6ah	6bh	6ch	6dh	6eh	6fh
104	105	106	107	108	109	110	111

* means not yet supported.

The Mini also supports power levels, but that feature is not used by *Seq66*.

18.2 System Survey, ALSA

Let's start with ALSA. The following devices were discovered by running the commands `aconnect -lio` and `aplaymidi -l` and combining the information with the information shown on the **MIDI Clock** and **MIDI Input** tabs.

In	Out	Port	Client name	Port name
		0:0	System	Timer
[0]		0:1	System	Announce
[1]	[0]	14:0	Midi Through	Midi Through Port-0
[2]	[1]	28:0	Launchpad Mini	Launchpad Mini MIDI 1 (card 3)
[3]	[2]	32:0	E-MU XMidi1X1 Tab	E-MU XMidi1X1 Tab MIDI 1 (card 4)
[4]	[3]	36:0	nanoKEY2	nanoKEY2 MIDI 1 (card 5)
[5]	[4]	40:0	USB Midi	USB Midi MIDI 1 (card 6)

Note the "Timer" device, which *Seq66* does not show, and the "Announce" device, which it does show (as disabled). The device/port we're interested in is the **Launchpad Mini MIDI 1**, port 2 for input from the Mini, and port 1 for output to the Mini.

18.3 Control Setup

A couple of *Launchpad* control files are provided in the `/usr/share/seq66-0.92/data/linux` directory. Copy the `qseq66-lp-mini.ctrl` file to `$HOME/.config/seq66`. Make sure to exit *Seq66* before the next steps.

Open the `qseq66.rc` file. Change

```
[midi-control-file]
"qseq66.ctrl"
```

to

```
[midi-control-file]
"qseq66-lp-mini.ctrl"
```

In `qseq66-lp-mini.ctrl`, first read through the file to get familiar with the format and purpose of this file.

18.3.1 Input Control Setup

We first want to use the Mini as a MIDI controller for the selection of loops, mute-groups, and various automation (user-interface) functions. In `qseq66-lp-mini.ctrl`, the only change to make for input-control is to change `0xff` to the proper *input* port. On our system, as noted above, that would be input port [2].

```
[midi-control-settings]
control-buss = 0xff      # change 0xff to 2
```

Remember that [midi-control-settings] refers to controls sent to *Seq66* to control that application. There are three sets of controls: loops, mute-groups, and automation.

18.3.1.1 [loop-control]

In the [loop-control] section of `qseq66-1p-mini.ctrl`, keystrokes are assigned, and only the "Toggle" (first) stanza of each MIDI control line is enabled, although there are definitions for the On and Off stanzas should one want to enable them. Here are the first four lines, truncated:

```
[loop-control]
0 "1"  [ 1 0 0x90 0 1 127 ] [ 0 0 0x90 0 1 127 ] ...
1 "q"  [ 1 0 0x90 16 1 127 ] [ 0 0 0x90 16 1 127 ] ...
2 "a"  [ 1 0 0x90 32 1 127 ] [ 0 0 0x90 32 1 127 ] ...
3 "z"  [ 1 0 0x90 48 1 127 ] [ 0 0 0x90 48 1 127 ] ...
```

The note values (0, 16, 32, 48) are in decimal. Why? Less to type. The whole section is 32 lines, so only the top 4 rows of the Mini are assigned to loop-control by this configuration file. The pattern numbers are shown inside each Mini slot:

1	2	3	4	5	6	7	8	
[0]	[4]	[8]	[12]	[16]	[20]	[24]	[28]	A
[1]	[5]	[9]	[13]	[17]	[21]	[25]	[29]	B
[2]	[6]	[10]	[14]	[18]	[22]	[26]	[30]	C
[3]	[7]	[11]	[15]	[19]	[23]	[27]	[31]	D

By pressing the appropriate button on the Mini, a pattern toggles between being armed and being muted.

18.3.1.2 [mute-group-control]

The mute-group controls are similar, except we didn't bother filling the On and Off stanzas at this time; they are all zeroes.

```
[mute-group-control]
0 "!"  [ 1 0 0x90 64 1 127 ] ...
1 "Q"  [ 1 0 0x90 80 1 127 ] ...
2 "A"  [ 1 0 0x90 96 1 127 ] ...
3 "Z"  [ 1 0 0x90 112 1 127 ] ...
```

The mapping is the similar to loop-control, but offset by four rows. By pressing the appropriate button on the Mini, a mute-group toggles between being on (selected patterns armed) and off (all patterns muted).

18.3.1.3 [automation-control]

A large number of actions available from the user-interface can also be controls by keystrokes or a MIDI device. Here is a brief sample. See the 'ctrl' file itself for more information.

```

0 """ [ 0 0 0x00 0 0 0 ] [ 1 0 0xb0 104 127 127 ] [ 1 0 0xb0 104 127 127 ] # BPM Up
1 ";" [ 0 0 0x00 0 0 0 ] [ 1 0 0xb0 105 127 127 ] [ 1 0 0xb0 105 127 127 ] # BPM Dn
2 "]" [ 0 0 0x00 0 0 0 ] [ 0 0 0xb0 0 0 0 ] [ 0 0 0xb0 0 0 0 ] # Set Up
3 "[" [ 0 0 0x00 0 0 0 ] [ 0 0 0xb0 0 0 0 ] [ 0 0 0xb0 0 0 0 ] # Set Dn

```

In `qseq66-lp-mini.ctrl`, all 64 square buttons are defined, which leaves the 16 circular buttons available for MIDI control. Only a few of those are defined so far.

18.3.2 Output Control Setup

Here, we want *Seq66* to send information to the Mini so that the lights on the Mini match the unmuted loops and some of the *Seq66* controls. Here are the changes to make to the output settings (while *Seq64* is *not* running). Change

```
[midi-control-out-settings]
output-buss = 0xff
midi-enabled = false
```

to

```
[midi-control-out-settings]
output-buss = 1
midi-enabled = true
```

18.3.2.1 [midi-control-out]

The `[midi-control-out]` section provides a way to see the status of each pattern/loop in the Mini's grid. Here are a few entries. As per the section above, 60 is green, 15 red, 62 is yellow, and 12 is off.

```

0 [1 0 0x90 0 60] [1 0 0x90 0 15] [1 0 0x90 0 62] [1 0 0x90 0 12]
1 [1 0 0x90 16 60] [1 0 0x90 16 15] [1 0 0x90 16 62] [1 0 0x90 16 12]
2 [1 0 0x90 32 60] [1 0 0x90 32 15] [1 0 0x90 32 62] [1 0 0x90 32 12]
3 [1 0 0x90 48 60] [1 0 0x90 48 15] [1 0 0x90 48 62] [1 0 0x90 48 12]

```

For the `qseq66-lp-mini.ctrl` file, only the upper 32 buttons and LEDS are used for this purpose, so there are 32 lines of data in this section.

The four stanzas (numbers in square brackets) are:

- **Armed**. This stanza is configured to show unmuted pattern slots as green.
- **Muted**. This stanza is configured to show muted pattern slots as red.
- **Armed**. This stanza is configured to show a queued pattern slots as yellow.
- **Armed**. This stanza is configured to show an empty pattern slots as off (dark).

18.3.2.2 [mute-control-out]

With the `qseq66-lp-mini.ctrl` file, the lower 32 buttons can be used to see which mute-group is selected (as well as to select a mute-group). The layout is pretty simple; here are the first four of the 32 lines:

```

1 [ 0 0x90 64 60 ] [ 0 0x90 64 15 ] [ 0 0x90 64 12 ]
2 [ 0 0x90 80 60 ] [ 0 0x90 80 15 ] [ 0 0x90 80 12 ]
3 [ 0 0x90 96 60 ] [ 0 0x90 96 15 ] [ 0 0x90 96 12 ]
4 [ 0 0x90 112 60 ] [ 0 0x90 112 15 ] [ 0 0x90 112 12 ]

```

The slots are numbered; all of the entries in the section are always enabled. The first stanza indicates that the button the selected mute-group will be green. The second stanza indicates that the unselected mute-group buttons will all be red, as long as they have mutes defined in them. The third stanza indicates that the inactive (empty) mute-groups will be dark.

18.3.2.3 [automation-control-out]

This section allows for the following status to be shown in the top row of circular buttons:

```

1 [ 0 0xb0 104 60 ] [ 0 0xb0 104 0 ] # play on/off
1 [ 0 0xb0 104 15 ] [ 0 0xb0 104 0 ] # stop on/off
1 [ 0 0xb0 104 62 ] [ 0 0xb0 104 0 ] # pause on/off
0 [ 0 0x0 0 0 ] [ 0 0x0 0 0 ] # queue on/off
0 [ 0 0x0 0 0 ] [ 0 0x0 0 0 ] # oneshot on/off
0 [ 0 0x0 0 0 ] [ 0 0x0 0 0 ] # replace on/off
0 [ 0 0x0 0 0 ] [ 0 0x0 0 0 ] # snap1 store/restore
0 [ 0 0x0 0 0 ] [ 0 0x0 0 0 ] # snap2 store/restore
0 [ 0 0x0 0 0 ] [ 0 0x0 0 0 ] # learn on/off

```

Note that the play, stop, and pause statuses are all shown on the same button, as green, red, or yellow.

Some of these might still be in progress as you read this.

18.4 Test Run, ALSA

Now that we're set up, start *Seq66*.




Figure 27: Launchpad Minu Running with Seq66

This picture shows that playback is paused (yellow), that mute-group 7 is active, and that all the patterns in that mute-group are green, except for one that got muted accidentally while taking the picture.

If the **File / New** option is selected, all the patterns are turned off, but the four mute-group buttons at the bottom left remain, as the mute-groups are not erased. (Bug or feature?)

What's next? First, add more controls and statuses to the configuration. Second, start working on a MIDI file to produce a light show!

18.5 System Survey, JACK

Now let's see what we have to do in **JACK**. First peruse section [10 "Seq66 JACK Support"](#) on page [81](#), to understand the basics about **JACK**, including the last section there that describes how to set up *ALSA-to-JACK* bridging.

Run the following command, verify the ports in **Edit / Preferences / MIDI Clock** and **MIDI Input**, and then exit.

```
$ qseq66 --jack-midi
```

In `qseq66.rc`, one will find this setting:

```
1      # with_jack_midi
```

The MIDI inputs are shown, decorated with the "a2j" designation:

```
[midi-input]
5    # number of input MIDI busses
0 1 "[0] 0:0 seq66:a2j Midi Through [14] (capture): Midi Through Port-0"
1 0 "[1] 0:1 a2j:Launchpad Mini [28] (capture): Launchpad Mini MIDI 1"
2 0 "[2] 0:2 a2j:E-MU XMidi1X1 Tab [32] (capture): E-MU XMidi1X1 ..."
3 0 "[3] 0:3 a2j:nanoKEY2 [36] (capture): nanoKEY2 MIDI 1"
4 0 "[4] 0:4 a2j:USB Midi [40] (capture): USB Midi MIDI 1"
```

This is very similar to the *ALSA* setup, except that there is no "announce" port in *JACK*. The Mini's input buss has shifted from port 2 to port 1. And, of course, the port names are a lot longer. Similarly, for the MIDI outputs:

```
[midi-clock]
5    # number of MIDI clocks (output busses)
0 0 "[0] 0:0 seq66:a2j Midi Through [14] (playback): Midi Through. . ."
1 0 "[1] 0:1 seq66:a2j Launchpad Mini [28] (playback): Launchpad. . ."
2 0 "[2] 0:2 seq66:a2j E-MU XMidi1X1 Tab [32] (playback): E-MU . . ."
3 0 "[3] 0:3 seq66:a2j nanoKEY2 [36] (playback): nanoKEY2 MIDI 1"
4 0 "[4] 0:4 seq66:a2j USB Midi [40] (playback): USB Midi MIDI 1"
```

We make sure that the correct *control-buss* and *output-buss* are set, and both have the setting *midi-enabled = true* in *qseq66-lp-mini.ctrl*. Then make sure that *qseq66.rc* has its *[midi-control-file]* set to:

```
"qseq66-lp-mini.ctrl"
```

Run *qseq66* again, and make sure that the Mini's input and output ports are enabled. (Unfortunately, if one has to enable them, the application will need to be restarted.) The results should be just like section 18.4 "Test Run, *ALSA*" on page 127.

19 Concepts

The *Seq66* program is a loop-player machine with a number of interfaces. This section is useful to present some concepts and definitions of terms as they are used in *Seq66*. Various terms have been used over the years to mean the same thing (e.g. "sequence", "pattern", "loop", "track", and "slot"), so it is good to clarify the terminology.

19.1 Concepts / Terms

This section doesn't provide comprehensive coverage of terms. It covers terms that might be puzzling.

19.1.1 Concepts / Terms / loop, pattern, track, sequence

Loop is a synonym for *pattern*, *track*, or *sequence*; the terms are used interchangeably. Each loop is represented by a box (pattern slot) in the Pattern (main) Window.

A loop is a unit of melody or rhythm extending for a small number of measures (in most cases). Each loop is represented by a box in the patterns panel. Each loop is editable. All patterns can be laid out in a particular arrangement to generate a more complex song.

A *slot* is a box in a pattern grid that holds a loop.

Note that other sequencer applications use the term "sequence" to apply to the complete song, and not just to one track or pattern in the entire song.

19.1.2 Concepts / Terms / armed, muted

An armed sequence is a MIDI pattern that will be heard. "Armed" is the opposite of "muted", and the same as "unmuted". Performing an *arm* operation in *Seq66* means clicking on an "unarmed" sequence in the patterns panel (the main window of *Seq66*). An unarmed sequence will not be heard, and it has a normal background. When the sequence is *armed*, it will be heard, and it has a more noticeable background. A sequence can be armed or unarmed in many ways:

- Clicking on a sequence/pattern box.
- Pressing the hot-key for that sequence/pattern box.
- Opening up the Song Editor and starting playback; the sequences arm/unarm depending on the layout of the sequences and triggers in the piano roll of the Song Editor.
- Using a MIDI control, as configured in a 'ctrl' file, to toggle the armed status of a pattern.

19.1.3 Concepts / Terms / bank, screenset

The *screen set* is a set of patterns that fit within the **4 x 8** grid of loops/patterns in the patterns panel. *Seq66* supports multiple screens sets, up to 32 of them, and a name can be given to each for clarity. Some other sizes, such as **8 x 8** and **12 x 8**, are partly supported. For the most part, the column number is best left at 8. The term "bank" is *Kepler34*'s name for "screen set".

By default, only one set is active and playing at a time. This set is informally termed the "play screen".

19.1.4 Concepts / Terms / buss, bus, port

A *buss* (also spelled "bus" these days; <https://en.wikipedia.org/wiki/Busbar>) is an entity onto which MIDI events can be placed, in order to be heard or to affect the playback, or into which MIDI events can be received, for recording. A *buss* is just another name for port. *Seq66* can also perform some mapping of I/O ports for a more flexible studio setup.

19.1.5 Concepts / Terms / performance, song, trigger

In the jargon of *Seq66*, a *performance* or *song* is an organized collection of patterns that play a tune automatically. This layout of patterns is created using the song editor, sometimes called the

"performance editor". This window controls the song playback in "Song Mode" (as opposed to "Live Mode").

The playback of each track is controlled by a set of triggers created for that track. A *trigger* is indicates when a sequence/pattern/loop should be played, and how much of the sequence (including repeats) should be played. A song performance consists of a number of sequences, each triggered as the musician laid them out.

19.1.6 Concepts / Terms / export

A *export* in *Seq66* is a way of writing a song-performance to a more standard MIDI file, so that it can be played exactly by other sequencers. An export collects all of the unmuted tracks that have performance information (triggers) associated with them, and creates one larger trigger for each track, repeating the events as indicated by the original performance.

19.1.7 Concepts / Terms / group, mute-group

A *group* in *Seq66* is a set of patterns, that can arm (unmute) their playing state together. Every group contains all sequences in the active screen set. This concept is similar to mute/unmute groups in hardware sequencers. Also known as a "mute-group". Mute-groups can be stored in the MIDI file or in a 'mutes' file. Each mute-group is associated with a keystroke or a MIDI control. When applied, the mute-group enables one or more patterns in the current screenset.

19.1.8 Concepts / Terms / PPQN, pulses ticks, clocks, divisions

The concept of "pulses per quarter note", or PPQN, is very important for MIDI timing. To make it a bit more confusing, sometimes these pulses are referred to as "ticks", "clocks", and "divisions". To make it even more confusing, there are separate timing concepts to understand, such as "tempo", "beats per measure", "beats per minute", and "MIDI clocks". A full description of all these terms, and how they are calculated, is beyond the scope of this document. Check out the source code.

19.1.9 Concepts / Terms / queue, keep queue, snapshot, one-shot

To "queue" a pattern means to ready it for playback on the next repeat of a pattern. A pattern can be armed immediately, or it can be queued to play back the next time the pattern restarts. Pattern toggle occurs at the end of the pattern, rather than being set immediately.

A set of queued patterns can be temporarily stored, so that a different set of playbacks can occur, before the original set of playbacks is restored.

The "keep queue" functionality allows the queue to be held without holding down a button the whole time. Once this key is pressed, then the hot-keys for any pattern can be pressed, over and over, to queue each pattern.

A *Seq66 snapshot* is a briefly preserved state of the patterns. One can press a snapshot key, change the state of the patterns for live playback, and then release the snapshot key to revert to the state when it was first pressed. (One might call it a "revert" key.)

19.2 Concepts / Sound Subsystems

19.2.1 Concepts / Sound Subsystems / ALSA

ALSA is a audio/MIDI system for *Linux*, with components built into the *Linux* kernel. It is the main subsystem used by *Seq66*. It supports virtual port connections via the `aconnect` program. The name of the library used to build *ALSA* projects is `libasound`. See reference [1].

19.2.2 Concepts / Sound Subsystems / PortMIDI

PortMIDI is a cross-platform API (applications programming interface) for MIDI refactored for *Seq66*. It is used in the "portmidi" C++ modules, and provides support for *Seq66* in *Microsoft Windows* (and potentially *Mac OSX*). See reference [12] for the *PortMIDI* home page; our version cuts out code that requires Java.

19.2.3 Concepts / Sound Subsystems / JACK

JACK is a cross-platform API and infrastructure (with an emphasis on *Linux*) to make it easier to connect and reroute MIDI and audio event between various applications and hardware ports. It should be preferred over *ALSA*, and is selected automatically if running. It supports virtual port connections via the `qjackctl` program or the *Non Session Manager*. See reference [5].

20 MIDI Format and Other MIDI Notes

20.1 Standard MIDI Format 0

Seq66 can read and import SMF 0 MIDI files, and performs channel splitting automatically. When an SMF 0 format is detected, *Seq66* first puts all of the events into the same sequence/pattern. As the file is processed, a list of the channels present in the track is maintained.

Tempo and Time Signature events are read, if present. When saving a *Seq66* MIDI file, the Tempo and Time Signature events are saved as MIDI events. This allows other sequencers to read a *Seq66* MIDI file. This addition of Tempo can fix imported tracks that don't have a measure value.

Once the end-of-track is encountered in the SMF 0 file, a new empty slot is created for each channel found. The events in the main pattern are scanned and added to the appropriate pattern. If the event is a channel event, then the event is inserted into the pattern that was created for that channel. If the event is a non-channel event, then each pattern gets a copy of that event.

After processing, the MIDI buss information, track name, and other pieces of information are attached to each sequence. The imported SMF 0 track is preserved, in pattern slot #16. One can delete this track before saving the file, or keep it muted.

The sequence number of each new track is the internal channel number (always the actual MIDI channel number minus one). The time-signature of each track is set to defaults, unless a time-signature event is encountered in the imported file.

Seq66 supports reading some other information a MIDI SMF 0 track might have, such as the Tempo and the Time Signature. It saves this information in the first track of the MIDI file.

20.2 Proprietary Track Format

The authors of *Sq24* took trouble to ensure that the format of the MIDI files it writes are compatible with other MIDI applications. *Sq24* also stores its own information (triggers, MIDI control information, etc) in the file, but marked so that other sequencers can read the file and ignore its *Sq24*-specific information. *Sq66* continues that MIDI-compliant behavior, and improved it.

Each sequence/pattern/loop can contain proprietary information, such as the palette color assigned to that track. The last chunk of sequencer-specific information, that covers the whole tune, is the "proprietary track".

All of the SeqSpecs are shown in the next table. The `c_triggers` tag is obsolete, but still present.

Table 7: All SeqSpec Items

<code>c_midibus</code>	0x24240001 00 00 00 00
<code>c_midich</code>	0x24240002 00 00 00 00
<code>c_midi_clocks</code>	0x24240003 00 00 00 00
<code>c_triggers</code>	0x24240004 00 00 00 00
<code>c_notes</code>	0x24240005 00 00 00 00
<code>c_timesig</code>	0x24240006 00 00 00 00
<code>c_bpmtag</code>	0x24240007 00 00 00 00
<code>c_triggers_new</code>	0x24240008 00 00 00 00
<code>c_mutegroups</code>	0x24240009 00 00 00 00
<code>c_gap_A</code>	0x2424000A 00 00 00 00
<code>c_gap_B</code>	0x2424000B 00 00 00 00
<code>c_gap_C</code>	0x2424000C 00 00 00 00
<code>c_gap_D</code>	0x2424000D 00 00 00 00
<code>c_gap_E</code>	0x2424000E 00 00 00 00
<code>c_gap_F</code>	0x2424000F 00 00 00 00
<code>c_midictrl</code>	0x24240010 00
<code>c_musickey</code>	0x24240011 00
<code>c_musicscale</code>	0x24240012 00
<code>c_backsequence</code>	0x24240013 00 00 00 00
<code>c_transpose</code>	0x24240014 00 00 00 00
<code>c_perf_bp_mess</code>	0x24240015 00 00 00 00
<code>c_perf_bw</code>	0x24240016 00 00 00 00
<code>c_tempo_map</code>	0x24240017 00 00 00 00
<code>c_reserver_1</code>	0x24240018 00 00 00 00
<code>c_reserver_2</code>	0x24240019 00 00 00 00
<code>c_tempo_track</code>	0x2424001A 00 00 00 00
<code>c_seq_color</code>	0x2424001B 00 00 00 00
<code>c_seq_edit_mode</code>	0x2424001C 00 00 00 00
<code>c_seq_loopcount</code>	0x2424001D 00 00 00 00

The `c_musickey`, `c_musicscale`, `c_backsequence`, and a few other control tags are new with *Sq66*. They are saved as additional information in each sequence in which they have been specified in the sequence editor, in the proprietary track. These tags are preceded by the standard MIDI "FF 7F length" meta-event sequence, not shown in the table. Next, MIDI wants to see this triad of

bytes:

```
status = FF, type= 7F (proprietary), length = whatever
```

to precede proprietary data.

Sq66 writes this information properly, starting with the 0xFF 7F 242 400 nn marker. The ability to read *Sq24* MIDI files been preserved in *Sq66*.

At this point, we have the **c_midictrl** information now. Next, we read a long value, 24 24 00 10 00 00 00 00, to get the seqs. It is 0.

Read the next long value, 24 24 00 03 00 00 00 00. This is **c_midiclocks**. We get a value of 0 for "TrackLength" (now a local variable called "busscount"): If the buss-count was greater than 0, then for each value, we would read a byte value represent the bus a clock was on, and setting the clock value of the master MIDI buss. Another check for more data is made.

0x24 24 00 05 00 20 00 00 is **c_notes**. The value screen_sets is read (two bytes) and here is 0x20 = 32. For each screen-set:

```
len = read\_\_short()
```

If non-zero, each of the **len** bytes is appended as a string. Here, len is 0 for all 32 screensets, so the screen-set notepad is set to an empty string. Another check for more data is made.

24 24 00 07 00 00 00 78 is **c_bpmtag**. The long value is read and sets the perform object's bpm value. Here, it is 120 bpm. Another check for more data is made.

24 24 00 09 00 00 04 00 is **c_mutegroups**. The long value obtained here is 1024. If this value is not equal to the constant **c_gmute_tracks** (1024), a warning is emitted to the console, but processing continues anyway, 32 x 32 long values are read to select the given group-mute, and then set each of its 32 group-mute-states.

Note that control information is now read only from the 'ctrl' file, and mutes information can also be read from a separate file.

For the new format, the components of the final proprietary track size are as shown here:

1. **Delta time**. 1 byte, always 0x00.
2. **Sequence number**. 5 bytes. OPTIONAL.
3. **Track name**. 3 + 10 or 3 + 15
4. **Series of proprietary specs**:

- **Prop header**:
 - If legacy format, 4 bytes.
 - Otherwise, 2 bytes + varinum_size(length) + 4 bytes.
 - Length of the prop data.

5. **Track End**. 3 bytes.

Note that we still need to dig into all the new values that have accumulated over the last five years!

20.3 MIDI Information

This section provides some useful, basic information about MIDI data.

20.3.1 MIDI Variable-Length Value

A *variable-length value* (VLV) is a quantity that uses additional bytes and continuation bits to encode large numbers. See https://en.wikipedia.org/wiki/Variable-length_quantity. The length of a VLV depends on the value it represents. Here is a list of the numbers that can be represented by a VLV:

```
1 byte: 0x00 to 0x7F
2 bytes: 0x80 to 0x3FFF
3 bytes: 0x4000 to 0x001FFFFF
4 bytes: 0x200000 to 0x0FFFFFFF
```

20.3.2 MIDI Track Chunk

```
Track chunk == MTrk + length + track_event [+ track_event ...]
```

- *MTrk* is 4 bytes representing the literal string "MTrk". This marks the beginning of a track.
- *length* is 4 bytes the number of bytes in the track chunk following this number. That is, the marker and length are not counted in the length value.
- *track_event* denotes a sequenced track event; usually there are many track events in a track. However, some of the events may simply be informational, and not modify the audio output.

A track event consists of a delta-time since the last event, and one of three types of events.

```
track_event = v_time + midi_event | meta_event | syssex_event
```

- *v_time* is the VLV for elapsed time (delta time) from the previous event to this event.
- *midi_event* is any MIDI channel message such as note-on or note-off.
- *meta_event* is an SMF meta event.
- *syssex_event* is an SMF system exclusive event.

20.3.3 MIDI Meta Events

Meta events are non-MIDI data of various sorts consisting of a fixed prefix, type indicator, a length field, and actual event data.

```
meta_event = 0xFF + meta_type + v_length + event_data_bytes
```

- *meta_type* is 1 byte, expressing one of the meta event types shown in the table that follows this list.
- *v_length* is length of meta event data, a variable length value.
- *event_data_bytes* is the actual event data.

Windows MP is the built-in *Windows Media Player*.

20.4 More MIDI Information

This section goes into even more detail about the MIDI format, especially as it applies to the processing done by *Seq66*. The following sub-sections describe how *Seq66* parses a MIDI file.

Table 8: MIDI Meta Event Types

Type	Event
0x00	Sequence number
0x01	Text event
0x02	Copyright notice
0x03	Sequence or track name
0x04	Instrument name
0x05	Lyric text
0x06	Marker text
0x07	Cue point
0x20	MIDI channel prefix assignment
0x2F	End of track
0x51	Tempo setting
0x54	SMPTE offset
0x58	Time Signature
0x59	Key Signature
0x7F	Sequencer-Specific event

Table 9: Application Support for MIDI Files

Application	Legacy	New	Original File
ardour	TBD	TBD	TBD
composite	TBD	TBD	TBD
gsequencer	No	No	No
lmms	Yes	Yes	Yes
midily	Yes	Yes	TBD
midicvt	No	Yes	Yes
midish	TBD	TBD	TBD
muse	TBD	TBD	TBD
playmidi	TBD	TBD	TBD
pmidi	TBD	TBD	TBD
qtractor	Yes	Yes	Yes
rosegarden	Yes	Yes	Yes
superlooper	TBD	TBD	TBD
timidity	Yes	Yes	Yes
Windows MP	TBD	TBD	TBD

20.4.1 MIDI File Header, MThd

The first thing in a MIDI file is The data of the header:

```

Header ID:      "MThd"           4 bytes
MThd length:    6               4 bytes
Format:         0, 1, 2          2 bytes
No. of track:   1 or more       2 bytes
PPQN:           192             2 bytes

```

The header ID and it's length are always the same values. The formats that Seq66 supports are

0 or 1. SMF 0 has only one track, while SMF 1 can support an arbitrary number of tracks. The last value in the header is the PPQN value, which specifies the "pulses per quarter note", which is the basic time-resolution of events in the MIDI file. Common values are 96 or 192, but higher values are also common. Seq66 and its precursor, Seq24, default to 192.

20.4.2 MIDI Track, MTrk

The next part of the MIDI file consists of the tracks specified in the file. In SMF 1 format, each track is assumed to cover a different MIDI channel, but always the same MIDI buss. The MIDI buss is not a data item in standard MIDI files, but it is a special data item in the sequencer-specific section of Seq66 MIDI files.) Each track is tagged by a standard chunk marker, "MTrk". Other markers are possible, and are to be ignored, if nothing else. Here are the values read at the beginning of a track:

Track ID:	"MTrk"	4 bytes
Track length:	varies	4 bytes

The track length is the number of bytes that need to be read in order to get all of the data in the track.

Delta time. The amount time that passes from one event to the next is the *delta time*. For some events, the time doesn't matter, and is set to 0. This value is a *variable length value*, also known as a "VLV" or a "varinum". It provides a way of encoding arbitrarily large values, a byte at a time.

Delta time:	varies	1 or more bytes
-------------	--------	-----------------

The running-time accumulator is incremented by the delta-time. The current time is adjusted as per the PPQN ratio, if needed, and passed along.

20.4.3 Channel Events

Status. The byte after the delta time is examined by masking it against 0x80 to check the high bit. If not set, it is a "running status", it is replaced with the "last status", which is 0 at first.

Status byte:	varies	1 byte
--------------	--------	--------

If the high bit is set, it is a status byte. What does the status mean? To find out, the channel part of the status is masked out using the 0xF0 mask. If it is a 2-data-byte event (note on, note off, aftertouch, control-change, or pitch-wheel), then the two data bytes are read:

Data byte 0:	varies	1 byte
Data byte 1:	varies	1 byte

If the status is a Note On event, with velocity = data[1] = 0, then it is converted to a Note Off event, a fix for the output quirks of some MIDI devices. If it is a 1-data-byte event (Program Change or Channel Pressure), then only data byte 0 is read. The one or two data bytes are added

to the event, the event is added to the current sequence, and the MIDI channel of the sequence is set.

20.4.4 Meta Events Revisited

If the event status masks off to 0xF0 (0xF0 to 0xFF), then it is a Meta event. If the Meta event byte is 0xFF, it is called a "Sequencer-specific", or "SeqSpec" event. For this kind of event, then a type byte and the length of the event are read.

Meta type:	varies	1 byte
Meta length:	varies	1 or more bytes

If the type of the SeqSpec (0xFF) meta event is 0x7F, parsing checks to see if it is one of the Seq24 "proprietary" events. These events are tagged with various values that mask off to 0x24240000. The parser reads the tag:

Prop tag:	0x242400nn	4 bytes
------------------	-------------------	----------------

These tags provide a way to save and recover Seq24/Seq66 properties from the MIDI file: MIDI buss, MIDI channel, time signature, sequence triggers, and (new), the key, scale, and background sequence to use with the track/sequence. Any leftover data for the tagged event is let go. Unknown tags are skipped.

If the type of the SeqSpec (0xFF) meta event is 0x2F, then it is the End-of-Track marker. The current time marks the length (in MIDI pulses) of the sequence. Parsing is done for that track.

If the type of the SeqSpec (0xFF) meta event is 0x03, then it is the sequence name. The "length" number of bytes are read, and loaded as the sequence name.

If the type of the SeqSpec (0xFF) meta event is 0x00, then it is the sequence number, which is read:

Seq number:	varies	2 bytes
--------------------	---------------	----------------

Note that the sequence number might be modified latter to account for the current *Seq24* screenset in force for a file import operation.

Anything other SeqSpec type is simply skipped by reading the "length" number of bytes.

The remaining sections simply describe MIDI meta events in more detail, for reference.

20.5 Meta Events

Here, we summarize the MIDI meta events.

1. FF 00 02 **ssss**: Sequence Number.
2. FF 01 **len text**: Text Event.
3. FF 02 **len text**: Copyright Notice.
4. FF 03 **len text**: Sequence/Track Name.
5. FF 04 **len text**: Instrument Name.
6. FF 05 **len text**: Lyric.

7. FF 06 len text: Marker.
8. FF 07 len text: Cue Point.
9. FF 08 through 0F len text: Other kinds of text events.
10. FF 2F 00: End of Track.
11. FF 51 03 ttttt: Set Tempo, us/qn.
12. FF 54 05 hr mn se fr ff: SMPTE Offset.
13. FF 58 04 nn dd cc bb: Time Signature.
14. FF 59 02 sf mi: Key Signature.
15. FF 7F len data: Sequencer-Specific.
16. FF F0 len data F7: System-Exclusive

The next sections describe the events that *Sequencer* tries to handle. These are:

- Sequence Number (0x00)
- Track Name (0x03)
- End-of-Track (0x2F)
- Set Tempo (0x51) (Seq66 only)
- Time Signature (0x58) (Seq66 only)
- Sequencer-Specific (0x7F) (Handled differently in Seq66)
- System Exclusive (0xF0) Sort of handled, functionality incomplete.

20.5.1 Sequence Number (0x00)

FF 00 02 ss ss

This optional event must occur at the beginning of a track, before any non-zero delta-times, and before any transmittable MIDI events. It specifies the number of a sequence.

20.5.2 Track/Sequence Name (0x03)

FF 03 len text

If in a format 0 track, or the first track in a format 1 file, the name of the sequence. Otherwise, the name of the track.

20.5.3 End of Track (0x2F)

FF 2F 00

This event is not optional. It is included so that an exact ending point may be specified for the track, so that it has an exact length, which is necessary for tracks which are looped or concatenated.

20.5.4 Set Tempo Event (0x51)

The MIDI Set Tempo meta event sets the tempo of a MIDI sequence in terms of the microseconds per quarter note. This is a meta message, so this event is never sent over MIDI ports to a MIDI device. After the delta time, this event consists of six bytes of data:

```
FF 51 03 tt tt tt
```

Example:

```
FF 51 03 07 A1 20
```

1. 0xFF is the status byte that indicates this is a Meta event.
2. 0x51 the meta event type that signifies this is a Set Tempo event.
3. 0x03 is the length of the event, always 3 bytes.
4. The remaining three bytes carry the number of microseconds per quarter note. For example, the three bytes above form the hexadecimal value 0x07A120 (500000 decimal), which means that there are 500,000 microseconds per quarter note.

Since there are 60,000,000 microseconds per minute, the event above translates to: set the tempo to $60,000,000 / 500,000 = 120$ quarter notes per minute (120 beats per minute).

This event normally appears in the first track. If not, the default tempo is 120 beats per minute. This event is important if the MIDI time division is specified in "pulses per quarter note", which does not itself define the length of the quarter note. The length of the quarter note is then determined by the Set Tempo meta event.

Representing tempos as time per beat instead of beat per time allows absolutely exact DWORD-term synchronization with a time-based sync protocol such as SMPTE time code or MIDI time code. This amount of accuracy in the tempo resolution allows a four-minute piece at 120 beats per minute to be accurate within 500 usec at the end of the piece.

20.5.5 Time Signature Event (0x58)

After the delta time, this event consists of seven bytes of data:

```
FF 58 04 nn dd cc bb
```

The time signature is expressed as four numbers. **nn** and **dd** represent the numerator and denominator of the time signature as it would be notated. The denominator is a negative power of two: 2 represents a quarter-note, 3 represents an eighth-note, etc. The **cc** parameter expresses the number of MIDI clocks in a metronome click. The **bb** parameter expresses the number of notated 32nd-notes in a MIDI quarter- note (24 MIDI Clocks).

Example:

```
FF 58 04 04 02 18 08
```

1. 0xFF is the status byte that indicates this is a Meta event.
2. 0x58 the meta event type that signifies this is a Time Signature event.
3. 0x04 is the length of the event, always 4 bytes.
4. 0x04 is the numerator of the time signature, and ranges from 0x00 to 0xFF.
5. 0x02 is the log base 2 of the denominator, and is the power to which 2 must be raised to get the denominator. Here, the denominator is 2 to 0x02, or 4, so the time signature is 4/4.
6. 0x18 is the metronome pulse in terms of the number of MIDI clock ticks per click. Assuming 24 MIDI clocks per quarter note, the value here (0x18 = 24) indicates that the metronome will

tick every 24/24 quarter note. If the value of the sixth byte were $0x30 = 48$, the metronome clicks every two quarter notes, i.e. every half-note.

7. $0x08$ defines the number of 32nd notes per beat. This byte is usually 8 as there is usually one quarter note per beat, and one quarter note contains eight 32nd notes.

If a time signature event is not present in a MIDI sequence, a 4/4 signature is assumed.

In *Seq66*, the `c_timesig` SeqSpec event is given priority. The conventional time signature is used only if the `c_timesig` SeqSpec is not present in the file.

20.5.6 SysEx Event (0xF0)

If the meta event status value is $0xF0$, it is called a "System-exclusive", or "SysEx" event.

Seq66 has some code in place to store these messages, but the data is currently not actually stored or used. Although there is some infrastructure to support storing the SysEx event within a sequence, the SysEx information is simply skipped. *Seq66* warns if the terminating $0xF7$ SysEx terminator is not found at the expected length. Also, some malformed SysEx events have been encountered, and those are detected and skipped as well.

20.5.7 Sequencer Specific (0x7F)

This data, also known as SeqSpec data, provides a way to encode information that a specific sequencer application needs, while marking it so that other sequences can safely ignore the information.

```
FF 7F len data
```

In *Seq24* and *Seq66*, the data portion starts with four bytes that indicate the kind of data for a particular SeqSpec event:

<code>c_midibus</code>	<code>^</code>	<code>0x24240001</code>	Track buss number
<code>c_midich</code>	<code>^</code>	<code>0x24240002</code>	Track channel number
<code>c_midiclocks</code>	<code>*</code>	<code>0x24240003</code>	Track clocking (not fully implemented!)
<code>c_triggers</code>	<code>^</code>	<code>0x24240004</code>	See <code>c_triggers_new</code> ; no offset here
<code>c_notes</code>	<code>*</code>	<code>0x24240005</code>	Song data, notes (names of sets)
<code>c_timesig</code>	<code>^</code>	<code>0x24240006</code>	Track time signature (not global)
<code>c_bpmtag</code>	<code>*</code>	<code>0x24240007</code>	Song beats/minute (global)
<code>c_triggers_new</code>	<code>^</code>	<code>0x24240008</code>	Track trigger data
<code>c_mutegroups</code>	<code>*</code>	<code>0x24240009</code>	Song mute group data (global)
<code>c_gap_A</code>	<code>s</code>	<code>0x2424000A</code>	Gap A
<code>c_gap_B</code>	<code>s</code>	<code>0x2424000B</code>	Gap B
<code>c_gap_C</code>	<code>s</code>	<code>0x2424000C</code>	Gap C
<code>c_gap_D</code>	<code>s</code>	<code>0x2424000D</code>	Gap D
<code>c_gap_E</code>	<code>s</code>	<code>0x2424000E</code>	Gap E
<code>c_gap_F</code>	<code>s</code>	<code>0x2424000F</code>	Gap F
<code>c_midictrl</code>	<code>*</code>	<code>0x24240010</code>	Song MIDI control (always empty)
<code>c_musickey</code>	<code>+</code>	<code>0x24240011</code>	Track key (<i>Seq66</i> only) (global too)
<code>c_musicscale</code>	<code>+</code>	<code>0x24240012</code>	Track scale (<i>Seq66</i> only) (global too)
<code>c_backsequence</code>	<code>+</code>	<code>0x24240013</code>	Track background sequence (global too)
<code>c_transpose</code>	<code>t</code>	<code>0x24240014</code>	Track transpose value
<code>c_perf_bp_mes</code>	<code>t</code>	<code>0x24240015</code>	Perfedit beats/measure
<code>c_perf_bw</code>	<code>t</code>	<code>0x24240016</code>	Perfedit beat-width
<code>c_tempo_map</code>	<code>t</code>	<code>0x24240017</code>	Reserve seq32 tempo map
<code>c_reserved_1</code>	<code>t</code>	<code>0x24240018</code>	Reserved for expansion

```
c_reserved_2      t 0x24240019 Reserved for expansion
c_tempo_track    t 0x2424001A Alternate tempo track no. (unimplemented)
c_seq_color      t 0x2424001B Track color, from Kepler34
c_seq_edit_mode  t 0x2424001C Unimplemented feature from Kepler34
c_seq_loopcount  t 0x2424001D Future: Track N-play pattern
```

Here are the meanings of the markers:

```
* = global only
^ = track only
+ = both
s = reserved for seq32
t = TBD
```

In *Seq24*, these events are placed at the end of the song, but are not marked as SeqSpec data. Most MIDI applications handle this situation fine, but some (e.g. *midicvt*) do not. *Seq66* makes sure to wrap each data item in the 0xFF 0x7F wrapper.

Also, the last three items above (key, scale, and background sequence) can also be stored (by *Seq66*) with a particular sequence/track, as well as at the end of the song. Not sure if this bit of extra flexibility is useful, but it is there.

20.5.8 Non-Specific End of Sequence

Any other statuses are deemed unsupportable in *Seq66*, and abort parsing with an error.

If the `-bus` option is in force, it overrides the bus number (if any) stored with the sequence. This option is useful for testing a setup. Note that it also applies to new sequences.

At the end, *Seq66* adds the sequence to the encoded tune.

21 Kudos

This section gives some credit where credit is due. We have contributors to acknowledge, and have not caught up with all the people who have helped this project:

- *Tim Deagan (tdeagan)*: Fixes to the mute-group support.
- *Orel*: An important fix to add and relink notes after a paste action in the pattern editor.
- *arnaud-jacquemin*: A bug report and fix for a regression in mute-groups support. Also suggestions for enhancing mute-group support.
- *Stan Preston (stazed)*: Ideas for many improvements based on his *seq32* project. A lot of ideas. And a lot of code!
- *Animtim*: A number of bug reports and a new logo for *Sequencer64*.
- *jean-emmanuel*: Scrollable main-window support, other features and reports.
- *Olivier Humbert (trebmuh)*: French translation for the desktop files.
- *Oli Kester*: The creator of *Kepler34*, from which we got many clues on porting the user-interface to Qt 5 and Windows.

Also some bug-reporters and testers:

- *F0rth*: A request for scripting support, a possible future feature.
- *gimmeapill*: Testing, bug-reports, and, um, "marketing".
- *georgkrause*: A number of helpful bug reports.
- *goguetchapuisb*: Found that *Sequencer64* native JACK did not properly handle the copious Active Sensing messages emitted by Yamaha keyboards.
- *milkmiruku*: Mainwids issues and many ideas, suggestions, feature requests, and bug report.
- *muranya*: Feature request for numbered piano keys and bug-reports.
- *simonvanderveldt*: Issues with window sizing and more.
- *ssj71*: A request for an LV2 plugin version, a possible future feature.
- *triss*: A request for OSC support, a possible future feature. We added some OSC support in order to play well with the *Non Session Manager (NSM)*.
- *layk*: Some bug reports, and, we are pretty sure, some nice videos that demonstrate *Seq66* on YouTube. See [7].
- *matt-bel*: Reported a regression from *Seq24*, which could use a MIDI control event to mute / unmute multiple patterns at once, a cool feature!
- *zigmhount*: A pending request for a control that would automatically set up a pattern for recording and playback with one "click".
- *grammoboy* and *J. Liles*: Bug reports and other help with *NSM* support.
- *Houston4444*: Similarly, help with *RaySession*, a work-alike of *NSM*, written in *Python*.
- *unfa*: Bug reports for coloring, and for inspiring the "*.*palette*" file feature, as well as making coloring more comprehensive.

... and there are many more to add to this list....

There are a number of authors of *Seq24*. ideas from other *Seq24* fans, and some deep history. All of these people, and more, have contributed to *Seq66*, whether they know it or not. The original author is Rob C. Buse. Without his work, we would never have started this years-long project. *Seq66*:

Seq24 is a real-time MIDI sequencer. It was created to provide a very simple interface for editing and playing MIDI 'loops'. After searching for a software based sequencer that would provide the functionality needed for a live performance, there was little found in the software realm. I set out to create a very minimal sequencer that excludes the bloated features of the large software sequencers, and includes a small subset of features that I have found usable in performing.

Written by Rob C. Buse. I wrote this program to fill a hole. I figure it would be a waste if I was the only one using it. So, I released it under the GPL.

Taking advantage of Rob's generosity, we've created a reboot, a refactoring, an improvement (we hope) of *Seq24*. It preserves (we hope) the lean nature of *Seq24*, while adding a few useful features. Without *Seq24* and its authors, *Sequencer64* and then *Seq66* would never have come into being.

22 Summary

Contact: If you have ideas about *Seq66* or a bug report, please email us (at <mailto:ahlstromcj@gmail.com>). If it's a bug report, please add [BUG] to the Subject, or use the GitHub bug-reporting interface.

23 References

The *Seq66* reference list.

References

- [1] ALSA team. *Advanced Linux Sound Architecture (ALSA) project homepage*. <http://www.alsa-project.org/>. ALSA tools through version 1.0.29. 2015.
- [2] Coolsoft. *Coolsoft MIDIMapper (Windows)*. <https://coolsoft.altervista.org/en/midimapper>. 2018.
- [3] Coolsoft. *Coolsoft VirtualMIDISynth (Windows)*. <https://coolsoft.altervista.org/en/virtualmidisynth>. 2018.
- [4] Jay Capela Music. "Combine": A Seq24 Demonstration. <https://www.youtube.com/watch?v=fUiXbVT0bJQ>. 2010.
- [5] JACK team. *JACK Audio Connection Kit*. <http://jackaudio.org/>. 2015.
- [6] Oli Kester. *Kepler34: Seq24 for the 2010s*. <https://github.com/oli-kester/kepler34>. 2010-2016.
- [7] Lassi Ylikojola. *Many demo videos of Sequencer64* <https://www.youtube.com/watch?v=YStYVjFv1TM>, <https://www.youtube.com/watch?v=GB1EP8Ffqss>, <https://www.youtube.com/watch?v=4gG8SvJxJkA&t=28s>, <https://www.youtube.com/watch?v=n4Z4WPK6FpA>. 2010-2017.
- [8] Chris Ahlstrom. *Extension of midicomp/midi2text to convert between MIDI and ASCII text format*. <https://github.com/ahlstromcj/midicvt>. 2015-2016.
- [9] linuxaudio.org. *seq24: toggle sequences with a MIDI controller*. <http://wiki.linuxaudio.org/wiki/seq24togglemiditutorial>. 2013.
- [10] midi.org. *Summary of MIDI Messages*. <https://www.midi.org/specifications/item/table-1-summary-of-midi-message#2>. Year unknown.
- [11] Roy Vegard. *Configurator software for the Korg nanoSERIES of MIDI controllers*. <https://github.com/royvegard/Nano-Basket>. 2015.
- [12] PortMedia team. *Platform Independent Library for MIDI I/O*. <http://portmedia.sourceforge.net/>. 2010.
- [13] Gary P. Scavone. *The RtMIDI Tutorial*. <https://www.music.mcgill.ca/~gary/rtmidi/>. 2016.
- [14] Seq24 Team. *The home site for the Seq24 looping sequencer*. <http://www.filter24.org/seq24/download.html>. 2010.
- [15] Seq24 Team. *The home site for the Seq66 looping sequencer*. <https://edge.launchpad.net/seq24>. 2016.

- [16] Excds. *A simple mapping for toggling the LEDs on the Novation launchpad together with seq24.* <https://github.com/Excds/seq24-launchpad-mapper>. 2013.
- [17] Stan Preston (stazed). *The home site for the Seq32 looping sequencer.* <https://github.com/Stazed/seq32>. 2016.
- [18] Chris Ahlstrom. *A reboot of the Seq24 project as "Seq66".* <https://github.com/ahlstromcj/seq66/>. 2015-2017.
- [19] Timidity++ Team. *Download site for Timidity++ source code.* <http://sourceforge.net/projects/timidity/>. 2015.
- [20] VMPK Team. *Virtual MIDI Piano Keyboard.* <http://vmpk.sourceforge.net/>. 2015.
- [21] The Wootangent man. *Seq66 Tutorial Videos, Part 1 and Part 2.* <http://wootangent.net/2010/10/linux-music-tutorial-seq24-part-1/>. <http://wootangent.net/2010/10/linux-music-tutorial-seq24-part-2/>. 2010.

Index

-auto-ports, 94
-bus option, 34
-A, 90
-C, 90
-F, 90
-H, 89
-J, 90
-K, 90
-L, 89
-M, 90
-R, 89
-U, 90
-X, 90
-a, 89
-b, 89
-c, 90
-f, 90
-h, 89
-j, 90
-k, 90
-m, 89
-o, 90
-p, 90
-q, 89
-r, 89
-s, 90
-t, 90
-u, 90
-v, 89
--alsa, 90
--auto-ports, 89
--bus [buss], 89
--config basename, 90
--help, 89
--hide-ports, 89
--home [directory], 89
--inverse, 90
--jack-master, 90
--jack-master-cond, 90
--jack-midi, 90
--jack-session-uuid [uuid], 90
--jack-start-mode [x], 90
--jack-transport, 90
--lash, 89
--manual-ports, 89
--option opvalue, 90
--playlist [filename], 90
--ppqn [ppqn], 89
--priority, 90
--rc filename, 90
--reveal-ports, 89
--show-keys, 90
--show-midi, 90
--user-save, 90
--usr filename, 90
--version, 89
[allow-click-edit], 95
[allow-snap-split], 95
[auto-option-save], 95
[jack-transport], 93
[last-used-dir], 96
[loop-control], 104
[manual-ports], 94
[midi-clock-mod-ticks], 93
[midi-clock], 92
[midi-control-file], 91
[midi-input], 94
[midi-meta-events], 93
[playlist], 96
[recent-files], 96
[reveal-ports], 95
[user-instrument-definitions], 100
[user-instrument-n], 100
[user-interface-settings], 101
[user-midi-bus-definitions], 99
[user-midi-bus-n], 99
[user-midi-settings], 102
[user-options], 102

Add List, 114
Add Song, 114
Apply Song Transpose, 20
armed, 130
Armed/Mute Toggle, 52
auto-connect, 82
auto-note, 47
auto-shift, 74, 75

Background Sequence, 45
bank, 130
Beat, 46

Beat Width, 42
beat width, 42
Beats Per Bar, 42
beats per bar, 42
BPM, 38
bpm
 step increment, 105
bugs
 event delete key, 64
 event insert key, 64
bus, 130
buss, 130
 mapping, 23
 override, 23
Buss Name, 23

Channel Number, 62
channel split, 132
Chord Generation, 42, 45, 50
chord generation, 42, 50
Chord Types, 42
Clear, 65
Clear All Mutes, 117
Clear Mute Groups, 20
Clear This Track's Song Data, 33
client ID, 23
Client Number, 23
client number, 23
Clock Start Modulo, 23
Color, 34
Connect, 27
Copy, 33
Copy/Paste, 48
Cut, 33

D0, 64
D1, 64
daemonize, 91
Data Bytes, 62
data pane, 50
data panel, 50
Delete, 64
Delete List, 114
Delete Selected Set, 116
Delete Song, 114
Disable, 75
Disconnect, 27
down arrow, 47

draw mode, 46
Drum Note Mode, 49
Dump, 65

edit
 clear mute groups, 20
 load mute groups, 20
 mute all tracks, 20
 preferences, 20
 song editor, 20
 song transpose, 20
 toggle all, 20
 unmute all tracks, 20
Edit Pattern In Tab, 31
Edit Pattern In Window, 31
Edit..., 32
editing shortcut, 31
Editor Key Height, 25
empty pattern, 31
empty slot double-click, 31, 33
Enable, 75
Enable/Disable Transpose, 34
Event, 64
event
 compression, 48
 select, 47
 stretch, 48
event -, 33
Event Category, 63
Event Category Selector, 50
event data editor
 mouse wheel, 50
event edit, 74
Event Edit..., 33
event editor
 channel number, 62
 clear events, 65
 data byte 1, 64
 data byte 2, 64
 data bytes, 62
 delete event, 64
 dump events, 65
 event category, 63
 event name, 62, 64
 event timestamp, 64
 index number, 62
 insert event, 65
 modify event, 65

save events, 65
 time stamp, 62
 Event Name, 62
 Event Selection, 47, 51
 event strip, 49
 events
 insert, 49
 Existing Event Menu, 51
 expand, 53
 export, 131
 exportable, 73
 External live frame for set 0, 30
 fast forward, 76
 follow jack, 76
 Follow Progress, 43, 56
 global-sequence, 44
 grave, 75
 Grid Snap, 43, 56
 group, 131
 learn, 75
 off, 75
 on, 75
 Group Patterns, 117
 Group Table, 116
 group-learn, 75
 igrave, 75
 Index Number, 22, 62
 index number, 22
 Input Buses, 24
 input buses, 24
 input by channel, 24
 Input Option, 24
 Input Options, 24
 input options, 24
 Input Ports Mapped, 24
 Insert, 65
 JACK
 live mode, 27
 master conditional, 26
 native midi, 27
 song mode, 27
 transport, 26
 transport master, 26
 jack
 auto-connect, 82
 reveal-ports, 95
 JACK Start mode, 27
 jack sync
 connect, 27
 disconnect, 27
 start mode, 27
 transport/midi, 26
 JACK toggle, 76
 keep queue, 75, 131
 Keep-Queue Status, 38
 key height, 25
 Key of Sequence, 44
 keyboard
 disable, 75
 enable, 75
 group off, 75
 group on, 75
 igrave, 75
 learn, 75
 mute-group slots, 75
 sequence toggle keys, 75
 keys
 -, 31, 33
 =, 31, 33
 [, 28, 35
], 28, 35
 0, 48, 53
 alt, 35
 apostrophe, 38, 75
 avoid ctrl/alt, 35
 backspace, 48, 60
 copy, 60
 ctrl-a, 43, 47
 ctrl-c, 48, 60
 ctrl-end, 45
 ctrl-home, 45
 Ctrl-L, 106
 ctrl-v, 48, 60
 ctrl-x, 48, 60
 ctrl-z, 43
 decrement set, 35
 del, 48
 delete, 59, 60
 down-arrow, 60
 esc (stop), 37, 56
 event edit, 31, 33
 F8, 34

focus, 74
 gotchas, 74
 Home, 14, 29
 hot, 34
 increment set, 35
 keep queue, 35, 75
 l, 57, 106
 one-shot, 75
 one-shot queue, 35
 p, 40, 47, 49
 page-down, 45, 53, 60
 page-up, 45, 53, 60
 paste, 60
 pattern edit, 31, 33
 pattern toggles, 34
 period (pause), 56
 qt, 74
 queue, 35, 75
 r, 57
 replace, 35
 right ctrl, 35
 screenset down, 28, 35
 screenset play, 29
 screenset up, 28, 35
 semicolon, 38
 shift, 74
 shift page-down, 53
 shift page-up, 53
 shift-v, 49
 shift-z, 48
 shortcut, 34
 slot-shift, 74
 snapshot, 35, 74
 space (play), 37, 56
 up-arrow, 60
 v, 49
 x, 40, 47, 49
 Z, 53
 z, 48, 53

L anchor, 57
 L button, 106
 L marker, 56, 57
 L/R Collapse, 57
 L/R Expand, 57
 L/R Expand and Copy, 57
 L/R Loop, 56
 lash

option, 27
 LASH Options, 27
 Learn, 75
 left arrow, 48
 LFO, 51
 Lists Active, 114
 live
 external, 30
 live mode, 27, 28, 32
 Load List, 114
 Load Song, 114
 log, 91
 loop, 130
 loop mode, 56
 Loop Record Type, 53
 main window, 28
 mapping, 23, 24
 marker
 mode, 57
 movement, 57
 Measure, 46
 measures ruler, 57
 left-click, 57
 right-click, 57
 menu mode, 76
 merge, 53
 Meta Events, 23
 Meta events, 19
 midi
 VLV, 135
 MIDI Bus, 34
 midi clock
 buss name, 23
 client number, 23
 clock start modulo, 23
 index number, 22
 meta events, 23
 off, 23
 on (mod), 23
 on (pos), 23
 port disabled, 23
 port mapping, 23
 port name, 23
 port number, 23
 MIDI Out Channel, 42
 MIDI Out Device (Buss), 42
 MIDI Record Quantized, 53

MIDI Record Toggle, 53
 MIDI Thru Toggle, 52
 mode
 draw, 46
 live, 28
 paint, 46
 song, 28
 Modify, 65
 modify event-data, 50
 Modify List, 114
 modify pitch, 43
 Modify Song, 114
 mouse
 ctrl-left-click, 47
 ctrl-left-click-drag, 48
 left-click, 40, 47
 left-click-drag, 40, 47, 50
 right-click-drag, 50
 Musical Scale, 44
 musical scales, 44
 mute all, 20
 Mute All Tracks, 20, 33
 mute groups, 20
 mute master
 clear all mutes, 117
 groups, 117
 mutes file, 117
 pattern offset, 118
 patterns, 117
 save file, 117
 set mutes, 117
 table, 116
 trigger mode, 117
 up/down buttons, 118
 write format, 117
 mute-group, 131
 mute-group control, 105
 Mute-group slots, 75
 Mute-Groups, 117
 Mutes File, 117
 Name, 38
 New, 30
 new
 click-edit, 95
 snap-split, 95
 time/tempo saved, 132
 no-daemonize, 91
 non-playback mode, 27
 Note Length, 43
 note step, 45
 Notes, 46
 notes
 inserting, 47
 Off, 23
 On (Mod), 23
 On (Pos), 23
 one-shot, 75
 one-shot queue, 35
 Output Ports Mapped, 23
 paint mode, 46, 59
 palette, 25, 26
 palette, 90
 Palette File Base Name, 25
 pan
 seqroll notes, 53
 seqroll time, 53
 Panic, 37
 Paste, 31
 pattern, 130
 beat, 32, 57
 BPM, 38
 bus-channel, 32
 buss-channel, 57
 channel, 57
 clear song data, 33
 color, 34
 color menu, 30
 contents, 31
 copy, 33
 cut, 33
 edit, 32
 edit in tab, 31
 edit in window, 31
 end marker, 46
 event edit, 33
 keep-queue, 38
 left click, 32, 37
 left click-drag, 37
 length, 31
 middle click, 37
 midi bus, 34
 mute, 37
 mute all tracks, 33

mute toggle, 37
 name, 31, 57
 new, 30
 panic, 37
 paste, 31
 Pause, 37
 Play, 37
 right click, 30, 32, 37
 set name, 38
 set number, 38
 shift-left-click, 36, 58
 slot, 30
 song, 31, 33
 song record, 37
 song record snap, 37
 split, 59
 stop, 37
 tap tempo, 38
 title, 57
 toggle all tracks, 34
 toggle live tracks, 34
 toggle song editor, 38
 transpose, 34
 unmute, 37
 unmute all tracks, 34
 pattern edit, 33, 74
 pattern editor
 background sequence, 45
 beat width, 42
 beats/bar, 42
 chord generation, 42, 45, 50
 chord types, 42
 copy, 48
 copy/paste, 48
 cut, 48
 data to midi buss, 52
 delete, 48
 deselect notes, 48
 drum mode, 49
 event compression, 48
 event selection, 51
 event selector, 50
 event stretch, 48
 existing events, 51
 grid snap, 43
 key, 44
 left click, 47
 length, 42
 LFO, 51
 midi data pass-through, 52
 midi out channel, 42
 midi out device, 42
 move notes in time, 48
 name, 42
 note length, 43
 number, 42
 paste, 48
 progress bar, 42
 quantize, 43
 quantized record, 53
 record midi data, 53
 recording type, 53
 redo, 43
 scale, 44
 select multiple notes, 47
 select note, 47
 time scroll, 46
 tools, 43
 transpose notes, 47
 transpose toggle, 49
 undo, 43
 vol, 53
 zoom, 43
 pattern event edit, 33
 pattern extension, 60
 Pattern Length, 42
 Pattern Offset, 118
 pattern subsection, 58
 patterns column
 ctrl-left-click, 58
 left-click, 58
 right-click, 58
 patterns panel
 inverse muting, 36
 solo, 36
 pause, 37, 74
 performance, 54, 130
 performance mode, 27
 piano roll
 beat, 46
 measure, 46
 notes, 46
 virtual piano keyboard, 46
 Play, 56
 Play and Pause, 37
 play screen, 115, 130

playback mode, 27
 playing set, 75
 playlist
 number, 110
 playlist, 90
 song-storage directory, 110
 tag, 110
 title, 110
 playlist editor
 add list, 114
 add song, 114
 delete list, 114
 delete song, 114
 lists active, 114
 load list, 114
 load song, 114
 modify song, 114
 save lists, 114
 pointer position, 76
 port
 mapping, 23
 override, 23
 Port Disabled, 23
 port mapping, 23
 port name, 23
 Port Number, 23
 port number, 23
 ports
 manual, 83, 94
 virtual, 83, 94
 ppqn, 62
 \$ shortcut, 62
 Preferences, 20
 proprietary track, 133
 pulses, 131
 quantize, 43
 Quantize Selection, 43
 queue, 75
 cancel, 35
 clear, 36
 end, 36
 keep, 35, 75, 131
 one-shot, 35
 replace, 36
 solo, 36
 temporary, 35
 R anchor, 57
 R marker, 56, 57
 rc
 auto-option-save, 90
 jack-transport, 90
 manual-ports, 89
 mute groups, 20
 playlist, 90
 reveal-ports, 89
 rc file, 34, 35
 recording type
 expand, 53
 merge, 53
 replace, 53
 Redo, 43, 56
 Reload Mute Groups, 20
 replace, 53
 rewind, 76
 right arrow, 48
 Save, 65
 save background sequence, 45
 Save Clock/Input Maps, 23
 Save Current Palette, 26
 Save File, 117
 Save Lists, 114
 save musical key, 44
 save musical scale, 45
 saved control tags, 133
 scaling, 91
 Scaling of User Interface, 25
 screen set, 130
 screen-set, 28
 scroll
 ctrl scroll, 53
 horizontal pan, 53
 horizontal zoom, 53
 normal scroll, 53
 notes pan, 53
 shift scroll, 53
 timeline pan, 53
 timeline zoom, 53
 vertical pan, 53
 selection
 all, 47
 deselect, 48
 selection action, 47
 Seq66 Client ID, 23
 seq66.usr, 98

SeqSpec, 19
 sequence, 130
 sequence extension, 60
 Sequence toggle keys, 75
 sessions
 lash, 72
 non-starter, 67
 nsm, 65
 OSC, 65
 signals, 72
 ui, 70
 Set, 38
 Set List, 116
 set master
 delete selected set, 116
 grid, 115
 list, 116
 number/name, 116
 show all set tracks, 116
 up/down buttons, 116
 Set Mutes, 117
 Set Number/Name Fields, 116
 Set Up/Down Buttons, 116
 Sets Grid, 115
 shift left click, 32, 58
 shift-left-click solo, 36, 58
 Show All Set Tracks, 116
 slot, 130
 empty slot right-click, 30
 slot-shift, 74
 smf 0, 132
 snapshot, 74, 131
 solo
 true, 36
 Song, 31, 33
 song, 130
 Song Editor, 20
 song editor, 20
 collapse, 57
 deletion, 59
 draw, 59
 dual, 54
 expand, 57
 expand and copy, 57
 follow, 56
 grid snap, 56
 handle, 58
 insert, 59
 inverse muting, 58
 left-click, 59
 left-click-right-hold, 59
 middle click, 58
 middle-click, 59
 multiple insert, 59
 mute indicator, 58
 muting, 58
 paint, 56
 pattern subsection, 59
 play, 56
 play loop, 56
 redo, 56
 right left click, 59
 right-click-hold, 59
 right-left-hold-drag, 59
 section deselection, 58
 section expansion, 59
 section length, 58
 selection, 59
 selection movement, 58
 solo, 58
 split pattern, 58
 stop, 56
 transpose, 56
 undo, 56
 zoom, 56, 59
 song mode, 27, 28, 54, 75
 Song Record, 37
 Song Record Snap, 37
 song transpose, 20
 step, 45
 sticky options, 82
 Stop, 37, 56
 tap bpm, 76
 Tap Tempo, 38
 tempo events, 132
 tempo-track-number, 23, 93
 tighten, 43
 Time, 64
 Time Scroll, 46
 time signature events, 132
 Time Stamp, 62
 todo
 high precision events, 49
 manual alsalgui option, 23
 toggle all, 20

Toggle All Tracks, 20, 34
toggle JACK, 76
Toggle Live Tracks, 34
toggle mutes, 76
Toggle Section Painting, 56
Toggle Song Editor, 38
Tools, 43
Track Name, 42
Track Number, 42
Transport/MIDI, 26
Transpose, 49, 56
trigger, 131
Trigger Mode, 117

Undo, 43, 56
unmute all, 20
Unmute All Tracks, 20, 34
up arrow, 47
Up/Down Buttons, 118
usr
 -user-save, 96
 -u, 96
 bpm-page-increment, 102
 bpm-precision, 102
 bpm-step-increment, 102
 grid-brackets, 101
 grid-style, 101
 mainwnd-cols, 101
 mainwnd-rows, 101
 max-sets, 101
 midi-beat-width, 102
 midi-beats-per-measure, 102
 midi-beats-per-minute, 102
 midi-bpm-maximum, 102
 midi-bpm-minimum, 102
 midi-buss-override, 102
 midi-ppqn, 102
 option-daemonize, 102
 option-logfile, 103
 step increment, 105
 user-instrument-definitions, 100
 user-instrument-n, 100
 user-interface-settings, 101
 user-midi-bus-definitions, 90, 99
 user-midi-bus-n, 99
 user-midi-settings, 15, 89
 user-session, 89
 velocity-override, 102
 usr config, 24
 variable-length value, 135
 variset, 38, 91, 101
 slash key, 35
 virtual keyboard
 right-click, 46
 Virtual Piano Keyboard, 46
 Vol, 53

warning
 down arrow, 48
 note loss, 48
 up arrow, 48
 wrap-around notes, 48
warnings
 usr config, 24
window
 close, 54
window scaling, 25
Write Format, 117

Zoom, 43
zoom, 59
 seqroll time, 53
zoom keys, 48
Zoom Out and Zoom In, 56