Logic Instructions

Course Code: 0052 Course Title: : Computer Organization and

Architecture



Dept. of Computer Science Faculty of Science and Technology

Lecturer No:	7(a)	Week No:	Semester:	Fall 23
	" "			

Overview: LOGIC



- Instructions to change the bit pattern in a byte or word
- The ability to manipulate bits manually which is unlikely in high level languages (Except C)
- Logic Instructions: AND, OR, XOR and NOT
- Logic Instructions can be used to **clear, set, and examine** bits, a register or variable. i.e. these will be used for
 - Converting a lowercase letter to upper case
 - > Determining If a register contains an even or odd number.

Overview: SHIFT




- ➢ Bits can be shifted left or right in a register or memory location.
- When a bit is shifted out, it goes into CF.
- Because a left shift doubles a number and a right shift halves it, these instructions give us a way to multiply and divide powers of 2.
- Shifting is much faster than Multiplication and Division.

LOGIC Instructions



- The ability to **manipulate individual bits** is one the main advantages of assembly language.
- Individual bits can be changed in computer by using logic operations.
- The binary values of 0 = False and 1= True
- When a logic operation is applied to 8- or 16-bit operands, the result is obtained by applying the logic operation at each bit position.


Truth Table for AND, OR, XOR and NOT



a	b	a AND b	a OR b	a XOR b
0	0	0	0	0
0	1	0	1	1
1	0	0	1	· 1
1	1	1	1 .	0


a	NOTa
0	1
1	0

Solve the Following



- 1. AND Operation: 10101010 AND 11110000
- 2. OR Operation: 10101010 OR 11110000
- 3. XOR Operation: 10101010 XOR 11110000
- 4. NOT Operation: NOT 10101010

Solution



1 10101010

AND 11110000

=10100000

3 10101010

XOR 11110000

= 01011010

2 10101010

OR 11110000

=11111010

4 **NOT** 10101010

=01010101

AND, OR, and XOR instructions



- ➤ The **AND**, **OR**, **and XOR** instructions perform the named logic operations. The formats are:
 - AND destination, source
 - OR destination, source
 - XOR destination, source
- The result of the operation is stored in the destination, which must be a register or memory location.
- The source may be a constant, register, or memory location.
- However, memory-to-memory operations are not allowed.

Effect on Flags



- > SF, ZF, PF reflect the result
- > AF is undefined
- > CF, OF= 0
- > One use of AND, OR, and XOR is to selectively modify the bits in the destination.
- To do this, we construct a **source bit pattern** known as **mask**.
- The mask bits are chosen so that the corresponding destination bits are modified in the desired manner when the instruction is executed.

MASK



- To choose the mask bits, we make use of the following properties of AND, OR, and XOR:
- b AND 1 = b
- \rightarrow b OR 0 = b
- \rightarrow b XOR 0 = b
- b AND 0 = 0
- ▶ b OR 1 = 1
- b XOR 1 = ~b (complement of b)

- The **AND** instruction can be used to **CLEAR** specific destination bits while preserving the others.
 - A 0 mask bit clears the corresponding destination bit.
 - a 1 mask bit preserves the corresponding destination bit.
- The **OR** instruction can be used to **SET** specific destination bits while preserving the others.
 - A 1 mask bit sets the corresponding destination bit.
 - A **0 mask** bit **preserves** the corresponding destination bit. ·
- The **XOR** instruction can be used to **complement** specific destination bits while preserving the others.
 - A 1 mask bit complements the corresponding destination bit;
 - A 0 mask bit preserves the corresponding destination bit.

Clear bit



Example

 Clear the sign bit of AL while leaving the other bits unchanged

Solution:

- Use the AND instruction with 01111111b=7Fh as the mask.
- Thus. AND AL,7Fh

Set or Complement Bit



- Example: Set the most significant and least significant bits of AL while preserving the other bits.
 - Solution: Use the OR instruction with 10000001b =81h as the mask.
 - Thus, OR AL,81h
- Example: Change the sign bit of DX.
 - Solution: Use the XOR instruction with a mask of 8000h.
 - Thus, XOR DX,8000h

*** To avoid typing errors, it's best to express the mask in hex rather than binary, especially if the mask would be 16 bits long.

Converting an ASCII Digit to a Number



- when program reads a character or digit from the keyboard, AL gets the ASCII code of the character.
- For example, if the "5" key is pressed, AL gets 35h instead of 5. To get 5 in AL, we did
 - > SUB AL,30h
- We can also do this by using an AND instructions to clear the high four bits of AL.
 - > AND AL,0Fh
- As the ASCII codes of "0" to "9" are 30h to 39h, this method will convert any ASCII digit to a decimal value.
- Using AND emphasizes on modifying bit pattern of AL and makes program more readable.

Problem: convert a stored decimal digit to Its ASCII code?

Converting a Lowercase Letter to Upper Case



- The ASCII codes range for
 - "a" to "z" is 61h to 7Ah
 - "A" to "Z" is 41h to 5Ah.
- So, to convert a lowercase to UPPERCASE we use the following operation:
 - Sub DL,20h
- However, if we compare binary codes of corresponding lower and uppercase letters,

Character		Code	Character	Code
а		0110001	A	010000
b	7	01100010	В	01000010
		٠.	• .	
		01111010	z	01011010

Conversion using AND



- To convert lower to upper case we need to clear only bit 5. This can be done by using an AND instruction with the mask **11011111** or **0DFh**. So if the lowercase character to be converted is In DL, we execute
- AND DL, ODFh

Clearing a Register



- ➤ MOV AX,o
- > SUB AX, AX
- \triangleright XOR AX,AX [1 XOR 1 = o and o XOR o=o]

Testing a Register for Zero

- To test the contents of a register for zero, or to check the sign of the contents, we may use:
- > CMP CX,0

Not Instruction



- The NOT instruction performs the one's complement operation on the destination. The format is:
- NOT destination (**No effect on status flags)
- Example: Complement the bits in AX:
- > NOT AX

Status Flags

- The Zero flag is set when the result of an operation equals zero.
- · The Carry flag is set when an instruction generates a carry during add operation.
- The Sign flag is set if the destination operand is negative, and it is clear if the destination operand is positive.
- The Overflow flag is set when an instruction generates an invalid signed result.
- Less important:
 - The Parity flag is set when an instruction generates an even number of 1 bits in the low byte of the destination operand.
 - The Auxiliary Carry flag is set when an operation produces a carry out from bit 3 to bit 4

TEST Instruction




- The **TEST** Instruction performs an AND operation of the destination with the source but **does not change** the destination contents.
- The purpose of the test instruction is to **set the status flags**. The format is:
 - TEST destination, Source
- > Effects of flags on test operation:
 - CF, OF =0
 - AF = Undefined
 - SF, ZF, PF reflect the result

AND Instruction

- Performs a Boolean AND operation between each pair of matching bits in two operands
- Syntax:

AND destination, source (same operand types as MOV)

AL= 0011 1011 AND AL,0FH




AND

x	у	x ^ y
0	0	0
0	1	0
1	0	V
(-)	(-)	10

OR Instruction

- Performs a Boolean OR operation between each pair of matching bits in two operands
- Syntax:

OR destination, source




OR

x	у	$\boldsymbol{x}\vee\boldsymbol{y}$
0	0	0 6
0	VI	(1)
1	0	1
1	1	U

XOR Instruction

- Performs a Boolean exclusive-OR operation between each pair of matching bits in two operands
- Syntax:

XOR destination, source



XOR

XOR is a useful way to toggle (invert) the bits in an operand.

NOT Instruction

- · Performs a Boolean NOT operation on a single destination operand
- Syntax:

NOT destination

NOT 00111011 11000100 inverted NOT

х	¬х
F	<u>T</u>
T	F

Problem-1

- Task: Convert the character in AL to upper case.
- Solution: Use the AND instruction to clear bit 5.

```
mov al,'a' ; AL = 97 = 01100001b and al,11011111b ; AL = 65 = 01000001b
```

Bit Examination on TEST



- > TEST instruction can be used to examine individual bits in operand.
- The mask should contain 1's in the bit positions to be tested and 0's elsewhere
 - As 1 AND b = b, 0 AND b = 0
- The operation TEST destination, mask
- ➤ Will have 1's in the tested bit positions if and only if the destination has 1's in these positions; and 0's elsewhere.
- if the destination has 0's in all the tested positions, the result will be 0 and thus ZF=1

Problem-2

- Task: Convert a binary decimal byte into its equivalent ASCII decimal digit.
- Solution: Use the OR instruction to set bits 4 and 5.

```
mov al,6 ; AL = 6 = 00000110b
or al,00110000b ; AL = 54 = 00110110b
```

TEST Instruction

- Bitwise AND operation between each pair of bits
 - TEST Destination, Source
- The flags are affected similar to the AND Instruction.
- However, TEST dost NOT modify the destination operand. The Zero flag is affected
- TEST instruction can check several bits at once.
- Example: Test whether bit 0 or bit 3 is set in AL

Solution: test al,00001001b Test bits 0 & 3

- We only need to check the zero flag.
 - If zero flag=>both bits 0 and 3 are clear.
 - If Not zero => either bit 0 or 3 is set.

Activate Wind

CMP Instruction

- · Compares the destination operand to the source operand
 - Nondestructive subtraction of source from destination (destination operand is not changed)
- · Syntax: CMP destination, source
- Example: destination = source

mov al,5 cmp al,5 ; Zero flag set

Example: destination < source



CMP Instruction

Example: destination > source

-5

(both the Zero and Carry flags are clear)

Find Even Number



- Example: Jump to label BELOW If AL contains an even number.
- > **Solution:** Even numbers have a 0 in bit 0. Thus, the mask is 00000001b=1
 - TEST AL, 1
 - JZ BELOW

- The shift and rotate instructions **shift the bits** in the **destination operand** by one or more positions either to the left or right.
- > For a shift instruction, the bits shifted out are lost
- For a rotate instruction, bits shifted out from one end of the operand are put back into the other end.
- The instruction have two possible formats. For a single shift or rotate, the form is
 - Opcode destination,1
- \triangleright For a shift or rotate of **N** positions, the form is
 - Opcode destination, CL
- ➤ Where CL contains N In both cases, destination is an 8- or 16-bit register or memory location.

Shift Instructions...



Shift or Rotate instructions can be used to multiply and divide by powers of 2, and we will use them in programs for binary and hex I/O

***Note that for Intel's more advanced processors, a shift or rotate instruction also allows the use of an 8-bit **constant**.

Left Shift (SHL) Instructions



- ➤ The SHL (shift left) instruction shifts the bits in the destination to the left. The format for a single shift is
 - SHL destination, 1
- A 0 is shifted into the **rightmost bit position** and the **msb is shifted into CF**. If the shift count **N** is different from 1, the instruction takes the form
 - > SHL destination, CL (Here CL contains N and the above instruction made N single shifts)
 - The value of CL remains the same after the shift operation

Effect on flags

SF, PF, ZF reflect the result

AF is undefined


CF = last bit shifted out

OF = 1 if result changes sign on last shift

SHL Instruction



- Example: Suppose DH contains **8Ah** and **CL** contains **3**. What are the values of DH and of CF after the instruction **SHL DH,CL** is executed?
- The binary value of DH is **10001010**. After **3 left shifts**, CF will contain 0. The new contents of DH may be obtained by
- Erasing the leftmost three bits
- Adding three zero bits to the right end, thus 01010000b = 50h.



Multiplication by Left Shift



- Let us consider a decimal number 235.
 - If each digit is shifted left and 0 is attached on the right end, we get 2350 which is same as multiplying by 10.
 - Similarly, a left shift on a binary number multiplies it by 2.
- For example, suppose that AL contains 5=00000101b
 - A left shift gives 00001010b = 10 thus doubling its value.
 - Another left shift yields 00010100= 20d, so it is doubled again.

Shift Arithmetic Left (SAL)




- > SHL Instruction can be used to multiply an operand by multiples of 2.
- However, to emphasize the arithmetic nature of the operation the opcode SAL (shift arithmetic left)often used in instances for numeric multiplication.
- Both instructions generate the same machine code.
- When we treat left shifts as multiplication, overflow may occur.
- For a single left shift, CF and OF accurately indicate unsigned and signed over- flow, respectively.
- However, the overflow flags are not reliable indicators for a multiple left shift as multiple shift is really a series of single shifts, and OF and CF only reflect the **result of the last shift**.

Right Shift (SHL) Instructions



- The instruction SHR (shift right) performs right shifts on the destination operand
- SHR destination, 1
- A 0 is shifted Into the msb position, and the rightmost bit is shifted
- > SHR destination, CL
- ** here CL contains N In this case N single right shifts are made. The effect on the flags is the same as for SHL



References



- Assembly Language Programming and Organization of the IBM PC, Ytha Yu and Charles Marut, McGraw Hill, 1992. (ISBN: 0-07-072692-2).
- http://faculty.cs.niu.edu/~byrnes/csci360/notes/360shift.htm

Books



- Assembly Language Programming and Organization of the IBM PC, Ytha Yu and Charles Marut, McGraw Hill, 1992. (ISBN: 0-07-072692-2).
- Essentials of Computer Organization and Architecture, (Third Edition), Linda Null and Julia Lobur
- W. Stallings, "Computer Organization and Architecture: Designing for performance", 67h Edition, Prentice Hall of India, 2003, ISBN 81 – 203 – 2962 – 7
- Computer Organization and Architecture by John P. Haynes.