
## Contents


Things You Just Gotta Know	2
Coordinate Systems	
Polar Coordinates	3
Spherical and Cylindrical Coordinates	5
Scale Factors and Jacobians	
Complex Numbers	
Introduction	
Some Trigonometry with Complex Exponentials	
Index Algebra	
Contractions and Dummy Indices	
Two Special Tensors	
Binomial Theorem	
Infinite Series	
Power Series	
Taylor Series	
Ten Integration Techniques	
Integration by Parts	
Change of Variables	
Even/Odd	
Products and Powers of Sines and Cosines	
Axial and Spherical Symmetry	
Differentiation with Respect to a Parameter	
Gaussian Integral	
Completing the Square	
Series Expansion	28
Partial Fractions	29
Delta Distribution	29
Properties of the Delta Distribution	30
Vector Calculus	34
Vector Fields	
Gradient, Divergence, and Curl	
The $\nabla$ Operator	
Applying Vector Identities to the $\nabla$ Operator	
Changing Coordinates	42
Understanding $\nabla^2$ , $\nabla \cdot$ , and $\nabla \times \cdot $	42
Integrating Scalar and Vector Fields	46
Line Integrals	46
Surface Integrals	48
Circulation	
Flux	52
Calculating Flux Integrals with Boundary Geometry	56
Divergence Theorem	57
Stokes's Theorem	
The Fundamental Theorem of Calculus, Revisited	
Helmholtz Decomposition	
Maxwell's Equations	
Integrating Maxwell	
From Integrals to Derivatives	
Substituting Potentials	

Linear Algebra	67
Superposition	67
	68
Essentials of Vector Spaces	68
	68
	70
	71
	72
,	75
	76
	81
	84
	86
	88
	88
	89
	93
	95
	96
	98
O .	
O .	100
Finding Eigenvalues	
	104
Diagonalization	
Normal Modes	109

# Things You Just Gotta Know

## **Coordinate Systems**






We want to focus on vector-valued functions of coordinates.

$$\vec{V}(\mathbf{r}) = V_x(x, y)\hat{\mathbf{i}} + V_y(x, y)\hat{\mathbf{j}}.$$

Notice that a vector function uses the coordinate system twice. Once for the function's inputs, once for the vectors themselves.

#### **Polar Coordinates**



We can also express the inputs to  $\vec{V}$  in polar coordinates,  $(\rho, \varphi)$ .

$$\vec{V}(\mathbf{r}) = V_{\rho} (\rho, \phi) \hat{\mathbf{i}} + V_{\phi} (\rho, \phi) \hat{\mathbf{j}}.$$

To extract the input functions, we take

$$V_x = \hat{i} \cdot \vec{V}$$

$$V_y = \hat{j} \cdot \vec{V}$$
.

Alternatively, we can project  $\vec{V}$  onto the  $\hat{\rho},\hat{\varphi}$  axis:

$$\vec{V}(\textbf{r}) = V_{\rho}\left(\rho,\varphi\right)\hat{\rho} + V_{\varphi}\left(\rho,\varphi\right)\hat{\varphi},$$

and we extract

$$V_{\rho} = \hat{\rho} \cdot \vec{V}$$

$$V_{\Phi} = \hat{\Phi} \cdot \vec{V}.$$

Notice that **r** is an abstract vector; we need to project it onto a basis.

For instance, we can take the position vector and project it onto the cartesian and polar axes:

$$\mathbf{s} = x\hat{\mathbf{i}} + y\hat{\mathbf{j}}$$

$$= \rho \cos \phi \hat{\mathbf{i}} + \rho \sin \phi \hat{\mathbf{j}}$$

$$= \rho \hat{\rho}$$

$$= \sqrt{x^2 + y^2} \hat{\rho}$$

The main reason we avoided using the  $\hat{\rho}$ ,  $\hat{\varphi}$  axis up until this point is that  $\rho$  and  $\varphi$  are *position-dependent*, while the  $\hat{i}$ ,  $\hat{j}$  axis is position-independent.

Now, we must figure out the position-dependence of  $\hat{\rho}$  and  $\hat{\phi}$ :

$$d\mathbf{r} = \frac{\partial \mathbf{r}}{\partial \rho} d\rho + \frac{\partial \mathbf{r}}{\partial \phi} d\phi.$$

If we hold  $\phi$  constant, it must be the case that any change in  $\rho$  is in the  $\hat{\rho}$  direction. Therefore,

$$\hat{\rho} = \frac{\frac{\partial \mathbf{r}}{\partial \rho}}{\left\| \frac{\partial \mathbf{r}}{\partial \rho} \right\|}$$

$$= \frac{\cos \phi \hat{\mathbf{i}} + \sin \phi \hat{\mathbf{j}}}{\left| \cos \phi \hat{\mathbf{i}} + \sin \phi \hat{\mathbf{j}} \right|}$$

$$= \cos \phi \hat{\mathbf{i}} + \sin \phi \hat{\mathbf{i}}$$

Similarly,

$$\hat{\Phi} = \frac{\frac{\partial \mathbf{r}}{\partial \Phi}}{\left\| \frac{\partial \mathbf{r}}{\partial \rho} \right\|}$$

$$= \frac{-\rho \sin \Phi \hat{\mathbf{i}} + \rho \cos \Phi \hat{\mathbf{j}}}{\left\| -\rho \sin \Phi \hat{\mathbf{i}} + \rho \cos \Phi \hat{\mathbf{j}} \right\|}$$

$$= -\sin \Phi \hat{\mathbf{i}} + \cos \Phi \hat{\mathbf{j}}.$$

Thus, we can see that the  $\hat{\rho}$ ,  $\hat{\phi}$  axis is orthogonal.

$$\begin{aligned} \frac{\partial \hat{\rho}}{\partial \phi} &= -\sin \phi \hat{i} + \cos \phi \hat{j} \\ &= \hat{\phi}, \\ \frac{\partial \hat{\phi}}{\partial \phi} &= -\hat{\rho}, \\ \frac{\partial \hat{\phi}}{\partial \rho} &= 0, \end{aligned}$$

and

$$\frac{\partial \hat{\rho}}{\partial \rho} = 0$$

Example (Velocity).

$$\mathbf{v} = \frac{\mathrm{d}\mathbf{s}}{\mathrm{d}t}$$

$$= \frac{\mathrm{d}}{\mathrm{d}t} \left( x \hat{\mathbf{i}} \right) + \frac{\mathrm{d}}{\mathrm{d}t} \left( y \hat{\mathbf{j}} \right).$$

In the case of cartesian coordinates,  $\hat{i}$  and  $\hat{j}$  are constants.

$$= v_x \hat{i} + v_y \hat{j}$$

When we examine polar coordinates, since  $\hat{\rho}$  and  $\hat{\varphi}$  are position-dependent, we must use the chain rule.<sup>I</sup>

$$\mathbf{v} = \frac{d\mathbf{s}}{dt}$$

$$= \frac{d\rho}{dt}\hat{\rho} + \rho \frac{d\hat{\rho}}{dt}$$


$$= \frac{d\rho}{dt}\hat{\rho} + \rho \left( \frac{\partial \hat{\rho}}{\partial \rho} \frac{d\rho}{dt} + \underbrace{\frac{\partial \hat{\rho}}{\partial \varphi}}_{=\hat{\varphi}} \frac{d\varphi}{dt} \right)$$

$$= \frac{d\rho}{dt}\hat{\rho} + \rho \frac{d\varphi}{dt}\hat{\varphi}$$


$$= \dot{\rho}\hat{\rho} + \rho \dot{\varphi}\hat{\varphi}.$$

Notice that  $\dot{\rho}$  is the radial velocity and  $\dot{\phi} = \omega$  is the angular velocity.

## **Spherical and Cylindrical Coordinates**



<sup>I</sup>Note that  $\hat{\rho} = \hat{\rho}(\rho, \phi)$  and  $\hat{\phi} = \hat{\phi}(\rho, \phi)$ .



Here,  $^{\text{II}}$   $\varphi$  denotes the polar angle and  $\theta$  denotes the azimuthal angle. Notice that  $\varphi \in [0,2\pi)$  and  $\theta \in [0,\pi]$ .

We can see that  $\hat{\rho}$ ,  $\hat{\phi}$ , and  $\hat{\theta}$  in spherical coordinates are also position-dependent.

$$\hat{r} = \frac{\frac{\partial s}{\partial r}}{\left\|\frac{\partial s}{\partial r}\right\|}$$

$$= \sin \theta \cos \phi \hat{i} + \sin \theta \sin \phi \hat{j} + \cos \theta \hat{k}$$

$$\hat{\Phi} = \frac{\frac{\partial s}{\partial \varphi}}{\left\|\frac{\partial s}{\partial \varphi}\right\|}$$

$$= -\sin \phi \hat{i} + \cos \phi \hat{j}$$

$$\hat{\theta} = \frac{\frac{\partial s}{\partial \theta}}{\left\|\frac{\partial s}{\partial \theta}\right\|}$$

$$= \cos \phi \cos \theta \hat{i} + \cos \theta \sin \phi \hat{j} - \sin \theta \hat{k}$$

#### Scale Factors and Jacobians

In cylindrical coordinates, we can use the chain rule to find the value of dr:

$$d\mathbf{r} = \hat{\rho}d\rho + \rho\hat{\Phi}d\Phi + \hat{k}dz.$$

The extra factor of  $\rho$  in the expression of  $\rho \hat{\varphi} d\varphi$  is the *scale factor* on  $\varphi$ .

Similarly, in spherical coordinates, we have

$$d\mathbf{r} = \hat{\mathbf{r}}d\mathbf{r} + \mathbf{r}\sin\theta\hat{\mathbf{\varphi}}d\mathbf{\varphi} + \mathbf{r}\hat{\mathbf{\theta}}d\mathbf{\theta},$$

with scale factors of  $r \sin \theta$  on  $\hat{\phi} d\phi$  and r on  $\hat{\theta} d\theta$ .

When we go from line elements (of the form dr) to area elements (of the form da), we can see that the area element in polar coordinates is  $d\mathbf{a} = \rho d\rho d\phi$  — we need the extra factor of  $\rho$  to account for the fact that the

IIPhysicists amirite?

magnitude of the area element scales with the radius.

Similarly, the volume element in cylindrical coordinates is  $d\tau = r dr d\varphi dz$  and the volume element in spherical coordinates is  $r^2 \sin \theta dr d\varphi d\theta$ .

Recall that the definition of an angle  $\phi$  that subtends an arc length s is  $\phi \frac{s}{r}$ , where r is the radius of a circle. We can imagine a similar concept on a sphere — a *solid angle* measured in steradians is of the form  $\Omega = \frac{A}{r^2}$ , where A denotes the surface area subtended by the angle  $\Omega$ . In particular, since  $d\Omega = \frac{dA}{r^2}$ , we find that  $d\Omega = \sin\theta d\phi d\theta$ .

When we are dealing with products of scale factors, we need to use the Jacobian to determine the proper scale factor on any given element:

$$d\mathbf{a} = dxdy$$
$$= |J| dudv,$$

where |J| denotes the determinant of the Jacobian matrix. We write the Jacobian as follows:


$$J = \frac{\partial (x, y)}{\partial (u, v)}$$
$$= \begin{pmatrix} \frac{\partial x}{\partial u} & \frac{\partial y}{\partial u} \\ \frac{\partial x}{\partial v} & \frac{\partial y}{\partial v} \end{pmatrix}.$$

We specifically desire the determinant:

$$|J| = \frac{\partial x}{\partial u} \frac{\partial y}{\partial v} - \frac{\partial y}{\partial u} \frac{\partial x}{\partial v}.$$

## **Complex Numbers**

#### Introduction



A complex number is denoted

$$z = a + bi$$

where  $i^2 = -1$  and  $a, b \in \mathbb{R}$ . This is known as the Cartesian representation. However, we can also imagine z as the polar representation:

$$z = re^{i\varphi}$$
.

where  $\phi = \arg z$  is known as the argument, and r = |z| is the modulus. We can see the relation between the Cartesian and polar representations through Euler's identity:<sup>III</sup>

$$r(\cos \phi + i \sin \phi) = re^{i\phi}$$
.

We denote the conjugate of z as  $\overline{z}$ , found by  $\overline{z} = a - bi = re^{-i\phi}$ .

We find Re(z) and Im(z), the real and imaginary parts of z, by

$$Re(z) = \frac{z + \overline{z}}{2}$$
$$Im(z) = \frac{z - \overline{z}}{2i}.$$

We say that a complex number of the form  $e^{i\phi}$  is a *pure phase*, as  $|e^{i\phi}| = 1$ .

To find if some complex number z is purely real or purely imaginary, we can use the following criterion:

$$z \in \mathbb{R} \Leftrightarrow z = \overline{z}$$
$$z \in i\mathbb{R} \Leftrightarrow z = -\overline{z}.$$

Example (Real, Imaginary, or Complex?). Consider

$$z_1 = i^i$$
.

To find if this is purely real or complex, we take

$$\overline{z_1} = (-i)^{-i}$$

$$= \left(\frac{1}{-i}\right)^{i}$$

$$= i^{i}.$$

Thus,  $z_1 \in \mathbb{R}$ . In order to determine the value of  $i^i$ , we substitute the polar form:

$$z_1 = \left(e^{i\frac{\pi}{2}}\right)^i$$
$$= e^{-\frac{\pi}{2}}.$$

#### Some Trigonometry with Complex Exponentials

Consider  $z = \cos \phi + i \sin \phi$ . We can see that

$$Re(z) = \cos \phi$$

$$= \frac{(\cos \phi + i \sin \phi) + (\cos \phi - i \sin \phi)}{2}$$

$$= \frac{e^{i\phi} + e^{-i\phi}}{2}$$

$$Im(z) = \sin \phi$$

$$= \frac{(\cos \phi + i \sin \phi) - (\cos \phi - i \sin \phi)}{2i}$$

$$= \frac{e^{i\phi} - e^{-i\phi}}{2i}.$$

We can actually define  $\sin \phi$  and  $\cos \phi$  with the above derivation.

<sup>&</sup>lt;sup>III</sup>This can be proven relatively easily through substitution into the Taylor series, which is allowed because  $e^z$  is entire.

Theorem (De Moivre):

$$e^{inx} = \cos(nx) + i\sin(nx)$$
$$= (e^{ix})^n$$
$$= (\cos x + i\sin x)^n.$$

**Example** (Finding  $\cos(2x)$  and  $\sin(2x)$ ).

$$\cos(2x) + i \sin(2x) = (\cos x + i \sin x)^{2}$$
$$= (\cos^{2} x - \sin^{2} x) + i (2 \sin x \cos x).$$

Since the real parts and imaginary parts have to be equal, this means

$$\cos 2x = \cos^2 x - \sin^2 x$$
$$\sin^2 x = 2\sin x \cos x.$$

In particular, we can see that  $e^{in\phi} = (-1)^n$  and  $e^{in\frac{\pi}{2}} = i^n$ . In

Additionally, we can see that for  $z = re^{i\phi}$ ,

$$z^{1/m} = \left(re^{i\phi + 2\pi n}\right)^{1/m}$$
$$= r^{1/m}e^{i\frac{1}{m}(\phi + 2\pi n)}$$

where  $n \in \mathbb{N}$  and m is fixed. For r = 1, we call these values the m roots of unity.

**Example** (Waves and Oscillations). Recall that for a wave with spatial frequency k, angular frequency  $\omega$ , and amplitude A, the wave is represented by

$$f(x, t) = A \cos(kx - \omega t)$$
.

The speed of a wave v is equal to  $\frac{\omega}{k}$ .

Simple harmonic motion is characterized by the solution to the differential equation  $\ddot{\mathbf{x}} = -\omega^2 \mathbf{x}$ , where  $\mathbf{x}$  denotes position. In simple harmonic motion, there is no spatial motion, meaning our function is only of time:

$$f(t) = A \cos \omega t$$
$$= Re \left( A e^{i\omega t} \right).$$

As a result of the representation of complex numbers in polar form, we can do math entirely in exponentials, then take the real part of our solution to find f(t).

Unfortunately, in the real world, there is friction; as a result, our oscillation is damped by an exponential factor.

**Example** (Hyperbolic Sine and Hyperbolic Cosine). We wish to calculate cos ix and sin ix.

$$\cos ix = \frac{1}{2} \left( e^{i(ix)} + e^{-i(ix)} \right)$$
$$= \frac{e^{-x} + e^x}{2}$$

<sup>&</sup>lt;sup>IV</sup>This will be especially useful when we get to Fourier series.

We define  $\cosh x = \cos(ix)$ . Additionally,

$$-i\sin ix = -i\frac{1}{2i} \left( e^{i(ix)} - e^{-i(ix)} \right)$$
$$= i\frac{e^x - e^{-x}}{2i}.$$
$$= \frac{e^x - e^{-x}}{2}.$$

We define  $\sinh x = -i \sin (ix)$ .

Similar to how  $\cos^2 x + \sin^2 x = 1$ , we can find that  $\cosh^2 x - \sinh^2 x = 1$ .

## Index Algebra

We usually denote vectors by either  $\vec{A}$ ,  $\vec{A}$ , or

$$\begin{pmatrix} a_1 \\ a_2 \\ \vdots \\ a_n \end{pmatrix}'$$

which is defined by a basis.

If we imagine we are in n-dimensional space, we can let  $A_i$  where i = 1, 2, ..., n denote both

- the ith component of  $\vec{A}$ ;
- the entire vector  $\vec{A}$  (since i can be arbitrary).

#### **Contractions and Dummy Indices**

Consider C = AB, where A, B are  $n \times m$  and  $m \times p$  matrices respectively.

$$C = \begin{pmatrix} A_{11} & A_{12} & \cdots & A_{1m} \\ \vdots & \vdots & \ddots & \vdots \\ A_{n1} & A_{n2} & \cdots & A_{nm} \end{pmatrix} \begin{pmatrix} B_{11} & B_{12} & \cdots & B_{1p} \\ \vdots & \vdots & \ddots & \vdots \\ B_{m1} & B_{m2} & \cdots & B_{mp} \end{pmatrix}.$$

**Definition** (Matrix Multiplication in Index Notation). For matrices A and B, where A is an  $m \times n$  and B is a  $n \times p$  matrix, we write

$$C_{ij} = \sum_{k=1}^{n} A_{ik} B_{kj}$$

We say that k is a dummy index, since k takes values from 1 to n. Note that the value we calculate is  $C_{ij}$ ; in other words, in the sum  $\sum_k A_{ik} B_{kj}$ , the indices of the form ij are the "net indices" from the multiplication.

Note that if C = BA, then

$$C_{ij} = \sum_{k=1}^{n} B_{ik} A_{kj}$$
$$= \sum_{k=1}^{n} A_{kj} B_{ik}$$

$$\neq \sum_{k=1}^{n} A_{ik} B_{kj}.$$

The corresponding fact is that  $AB \neq BA$  necessarily.

Note that the index that is summed over always appears exactly twice.

**Definition** (Symmetric Matrix). Let C be a matrix. Then, we say C is symmetric if

$$C_{ii} = C_{ii}$$

**Definition** (Antisymmetric Matrix). Let C be a matrix. We say C is antisymmetric if

$$C_{ii} = -C_{ii}$$
.

We can always decompose a random matrix into the sum of a symmetric matrix and an antisymmetric matrix.

## **Two Special Tensors**

**Definition** (Kronecker Delta). The Kronecker Delta,  $\delta_{ij}$ , is the tensor that denotes the identity matrix.

$$\delta_{ij} = \begin{cases} 1 & i = j \\ 0 & i \neq j \end{cases}$$

Example (Extracting an Index). Consider A as vector. Then,

$$\sum_{i} A_{i} \delta_{ij} = A_{j}.$$

In other words, the Kronecker Delta collapses the sum to the jth index.

**Example** (Orthonormal Basis from Kronecker Delta). Let  $\{\hat{e}_i\}_{i=1}^n$  be a basis for some vector space V. If

$$\hat{e}_{i} \cdot \hat{e}_{i} = \delta_{ii}$$

for every i, j, then  $\{\hat{e}_i\}_{i=1}^n$  is an orthonormal basis for V.

Definition (Levi-Civita Symbol). In two dimensions, as a matrix, we write

$$\epsilon_{ij} = \begin{pmatrix} 0 & 1 \\ -1 & 0 \end{pmatrix},$$

meaning

$$\varepsilon_{ij} = \begin{cases} 1 & \text{i} = 1, \text{j} = 2 \\ -1 & \text{i} = 2, \text{j} = 1 \\ 0 & \text{else} \end{cases}$$

The Levi-Civita Symbol is antisymmetric, just as the Kronecker Delta is symmetric.

In three dimensions, we define

$$\varepsilon_{ijk} = \begin{cases} 1 & (i,j,k) = (1,2,3) \text{ cyclically} \\ -1 & (i,j,k) = (2,1,3) \text{ cyclically }. \\ 0 & \text{else} \end{cases}$$

In other words,  $\epsilon_{ijk} = -\epsilon_{jik}$ .

**Exercise** (Relations between  $\delta_{ij}$  and  $\epsilon_{ijk}$ ):

$$\begin{split} &\sum_{j,k} \varepsilon_{mjk} \varepsilon_{njk} = 2\delta_{mn} \\ &\sum_{\ell} \varepsilon_{mn\ell} \varepsilon_{ijl} = \delta_{mi} \delta_{nj} - \delta_{mj} \delta_{ni} \end{split}$$

**Definition** (Dot Product). Let  $\{\hat{e}_i\}_{i=1}^n$  be an orthonormal basis for V. Let  $\mathbf{A} = \sum_i A_i \hat{e}_i$  and  $\mathbf{B} = \sum_i B_i \hat{e}_i$ . Then,

$$\mathbf{A} \cdot \mathbf{B} = \sum_{i,j} (A_i \hat{e}_i) \cdot (B_j \hat{e}_j)$$

$$= \sum_{i,j} A_i B_j (\hat{e}_i \cdot \hat{e}_j)$$

$$= \sum_{i,j} A_i B_j \delta_{ij}$$

$$= \sum_{i} A_i B_i$$

**Definition** (Cross Product). Let  $\{\hat{e}_i\}_{i=1}^3$  be the standard basis over  $\mathbb{R}^3$ . Let  $\mathbf{A} = \sum_i A_i \hat{e}_i$  and  $\mathbf{B} = \sum_i B_i \hat{e}_i$ . Then,

$$\begin{split} \boldsymbol{A} \times \boldsymbol{B} &= \sum_{i,j} \left( A_i \hat{\boldsymbol{e}}_i \right) \times \left( B_j \hat{\boldsymbol{e}}_j \right) \\ &= \sum_{i,j} A_i B_j \left( \hat{\boldsymbol{e}}_i \times \hat{\boldsymbol{e}}_j \right) \\ &= \sum_{i,j,k} A_i B_j \left( \boldsymbol{\varepsilon}_{ijk} \hat{\boldsymbol{e}}_k \right). \end{split}$$

Instead of asking about  $A \times B$ , we ask about  $(A \times B)_{\ell}$ , yielding

$$\begin{split} (\mathbf{A} \times \mathbf{B})_{\ell} &= (\mathbf{A} \times \mathbf{B}) \cdot \hat{\mathbf{e}}_{\ell} \\ &= \left( \sum_{i,j,k} A_{i} B_{j} \left( \boldsymbol{\epsilon}_{ijk} \hat{\mathbf{e}}_{k} \right) \right) \cdot \hat{\mathbf{e}}_{\ell} \\ &= \sum_{i,j} \boldsymbol{\epsilon}_{ij\ell} A_{i} B_{j}. \end{split}$$

**Remark:** This notation for  $A \times B$  automatically shows us that

$$\begin{split} (\mathbf{B} \times \mathbf{A})_{\ell} &= \sum_{i,j} \varepsilon_{ij\ell} B_i A_j \\ &= -\sum_{i,j} \varepsilon_{ji\ell} B_i A_j \\ &= -\sum_{i,j} \varepsilon_{ji\ell} A_j B_i \\ &= -\sum_{i,j} \varepsilon_{ij\ell} A_i B_j \\ &= -(\mathbf{A} \times \mathbf{B})_{\ell} \,. \end{split}$$
 i, j are dummy indices

Example (Central Force and Angular Momentum). A central force is defined by

$$\mathbf{F} = f(\mathbf{r})\hat{\mathbf{r}}$$
,

where  $\hat{r}$  is a radial vector.

Angular momentum is defined by

$$L = r \times p$$

where  $\mathbf{r}$  denotes position and  $\mathbf{p}$  denotes momentum. Then,

$$\begin{split} \frac{d\mathbf{L}}{dt} &= \frac{d}{dt} \left( \mathbf{r} \times \mathbf{p} \right) \\ &= \left( \frac{d}{dt} \mathbf{r} \times \mathbf{p} \right) + \mathbf{r} \times \left( \frac{d\mathbf{p}}{dt} \right) \\ &= m \left( \frac{d}{dt} \mathbf{r} \times \frac{d}{dt} \mathbf{r} \right) + \mathbf{r} \times (\mathbf{f}(\mathbf{r})\hat{\mathbf{r}}) \\ &= \mathbf{f}(\mathbf{r}) \left( \mathbf{r} \times \hat{\mathbf{r}} \right). \end{split}$$

This implies that  $\frac{d\mathbf{L}}{dt} = 0$  under a central force.

**Example** (Determinant). Let  $\mathbf{M} = M_{ij}$  be square. We denote  $\mathbf{M}_i$  to be the vector denoting the ith-row. Then,

$$m = |\mathbf{M}|$$

$$= \mathbf{M}_1 \cdot (\mathbf{M}_2 \times \mathbf{M}_3)$$

$$= \mathbf{M}_3 \cdot (\mathbf{M}_1 \times \mathbf{M}_2)$$

$$= \mathbf{M}_2 \cdot (\mathbf{M}_3 \times \mathbf{M}_1).$$

**Example** (Trace). Let  $\mathbf{M} = M_{ij}$  be a square matrix. We define  $\operatorname{tr}(\mathbf{M}) = \sum_{i} M_{ii}$ . Equivalently,

$$\begin{split} \operatorname{tr}\left(\mathbf{M}\right) &= \sum_{ij} M_{ij} \delta_{ij} \\ &= \sum_{i} M_{ii}. \end{split}$$

Note that

$$tr(I_n) = \sum_{i} \delta_{ii}$$
$$= n.$$

When we upgrade to 3 matrices, we take

$$tr(ABC) = \sum_{i,j} \left( \sum_{k,\ell} A_{ik} B_{k\ell} C_{\ell j} \right) \delta_{ij}$$

$$= \sum_{i,k,\ell} A_{ik} B_{k\ell} C_{\ell i}$$

$$= \sum_{i,k,\ell} C_{\ell i} A_{ik} B_{k\ell}$$

$$= tr(CAB).$$

In other words, the trace is invariant under cyclic permutations.

**Example** (Moment of Inertia Tensor).

Recall that

$$= I\omega$$
.

where  $\mathbf{p} = m\dot{\mathbf{x}}$ , and I denotes the moment of inertia. Note that I  $\sim mr^2$ . On a more fundamental level, it is the case that the first equation,  $\mathbf{L} = \mathbf{r} \times \mathbf{p}$ , is the "true" definition of  $\mathbf{L}$ .

Consider a small portion  $\mathfrak{m}_{\alpha}$  about some axis at radius  $\mathbf{r}_{\alpha}$  and momentum  $\mathfrak{p}_{\alpha}$ . Then, we have

$$\begin{split} L_{\alpha} &= \sum_{\alpha} r_{\alpha} \times p_{\alpha} \\ &= \sum_{\alpha} m_{\alpha} \left( r_{\alpha} \times (\omega \times r_{\alpha}) \right). \end{split}$$

In the infinitesimal case (i.e., as  $\alpha \to 0$ ), we get

$$\mathbf{L} = \int \mathbf{r} \times (\boldsymbol{\omega} \times \mathbf{r}) \, \rho \, d\tau,$$

where  $\rho$  denotes volume density. Applying the identity  $\mathbf{A} \times (\mathbf{B} \times \mathbf{C}) = \mathbf{B} (\mathbf{A} \cdot \mathbf{C}) - \mathbf{C} (\mathbf{A} \cdot \mathbf{B})$ , we find

$$L = \int \left( \omega \left( r \cdot r \right) - r \left( r \cdot \omega \right) \right) \rho \ d\tau.$$

Switching to index notation, we have

$$\begin{split} L_i &= \int \left( \omega_i r^2 - r_i \sum_j r_j \omega_j \right) \rho \; d\tau \\ &= \sum_j \int \omega_j \left( \delta_{ij} r^2 - r_i r_j \right) \rho \; d\tau \\ &= \sum_j \omega_j \underbrace{\left( \int \left( \delta_{ij} r^2 - r_i r_j \right) \rho \; d\tau \right)}_{moment \; of \; inertia \; tensor} \\ &= \sum_j I_{ij} \omega_j. \end{split}$$

## **Binomial Theorem**

The binomial theorem allows us to calculate the expansion

$$(x+y)^{n} = \sum_{m=0}^{n} \binom{n}{m} x^{n-m} y^{m}.$$

In the case of  $(x + y)^2 = x^2y^0 + 2x^1y^1 + x^0y^2 = x^2 + 2xy + y^2$ . Recall that

$$\binom{n}{m} = \frac{n!}{m!(n-m)!}.$$

Recall that 0! = 1.

#### **Infinite Series**

Let

$$S = \sum_{k=0}^{\infty} a_k$$

be an infinite series. We are often curious as to the convergence of this sum (for a variety of reasons). Formally, we have to invoke partial sums

$$S_{N} = \sum_{k=0}^{N} \alpha_{k},$$

and see if the sequence of partial sums is convergent. However, we will prefer to use series convergence tests.

Example (Geometric Series). Let

$$S = \sum_{k=0}^{\infty} r^k$$
$$= 1 + r + r^2 + \cdots$$

Then, we have

$$S_{N} = \sum_{k=0}^{N} r^{k}$$
$$rS_{N} = \sum_{k=0}^{N} r^{k}.$$

Subtracting, we get

$$(1-r)S_N = 1 - r^{N+1}$$
 
$$S_N = \frac{1-r^{N+1}}{1-r}.$$

In the limit, we expect that if  $r \to \infty$ , and r < 1, then  $r^{N+1} \to 0$ . In the infinite case, we have

$$S = \sum_{k=0}^{\infty} r^k$$
$$= \frac{1}{1 - r'}$$

if r < 1.

There are a few prerequisites for series convergence:

- there exists some K for which for all  $k \ge K$ ,  $a_{k+1} \le a_k$ ;
- $\lim_{k\to\infty} < \infty$ ;
- we need the series to reduce "quickly" enough.

**Example** (Ratio Test). A series  $S = \sum_k \alpha_k$  converges if the ratio of consecutive terms is (eventually) less than 1:

$$r = \lim_{k \to \infty} \frac{\alpha_{k+1}}{\alpha_k} < 1.$$

**Example** (Applying the Ratio Test). Consider  $S = \sum_{k} \frac{1}{k!}$ . Then,

$$r = \lim_{k \to \infty} \frac{\frac{1}{(k+1)!}}{\frac{1}{k!}}$$
$$= \lim_{k \to \infty} \frac{1}{k+1}$$
$$= 0 < 1$$

Example (Riemann Zeta Function). We write

$$\zeta(s) = \sum_{k=1}^{\infty} \frac{1}{k^s}.$$

In order to evaluate the convergence of the Riemann zeta function. We have

$$r = \lim_{k \to \infty} \frac{\frac{1}{(k+1)^s}}{\frac{1}{k^s}}$$
$$= \lim_{k \to \infty} \left(\frac{k}{k+1}\right)^s$$
$$= 1$$

Unfortunately, this means the ratio test is inconclusive.

For examples of evaluations of the zeta function, we have

$$\zeta(1) = 1 + \frac{1}{2} + \frac{1}{3} + \cdots$$

$$\zeta(2) = 1 + \frac{1}{4} + \frac{1}{9} + \cdots$$

$$= \frac{\pi^2}{6}.$$

**Example** (Absolute Convergence). In our original ratio test, we had assumed that  $a_k$  are real and positive. However, if the  $a_k \in \mathbb{C}$ , we have to look at the convergence in modulus:

$$r = \lim_{k \to \infty} \left| \frac{\alpha_{k+1}}{\alpha_k} \right|.$$

If  $\sum_{k} |a_k|$  converges, this is known as absolute convergence.

**Example** (Alternating Series Test). If the series

$$\sum_{k=0}^{\infty} \left(-1\right)^k a_k$$

has the following conditions:

- $a_{k+1} < a_k$  for k > K;
- $\lim_{k\to\infty} a_k = 0$ ;

then  $\sum_{k} (-1)^{k} a_{k}$  converges.

For instance, the alternating harmonic series converges

$$\sum_{k=1}^{\infty} (-1)^{k+1} \frac{1}{k} = \ln 2.$$

#### **Power Series**

Consider the function

$$S(x) = \sum_{k=0}^{\infty} \alpha_k x^k.$$

This is a series both in  $a_k$  and in x. In order to determine convergence, we use the ratio test as follows:

$$\lim_{k \to \infty} \left| \frac{a_{k+1} x^{k+1}}{a_k x^k} \right| = |x| \lim_{k \to \infty} \left| \frac{a_{k+1}}{a_k} \right|$$
$$\equiv |x| r.$$

In particular, for convergence, it must be the case that

We define

$$R = \begin{cases} \frac{1}{r} & 0 < r < \infty \\ 0 & r = \infty \\ \infty & r = 0 \end{cases}.$$

In particular, this means

$$|x| < R$$
.

**Definition** (Radius of Convergence). For a power series  $\sum_k a_k x^k$ , the series converges for |x| < R, where

$$\begin{split} r &= \lim_{k \to \infty} \left| \frac{\alpha_{k+1}}{\alpha_k} \right| \\ R &= \begin{cases} \frac{1}{r} & 0 < r < \infty \\ 0 & r = \infty \\ \infty & r = 0 \end{cases}. \end{split}$$

Note that convergence for |x| < R does not provide information regarding convergence at the boundary.

Example (Geometric Series). We have

$$\frac{1}{1-x} = \sum_{k=0}^{\infty} x^k$$

has R = 1, meaning the power series converges for |x| < 1.

Example (Exponential Function). We have

$$e^{x} = \sum_{k=0}^{\infty} \frac{x^{k}}{k!},$$

with  $R = \infty$ .

Example (Natural Log). We have

$$\ln{(1+x)} = x - \frac{1}{2}x^2 + \frac{1}{3}x^3 - \cdots$$

In particular, since R = 1, we know that the radius of convergence is |x| < 1. However, the series does converge on the boundary when x = 2, but not when x = 0 (for obvious reasons).

<sup>&</sup>lt;sup>v</sup>The definition is not the true radius of convergence; it is actually that  $r = \limsup_{k \to \infty} \sqrt[k]{|\alpha_k|}$ . It just happens to be the case that the ratio test and root test return the same value when they're regular limits (rather than limits superior).

**Example** (Why Radius of Convergence?). Consider two series

$$\frac{1}{1-x^2} = \sum_{k=0}^{\infty} x^{2k}$$
$$\frac{1}{1+x^2} = \sum_{k=0}^{\infty} (-1)^k x^{2k}.$$

We can see that the first series converges for |x| < 1. However, even though  $\frac{1}{1+x^2}$  has a domain across the entire real numbers, it is still the case that the *series* converges for |x| < 1.

The primary reason that the radius of convergence is defined as such is because, over the complex numbers, it is the case that  $x^2 + 1 = 0$  at  $x = \pm i$ , meaning  $\frac{1}{1+z^2}$  has singularities at those values of z.

The main reason power series are useful is that, when truncated, they are simply polynomials. In particular, with power series, we can reverse the order of sum and derivative.

#### **Taylor Series**

**Definition.** The Taylor series of a function f(x) about  $x_0$  is defined by

$$f(x) = \sum_{n=0}^{\infty} \frac{(x - x_0)^n}{n!} \left( \frac{d^n f}{dx^n} \Big|_{x = x_0} \right).$$

**Remark:** The reason we write  $\frac{d^n f}{dx^n}$  is because  $\frac{d^n}{dx^n}$  is an operator in and of itself.

Example (The Most Important Taylor Series).

$$e^{x} = \sum_{n=0}^{\infty} \frac{x^{n}}{n!}$$

$$\cos x = \sum_{n=0}^{\infty} \frac{(-1)^{n} x^{2n}}{(2n)!}$$

$$\sin x = \sum_{n=0}^{\infty} \frac{(-1)^{n+1} x^{2n+1}}{(2n+1)!}$$

**Example** (Equilibrium Points). Let U(x) denote a potential over x. Then,  $F = -\nabla U$ . We have

$$U(x) = U(x_0) + (x - x_0) U'(x_0) + \frac{1}{2!} (x - x_0)^2 U''(x_0) + \frac{1}{3!} (x - x_0)^3 U'''(x_0) + \cdots$$

When we analyze an equilibrium point, we disregard the  $U(x_0)$  term, and see that the derivative of U is zero; thus, we can truncate our series at the second derivative close to  $x = x_0$ :

$$U(x) \approx \frac{1}{2}U''(x_0)(x - x_0)^2$$
  
=  $\frac{1}{2}m\omega^2(x - x_0)^2$ .

In other words, when we are very close to equilibrium, we have simple harmonic motion.

**Example** (Faster Taylor Series). Consider the function

$$\exp\left(\frac{x}{1-x}\right)$$
.

In order to create its Taylor series, we can create this Taylor series piecewise:

$$\exp\left(\frac{x}{1-x}\right) = 1 + \left(\frac{x}{1-x}\right) + \frac{1}{2!} \left(\frac{x}{1-x}\right)^2 + \frac{1}{3!} \left(\frac{x}{1-x}\right)^3.$$

Now, we expand the denominators as geometric series:

$$= 1 + x \left( \sum_{k=0}^{\infty} x^k \right) + \frac{x^2}{2!} \left( \sum_{k=0}^{\infty} x^k \right)^2 + \frac{x^3}{3!} \left( \sum_{k=0}^{\infty} x^k \right) + \cdots$$

If we want to expand through  $x^3$ , we have to expand by keeping track of *every* term:

$$= 1 + x + \frac{3}{2}x^2 + \frac{13}{6}x^3 + O\left(x^4\right).$$

We say we have expanded the series through the third order; the lowest order correction, denoted  $O(x^n)$ , is the fourth order (in this case).

Example (Exponentiated Operator). Consider a (square) matrix M. Then, we define

$$e^{M} = \sum_{k=0}^{\infty} \frac{M^{k}}{k!},$$

where  $M^k = \prod_{i=1}^k M_i$ ; we define  $M^0 = I$ . Similarly,

$$e^{\frac{d}{dx}} = \sum_{k=0}^{\infty} \frac{d^k}{dx^k} \frac{1}{k!}.$$

In particular,  $e^{\frac{d}{dx}}$  is the Taylor series operator.

Remark: In quantum mechanics, the momentum operator is

$$P = -i\hbar \frac{d}{dx}.$$

**Example** (Binomial Expansion). For any  $\alpha \in \mathbb{C}$  and |x| < 1, we have

$$(1+x)^{\alpha} = 1 + \alpha x + \frac{\alpha(\alpha-1)}{2!}x^2 + \frac{\alpha(\alpha-1)(\alpha-2)}{3!}x^3 + \cdots$$

Note that if  $\alpha \in \mathbb{Z}^+$ , then the series truncates (and we recover the binomial theorem again).

The main use of the binomial expansion is with very small quantities. For instance,

$$E \sim \frac{1}{(x^2 + \alpha^2)^{3/2}}$$

$$= \frac{1}{x^3 \left(1 + \frac{\alpha^2}{x^2}\right)^{3/2}}$$

$$\approx \frac{1}{x^3} \left(1 - \frac{3}{2} \frac{\alpha^2}{x^2}\right)$$
For  $x \gg \alpha$ 

**Remark:** The binomial expansion only applies to the form  $(1 + x)^{\alpha}$ . If we are dealing with an expression of the form  $(\alpha + x)^{\alpha}$ , we need to factor out  $\alpha$ , making the expression  $\alpha^{\alpha} (1 + x/\alpha)^{\alpha}$ .

**Example** (Special Relativity with the Binomial Expansion). In the theory of special relativity, Einstein came up with the equations

$$E = \gamma mc^2$$

$$\gamma = \frac{1}{\sqrt{1 - \frac{v^2}{c^2}}}.$$

We can use the binomial expansion to find more information about  $\gamma$ .

$$E = \left(1 - \frac{v^2}{c^2}\right)^{-1/2} mc^2$$

$$= \left(1 + \frac{1}{2} \frac{v^2}{c^2} + \frac{\left(-\frac{1}{2}\right)\left(-\frac{3}{2}\right)}{2!} \left(-\frac{v^2}{c^2}\right)^2 + \cdots\right) mc^2$$

$$= mc^2 + \frac{1}{2} mv^2 \left(1 + \frac{3}{4} \frac{v^2}{c^2} + \frac{5}{8} \left(\frac{v^2}{c^2}\right)^2 + \cdots\right)$$
Kinetic Energy

As we take  $v \ll c$ , we only need to keep the first order term in the expansion, meaning we have  $E = mc^2 + \frac{1}{2}mv^2$ .

Thus, we can find kinetic energy as  $KE = (\gamma - 1) \text{ mc}^2$ . Notice that this means that *most* energy is internal energy emergent as mass.

## **Ten Integration Techniques**

While Mathematica may exist, vi it is still valuable to know how to take various integrals. More importantly, knowing how to take integrals provides valuable insights into what exactly integrals are.

#### **Integration by Parts**

**Definition** (Integration by Parts). Using the product rule, we have

$$\int \frac{d}{dx} (uv) dx = \int \frac{du}{dx} v - \frac{dv}{dx} u dx$$
$$= \int \frac{du}{dx} v dx - \int \frac{dv}{dx} u dx.$$

Thus, we get

$$\int u \, dv = uv - \int v \, du.$$

In the case where our integrals are definite, we have

$$\int_a^b u \, dv = uv \Big|_a^b - \int_a^b v \, du.$$

We say  $uv|_a^b$  is the boundary term (or surface term). VII

VICitation needed.

VIIWe can also use integration by parts to define the (weak) derivative, assuming the boundary term is zero.

Example.

$$\int xe^{\alpha x} dx = \frac{1}{\alpha}xe^{\alpha x} - \int \frac{1}{\alpha}e^{\alpha x} dx$$

$$= \frac{1}{\alpha}xe^{\alpha x} - \frac{1}{\alpha^2}e^{\alpha x}$$

$$= \frac{1}{\alpha^2}e^{\alpha x} (\alpha x - 1).$$

$$u = x, dv = e^{\alpha x} dx$$

The +C is implicit.

Example.

$$\int \ln x \, dx = x \ln x - \int x \left(\frac{1}{x}\right) \, dx$$

$$= x \ln x - x.$$

$$u = \ln x, \, dv = dx$$

## **Change of Variables**

**Definition** (u-Substitution). Let x = x(u), meaning  $dx = \frac{dx}{du} du$ . Thus, we get

$$\int_{x_1}^{x_2} f(x) du = \int_{u(x_1)}^{u(x_2)} f(x(u)) \frac{dx}{du} du.$$

Example.

$$I_{1} = \int_{0}^{\infty} xe^{-\alpha x^{2}} dx$$

$$= \frac{1}{2} \int_{0}^{\infty} e^{-\alpha u} du$$

$$= \frac{1}{2a}$$

$$= \frac{1}{2a}$$

Example.

$$\int_0^{\pi} \sin \theta \, d\theta = \int_{-1}^1 du$$

$$= 2.$$

More generally, we have, for  $f(\theta) = f(\cos \theta)$ ,

$$\int_0^{\pi} f(\theta) \sin \theta \ d\theta = \int_{-1}^1 f(u) \ du.$$

Example (Trig Substitution).

$$\int_0^\alpha \frac{x}{x^2 + \alpha^2} dx = \int_0^{\pi/4} \frac{\alpha^2 \tan \theta \sec^2 \theta}{\alpha^2 (1 + \tan^2 \theta)} d\theta$$

$$= \int_0^{\pi/4} \tan \theta d\theta$$

$$= -\ln(\cos \theta)|_0^{\pi/4}$$

$$= \ln(\sqrt{2})$$

$$= \frac{1}{2} \ln(2).$$

**Example** (Trig Substitution 2.0). For rational functions of  $\sin \theta$  and  $\cos \theta$ , we can use the half-angle trig substitution  $u = \tan(\theta/2)$ . VIII This yields

$$d\theta = \frac{2du}{1 + u^2}$$
$$\sin \theta = \frac{2u}{1 + u^2}$$
$$\cos \theta = \frac{1 - u^2}{1 + u^2}.$$

For instance,


$$\int \frac{1}{1+\cos\theta} d\theta = \int \frac{1}{1+\frac{1-u^2}{1+u^2}} \frac{2}{1+u^2} du$$

$$= \int du$$

$$= \tan(\theta/2)$$

$$= \frac{\sin\theta}{1+\cos\theta}.$$

Example (Dimensionless Integrals).



Anything that has a nonzero absolute temperature radiates some energy. In particular, we want to know how this radiation is distributed among various wavelengths.

For a box of photons in equilibrium at temperature T, the energy per volume per wavelength  $\lambda^{IX}$  is

$$u\left(\lambda\right)=\frac{8\pi hc}{\lambda^{5}\left(e^{hc/\lambda kT}-1\right)}.$$

Here, h denotes Planck's constant, c is the speed of light, and k is Boltzmann's constant.

 $v^{\text{III}} tan(\theta/2) = \frac{\sin \theta}{1 + \cos \theta}$ 

read as (energy per volume) per wavelength

In order to find the total energy density, we have to integrate  $u(\lambda)$  over all possible values of  $\lambda$ :

$$U = \int_0^\infty u(\lambda) d\lambda$$
$$= 8\pi hc \int_0^\infty \frac{1}{\lambda^5 (e^{hc/\lambda kT} - 1)} d\lambda$$

This integral is, for lack of a better word, hard. However, if we remove the dimensions of  $\lambda$  by substituting  $x = \frac{hc}{\lambda kt}$ , we can verify that the value of U now becomes

$$U = 8\pi hc \left(\frac{kT}{hc}\right)^4 \underbrace{\int_0^\infty \frac{x^3}{e^x - 1} dx}_{\text{scalar}}.$$

Thus, all the physics<sup>x</sup> is captured as a coefficient on the integral; namely, this integral captures the Stefan–Boltzmann law, which has that energy density scales by T<sup>4</sup>.

Using some fancy techniques we will learn later, we can evaluate

$$\int_0^\infty \frac{x^3}{e^x - 1} \, \mathrm{d}x = \frac{\pi^4}{15}.$$

#### Even/Odd

**Definition** (Even and Odd Functions). A function f(x) is

- even if f(-x) = f(x);
- odd if f(-x) = -f(x).

Just as a matrix can be decomposed into a sum of a symmetric and antisymmetric matrix, we can decompose a function into a sum of an even function and an odd function.

Integrals over symmetric intervals on functions with definite parity are very simple:

$$\int_{-\alpha}^{\alpha} f(x) dx = \begin{cases} 2 \int_{0}^{\alpha} f(x) dx & \text{f odd} \\ 0 & \text{f even} \end{cases}.$$

For the case of a function g(x) = g(|x|), we have

$$\int_{-a}^{b} g(|x|) dx = \int_{-a}^{0} g(-x) dx + \int_{0}^{b} g(x) dx.$$

#### **Products and Powers of Sines and Cosines**

**Example.** If we have an integral

$$\int \sin(3x)\cos(2x) \, dx = \frac{1}{2} \int \sin(5x) + \sin(x) \, dx$$
$$= \frac{1}{2} \left( -\frac{1}{5}\cos(5x) - \cos(x) \right).$$

xWho cares about that stuff?

**Example.** To evaluate

$$\int \sin^2(x) dx,$$
$$\int \cos^2(x) dx$$

we use the identity

$$\sin^{2}(x) = \frac{1}{2} (1 - \cos(2x))$$
$$\cos^{2}(x) = \frac{1}{2} (1 + \cos(2x)),$$

and take

$$\int \sin^2(x) \, dx = \frac{1}{2} \int (1 - \cos(2x)) \, dx$$
$$= \frac{x}{2} - \frac{1}{4} \sin(2x)$$
$$\int \cos^2(x) \, dx = \frac{1}{2} \int (1 + \cos(2x)) \, dx$$
$$= \frac{x}{2} + \frac{1}{4} \sin(2x).$$

Thus, we can see that

$$\int_0^{\pi} \sin^2(x) \, dx = \frac{\pi}{2}$$

$$\int_0^{\pi} \cos^2(x) \, dx = \frac{\pi}{2}$$

## **Axial and Spherical Symmetry**

Consider a function of the form  $f(x, y) = x^2 + y^2$ . If we were to integrate with respect to dxdy, we would need a two dimensional integral. With polar coordinates, though, we would have dxdy = rdrd $\phi$ . Since f is axially symmetric, we would have our dxdy =  $2\pi rdr$ , which is a one-dimensional integral.

If we have something with spherical symmetry, then there is no dependence on either  $\theta$  or  $\varphi$ , yielding a function  $f(\mathbf{r}) = f(r)$ , meaning

$$\int f(\mathbf{r}) \ d\tau = \int f(r)r^2 \sin\theta \ dr d\theta d\varphi$$
 
$$= 4\pi \int f(r)r^2 \ dr.$$

Note that  $\int \sin \theta \ d\theta d\phi$  over the sphere is  $4\pi$ .

**Example.** Consider a surface S with charge density  $\sigma(\mathbf{r})$ . Finding the total charge requires evaluating

$$Q = \int_{S} \sigma(\mathbf{r}) dA.$$

If S is hemispherical with z > 0 with radius R, and  $\sigma = k \frac{x^2 + y^2}{R^2}$ , the integrand is axially symmetric.

Using spherical coordinates, we evaluate

$$Q = \int_{S} \sigma(\mathbf{r}) dA$$

$$= \frac{k}{R^{2}} \int x^{2} + y^{2} dA$$

$$= \frac{k}{R^{2}} \int \left( R^{2} \sin^{2}\theta \cos^{2}\phi + R^{2} \sin^{2}\theta \sin^{2}\phi \right) R^{2} \sin\theta d\theta d\phi$$

$$= kR^{2} \int_{S} \sin^{3}\theta d\theta d\phi$$

$$= 2\pi kR^{2} \int_{0}^{\pi/2} \sin^{3}\theta d\theta$$

$$= \frac{4\pi kR^{2}}{3}.$$

#### Example. Let

$$\Phi(\mathbf{r}) = \int \frac{e^{-i\mathbf{k}\cdot\mathbf{r}}}{(2\pi)^3 \|\mathbf{k}\|^2} d^3k$$

where k-space is an abstract 3-dimensional Euclidean space. In Cartesian coordinates,  $d^3k = dk_x dk_y dk_z$ , which yields the integral

$$\Phi(\mathbf{r}) = \int \frac{e^{-ik_x x} e^{-ik_y y} e^{-ik_z z}}{(2\pi)^3 (k_x^2 + k_u^2 + k_z^2)} dk_x dk_y dk_z.$$

This integral is very hard to evaluate (over Cartesian coordinates, anyway), XI so we need to use some other methods.

In spherical coordinates, we have  $d^3k = k^2dkd\Omega$ , yielding

$$\Phi(\mathbf{r}) = \frac{1}{(2\pi)^3} \int k^2 \frac{e^{-ikr\cos\theta}}{k^2} dkd(\cos\theta) d\phi.$$

Since we are summing away all our k-dependence, we can orient r along the  $k_z$  axis. Thus, we can evaluate the integral as

$$\Phi(\mathbf{r}) = \frac{1}{(2\pi)^3} \int k^2 \frac{e^{-ikr\cos\theta}}{k^2} dkd(\cos\theta) d\phi$$

$$= \frac{1}{(2\pi)^2} \int_{-1}^1 \int_0^\infty e^{-ikr\cos\theta} dkd(\cos\theta)$$

$$= \frac{1}{(2\pi)^2} \int \frac{1}{(-ikr)} \left( e^{-ikr} - e^{ikr} \right) dk$$

$$= \frac{1}{(2\pi)^2} \int_0^\infty \frac{2\sin(kr)}{kr} dk$$

$$= \frac{1}{2\pi^2} \int_0^\infty \frac{\sin(kr)}{kr} dk.$$

In order to evaluate the sinc integral, we have to use some different techniques.

XICitation needed.

#### Differentiation with Respect to a Parameter

Example. We can evaluate

$$\int xe^{\alpha x} dx = \frac{\partial}{\partial a} \left( \int e^{\alpha x} dx \right)$$
$$= \frac{\partial}{\partial a} \left( \frac{1}{a} e^{\alpha x} \right)$$
$$= -\frac{1}{a^2} e^{\alpha x} + \frac{1}{a} x e^{\alpha x}$$
$$= \frac{1}{a^2} e^{\alpha x} (\alpha x - 1)$$

When differentiating with respect to a parameter, it is important to remember that we are often differentiating with respect to the parameter, not with respect to our main variable.

**Example** (Introducing a Parameter). We wish to solve the sinc integral,

$$\int_0^\infty \frac{\sin x}{x} \, dx.$$

In order to do this, we will introduce a parameter such that differentiation will cancel out the x in the denominator:

$$J(\alpha) = \int_0^\infty e^{-\alpha x} \frac{\sin x}{x} dx.$$
  $\alpha > 0$ 

In particular,  $\alpha > 0$ . We calculate

$$\frac{dJ}{d\alpha} = -\int_0^\infty e^{-\alpha x} \sin x \, dx$$
$$= -\frac{1}{1 + \alpha^2}.$$

Therefore,

$$J(\alpha) = -\int \frac{1}{\alpha^2} d\alpha$$
$$= -\arctan(\alpha) + C.$$

In order to determine the value of C, we need to make sure  $J(\infty)=0$ . Therefore,  $C=\frac{\pi}{2}$ . Therefore, we have

$$J(0) = \frac{\pi}{2}.$$

#### **Gaussian Integral**

We cannot evaluate  $I_0 = \int_0^\infty e^{-\alpha x^2} dx$  using elementary methods, because  $e^{-\alpha x^2}$  is not an elementary function. The reason we care a lot about  $e^{-\alpha x^2}$  is because it is very important in quantum mechanics and statistics. XII

It is clear that  $I_0$  converges. We can see that the dimension of a is  $x^{-2}$ , and since we are integrating with respect to dx, we can see that our integral is related to  $\frac{1}{\sqrt{a}}$ .

XIIWho cares about that?

**Example.** We will not solve for  $I_0$ , but for  $I_0^2$ . Thus, we have

$$\begin{split} &I_0^2 = \left(\frac{1}{2} \int_{-\infty}^{\infty} e^{-\alpha x^2} \, dx\right) \left(\frac{1}{2} \int_{-\infty}^{\infty} e^{-\alpha y^2} \, dy\right) \\ &= \frac{1}{4} \int_{-\infty}^{\infty} \int_{-\infty}^{\infty} e^{-\alpha (x^2 + y^2)} \, dx dy \\ &= \frac{1}{4} \int_{0}^{2\pi} \int_{0}^{\infty} r e^{-\alpha r^2} \, dr d\phi \\ &= \frac{\pi}{2} \int_{0}^{\infty} r e^{-\alpha r^2} \, dr \\ &= \frac{\pi}{2} \left(\frac{1}{2} \int_{0}^{\infty} e^{-\alpha u} \, du\right) \\ &= \frac{\pi}{4\alpha}. \end{split}$$

Therefore,  $I_0 = \frac{1}{2} \sqrt{\frac{\pi}{\alpha}}$ .

**Definition** (Family of Gaussian Integrals).

$$I_n = \int_0^\infty x^n e^{-\alpha x^2} dx.$$

It is important to note that there are different expressions for the Gaussian integral:

$$\int e^{-\alpha x^2} dx$$

$$\int e^{-\alpha^2 x^2} dx$$

$$\int e^{-\alpha^2 x^2/2} dx$$

$$\int e^{-x^2/\alpha} dx$$

$$\int e^{-x^2/\alpha^2} dx$$

meaning we have to be careful when evaluating these integrals.

**Example** (Error Function). Consider the integral

$$\int_0^{53} e^{-\alpha x^2} \, \mathrm{d}x.$$

Unfortunately, there is no way to do this integral analytically. It is only able to be calculated numerically.

We define

$$\operatorname{erf}(\mathbf{u}) = \int_0^{\mathbf{u}} e^{-ax^2} \, \mathrm{d}x$$

Completing the Square

Example. Consider the integral

$$\int_{-\infty}^{\infty} e^{-ax^2 - bx} dx.$$

This integral is Gaussian-esque, but it isn't fully Gaussian, yet.

To do this, we will complete the square:

$$ax^{2} + bx = a\left(x^{2} + \frac{b}{a}x\right)$$

$$= a\left(x^{2} + \frac{b}{a}x + \frac{b^{2}}{4a^{2}} - \frac{b^{2}}{4a^{2}}\right)$$

$$= a\left(x + \frac{b}{2a}\right)^{2} - \frac{b^{2}}{4a}.$$

In particular, this turns the integral into

$$\begin{split} \int_{-\infty}^{\infty} e^{-\alpha x^2 - bx} \ dx &= \int_{-\infty}^{\infty} e^{-\alpha (x + b/2\alpha)^2 + b^2/4\alpha} \ dx \\ &= e^{b^2/4\alpha} \int_{-\infty}^{\infty} e^{-\alpha (x + b/2\alpha)} \ dx \\ &= e^{b^2/4\alpha} \left( \sqrt{\frac{\pi}{a}} \right) \\ &= e^{b^2/4\alpha} \sqrt{\frac{\pi}{a}}. \end{split}$$

#### **Series Expansion**

Consider the integral

$$\int_0^\infty \frac{x^{s-1}}{e^x - 1} \, \mathrm{d}x.$$

This is a very nasty integral, XIII but we will need to know this value because it is useful in statistical mechanics. XIV We want to ensure this converges.

Notice that for large x, the integrand looks like  $e^{-x}x^{s-1}$ .

**Example.** To resolve the integral we take

$$\int_0^\infty \frac{x^{s-1}}{e^x - 1} \, dx = \int_0^\infty \frac{e^{-x} x^{s-1}}{1 - e^{-x}} \, dx$$

We will use the geometric series expansion for the denominator:

$$= \int_0^\infty e^{-x} x^{s-1} \sum_{k=0}^\infty e^{-kx} dx$$
$$= \sum_{k=0}^\infty \int_0^\infty x^{s-1} e^{-(k+1)x} dx.$$

We make the change of variables u = (n + 1)x.

$$= \sum_{n=0}^{\infty} \frac{1}{(n+1)^s} \int_0^{\infty} u^{s-1} e^{-u} \ du$$

XIIICitation needed.

xIVOkay actually I do kinda care about this.

$$= \underbrace{\sum_{n=1}^{\infty} \frac{1}{n^s}}_{\zeta(s)} \underbrace{\int_0^{\infty} u^{s-1} e^{-u} \ du}_{\Gamma(s)}.$$

Thus, our integral resolves to

$$\int_0^\infty \frac{x^{s-1}}{e^x - 1} \, \mathrm{d}x = \Gamma(s) \zeta(s).$$

#### **Partial Fractions**

Example (A Partial Fraction Decomposition).

$$\frac{1}{1-x^2} = \frac{\alpha}{1-x} + \frac{\beta}{1+x}$$
$$= \frac{1/2}{1-x} + \frac{1/2}{1+x}.$$

Example (Integrating using Partial Fractions). To evaluate

$$\int \frac{4-2x}{(x^2+1)(x-1)^2} \, dx,$$

we do the partial fraction decomposition to find

$$\int \frac{4-2x}{(x^2+1)(x-1)^2} dx = \int \frac{2x+1}{x^2+1} + \frac{-2}{x-1} + \frac{1}{(x-1)^2} dx.$$

**Example** (Mean Value Theorem). If we have a function f defined on [a,b], then there is a point  $c \in (a,b)$  such that

$$f(c)(b-a) = \int_a^b f(x) dx.$$

More generally, the mean value theorem says there exists  $c \in (a, b)$  such that

$$\int_{a}^{b} f(x)g(x) dx = f(c) \int_{a}^{b} g(x) dx$$

#### **Delta Distribution**

Consider a "function"  $\delta(x)$  such that

$$\int_{-\infty}^{\infty} f(x)\delta(x-\alpha) dx = f(\alpha).$$

This idea seems absurd on its face — after all, singletons have measure zero, so the idea of an integral collapsing into a single point doesn't sound normal.

The structure of the delta distribution is

$$\delta(x - a) = \begin{cases} +\infty & x = a \\ 0 & \text{else} \end{cases}.$$

In particular, we also have to define

$$\int_{-\infty}^{\infty} \delta(x - a) \ dx = 1.$$

This is known as the Dirac delta function (or rather, distribution). The delta distribution "weights" f to infinity at x = a and zero everywhere else.

**Example** (Delta Distribution as a Limit). Imagine a Gaussian function with area under the curve 1. In particular,

$$f_n(x) = \frac{1}{\sqrt{\pi}} n e^{-n^2 x^2}.$$

In particular, we have

$$\delta(x) = \lim_{n \to \infty} \frac{1}{\sqrt{\pi}} n e^{-n^2 x^2}$$

**Example** (A Physical Example). Imagine a ball is kicked. The force is dependent on time, F(t).

There isn't an easy to find the force, but by Newton's second law, we have

$$\delta p = \int F(t) dt,$$

where

$$I \equiv \int F(t) dt$$

is the impulse.

If we want to model F(t), where we don't care about a nonzero time over which the force is occurring, we can simply state F(t) as

$$F(t) = \Delta p \delta(t - t_0).$$

Taking this integral yields I.

**Example** (Fourier Integral Representation of Delta Distribution). A different representation of  $\delta(x)$  is

$$\delta(x) = \frac{1}{2\pi} \int_{-\infty}^{\infty} e^{ikx} dk.$$

We are superimposing all the waves  $e^{ikx}$  — in particular, for all values of  $k \neq 0$ , both  $e^{ikx}$  and  $e^{-ikx}$  are "added" together, yielding absolute destructive interference.

The factor of  $\frac{1}{2\pi}$  is necessary to normalize the integral.

#### Properties of the Delta Distribution

#### Normalization:

$$\int_{-\infty}^{\infty} \delta(x) dx = 1$$

$$\int_{x_1}^{x_2} \delta(x - \alpha) dx = \begin{cases} 1 & x_1 < \alpha < x_2 \\ 0 & \text{else} \end{cases}.$$

Sieve:

$$\int_{x_1}^{x_2} f(x)\delta(x-\alpha) dx = \begin{cases} f(\alpha) & x_1 < \alpha < x_2 \\ 0 & \text{else} \end{cases}.$$

Example (Delta Distribution as a Limit of Rectangles). We define the family of functions

$$\phi_k(x) = \begin{cases} k/2 & |x| < 1/k \\ 0 & |x| > 1/k \end{cases}.$$

We can see that integrating  $\phi_k$  over  $\mathbb{R}$  yields 1 for each k.

We now need to evaluate if  $\lim_{k\to\infty} \phi_k(x) = \delta(x)$ . In order to see this, we take

$$\lim_{k \to \infty} \int_{-\infty}^{\infty} f(x) \varphi_k(x) dx = \lim_{k \to \infty} \frac{k}{2} \int_{-1/k}^{1/k} f(x) dx$$

$$= \lim_{k \to \infty} f(c_k) \left( \frac{k}{2} \int_{-1/k}^{1/k} dx \right)$$

$$= \lim_{k \to \infty} f(c_k),$$

where we define  $c_k$  from the mean value theorem. In particular, since  $c_k \in (-1/k, 1/k)$ , it is the case that  $c_k \to 0$  as  $k \to \infty$ , so

$$\lim_{k \to \infty} \int_{-\infty}^{\infty} f(k) \phi_k(x) dx = \lim_{k \to \infty} f(c_k)$$
$$= f(0).$$

Thus,  $\lim_{k\to\infty} \phi_k(x) = \delta(x)$ .

We can imagine the delta distribution to be the density distribution of a single point.

The units of  $\delta(x)$  are

$$[\delta(x)] = x^{-1}.$$

**Example** (Linear Argument for  $\delta$ ). Consider  $\delta(\alpha x)$ . For instance, we want to evaluate

$$\int_{-\infty}^{\infty} f(x)\delta(\alpha x) dx.$$

To do so, we use u substitution with u = ax:

$$\int_{-\infty}^{\infty} f(x)\delta(\alpha x) dx = \frac{1}{\alpha} \int_{-\infty}^{\infty} f(u/\alpha) \delta(u) du$$
$$= \frac{1}{\alpha} f(0).$$

It is important to note that the integration variable dx and the argument of  $\delta(x)$  must be equal.

In general, we have

$$\delta(\alpha x) = \frac{1}{|\alpha|} \delta(x).$$

**Example** (Function Argument for  $\delta$ ). We now want to evaluate

$$\int_{-\infty}^{\infty} f()\delta(g(x)) dx.$$

When we take the change of variables, we have

$$\int_{y_1}^{y_2} f(y)\delta(y) \ dy = \int_{x_1}^{x_2} f(g(x))\delta(g(x)) \left| \frac{dg}{dx} \right| \ dx.$$

Therefore, we must have  $\delta(g(x)) = \frac{1}{|dg/dx|_{g(x)=0}} \delta(x)$ .

In the general case, we have

$$\delta(g(x)) = \frac{1}{|dg/dx|_{x_0}} \delta(x - x_0)$$

where  $g(x_0) = 0$ .

If, in the region of integration, g takes multiple zeros, we must take a sum:

$$\delta(g(x)) = \sum_{i} \frac{1}{|dg/dx|_{x_i}} \delta(x_i);$$

where we assume  $\left|\frac{dg}{dx}\right|_{x_i} \neq 0$ .

**Example** ( $x^2 - a^2$  Argument for  $\delta$ ). Consider the distribution

$$\delta(x^2-a^2)$$
.

The derivative of g(x) is 2x; the two zeros of g are at  $x = \pm a$ . Therefore,

$$\delta(x^2 - a^2) = \frac{1}{|2x|_a} \delta(x - a) + \frac{1}{|2x|_{-a}} \delta(x + a)$$
$$= \frac{1}{2a} \left(\delta(x - a) + \delta(x + a)\right).$$

For example, if we took

$$\int_{-\infty}^{\infty} x^3 \delta \left( x^2 - a^2 \right) dx = \frac{1}{2a} \int_{-\infty}^{\infty} x^3 \left( \delta(x - a) + \delta(x + a) \right) dx$$
$$= \frac{1}{2a} \left( a^3 + (-a)^3 \right)$$
$$= 0.$$

Now, evaluating

$$\int_0^\infty x^3 \left( \delta \left( x^2 - a^2 \right) \right) dx = \frac{1}{2a} \int_0^\infty x^3 \left( \delta (x - a) + \delta (x + a) \right) dx$$
$$= \frac{1}{2a} \left( a^3 \right)$$
$$= \frac{1}{2} a^2.$$

**Example** ((Weak) Derivative of  $\delta$ ). Obviously we cannot formally take  $\delta'(x)$ , but we can always place  $\delta(x)$  under the integral sign and treat  $\delta'(x)$  as the "derivative" via integration by parts:

$$\int_{-\infty}^{\infty} f(x)\delta'(x) dx = f(x)\delta(x)\Big|_{-\infty}^{\infty} - \int_{-\infty}^{\infty} \frac{df}{dx}\delta(x) dx$$
$$= -\frac{df}{dx}\Big|_{0}$$


$$= -f'(0).$$

The "identity" for the delta function's derivatives is

$$f(x)\delta'(x) = -f'(x)\delta(x).$$

**Example** (Heaviside Step Function). The Heaviside step function,  $\Theta(x)$ , is

$$\Theta(x) = \begin{cases} 0 & x < 0 \\ 1 & x > 0. \end{cases}$$



Example (Higher Dimension Delta Distributions). In higher dimensions,

$$\int_{\text{all space}} \delta(\mathbf{r}) \ d\tau = 1,$$

and

$$\int_V f(\mathbf{r}) \, \delta(\mathbf{r} - \mathbf{a}) \ d\tau = \begin{cases} f(\mathbf{a}) & \mathbf{a} \in V \\ 0 & \text{otherwise} \end{cases}.$$

One of the common notations for higher dimensional delta functions is  $\delta^{(n)}(\mathbf{r})$ , where (n) denotes the dimension (not to be confused with nth derivative).

Instead, we can use  $\delta(\mathbf{r})$ , which lets us know that we are dealing in higher dimensions, and context is evident.

**Example** (Voltage under a Point Charge). The voltage of a point charge q at a position **a** is given by Coulomb's law

$$\Phi(\mathbf{r}) = \frac{\mathsf{q}}{4\pi\epsilon_0} \frac{1}{|\mathbf{r} - \mathbf{a}|},$$

with  $\Phi = 0$  at  $\infty$ .

For a continuous point charge distribution  $\rho$  ( $\mathbf{r}$ ), we consider each element of the volume  $d\tau$  centered at  $\mathbf{r}$  with charge  $d\mathbf{q} = \rho$  ( $\mathbf{r}$ )  $d\tau$ .

$$\begin{split} d\Phi\left(\mathbf{r}\right) &= \frac{dq}{4\pi\epsilon_{0}} \frac{1}{|\mathbf{r} - \mathbf{a}|} \\ &= \frac{1}{4\pi\epsilon_{0}} \frac{\rho\left(\mathbf{r}\right) d\tau}{|\mathbf{r} - \mathbf{a}|}. \end{split}$$

In particular, for some  $\mathbf{r}$ , we need to add up over  $\mathbf{a}$ , yielding

$$\Phi\left(\mathbf{r}\right) = \frac{1}{4\pi\epsilon_{0}} \int_{V} \frac{\rho\left(\mathbf{r}'\right)}{|\mathbf{r} - \mathbf{r}'|} d\tau'$$

This expression should hold for every physically reasonable volume charge distribution  $\rho$ , what  $\rho$  ( $\mathbf{r}$ ) denotes a point charge?

In particular, if  $\rho(\mathbf{r})$  is a point charge, then  $\rho = q\delta(\mathbf{r} - \mathbf{a})$ .

**Example** (Using the Multi-Dimensional Delta Distribution). In Cartesian coordinates, we have

$$\delta(\mathbf{r} - \mathbf{r}_0) = \delta(x - x_0) \, \delta(y - y_0) \, \delta(z - z_0) \,.$$

If we want to transform  $\delta(\mathbf{r} - \mathbf{r}_0)$  into a different coordinate system such as  $d\tau = du \, dv \, dw$ , we need the Jacobian. Thus,

$$\delta(\mathbf{r} - \mathbf{r}_0) = \frac{1}{|\mathsf{I}|} \delta(\mathsf{u} - \mathsf{u}_0) \, \delta(\mathsf{v} - \mathsf{v}_0) \, \delta(\mathsf{w} - \mathsf{w}_0) \,.$$

For instance, in spherical coordinates, we have

$$\begin{split} \delta(\mathbf{r} - \mathbf{r}_0) &= \frac{1}{r^2 \sin \theta} \delta(\mathbf{r} - \mathbf{r}_0) \, \delta(\theta - \theta_0) \, \delta(\varphi - \varphi_0) \\ &= \frac{1}{r^2} \delta(\mathbf{r} - \mathbf{r}_0) \, \delta(\cos \theta - \cos \theta_0) \, \delta(\varphi - \varphi_0) \,. \end{split}$$

## **Vector Calculus**

**Question:** What is a vector?

**Answer:** A vector is an element of a vector space.

Remark: Yes, vectors as defined by "magnitude and direction" also are elements of vector spaces.

For the purposes of this unit, we will focus on vectors in the vector space  $\mathbb{R}^n$  over  $\mathbb{R}$ .

Notation: Vector-valued functions with vector-valued outputs will be denoted

 $\mathbf{F}(\mathbf{r})$ .


#### **Vector Fields**

**Definition** (Vector Field). A vector-valued function  $\mathbf{F}(\mathbf{r})$  with vector-valued outputs is known as a vector field.

**Example.** The field

$$\mathbf{F}(x, y, z) = x\hat{\mathbf{i}} + y\hat{\mathbf{j}} + z\hat{\mathbf{k}}$$

can be seen below.



Notice that, in terms of spherical coordinates,  $\mathbf{F}(x, y, z) = r\hat{\mathbf{r}} = \mathbf{r}$ .

**Definition** (Incompressible Fluid). A fluid is incompressible if its density is constant.

In particular, incompressible fluids cannot have either sources or sinks, since sources imply a local reduction in density, while sinks imply a local increase in density.

**Example.** Consider a sprinkler with N streams. Since water is incompressible, the density of streamlines  $\sigma$  and the surface area of the spherical shells, A must be inversely proportional to each other.



Thus, we have

$$N = \sigma A$$
,

meaning  $\sigma \sim \frac{1}{r^2}$  since  $A \sim r^2.$ 

In particular, the strength of the vector field must diminish with the square of the distance.



**Example.** Vector fields can be added.



**Example.** Consider the field

$$\mathbf{G}(x,y) = \frac{1}{\sqrt{x^2 + y^2}} \left( -y\hat{\mathbf{i}} + x\hat{\mathbf{j}} \right)$$

As depicted, we can see that the vector field looks as follows.

In particular, we can see that  $G = \hat{\phi}$ .

Notice that our vector fields are dependent on both the basis and the coordinate system.

In particular, we have reason to prefer a Cartesian basis over the polar or spherical basis, since the Cartesian basis is position-independent.

# Gradient, Divergence, and Curl

## The ∇ Operator

Consider a scalar function  $f(\mathbf{r})$ . If we want to imagine how f changes as we move  $\mathbf{r}$  to  $\mathbf{r} + d\mathbf{r}$ , we use the chain rule.

$$df = \left(\frac{\partial f}{\partial x}\right) dx + \left(\frac{\partial f}{\partial y}\right) dy + \left(\frac{\partial f}{\partial z}\right) dz$$
$$= \left(\frac{\partial f}{\partial x}\right) \left(\frac{\partial f}{\partial y}\right) \left(\frac{\partial f}{\partial z}\right)$$
$$= \nabla f \cdot d\mathbf{r}$$

In particular, we define

$$\nabla f = \frac{\partial f}{\partial x}\hat{i} + \frac{\partial f}{\partial y}\hat{j} + \frac{\partial f}{\partial z}\hat{k}.$$

Notice that, since  $dx\hat{i} + dy\hat{j} + dz\hat{k}$  is a vector, and df is a scalar, we know that  $\nabla f$  *must* be a vector.

**Definition** (Gradient).

$$\nabla f = \frac{\partial f}{\partial x} \hat{i} + \frac{\partial f}{\partial y} \hat{j} + \frac{\partial f}{\partial z} \hat{k}$$
$$df = |\nabla f| |d\mathbf{r}| \cos \theta.$$

If  $\nabla f$  is in the direction of d**r**, then  $\cos \theta = 1$ , meaning df is maximized. In particular,  $\nabla f$  points in the direction of maximum change in f.

In particular, this means that for every (differentiable) scalar field, there is a natural vector field associated with the direction of largest increase.

**Example.** The electric field

$$\mathbf{E} = -\nabla \mathbf{V}$$
.

Similarly, for any given potential U,

$$\mathbf{F} = -\nabla \mathbf{U}$$
.

**Definition** (The  $\nabla$  Operator).

$$\nabla f = \begin{pmatrix} \frac{\partial f}{\partial x} \\ \frac{\partial f}{\partial y} \\ \frac{\partial f}{\partial z} \end{pmatrix}$$
$$= \begin{pmatrix} \frac{\partial}{\partial x} \\ \frac{\partial}{\partial y} \\ \frac{\partial}{\partial z} \end{pmatrix} (f)$$

Thus, we get

$$\nabla \equiv \frac{\partial}{\partial x}\hat{\mathbf{i}} + \frac{\partial}{\partial y}\hat{\mathbf{j}} + \frac{\partial}{\partial z}\hat{\mathbf{k}}.$$

## Example.

(1) For some scalar field  $f(\mathbf{r})$ , we can take

$$\nabla (\mathbf{f}) = \nabla \mathbf{f}$$

which yields the gradient field.

(2) For some vector field **E**, we can take

$$\nabla \cdot \mathbf{E} = \mathbf{q}$$

which yields a scalar field known as the divergence of E.

In particular,

$$\nabla \cdot \mathbf{E} = \frac{\partial}{\partial x} \left( \mathbf{E} \cdot \hat{\mathbf{i}} \right) + \frac{\partial}{\partial y} \left( \mathbf{E} \cdot \hat{\mathbf{j}} \right) + \frac{\partial}{\partial z} \left( \mathbf{E} \cdot \hat{\mathbf{k}} \right).$$

(3) For some vector field **B**, we can take

$$\nabla \times \mathbf{B} = \mathbf{A}$$
,

which yields a vector field known as the curl of **B**.

(4)

$$\nabla \cdot (\nabla f) = (\nabla \cdot \nabla) f$$

$$= \frac{\partial^2 f}{\partial x^2} + \frac{\partial^2 f}{\partial y^2} + \frac{\partial^2 f}{\partial z^2}$$

$$= \nabla^2 f$$

$$= \Delta f,$$

which yields an operator known as the Laplacian.

**Example.** Let  $\mathbf{v}_1 = xy\hat{\mathbf{i}} + y^2\hat{\mathbf{j}}$ . Then,

$$\nabla \cdot \mathbf{v}_1 = \frac{\partial}{\partial x} (xy) + \frac{\partial}{\partial y} (y^2)$$
$$= y + 2y$$
$$= 3y,$$

and

$$\nabla \times \mathbf{v}_1 = \left(\frac{\partial}{\partial x} \left( y^2 \right) - \frac{\partial}{\partial y} \left( xy \right) \right) \hat{\mathbf{k}}$$
$$= -x \hat{\mathbf{k}}.$$

**Example.** Let  $\mathbf{v}_2 = \frac{1}{x^2 + y^2 + z^2} \left( x \hat{\mathbf{i}} + y \hat{\mathbf{j}} + z \hat{\mathbf{k}} \right)$ . Then,

$$\nabla \cdot \mathbf{v}_2 = \frac{\partial}{\partial x} \left( \frac{x}{x^2 + y^2 + z^2} \right) + \frac{\partial}{\partial y} \left( \frac{y}{x^2 + y^2 + z^2} \right) + \frac{\partial}{\partial z} \left( \frac{z}{x^2 + y^2 + z^2} \right)$$
$$= \frac{1}{x^2 + y^2 + z^2} \nabla \times \mathbf{v}_2$$
$$= 0$$

Example. Consider

$$\mathbf{v} = x^2 \hat{\mathbf{i}} + y^2 \hat{\mathbf{j}} + z^2 \hat{\mathbf{k}}$$
  
$$\mathbf{u} = yz\hat{\mathbf{i}} + zx\hat{\mathbf{j}} + xy\hat{\mathbf{k}}.$$

In particular, it is easily verified that  $\nabla \times \mathbf{v} = 0$  and  $\nabla \cdot \mathbf{u} = 0$ .

## Applying Vector Identities to the $\nabla$ Operator

We are aware that

$$\mathbf{a}\mathbf{V} = \mathbf{V}\mathbf{a}$$
$$\mathbf{A} \cdot \mathbf{B} = \mathbf{B} \cdot \mathbf{A}.$$

However, when we deal with  $\nabla$ , we have to respect both the properties of the vectors *and* the properties of the operator. In particular,

$$f\nabla \neq \nabla f$$
.

This is because  $f\nabla$  is a vector operator, while  $\nabla f$  is a vector field. Similarly,

$$\nabla \cdot \mathbf{E} \neq \mathbf{E} \cdot \nabla$$
,

since  $\nabla \cdot \mathbf{E}$  is a scalar field, while  $\mathbf{E} \cdot \nabla$  is a scalar operator.

Example (Curl of Curl). Consider

$$\nabla \times (\nabla \times \mathbf{v})$$
.

On first glance, we want to use the identity  $\mathbf{A} \times (\mathbf{B} \times \mathbf{C}) = \mathbf{B} (\mathbf{A} \cdot \mathbf{C}) - \mathbf{C} (\mathbf{A} \times \mathbf{B})$ , yielding

$$\nabla \times (\nabla \times \mathbf{v}) = \nabla (\nabla \cdot \mathbf{v}) - \mathbf{v} (\nabla \cdot \nabla).$$

However, notice that  $\mathbf{v}(\nabla \cdot \nabla)$  is a scalar operator, while  $\nabla \times (\nabla \times \mathbf{v})$  is a vector field. Thus, we have to modify the double cross product to  $\mathbf{A} \times (\mathbf{B} \times \mathbf{C}) = \mathbf{B}(\mathbf{A} \cdot \mathbf{C}) - (\mathbf{A} \times \mathbf{B})\mathbf{C}$ 

$$\nabla \times (\nabla \times \mathbf{v}) = \nabla (\nabla \times \mathbf{v}) - \nabla^2 \mathbf{v}.$$

Example (Curl of Gradient and Divergence of Curl). Consider

$$\nabla \times (\nabla f)$$
.

In particular, we are tempted to take

$$\nabla \times (\nabla f) = (\nabla \times \nabla) f$$
$$= 0.$$

This is allowed, since we do not affect the property of the operation.

The following identity is also true,

$$\nabla \cdot (\nabla \times \mathbf{v}) = 0,$$

but we cannot use a cheesy method to prove this.

**Remark:** Faraday's law is  $\nabla \times \mathbf{E} = 0$ , and Gauss's law for magnetism is  $\nabla \times \mathbf{B} = 0$ , where  $\mathbf{E}$  denotes the electric field and  $\mathbf{B}$  denotes the magnetic field.

If  $\nabla \times E = 0$  in electrostatics, then  $E = \nabla A$  for some scalar function A. In particular, we say  $E = -\nabla V$ . We call V the scalar potential.

Similarly, if  $\nabla \cdot \mathbf{B} = 0$ , then  $\mathbf{B} = \nabla \times \mathbf{A}$  for some vector field  $\mathbf{A}$ . We call  $\mathbf{A}$  the vector potential.

Example (Products). Consider

$$\nabla$$
 (fg).

Using the product rule, we have

$$\nabla (fg) = (\nabla f) g + f(\nabla g).$$

However, when we look at

$$\nabla \cdot (f\mathbf{A})$$
,

things get a little more complicated. Notice that  $\nabla \cdot (f\mathbf{A})$  is a scalar, meaning we apply the product rule using dot products to yield such a scalar.

$$\nabla \cdot (f\mathbf{A}) = \nabla f \cdot \mathbf{A} + f \nabla \cdot \mathbf{A}.$$

Similarly,

$$\nabla \times (\mathbf{A}f) = (\nabla \times \mathbf{A}) f + \nabla f \times \mathbf{A}$$
$$= (\nabla \times \mathbf{A}) f - \mathbf{A} \times \nabla f.$$

## **Changing Coordinates**

Vector equations are fundamentally independent of their coordinate systems. Thus, the established identities in the previous subsection must be valid regardless of the coordinate system.

For instance, we should be able to calculate

$$\nabla \cdot \mathbf{E}$$

regardless of the coordinate system.

Example (Converting to Polar Coordinates). Consider

$$\mathbf{v}_1 = x \mathbf{y} \hat{\mathbf{i}} + \mathbf{y}^2 \hat{\mathbf{j}}.$$

Conversion to polar coordinates yields

$$\mathbf{v}_1 = \left(\mathbf{r}^2 \sin \phi\right) \hat{\mathbf{r}}.$$

Understanding  $\nabla^2$ ,  $\nabla$ , and  $\nabla$ ×

**Example** (Understanding the Laplacian). One of the most important differential equations is the equation for simple harmonic motion:

$$\frac{d^2}{dt^2}f(t) = -\omega^2 f(t).$$

However, this equation does not need to be in time. We can also imagine this oscillation happening in space:

$$\frac{\mathrm{d}^2}{\mathrm{d}x^2} f(x) = -k^2 f(x).$$

This doesn't need to occur in one dimension, though. A reasonable assumption is that what occurs in x should occur in y and z symmetrically.

$$\underbrace{\left(\frac{\partial^{2}}{\partial x^{2}} + \frac{\partial^{2}}{\partial y^{2}} + \frac{\partial^{2}}{\partial z^{2}}\right)}_{\nabla^{2}} f(x, y, z) = -\underbrace{\left(k_{x}^{2} + k_{y}^{2} + k_{z}^{2}\right)}_{\|\mathbf{k}\|^{2}} f(x, y, z).$$

Essentially,  $\nabla^2$  is a measure of the concavity of the function in a particular direction.

In one dimension, if  $\frac{df}{dx}\Big|_{P} = 0$  and  $\frac{d^2f}{dx^2}\Big|_{x=P} < 0$ , we know that f(P) is lower than the average value "around" the point x = P.

**Example** (Understanding the Divergence). If we have a vector field **F** in three dimensions, there are nine different ways to understand a rate of change,  $\partial_i F_i$ .

We start by choosing axes such that  $\mathbf{F}(P) = F_x(P)\hat{\mathbf{i}}$ . Moving along the streamline by dx, a simple linear approximation gives,

$$F_x \left( P + dx \hat{i} \right) = F_x(P) + \frac{\partial F_x}{\partial x} \Big|_{x=P} dx.$$

When we move along the streamline by dx, if  $\frac{\partial F_x}{\partial x}\Big|_{x=P} > 0$ , we see that  $F_x\left(P + dx\hat{i}\right)$  increases. Essentially, this derivative measures the "surge" from point P.

If we look at F by moving along dyj, we find

$$F_y\left(P + dy\hat{j}\right) = \frac{\partial F_y}{\partial y}\Big|_{y=P} dy,$$


since  $F_y(P) = 0$ . If  $\frac{\partial F_y}{\partial y} > 0$ , the streamlines seem to "spread out" from each other.

These derivatives measure how a field "surges" out of a point and how it "spreads" out of a point.

This measure of surge and/or spread has to be axis-independent. All of these have to coincide, meaning the full measure of surge and spread is

$$\nabla \cdot \mathbf{F} = \frac{\partial F_x}{\partial x} + \frac{\partial F_y}{\partial y} + \frac{\partial F_z}{\partial z}.$$

**Example** (Coordinate Dependence of Divergence). The following field represents  $F = \hat{i} + \hat{j}$ , which has zero divergence.



The following field represents  $\mathbf{F} = \hat{\mathbf{r}}$ , which has positive divergence (recall that  $\hat{\mathbf{r}}$  is not position-independent).



**Definition** (Solenoidal Field). A field that has zero divergence is known as a solenoidal or divergence-free field.

Solenoidal fields are useful for modeling incompressible fluids, as incompressible fluids have constant density.

If  $\nabla \cdot \mathbf{F} = 0$ , then  $\mathbf{F} = \nabla \times \mathbf{A}$  for some other vector field  $\mathbf{A}$ . Additionally, since  $\mathbf{F} = \nabla \Phi$  for some scalar field  $\Phi$ , we recover Laplace's equation:

$$\nabla \cdot (\nabla \Phi) = 0$$
$$\nabla^2 \Phi = 0.$$

**Example** (Understanding the Curl). Of the nine combinations  $\partial_i F_j$ , we have used 3 of them via the divergence.

Now, we explore the curl, which is  $\nabla \times \mathbf{F}$ , which gives information about  $\partial_i F_j$  where  $i \neq j$ .

By the definition of the cross product, we have

$$(\nabla \times \mathbf{F})_k = \partial_i F_i - \partial_i F_i$$

where  $i \neq j$ .

Considering water rotating with angular velocity  $\omega$ , we find  $\mathbf{v} = \omega \times \mathbf{r}$ . Now, taking


$$\nabla \times \mathbf{v} = \nabla \times (\mathbf{r} \times \omega)$$
$$= 2\omega.$$

Therefore, curl measures some "swirl" of a given vector field.

**Example** (Fields with Differing Curl). The field  $\mathbf{F} = (x - y)\hat{\mathbf{i}} + (x + y)\hat{\mathbf{j}}$  has positive curl everywhere.



Meanwhile, the field  $\mathbf{F} = (x+y)\,\hat{\mathbf{i}} + (x-y)\,\hat{\mathbf{j}}$  has zero curl everywhere.



## **Integrating Scalar and Vector Fields**

Integration is summation, xv meaning the expression

$$\int_{x_1}^{x_2} f(x) \, dx$$

describes a sum along a unique interval defined by  $x_1$  and  $x_2$ .

When we go to higher dimensions, we first think of

$$\int_{P_1}^{P_2} f(x, y) dx,$$

which wants us to sum f(x, y) from  $P_1 = (x_1, y_1)$  to  $P_2 = (x_2, y_2)$ . However, this is not a fully specific expression — we need a *path* along which we integrate. We specify the path by y = g(x). Now, the integral becomes

$$\int_{P_1}^{P_2} f(x, g(x)) dx.$$

Similarly, for a surface integral

$$\int_{S} f(x,y) dxdy,$$

we need the surface S along which we integrate, where we say z = g(x, y).

However, while there are certain functions that are path-independent,<sup>XVI</sup> we must assume that every function is path-*dependent*.

#### **Line Integrals**

A line integral is a sum over a curve C.

$$\int_{C} f(\mathbf{r}) d\ell.$$

Here,  $d\ell$  denotes the length element along C. For instance, if f denotes the charge density per unit length, and C is a wire, then  $\int_C f(\mathbf{r}) d\ell$ .

If we define C by y = q(x), then the integral is

$$\int_C f(x,y) d\ell = \int_C f(x,g(x)) d\ell.$$

However, we need to figure out how to deal with  $d\ell$  — in particular, we need  $d\ell$  to be an expression only in dx. In particular,  $d\ell$  is given by the Pythagorean theorem:

$$(d\ell)^2 = (dx)^2 + (dy)^2$$
.

Notation: Everyone (else) drops the parentheses:

$$d\ell^2 = dx^2 + du^2.$$

xvkinda

<sup>&</sup>lt;sup>XVI</sup>Holomorphic functions, for instance

Our integral now becomes

$$\int_{C} f(x, g(x)) d\ell = \int_{C} f(x, g(x)) \sqrt{(dx)^{2} + (dy)^{2}}$$
$$= \int_{x_{1}}^{x_{2}} f(x, g(x)) dx \sqrt{1 + \left(\frac{dy}{dx}\right)^{2}}$$

Example. Let

$$f(\mathbf{r}) = \sqrt{\frac{1}{4}x^2 + y^2}$$
  
 $y(x) = \frac{1}{2}x^2$ ,

integrated from 0 < x < 1.

Then,

$$\int_{C} f(\mathbf{r}) d\ell = \int_{0}^{1} \sqrt{\frac{1}{4}x^{2} + \frac{1}{4}x^{4}} \sqrt{1 + \left(\frac{dy}{dx}\right)^{2}} dx$$

$$= \frac{1}{2} \int_{0}^{1} x \sqrt{1 + x^{2}} \sqrt{1 + x^{2}} dx$$

$$= \frac{1}{2} \int_{0}^{1} x \left(1 + x^{2}\right) dx$$

$$= \frac{3}{8}.$$

Note that we can also evaluate this integral as a function of y, and still get the same outcome.

#### Example. Let

$$f(\mathbf{r}) = \sqrt{\frac{1}{4}x^2 + y^2}$$
$$y(x) = x,$$

integrated from 0 < x < 1.

Then,

$$\int_{C} f(\mathbf{r}) d\ell = \int_{0}^{1} \sqrt{\frac{1}{4}x^{2} + x^{2}} \sqrt{1 + \left(\frac{dy}{dx}\right)^{2}} dx$$
$$= \sqrt{\frac{5}{2}} \int_{0}^{1} x dx$$
$$= \sqrt{\frac{5}{8}}.$$

We can also do this in polar coordinates. First, we have

$$(d\ell)^2 = (dr)^2 + r^2 (d\theta)^2.$$

Then,

$$\int_{C} f(\mathbf{r}) d\ell = \int_{0}^{\sqrt{2}} \sqrt{\frac{1}{4} r^{2} \cos^{2} \theta + r^{2} \sin^{2} \theta} dr$$

$$=\sqrt{\frac{5}{8}}.$$

When we integrate with respect to a parametrized curve in one dimension, we have

$$\int_{x_1}^{x_2} f(x) dx = \int_{t(x_1)}^{t(x_2)} f(x(t)) \frac{dx}{dt} dt.$$

In multiple dimensions for c(t) = (x(t), y(t)), we have

$$d\ell = \sqrt{(dx)^2 + (dy)^2}$$
$$= dt \sqrt{\left(\frac{dx}{dt}\right)^2 + \left(\frac{dy}{dt}\right)^2}$$
$$= \left\|\frac{d\mathbf{c}}{dt}\right\|,$$

yielding

$$\int_C f(\textbf{r}) \ d\ell = \int_{t_1}^{t_2} f(x(t),y(t)) \left\| \frac{d\textbf{c}}{dt} \right\| \, dt.$$

## **Surface Integrals**

When we turn to a surface

$$\int_{S} f(\mathbf{r}) dA,$$

we parametrize z = g(x, y) to yield

$$\int_{S} f(x, y, z) dA = \int_{D} f(x, y, g(x, y)) \sqrt{1 + ||\nabla g||^{2}} dxdy,$$

where D is the projection of S onto the x, y-plane.

## Circulation

So far, we have only considered scalar fields, When we look at

$$\int_{C} \mathbf{F}(\mathbf{r}) \ d\ell = \hat{\mathbf{i}} \int_{C} F_{x}(\mathbf{r}) \ d\ell + \hat{\mathbf{j}} \int_{C} F_{y}(\mathbf{r}) \ d\ell + \hat{\mathbf{k}} \int_{C} F_{z}(\mathbf{r}) \ d\ell.$$

More commonly, though, we are interested in

$$\int_{C} \mathbf{F}(\mathbf{r}) \cdot d\vec{\ell},$$

which is a scalar quantity. When we add the dot product into the integral, we signal that we are most interested in the *parallel* component of  $\vec{F}$  to  $d\vec{\ell}$ .

In cartesian coordinates, this integral is equal to

$$\int_{C} \mathbf{F}(\mathbf{r}) \cdot d\vec{\ell} = \int_{C} F_{x} dx + F_{y} dy + F_{z} dz.$$

For a more physical example, xvii this integral is a measure of work if F(r) denotes force. Similarly,

$$\Delta V = -\int_{P_1}^{P_2} \mathbf{E} \cdot d\vec{\ell}$$

xvIIWho cares about that?

**Definition** (Circulation). When we integrate over a closed curve C, our line integral now becomes

$$\Psi = \oint_C \mathbf{F} \cdot d\vec{\ell}$$

**Remark:** It is not always the case that  $\Psi$  is zero.

Summing F along a closed path C measures the net "swirl" of the vector field.

Example (Symmetry in Circulation). Ampère's law says that

$$\oint_C \mathbf{B} \cdot d\vec{\ell} = \mu_0 \mathbf{I},$$

where  $\mu_0$  is the permeability of free space, I denotes current, and **B** is the magnetic field.

Consider the case of a wire with constant radius a and uniform current  $I_0$ . From cylindrical symmetry, it must be the case that **B** forms concentric circles about the wire.

Since Ampère's law says we can *always* pick a curve that yields a constant, we can let C correspond to one of the circles with constant  $\|\mathbf{B}\|$ .

$$\oint_{C} \mathbf{B} \cdot d\vec{\ell} = \oint_{C} \mathbf{B} d\ell$$
$$= \mathbf{B} \oint_{C} d\ell$$
$$= 2\pi r \mathbf{B}.$$

where r is the radius of the loop C.

Note that this value does not depend on the radius of C, but the value of  $\mu_0 I$  does depend on the radius of C.

In particular,

$$I(r < a) = I_0 \frac{r^2}{a^2},$$

yielding

$$\mathbf{B}(\mathbf{r} < \mathbf{a}) = \frac{\mu_0 I_0}{2\pi} \frac{\mathbf{r}}{\mathbf{a}^2} \hat{\mathbf{\phi}}$$
$$\mathbf{B}(\mathbf{r} > \mathbf{a}) = \frac{\mu_0 I_0}{2\pi \mathbf{r}} \hat{\mathbf{\phi}}.$$

Inside the wire, the magnitude of the B field grows linearly with respect to r, and outside, the magnitude of the B field falls off by a factor of  $r^{-1}$ .

However, in the general case, we need to parametrize our line integral.

$$\int_{C} \mathbf{F} \cdot d\vec{\ell} = \int_{t_{1}}^{dt} \left( \mathbf{F} \cdot \frac{d\mathbf{c}}{dt} \right) dt$$

**Example** (Path-Dependence (or Path-Independence) of Work). Let  $\mathbf{B} = x^2y\hat{\mathbf{i}} - xy^2\hat{\mathbf{j}}$ ,  $P_1 = (0,0)$ , and  $P_2 = (1,1)$ . We will calculate the work done by  $\mathbf{B}$  as follows:

$$\int_C \mathbf{B} \cdot d\vec{\ell} = \int_C B_x dx + B_y dy.$$

Along the path  $C_1$ , which goes from (0,0) to (1,0), then (1,0) to (1,1), the work is given by

$$\int_{C} \mathbf{B} \cdot d\vec{\ell} = \int_{C_{1}} x^{2}y \, dx - xy^{2} \, dy$$

$$= \int_{0}^{1} x^{2}y \big|_{y=0} \, dx - \int_{0}^{1} xy^{2} \big|_{x=1} \, dy$$

$$= -\frac{1}{3}.$$

Along the path  $C_2$ , which goes from (0,0) to (1,1) directly, with x = y and dy = dx, we have

$$\int_{C_2} \mathbf{B} \cdot d\vec{\ell} = \int_{C_2} \left( x^2 y - x y^2 \right) \Big|_{y=x} dx$$
$$= 0.$$

Along the path  $C_3$ , defined by  $x = 1 - \cos \theta$  and  $y = \sin \theta$ , we have  $(dx, dy) = (\sin \theta, \cos \theta) d\theta$ , meaning

$$\int_{C_3} \mathbf{B} \cdot d\vec{\ell} = \int_0^{\pi/2} \left( (1 - \cos \theta)^2 \sin \theta \right) \sin \theta \ d\theta - \int_0^{\pi/2} \left( (1 - \cos \theta) \sin^2 \theta \right) \cos \theta \ d\theta$$
$$= \frac{3\pi}{8} - 1.$$

Meanwhile, for  $\mathbf{E} = xy^2\hat{\mathbf{i}} + x^2y\hat{\mathbf{j}}$ , it is the case that

$$\int_{C_1} \mathbf{E} \cdot d\vec{\ell} = \frac{1}{2}$$

$$\int_{C_2} \mathbf{E} \cdot d\vec{\ell} = \frac{1}{2}$$

$$\int_{C_3} \mathbf{E} \cdot d\vec{\ell} = \frac{1}{2}.$$

**Definition** (Path-Independence). Let F(r) be a vector field. If, for every closed path C, it is the case that

$$\oint_C \mathbf{F} \cdot d\vec{\ell} = 0,$$

then we say **F** is path-independent.

If our vector field is path-independent, then we are allowed to pick the path that is easiest to calculate.

If **E** is path-independent, then there has to exist some scalar field  $\Phi$  such that

$$\int_{t_1}^{t_2} \mathbf{E} \cdot d\vec{\ell} = \Phi(t_2) - \Phi(t_1)$$

**Definition** (Equivalent Conditions for Path-Independence). Let  $\mathbf{F}(\mathbf{r})$  be a vector field. Then, the following are equivalent:

- $\oint \int_C \mathbf{F} \cdot d\vec{\ell} = 0$
- $\mathbf{F} = \nabla \Phi$
- $\nabla \times \mathbf{F} = 0$

**Example** (Finding the Scalar Field). Consider  $\mathbf{E} = xy^2\hat{\mathbf{i}} + x^2y\hat{\mathbf{j}}$ . Since  $\mathbf{E}$  has curl 0, we know there must exist some  $\Phi$  such that

$$\frac{\partial \Phi}{\partial x} = xy^2$$

$$\Phi = \frac{1}{2}x^2y^2 + f(y)$$
$$\frac{\partial \Phi}{\partial y} = x^y$$
$$\Phi = \frac{1}{2}x^2y^2 + g(x).$$

Such a  $\Phi$  exists if and only if we can choose f and g to be the same function. Since we can set  $f(y) = g(x) = c \in \mathbb{R}$ , such a  $\Phi$  exists — namely,  $\Phi(x, y) = \frac{1}{2}x^2y^2$ .

Consider  $\mathbf{B} = x^2 y \hat{\mathbf{i}} = xy^2 \hat{\mathbf{j}}$ . We know such a  $\Phi$  must not exist.

$$\frac{\partial \Phi}{\partial x} = x^2 y$$

$$\Phi = \frac{1}{3}x^3 y + f(y)$$

$$\frac{\partial \Phi}{\partial y} = -xy^2$$

$$\Phi = -\frac{1}{3}xy^3 + g(x).$$

There cannot exist such f and g that makes these antiderivatives equal to each other.

**Example** (Gravity). A mass m has a gravitational field

$$\mathbf{g} = -Gm\frac{\hat{\mathbf{r}}}{r^2}.$$

Conventionally, the gravitational potential is the negative of the line integral of **g**, since we want  $\Phi(\infty) = 0$ , yielding

$$\Phi(r) = -\int_{\infty}^{r} \mathbf{g} \cdot d\vec{\ell}$$
$$= Gm \int_{\infty}^{r} \frac{1}{s^{2}} ds$$
$$= -\frac{Gm}{r}.$$

Consider a planet. A planet is a bunch of point masses, which means we orient our focus away from **g** towards d**g**, and m to dm =  $\rho$ d $\tau$ .

However, instead of trying to work out this integral in vector form, we want to find a scalar field  $\Phi$ , then take  $\mathbf{g} = -\nabla \Phi$ .

Let's construct a planet that is a spherical shell at radius  $\alpha$  with mass m. Then,  $\sigma = \frac{m}{4\pi\alpha^2}$  (constant), with the area dA has mass  $dm = \sigma dA$ . Thus, the mass at distance r is

$$d\mathbf{g} = -G \frac{(\mathbf{r} - \mathbf{s})}{\|\mathbf{r} - \mathbf{s}\|^3} \sigma dA.$$

To find the total gravitational field, we find

$$\mathbf{g}(\mathbf{r}) = -G \int_{S} \frac{\mathbf{r} - \mathbf{s}}{\|\mathbf{r} - \mathbf{s}\|^{3}} \sigma \, dA,$$

where the integral with respect to  $\mathbf{s}$  is over the surface.

This vector-valued integral kind of sucks, XVIII so instead, we want to integrate

$$\Phi(\mathbf{r}) = -G \int_{S} \frac{1}{\|\mathbf{r} - \mathbf{s}\|} \sigma \, dA,$$

which is much easier to do. Notice that

$$\|\mathbf{r} - \mathbf{s}\|^2 = \langle \mathbf{r} - \mathbf{s}, \mathbf{r} - \mathbf{s} \rangle$$
$$= \|\mathbf{r}\|^2 + \|\mathbf{s}\|^2 - 2\|\mathbf{r}\| \|\mathbf{s}\| \cos \theta,$$

meaning, with  $\|\mathbf{r}\| = r$  and  $\|\mathbf{s}\| = a$ ,

$$\|\mathbf{r} - \mathbf{s}\| = \sqrt{r^2 + a^2 - 2ra\cos\theta}.$$

Using the area element,  $dA = a^2 d\Omega$ , or  $dA = 2\pi a^2 d(\cos \theta)$ , we get

$$\begin{split} \Phi\left(\mathbf{r}\right) &= -2\pi G\sigma\alpha^2 \int_{-1}^{1} \frac{1}{\sqrt{r^2 + \alpha^2 - 2r\alpha\cos\theta}} \; d\left(\cos\theta\right) \\ &= \frac{-2\pi G\sigma\alpha}{r} \left( \left(r + \alpha\right) - \left|r - \alpha\right| \right). \end{split}$$

We need to evaluate  $\Phi$  for r < a and for r > a.

$$\Phi (r < a) = -4\pi G \sigma a$$

$$= -\frac{Gm}{a}$$

$$\Phi (r > a) = -\frac{4\Pi G \sigma a^2}{r}$$

$$= -\frac{Gm}{r}.$$

Notice that inside the shell, the gravitational potential is constant, while outside the shell, the gravitational potential falls off as if the shell has its mass concentrated at a point in the center.

When we convert the spherical shell into a ball (by integrating over  $\alpha$ ), we can see that, outside the planet, it is still the case that gravitational potential depends solely on the distance to the center of the sphere.

#### Flux

While circulation is the measure of the "swirl" of a vector field about a curve, we are also interested in the "surge" of a vector field about a surface. This is what flux is.

**Definition** (Flux). The flux is the product of the field's magnitude and surface area A that it crosses.

$$\Phi \equiv EA$$
.

A surface is identified with its orientation, \(\hat{n}\), meaning

$$\Phi = \mathbf{E} \cdot \hat{\mathbf{n}} A.$$

If  $\hat{n}$  is not constant along a curve's surface, flux is calculated with an integral.

$$\Phi = \int_{S} \mathbf{E} \cdot \hat{\mathbf{n}} \, d\mathbf{a}$$

xvIIICitation needed.

$$= \int_{S} \mathbf{E} \cdot d\mathbf{a}.$$

If S is a closed surface, XIX the flux is known as the net flux, and is denoted

$$\Phi_{\text{net}} = \oint_{S} \mathbf{E} \cdot d\mathbf{a}.$$

**Example** (Continuity Equation). The conservation of electric charge is expressed by continuity — the rate at which charge is lost in a surface,  $Q_{in}$  must be accounted for by the current flowing out of the surface,  $I_{out}$ .

$$I_{out} = -\frac{dQ_{in}}{dt}.$$

We define the charge density  $\rho$  as

$$Q_{\rm in} = \int_{V} \rho \ d\tau,$$

and the movement of charge density with average drift velocity  $\mathbf{v}$  gives the current density,  $\mathbf{J} = \rho \mathbf{v}$ . Since  $\mathbf{J}$  has units of current per area, the usual current is measured by

$$I = \int_{S} \mathbf{J} \cdot d\mathbf{a}.$$

In particular, continuity is concerned with net flux, meaning

$$I_{out} = \oint_{S} \mathbf{J} \cdot d\mathbf{a},$$

so the continuity equation is

$$\oint_{S} \mathbf{J} \cdot d\mathbf{a} = -\frac{d}{dt} \int_{V} \rho \ d\tau,$$

where S bounds the volume V.

**Example** (Gauss's Law). Gauss's Law states that the net flux about an enclosed surface is proportional to the charge enclosed.

$$\oint_{S} \mathbf{E} \cdot d\mathbf{a} = \frac{q_{\text{encl}}}{\epsilon_0}.$$

We would find it weird to find E using Gauss's law, unless the symmetry works heavily in our favor.

Consider a uniform ball with positive charge  $Q_0$  and radius  $\alpha$ . Since the charge is spherically symmetric, E must be radial, implying  $E = E(r)\hat{r}$ .

With this in mind, we can choose a surface S such that E is parallel to  $d\mathbf{a} = \hat{\mathbf{n}} d\mathbf{a}$ ,  $\mathbf{x}$  and of constant magnitude on S.

For r > a, our enclosed charge is

$$\oint_{S} \mathbf{E} \cdot d\mathbf{a} = \oint_{S} E(\mathbf{r}) \hat{\mathbf{r}} \cdot \hat{\mathbf{r}} d\alpha$$

XIX A surface with no boundary.

xxFor a sphere,  $\hat{n} = \hat{r}$ 

$$= E(r) \oint_{S} d\alpha$$

$$= 4\pi r^{2} E(r)$$

$$= \sigma 4\pi a^{2}$$

$$E = \frac{Q_{0}}{4\pi \varepsilon r^{2}}$$

$$E = \frac{Q_{0}}{4\pi \varepsilon_{0} r^{2}} \hat{r}.$$

If our Gaussian surface is inside the sphere, then with our charge density  $\rho = \frac{Q_0}{4/3\pi a^3}$ , implying

$$q_{encl} = \rho \frac{4}{3} \pi r^3$$
$$= Q_0 \frac{r^3}{a^3}.$$

Thus, inside the ball, we get

$$\mathbf{E} = \frac{Q_0}{4\pi\varepsilon_0} \frac{\mathbf{r}}{\mathbf{a}^3} \hat{\mathbf{r}}.$$

Recall: A vector field E is path independent if

$$\oint_C \mathbf{E} \cdot d\vec{\ell} = 0$$
$$\mathbf{E} = \nabla \Phi$$
$$\nabla \times \mathbf{E} = 0.$$

This is also known as an irrotational vector field.

**Example** (Surface Independence). Let  $\mathbf{E} = xy^2\hat{\mathbf{i}} + x^2y\hat{\mathbf{j}}$  and  $\mathbf{B} = x^2y\hat{\mathbf{i}} - xy^2\hat{\mathbf{j}}$ . We will examine the flux of these fields about different surfaces.

**Example** (Flux of **E** about  $S_1$ ). We define  $S_1$  to be a quarter circle of radius  $\alpha$  in the yz-plane, defined at x = b. To define d**a**, we define the orientation to be in the  $\hat{i}$  direction, meaning d**a** =  $\hat{i}$  dydz. Our integral becomes

$$\int_{S_1} \mathbf{E} \cdot d\mathbf{a} = \int_{S_1} xy^2 \, dy \, dz.$$

We don't want to do this integral in cartesian coordinates, so we do a change of coordinates

$$\int_{S_1} \mathbf{E} \cdot d\mathbf{a} = \int_{S_1} xy^2 \, dy \, dz$$

$$= \int_{S_1} xy^2 r \, dr d\phi,$$

$$= b \int_{S_1} y^2 \, dr d\phi$$

$$= b \int_0^a r^3 \, dr \int_0^{\pi/2} \cos^2 \phi \, d\phi$$

$$= \frac{\pi}{16} a^4 b.$$

**Example** (Flux of E about  $S_2$ ). Let  $S_2$  be a quarter cylinder of radius  $\mathfrak a$  in the yz-plane, with  $\mathfrak b < \mathfrak x < 2\mathfrak b$ . We are integrating over four faces — the rectangle in the xz-plane, the rectangle in the xy-plane, the

quarter-circle at x = 2b in the yz-plane, and the radial face between x = b and x = 2b.

The rectangle in the xy-plane has its orientation in the  $-\hat{k}$  direction, meaning  $\mathbf{E} \cdot d\mathbf{a}_1 = 0$ , and similarly, the rectangle in the xz-plane has its orientation in the  $-\hat{j}$  direction, meaning  $\mathbf{E} \cdot d\mathbf{a}_2 = 0$ . The quarter circle cap at x = 2b has its orientation in the positive x direction — in cylindrical coordinates, this becomes  $d\mathbf{a}_3 = \hat{i} \rho d\rho d\varphi$ . On the radial face, we have  $d\mathbf{a}_4 = \hat{\rho} a d\varphi dx$ .

$$\int_{S_2} \mathbf{E} \cdot d\mathbf{a} = \sum_{i} \int_{s_i} \mathbf{E} \cdot d\mathbf{a}_i$$

$$= 0 + 0 + \int_{s_3} xy^2 \rho \, d\rho d\phi + \int_{s_4} \mathbf{E} \cdot \hat{\rho} \, d\phi dx$$

$$= \frac{\pi}{8} \alpha^2 b \left( \alpha^2 + \frac{14}{3} b^2 \right).$$

Note that in our previous two examples, the surface affected the flux.

**Example** (Flux of **B** about  $S_1$ ).

$$\int_{S_1} \mathbf{B} \cdot d\mathbf{a} = \frac{1}{3} \alpha^3 b^2$$

**Example** (Flux of **B** about  $S_2$ ).

$$\begin{split} \int_{S_2} \mathbf{B} \cdot d\mathbf{a} &= \int_{s_3} x y^2 \rho \ d\rho d\phi + \int_{s_4} \mathbf{B} \cdot \hat{\rho} \alpha \ d\phi dx \\ &= \frac{1}{3} \alpha^3 b^2. \end{split}$$

In this case, we can see that  $\bf B$  has the same flux integral. Later, we will see that  $\bf B$  is "surface independent," in the sense that since both  $S_1$  and  $S_2$  have the same boundary, the flux integral of  $\bf B$  only depends on the boundary.

**Definition** (Surface Independence). Let **B** be a vector field. If, for any closed surface S,

$$\oint_{S} \mathbf{B} \cdot d\mathbf{a} = 0,$$

then we say **B** is surface independent.

For a surface-independent field, the integral about an arbitrary surface must be the same same through any surface bounded by the same closed curve, implying the existence of a vector potential **A** such that

$$\int_{S} \mathbf{B} \cdot d\mathbf{a} = \oint_{C} \mathbf{A} \cdot d\vec{\ell},$$

where C is the boundary of S — note that this equivalence only holds with respect to a particular orientation. By convention, we use the positive orientation on C, which implies that  $\hat{n}$  has outward orientation on S.

Since **A** is a vector potential, we can yield another field  $\mathbf{F} = \nabla \times \mathbf{A}$ . Thus, we get Stokes's Theorem

$$\int_{S} \nabla \times \mathbf{A} \cdot d\mathbf{a} = \oint_{C} \mathbf{A} \cdot d\vec{\ell}.$$

Notice that the divergence of a curl is zero, so we can see that  $\nabla \cdot \mathbf{F} = 0$ .

**Definition** (Three Equivalent Criteria for Surface Independence). Let **F** be a surface independent vector field. Then, the following are equivalent:

$$\oint_{S} \mathbf{F} \cdot d\mathbf{a} = 0$$

$$\mathbf{F} = \nabla \times \mathbf{A}$$

$$\nabla \cdot \mathbf{F} = 0.$$

**Example** (Finding A). Let B be such that  $\nabla A = B$ . Then,

$$\mathbf{B} = \begin{cases} x^2 \mathbf{y} = \partial_{\mathbf{y}} A_z - \partial_z A_{\mathbf{y}} \\ -x \mathbf{y}^2 = \partial_z A_{\mathbf{x}} - \partial_x A_{\mathbf{z}} \\ 0 = \partial_x A_{\mathbf{y}} - \partial_{\mathbf{y}} A_{\mathbf{x}} \end{cases}.$$

If we let  $A_x = A_y = 0$ , then we solve the equation by taking

$$x^{2}y = \partial_{y}A_{z}$$
$$xy^{2} = \partial_{x}A_{z},$$

yielding

$$A_z = \frac{1}{2}x^2y^2 + \alpha(x, z)$$

$$A_z = \frac{1}{2}x^2y^2 + \beta(y, z).$$

For consistency, it must be the case that  $\alpha(x, z) = \beta(y, z) = \gamma(z)$ . Thus, we get

$$\mathbf{A}_1 = \left(\frac{1}{2}x^2y^2 + \gamma(z)\right)\hat{\mathbf{k}}.$$

We can also find

$$\mathbf{A}_2 = \left(-xy^2z + \beta(x,y)\right)\hat{\mathbf{i}} + \left(-x^2yz + \alpha(x,y)\right)\hat{\mathbf{j}},$$

whose curl is also **B**.

Note that this means **A** it not unique. In particular, for any **A**, we can add any gradient field  $\nabla \chi$ , since  $\nabla \times \nabla \chi = 0$ .

# Calculating Flux Integrals with Boundary Geometry

Recall the fundamental theorem of calculus:

$$\int_{a}^{b} \frac{df}{dx} dx = f(b) - f(a).$$

In higher dimensions along a path C traveling from  $r_1$  to  $r_2$ , we have

$$\int_{C} \nabla f \cdot d\vec{\ell} = f(\mathbf{r}_{2}) - f(\mathbf{r}_{1}).$$

Notice that, via this process, we convert from a local property (derivatives) to a property defined by the boundary of a region (in this case, the endpoints of an interval and/or curve).

#### **Divergence Theorem**

Consider an infinitesimal box with length dx, height dy, and depth dz. We can see that the flux of **E** about these faces is

$$d\Phi_{\text{net}} = \sum_{i} \mathbf{E} \cdot d\mathbf{a}_{i}.$$

Evaluating **E** at the faces on the yz plane parallel to the x axis, we get

$$\mathbf{E}(0,0,0) \cdot d\mathbf{a}_{left} + \mathbf{E}(dx,0,0) \cdot d\mathbf{a}_{right} = -\mathbf{E}_{x}(0,0,0) dy dz + \mathbf{E}_{x}(dx,0,0) dy dz.$$

The x component of  $d\Phi_{net}$  is, thus,

$$d\phi_1 - (\mathsf{E}_x (dx, 0, 0) - \mathsf{E}_x (0, 0, 0)) \, dy dz$$
$$= \left(\frac{\partial \mathsf{E}_x}{\partial x} \, dx\right) dy dz.$$

Similarly,

$$d\phi_2 = \left(\frac{\partial E_y}{\partial y} dy\right) dz dx$$
$$d\phi_3 = \left(\frac{\partial E_z}{\partial z} dz\right) dx dy.$$

Therefore,

$$d\Phi_{\text{net}} = \left(\frac{\partial \mathsf{E}_{x}}{\partial x} dx\right) dy dz + \left(\frac{\partial \mathsf{E}_{y}}{\partial y} dy\right) dz dx + \left(\frac{\partial \mathsf{E}_{z}}{\partial z} dz\right) dx dy$$
$$= (\nabla \cdot \mathbf{E}) d\tau,$$

where  $d\tau = dxdydz$  is the volume element. Thus, we see that the infinitesimal flux is proportional to the divergence of E.

To convert from infinitesimal boxes to a full (bounded) region, we cut up V into a bunch of small boxes. The interior box faces' respective fluxes cancel each other out since they have opposite-facing normals.

**Theorem:** Let V be a compact surface in  $\mathbb{R}^3$  with piecewise smooth boundary  $\partial V$ , and E a continuously differentiable vector field defined on a neighborhood of V. Then, the following is true

$$\int_{\mathcal{V}} \nabla \cdot \mathbf{E} \, d\tau = \oint_{\partial \mathcal{V}} \mathbf{E} \cdot d\mathbf{a}.$$

**Example.** Let  $E = r^{\alpha}\hat{r}$ , and V be a sphere of radius R. Since we have spherical symmetry, we can find the flux of E about the sphere by taking

$$\oint_{S} \mathbf{E} \cdot d\mathbf{a} = \oint r^{\alpha} R^{2} d\Omega$$
$$= 4\pi R^{\alpha+2}.$$

Using the divergence theorem, we take  $\nabla \cdot \mathbf{E} = \frac{1}{r^2} \frac{\partial}{\partial r} (r^2 E_r) = (\alpha + 2) r^{\alpha - 1}$ , and take

$$\int_{V} \nabla \cdot \mathbf{E} \, d\tau = (\alpha + 2) \int_{0}^{R} r^{\alpha - 1} r^{2} \, dr d\Omega$$
$$= 4\pi R^{\alpha + 2}.$$

Notice that at  $\alpha = -2$ , this expression appears to fail — the divergence is zero, but the flux is clearly not zero.

**Example.** Let  $E = r^{\alpha}\hat{r}$ , and V be the region between a sphere of radius  $R_1$  and radius  $R_2$ , with  $R_1 < R_2$ .

To find the flux about E, we find

$$\int_{\partial V} \mathbf{E} \cdot d\mathbf{a} = \oint_{S_2} \mathbf{E} \cdot d\mathbf{a} + \oint_{S_1} \mathbf{E} \cdot d\mathbf{a}$$
$$= 4\pi \left( R_2^{\alpha+2} - R_1^{\alpha+2} \right).$$

Similarly, we get

$$\int_{V} \nabla \cdot \mathbf{E} \ d\tau = 4\pi \left( R_{2}^{\alpha+2} - R_{1}^{\alpha+2} \right).$$

Calculating for  $\alpha = -2$ , we know that

$$\begin{split} \int_{V} \nabla \cdot \frac{\hat{\mathbf{r}}}{r^{2}} d\tau &= \oint_{S} \frac{\hat{\mathbf{r}} \cdot \hat{\mathbf{n}}}{r^{2}} d\alpha \\ &= \oint_{S_{1}} \frac{\hat{\mathbf{r}} \cdot \hat{\mathbf{n}}_{1}}{r^{2}} d\alpha + \underbrace{\oint_{S_{2}} \frac{\hat{\mathbf{r}} \cdot \hat{\mathbf{n}}_{2}}{r^{2}} d\alpha}_{-\oint_{S_{1}} \frac{\hat{\mathbf{r}} \cdot \hat{\mathbf{n}}_{1}}{r^{2}} d\alpha} \\ &= 0. \end{split}$$

Thus,

$$\oint_{S_2} \frac{\hat{\mathbf{r}}}{\mathbf{r}^2} d\mathbf{a} = \oint_{S_1} \frac{\hat{\mathbf{r}}}{\mathbf{r}^2} d\mathbf{a}$$

$$= \oint_{S_1} \frac{R_1^2}{R_1^2} d\Omega$$

$$= 4\pi$$

Thus, the integral over  $R_2$  has *no* dependence on  $R_2$ , and (as long as  $R_1 \neq 0$ ), we can change  $R_1$  however we like. If we let  $R_1 \rightarrow 0$ , we find

$$\int_V \left( \nabla \cdot \frac{\hat{r}}{r^2} \right) d\tau = 4\pi.$$

Since the divergence is 0 everywhere except the origin, this means

$$\nabla \cdot \frac{\hat{\mathbf{r}}}{\mathbf{r}^2} = 4\pi \delta(\mathbf{r})$$

Thus,

$$\Phi_{\text{net}} = \oint_{S} \mathbf{E} \cdot d\mathbf{a}$$

$$= \oint_{S} \frac{R^{2}}{R^{2}} d\Omega$$

$$= 4\pi$$

$$= \frac{1}{\epsilon_{0}} Q_{\text{encl}},$$

meaning we get back Gauss's law:

$$\mathbf{E} = \frac{\mathbf{Q}}{4\pi\epsilon_0} \frac{\hat{\mathbf{r}}}{\mathbf{r}^2}.$$

Remark: Gauss's law for magnetism has

$$\Phi_{\text{net}} = \oint_{S} \mathbf{B} \cdot d\mathbf{a}$$
$$= 0.$$

This means that  $\nabla \cdot \mathbf{B} = 0$  at all points (rather than yielding the Dirac delta distribution), or that there are no magnetic monopoles. All magnetic fields must form closed loops.

#### Stokes's Theorem

The divergence theorem allows us to move from flux (which is defined on the boundary of a region) and the divergence (defined on the interior). Similarly, we want to find some similar relation for circulation.

Consider a field **B** and an infinitesimal rectangular curve with length dx and width dy. Then,

$$d\Psi = \sum_{i} \mathbf{B} \cdot d\vec{\ell}_{i}.$$

Looking at the bottom and top segments, we find

$$\mathbf{B}(0,0,0) \cdot d\vec{\ell}_{bottom} + \mathbf{B}(0,dy,0) \cdot d\vec{\ell}_{top} = B_x(0,0,0) dx - B_x(0,dy,0) dx,$$

where the minus sign appears from integrating right to left along the top segment. Thus, we get

$$\begin{split} d\psi_1 &= \left(-B_x\left(0,dy,0\right) + B_x\left(0,0,0\right)\right) dx \\ &= -\left(\frac{\partial B_y}{\partial x} dy\right) dx. \end{split}$$

Similarly, for left and right segments, we get

$$d\psi_2 = \left( B_y (dx, 0, 0) - B_y (0, 0, 0) \right) dy$$
$$= \left( \frac{\partial B_y}{\partial x} dx \right) dy.$$

Thus, we get

$$d\Psi = \left(\frac{\partial B_y}{\partial x} - \frac{\partial x}{\partial y}\right) dx dy$$
$$= \left(\frac{B_y}{x} - \frac{\partial B_x}{\partial y}\right) dA,$$

where dA = dxdy is the area element.

To build up to a simply connected region, split the region into rectangles. The interior infinitesimal segments cancel each other out, yielding Green's Theorem:

**Theorem:** Let C be a piecewise smooth simple closed curve in  $\mathbb{R}^2$ , and let S be the region in  $\mathbb{R}^2$  that is bounded by C. Then, for a continuously differentiable vector field **B**,

$$\oint_C \mathbf{B} \cdot d\vec{\ell} - \int_S \left( \frac{\partial B_y}{\partial x} - \frac{\partial B_x}{\partial y} \right) dx dy,$$

Notice that

$$\frac{\partial B_y}{\partial x} - \frac{\partial B_x}{\partial y} = (\nabla \times \mathbf{B})_z.$$

With this in mind, we can move to three dimensions using the curl, yielding Stokes's Theorem.

**Theorem:** Let S be a smooth oriented surface with boundary  $C = \partial S$ . Then, for a continuously differentiable vector field **B**,

$$\oint_C \mathbf{B} \cdot d\vec{\ell} = \int_S \nabla \times \mathbf{B} \cdot d\mathbf{a}.$$

**Example.** Let  $\mathbf{B} = x^2 y \hat{\mathbf{i}} - x y^2 \hat{\mathbf{j}}$ .

We calculated the circulation from  $P_1 = (0,0)$  and  $P_2 = (1,1)$ , via  $C_1$ , defined by the straight line from (0,0) to (1,0) to (1,1), to be

$$\int_{C_1} \mathbf{B} \cdot d\vec{\ell} = -\frac{1}{3},$$

and the circulation along  $C_2$ , which is a straight line from (0,0) to (1,1), to be

$$\int_{C_2} \mathbf{B} \cdot d\vec{\ell} = 0.$$

Thus, the circulation along the path  $C_2 - C_1$  is  $\frac{1}{3}$ .

Verifying with Green's Theorem, we find  $\nabla \times \mathbf{B} = -(x^2 + y^2) \hat{k}$ , and take

$$\int_{S} \nabla \times \mathbf{B} \cdot d\mathbf{a} = \int_{S} \left( -\left(x^{2} + y^{2}\right) \hat{\mathbf{k}} \right) \cdot \left( -\hat{\mathbf{k}} \right) dx dy$$

$$= \int_{0}^{1} dx \int_{0}^{x} \left(x^{2} + y^{2}\right) dy$$

$$= \frac{4}{3} \int_{0}^{1} x^{3} dx$$

$$= \frac{1}{3}.$$

**Example.** Let  $\mathbf{B} = \mathbf{r}^{\alpha} \hat{\boldsymbol{\varphi}}$ , and consider a circle of radius R.

Since our field is axially symmetric, we evaluate the cirulation to find

$$\int_{C} \mathbf{B} \cdot d\vec{\ell} = \oint_{C} r^{\alpha} R d\phi$$
$$= R^{\alpha+1} \int_{0}^{2\pi} d\phi$$
$$= 2\pi R^{\alpha+1}.$$

Calculating the curl, since the field only has a  $\hat{\phi}$  component, we get

$$\nabla \times \mathbf{B} = \frac{1}{r} \frac{\partial}{\partial r} (r \mathbf{B}_{\Phi}) \hat{z}$$
$$= (\alpha + 1) r^{\alpha - 1} \hat{z},$$

meaning over the circular disc bounded by C, we have

$$\int_{S} (\nabla \times \mathbf{B}) \cdot d\mathbf{a} = (\alpha + 1) \int_{S} r^{\alpha} dr d\phi$$
$$= 2\pi R^{\alpha + 1}.$$

Notice that we seem to be missing a curl here — if  $\alpha = -1$ , one side of Stokes's theorem says  $\int_S (\nabla \times \mathbf{B}) \cdot d\mathbf{a} = 0$ , but the circulation is not zero.

**Example.** Consider a field of  $\mathbf{B} = -\hat{\mathbf{k}}$ , and we want to know the flux about a hemispherical surface of radius R bounded by a curve C in the xy-plane.

We can integrate about the hemisphere,

$$\int_{S_1} \mathbf{B} \cdot d\mathbf{a} = \int_{S} \left( \hat{\mathbf{r}} \cos \theta - \hat{\theta} \sin \theta \right) \cdot \hat{\mathbf{r}} R^2 d\Omega$$
$$= -2\pi R^2 \int_{0}^{1} \cos \theta d (\cos \theta)$$
$$= -\pi R^2.$$

We can also use the boundary integral. In particular, since  $\nabla \times \mathbf{B} = 0$ , we can find  $\mathbf{A} = -y\hat{\imath}$ . Now, we can evaluate it as the circulation of A.

Notice that  $d\vec{\ell} = \hat{\phi}Rd\phi$ , meaning we only need  $A_{\phi} = -y \sin \phi$ ; since  $y = R \sin \theta \sin \phi$  and  $\theta = \pi/2$ , we have

$$\int_{C} \mathbf{A} \cdot d\vec{\ell} = -\oint_{C} y \sin \phi R d\phi$$
$$= -\pi R^{2}.$$

However, the easiest way to do this integral is by selecting our surface to be the disk in the plane bounded by C. Thus,

$$\int_{S_2} \mathbf{B} \cdot d\mathbf{a} = -\int \hat{\mathbf{k}} \cdot \hat{\mathbf{k}} r \, dr d\phi$$
$$= -\pi R^2.$$

## The Fundamental Theorem of Calculus, Revisited

The fundamental theorem of calculus says

$$f(P_2) - f(P_1) = \int_C \nabla F \cdot d\vec{\ell},$$

which expresses the accumulation of  $\nabla f \cdot d\vec{\ell}$  along the one-dimensional curve C via its expression over the (zero-dimensional) boundary. Similarly, the divergence theorem says

$$\oint_{S} \mathbf{E} \cdot d\mathbf{a} = \int_{V} \nabla \cdot \mathbf{E} \, d\tau,$$

which expresses the accumulation of  $\nabla \cdot \mathbf{E} \, d\tau$  over the three-dimensional volume via its expression over the two-dimensional boundary. Similarly,

$$\oint_C \mathbf{B} \cdot d\vec{\ell} = \int_S (\nabla \times \mathbf{B}) \cdot d\mathbf{a}$$

expresses the accumulation of  $(\nabla \times \mathbf{B}) \cdot d\mathbf{a}$  over the two-dimensional surface via its expression on the one-dimensional boundary C.

Example (Integration By Parts). Recall that integration by parts is the inverse of the product rule

$$\frac{\mathrm{d}}{\mathrm{d}x}\left(f(x)g(x)\right) = \frac{\mathrm{d}f}{\mathrm{d}x}g + f\frac{\mathrm{d}g}{\mathrm{d}x},$$

meaning

$$\int_a^b f(x) \frac{dg}{dx} dx = f(x)g(x) \Big|_a^b - \int_a^b \frac{df}{dx} g(x) dx.$$

However, we can do this for higher dimensions too, since the fundamental theorem of calculus still holds.

$$\nabla \cdot (f\mathbf{E}) = f(\nabla \cdot \mathbf{E}) + (\nabla f) \cdot \mathbf{E},$$

meaning

$$\int_{V} f(\nabla \cdot \mathbf{E}) \ d\tau = \oint_{S} f \mathbf{E} \cdot d\mathbf{a} - \int_{V} (\nabla f) \cdot \mathbf{E} \ d\tau,$$

which yields a boundary term.

Similarly,

$$\nabla \times (f\mathbf{B}) = f(\nabla \times \mathbf{B}) + (\nabla f) \times \mathbf{B}$$

meaning

$$\int_{S} f(\nabla \times \mathbf{B}) \cdot d\mathbf{a} = \oint_{C} f\mathbf{B} \cdot d\vec{\ell} - \int_{S} ((\nabla f) \cdot \mathbf{B}) \cdot d\mathbf{a}.$$

**Example** (Boundary of the Boundary). The fundamental theorem of calculus for an arbitrary field f in relation to its infinitesimal change df integrated over  $\Omega$  can be expressed by the generalized Stokes's theorem (which is the fundamental theorem of calculus):

$$\int_{\partial\Omega} f = \int_{\Omega} df.$$

When we take the integral of the second derivative, we get

$$\int_{\Omega} d^2 f = \int_{\partial \Omega} df$$
$$= \int_{\partial^2 \Omega} f.$$

Since there is no boundary of a boundary, this means the integral is

$$= 0$$

Consider a field  $E = \nabla \Phi$ . Using generalized Stokes's theorem

$$\begin{split} \int_{S} \left( \nabla \times \mathbf{E} \right) \cdot \mathbf{a} &= \int_{S} \nabla \times \left( \nabla \Phi \right) \cdot d\mathbf{a} \\ &= \oint_{C} \nabla \Phi \cdot d\vec{\ell} \\ &= \Phi \left( P_{2} \right) - \Phi \left( P_{1} \right) \\ &= 0 \end{split}$$

Similarly, for  $\mathbf{B} = \nabla \times \mathbf{A}$ , using the generalized Stokes theorem, we get

$$\int_{V} \nabla \times \mathbf{B} \, d\tau = \int_{V} \nabla \times (\nabla \times \mathbf{B}) \, d\tau$$
$$= \oint_{S} (\nabla \times \mathbf{A}) \cdot d\mathbf{a}$$
$$= \oint_{C} \mathbf{A} \cdot d\vec{\ell}$$
$$= 0.$$

Since these hold for any arbitrary region in  $\mathbb{R}^3$ , we get the previously shown results that

$$\nabla \times \nabla \Phi = 0$$
$$\nabla \cdot (\nabla \times \mathbf{A}) = 0.$$

## **Helmholtz Decomposition**

In electrostatics, we have

$$\Phi(\mathbf{r}) = \int \frac{\rho(\mathbf{x})}{|\mathbf{r} - \mathbf{x}|} d^3 \mathbf{x}$$
$$\mathbf{E} = -\nabla \Phi.$$

However, this integral is hard to calculate, XXI so we focus on trying to find the behavior of the field.

The Helmholtz decomposition basically tells us that, if the field goes to zero "fast enough," then we can reconstruct the field from the divergence and the curl.

We start with a generic field,

$$\mathbf{F}(\mathbf{r}) = \int_{V} \mathbf{F}(\mathbf{x}) \, \delta(\mathbf{r} - \mathbf{x}) \, \mathrm{d}^{3} \mathbf{x},$$

where V includes r. The identity

$$\nabla \cdot \left( \nabla \left( \frac{1}{|\mathbf{r} - \mathbf{x}|} \right) \right) = -4\pi\delta \left( \mathbf{r} - \mathbf{x} \right)$$

allows us to substitute into the original expression of F.

$$\mathbf{F}(\mathbf{r}) = -\frac{1}{4\pi} \int_{V} \mathbf{F}(\mathbf{x}) \nabla^{2} \left( \frac{1}{|\mathbf{r} - \mathbf{x}|} \right) d^{3}x$$
$$= -\frac{1}{4\pi} \nabla^{2} \int_{V} \frac{\mathbf{F}(\mathbf{x})}{|\mathbf{r} - \mathbf{x}|} d^{3}x,$$

which we are allowed to do<sup>XXII</sup> since  $\nabla^2$  acts on **x** rather than **r**.

The integrand can be rewritten by taking  $\nabla^2 \mathbf{v} = \nabla (\nabla \cdot \mathbf{v}) - \nabla \times (\nabla \times \mathbf{v})$ , yielding

$$\mathbf{F}(\mathbf{r}) = -\nabla \underbrace{\left(\frac{1}{4\pi}\nabla \cdot \int_{V} \frac{\mathbf{F}(\mathbf{x})}{|\mathbf{r} - \mathbf{x}|} d^{3}\mathbf{x}\right)}_{\Phi} + \nabla \times \underbrace{\left(\frac{1}{4\pi}\nabla \times \int_{V} \frac{\mathbf{F}(\mathbf{r})}{|\mathbf{r} - \mathbf{x}|} d^{3}\mathbf{x}\right)}_{\mathbf{A}},$$

$$= -\nabla \Phi + \nabla \times \mathbf{A}.$$

Now that we have completed the decomposition, we can reconstruct our field. Starting with  $\Phi$ , we take

$$\Phi(\mathbf{r}) = \frac{1}{4\pi} \nabla \cdot \int_{V} \frac{\mathbf{F}(\mathbf{x})}{|\mathbf{r} - \mathbf{x}|} d^{3}x$$

$$= \frac{1}{4\pi} \int_{V} \mathbf{F}(\mathbf{x}) \cdot \nabla \frac{1}{|\mathbf{r} - \mathbf{x}|} d^{3}x$$

$$= -\frac{1}{4\pi} \int_{V} \mathbf{F}(\mathbf{x}) \cdot \nabla_{\mathbf{x}} \frac{1}{|\mathbf{r} - \mathbf{x}|} d^{3}x$$

where we move the r derivative in the integral, and use the technique that

$$\nabla \frac{1}{|\mathbf{r} - \mathbf{x}|} = -\nabla_{\mathbf{x}} \frac{1}{|\mathbf{r} - \mathbf{x}|},$$

xxICitation needed.

xxIIWell, we need a little more, but we're physicists so everything is assumed to be nice.

to move the derivative to the x. Now, we can use integration by parts to take

$$\Phi(\mathbf{r}) = -\frac{1}{4\pi} \oint_{S} \frac{\mathbf{F}(\mathbf{x}) \cdot d\mathbf{a}}{|\mathbf{r} - \mathbf{x}|} + \frac{1}{4\pi} \int_{V} \frac{\nabla_{\mathbf{x}} \cdot \mathbf{F}(\mathbf{x})}{|\mathbf{r} - \mathbf{x}|} d^{3}\mathbf{x}.$$

Using a similar technique for A, we get

$$\mathbf{A}(\mathbf{r}) = -\frac{1}{4\pi} \oint_{S} \frac{d\mathbf{a} \times \mathbf{F}(\mathbf{x})}{|\mathbf{r} - \mathbf{x}|} + \frac{1}{4\pi} \int_{V} \frac{\nabla_{\mathbf{x}} \times \mathbf{F}(\mathbf{x})}{|\mathbf{r} - \mathbf{x}|} d^{3}\mathbf{x}.$$

Thus, assuming these integrals converge, these expressions allow us to *uniquely* determine **F** from its curl and divergence.

## Maxwell's Equations

Maxwell's equations (see Table 17) help move beyond Coulomb's Law and the Biot–Savart law by showing that electricity and magnetism are connected to each other once time is involved.

#### **Integrating Maxwell**

We saw that we can derive the expression for conservation of charge by the continuity equation:

$$\oint_{S} \mathbf{J} \cdot d\mathbf{a} = -\frac{\mathrm{d}}{\mathrm{d}t} \int_{V} \rho \, \mathrm{d}\tau,$$

where  $\rho$  is the charge density and **J** is the current density. The continuity equation states that the charge that disappears from a volume is equal to the flux of the charge.

Since Maxwell's equations lay claim to being able to describe everything with respect to electric and magnetic fields (as they include both a divergence and curl), we see if we can derive the continuity equation from Maxwell's equations.

Only one of Maxwell's equations uses current: Ampère's law. In a time-independent field, we have

$$\oint_{C} \mathbf{B} \cdot d\vec{\ell} = \mu_0 \int_{S} \mathbf{J} \cdot d\mathbf{a}.$$

Assuming that both  $\bf B$  and  $\bf J$  are continuous, we can shrink the bounding curve to a single point, meaning  $\bf S$  becomes a closed surface, yielding

$$\oint_{S} \mathbf{J} \cdot d\mathbf{a} = 0.$$

This is what we expected for time-independence.

However, when we deal with a time-dependent system, we need a displacement current,  $I_{disp} = \epsilon_0 \frac{d}{dt} \int_S \mathbf{E} \cdot d\mathbf{a}$ . Thus, our modified Ampère's law for a closed surface yields

$$\begin{split} 0 &= \oint_S \boldsymbol{B} \cdot \vec{\ell} \\ &= \mu_0 \oint_S \boldsymbol{J} \cdot d\boldsymbol{a} + \mu_0 \varepsilon_0 \frac{d}{dt} \underbrace{\oint_S \boldsymbol{E} \cdot d\boldsymbol{a}}_{\frac{Q_{encl}}{\varepsilon_0}} \\ \oint_S \boldsymbol{J} \cdot d\boldsymbol{a} &= -\frac{dQ}{dt}. \end{split}$$

## From Integrals to Derivatives

Derivation (Gauss's Law). Let's start with Gauss's Law:

$$\oint_{S} \mathbf{E} \cdot d\mathbf{a} = \frac{Q_{\text{encl}}}{\epsilon_0}.$$

Using the Divergence theorem, we rewrite the integral as

$$\oint_{S} \mathbf{E} \cdot d\mathbf{a} = \int_{V} \nabla \cdot \mathbf{E} \, d\tau$$

and, setting  $\rho$  to be the charge density,

$$\frac{Q_{encl}}{\epsilon_0} = \frac{1}{\epsilon_0} \int_V \rho \ d\tau.$$

Thus, we get

$$\int_{V} \nabla \cdot \mathbf{E} \ d\tau = \frac{1}{\varepsilon_0} \int \ \rho \ d\tau.$$

Since this is true for arbitrary V, we can remove the integrals, and take

$$\nabla \cdot \mathbf{E} = \frac{\rho}{\varepsilon_0}.$$

Derivation (Gauss's Law for Magnetism). Similarly, with Gauss's Law for Magnetism, we get

$$\nabla \cdot \mathbf{B} = 0.$$

Derivation (Faraday's Law). Turning our attention to Faraday's Law, we take

$$\oint_C \mathbf{E} \cdot d\vec{\ell} = -\frac{d}{dt} \int_S \mathbf{B} \cdot d\mathbf{a}.$$

Using Stokes's theorem, we get

$$\int_{S} (\nabla \times \mathbf{E}) \cdot d\mathbf{a} = \int_{S} -\frac{\partial \mathbf{B}}{\partial t} \cdot d\mathbf{a}.$$

This this holds for arbitrary S, we get

$$\nabla \times \mathbf{E} = -\frac{\partial \mathbf{B}}{\partial t}.$$

Derivation (Ampère's Law). Finally, in Ampère's law, we get

$$\oint_C \boldsymbol{B} \cdot d\vec{\ell} = \mu_0 I_{encl} + \mu_0 \varepsilon_0 \frac{d}{dt} \int_S \boldsymbol{E} \cdot d\boldsymbol{a}.$$

Using the fact that  $I_{encl} = \int_{S} \mathbf{J} \cdot d\mathbf{a}$ , and Stokes's theorem, we get

$$\int_{S} (\nabla \times \mathbf{B}) \cdot d\mathbf{a} - \mu_{0} \left( \int_{S} \mathbf{J} \cdot d\mathbf{a} + \epsilon_{0} \int_{S} \frac{\partial \mathbf{E}}{\partial t} \cdot d\mathbf{a} \right)$$
$$= \mu_{0} \int_{S} \left( \mathbf{J} + \epsilon_{0} \frac{\partial \mathbf{E}}{\partial t} \right) \cdot d\mathbf{a}.$$

Since this holds for arbitrary S, we get

$$\nabla \times \mathbf{B} = \mu_0 \mathbf{J} + \mu_0 \varepsilon_0 \frac{\partial \mathbf{E}}{\partial \mathbf{t}}.$$

Derivation (Continuity Equation). If we take the divergence of Ampère's Law, we get

$$\nabla \cdot (\nabla \times \mathbf{B}) = \mu_0 \nabla \cdot \mathbf{J} + \mu_0 \epsilon_0 \nabla \cdot \frac{\partial \mathbf{E}}{\partial t}$$
$$0 = \nabla \cdot \mathbf{J} + \epsilon_0 \frac{\partial}{\partial t} (\nabla \cdot \mathbf{E})$$
$$\nabla \cdot \mathbf{J} = -\frac{\partial \rho}{\partial t},$$

which is exactly the continuity equation.

Derivation (Wave Equation). If we take the curl of Faraday's Law, we get

$$\begin{split} \nabla\times(\nabla\times\mathbf{E}) &= -\nabla\times\frac{\partial\mathbf{B}}{\partial t}\\ \nabla\left(\nabla\cdot\mathbf{E}\right) - \nabla^2\mathbf{E} &= -\frac{\partial}{\partial t}\left(\nabla\times\mathbf{B}\right)\\ &= -\frac{\partial}{\partial t}\left(\mu_0\mathbf{J} + \mu_0\varepsilon_0\frac{\partial\mathbf{E}}{\partial t}\right). \end{split}$$

We are now interested to see what happens in empty space — i.e., we want to see what happens in the homogeneous case (where there are no charges or currents).

In particular,  $\rho = 0$  and J = 0.

$$\begin{split} -\nabla^2 \mathbf{E} &= -\frac{\partial}{\partial t} \left( \mu_0 \varepsilon_0 \frac{\partial \mathbf{E}}{\partial t} \right) \\ \nabla^2 \mathbf{E} &= \mu_0 \varepsilon_0 \frac{\partial^2 \mathbf{E}}{\partial t^2}. \end{split}$$

This is the wave equation.

In particular,  $\frac{1}{\sqrt{\mu_0 \, \epsilon_0}} = c$ , so  $\nu = c$ . This is the connection between optics and electromagnetism.

## **Substituting Potentials**

In a static field, we get

$$\nabla \cdot \mathbf{E} = \frac{\rho}{\epsilon_0}$$
$$\nabla \times \mathbf{E} = 0$$
$$\nabla \cdot \mathbf{B} = 0$$
$$\nabla \times \mathbf{B} = \mu_0 \mathbf{J}.$$

In particular, this case means we can write **E** as  $-\nabla \Phi$ , and **B** =  $\nabla \times \mathbf{A}$  for some scalar potential  $\Phi$  and vector potential  $\mathbf{A}$ .

Rewriting Gauss's law in terms of  $\Phi$ , we get

$$\nabla^2 \Phi = -\frac{\rho}{\epsilon_0},$$

which is known as Poisson's equation.

Rewriting the time-independent Ampère's law in terms of A, we get

$$\nabla^2 \mathbf{A} - \nabla \left( \nabla \cdot \mathbf{A} \right) = -\mu_0 \mathbf{J}.$$

When we add in time dependence, unfortunately we don't have  $\Phi$  anymore. However, we still have **A**, so

$$\nabla \times \mathbf{E} = -\frac{\partial \mathbf{B}}{\partial t}$$

$$= -\frac{\partial}{\partial t} (\nabla \times \mathbf{A})$$

$$= -\nabla \times \frac{\partial \mathbf{A}}{\partial t}$$

$$\nabla \times \left( \mathbf{E} + \frac{\partial \mathbf{A}}{\partial t} \right) = 0.$$

We redefine E with this in mind to yield

$$\mathbf{E} = -\nabla \Phi - \frac{\partial \mathbf{A}}{\partial t},$$

meaning Gauss's law yields

$$\nabla^2 \Phi + \frac{\partial}{\partial t} \left( \nabla \cdot \mathbf{A} \right) = -\frac{\rho}{\varepsilon_0}$$

and Ampère's Law yields

$$\nabla^2 \mathbf{A} - \mu_0 \varepsilon_0 \frac{\partial^2 \mathbf{A}}{\partial t^2} - \nabla \left( \nabla \cdot \mathbf{A} + \mu_0 \varepsilon_0 \frac{\partial \Phi}{\partial t} \right) = -\mu_0 \mathbf{J}.$$

Note that for any particular  $\lambda(x, t)$ , we can make the transformation

$$\mathbf{A} \mapsto \mathbf{A} + \nabla \lambda$$
$$\Phi \mapsto \Phi - \frac{\partial \lambda}{\partial t}.$$

In particular, we can choose a gauge such that  $\nabla \cdot \mathbf{A} = 0$ , which is known as the Coulomb gauge. We can also use the Lorenz gauge, which sets

$$\nabla \cdot \mathbf{A} + \frac{1}{c^2} \frac{\partial \Phi}{\partial t} = 0.$$

# Linear Algebra

## Superposition

Waves, unlike particles, are able to be superimposed — we can add waves together to get new waves.

Consider a charge with density  $\rho = \rho_1 + \rho_2$ . Then, each charge density yields  $E_1$  and  $E_2$ , where  $\nabla \cdot E_1 + \nabla \cdot E_2 = \nabla \cdot (E_1 + E_2) = \nabla \cdot E$ .

Generally, for superposition to hold, we need an operator  $\mathcal{L}$  to be linear. For any inputs f and g and a, b  $\in$   $\mathbb{F}$ , we must have

$$\mathcal{L}(af + bg) = a\mathcal{L}(f) + b\mathcal{L}(g).$$

**Example** (Some Linear and Nonlinear Operators). (1) Consider f(x) = mx + b with  $b \ne 0$ . Then, f is a linear function, but f is not a linear operator, since

$$f(ax_1 + bx_2) = m(ax_1 + bx_2) + b$$
  
 $\neq af(x_1) + bf(x_2).$ 

We say f is an affine transformation of  $\mathbb{R}$  (or  $\mathbb{C}$ ).

(2) In finite dimensions, a linear operator can always be expressed as a matrix.

$$\begin{pmatrix} y_1 \\ y_2 \\ y_3 \end{pmatrix} = \begin{pmatrix} m_{11} & m_{12} & m_{13} \\ m_{21} & m_{22} & m_{23} \\ m_{31} & m_{32} & m_{33} \end{pmatrix} \begin{pmatrix} x_1 \\ x_2 \\ x_3 \end{pmatrix}$$
$$y_i = \sum_j M_{ij} x_j.$$

(3) The linear operator

$$P = \begin{pmatrix} 1 & 0 & 0 \\ 0 & 1 & 0 \\ 0 & 0 & 0 \end{pmatrix}$$

is a projection. In particular, P maps any vector v to its x and y components. The projection operator is idempotent —  $P^2 = P$ .

Note that "magnitude and direction" follows from the idea of a vector.

## **Vector Spaces**

#### **Essentials of Vector Spaces**

A vector space is a free module generated over a field. The generating set is known as a basis.

Unfortunately, physicists don't care about that stuff so we have to go the long way to define a vector space.

**Definition** (Properties of a Vector Space). Let **A** and **B** be vectors and  $a, b \in \mathbb{F}$ . Our vector space must be closed under addition. Then, we must have

- Commutativity: A + B = B + A.
- Associativity:  $(\mathbf{A} + \mathbf{B}) + \mathbf{C} = \mathbf{A} + (\mathbf{B} + \mathbf{C})$ .
- Additive Inverse:  $\mathbf{A} + (-\mathbf{A}) = 0$ .
- Distributivity of Scalar Multiplication: a(A + B) = aA + aB.
- Associativity of Scalar Multiplication: (ab) A = a(bA).

**Example** (Understanding  $\mathbb{R}^3$ ). • Arrows in  $\mathbb{R}^3$  are a vector space.

- Vectors in  $\mathbb{R}^3$  with one vanishing component *are not* a vector space. However, vectors in  $\mathbb{R}^3$  with the same vanishing component *are* a vector space (also known as a subspace) this vector space is isomorphic to  $\mathbb{R}^2$ .
- A plane that slices through the origin in  $\mathbb{R}^3$  is a subspace, and any line that slices through the origin in  $\mathbb{R}^3$  is also a subspace.

## Touching Base(s)

The primary circumstance under which  $a\mathbf{A} + b\mathbf{B} = 0$  is if  $\mathbf{B} = -\left(\frac{a}{b}\right)\mathbf{A}$ , meaning  $\mathbf{A}$  and  $\mathbf{B}$  are parallel.

If the only way  $a\mathbf{A} + b\mathbf{B} = 0$  is if a = b = 0, then **A** and **B** are independent of each other.

**Definition.** A collection  $\{A_i\}_{i=1}^k$  of vectors is called linearly independent if

$$\sum_{i=1}^{k} c_i \mathbf{A}_i = 0$$

if and only if  $c_i = 0$  for all i = 1, ..., k.

**Definition** (Spanning Set). A collection  $\left\{B_{j}\right\}_{j=1}^{m}$  is said to be spanning if for any vector **A**, there exist  $c_{1},\ldots,c_{m}$  such that

$$\mathbf{A} = \sum_{j=1}^{m} c_j \mathbf{B}_j.$$

**Definition** (Basis). A collection of vectors  $\{e_i\}_{i=1}^n$  is a basis if it is both linearly independent and spanning for the vector space.

The dimension of a vector space is equal to the cardinality of the basis.

The basis  $\{e_i\}_{i=1}^n$  "supports" any vector in a set. For any vector  $\mathbf{A}$ , then

$$\mathbf{A} = \sum_{j=1}^{n} c_j e_j.$$

We say the  $c_j$  are the components of **A** on the basis  $\{e_i\}_{i=1}^n$ .

**Example** (Standard Basis). Consider the set of  $n \times 1$  arrays,

$$\mathbf{A} = \begin{pmatrix} a_1 \\ \vdots \\ a_n \end{pmatrix}.$$

This set obeys the necessary rules for the column vectors. We define the standard basis for this set by

$$e_{i} = \begin{pmatrix} 0 \\ \vdots \\ 1 \\ \vdots \\ 0 \end{pmatrix},$$

where the 1 is at the ith position. We will write  $e_i = \hat{e}_i$ .

We can write

$$\mathbf{A} = \sum_{i=1}^{n} a_i \hat{e}_i.$$

Note that the expansion coefficients are the elements of the column vector **A**.

Example (Non-standard Basis). Let

$$\epsilon_1 = \begin{pmatrix} 1 \\ 1 \\ 1 \end{pmatrix}$$

$$\epsilon_2 = \begin{pmatrix} 1 \\ -2 \\ 1 \end{pmatrix}$$

$$\epsilon_3 = \begin{pmatrix} 1 \\ 0 \\ -1 \end{pmatrix}$$

Then,  $\{\epsilon_1, \epsilon_2, \epsilon_3\}$  forms a basis.

We have

$$\begin{pmatrix} a_1 \\ a_2 \\ a_3 \end{pmatrix} = \left(\frac{a_1 + a_2 + a_3}{3}\right) \epsilon_1 + \left(\frac{a_1 - 2a_2 + a_3}{6}\right) \epsilon_2 + \left(\frac{a_1 - a_3}{2}\right) \epsilon_3.$$

$$= \sum_{i=1}^3 c_i \epsilon_i.$$

**Example** (Matrix Basis). Consider Mat<sub>2</sub> ( $\mathbb{C}$ ), the set of all  $2 \times 2$  matrices over  $\mathbb{C}$ . Then, the set

$$\mathcal{B} = \left\{ \begin{pmatrix} 1 & 0 \\ 0 & 0 \end{pmatrix}, \begin{pmatrix} 0 & 1 \\ 0 & 0 \end{pmatrix}, \begin{pmatrix} 0 & 0 \\ 1 & 0 \end{pmatrix}, \begin{pmatrix} 0 & 0 \\ 0 & 1 \end{pmatrix} \right\}$$

is linearly independent. Also,

$$S = \left\{ \begin{pmatrix} 1 & 0 \\ 0 & 1 \end{pmatrix}, \begin{pmatrix} 0 & 1 \\ 1 & 0 \end{pmatrix}, \begin{pmatrix} 0 & -i \\ i & 0 \end{pmatrix}, \begin{pmatrix} 1 & 0 \\ 0 & -1 \end{pmatrix} \right\}$$
$$= \left\{ \sigma_0, \sigma_1, \sigma_2, \sigma_3 \right\}$$

forms a basis for Mat<sub>2</sub> ( $\mathbb{C}$ ). The set  $\sigma_1$ ,  $\sigma_2$ ,  $\sigma_3$  are known as the Pauli matrices.

**Example** (Vector Spaces of Polynomials). Consider the set of polynomials with degree n,  $\mathcal{P}_n$ . An element of  $\mathcal{P}_n$  is written

$$P_n(x) = a_n x^n + a_{n-1} x^{n-1} + \dots + a_1 x + a_0.$$

This is *not* closed under addition, since we can subtract two polynomials to yield a polynomial with degree n - 1. However, the set of polynomials with degree *at most* n is closed under n.

A basis for 
$$\mathcal{P}_n$$
 is  $\mathcal{B} = \{1, x, x^2, \dots, x^n\}$ .

**Example** (Vector Spaces of Periodic Functions). Consider the set of functions f such that f(x + T) = f(x) for some fixed period T. This *is* a vector space, since we can add two functions with the same period to yield another function with that same period.

Finding a basis is much more difficult. However, we know that sine and cosine have a periodicity. In particular,  $\sin(2\pi n/T)$  and  $\cos(2\pi n/T)$  can form a Schauder basis for the set of functions with period T.

$$f(t) = \sum_{n=0}^{\infty} a_n \cos(2\pi n t/T) + b_n \sin(2\pi n t/T).$$

However, when we have infinitely many dimensions, we run into issues of convergence, which we will deal with in a future part of this course. XXIII

#### **Kets and Reps**

Since vectors are not universally arrows (as vectors are elements of vector spaces), we want to find a universal way to represent vectors that is not  $\mathbf{v}$  or  $\vec{v}$ .

**Definition** (Ket). Let V be a vector space. Any element of V is written as  $|v\rangle$ .

XXIII Presumably very poorly, because this isn't a math class.

For a basis  $\{|e_i\rangle\}_{i\in I}$ , we abbreviate it as  $|i\rangle$ .

We express  $|v\rangle$  on a basis as follows.

$$|v\rangle = \sum_{i=1}^{n} v_i |i\rangle$$
$$= v_1 |1\rangle + v_2 |2\rangle + \dots + v_n |n\rangle.$$

We can express addition of  $|v\rangle$  and  $|w\rangle$  on a common basis as follows.

$$|v\rangle + |w\rangle = \sum_{i=1}^{n} v_{i} |i\rangle + w_{i} |i\rangle$$
$$= \sum_{i=1}^{n} (v_{i} + w_{i}) |i\rangle$$
$$= |v + w\rangle.$$

Scalar multiplication works as follows

$$c |v\rangle = \sum_{i=1}^{n} cv_{i} |i\rangle$$
$$= |cv\rangle$$

Note that we use 0 to denote the zero vector in V, rather than  $|0\rangle$ , which we use to denote a concrete basis vector.

**Example** (Representing Vectors). Let  $\{|0\rangle, |1\rangle, |2\rangle, |3\rangle\}$  be a four-dimensional basis. Let

$$|P\rangle = 2|0\rangle - |1\rangle + 3|2\rangle + |3\rangle$$
.

We can let  $|P\rangle$  be abstract, or create a concrete representation. For instance, if we take

$$|i\rangle = x^i$$

for each  $i \in \{0, 1, 2, 3\}$ , then

$$P(x) = x^3 + 3x^2 - x + 2$$
.

However, if we take  $|i\rangle = \sigma_i$ , where  $\sigma_i$  are the Pauli matrices, then we get

$$|P\rangle = \begin{pmatrix} 3 & -1 - 3i \\ -1 + 3i & 1 \end{pmatrix}.$$

We can also take  $|i\rangle = e_{i+1}$ , where  $e_j$  represents the standard basis in  $\mathbb{C}^4$ . This representation yields

$$|P\rangle = \begin{pmatrix} 2\\-1\\3\\1 \end{pmatrix}.$$

## **Inner Products**

We have yet to define the "multiplication" of vectors. In order to do this, taking  $|A\rangle$  and  $|B\rangle$ , we let  $\langle A|B\rangle$  be the inner product on  $|A\rangle$  and  $|B\rangle$ . Note that  $\langle A|B\rangle$  is a scalar.

We will delay the formal definition of an inner product; we will start by discussing a more intuitive definition of inner products.

## **Adjoints**

First, let's try to figure out why  $\langle A|B \rangle \neq |A \rangle \cdot |B \rangle$  generally.

In  $\mathbb{R}^2$ , however,  $\langle A|B\rangle = |A\rangle \cdot |B\rangle$ . We represent

$$\mathbf{A} = \begin{pmatrix} a_1 \\ a_2 \end{pmatrix}$$
$$\mathbf{B} = \begin{pmatrix} b_1 \\ b_2 \end{pmatrix},$$

and

$$\langle A|B\rangle = \mathbf{A}^{\mathsf{T}}\mathbf{B}$$
$$= (\alpha_1 \quad \alpha_2) \begin{pmatrix} b_1 \\ b_2 \end{pmatrix}$$
$$= \sum_{i} \alpha_i b_i.$$

Note that we need to take the transpose of **A**. This seems trivial in  $\mathbb{R}^n$ , since  $\mathbf{A} \cdot \mathbf{B} = \mathbf{B} \cdot \mathbf{A}$  over the real numbers.

However, over  $\mathbb{C}^n$ , things become slightly different. Note that the norm

$$||\mathbf{A}|| = \langle A|A\rangle$$
  
$$\geq 0$$

for all  $A \in \mathbb{C}^n$ . Using the traditional transpose on A, we would get

$$A^{\mathsf{T}}A = \begin{pmatrix} \alpha_1 & \cdots & \alpha_n \end{pmatrix} \begin{pmatrix} \alpha_1 \\ \vdots \\ \alpha_n \end{pmatrix}$$
$$= \sum_{i=1}^n \alpha_i^2,$$

which is not necessarily in  $[0, \infty)$  (let alone  $A^TA$  is a norm).

Therefore, we need to take the conjugate of  $A^{T}$ ,  $A^{*xxiv}$  in order to use the inner product.

$$\langle A|A\rangle = \overline{\left(\alpha_1 \quad \cdots \quad \alpha_n\right)} \begin{pmatrix} \alpha_1 \\ \vdots \\ \alpha_n \end{pmatrix}$$

$$= \sum_{i \in I} |\alpha_i|^2.$$

In the general case, we take

$$\langle A|B\rangle = A^*B$$
  
=  $\sum_{i} \overline{a_i}b_i$ .

xxivThe physicists use † instead of \* to denote the conjugate transpose, but they're wrong. I will also begin using  $\overline{z}$  to denote the complex conjugate now.

We let  $A^*$  be the Hermitian adjoint for A.

Note that, with this definition, we now have

$$\begin{split} \langle A|B\rangle &= \sum_{i} \overline{\alpha_{i}} b_{i} \\ &= \overline{\left(\sum_{i} \alpha_{i} \overline{b_{i}}\right)} \\ &= \overline{\langle B|A\rangle}, \end{split}$$

meaning the inner product is also *conjugate symmetric*. Additionally,  $A^{**} = A.^{XXV}$ 

Note that since  $\langle A|B\rangle = \overline{\langle B|A\rangle}$  is an equality, this means the inner product is basis-independent.

In matrices, we have

$$M_{ij}^* = \overline{M_{ji}}.$$

Example. Let

$$v = \begin{pmatrix} -1\\2 \end{pmatrix}$$
$$w = \begin{pmatrix} 1\\-i \end{pmatrix}.$$

Then,

$$\langle v|w\rangle = -1 - 2i$$
  
 $\langle w|v\rangle = -1 + 2i$ .

Example. Let

$$S = \begin{pmatrix} i & -1 \\ 1 & i \end{pmatrix}$$
$$T = \begin{pmatrix} 1 & 2i \\ -i & 1 \end{pmatrix}.$$

Then,

$$S^* = \begin{pmatrix} -i & 1 \\ -1 & i \end{pmatrix}$$
$$T^* = \begin{pmatrix} 1 & i \\ -2i & 1 \end{pmatrix}.$$

We can see that

$$(ST)^* = \begin{pmatrix} -2i & 2\\ -3 & -3i \end{pmatrix}$$
$$= T^*S^*$$

**Definition** (Dirac Notation). Let V be a vector space.

We denote any vector in V by  $|v\rangle$ , and its adjoint,  $|v\rangle^* = \langle v|$  the unique linear functional such that

$$|v\rangle^*(|w\rangle) = \langle v|w\rangle$$
.

Note that for any  $|v\rangle \in V$ ,  $\langle v| \in V^*$  necessarily exists by the Riesz representation theorem.

xxvWe refer to the \* operation as an involution.

**Example** (Vector Space of Kets and Bras). Note that we have

$$|v + w\rangle = |v\rangle + |w\rangle$$
,

and similarly,

$$\langle v + w | = \langle v | + \langle w |$$
,.

However, unlike in kets, where we have

$$|cv\rangle = c |v\rangle$$
,

for bras, we have

$$\langle cv | = |cv \rangle^*$$
  
=  $\overline{c} |v \rangle^*$   
=  $\overline{c} \langle v |$ .

We can generalize to application by any linear operator.

**Example** (Linear Operators on Kets and Bras). We can take  $\mathcal{L}$  to be some linear operator, giving

$$|w\rangle = \mathcal{L} |v\rangle$$
.

When it comes to bras, though, we get

$$\langle w| = |w\rangle^*$$

$$= (\mathcal{L}|v\rangle)^*$$

$$= |v\rangle^* \mathcal{L}^*$$

$$= \langle v| \mathcal{L}^*.$$

Similarly, we can define

$$\begin{split} |w\rangle &= |\mathcal{L}v\rangle \\ &= \mathcal{L} \, |v\rangle \,, \end{split}$$

and

$$\langle w | = \langle \mathcal{L}v |$$
  
=  $\langle v | \mathcal{L}^*$ .

**Definition** (The Adjoint through Inner Products). Let  $\mathcal{L}$  be a linear operator. The adjoint,  $\mathcal{L}^*$ , is the unique linear operator such that

$$\langle v | \mathcal{L}w \rangle = \langle \mathcal{L}^* v | w \rangle$$

or, equivalently,

$$\overline{\langle v | \mathcal{L} | w \rangle} = \langle w | \mathcal{L}^* | v \rangle$$

**Definition** (Hermitian Operator). A linear operator  $\mathcal{L}$  is known as Hermitian (or self-adjoint) if  $\mathcal{L}^* = \mathcal{L}$ .

Example. Let

$$v = \begin{pmatrix} -1 \\ 2 \end{pmatrix}$$

$$w = \begin{pmatrix} 1 \\ -i \end{pmatrix}$$
$$S = \begin{pmatrix} i & -1 \\ 1 & i \end{pmatrix}.$$

Then,

$$\overline{\langle v | S | w \rangle} = \langle v | Sw \rangle$$

$$= \overline{\left[ \overline{(-1 \quad 2)} \begin{pmatrix} i & -1 \\ 1 & i \end{pmatrix} \begin{pmatrix} 1 \\ -i \end{pmatrix} \right]}$$

$$= 4 + 2i$$

$$\langle w | S^* | v \rangle = \langle w | S^* v \rangle$$

$$= \overline{(1 \quad -i)} \begin{pmatrix} -i & 1 \\ -1 & -i \end{pmatrix} \begin{pmatrix} -1 \\ 2 \end{pmatrix}$$

$$= 4 + 2i.$$

**Example** (A Hermitian Operator). The matrix

$$A = \begin{pmatrix} 1 & i \\ -i & 3 \end{pmatrix}$$

is a Hermitian operator.

## Cauchy-Schwarz Inequality

**Definition** (Inner Product Space). An inner product space is a vector space with an additional operation which takes two vectors,  $|v\rangle$  and  $|w\rangle$  such that the following are true.

- (1) Positive definite norm:  $\langle v|v\rangle = ||v||^2$ .
- (2) Conjugate symmetry:  $\langle v|w\rangle = \overline{\langle w|v\rangle}$ .
- (3) Linearity:  $\langle \mathbf{u} | (\mathbf{a} | \mathbf{v}) + \mathbf{b} | \mathbf{w} \rangle = \mathbf{a} \langle \mathbf{u} | \mathbf{v} \rangle + \mathbf{b} \langle \mathbf{u} | \mathbf{w} \rangle$ .

Consider  $|A\rangle$ ,  $|B\rangle$  be vectors, and let

$$\langle A|B\rangle = e^{i\phi} |\langle A|B\rangle|.$$

Define

$$|C\rangle = se^{i\phi} |A\rangle + |B\rangle$$

for some  $s \in \mathbb{R}$ . Then, we have

$$\langle C| = se^{-i\phi} \langle A| + \langle B|,$$

meaning

$$\begin{split} \langle C|C\rangle &= s^2 \, \langle A|A\rangle + s e^{-i\,\varphi} \, \langle A|B\rangle + s e^{i\,\varphi} \, \langle B|A\rangle + \langle B|B\rangle \\ &= s^2 \, \langle A|A\rangle + 2s \, \text{Re} \left( e^{-\varphi} \, \langle A|B\rangle \right) + \langle B|B\rangle \\ &= s^2 \, \langle A|A\rangle + 2s \, |\langle A|B\rangle| + \langle B|B\rangle \, . \end{split}$$

Since  $\langle C|C\rangle \geqslant 0$  necessarily, it is the case that

$$|\langle A|B\rangle|^2 \le \langle A|A\rangle \langle A|A\rangle$$
.

**Definition** (Cauchy–Schwarz Inequality). Let V be an inner product space, and let A,  $B \in V$ . Then,

$$|\langle A|B\rangle| \le ||A|| ||B||.$$

**Example.** In  $\mathbb{C}^n$ , the Cauchy–Schwarz inequality becomes

$$\left| \sum_{i=1}^{n} \overline{a_i} b_i \right|^2 \leqslant \left( \sum_{i=1}^{n} |a_i|^2 \right) \left( \sum_{i=1}^{n} |b_i|^2 \right).$$

From the Cauchy–Schwarz inequality, we can find a limit on the norm of A + B.

$$\|\mathbf{A} + \mathbf{B}\|^{2} = \langle A + B|A + B \rangle$$

$$= \langle A|A \rangle + \langle B|B \rangle + \langle A|B \rangle + \langle B|A \rangle$$

$$= \langle A|A \rangle + \langle B|B \rangle + 2 \operatorname{Re} (\langle A|B \rangle)$$

$$\leq \langle A|A \rangle + \langle B|B \rangle + 2 |\langle A|B \rangle|$$

$$\leq \langle A|A \rangle + \langle B|B \rangle + 2 ||\mathbf{A}|| ||\mathbf{B}||$$

$$= (||\mathbf{A}|| + ||\mathbf{B}||)^{2}.$$

Thus, we recover the triangle inequality.

**Definition** (Triangle Inequality). Let  $A, B \in V$ , where V is any normed vector space. Then,

$$||A + B|| \le ||A|| + ||B||.$$

We define  $\cos \theta = \frac{|\langle A|B \rangle|}{||A||||B||}$ . The geometric interpretation of  $\langle A|B \rangle$  is, then, the projection of  $|B \rangle$  onto  $|A \rangle$ .

Note that the inner product, norm, and the Cauchy-Schwarz inequality are completely basis-independent.

#### **Orthonormal Sets and Bases**

Now that we have shown that the inner product is basis-independent, we can select a basis to make our lives a lot easier. Specifically, we can select  $\{|\hat{e}_i\rangle\}_{i\in I}$  to be a (Schauder) basis such that

$$\langle \hat{e}_i | \hat{e}_j \rangle = \delta_{ij}$$
.

In the case of the inner product between two vectors, this basis collapses to yield the standard inner product on  $\mathbb{C}^n$ :

$$\begin{split} \langle A|B\rangle &= \sum_{i,j} \overline{\alpha_i} b_j \left\langle \hat{e}_i \middle| \hat{e}_j \right\rangle \\ &= \sum_i \overline{\alpha_i} b_i. \end{split}$$

For instance, the standard basis on  $\mathbb{C}^2$  is

$$\hat{\mathbf{e}}_1 = \begin{pmatrix} 1 \\ 0 \end{pmatrix}$$

$$\hat{\mathbf{e}}_2 = \begin{pmatrix} 0 \\ 1 \end{pmatrix}.$$

Example (A Non-Standard Basis). Let

$$|\epsilon_{1,2}\rangle = \frac{1}{\sqrt{2}} (\pm |\hat{e}_1\rangle + |e_2\rangle).$$

Then,

$$\begin{split} \left\langle \varepsilon_{1,2} \middle| \varepsilon_{1,2} \right\rangle &= \frac{1}{\sqrt{2}} \frac{1}{\sqrt{2}} \left( \pm \left\langle \hat{e}_{1} \middle| + \left\langle \hat{e}_{2} \middle| \right) \left( \middle| \hat{e}_{1} \right\rangle + \middle| \hat{e}_{2} \right\rangle \right) \\ &= \frac{1}{2} \left( \left\langle \hat{e}_{1} \middle| \hat{e}_{1} \right\rangle + \left\langle \hat{e}_{1} \middle| \hat{e}_{2} \right\rangle + \left\langle \hat{e}_{2} \middle| \hat{e}_{1} \right\rangle + \left\langle \hat{e}_{2} \middle| \hat{e}_{2} \right\rangle \right) \\ &= 1. \\ \left\langle \varepsilon_{1} \middle| \varepsilon_{2} \right\rangle &= \frac{1}{\sqrt{2}} \frac{1}{\sqrt{2}} \left( \left\langle \hat{e}_{1} \middle| + \left\langle \hat{e}_{2} \middle| \right) \left( - \middle| \hat{e}_{1} \right\rangle + \middle| \hat{e}_{2} \right\rangle \right) \\ &= \frac{1}{2} \left( - \left\langle \hat{e}_{1} \middle| \hat{e}_{1} \right\rangle + \left\langle \hat{e}_{1} \middle| \hat{e}_{2} \right\rangle - \left\langle \hat{e}_{1} \middle| \hat{e}_{2} \right\rangle + \left\langle \hat{e}_{2} \middle| \hat{e}_{2} \right\rangle \right) \\ &= 0. \end{split}$$

Example (Using an Orthonormal Basis). With the previous example, we have

$$|\hat{\epsilon}_1\rangle = \frac{1}{\sqrt{2}} \begin{pmatrix} 1\\1 \end{pmatrix}$$
$$|\hat{\epsilon}_2\rangle = \frac{1}{\sqrt{2}} \begin{pmatrix} -1\\1 \end{pmatrix}.$$

Consider the vectors

$$|v\rangle = \begin{pmatrix} -1\\2 \end{pmatrix}$$
$$|w\rangle = \begin{pmatrix} 1\\-i \end{pmatrix}.$$

We wish to expand these vectors along the  $\{|\epsilon_1\rangle, |\epsilon_2\rangle\}$  basis.

To do this, we can project using the inner product's projection properties:

$$v_{1} = \langle \hat{\epsilon}_{1} | v \rangle$$

$$= \frac{1}{\sqrt{2}} \overline{(1 - 1)} \begin{pmatrix} -1\\2 \end{pmatrix}$$

$$= \frac{1}{\sqrt{2}}$$

$$v_{2} = \langle \hat{\epsilon}_{2} | v \rangle$$

$$= \frac{1}{\sqrt{2}} \overline{(-1 - 1)} \begin{pmatrix} -1\\2 \end{pmatrix}$$

$$= \frac{3}{\sqrt{2}}$$

$$v = \frac{1}{\sqrt{2}} |\hat{\epsilon}_{1}\rangle + \frac{3}{\sqrt{2}} |\hat{\epsilon}_{2}\rangle$$

$$w_{1} = \langle \hat{\epsilon}_{1} | w \rangle$$

$$= \frac{1}{\sqrt{2}} \overline{(1 - 1)} \begin{pmatrix} 1\\-i \end{pmatrix}$$

$$= (1 - i) \frac{1}{\sqrt{2}}$$

$$w_{2} = \langle \hat{\epsilon}_{2} | w \rangle$$

$$= \frac{1}{\sqrt{2}} \overline{(-1 \quad 1)} \begin{pmatrix} 1 \\ -i \end{pmatrix}$$
$$= (-1 - i) \frac{1}{\sqrt{2}}$$
$$w = \frac{1 - i}{\sqrt{2}} |\hat{\epsilon}_1\rangle + \frac{-1 - i}{\sqrt{2}} |\hat{\epsilon}_2\rangle.$$

**Example** (Using a Complex-Valued Basis). Consider the basis

$$\begin{aligned} |\hat{e}_{\mathrm{I}}\rangle &= \frac{1}{\sqrt{5}} \begin{pmatrix} 1\\2\mathrm{i} \end{pmatrix} \\ |\hat{e}_{\mathrm{II}}\rangle &= \frac{1}{\sqrt{5}} \begin{pmatrix} 2\\-\mathrm{i} \end{pmatrix}. \end{aligned}$$

This is an orthonormal basis.

$$\langle \hat{\mathbf{e}}_{\mathrm{I}} | \hat{\mathbf{e}}_{\mathrm{II}} \rangle = \frac{1}{\sqrt{5}} \frac{1}{\sqrt{5}} \begin{pmatrix} 1 & -2i \end{pmatrix} \begin{pmatrix} 2 \\ -i \end{pmatrix}$$
  
= 0.

The components of a vector

$$|A\rangle = \begin{pmatrix} a_1 \\ a_2 \end{pmatrix}$$

on this basis are

$$\begin{split} \alpha_{\rm I} &= \left\langle \hat{e}_{\rm I} \middle| A \right\rangle \\ &= \frac{1}{\sqrt{5}} \overline{\left(1 - 2i\right)} \begin{pmatrix} \alpha_1 \\ \alpha_2 \end{pmatrix} \\ &= \frac{\alpha_1 - 2i\alpha_2}{\sqrt{5}} \\ \alpha_{\rm II} &= \left\langle \hat{e}_{\rm II} \middle| A \right\rangle \\ &= \frac{1}{\sqrt{5}} \overline{\left(2 - i\right)} \begin{pmatrix} \alpha_1 \\ \alpha_2 \end{pmatrix} \\ &= \frac{2\alpha_1 + i\alpha_2}{\sqrt{5}} \\ A &= \left( \frac{\alpha_1 - 2i\alpha_2}{\sqrt{5}} \right) \middle| \hat{e}_{\rm II} \right\rangle + \left( \frac{2\alpha_1 + i\alpha_2}{\sqrt{5}} \right) \middle| \hat{e}_{\rm II} \right\rangle. \end{split}$$

We can see that

$$||A||^2 = |a_1|^2 + |a_2|^2$$
.

It can also be shownXXVI that

$$||A||^2 = |a_I|^2 + |a_{II}|^2$$
  
=  $|a_1|^2 + |a_2|^2$ .

xxvII will not show this, though, because I don't want to.

## **Example.** Consider the vectors

$$|\epsilon_1\rangle = \begin{pmatrix} 1\\1\\1 \end{pmatrix}$$

$$|\epsilon_2\rangle = \begin{pmatrix} 1\\-2\\1 \end{pmatrix}$$

$$|\epsilon_3\rangle = \begin{pmatrix} 1\\0\\-1 \end{pmatrix}.$$

This is an orthogonal basis, but not an orthonormal basis. To normalize these vectors, we divide out by the magnitude.

$$|\hat{\epsilon}_1\rangle = \frac{1}{\sqrt{3}} \begin{pmatrix} 1\\1\\1 \end{pmatrix}$$

$$|\hat{\epsilon}_2\rangle = \frac{1}{\sqrt{6}} \begin{pmatrix} 1\\-2\\1 \end{pmatrix}$$

$$|\hat{\epsilon}_3\rangle = \frac{1}{\sqrt{2}} \begin{pmatrix} 1\\0\\-1 \end{pmatrix}.$$

We project the arbitrary vector

$$A = \begin{pmatrix} a_1 \\ a_2 \\ a_3 \end{pmatrix}$$

onto each basis element to obtain a new representation.

$$\begin{split} \langle \hat{\varepsilon}_1 | A \rangle &= \frac{1}{\sqrt{3}} \left( \alpha_1 + \alpha_2 + \alpha_3 \right) \\ \langle \hat{\varepsilon}_2 | A \rangle &= \frac{1}{\sqrt{6}} \left( \alpha_1 - 2\alpha - 2 + \alpha_3 \right) \\ \langle \hat{\varepsilon}_3 | A \rangle &= \frac{1}{\sqrt{2}} \left( \alpha_1 - \alpha_3 \right). \end{split}$$

Thus, we can write

$$A = \frac{a_1 + a_2 + a_3}{\sqrt{3}} |\hat{\epsilon}_1\rangle + \frac{a_1 - 2a_2 + a_3}{\sqrt{6}} |\hat{\epsilon}_2\rangle + \frac{a_1 - a_3}{\sqrt{2}} |\hat{\epsilon}_3\rangle.$$

We can actually write in terms of the non-normalized basis, by dividing each  $|\hat{\varepsilon}_i\rangle$  by its corresponding normalization constant.

$$A = \frac{\alpha_1 + \alpha_2 + \alpha_3}{3} |\epsilon_1\rangle + \frac{\alpha_1 - 2\alpha_2 + \alpha_3}{6} |\epsilon_2\rangle + \frac{\alpha_1 - \alpha_3}{2} |\epsilon_3\rangle$$

**Example** (Pauli Basis). Consider the three Pauli matrices

$$\sigma_1 = \begin{pmatrix} 0 & 1 \\ 1 & 0 \end{pmatrix}$$

$$\begin{split} \sigma_2 &= \begin{pmatrix} 0 & -i \\ i & 0 \end{pmatrix} \\ \sigma_3 &= \begin{pmatrix} 1 & 0 \\ 0 & -1 \end{pmatrix}. \end{split}$$

We can construct an inner product on these matrices. Specifically, we see that the Frobenius inner product xxv

$$\langle \sigma_{i} | \sigma_{j} \rangle = \operatorname{tr} (\sigma_{i}^{*} \sigma_{j})$$
  
=  $2\delta_{ij}$ ,

meaning that we need to redefine our inner product. Specifically, we take

$$\left\langle \sigma_{i} \middle| \sigma_{j} \right\rangle = \frac{1}{2} \operatorname{tr} \left( \sigma_{i}^{*} \sigma_{j} \right).$$

Note that with the Pauli matrices,  $\sigma_i^* = \sigma_j$ . If we add

$$\sigma_0 = \begin{pmatrix} 1 & 0 \\ 0 & 1 \end{pmatrix},$$

we now form a complete orthonormal basis in  $Mat_2(\mathbb{C})$ .

If A is any complex-valued matrix, then

$$A = \sum_{\alpha=0}^{3} \alpha_{\alpha} \sigma_{\alpha}$$

$$= \sum_{\alpha=0}^{3} \langle \sigma_{\alpha} | A \rangle \sigma_{\alpha}$$

$$= \sum_{\alpha=0}^{3} \frac{1}{2} \operatorname{tr} (\sigma_{\alpha}^{*} A) \sigma_{\alpha}.$$

$$= \frac{1}{2} \operatorname{tr}(A) I_{2} + \frac{1}{2} \sum_{i=1}^{3} \operatorname{tr} (\sigma_{i}^{*} A) \sigma_{i}.$$

One of the interesting applications of the Pauli basis is that, using the Pauli basis, we can represent any  $\mathbf{v} \in \mathbb{R}^3$  and represent with the Pauli matrices.

$$V = \sum_{i=1}^{3} v_i \sigma_i$$

$$= \sum_{i=1}^{3} \langle \sigma_i | v \rangle$$

$$= \begin{pmatrix} v_z & v_x - i v_y \\ v_x + i v_y & -v_z \end{pmatrix}.$$

Note that  $V = V^*$  and tr(V) = 0. Thus, using the Pauli basis, we can express any 3-dimensional vector as a trace-free Hermitian matrix.

 $xxvII\langle A|B\rangle = tr(A^*B)$ 

## Constructing an Orthonormal Basis: Gram-Schmidt Decomposition

The ultimate question behind linear algebra is what basis to choose.

However, even if we are given a basis, it may not be an orthonormal basis.

**Method.** Consider a set of n linearly independent vectors in  $\mathbb{C}^n$ ,  $\{|\phi_1\rangle, |\phi_n\rangle, \dots, |\phi_n\rangle\}$ . From these n vectors, we want to create a set of n orthonormal vectors.

Starting with  $|\phi_1\rangle$ , we normalize to make

$$|\hat{e}_1\rangle = \frac{|\phi_1\rangle}{\sqrt{\langle\phi_1|\phi_1\rangle}}.$$

To get  $|\hat{e}_2\rangle$ , we take  $|\phi_2\rangle$  and remove the component of  $|\phi_2\rangle$  along the "direction" of  $|\hat{e}_1\rangle$ . This gives us

$$|e_2\rangle = |\phi_2\rangle - \langle \hat{e}_1 |\phi_2\rangle |\hat{e}_1\rangle$$
.

Now, we normalize to get

$$|\hat{e}_2\rangle = \frac{|e_2\rangle}{\sqrt{\langle e_2|e_2\rangle}}.$$

Note that

$$\begin{split} \langle \hat{e}_1 | \hat{e}_2 \rangle &= \langle \hat{e}_1 | \varphi_2 \rangle - \langle \hat{e}_1 | \varphi_2 \rangle \langle \hat{e}_1 | \hat{e}_1 \rangle \\ &= 0. \end{split}$$

For  $|\hat{e}_3\rangle$ , we start by taking  $|\phi_3\rangle$ , removing the components along the  $|\hat{e}_1\rangle$  and  $|\hat{e}_2\rangle$  directions, giving

$$|e_3\rangle = |\phi_3\rangle - \langle \hat{e}_1|\phi_3\rangle |\hat{e}_1\rangle - \langle \hat{e}_2|\phi_3\rangle |\hat{e}_2\rangle.$$

Normalizing, we get

$$|\hat{e}_3\rangle = \frac{|e_3\rangle}{\sqrt{\langle e_3|e_3\rangle}}.$$

In the general form, we have

$$\begin{split} |e_{m}\rangle &= |\varphi_{m}\rangle - \sum_{\ell=1}^{m-1} \langle \hat{e}_{\ell} | \varphi_{m} \rangle \, |\hat{e}_{\ell} \rangle \\ |\hat{e}_{m}\rangle &= \frac{|e_{m}\rangle}{\sqrt{\langle e_{m} | e_{m}\rangle}}. \end{split}$$

**Example.** Consider the vectors

$$|\phi_1\rangle = \begin{pmatrix} 1\\ -i\\ 1 \end{pmatrix}$$

$$|\phi_2\rangle = \begin{pmatrix} i\\ 0\\ i \end{pmatrix}$$

$$|\phi_3\rangle = \begin{pmatrix} 1\\ i\\ -1 \end{pmatrix}.$$

This set is linearly independent. We start with

$$|\hat{\mathbf{e}}_1\rangle = \frac{1}{\sqrt{3}} \begin{pmatrix} 1\\ -i\\ 1 \end{pmatrix}.$$

Then,

$$\begin{split} |e_2\rangle &= |\varphi_2\rangle - \langle \hat{e}_1 |\varphi_2\rangle \, |\hat{e}_1\rangle \\ &= \begin{pmatrix} i \\ 0 \\ i \end{pmatrix} - \left[ \overline{\left(\frac{1}{\sqrt{3}}\right) (1 \quad -i \quad 1)} \begin{pmatrix} i \\ 0 \\ i \end{pmatrix} \right] \left(\frac{1}{3}\right) \begin{pmatrix} 1 \\ -i \\ 1 \end{pmatrix} \\ &= \begin{pmatrix} i \\ 0 \\ i \end{pmatrix} - \frac{2i}{3} \begin{pmatrix} 1 \\ -i \\ 1 \end{pmatrix} \\ &= \frac{1}{3} \begin{pmatrix} i \\ -2 \\ i \end{pmatrix}. \end{split}$$

Normalizing, we get

$$|\hat{e}_2\rangle = \frac{1}{\sqrt{6}} \begin{pmatrix} i \\ -2 \\ i \end{pmatrix}.$$

Finally, to get  $|\hat{e}_3\rangle$ , we take

$$\begin{split} |e_3\rangle &= |\varphi_3\rangle - \langle \hat{e}_1 |\varphi_3\rangle \, |\hat{e}_1\rangle - \langle \hat{e}_2 |\varphi_3\rangle \, |\hat{e}_2\rangle \\ &= \begin{pmatrix} 1\\ \mathrm{i}\\ -1 \end{pmatrix} - \left[ \frac{1}{\sqrt{3}} \overline{\begin{pmatrix} 1\\ -\mathrm{i} \end{pmatrix}} \right] \begin{pmatrix} 1\\ \mathrm{i}\\ -1 \end{pmatrix} \right] \begin{pmatrix} 1\\ \mathrm{i}\\ -1 \end{pmatrix} - \left[ \frac{1}{\sqrt{6}} \overline{\begin{pmatrix} \mathrm{i}\\ \mathrm{i} \end{pmatrix} - 2 \quad \mathrm{i} \right] \begin{pmatrix} 1\\ \mathrm{i}\\ -1 \end{pmatrix} \right] \begin{pmatrix} \mathrm{i}\\ -2\\ \mathrm{i} \end{pmatrix} \\ &= \begin{pmatrix} 1\\ 0\\ -1 \end{pmatrix}. \end{split}$$

Thus,

$$|\hat{e}_3\rangle = \frac{1}{\sqrt{2}} \begin{pmatrix} 1\\0\\-1 \end{pmatrix}.$$

The orthonormal basis is, as follows:

$$|\hat{e}_1\rangle = \frac{1}{\sqrt{3}} \begin{pmatrix} 1\\ -i\\ 1 \end{pmatrix}$$

$$|\hat{e}_2\rangle = \frac{1}{\sqrt{6}} \begin{pmatrix} i \\ -2 \\ i \end{pmatrix}$$

$$|\hat{e}_3\rangle = \frac{1}{\sqrt{2}} \begin{pmatrix} 1\\0\\-1 \end{pmatrix}.$$

Example (Gram-Schmidt with Matrices). Let

$$|M_1\rangle = \begin{pmatrix} 1 & 1 \\ 1 & 1 \end{pmatrix}$$

$$|M_2\rangle = \begin{pmatrix} 0 & i \\ i & 0 \end{pmatrix}$$

$$|M_3\rangle = \begin{pmatrix} 1 & 0 \\ 0 & i \end{pmatrix}$$

$$|M_4\rangle = \begin{pmatrix} 0 & -1 \\ 1 & 0 \end{pmatrix}.$$

These matrices are linearly independent, but it is not the case that

$$\begin{split} \left\langle M_{i} \middle| M_{j} \right\rangle &= \frac{1}{2} \operatorname{tr} \left( M_{i}^{*} M_{j} \right) \\ &\neq \delta_{ij}. \end{split}$$

Let

$$\begin{split} |\hat{e}_1\rangle &= \frac{|M_1\rangle}{\||M_1\rangle\|} \\ &= \begin{pmatrix} 1 & 1\\ 1 & 1 \end{pmatrix} \frac{1}{\sqrt{\frac{1}{2}\operatorname{tr}\left(M_1^*M_1\right)}} \\ &= \frac{1}{\sqrt{2}} \begin{pmatrix} 1 & 1\\ 1 & 1 \end{pmatrix}. \end{split}$$

Then, we have

$$\begin{split} |e_2\rangle &= |M_2\rangle - \langle \hat{e}_1|M_2\rangle \, |\hat{e}_1\rangle \\ &= \begin{pmatrix} 0 & \mathrm{i} \\ \mathrm{i} & 0 \end{pmatrix} - \frac{1}{2} \operatorname{tr} \left( \hat{e}_1^* M_2 \right) \, \frac{1}{\sqrt{2}} \begin{pmatrix} 1 & 1 \\ 1 & 1 \end{pmatrix} \\ &= \begin{pmatrix} 0 & \mathrm{i} \\ \mathrm{i} & 0 \end{pmatrix} - \frac{\mathrm{i}}{2} \begin{pmatrix} 1 & 1 \\ 1 & 1 \end{pmatrix} \\ &= \frac{\mathrm{i}}{2} \begin{pmatrix} -1 & 1 \\ 1 & -1 \end{pmatrix}. \end{split}$$

Normalizing, we get

$$\begin{split} |\hat{e}_2\rangle &= \frac{|e_2\rangle}{\||e_2\rangle\|} \\ &= \frac{\mathrm{i}}{\sqrt{2}} \begin{pmatrix} -1 & 1\\ 1 & -1 \end{pmatrix}. \end{split}$$

Continuing, we get

$$\begin{aligned} |\hat{e}_3\rangle &= \frac{1-i}{\sqrt{2}} \begin{pmatrix} 1 & 0\\ 0 & -1 \end{pmatrix} \\ |\hat{e}_4\rangle &= \begin{pmatrix} 0 & -1\\ 1 & 0 \end{pmatrix}. \end{aligned}$$

## Completeness

The most important fact of a basis is that it can support any vector in V.

$$|v\rangle = \sum_{i=1}^{n} \langle \hat{e}_{i} | v \rangle | \hat{e}_{i} \rangle.$$

This is redundant in finite dimensions, but in infinite dimensions, we actually need our basis to support any vector.

Consider

$$\begin{split} |A\rangle &= \sum_{\ell} \alpha_{\ell} \, |\hat{e}_{\ell}\rangle \\ &= \sum_{\ell} \, \langle \hat{e}_{\ell} |A\rangle \, |\hat{e}_{\ell}\rangle \, . \end{split}$$

Since  $\langle \hat{e}_{\ell} | A \rangle$  is a number, we can switch the order, yielding

$$\begin{split} &= \sum_{\ell} |\hat{e}_{\ell}\rangle \langle \hat{e}_{\ell} | A \rangle \\ &= \left( \sum_{\ell} |\hat{e}_{\ell}\rangle \langle \hat{e}_{\ell} | \right) | A \rangle \\ &= I_{n} | A \rangle. \end{split}$$

**Definition** (Completeness Relation). The completeness relation states

$$\sum_{\ell} \left| \hat{e}_{\ell} \right\rangle \left\langle \hat{e}_{\ell} \right| = i d_{V} \, . \label{eq:epsilon}$$

We let  $\mathcal{P}_{\ell} = |\hat{e}_{\ell}\rangle \langle \hat{e}_{\ell}|$  be the projection onto the subspace span  $(|\hat{e}_{\ell}\rangle)$ . Note that

$$\mathcal{P} = \sum_{\ell} \mathcal{P}_{\ell}$$

satisfies the definition of the projection operator,  $\mathcal{P}^2 = \mathcal{P}$ :

$$\begin{split} \mathcal{P}^2 &= \left(\sum_{\ell} \left| \hat{e}_{\ell} \right\rangle \left\langle \hat{e}_{\ell} \right| \right) \left(\sum_{m} \left| \hat{e}_{m} \right\rangle \left\langle \hat{e}_{m} \right| \right) \\ &= \sum_{\ell,m} \left| \hat{e}_{\ell} \right\rangle \left\langle \hat{e}_{\ell} \right| \hat{e}_{m} \right\rangle \left\langle \hat{e}_{m} \right| \\ &= \sum_{\ell,m} \left| \hat{e}_{\ell} \right\rangle \delta_{\ell m} \left\langle \hat{e}_{m} \right| \\ &= \sum_{\ell} \left| \hat{e}_{\ell} \right\rangle \left\langle \hat{e}_{\ell} \right|. \end{split}$$

We sometimes write  $|A\rangle\langle B|$  to be the outer product, which is the unique operator such that, for any  $C\in V$ , we have

$$(|A\rangle \langle B|) |C\rangle = |A\rangle \langle B|C\rangle$$
.

**Example** (Completeness Relation in  $\mathbb{R}^3$ ). Consider

$$|\hat{\mathbf{e}}_1\rangle = \begin{pmatrix} 1\\0\\0 \end{pmatrix}$$

$$|\hat{e}_2\rangle = \begin{pmatrix} 0\\1\\0 \end{pmatrix}$$
$$|\hat{e}_3\rangle = \begin{pmatrix} 0\\0\\1 \end{pmatrix}.$$

Note that we have

$$\begin{aligned} |\hat{e}_{1}\rangle \langle \hat{e}_{1}| &= \begin{pmatrix} 1 & 0 & 0 \\ 0 & 0 & 0 \\ 0 & 0 & 0 \end{pmatrix} \\ |\hat{e}_{2}\rangle \langle \hat{e}_{2}| &= \begin{pmatrix} 0 & 0 & 0 \\ 0 & 1 & 0 \\ 0 & 0 & 0 \end{pmatrix} \\ |\hat{e}_{3}\rangle \langle \hat{e}_{3}| &= \begin{pmatrix} 0 & 0 & 0 \\ 0 & 0 & 0 \\ 0 & 0 & 1 \end{pmatrix}, \end{aligned}$$

so the completeness relation is satisfied.

**Definition** (Complete Orthonormal Basis). A set  $\{|\hat{e}_i\rangle\}_{i\in I}$  of normalized vectors is said to be a complete orthonormal basis if

$$\langle \hat{e}_{i} | \hat{e}_{j} \rangle = \delta_{ij}$$

$$\sum_{i \in I} |\hat{e}_{i}\rangle \langle \hat{e}_{i}| = id.$$

Note that we get

$$\begin{split} |A\rangle &= i d_V |A\rangle \\ &= \left( \sum_\ell |\hat{e}_\ell\rangle \langle \hat{e}_\ell| \right) |A\rangle \\ &= \sum_\ell \langle \hat{e}_\ell|A\rangle |\hat{e}_\ell\rangle \\ &= \sum_\ell \alpha_\ell |\hat{e}_\ell\rangle \,. \end{split}$$

Additionally, this allows us to decompose along any complete basis:

$$\begin{split} |A\rangle &= \sum_{\ell} \alpha_{\ell} \, |\hat{e}_{\ell}\rangle \\ &= \sum_{\ell} \alpha_{\ell} \, id_{V} \, |\hat{e}_{\ell}\rangle \\ &= \sum_{\ell} \alpha_{\ell} \left( \sum_{k} |\hat{\epsilon}_{k}\rangle \, \langle \hat{\epsilon}_{k}| \right) |\hat{e}_{\ell}\rangle \\ &= \sum_{k,\ell} \alpha_{\ell} \, \langle \hat{\epsilon}_{k}|\hat{e}_{\ell}\rangle \, |\hat{\epsilon}_{k}\rangle \\ &= \sum_{k} \underbrace{\left( \sum_{\ell} \alpha_{\ell} \, \langle \hat{\epsilon}_{k}|\hat{e}_{\ell}\rangle \right)}_{\alpha_{k}'} |\hat{\epsilon}_{k}\rangle \end{split}$$

$$= \sum_{k} \alpha'_{k} \left| \hat{\epsilon}_{k} \right\rangle.$$

**Example** (Quantum Mechanics). Fundamental particles like protons, electrons, etc. have an intrinsic angular momentum, known as spin. This angular momentum has a value  $\frac{1}{2}\hbar$ , where  $\hbar = \frac{h}{2\pi}$  is the reduced Planck constant.

We represent

$$|\psi\rangle = a |\hat{e}_{\uparrow}\rangle + b |\hat{e}_{\downarrow}\rangle$$

subject to the fact that

$$E_{\psi} (\uparrow) = \left| \left\langle \hat{e}_{\uparrow} \middle| \psi \right\rangle \right|^{2}$$

$$E_{\psi} (\downarrow) = \left| \left\langle \hat{e}_{\downarrow} \middle| \psi \right\rangle \right|^{2}.$$

However, since we have to measure some probability, we must have

$$\underbrace{\left|\left\langle \hat{e}_{\uparrow} \middle| \psi \right\rangle\right|^{2}}_{|\alpha|^{2}} + \underbrace{\left|\left\langle \hat{e}_{\downarrow} \middle| \psi \right\rangle\right|^{2}}_{|b|^{2}} = \langle \psi \middle| \psi \rangle$$

$$-1$$

On the z basis, we have

$$\begin{aligned} |\hat{e}_{\uparrow}\rangle &= \begin{pmatrix} 1\\0 \end{pmatrix} \\ |\hat{e}_{\downarrow}\rangle &= \begin{pmatrix} 0\\1 \end{pmatrix}. \end{aligned}$$

However, on the x basis, we have

$$|\hat{e}_{+}\rangle = \frac{1}{\sqrt{2}} \begin{pmatrix} 1\\1 \end{pmatrix}$$
$$|\hat{e}_{-}\rangle = \frac{1}{\sqrt{2}} \begin{pmatrix} 1\\-1 \end{pmatrix}.$$

However, despite this basis change, since these are a complete orthonormal basis for  $\mathbb{C}^2$ , we must have

$$\left|\left\langle \hat{e}_{\uparrow}\middle|\psi\right\rangle \right|^{2}+\left|\left\langle \hat{e}_{\downarrow}\middle|\psi\right\rangle \right|^{2}=\left|\left\langle \hat{e}_{+}\middle|\psi\right\rangle \right|^{2}+\left|\left\langle \hat{e}_{-}\middle|\psi\right\rangle \right|^{2}.$$

#### **Matrix Representation of Operators**

Consider a linear operator  $|W\rangle = \mathcal{M} |V\rangle$  with vectors  $|V\rangle$  and  $|W\rangle$ . We can project this onto a basis  $\{\hat{e}_i\}$  to find the relationship between the components.

$$\begin{split} w_{i}' &= \langle \hat{e}_{i} | W \rangle \\ &= \langle \hat{e}_{i} | \mathcal{M} | V \rangle \\ &= \sum_{j} \langle \hat{e}_{i} | \mathcal{M} | \hat{e}_{j} \rangle \langle \hat{e}_{j} | V \rangle \\ &= \sum_{j} M_{ij} v_{j}. \end{split}$$

This yields

$$\begin{pmatrix} w_1' \\ w_2' \\ \vdots \\ w_n' \end{pmatrix} \begin{pmatrix} M_{11} & M_{12} & \cdots & M_{1n} \\ M_{21} & M_{22} & \cdots & M_{2n} \\ \vdots & \vdots & \ddots & \vdots \\ M_{n1} & M_{n2} & \cdots & M_{nn} \end{pmatrix} \begin{pmatrix} v_1 \\ v_2 \\ \vdots \\ v_n \end{pmatrix}.$$

Note that the element M<sub>ij</sub> requires *two* projections.

$$M_{ij} = \langle \hat{e}_i | \mathcal{M} | \hat{e}_j \rangle$$

However, consider a different basis, with

$$\begin{split} M &= M_{\alpha b}' \\ &= \left< \hat{\varepsilon}_{\alpha} \right| \mathcal{M} \left| \hat{\varepsilon}_{b} \right> \\ &= \sum_{ij} \left< \hat{\varepsilon}_{\alpha} \middle| \hat{e}_{i} \right> \left< \hat{e}_{i} \middle| \mathcal{M} \left| \hat{e}_{j} \right> \left< \hat{e}_{j} \middle| \hat{\varepsilon}_{b} \right> \\ &= \sum_{ij} \overline{a_{i}} M_{ij} b_{j}, \end{split}$$

where  $a_i = \langle \hat{e}_i | \hat{e}_\alpha \rangle$  and  $b_i = \langle \hat{e}_i | \hat{e}_b \rangle$  are the projections of  $|\hat{e}_\alpha \rangle$  and  $|\hat{e}_b \rangle$  onto the  $|\hat{e}_i \rangle$  basis respectively.

**Example.** Let  $\mathcal{M}$  be defined by

$$\begin{split} \left\langle \hat{e}_{1} \right| \mathcal{M} \left| \hat{e}_{1} \right\rangle &= 1 \\ \left\langle \hat{e}_{2} \right| \mathcal{M} \left| \hat{e}_{2} \right\rangle &= 1 \\ \left\langle \hat{e}_{1} \right| \mathcal{M} \left| \hat{e}_{2} \right\rangle &= 2 \\ \left\langle \hat{e}_{2} \right| \mathcal{M} \left| \hat{e}_{1} \right\rangle &= 2. \end{split}$$

In the standard basis, we get

$$M = \begin{pmatrix} 1 & 2 \\ 2 & 1 \end{pmatrix}.$$

On the  $|\hat{\epsilon}\rangle$  basis, we have

$$|\hat{\varepsilon}_1\rangle = \frac{1}{\sqrt{2}} \begin{pmatrix} 1\\1 \end{pmatrix}$$
$$|\hat{\varepsilon}_2\rangle = \frac{1}{\sqrt{2}} \begin{pmatrix} 1\\-1 \end{pmatrix}.$$

M has the matrix elements

$$\begin{aligned} M'_{11} &= \langle \hat{\varepsilon}_1 | \, \mathcal{M} \, | \hat{\varepsilon}_1 \rangle \\ &= \frac{1}{\sqrt{2}} \overline{\begin{pmatrix} 1 & 1 \end{pmatrix}} \begin{pmatrix} 1 & 2 \\ 2 & 1 \end{pmatrix} \frac{1}{\sqrt{2}} \begin{pmatrix} 1 \\ 1 \end{pmatrix} \\ &= 3 \end{aligned}$$

$$\begin{aligned} M_{22}' &= \langle \hat{\varepsilon}_1 | \, \mathcal{M} \, | \hat{\varepsilon}_1 \rangle \\ &= \frac{1}{\sqrt{2}} \overline{\begin{pmatrix} 1 & -1 \end{pmatrix}} \begin{pmatrix} 1 & 2 \\ 2 & 1 \end{pmatrix} \frac{1}{\sqrt{2}} \begin{pmatrix} 1 \\ -1 \end{pmatrix} \\ &= -1, \end{aligned}$$

and similarly,  $M'_{12} = 0$  and  $M'_{21} = 0$ . On the  $|\hat{\varepsilon}\rangle$  basis, we have

$$M' = \begin{pmatrix} 3 & 0 \\ 0 & -1 \end{pmatrix}.$$

Similarly, if we have the basis

$$\begin{split} |\hat{\epsilon}_1\rangle &= \frac{1}{\sqrt{2}} \begin{pmatrix} 1 \\ i \end{pmatrix} \\ |\hat{\epsilon}_2\rangle &= \frac{1}{\sqrt{2}} \left( 1//-i \right), \end{split}$$

we calculate

$$\begin{split} M_{11}'' &= \langle \hat{\epsilon}_1 | \, \mathcal{M} \, | \, \hat{\epsilon}_1 \rangle \\ &= \frac{1}{\sqrt{2}} \overline{(1 \quad i)} \begin{pmatrix} 1 & 2 \\ 2 & 1 \end{pmatrix} \frac{1}{\sqrt{2}} \begin{pmatrix} 1 \\ i \end{pmatrix} \\ &= 1 \\ \vdots \\ M'' &= \begin{pmatrix} 1 & -2i \\ 2i & 1 \end{pmatrix}. \end{split}$$

Note that the following are true:

$$M = M^*$$

$$M' = (M')^*$$

$$M'' = (M'')^*$$

and 
$$tr(M) = tr(M') = tr(M'')$$
.

This is an example of the fact that hermiticity, trace, determinant, etc. are all basis-independent.

Some bases are better than others — specifically, for normal operators, we will be able to choose a basis of orthonormal eigenvectors, which will allow the operator to be realized as a diagonal matrix.

## **Rotations**

Rotations are important in physics. \*\*XVIII\* Therefore, we must study the groups of (continuous) rotations — and, specifically, their representations as matrices.

#### **Introduction to Rotations**

Consider a two dimensional vector  $\mathbf{v} = \begin{pmatrix} v_1 \\ v_2 \end{pmatrix}$ . Here, we define

$$v_1 = v \cos \alpha$$
$$v_2 = v \sin \alpha$$

$$v_1' = v \cos \beta$$
$$v_2' = v \sin \beta,$$

subject to  $\beta = \alpha + \phi$ .

$$v'_1 = v \cos(\alpha + \phi)$$

$$= v \cos \alpha \cos \phi - v \sin \alpha \sin \phi$$

$$= v_1 \cos \phi - v_2 \sin \phi$$

$$v'_2 = v \sin(\alpha + \phi)$$

$$= v \sin \alpha \cos \phi + v \cos \alpha \sin \phi$$

$$= v_2 \cos \phi + v_1 \sin \phi.$$

Thus, we can write

$$\begin{pmatrix} v_1' \\ v_2' \end{pmatrix} = \begin{pmatrix} \cos \varphi & -\sin \varphi \\ \sin \varphi & \cos \varphi \end{pmatrix} \begin{pmatrix} v_1 \\ v_2 \end{pmatrix}.$$

Here, we denote

$$R(\phi) = \begin{pmatrix} \cos \phi & -\sin \phi \\ \sin \phi & \cos \phi \end{pmatrix}$$

to be the rotation matrix. Note that  $R^{-1}(\varphi) = R(-\varphi) = R^{T}(\varphi)$ . The definition that  $R^{-1} = R^{T}$  is the crucial, defining property of rotations in  $\mathbb{R}^{n}$ .

Note that we rotated the vector  $\mathbf{v}$  to make  $\mathbf{v}'$ . However, we can also rotate the *axes*.

Rotating the vector is known as an "active" rotation, while rotating the axes is known as a "passive" rotation.

To execute a passive rotation, we need to use the rotation matrix on the basis vectors. This yields

$$\begin{pmatrix} \begin{vmatrix} \hat{e}'_1 \\ \hat{e}'_2 \end{pmatrix} = \begin{pmatrix} \cos \varphi & -\sin \varphi \\ \sin \varphi & \cos \varphi \end{pmatrix} \begin{pmatrix} |\hat{e}_1 \rangle \\ |\hat{e}_2 \rangle \end{pmatrix}.$$

Note that we are having the rotation matrix act on the "vector" of basis vectors to yield a vector of basis vectors.

### What is a Rotation?

Consider successive rotations,  $\phi_1 + \phi_2$ . Then,

$$R\left(\varphi_{1}+\varphi_{2}\right)=\begin{pmatrix}\cos\left(\varphi_{1}+\varphi_{2}\right)&-\sin\left(\varphi_{1}+\varphi_{2}\right)\\\sin\left(\varphi_{1}+\varphi_{2}\right)&\cos\left(\varphi_{1}+\varphi_{2}\right)\end{pmatrix}.$$

Intuitively, we must have

$$\begin{split} R\left(\varphi_{1}+\varphi_{2}\right) &= R\left(\varphi_{2}\right)R\left(\varphi_{1}\right) \\ &= \begin{pmatrix} \cos\varphi_{2} & -\sin\varphi_{2} \\ \sin\varphi_{2} & \cos\varphi_{2} \end{pmatrix} \begin{pmatrix} \cos\varphi_{1} & -\sin\varphi_{1} \\ \sin\varphi_{1} & \cos\varphi_{1} \end{pmatrix} \\ &= \begin{pmatrix} \cos\varphi_{2}\cos\varphi_{1} - \sin\varphi_{2}\sin\varphi_{1} & -\sin\varphi_{1}\cos\varphi_{2} - \sin\varphi_{2}\cos\varphi_{1} \\ \sin\varphi_{1}\cos\varphi_{2} + \cos\varphi_{1}\sin\varphi_{2} & \cos\varphi_{2}\cos\varphi_{1} - \sin\varphi_{1}\sin\varphi_{2} \end{pmatrix} \end{split}$$

Additionally, the rotation of doing nothing is

$$R\left(\phi = 0\right) = \begin{pmatrix} 1 & 0 \\ 0 & 1 \end{pmatrix}$$

$$= I_2.$$

Additionally, we must have

$$R^{-1}(\varphi) = R(-\varphi).$$

Thus, we have established that rotations indeed form a group.

**Example** (Rotations in Real Space). By the definition of a rotation, we must have

$$\|\mathbf{v}\|^2 = \sum_{i} v_i^2.$$

remain constant. Thus, we have

$$\begin{split} \sum_{i} \nu_{i} \nu_{i} &= \sum_{i} \nu'_{i} \nu'_{i} \\ &= \sum_{i} \left( \sum_{k} R_{ik} \nu_{k} \right) \left( \sum_{\ell} R_{i\ell} \nu_{\ell} \right) \\ &= \sum_{i,k,\ell} R_{ik} R_{i\ell} \nu_{k} \nu_{\ell} \\ &= \sum_{k,\ell} \left( \sum_{i} R_{ki}^{\mathsf{T}} R_{i\ell} \right) \nu_{k} \nu_{\ell} \end{split}$$

Thus, we must have

$$\sum_{i} R_{ki}^{\mathsf{T}} R_{i\ell} = \delta_{k\ell},$$

so

$$R^TR = I_2$$

meaning

$$R^{\mathsf{T}} = R^{-1}.$$

These are known as the orthogonal matrices.

The orthogonal matrices form a group, O(n). In two dimensions, the rotations are (part of) the group O(2).

**Example** (Rotations in Complex Space). Using a similar derivation to the case of real space, we are able to determine the criterion for a rotation in complex space, yielding a unitary matrix

$$U^*U = UU^*$$
$$= I.$$

where U\* is the adjoint of U.

We can also obtain this result by taking

$$\langle v'|w'\rangle = \langle Uv|Uw\rangle$$
$$= \langle v|U^*U|w\rangle.$$
$$= \langle v|w\rangle$$

Thus, we must have  $U^*U = I$ .

**Example** (Rotations in  $\mathbb{R}^2$  and Rotations in  $\mathbb{C}$ ). We know that  $\mathbb{C}$  is isomorphic to  $\mathbb{R}^2$  as  $\mathbb{R}$ -vector spaces. Additionally, for

$$z_1 = r_1 e^{i\phi_1}$$
$$z_2 = r_2 e^{i\phi_2},$$

we have

$$z_1 z_2 = r_1 r_2 e^{i(\phi_1 + \phi_2)}.$$

Complex multiplication is, essentially, a rotation.

If we take

$$z = a + ib$$
,

we can represent it as

$$= \begin{pmatrix} a & -b \\ b & a \end{pmatrix}.$$

We need to verify that this is a faithful representation.

$$z_1 + z_2 = \begin{pmatrix} a_1 + a_2 & -b_1 - b_2 \\ b_1 + b_2 & a_1 + a_2 \end{pmatrix}$$
$$z_1 z_2 = \begin{pmatrix} a_1 a_2 - b_1 b_2 & -a_1 b_2 - a_2 b_1 \\ a_1 b_2 + a_2 b_1 & a_1 a_2 - b_1 b_2 \end{pmatrix}.$$

Since these are faithful representations, we can see that, for the circle group  $\mathbb{T}$  consisting of all complex numbers with modulus 1, we have

$$\mathbb{T} \cong SO(2)$$
.

In other words, complex numbers consisting of phase correspond one to one to rotations.

**Example** (Rotations in  $\mathbb{C}^2$ ). Consider the matrix

$$U = \begin{pmatrix} a & b \\ c & d \end{pmatrix}.$$

This matrix has 8 free parameters. However, by definition of unitary, we must have

$$\begin{split} U^*U &= I \\ &= \begin{cases} |\alpha|^2 + |c|^2 = 1 \\ |b|^2 + |d|^2 = 1 \\ \overline{\alpha}b + \overline{c}d = 0 \end{cases}. \end{split}$$

Applying these constraints, now we have 4 constraints. We have to add one more constraint — since det  $U = e^{i\alpha}$  for any phase  $\alpha$ , and as U is a rotation, we must have det  $U = \alpha d - bc = 1$ .

We can summarize the necessary constraints as follows:

$$U = \begin{pmatrix} \frac{a}{b} & -b \\ \frac{a}{b} & \frac{a}{a} \end{pmatrix}, |a|^2 + |b|^2 = 1$$

Example (Using the Complex Rotations). Let

$$\xi = \begin{pmatrix} \xi_1 \\ \xi_2 \end{pmatrix}.$$

Then,

$$\begin{split} \xi' &= U\xi \\ &= \left(\frac{\alpha}{b} - \frac{b}{a}\right) \begin{pmatrix} \xi_1 \\ \xi_2 \end{pmatrix} \\ &= \left(\frac{\alpha\xi_1 - b\xi_2}{b\xi_1 + \alpha\xi_2}\right). \end{split}$$

To ensure that we did this right, we require  $\langle \xi | \xi \rangle = \langle \xi' | \xi' \rangle$ .

**Example** (Converting from Rotations in  $\mathbb{R}^3$  to rotations in  $\mathbb{C}$ ). Note that for any complex matrix U, we can write

$$U = n_0 I + i \sum_{j=1}^{3} n_j \sigma_j$$

where  $\sigma_i$  are the Pauli matrices,

$$\begin{split} \sigma_1 &= \begin{pmatrix} 0 & 1 \\ 1 & 0 \end{pmatrix} \\ \sigma_2 &= \begin{pmatrix} 0 & -i \\ i & 0 \end{pmatrix} \\ \sigma_3 &= \begin{pmatrix} 1 & 0 \\ 0 & -1 \end{pmatrix}. \end{split}$$

As a matrix, we have

$$U = \begin{pmatrix} n_0 + in_3 & i(n_1 - in_2) \\ i(n_1 + in_2) & n_0 - in_3 \end{pmatrix}.$$

Note that, for  $n_i \in \mathbb{R}$ , we have U is Hermitian.

We call this the quaternion representation of the matrix.

Note that

$$UU^* = \begin{pmatrix} n_0^2 + n_1^2 + n_2^2 + n_3^2 & 0 \\ 0 & n_0^2 + n_1^2 + n_2^2 + n_3^2 \end{pmatrix},$$

meaning for U to be unitary, we must have det  $U=n_0^2+n_1^2+n_2^2+n_3^2=1$ .

Using the  $n_i$  is annoying, though, so we introduce angles. Define  $\phi$  to be such that  $n_0 = \cos(\phi/2)$ , and  $\vec{n} = \hat{n}\sin(\phi/2)$ . Note that this satisfies

$$\begin{split} n_0^2 + \vec{n} \cdot \vec{n} &= 1 \\ &= n_0^2 + n_1^2 + n_2^2 + n_3^2. \end{split}$$

We now have

$$U = \cos(\varphi/2) I + i\hat{n} \cdot \sigma \sin(\varphi/2).$$

Incidently, this looks a lot like  $e^{i\phi} = \cos \phi + i \sin \phi$ . In particular, we now have

$$U^* = \cos(\varphi/2) I + \overline{i}\hat{n} \cdot \sigma^* \sin(\varphi/2)$$
$$= \cos(\varphi/2) I - i\hat{n} \cdot \sigma \sin(\varphi/2).$$

Note that this means

$$U(\varphi) = e^{i\varphi \hat{\mathbf{n}} \cdot \sigma/2}$$

$$U^* = e^{-i\varphi \hat{\mathbf{n}} \cdot \sigma/2}$$

$$UU^* = I.$$

We can also use the determinant/trace identity

$$\det\left(e^{M}\right) = e^{\operatorname{tr}(M)}$$

to show that

$$\det\left(e^{i\varphi\,\hat{\mathbf{n}}\cdot\boldsymbol{\sigma}/2}\right) = e^{i(\varphi/2)\operatorname{tr}(\hat{\mathbf{n}}\cdot\boldsymbol{\sigma})}$$
$$= 1.$$

since  $tr(\sigma_i) = 1$ .

## **Improper Rotations**

Note that, by the definition of determinant, we have

$$1 = \det (R^{T}R)$$
$$= \det (R^{T}) \det (R)$$
$$= (\det (R))^{2}.$$

We can have  $det(R) = \pm 1$ . However, only det(R) = 1 yields a proper rotation.

When it comes to improper rotations, the "closest" to the identity is the pure reflection:

$$B(0) = \begin{pmatrix} 1 & 0 \\ 0 & -1 \end{pmatrix}.$$

Note that this yields

$$B(0)\mathbf{v} = \begin{pmatrix} 1 & 0 \\ 0 & -1 \end{pmatrix} \begin{pmatrix} v_x \\ v_y \end{pmatrix}$$
$$= \begin{pmatrix} v_x \\ -v_y \end{pmatrix}.$$

**Example** (Arbitrary Axes). Consider an arbitrary axis  $\hat{n}$  that we want to reflect across. In particular, we have  $\cos \varphi = \hat{n} \cdot \hat{i}$ .

In order to reflect an arbitrary vector  $|v\rangle$  about  $\hat{n}$ , we rotate to the x axis by  $\theta$ , reflect, then rotate back.

$$R(\phi) B(0)R^{-1}(\phi)(\mathbf{v}) = \begin{pmatrix} \cos \phi & -\sin \phi \\ \sin \phi & \cos \phi \end{pmatrix} \begin{pmatrix} 1 & 0 \\ 0 & -1 \end{pmatrix} \begin{pmatrix} \cos \phi & \sin \phi \\ -\sin \phi & \cos \phi \end{pmatrix} (\mathbf{v})$$

$$= \begin{pmatrix} \cos(2\varphi) & \sin(2\varphi) \\ \sin(2\varphi) & -\cos(2\varphi) \end{pmatrix} (\mathbf{v}).$$

When we consider a reflection about the x axis, followed by a reflection about the y axis, we get

$$B\left(\frac{\pi}{2}\right)B\left(0\right) = \begin{pmatrix} -1 & 0\\ 0 & -1 \end{pmatrix},$$

which is our desired rotation by  $\pi$ .

In particular, any reflection B ( $\phi$ ) can be written as R ( $\theta$ ) B (0).

Consider

$$T = \begin{pmatrix} 3/5 & 4/5 \\ 4/5 & -3/5 \end{pmatrix}$$

$$\tan(\theta) = \frac{1}{2}$$

$$T = \begin{pmatrix} 3/5 & -4/5 \\ 4/5 & 3/5 \end{pmatrix} \begin{pmatrix} 1 & 0 \\ 0 & -1 \end{pmatrix}$$

$$= R(53^{\circ}) B(0).$$

**Example** (Two Reflections). Let  $\phi_1$  be the angle from the x axis for mirror 1, and  $\phi_2$  the angle from the x axis for mirror 1. Then, we have

$$\begin{split} B\left(\varphi_{2}\right)B\left(\varphi_{1}\right) &= \begin{pmatrix} \cos\left(2\varphi_{2}\right) & \sin\left(2\varphi_{2}\right) \\ \sin\left(2\varphi_{2}\right) & -\cos\left(2\varphi_{2}\right) \end{pmatrix} \begin{pmatrix} \cos\left(2\varphi_{1}\right) & \sin\left(2\varphi_{1}\right) \\ \sin\left(2\varphi_{1}\right) & -\cos\left(2\varphi_{1}\right) \end{pmatrix} \\ &= \begin{pmatrix} \cos\left(2\left(\varphi_{2}-\varphi_{1}\right)\right) & -\sin\left(2\left(\varphi_{2}-\varphi_{1}\right)\right) \\ \sin\left(2\left(\varphi_{2}-\varphi_{1}\right)\right) & \cos\left(2\left(\varphi_{2}-\varphi_{1}\right)\right) \end{pmatrix} \\ &= R\left(2\left(\varphi_{2}-\varphi_{1}\right)\right). \end{split}$$

**Example** (Reflections in Three Dimensions). Consider the transformation  $(x, y, z) \mapsto (x, -y, -z)$ . The matrix for this transformation is

$$\mathsf{T} = \begin{pmatrix} 1 & 0 & 0 \\ 0 & -1 & 0 \\ 0 & 0 & -1 \end{pmatrix},$$

which has determinant 1, meaning it is a rotation.

The actual reflections in three dimensions are as follows

$$B_{x} = \begin{pmatrix} -1 & 0 & 0 \\ 0 & 1 & 0 \\ 0 & 0 & 1 \end{pmatrix}$$

$$B_{y} = \begin{pmatrix} 1 & 0 & 0 \\ 0 & -1 & 0 \\ 0 & 0 & -1 \end{pmatrix}$$

$$B_{z} = \begin{pmatrix} 1 & 0 & 0 \\ 0 & 1 & 0 \\ 0 & 0 & -1 \end{pmatrix}.$$

Here, the subscript denotes the direction perpendicular in which the "mirror" of the plane sits.

Note that if we take their product, we get

$$P = B_x B_y B_z$$

$$= \begin{pmatrix} -1 & 0 & 0 \\ 0 & -1 & 0 \\ 0 & 0 & -1 \end{pmatrix}.$$

We call P the parity operator. The operator maps  $\mathbf{r} \mapsto -\mathbf{r}$ .

In two dimensions, we can decompose an improper rotation into a rotation multiplied by a reflection — however, in three dimensions, we prefer to decompose into a rotation multiplied by a parity flip.

$$B = RP$$
.

#### Rotations in $\mathbb{R}^3$

In two dimensions, we only need one parameter (angle of rotation) to specify a rotation. However, in  $\mathbb{R}^3$ , we need three parameters — angle of rotation and axis of rotation.

The simplest way to do this is by embedding  $\mathbb{R}^2$  into  $\mathbb{R}^3$ . We take the matrix

$$R_{z}(\phi) = \begin{pmatrix} \cos \phi & -\sin \phi & 0\\ \sin \phi & \cos \phi & 0\\ 0 & 0 & 1 \end{pmatrix},$$

which is a rotation about *z*. Similarly, we embed

$$R_x = \begin{pmatrix} 1 & 0 & 0 \\ 0 & \cos \varphi & -\sin \varphi \\ 0 & \sin \varphi & \cos \varphi \end{pmatrix}$$
 
$$R_y = \begin{pmatrix} \cos \varphi & 0 & \sin \varphi \\ 0 & 1 & 0 \\ -\sin \varphi & 0 & \cos \varphi \end{pmatrix}.$$

We refer to  $\{R_x, R_y, R_z\}$  as the canonical rotation matrices.

Note that, aside from the number of parameters changing, rotations do not commute.

$$R_{x}(\alpha) R_{u}(\beta) \neq R_{u}(\beta) R_{x}(\alpha)$$
.

Example (Non-Commutative Rotations).

$$\begin{split} R_{x}\left(\pi/2\right)R_{y}\left(\pi/2\right) &= \begin{pmatrix} 1 & 0 & 0 \\ 0 & 0 & -1 \\ 0 & 1 & 0 \end{pmatrix} \begin{pmatrix} 0 & 0 & 1 \\ 0 & 1 & 0 \\ -1 & 0 & 0 \end{pmatrix} \\ &= \begin{pmatrix} 0 & 0 & 1 \\ 1 & 0 & 0 \\ 0 & 1 & 0 \end{pmatrix} \\ R_{y}\left(\pi/2\right)R_{x}\left(\pi/2\right) &= \begin{pmatrix} 0 & 1 & 0 \\ 0 & 0 & -1 \\ -1 & 0 & 0 \end{pmatrix}. \end{split}$$

Note that  $(R_x R_y)^3 = I_3$  and  $(R_y R_x)^3 = I_3$ . Thus, we know that  $R(\phi) = R_x R_y$  is equal to a rotation of  $2\pi/3$ .

If we try to rotate the axis of rotation, we must have  $R\hat{n} = \hat{n}$ .

Using eigenvalues, we can find \(\hat{n}\) to be

$$\hat{\mathbf{n}} = \frac{1}{\sqrt{3}} \begin{pmatrix} 1\\1\\1 \end{pmatrix}.$$

Similarly, for  $R' = R_u R_x$ , we find

$$\hat{\mathbf{n}}' = \frac{1}{\sqrt{3}} \begin{pmatrix} 1\\1\\-1 \end{pmatrix}.$$

## **Similarity Transformations**

Since the physical world<sup>XXIX</sup> is necessarily independent of coordinate systems, we have to make sure that all the matrix actions are also able to be converted between coordinate systems.

Consider the angular momentum, which is the result of the moment of inertia tensor acting on  $\vec{\omega}$ .

$$L = I\vec{\omega}$$
.

We apply a symmetry transformation, S, to both L and  $\vec{\omega}$ . Thus, we get

$$\mathbf{L}' = \mathbf{S}\mathbf{L}$$
  
=  $\mathbf{S}\mathbf{I}\vec{\omega}$ .

We want to obtain

$$\mathbf{L}' = \mathbf{I}'\vec{\omega}'$$
.

We want to obtain  $S\vec{\omega} = \vec{\omega}'$ . We can multiply by I, yielding

$$\mathbf{L}' = \operatorname{SI}\left(S^{-1}S\right)\vec{\omega}$$
$$= \left(\operatorname{SIS}^{-1}\right)\left(S\vec{\omega}\right)$$
$$= \operatorname{I}'\left(S\vec{\omega}\right)$$
$$= \operatorname{I}'\vec{\omega}'.$$

Therefore, any matrix will necessarily transform by  $I' = SIS^{-1}$ . Note that if S is a rotation matrix, then  $I' = RIR^{T}$ , while if S is a unitary matrix, then  $I = SIS^{*}$ .

In general, for  $S \in GL(\mathbb{C})$ , we call S a similarity transformation. We call S the change of basis matrix.

Note that matrices in the same similarity class have identical trace and determinant. If  $T' = STS^{-1}$ , then

$$tr(T') = tr(STS^{-1})$$
$$= tr(S^{-1}ST)$$
$$= tr(T).$$

and

$$det(T') = det(STS^{-1})$$

$$= det(S) det(T) det(S^{-1})$$

$$= det(T).$$

**Example.** We start by rotating by  $\pi/2$  about z. Then, we get  $x \mapsto y$  and  $y \mapsto -x$ , so we have

$$R_{z}(\pi/2) = \begin{pmatrix} 0 & -1 & 0 \\ 1 & 0 & 0 \\ 0 & 0 & 1 \end{pmatrix}.$$

We might ask how  $R_x$  changes as a result of this application. Thus, we get

$$\begin{split} R_{x}'\left(\alpha\right) &= R_{z}\left(\pi/2\right) R_{x}\left(\alpha\right) \left(R_{z}\left(\pi/2\right)\right)^{T} \\ &= \begin{pmatrix} 0 & -1 & 0 \\ 1 & 0 & 0 \\ 0 & 0 & 1 \end{pmatrix} \begin{pmatrix} 1 & 0 & 0 \\ 0 & \cos\alpha & -\sin\alpha \\ 0 & \sin\alpha & \cos\alpha \end{pmatrix} \begin{pmatrix} 0 & 1 & 0 \\ -1 & 0 & 0 \\ 0 & 0 & 1 \end{pmatrix} \\ &= \begin{pmatrix} \cos\alpha & 0 & \sin\alpha \\ 0 & 1 & 0 \\ -\sin\alpha & 0 & \cos\alpha \end{pmatrix} \\ &= R_{u}\left(\alpha\right). \end{split}$$

Note that, since the trace is invariant under similarity transformations, we must have

$$tr(R_n) = tr(SR_xS^{-1})$$
$$= tr(R_x)$$
$$= 1 + 2\cos\phi,$$

meaning

$$\cos \phi = \frac{1}{2} \left( \operatorname{tr} \left( R_{n} \right) - 1 \right).$$

Example. Since

$$A = \frac{1}{2} \begin{pmatrix} -1 & 1 & \sqrt{2} \\ -1 & 1 & -\sqrt{2} \\ -\sqrt{2} & -\sqrt{2} & 0 \end{pmatrix}$$

satisfies

$$AA^{\mathsf{T}} = I_3$$

we have A is a rotation of  $2\pi/3$  about

$$\hat{\mathbf{n}} = \frac{1}{\sqrt{3}} \begin{pmatrix} 0\\ \sqrt{2}\\ -1 \end{pmatrix}.$$

Example. Consider

$$T = \begin{pmatrix} 3 & 0 & -1 \\ 0 & -2 & 0 \\ -1 & 0 & 3 \end{pmatrix}.$$

We want to transform T with the matrix

$$S = \begin{pmatrix} 1 & 0 & 1 \\ 1 & 0 & -1 \\ 0 & \sqrt{2} & 0 \end{pmatrix}.$$

We can see that S is not orthogonal — however,  $\frac{1}{\sqrt{2}}$ S is. Thus, we have

$$T' = \frac{1}{2}STS^{T}$$

$$= \begin{pmatrix} 2 & 0 & 0 \\ 0 & 4 & 0 \\ 0 & 0 & -2 \end{pmatrix}.$$

We know that T and T' are the same operator, but T' is much easier to use than T, so we would prefer to work in T'.

## **Generating Rotations**

Rotations in  $\mathbb{R}^3$  do not commute. However, we know that the rotation by  $\varphi = 0$  is the identity, which does commute. We let  $\varepsilon > 0$  be a very small angle of rotation. Then, approximating to second order, we have

$$R_{z}(\varepsilon) = \begin{pmatrix} 1 - \frac{1}{2}\varepsilon^{2} & -\varepsilon & 0 \\ \varepsilon & 1 - \frac{1}{2}\varepsilon^{2} & 0 \\ 0 & 0 & 1 \end{pmatrix}$$

$$R_{x}(\varepsilon) = \begin{pmatrix} 1 & 0 & 0 \\ 0 & 1 - \frac{1}{2}\varepsilon^{2} & -\varepsilon \\ 0 & \varepsilon & 1 - \frac{1}{2}\varepsilon^{2} \end{pmatrix}$$

$$R_{y}(\varepsilon) = \begin{pmatrix} 1 - \frac{1}{2}\varepsilon^{2} & 0 & \varepsilon \\ 0 & 1 & 0 \\ -\varepsilon & 0 & 1 - \frac{1}{2}\varepsilon^{2} \end{pmatrix}.$$

Keeping everything through second order, we calculate

$$\begin{split} R_{x}\left(\varepsilon\right)R_{y}\left(\varepsilon\right) &= \begin{pmatrix} 1-\frac{1}{2}\varepsilon^{2} & 0 & \varepsilon \\ \varepsilon^{2} & 1-\frac{1}{2}\varepsilon^{2} & -\varepsilon \\ -\varepsilon & \varepsilon & 1-\varepsilon^{2} \end{pmatrix} \\ R_{y}\left(\varepsilon\right)R_{x}\left(\varepsilon\right) &= \begin{pmatrix} 1-\frac{1}{2}\varepsilon^{2} & \varepsilon^{2} & \varepsilon \\ 0 & 1-\frac{1}{2}\varepsilon^{2} & -\varepsilon & -\varepsilon & \varepsilon & 1-\varepsilon^{2} \end{pmatrix}. \end{split}$$

Calculating the commutator, we get

$$\begin{bmatrix} R_{x}(\varepsilon), R_{y}(\varepsilon) \end{bmatrix} = R_{x}(\varepsilon) R_{y}(\varepsilon) - R_{y}(\varepsilon) R_{x}(\varepsilon)$$
$$= \begin{pmatrix} 0 & -\varepsilon^{2} & 0 \\ \varepsilon^{2} & 0 & 0 \\ 0 & 0 & 0 \end{pmatrix}$$

$$=R_{z}\left( \varepsilon^{2}\right) -I_{3}.$$

In the limit as  $\varepsilon \to 0$ , since  $R_z(\varepsilon^2)$  falls at a higher order, it is the case that infinitesimal rotations do commute.

To explore the commutator further, we introduce introduce the Hermitian matrix

$$L_3 = \begin{pmatrix} 0 & -i & 0 \\ i & 0 & 0 \\ 0 & 0 & 0 \end{pmatrix},$$

meaning we now have

$$R_z(\varepsilon) = I_3 - i\varepsilon L_3$$
,

We can also introduce

$$L_1 = \begin{pmatrix} 0 & 0 & 0 \\ 0 & 0 & -i \\ 0 & i & 0 \end{pmatrix}$$

$$L_2 = \begin{pmatrix} 0 & 0 & i \\ 0 & 0 & 0 \\ -i & 0 & 0 \end{pmatrix}.$$

Now, we have

$$R_{x}(\varepsilon) = I_{3} - i\varepsilon L_{1}$$
  
 $R_{y}(\varepsilon) = I_{3} - i\varepsilon L_{2}$ .

For general n, we have

$$R_n(\varepsilon) = I_3 - i\varepsilon \hat{\mathbf{n}} \cdot \mathbf{L}$$

where

$$\hat{n}\cdot \mathbf{L} = \sum_{i} n_{i}L_{i}.$$

These matrices encode how  $R_n$  deviates from  $I_3$ , and are known as the generators of rotations. To understand how  $L_i$  are given the moniker of generator, we take advantage of the continuity of rotations,

$$R_z (\phi + d\phi) = R_z (d\phi) R_z (\phi)$$
$$= (1 - i d\phi L_3) R_z (\phi),$$

meaning

$$dR_z = R_z (\phi + d\phi) - R_z (\phi)$$
  
=  $-id\phi L_3 R_z (\phi)$ .

Integrating, using  $R_z(0) = I_3$ , we get

$$R_z(\phi) = e^{-i\phi L_3}$$
.

Similarly, we get

$$R_{x}(\phi) = e^{-i\phi L_{1}}$$

$$R_{u}(\phi) = e^{-i\phi L_{2}}.$$

Note that, since  $L_i^T = -L_i$ , we have

$$R_i R_i^T = I_3$$
.

The commutation relation on Li are found as follows

$$[L_i, L_j] = i\epsilon_{ijk}L_k.$$

Thus,  $L_i$  along with  $[\cdot, \cdot]$  form a Lie algebra.

# **Eigenstuff**

Recalling that for a rotation about  $\hat{n}$ , we must have

$$R\hat{n} = \hat{n}$$
,

we may want to solve for  $\hat{n}$ .

However, if B is an improper rotation, we have

$$B\mathbf{v} = \pm \mathbf{v}$$
,

meaning there are two distinct directions that the operation of the matrix B reduces to scalar multiplication.

In general, we write

$$M\mathbf{v} = \lambda \mathbf{v}$$
$$M | v \rangle = \lambda | v \rangle.$$

We say  $\lambda$  is an eigenvalue for M, and  $|\nu\rangle$  is the eigenvector corresponding to  $\lambda$ .

Recall the equation for angular momentum,

$$\mathbf{L} = \mathbf{I}\vec{\boldsymbol{\omega}}$$
$$= \lambda \vec{\boldsymbol{\omega}},$$

then the particular  $\omega$  for which  $I\vec{\omega} = \lambda \vec{\omega}$  are known as the principal axes.

## **Finding Eigenvalues**

To find the eigenvalues, we take

$$A |\nu\rangle = \lambda |\nu\rangle$$
$$(A - \lambda I_n) |\nu\rangle = 0.$$

The dumb answer is to set  $|v\rangle = 0$  — however, since  $|v\rangle = 0$  has no information to give us, we specifically need to find the values of  $\lambda$  for which  $A - \lambda I_n \notin GL_n(\mathbb{C})$ . We must have

$$\det\left(A - \lambda I_{n}\right) = 0.$$

## Example. Let

$$A = \begin{pmatrix} 5 & 2\sqrt{2} \\ 2\sqrt{2} & 3 \end{pmatrix}.$$

Then,

$$\det(A - \lambda I_2) = \lambda^2 - 8\lambda + 7,$$

meaning

$$\lambda_1 = 1$$
$$\lambda_2 = 7.$$

We say the set  $\{\lambda_1, \lambda_2\}$  is the spectrum of the operator.

To find the eigenvectors, we take

$$A |\nu\rangle = \lambda |\nu\rangle$$

$$\begin{pmatrix} 5 & 2\sqrt{2} \\ 2\sqrt{2} & 3 \end{pmatrix} \begin{pmatrix} a \\ b \end{pmatrix} = 7 \begin{pmatrix} a \\ b \end{pmatrix}$$

$$-2a + 2\sqrt{2}b = 0$$

$$2\sqrt{2}a - 4b$$

$$a = \sqrt{2}b$$

$$|\nu_2\rangle = \begin{pmatrix} \sqrt{2} \\ 1 \end{pmatrix}.$$

Similarly, for  $\lambda_1$ , we have

$$|v_1\rangle = \begin{pmatrix} 1 \\ -\sqrt{2} \end{pmatrix}.$$

## Example. Let

$$B = \begin{pmatrix} -1 & -1 & 5 \\ -1 & 5 & -1 \\ 5 & -1 & -1 \end{pmatrix}$$

$$det (B - \lambda I_3) = (\lambda - 3) (\lambda - 6) (\lambda + 6).$$

Taking det  $(B - \lambda I_3) = 0$ , we have

$$\lambda_1 = 3$$

$$\lambda_2 = 6$$

$$\lambda_2 = -6$$

Solving for the eigenvectors, we have

$$|\hat{\mathbf{v}}_1\rangle = \frac{1}{\sqrt{3}} \begin{pmatrix} 1\\1\\1 \end{pmatrix}$$

$$|\hat{\mathbf{v}}_2\rangle = \frac{1}{\sqrt{6}} \begin{pmatrix} 1\\ -2\\ 1 \end{pmatrix}$$

$$|\hat{\mathbf{v}}_3\rangle = \frac{1}{\sqrt{2}} \begin{pmatrix} 1\\0\\-1 \end{pmatrix}.$$

Example (Complex Matrices). Let

$$C_1 = \begin{pmatrix} 1 & 2 \\ -2 & 1 \end{pmatrix}$$

The characteristic polynomial is

$$\lambda^2 - 2\lambda + 5 = 0,$$

so the spectrum is  $\lambda_{1,2} = 1 \pm 2i$ , meaning we get

$$|\hat{\mathbf{v}}_1\rangle = \frac{1}{\sqrt{2}} \begin{pmatrix} 1\\ i \end{pmatrix}$$

$$|\hat{\mathbf{v}}_2\rangle = \frac{1}{\sqrt{2}} \begin{pmatrix} 1\\ -i \end{pmatrix}.$$

On the other hand,

$$C_2 = \begin{pmatrix} 1 & 2i \\ -2i & 1 \end{pmatrix}$$

has the same eigenvectors as  $C_1$ , but has real eigenvalues.

Meanwhile,

$$C_3 = \begin{pmatrix} 0 & 2 \\ -2 & 0 \end{pmatrix}$$

has purely imaginary eigenvalues,  $\lambda_{1,2} = \pm 2i$ .

Example (Repeated Eigenvalue). Consider the matrix

$$E = \begin{pmatrix} 3 & -8 & -2 \\ -8 & -9 & -4 \\ -2 & -4 & 6 \end{pmatrix}.$$

The characteristic polynomial for E is

$$(\lambda + 14)(\lambda - 7)^2 = 0.$$

As a double root, we must have  $\lambda_2=\lambda_3=7$ , meaning we have a doubly degenerate spectrum thanks to 7.

Solving for  $|v_1\rangle$ , we have

$$|v_1\rangle = \begin{pmatrix} 2\\4\\1 \end{pmatrix}$$

while solving for  $\lambda = 7$ , we get the system of equations

$$4a + 8b + 2c = 0$$
$$8a + 16b + 4c = 0$$
$$2a + 4b + c - 0.$$

These equations are not linearly independent, but also this equation is equivalent to a single condition c = -2(a + 2b). Solving for each of a, b, c = 0, we have

$$|\nu_{c=0}\rangle = \begin{pmatrix} -2\\1\\0 \end{pmatrix}$$
$$|\nu_{a=0}\rangle = \begin{pmatrix} 0\\1\\-4 \end{pmatrix}$$
$$|\nu_{b=0}\rangle = \begin{pmatrix} 1\\0\\-2 \end{pmatrix}.$$

These vectors are not linearly independent, meaning we can find any  $|u\rangle = \alpha |v_1\rangle + \beta |v_2\rangle$ . In particular, we can pick the degenerate eigenvectors to be orthogonal to each other.

$$|v_2\rangle = \begin{pmatrix} 1\\0\\-2 \end{pmatrix}$$
$$|v_3\rangle = \begin{pmatrix} 8\\-5\\4 \end{pmatrix}.$$

Example (Non-Orthogonal Eigenvectors). Consider

$$E = \begin{pmatrix} -2 & -4 & -3 \\ 3 & 5 & 3 \\ -2 & -2 & -1 \end{pmatrix},$$

from which we obtain eigenvalues of 1, -1, and 2. Their corresponding eigenvectors are

$$|v_1\rangle = \begin{pmatrix} 1\\0\\-1 \end{pmatrix}$$
$$|v_{-1}\rangle = \begin{pmatrix} 1\\-1\\1 \end{pmatrix}$$
$$|v_2\rangle = \begin{pmatrix} 1\\-1\\0 \end{pmatrix}.$$

Though linearly independent, these eigenvectors are not orthogonal, and it is not possible to choose a basis for which these eigenvectors are orthogonal.

**Example** (Common Eigenvectors). Eigenvalues must correspond to different eigenvectors to form a basis. However, different matrices can have the same eigenvectors. For instance, the matrix

$$F = \begin{pmatrix} 4 & 5 & 1 \\ -1 & -2 & -1 \\ -3 & -3 & 0 \end{pmatrix}$$

has the spectrum  $\lambda = \{3, 0, -1\}$ , but the same eigenvectors as E.

These matrices also have something else in common — it is the case that EF = FE.

**Example** (Defective Matrix). Consider the matrix

$$G = \begin{pmatrix} 1 & -1 & 1 \\ 1 & 3 & -1 \\ 1 & 1 & -1 \end{pmatrix}.$$

We get a double degeneracy,  $\lambda_1 = 1$ ,  $\lambda_{2,3} = 2$ , with

$$|v_1\rangle = \begin{pmatrix} -1\\1\\3 \end{pmatrix}$$

but there is only one eigenvector corresponding to  $\lambda_{2,3}$ .

We call G a defective matrix, in that it does not have a third eigenvector.

## **Normal Matrices**

In order to generally study eigenvectors and eigenvalues, we are interested in a particular class of matrices.

**Definition** (Normal Matrices). A matrix N is known as normal if

$$[\mathsf{N},\mathsf{N}^*]=0.$$

In other words,  $NN^* = N^*N$ .

Normal matrices have orthogonal eigenbasis, which makes doing analysis much easier.

**Example** (Hermitian Operators). Recall that an operator is Hermitian if  $H = H^*$ . Hermitian matrices are normal, as

$$[H, H^*] = [H, H]$$
  
= 0.

If  $\lambda$  is an eigenvalue of H with corresponding eigenvector  $|\nu\rangle$ , we have

$$\begin{split} \lambda \left\langle \nu \middle| \nu \right\rangle &= \left\langle \nu \middle| \lambda \middle| \nu \right\rangle \\ &= \left\langle \nu \middle| H \middle| \nu \right\rangle \\ &= \overline{\left\langle \nu \middle| H^* \middle| \nu \right\rangle} \\ &= \overline{\left\langle \nu \middle| H \middle| \nu \right\rangle} \\ &= \overline{\left\langle \nu \middle| \lambda \middle| \nu \right\rangle} \\ &= \overline{\lambda} \left\langle \nu \middle| \nu \right\rangle. \end{split}$$

Thus,  $\lambda = \overline{\lambda}$ , meaning it is necessarily the case that  $\lambda \in \mathbb{R}$ .

Additionally, for distinct eigenvalues  $\lambda_{1,2}$  with corresponding eigenvectors  $|v_{1,2}\rangle$ , we must have

$$\lambda_{2} \langle v_{1} | v_{2} \rangle = \langle v_{1} | H v_{2} \rangle$$
$$= \langle H^{*} v_{1} | v_{2} \rangle$$
$$= \langle H v_{1} | v_{2} \rangle$$

$$= \overline{\lambda_1} \langle v_1 | v_2 \rangle,$$
  
=  $\lambda_1 \langle v_1 | v_2 \rangle,$ 

meaning

$$(\lambda_1 - \lambda_2) \langle v_1 | v_2 \rangle = 0.$$

Since  $\lambda_1 \neq \lambda_2$ , we necessarily have  $\langle v_1 | v_2 \rangle = 0$ , or that  $v_1$  and  $v_2$  are orthogonal.

Thus, for non-degenerate eigenvalues, the eigenvectors of a Hermitian operator are orthogonal — for degenerate eigenvalues, we are able to choose the eigenvectors to be orthogonal.

Therefore, the eigenvectors of a  $n \times n$  Hermitian matrix form an orthogonal basis for  $\mathbb{C}^n$ .

Note that there exist anti-Hermitian matrices, with  $Q^* = -Q$ . Then, it is the case that Q = iH for some H, meaning the eigenvalues of Q are pure imaginary, with orthogonal eigenvectors.

Note that any matrix A can be written as A = H + Q, where H is Hermitian and Q is anti-Hermitian.

**Example** (Unitary Matrices). Recall that an operator is unitary if  $U^*U = I_n$ . Thus, we have

$$[u, u^*] = [u, u^{-1}]$$
  
=  $uu^{-1} - u^{-1}u$   
= 0.

If  $\lambda$  is an eigenvalue of U with corresponding eigenvector  $|\nu\rangle$ , we have

$$\begin{aligned} |\lambda|^2 \langle \nu | \nu \rangle &= \langle \nu | \, \overline{\lambda} \lambda \, | \nu \rangle \\ &= \langle \lambda \nu | \, \lambda \nu \\ &= \langle U \nu | U \nu \rangle \\ &= \langle \nu | \, U^* U \, | \nu \rangle \\ &= \langle \nu | \nu \rangle \, , \end{aligned}$$

meaning  $|\lambda|^2 = 1$ , so  $\lambda = e^{i\alpha}$ . Every unitary operator has as its eigenvalues a pure phase.

Note that, since unitary operators preserve relative orientation and magnitude, it must be the case that, in the case of e.g. time evolution, the operator for time evolution must be a unitary.

Following an identical derivation, we can see that the eigenvectors of a unitary operator U form a basis for  $\mathbb{C}^n$ .

#### Diagonalization

Given a normalized eigenvector  $|\hat{v}\rangle$  of a normal matrix T, we can project the eigenvalue by taking

$$\lambda = \langle \hat{\mathbf{v}} | \mathsf{T} | \hat{\mathbf{v}} \rangle$$
.

In particular, this is true if we rotate the basis. If  $|\hat{v}'\rangle = U^* |v\rangle$ . Then, we have

$$\lambda = \langle \hat{v} | T | \hat{v} \rangle$$

$$= \langle \hat{v} | (UU^*) T (UU^*) | \hat{v} \rangle$$

$$= \langle U^* \hat{v} | U^* T U | U^* \hat{v} \rangle$$

$$= | \hat{v}' \rangle U^* T U | \hat{v}' \rangle.$$

Thus, we can see that the eigenvalue is basis-independent.

It would be more efficient if we could construct all the eigenvalues at the same time. We can do this by constructing a matrix

$$U = \begin{pmatrix} \hat{v}_1 & \hat{v}_2 & \cdots & \hat{v}_n \end{pmatrix},$$

where each  $\hat{v}_i$  are normalized eigenvectors. Then, we take

$$TU = \begin{pmatrix} \lambda_1 \hat{v}_1 & \lambda_2 \hat{v}_2 & \cdots & \lambda_n \hat{v}_n \end{pmatrix}$$
$$= U\Lambda,$$

where

$$\Lambda = \begin{pmatrix} \lambda_1 & 0 & \cdots & 0 \\ 0 & \lambda_2 & \cdots & 0 \\ \vdots & \vdots & \ddots & \vdots \\ 0 & 0 & \cdots & \lambda_n \end{pmatrix}$$

is the collection of eigenvalues. Thus, we obtain

$$\Lambda = U^*TU$$
,

which means  $\Lambda$  is a unitary transformation induced by the vector rotation  $|\hat{v}'\rangle = U^*|\hat{v}\rangle$ . The matrices  $\Lambda$  and T are different matrix representations of the same operator  $\mathcal{T}$ , meaning this transformation  $\Lambda = U^*TU$  diagonalizes the matrix. In particular, on the diagonal basis,  $\Lambda$  has the standard basis representation for its eigenvectors.

What makes normal operators special is that they are *unitarily* diagonalizable.

## Example. Consider

$$B = \begin{pmatrix} -1 & -1 & 5 \\ -1 & 5 & -1 \\ 5 & -1 & -1 \end{pmatrix},$$

which has normalized eigenvectors

$$|\nu_1\rangle = \frac{1}{\sqrt{3}} \begin{pmatrix} 1\\1\\1\\1 \end{pmatrix}$$

$$|v_2\rangle = \frac{1}{\sqrt{6}} \begin{pmatrix} 1\\ -2\\ 1 \end{pmatrix}$$

$$|v_3\rangle = \frac{1}{\sqrt{2}} \begin{pmatrix} 1\\0\\-1 \end{pmatrix}.$$

Then, the unitary matrix

$$U = \begin{pmatrix} \frac{1}{\sqrt{3}} & \frac{1}{\sqrt{6}} & \frac{1}{\sqrt{2}} \\ \frac{1}{\sqrt{3}} & -\frac{2}{\sqrt{6}} & 0 \\ \frac{1}{\sqrt{3}} & \frac{1}{\sqrt{6}} & -\frac{1}{\sqrt{2}} \end{pmatrix},$$

meaning we now have the diagonalization

$$\mathbf{U}^*\mathbf{B}\mathbf{U} = \begin{pmatrix} 3 & 0 & 0 \\ 0 & 6 & 0 \\ 0 & 0 & -6 \end{pmatrix}.$$

**Example** (Matrix Powers). If T is a unitarily diagonalizable matrix, we can take

$$T^{m} = U(U^{*}TU)(U^{*}TU)\cdots(U^{*}TU)U^{*}$$
$$= U\Lambda^{m}U^{*},$$

meaning we find

$$\Lambda^{m} = \begin{pmatrix} \lambda_{1}^{m} & 0 & \cdots & 0 \\ 0 & \lambda_{2}^{m} & \cdots & 0 \\ \vdots & \vdots & \ddots & \vdots \\ 0 & 0 & \cdots & \lambda_{n}^{m} \end{pmatrix}.$$

**Example.** Consider the matrix

$$M = \frac{1}{2} \begin{pmatrix} 1 & 1 \\ 1 & 1 \end{pmatrix}.$$

This matrix has eigenvalues  $\lambda_1 = 1$  and  $\lambda_2 = 0$ , with corresponding eigenvectors

$$|\hat{v}_1\rangle = \frac{1}{\sqrt{2}} \begin{pmatrix} 1\\1 \end{pmatrix}$$
$$|\hat{v}_2\rangle = \frac{1}{\sqrt{2}} \begin{pmatrix} -1\\1 \end{pmatrix}.$$

We take

$$U = \frac{1}{\sqrt{2}} \begin{pmatrix} 1 & -1 \\ 1 & 1 \end{pmatrix}$$
$$U^* = \frac{1}{\sqrt{2}} \begin{pmatrix} 1 & 1 \\ -1 & 1 \end{pmatrix},$$

and

$$\Lambda = \mathbf{U}\mathbf{M}\mathbf{U}^*$$
$$= \begin{pmatrix} 1 & 0\\ 0 & 0 \end{pmatrix}.$$

Thus,

$$M = U^* \Lambda U$$

is a sequence that consists of a rotation counterclockwise by  $\pi/4$ , a projection, then rotation back by  $\pi/4$ .

**Example** (Spectral Decomposition). For any vector  $|a\rangle$ , it is possible to decompose the vector by an orthonormal basis

$$|\alpha\rangle = \sum_{i} |\hat{v}\rangle \langle \hat{v}_{i} | \alpha\rangle$$
$$= \sum_{i} c_{i} |\hat{v}_{i}\rangle.$$

We can expand an operator  $\mathcal{A}$  in a similar manner, yielding

$$\mathcal{A} = \sum_{i,j} |\hat{v}_{i}\rangle \langle \hat{v}_{i}| \mathcal{A} |\hat{v}_{j}\rangle \langle \hat{v}_{j}|$$
$$= \sum_{i,j} A_{ij} |\hat{v}_{i}\rangle \langle \hat{v}_{j}|.$$

However, if  $\mathcal{A}$  is a normal operator and  $|\hat{v}\rangle$  is its eigenbasis, then we can obtain the spectral decomposition of  $\mathcal{A}$  as follows

$$\begin{split} \mathcal{A} &= \sum_{i,j} \left| \hat{\mathbf{v}}_i \right\rangle \left\langle \hat{\mathbf{v}}_i \right| \mathcal{A} \left| \hat{\mathbf{v}}_j \right\rangle \left\langle \hat{\mathbf{v}}_j \right| \\ &= \sum_{ij} \lambda_j \left| \hat{\mathbf{v}}_i \right\rangle \left\langle \hat{\mathbf{v}}_i \middle| \hat{\mathbf{v}}_j \right\rangle \left\langle \hat{\mathbf{v}}_j \middle| \\ &= \sum_i \left| \hat{\mathbf{v}}_j \right\rangle \left\langle \hat{\mathbf{v}}_j \middle| \right. \end{split}$$

If we are dealing with two operators, A and B where we need a common basis.

Let  $A | v \rangle = \alpha | v \rangle$ . Then,

$$A (B |\nu\rangle) = (BA + [A, B]) |\nu\rangle$$
$$= (aB + [A, B]) |\nu\rangle.$$

Note that if [A, B] = 0 (that is, the matrices commute), then

$$A(B|v\rangle) = a(B|v\rangle)$$
,

meaning that B maps an eigenvector of A to an eigenvector of A (assuming a is nondegenerate) — i.e.,  $|v\rangle$  is an eigenvector for B.

This means commuting matrices have a common eigenbasis, meaning they can be simultaneously diagonalized.

Now, we consider

$$A\mathbf{v} = \lambda B\mathbf{v}$$
.

which is the so-called generalized eigenvalue problem. Ideally, we multiply both sides by B<sup>-1</sup> to get

$$B^{-1}A\mathbf{v} = \lambda \mathbf{v}$$
.

However, we don't even know if B has an inverse, or if  $M = B^{-1}A$  is normal.

In order to solve this problem, we find  $\lambda$  that satisfies

$$\det\left(A - \lambda B\right) = 0.$$

Example. Consider

$$A = \begin{pmatrix} 4 & 1 \\ 1 & -2 \end{pmatrix}$$
$$B = \begin{pmatrix} 5 & 3 \\ 3 & 2 \end{pmatrix}.$$

Substituting into the secular determinant, we have

$$\lambda_1 = -9$$

$$\mathbf{v}_1 = \begin{pmatrix} 4 \\ -7 \end{pmatrix}$$

$$\lambda_2 = 1$$

$$\mathbf{v}_2 = \begin{pmatrix} 2 \\ -1 \end{pmatrix}.$$

Notice that  $\mathbf{v}_1$  and  $\mathbf{v}_2$  are not orthogonal —  $\mathbf{v}_1^\mathsf{T}\mathbf{v}_2 = 0$ . However, we do have

$$\mathbf{v}_1^\mathsf{T} \mathsf{B} \mathbf{v}_2 = 0.$$

Generally, we will define

$$\mathbf{u}_1 = B^{1/2}\mathbf{v}_1$$
$$\mathbf{u}_2 = B^{1/2}\mathbf{v}_2,$$

where  $B^{1/2}$  is the unique matrix such that

$$B^{1/2}B^{1/2} = B.$$

We recover

$$B^{1/2} = \begin{pmatrix} 2 & 1 \\ 1 & 1 \end{pmatrix}$$
$$\mathbf{u}_1 = \begin{pmatrix} 1 \\ -3 \end{pmatrix}$$
$$\mathbf{u}_2 = \begin{pmatrix} 3 \\ 1 \end{pmatrix}.$$

## **Normal Modes**

Eigenvalues are useful in the real world.xxx

Consider a system with two masses connected by spring constants  $k_1$  on  $m_1$  to the left wall and  $k_2$  on  $m_2$  to the right wall, with a spring of constant  $\kappa$  in between the two masses. These masses have position functions of  $q_1$  and  $q_2$ .

Decoupling these oscillators, we have

$$\begin{split} m_1 \ddot{q}_1 &= -k_1 q_1 - \kappa (q_1 - q_2) \\ m_2 \ddot{q}_2 &= -k_2 q_2 - \kappa (q_2 - q_1). \end{split}$$

xxxWho cares about that?

Notice that the existence of  $\kappa$  yields coupling — if  $\kappa \to 0$ , we would have

$$m_1\ddot{q}_1 = -k_1q_1$$
  
 $m_2\ddot{q}_2 = -k_2q_2$ .

We define the vector

$$\begin{pmatrix} q_1 \\ q_2 \end{pmatrix} = q_1 \begin{pmatrix} 1 \\ 0 \end{pmatrix} + q_2 \begin{pmatrix} 0 \\ 1 \end{pmatrix}.$$

We write this as a ket equation.

$$|Q\rangle = q_1(t)|q_1\rangle + q_2(t)|q_2\rangle$$
.

We call the expansion on  $|q_1\rangle$  and  $|q_2\rangle$  the expansion on the position basis. We define the matrix operators

$$\begin{split} M &= \begin{pmatrix} m_1 & 0 \\ 0 & m_1 \end{pmatrix} \\ K &= \begin{pmatrix} k_1 + \kappa & -\kappa \\ -\kappa & k_2 + \kappa \end{pmatrix}. \end{split}$$

Then, we can write our coupled differential equations as

$$M |\ddot{Q}\rangle = -K |Q\rangle$$
.

We will use the time-tested "lucky guess" method to solve this equation. XXXI We specifically want a solution of the form

$$|Q(t)\rangle = A\cos(\omega t + \delta)|\Phi\rangle$$
,

where  $|\Phi\rangle = \phi_1 |q_1\rangle + \phi_2 |q_2\rangle$  is the expansion on the position basis. The masses in the state  $|\Phi\rangle$  oscillate with frequency  $\omega$  and relative amplitudes  $\phi_{1,2}$ , determined by

$$\begin{aligned} q_{1,2}(t) &= \langle q_{1,2} | Q(t) \rangle \\ &= A \cos(\omega t + \delta) \langle q_{1,2} | \Phi \rangle \\ &= A \cos(\omega t + \delta) (\phi_{1,2}). \end{aligned}$$

Our guess is only valid if we have a consistent expression for  $\omega$  and  $\phi_{1,2}$ .

Note that our lucky guess yields the derivatives of Q(t) to be

$$\left|\ddot{Q}\right\rangle = -\omega^{2} \left|Q\right\rangle,$$

$$K\left|\Phi\right\rangle = \omega^{2} M\left|\Phi\right\rangle.$$

This yields a generalized eigenvalue equation  $\lambda = \omega^2$ . The eigenvalues here are the various values of  $\omega^2$  that satisfy this equation.

**Example.** Let  $m_1 = m_2 = m$  and  $\kappa = k_1 = k_2 = k$ , meaning we get

$$\begin{split} M &= \begin{pmatrix} m & 0 \\ 0 & m \end{pmatrix} \\ K &= \begin{pmatrix} 2k & -k \\ -k & 2k \end{pmatrix}. \end{split}$$

xxxiThis is known as an *ansatz*, which is a very frequently utilized approach to solving differential equations, as differential equations given an initial condition have unique solutions.

Solving the equations, we get

$$\omega_1^2 = \frac{k}{m}$$
$$\omega_2^2 = \frac{3k}{m}.$$

We have eigenvectors

$$|\Phi_1\rangle = \frac{1}{\sqrt{2}} \begin{pmatrix} 1\\1 \end{pmatrix}$$
$$|\Phi_2\rangle = \frac{1}{\sqrt{2}} \begin{pmatrix} 1\\-1 \end{pmatrix}.$$

Here,  $|\Phi_1\rangle$  denotes perfect symmetry (i.e., both masses moving in the same direction), while  $|\Phi_2\rangle$  denotes perfect antisymmetry (i.e., both masses moving in opposite directions).

We say  $|\Phi_1\rangle$  and  $|\Phi_2\rangle$  are normal modes.

The solution is the set of all linear combinations of the normal modes.

$$|Q(t)\rangle = A_1 \cos(\omega_1 t + \delta_1) |\Phi_1\rangle + A_2 \cos(\omega_2 t + \delta_2) |\Phi_2\rangle$$

We find

$$q_i(t) = \langle q_i | Q(t) \rangle$$
.

For example,

$$\begin{aligned} q_{1,2}(t) &= \langle q_1 | Q(t) \rangle \\ &= A_1 \cos(\omega_1 t + \delta_1) \pm A_2 \cos(\omega_2 t + \delta_2) \,. \end{aligned}$$

We find normal modes by taking certain initial conditions.

Consider

$$q_1(0) = 0$$
  
 $q_2(0) = b$   
 $\dot{q}_{1,2}(0) = 0$ .

Note that the latter condition means that  $\delta_{1,2} = 0$ .

$$\begin{pmatrix} q_1 \\ q_2 \end{pmatrix} = A_1 \cos(\omega_2 t) \begin{pmatrix} 1 \\ 1 \end{pmatrix} + A_2 \cos(\omega_2 t) \begin{pmatrix} 1 \\ -1 \end{pmatrix},$$

meaning we get the solution of

$$q_{1,2}(t) = \frac{\alpha}{2} \left( \cos \left( \omega_1 t \right) \pm \cos \left( \omega_2 t \right) \right) + \frac{b}{2} \left( \cos \left( \omega_1 t \right) \mp \cos \left( \omega_2 t \right) \right).$$

Note that neither  $q_1$  nor  $q_2$  have definite frequency.

**Example** (Double Pendulum). Consider a double pendulum, with length  $\ell$ , masses m, and angles  $\theta_1, \theta_2$ .

Using Lagrangians, we can find the equations of motion to be

$$2\ddot{\theta}_1 + \ddot{\theta_2} = -\frac{2g}{\ell}\theta_1$$

$$\ddot{\theta}_1 + \ddot{\theta_2} = -\frac{g}{\ell}\theta_2,$$

which we can rewrite as

$$M|\ddot{Q}\rangle = -K|Q\rangle$$
,

where

$$M = \begin{pmatrix} 2 & 1 \\ 1 & 1 \end{pmatrix}$$
$$K = \frac{g}{\ell} \begin{pmatrix} 2 & 0 \\ 0 & 1 \end{pmatrix}.$$

This is a generalized eigenvalue problem. Using the ansatz, we find that

$$\omega_{1,2}^2 = \left(2 \pm \sqrt{2}\right) \frac{g}{\ell}$$
$$|\Phi_{1,2}\rangle = \begin{pmatrix} 1\\ \mp \sqrt{2} \end{pmatrix}.$$

Note that

$$M^{-1}K = \frac{g}{\ell} \begin{pmatrix} 2 & -1 \\ -2 & 2 \end{pmatrix},$$

which is not a normal matrix, so the modes are not purely orthogonal. However, they are generally orthogonal, in the sense that  $\langle \Phi_1 | M | \Phi_2 \rangle = 0$ .

**Example** (Higher Dimensions). Consider a three mass system with constant mass m and spring constant k. The equations of motion for this system are

$$\begin{split} &m\ddot{q}_1 = -kq_1 - k\left(q_1 - q_2\right) \\ &m\ddot{q}_1 = -k\left(q_2 - q_1\right) - k\left(q_2 - q_3\right) \\ &m\ddot{q}_3 = -k\left(q_3 - q_2\right) - kq_3. \end{split}$$

Our eigenvalue problem is

$$k \begin{pmatrix} 2 & -1 & 0 \\ -1 & 2 & -1 \\ 0 & -1 & 2 \end{pmatrix} \begin{pmatrix} \phi_1 \\ \phi_2 \\ \phi_3 \end{pmatrix} = m\omega^2 \begin{pmatrix} \phi_1 \\ \phi_2 \\ \phi_3 \end{pmatrix}.$$

Solving for the normal modes and frequencies, we have

$$\omega_1^2 = \left(2 - \sqrt{2}\right) \frac{k}{m}$$

$$\omega_2^2 = \frac{2k}{m}$$

$$\omega_3^2 = \left(2 + \sqrt{2}\right) \frac{k}{m}$$

$$|\Phi_1\rangle = \begin{pmatrix} 1\\\sqrt{2}\\1 \end{pmatrix}$$

$$|\Phi_2\rangle = \begin{pmatrix} 1\\0\\-1 \end{pmatrix}$$

$$|\Phi_3\rangle = \begin{pmatrix} 1 \\ -\sqrt{2} \\ 1 \end{pmatrix}.$$

We say the mode with the greatest symmetry has the lowest frequency — in this case, it is the normal mode corresponding to  $|\Phi_1\rangle$ , which is where all the masses oscillate in the same direction.

**Example.** If we remove the left-most and right-most springs from the wall, we have a different eigenvalue problem

$$k \begin{pmatrix} 1 & -1 & 0 \\ -1 & 2 & -1 \\ 0 & -1 & 1 \end{pmatrix} \begin{pmatrix} \phi_1 \\ \phi_2 \\ \phi_3 \end{pmatrix} = m\omega^2 \begin{pmatrix} \phi_1 \\ \phi_2 \\ \phi_3 \end{pmatrix}.$$

Solving for the eigenvalues, we get

$$\omega_1^2 = 0$$

$$\omega_2^2 = \frac{k}{m}$$

$$\omega_3^2 = \frac{3k}{m}$$

$$|\Phi_1\rangle = \begin{pmatrix} 1\\1\\1 \end{pmatrix}$$

$$|\Phi_2\rangle = \begin{pmatrix} 1\\0\\-1 \end{pmatrix}$$

$$|\Phi_3\rangle = \begin{pmatrix} 1\\-2\\1 \end{pmatrix}.$$

We call  $|\Phi\rangle$  a zero mode — since we do not have connection to the wall, we have translational symmetry.  $^{xxxII}$ 

**Example** (A Bracelet). Consider a bracelet of masses and springs — i.e., the masses m are all connected to each other with spring constant k in a circle.

We will get

$$T = M^{-1}K$$

$$= \frac{k}{m} \begin{pmatrix} 2 & -1 & 0 & -1 \\ -1 & 2 & -1 & 0 \\ 0 & -1 & 2 & -1 \\ -1 & 0 & -1 & 2 \end{pmatrix}.$$

Note that each row of T is a discrete right shift of the first row.

Instead of solving the eigenvalue problem directly, we will use symmetry. Note that, since every row is a discrete right shift of the first row, we have the symmetry operation

$$S = \begin{pmatrix} 0 & 1 & 0 & 0 \\ 0 & 0 & 1 & 0 \\ 0 & 0 & 0 & 1 \\ 1 & 0 & 0 & 0 \end{pmatrix},$$

xxxIIChemists love this stuff.

which maps  $q_n \mapsto q_{n+1}$  modulo 4. Note that this means

$$TS = ST$$
,

so we can solve for the eigenbasis of S and obtain the same eigenbasis for T. Since  $S^4 = I_4$ , we must have the eigenvalues s of S satisfy  $s^4 = 1$ . The eigenvalues are, thus,

$$s_{\ell} = e^{i\pi\ell/2}$$

The eigenvectors have components  $\langle q_n | s_\ell \rangle = e^{i\pi\ell n/2}$  for n ranging from 0 to 3 corresponding to the four eigenvectors.

$$|s_{0}\rangle = \begin{pmatrix} 1\\1\\1\\1 \end{pmatrix}$$

$$|s_{1}\rangle = \begin{pmatrix} 1\\i\\-1\\-i \end{pmatrix}$$

$$|s_{2}\rangle = \begin{pmatrix} 1\\-1\\1\\-1 \end{pmatrix}$$

$$|s_{3}\rangle = \begin{pmatrix} 1\\-1\\1\\-1\\i \end{pmatrix}$$

Each  $|s_{\ell}\rangle$  has a phase difference of  $\ell\pi/2$  between adjacent masses, but neighboring masses in  $|s_{1,3}\rangle$  are  $\pm\pi/2$  out of phase, meaning they describe waves travelling in opposite directions. This is because their eigenvalues are complex conjugates —  $\overline{s_1} = s_3$ .

We know that each of  $|s_i\rangle$  are eigenvectors for T. We now find

$$T\left|s_{\ell}\right\rangle = \omega_{\ell}^{2}\left|s_{\ell}\right\rangle,$$

giving

$$\omega_0^2 = 0$$

$$\omega_1^2 = 2k/m$$

$$\omega_2^2 = 4k/m$$

$$\omega_2^2 = 2k/m$$

The benefit of having a symmetry operator is that we don't have to take any determinants.

We can now take

$$|\Phi_0\rangle = |s_0\rangle$$
$$|\Phi_2\rangle = |s_2\rangle,$$

as the eigenvectors are real. However, when it comes to the complex eigenvectors  $|s_1\rangle$  and  $|s_3\rangle$ , we need to take linear combinations that yield proper normal modes (note that  $\omega_1^2=\omega_3^2$ ).

In particular, we can consider the normal modes for  $\omega_1^2$  and  $\omega_3^2$  as standing waves — we add and subtract to yield proper normal modes.

$$|\Phi_1\rangle = \frac{1}{2} (|s_1\rangle + |s_3\rangle)$$
$$|\Phi_3\rangle = \frac{1}{2i} (|s_1\rangle - |s_3\rangle).$$

Both  $|\Phi_1\rangle$  and  $|\Phi_3\rangle$  are eigenvectors of T (but not S), which are normal modes.

Expanding to the N bracelet, the eigenvalues s of S are the N roots of unity,

$$s_{\ell} = e^{2i\pi\ell/N}$$

with the nth components

$$\langle q_n | s_\ell \rangle = e^{2i\pi\ell n/N}.$$

The  $N \times N$  version of the matrix is

$$T = \frac{k}{m} \begin{pmatrix} 2 & -1 & 0 & 0 & \cdots & 0 & -1 \\ -1 & 2 & -1 & 0 & \cdots & 0 & 0 \\ 0 & -1 & 2 & -1 & \cdots & 0 & 0 \\ \vdots & \vdots & \vdots & \vdots & \ddots & 0 & -1 \\ -1 & 0 & 0 & 0 & \cdots & -1 & 2 \end{pmatrix}.$$

Since we have limited ourselves to nearest neighbor interactions, we can find the eigenfrequencies by considering one bead and its two neighbors. In other words, we only need to look at a  $3 \times 3$  submatrix within T.

With  $\phi_n$ , the nth component of a T eigenvector on the position basis, the eigenvalue equation is

$$\omega^2 \phi_n = \frac{k}{m} \left( -\phi_{n+1} + 2\phi_n - \phi_{n-1} \right),\,$$

so we take  $\phi_n = \langle q_n | \phi_\ell \rangle$  to find

$$\begin{split} \omega_{\ell}^2 &= \frac{k}{m} \left( -e^{2\pi i \ell/N} + 2 - e^{-2\pi i \ell/N} \right) \\ &= \frac{2k}{m} \left( 1 - \cos \left( 2\pi \ell/N \right) \right) \\ &= \frac{4k}{m} \sin^2 \left( \pi \ell/N \right). \end{split}$$

**Example** (The Finite Chain). Having solved the N bracelet we may turn our attention to a chain of identical masses and springs with arbitrary N. Given as the number of masses increases, so does the difficult of calculation, but oddly when we go to infinity, the solution becomes much easier.

An infinite chain is invariant under the shift  $q_n \mapsto q_{n+1}$ , so there is an infinite symmetry operator S with 1 along the superdiagonal, with 0 everywhere else.

The symmetry of the chain is the same as that of the bracelet, meaning we have similar eigenvalues (but with arbitrary  $\alpha$  in place of  $2\pi \ell/N$ ).

$$s_{\alpha} = e^{i\alpha}$$

where  $\alpha$  is real. Since  $S|s_{\alpha}\rangle=e^{i\alpha}|s_{\alpha}\rangle$ , the eigenvectors are represented as infinite column vectors with adjacent entries shifted in phase by  $e^{\pm i\alpha}$ .

$$|s_{\alpha}\rangle = \begin{pmatrix} \vdots \\ e^{-2i\alpha} \\ e^{-i\alpha} \\ 1 \\ e^{i\alpha} \\ e^{2i\alpha} \\ \vdots \end{pmatrix}.$$

It is easier to represent the individual amplitudes as  $\langle q_n | s_\alpha \rangle = e^{i n \alpha}$  for  $n \in \mathbb{Z}$ . Since S and T commute in the infinite-dimensional case, we have

$$T|s_{\alpha}\rangle = \omega_{\alpha}^{2}|s_{\alpha}\rangle,$$

from which we calculate

$$\omega_{\alpha}^{2} = \frac{k}{m} \left( -e^{i\alpha} + 2 - e^{-i\alpha} \right)$$
$$= \frac{2k}{m} \left( 1 - \cos \alpha \right).$$

When  $\alpha = 0$ , we have the zero mode, and every other value of  $\alpha$  is doubly degenerate, meaning the bracelet with the normal mode  $|\Phi_{\alpha}\rangle$  is given by real linear combinations of  $|s_{\alpha}\rangle$  and  $|s_{-\alpha}\rangle$ .

On the finite chain, we maintain that  $q_0 = 0$  must be fixed, and  $q_{N+1} = 0$ . Thus, we get the normal modes of the form

$$|\Phi_{\alpha}\rangle = |s_{\alpha}\rangle - |s_{-\alpha}\rangle.$$

This property holds position n = 0 fixed, and at position n = N + 1, we get

$$\begin{aligned} q_{N+1} &= \langle q_{N+1} | \Phi_{\alpha} \rangle \\ &= e^{i\alpha(N+1)} - e^{-i\alpha(N+1)} \\ &= 2i \sin \left( \alpha \left( N + 1 \right) \right). \end{aligned}$$

The only way for  $q_{N+1} = 0$  to hold is to take

$$\alpha = \frac{\ell \pi}{N+1}$$

for each of  $\ell = 1, 2, ..., N$ .

Earlier, we had no conditions on  $\alpha$  beyond  $\alpha$  being real. By imposing the boundary conditions, we find that we need to quantize the system. The chain has normal modes

$$|\Phi_{\ell}\rangle = \begin{pmatrix} \sin\left(\frac{\ell\pi}{N+1}\right) \\ \sin\left(\frac{2\ell\pi}{N+1}\right) \\ \vdots \\ \sin\left(\frac{N\ell\pi}{N+1}\right) \end{pmatrix}$$

## **List of Tables**

1	Coordinate Conversions
2	Line, Area, and Volume Elements in Different Coordinate Systems
3	Complex Number Identities
4	$\delta_{ij}$ and $\epsilon_{ijk}$
5	Values of $\epsilon_{ijk}$
6	Vector Identities, $\epsilon_{ijk}$ , and $\delta_{ij}$
7	Important Taylor Series
8	Useful Trig Identities
9	Integrals of Powers and Products of Sine and Cosine
10	Gaussian Integrals
11	Gamma and Zeta Functions
12	Gradient, Divergence, and Curl
13	Gradients in Coordinate Systems
14	Integrating Scalar Fields
15	Integrating Vector Fields
16	Generalized Stokes's Theorem
17	Maxwell's Equations
18	Some Normal Matrices

Polar	Cylindrical	Spherical
$\mathbf{s} = s(\rho, \phi)$	$\mathbf{s} = s(\rho, \phi, z)$	$\mathbf{s} = \mathbf{s}(\mathbf{r}, \boldsymbol{\phi}, \boldsymbol{\theta})$
$\mathbf{s} = \rho \cos \phi \hat{\mathbf{i}} + \rho \sin \phi \hat{\mathbf{j}}$	$\mathbf{s} = \rho \cos \phi \hat{\mathbf{i}} + \rho \sin \phi \hat{\mathbf{j}} + z \hat{\mathbf{k}}$	$\mathbf{s} = r\cos\phi\sin\theta\hat{\mathbf{i}} + r\sin\phi\sin\theta\hat{\mathbf{j}} + r\cos\theta\hat{\mathbf{k}}$

**Table 1: Coordinate Conversions** 

Coordinate System Line Element		Area Element	Volume Element
Polar $d\mathbf{s} = \hat{\rho}d\rho + \rho\hat{\varphi}d\varphi$		$d\mathbf{a} = r dr d\phi$	_
Cylindrical $d\mathbf{s} = \hat{\rho}d\rho + \rho\hat{\phi}d\phi + \hat{k}dz$		$d\mathbf{a} = \hat{\rho}  \rho d\phi dz$	$d\tau = r dr d\phi dz$
Spherical	$d\mathbf{s} = \hat{r}dr + r\sin\theta\hat{\varphi}d\varphi + r\hat{\theta}d\theta$	$d\mathbf{a} = \hat{\mathbf{r}}  \mathbf{r}^2 \sin \theta  d\phi  d\theta$	$d\tau = r^2 \sin\theta  dr d\phi d\theta$

Table 2: Line, Area, and Volume Elements in Different Coordinate Systems

Quantity	Expression and/or Criterion
Cartesian form	z = a + bi
Polar form	$z = re^{i\phi}$
r	$\sqrt{a^2+b^2}$
ф	$\arg z = \arctan\left(\frac{b}{a}\right)$
Cartesian $\bar{z}$	$\overline{z} = a - bi$
Polar $\overline{z}$	$\overline{z} = re^{-i\phi}$
z	$\sqrt{z\overline{z}}$
Re(z)	$Re(z) = \frac{z + \overline{z}}{2}$
Im(z)	$Im(z) = \frac{z - \overline{z}}{2i}$
cosφ	$\frac{e^{i\phi} + e^{-i\phi}}{2}$
$\sin \phi$	$\frac{e^{i\phi}-e^{-i\phi}}{2i}$
e <sup>iφ</sup>	$\cos \phi + i \sin \phi$
$e^{\mathrm{i} n \phi}$	$\cos(n\phi) + i\sin(n\phi)$

Table 3: Complex Number Identities

Name	Notation	Definition
Kronecker Delta	$\delta_{ij}$	$\delta_{ij} = \begin{cases} 1 & i = j \\ 0 & i \neq j \end{cases}$
Levi–Civita Symbol	$\epsilon_{ijk}$	$\epsilon_{ijk} = \begin{cases} 1 & (i,j,k) = (1,2,3) \text{ cyclically} \\ -1 & (i,j,k) = (2,1,3) \text{ cyclically} \\ 0 & \text{else} \end{cases}$

Table 4:  $\delta_{ij}$  and  $\varepsilon_{ijk}$ 

Order of $(i, j, k)$	Value of $\varepsilon_{ijk}$
1,2,3	1
3, 1, 2	1
2,3,1	1
1,3,2	-1
2,1,3	-1
3,2,1	-1
else	0

Table 5: Values of  $\varepsilon_{ijk}$ 

Value	Index Notation
$\mathbf{A} \times \mathbf{B}$	$\sum \epsilon_{ijk} A_i B_j \hat{e}_k$
$(\mathbf{A} \times \mathbf{B})_{\ell}$	$\sum_{i,j}^{i,j,k} \epsilon_{ij\ell} A_i B_j$
$(\hat{e}_{i} \times \hat{e}_{j}) \cdot \hat{e}_{k}$	$\epsilon_{ijk}$
$B_{i}$	$\sum B_{\alpha}\delta_{\alpha i}$
$\mathbf{A} \cdot \mathbf{B}$	$\sum_{i,j}^{\alpha} A_i B_j \delta_{ij}$
$\sum_{j,k} \epsilon_{mjk} \epsilon_{njk}$	$2\delta_{mn}$
$\sum_{\ell}^{j,\ell} \epsilon_{mn\ell} \epsilon_{ij\ell}$	$\delta_{mi}\delta_{nj}-\delta_{mj}\delta_{ni}$

Table 6: Vector Identities,  $\varepsilon_{ijk}$  , and  $\delta_{ij}$ 

Function	Taylor Series
f(x)	$\sum_{k=0}^{\infty} \frac{(x-x_0)^n}{n!} \left( \frac{d^n f}{dx^n} \Big _{x=x_0} \right)$
$e^{x}$	$\sum_{n=0}^{\infty} \frac{x^n}{n!}$
$\cos x$	$\sum_{n=0}^{\infty} \frac{(-1)^n x^{2n}}{(2n)!}$
$\sin x$	$\sum_{n=0}^{\infty} \frac{(-1)^{n+1} x^{2n+1}}{(2n+1)!}$
$(1+x)^{\alpha}$	$\sum_{n=0}^{\infty} \frac{\prod_{k=0}^{n-1} (\alpha - k)}{n!} \chi^n$

Table 7: Important Taylor Series

Value	Expression
$\sin(\alpha \pm \beta)$	$\sin \alpha \cos \beta \pm \sin \beta \cos \alpha$
$\cos(\alpha \pm \beta)$	$\cos \alpha \cos \beta \mp \sin \alpha \sin \beta$
$\sin \alpha \cos \beta$	$\frac{1}{2}\left(\sin(\alpha+\beta)+\sin(\alpha-\beta)\right)$
$\cos \alpha \cos \beta$	$\frac{1}{2}\left(\cos(\alpha-\beta)+\cos(\alpha+\beta)\right)$
$\sin \alpha \sin \beta$	$\frac{1}{2}\left(\cos(\alpha-\beta)-\cos(\alpha+\beta)\right)$

Table 8: Useful Trig Identities

Integral	Shortcut
$\int \sin^{\mathfrak{m}}(x) \cos^{2k+1}(x)  \mathrm{d}x$	$\int u^{m} \left(1 - u^{2}\right)^{k} du$
$\int \sin^{2k+1}(x) \cos^{n}(x) dx$	$-\int (1-u^2)^k u^n du$
$\int \sin^2(x)  dx$	$\frac{x}{2} - \frac{1}{4}\sin(2x)$
$\int \cos^2(x)  dx$	$\frac{x}{2} + \frac{1}{4}\sin(2x)$

Table 9: Integrals of Powers and Products of Sine and Cosine

Expression	Value
$I_0$	$\frac{1}{2}\sqrt{\frac{\pi}{a}}$
$I_1$	$\frac{1}{2a}$
$I_{2n}$	$(-1)^n \frac{d^n}{da^n} I_0$
$I_{2n+1}$	$(-1)^n \frac{d^n}{da^n} I_1$

Table 10: Gaussian Integrals

Function	Expression
Γ(s)	$\int_0^\infty x^{s-1} e^{-x} dx$
$\zeta(s)$	$\sum_{k=1}^{\infty} \frac{1}{k^s}$
$\Gamma(s+1)$	sΓ(s)

Table 11: Gamma and Zeta Functions

Value	Expression In Terms of $\nabla$	Expression In Terms of ∂
Gradient	∇f	$\frac{\partial f}{\partial x}\hat{i} + \frac{\partial f}{\partial y}\hat{j} + \frac{\partial f}{\partial z}\hat{k}$
Divergence	$ abla \cdot \mathbf{E}$	$\sum_{\mathfrak{i}} \mathfrak{d}_{\mathfrak{i}} E_{\mathfrak{i}}$
Curl	$\nabla \times \mathbf{B}$	$\sum_{i,j,k} \epsilon_{ijk} \partial_i B_j \hat{e}_k$
Laplacian of a scalar field	$ abla^2 f$	$\sum_{i} \frac{\partial^{2}}{\partial i^{2}} f$
Laplacian of a vector field	$ abla^2\mathbf{v}$	$\sum_{i} \frac{\partial^{2}}{\partial i^{2}} v_{i} \hat{e}_{i}$

Table 12: Gradient, Divergence, and Curl

Coordinate System	Value	Expression	
	Gradient	$\nabla f = \frac{\partial f}{\partial x} \hat{i} + \frac{\partial f}{\partial y} \hat{j} + \frac{\partial f}{\partial z} \hat{k}$	
Cartesian	Laplacian	$\nabla \cdot \nabla f = \frac{\partial^2 f}{\partial x^2} + \frac{\partial^2 f}{\partial y^2} + \frac{\partial^2 f}{\partial z^2}$	
	Divergence	$\nabla \cdot \mathbf{A} = \frac{\partial}{\partial x} A_x + \frac{\partial}{\partial y} A_y + \frac{\partial}{\partial z} A_z$	
	Curl	$\nabla \times \mathbf{A} = \left(\frac{\partial A_z}{\partial y} - \frac{\partial A_y}{\partial z}\right)\hat{\mathbf{i}} + \left(\frac{\partial A_x}{\partial z} - \frac{\partial A_z}{\partial x}\right)\hat{\mathbf{j}} + \left(\frac{\partial A_y}{\partial x} - \frac{\partial A_x}{\partial y}\right)\hat{\mathbf{k}}$	
	Gradient	$\nabla f = \frac{\partial f}{\partial \rho} \hat{\rho} + \frac{1}{\rho} \frac{\partial f}{\partial \phi} \hat{\phi} + \frac{\partial f}{\partial z} \hat{z}$	
Cylindrical	Laplacian	$\nabla \cdot \nabla f = \frac{1}{\rho} \frac{\partial}{\partial \rho} \left( \rho \frac{\partial}{\partial \rho} \right) + \frac{1}{\rho^2} \frac{\partial^2 f}{\partial \phi^2} + \frac{\partial^2 f}{\partial z^2}$	
	Divergence	$\nabla \cdot \mathbf{A} = \frac{1}{\rho} \frac{\partial}{\partial \rho} \left( \rho \frac{\partial A_{\rho}}{\partial \rho} \right) + \frac{1}{\rho} \frac{\partial A_{\phi}}{\partial \phi} + \frac{\partial A_{z}}{\partial z}$	
Curl $\left(\frac{1}{\rho} \frac{\partial A_z}{\partial \phi} - \frac{\partial A}{\partial}\right)$		$\left(\frac{1}{\rho}\frac{\partial A_z}{\partial \phi} - \frac{\partial A_{\varphi}}{\partial z}\right)\hat{\rho} + \left(\frac{\partial A_{\rho}}{\partial z} - \frac{\partial A_z}{\partial \rho}\right)\hat{\phi} + \frac{1}{\rho}\left(\frac{\partial}{\partial \rho}\left(\rho A_{\varphi}\right) - \frac{\partial A_z}{\partial \varphi}\right)\hat{z}$	
	Gradient	$\nabla f = \frac{\partial f}{\partial r} \hat{r} + \frac{1}{r \sin \theta} \frac{\partial f}{\partial \phi} \hat{\phi} + \frac{1}{r} \frac{\partial f}{\partial \theta} \hat{\theta}$	
Spherical	Laplacian	$\nabla \cdot \nabla f = \frac{1}{r^2} \frac{\partial}{\partial r} \left( r^2 \frac{\partial f}{\partial r} \right) + \frac{1}{r^2 \sin^2 \theta} \frac{\partial^2 f}{\partial \phi^2} + \frac{1}{r^2 \sin \theta} \frac{\partial}{\partial \theta} \left( \sin \theta \frac{\partial f}{\partial \theta} \right)$	
	Divergence	$\nabla \cdot \mathbf{A} = \frac{1}{r^2} \frac{\partial}{\partial r} \left( r^2 \frac{\partial A_r}{\partial r} \right) + \frac{1}{r \sin \theta} \frac{\partial A_{\phi}}{\partial \phi} + \frac{1}{r \sin \theta} \frac{\partial}{\partial \theta} \left( \sin \theta A_{\theta} \right)$	
	Curl	$\nabla \times \mathbf{A} = \frac{1}{r \sin \theta} \left( \frac{\partial}{\partial \theta} \left( \sin \theta A_{\Phi} \right) - \frac{\partial A_{\theta}}{\partial \Phi} \right) \hat{\mathbf{r}} + \frac{1}{r} \left( \frac{\partial}{\partial r} \left( r A_{\theta} \right) - \frac{\partial}{\partial \theta} \left( A_{r} \right) \right) \hat{\mathbf{\phi}} + \frac{1}{r} \left( \frac{1}{\sin \theta} \frac{\partial A_{r}}{\partial \Phi} - \frac{\partial}{\partial r} \left( r A_{\Phi} \right) \right) \hat{\mathbf{\theta}}$	

Table 13: Gradients in Coordinate Systems

Type of Integral	Expression	
Line Integral, $C = y(x)$	$\int_{x_1}^{x_2} f(x, g(x)) \sqrt{1 + \left(\frac{dy}{dx}\right)^2} dx$	
Line Integral, $c(t) = (x(t), y(t))$	$\int_{t_1}^{t_2} f(x(t), y(t)) \left\  \frac{dc}{dt} \right\  dt$	
Surface Integral, $z = g(x, y)$	$\int_{D} f(x, y, g(x, y)) \sqrt{1 + \ \nabla g\ ^2} dxdy$	
Surface Integral, $\mathbf{r} = \mathbf{x}(s, t)$	$\int_{t_1}^{t_2} \int_{s_1}^{s_2} f(\mathbf{r}) \left\  \frac{\partial \mathbf{x}}{\partial s} \times \frac{\partial \mathbf{x}}{\partial t} \right\  ds dt.$	

Table 14: Integrating Scalar Fields

Type of Integral	Expression	
$\int_{C} \mathbf{B} \cdot d\vec{\ell}, \mathbf{B} = B_{x}\hat{\mathbf{i}} + B_{y}\hat{\mathbf{j}} + B_{z}\hat{\mathbf{k}}$	$\int_{C} B_{x} dx + B_{y} dy + B_{z} dz$	
$\int_{C} \mathbf{B} \cdot d\vec{\ell}, \mathbf{B} = B_{r}\hat{r} + B_{\phi}\hat{\phi} + B_{z}\hat{k}$	$\int_C B_r dr + rB_{\phi} d\phi + B_z dz$	
$\int_{C} \mathbf{B} \cdot d\vec{\ell}, \mathbf{B} = B_{r}\hat{r} + B_{\phi}\hat{\phi} + B_{\theta}\hat{\theta}$	$\int_{C} B_{r} dr + r \sin \theta B_{\phi} d\phi + B_{\theta} d\theta$	
$\int_{C} \mathbf{E} \cdot d\vec{\ell}, \mathbf{E} = \nabla \Phi$	$\Phi\left(t_{2}\right)-\Phi\left(t_{1}\right)$	
Φ	$\int_{S} \mathbf{E} \cdot d\mathbf{a}$	
$\Phi_{ m net}$	$\oint_{S} \mathbf{E} \cdot d\mathbf{a}$	

Table 15: Integrating Vector Fields

Theorem	Expression	
Divergence Theorem	$\int_{V} \nabla \cdot \mathbf{E}  d\tau = \oint_{\partial V} \mathbf{E} \cdot d\mathbf{a}$	
Divergence Theorem, Gradients	$\int_{\mathcal{V}} \nabla \Phi \ d\tau = \oint_{\partial \mathcal{V}} \Phi d\mathbf{a}$	
Divergence Theorem, Curls	$\int_{V} \nabla \times \mathbf{E}  d\tau = \oint_{\partial V}  d\mathbf{a} \times \mathbf{E}$	
Green's Theorem	$\int_{C} \mathbf{B} \cdot d\vec{\ell} = \int_{S} \left( \frac{\partial B_{y}}{\partial x} - \frac{\partial B_{x}}{\partial y} \right) dxdy$	
Stokes's Theorem	$\int_{S} \nabla \times \mathbf{B}  d\mathbf{a} = \int_{\partial S} \mathbf{B} \cdot d\vec{\ell}$	
Stokes's Theorem, Gradients	$\oint_{C} \Phi d\vec{\ell} = \int_{S} d\mathbf{a} \times \nabla \Phi$	
Stokes's Theorem, Curls	$\oint_{C} d\vec{\ell} \times \mathbf{E} = \int_{S} (d\mathbf{a} \times \nabla) \times \mathbf{E}$	

Table 16: Generalized Stokes's Theorem

Equation	Integral form	Differential Form
Gauss's Law	$\oint_{S} \mathbf{E} \cdot d\mathbf{a} = \frac{Q_{\text{encl}}}{\epsilon_{0}}$	$\nabla \cdot \mathbf{E} = \frac{\rho}{\epsilon_0}$
Gauss's Law for Magnetism	$\oint_{S} \mathbf{B} \cdot d\mathbf{a} = 0$	$\nabla \cdot \mathbf{B} = 0$
Faraday's Law	$\oint_C \mathbf{E} \cdot d\vec{\ell} = -\frac{d}{dt} \int_S \mathbf{B} \cdot d\mathbf{a}$	$\nabla \times \mathbf{E} = -\frac{\partial \mathbf{B}}{\partial \mathbf{t}}$
Ampère's Law	$\oint_{C} \mathbf{B} \cdot d\vec{\ell} = \mu_{0} I_{\text{encl}} + \mu_{0} \epsilon_{0} \int_{S} \mathbf{E} \cdot d\mathbf{a}$	$\nabla \times \mathbf{B} = \mu_0 \mathbf{J} + \mu_0 \varepsilon_0 \frac{\partial \mathbf{E}}{\partial t}$

Table 17: Maxwell's Equations

Matrix	Criterion	Eigenvalues	Eigenbasis
Hermitian	$H^* = H$	Real	$\mathbb{C}^{\mathfrak{n}}$
Anti-Hermitian	$Q^* = -Q$	Imaginary	$\mathbb{C}^{\mathfrak{n}}$
Symmetric	$S^T = S$	Real	$\mathbb{R}^{n}$
Anti-symmetric	$A^{T} = -A$	Imaginary	$\mathbb{R}^{n}$
Unitary	$U^* = U^{-1}$	Pure Phase	$\mathbb{C}^{n}$
Orthogonal	$O^T = O^{-1}$	Pure Phase	$\mathbb{R}^n$

Table 18: Some Normal Matrices