ACM/CS 114 Parallel algorithms for scientific applications

Michael A. G. Aïvázis

California Institute of Technology

Winter 2010

Hello world

```
#include <pthread.h>
2 #include <stdio.h>
  #define THREADS 10
  void* hello(void* threadID) {
     long id = (long) threadID;
6
     printf("hello from %02ld/%0d\n", id, THREADS);
8
     pthread exit (NULL);
     return NULL;
9
10
  int main(int argc, char* argv[]) {
     long id;
     int status;
14
     pthread_t threads[THREADS];
16
     for (id=0; id<THREADS; id++) {</pre>
        printf("creating thread %02ld\n", id);
18
         status = pthread_create(&threads[id], NULL, hello, (void*) id);
19
        if (status) {
2.0
            printf("error %d in pthread_create\n", status);
     }
24
     pthread exit (NULL);
     return 0;
26
27
```

Joining and detaching

- ▶ in the example in Slide 2, the main thread exits without knowing whether any of the threads it spawned have finished
 - saying "hello" is asynchronous
 - but gathering the results of parallel calculations normally isn't
- thread synchronization can be achieved using pthread_join
 - ▶ the pthread_create caller saves the thread id
 - ▶ the thread is scheduled, executes, and calls pthread_exit
 - any other thread can wait for this thread to finish by calling pthread_join with the saved thread id and also retrieve the termination status
- ▶ for this to work, a thread must be *joinable*
 - controlled by the thread creation attributes
 - for portability, you should always mark your joinable threads explicitly
- a thread that will never be joined may be detached
 - by setting the corresponding attribute during thread creation
 - ▶ or, by calling pthread_detach at any point
 - detaching a thread saves some system resources



Creating mutexes

- a mutex is a locking mechanism that helps guarantee exclusive access to a section of code, most often to control access to shared variables
- mutexes are created using

```
int pthread_mutex_init(
   pthread_mutex_t* mutex, const pthread_mutexattr_t* attr);
```

- they start out unlocked
- ▶ the attr enables more advanced (but perhaps non-portable) use
- mutexes are destroyed using

```
int pthread_mutex_destroy(pthread_mutex_t* mutex);
```

destroy mutexes you are no longer using to prevent resource leakage

Locking and unlocking mutexes

threads manipulate mutexes through

```
int pthread_mutex_lock(pthread_mutex_t* mutex);
int pthread_mutex_trylock(pthread_mutex_t* mutex);
int pthread_mutex_unlock(pthread_mutex_t* mutex);
```

- pthread_mutex_lock attempts to gain exclusive access
 - ▶ if the mutex is unlocked, it locks it and returns
 - otherwise, it blocks until the mutex is unlocked; when the mutex is unlocked, it locks it and returns
- pthread_mutex_unlock attempts to release a mutex
 - ▶ if it was previously locked by this thread, the mutex is unlocked
 - ▶ if it was not previously locked, the call returns with an error code
 - if it was locked, but not by the calling thread, the call returns an error code
- ▶ pthread_mutex_trylock attempts to lock the mutex
 - ▶ if it is unlocked, the call locks it and returns
 - ▶ if it is locked, the call returns immediately with a *busy* error code
- locking and unlocking mutexes is explicitly orchestrated by the programmer
- when multiple threads are blocked waiting for a mutex, there is no way to predict which one will succeed when the mutex becomes available

A reduction using threads

```
#include <pthread.h>
  #include <stdio.h>
  #define THREADS 10
  long sum = 0:
  pthread mutex t mutex;
  void* squares(void* threadID) {
9
     long id = (long) threadID;
     pthread mutex lock(&mutex);
     sum += id*id;
     pthread mutex unlock (&mutex);
     pthread exit (NULL);
     return NULL:
14
15
16
  int main(int argc, char* argv[]) {
     long id;
18
     pthread_t threads[THREADS];
     pthread mutex init(&mutex, NULL);
2.0
     for (id=0; id<THREADS; id++) {</pre>
        pthread create(&threads[id], NULL, hello, (void*) id);
     pthread_exit(NULL);
24
     return 0:
26 }
```

Condition variables

- condition variables build upon mutexes to enable threads to signal each other when some condition is met
- ▶ they are created using

```
int pthread_cond_init(
    pthread_cond_t* condition, const pthread_condattr_t* attr);
```

- and destroyed using
- int pthread_cond_destroy(pthread_cond_t* condition);

Using condition variables

▶ the following three routies implement the condition variable semantics

```
int pthread_cond_wait(pthread_cond_t* cond, pthread_mutex_t* mutex);
int pthread_cond_signal(pthread_cond_t* cond);
int pthread_cond_broadcast(pthread_cond_t* cond);
```

- pthread_cond_wait blocks the calling thread until the specified condition is signaled
 - ▶ it must be called with the mutex locked by the calling thread
 - pthread_cond_wait releases the lock while the thread is blocked
 - after the matching signal is received, the thread is awakened and the mutex locked
 - ▶ the thread is responsible for releasing the mutex when it is done
- pthread_cond_signal wakes up a thread that is waiting for the given condition variable
 - mutex must be locked before calling it
 - mutex must be unlocked after signaling, so blocking threads can be awakened
- pthread_cond_broadcast can be used instead if multiple threads are waiting for a signal

Condition variable caveats

- be careful with condition variables; make sure that
 - a thread has called pthread_cond_wait before any thread calls pthread_cond_signal
 - the mutex associated with the condition is locked before calling pthread_cond_wait, otherwise it might not block
 - the thread that calls pthread_cond_signal unlocks the associated mutex, otherwise the threads waiting for the signal will continue to block

Attributes of threads, mutexes and condition variables

- ▶ threads, mutexes and condition variables have associated attribute structures that can be used to tune the default creation parameters
- they are created and destroyed using

```
int pthread_attr_init(pthread_attr_t* attr);
int pthread_attr_destroy(pthread_attr_t* attr);

int pthread_mutexattr_init(pthread_mutexattr_t* attr);
int pthread_mutexattr_destroy(pthread_mutexattr_t* attr);

int pthread_condattr_init(pthread_condattr_t* attr);

int pthread_condattr_destroy(pthread_condattr_t* attr);
```

- typically, the defaults are adequate and tuned to the details of the operating system
- ▶ if you make excessive use of the stack, e.g. large arrays as local variable or deep recursion, you might want to know about

```
int pthread_attr_getstacksize(pthread_attr_t* attr, size_t* size);
int pthread_attr_setstacksize(pthread_attr_t* attr, size_t size);
```

Other useful routines

- a thread can access its unique id assigned by the system by calling
- pthread_t pthread_self(void);
- since system thread ids are opaque types, you cannot use == to compare them; instead, use
 - int pthread_equal(pthread_t id1, pthread_t id2);
- you can place all thread initialization code in a startup routine and call
- int pthread_once(pthread_once_t* control_structure, void (*startup_routine)


Advanced topics

- there is quite a bit more in the standard
- keys: creating and accessing per-thread data
 - as the code get more complicated, it becomes increasingly difficult to pass complete thread-specific information from function to function
 - possible solutions:
 - the FORTRAN syndrome, where subroutines end up having dozens of arguments
 - global variables
 - an associative container that allows each thread to store and retrieve arbitrary data
- finer control over thread scheduling
 - scheduling algorithms and priorities are implementation dependent
 - there are routines in the standard that enable explicit tuning
 - the standard guarantees that the routines will be available, but they don't have to be implemented
- condition variable sharing across processes
- explicitly canceling threads
- ▶ the somewhat complicated interactions between threads and signals
- other synchronization constructs: barriers and read/write locks



Summary

 well-designed threaded programs must follow the same strategy as any other concurrent program



- identify the work that can be done concurrently
- partition it in terms of work units, the fine grain tasks
- analyze the communication patterns among work units with an eye for critical sections and protecting shared data structures
- coarsen into threads, define the mutex categories and synchronization points
- let the OS schedule the threads onto physical processors
- debugging threaded programs is very difficult
 - preventing bugs through careful design is critical
 - so is instrumenting the program to gain confidence in its execution

