
CHEM 153A Week 7

February 24, 2025


Enzyme Kinetics

• **enzyme kinetics** = the discipline focused on determining the **rate** of a reaction and how it changes in response to changes in experimental parameters

In enzyme kinetics, we study the **steady state** because it provides us a stable and consistent way to measure enzyme activity, allowing us to determine key kinetic parameters that describe the enzyme's efficiency and affinity for its substrate




Changes in Concentrations of Various Species in an Enzyme-Catalyzed Reaction Over Time



Substrate Concentration Affects the Rate of Enzyme-Catalyzed Reactions

- pre-steady state = initial transient period during which ES builds up
- steady state = period during which [ES] and other intermediates remain constant



Steady State

- During the steady state, the concentration of the enzyme-substrate complex (ES) remains relatively constant, even though substrate is being converted to product. This allows us to measure the reaction rate without fluctuations due to changing ES concentrations, making the data more reliable
- By measuring V_0 during the **steady state** phase and before significant product has accumulated, we minimize the effect of the reverse reaction from P to S, ensuring that we are observing the enzyme's pure catalytic activity in the forward reaction from S to P under optimal conditions

Goal of Enzyme Kinetics


The primary goal of enzyme kinetics is to quantify enzyme activity and determine parameters that describe how efficiently an enzyme converts substrate into product.

Key Terms in Kinetics

- Vmax maximum reaction velocity when the enzyme is saturated with substrate
- Km Substrate concentration at which the reaction velocity is half of Vmax
- kcat Turnover number: how many substrate molecules an enzyme converts per second
- kcat/Km The best measure of enzyme efficiency

Initial Velocities of Enzyme-Catalyzed Reactions

- initial rate (initial velocity), $V_0 = \text{tangent to each curve taken at time} = 0$
 - reflects a steady state: (When we measure V_0 , we are looking at the initial phase of the reaction, just after the enzyme-substrate complex (ES) has reached a steady state)
- At the beginning of the reaction, [S] is regarded as constant.
- In enzyme kinetics, we use V_0 or the **initial reaction velocity**, because it gives us a clear picture of how the enzyme behaves at the very start of the reaction, before any other factors start to interfere.
- Each curve (refer to below) represents the **accumulation of product** ([P]) over time for a specific starting substrate concentration ([S])



At relatively low concentrations of substrate, V0 increases almost linearly with an increase in [S]


Why do we use V_0 ?

- 1. **Minimized Complications:** At the beginning of the reaction, there's plenty of substrate, and the product concentration is low. This means we can ignore the effects of product buildup, which could slow down or reverse the reaction. So, V₀ reflects the enzyme's "pure" activity with minimal interference
- 2. Consistent Conditions: By measuring V_0 , we are looking at the rate when conditions (like substrate concentration) are constant. This helps us make accurate comparisons between different enzyme reactions and understand how factors like substrate concentration affect enzyme activity
- 3. **Simple to Analyze**: Initial velocity measurements are straightforward to analyze mathematically, making it easier to determine important kinetic parameters like Vmax (maximum velocity) and Km (Michaelis constant), which describe the enzyme's efficiency and affinity for the substrate

In short, V_0 gives us a clear, consistent snapshot of the enzyme's performance without interference from other reaction changes over time

Effect of [S] on the V_0 of an Enzyme-Catalyzed Reaction

• the plateau-like V_0 region is close to the maximum velocity, V_{max}



Substrate concentration, [S] (mm)

If only the **beginning of the reaction** is monitored, over a period in which only a small percentage of the available substrate is converted to product, [S] can be regarded as constnat, to a reasonable approximation. V_0 can then be explored as a function of [S], which is adjusted by the investigator. The effect on V_0 of varying [S] when the enzyme concentration is held constant is shown in the graph.

Vmax: Maximum Reaction Rate

Vmax represents the maximum velocity of the reaction when all enzyme active sites are saturated with substrate


• Vmax is dependent on enzyme concentration. If you double the enzyme concentration, you double Vmax

Anecdote: If a restaurant can make 100 burgers per hour, adding more chefs (enzyme molecules) increases V_{max}

Effect of [S] on the V_0 of an Enzyme-Catalyzed Reaction


The Saturation Effect:

- \bullet V_{max} is observed when *virtually* all the enzyme is present as the ES complex
 - further increases in [S] have no effect on rate
 - responsible for the plateau observed



A Double-Reciprocal, or Lineweaver-Burk, Plot

ullet For enzymes obeying the Michaelis-Menten relationship, a plot of $1/V_0$ versus $1/[{\bf S}]$ yields a straight line



An algebraic transformation of the Michaelis-Menten equation converts the hyperbolic curve into a linear form.

• Lineweaver-Burk Equation:

$$\frac{1}{V_0} = \frac{K_m}{V_{max}[S]} + \frac{1}{V_{max}}$$

K_m (Michaelis Constant): Substrate Binding Affinity

Km is the substrate concentration at which the enzyme operates at half of V_{max} . It does not measure speed but rather the enzyme's affinity for the substrate

- Low Km means high substrate affinity (enzyme binds tightly to substrate)
- High Km means low substrate affinity (enzyme binds weakly)

When do we use K_m ?

• Comparing different enzymes that use the same substrate

Interpreting K_m and V_{max}

• K_m can vary for different substrates of the same enzyme

K _m for Some Enzymes and Substrates					
Enzyme	Substrate	K _m (mM)			
Hexokinase (brain)	ATP D-Glucose D-Fructose	0.4 0.05 1.5			
Carbonic anhydrase	HCO ₃ -	26			
Chymotrypsin	Glycyltyrosinylglycine N-Benzoyltyrosinamide	108 2.5			
β-Galactosidase	D-Lactose	4.0			
Threonine dehydratase	L-Threonine	5.0			

Km can vary for different substrates of the same enzyme because each substrate has a unique interaction with the enzyme, leading to differences in binding affinity, catalytic efficiency, and how the enzyme accommodates each substrate

The General Rate Constant, k_{cat}

- general rate constant, $K_{cat} =$ describes the limiting rate of any enzyme-catalyzed reaction at saturation
- k_{cat} , also known as the **turnover number**, represents the maximum number of substrate molecules that a single enzyme can convert to product per unit time when the enzyme is fully saturated with substrate
- In the Michaelis-Menten equation, $k_{cat} = V_{max}/[E_t]$

$$V_0 = \frac{V_{max}[S]}{K_m + [S]} = \frac{k_{cat}[Et][S]}{K_m + [S]}$$

If an enzyme has a k_{cat} of $10000s^{-1}$, this means that each enzyme molecule, when fully loaded with substrate, can convert 10000 molecules of substrate into product every second

k_{cat} - Turnover Number (Catalytic Constant)

 k_{cat} is the turnover number, which measures how many substrate molecules an enzyme converts to product per second.

$$k_{cat} = \frac{V_{max}}{[E]_{total}}$$

- A high k_{cat} means an enzyme works very fast
- A low k_{cat} means an enzyme works slowly

When do we use k_{cat} ?

• Comparing how fast different enzymes catalyze reactions in saturating conditions

Anecdote: If each chef (enzyme) can make 10 burgers per hour, k_{cat} is 10 per hour per chef. More chefs increase V_{max} , but k_{cat} stays the same.

k_{cat} For Some Enzymes

Turnover Number, k_{cat} , of Some Enzymes					
Enzyme	Substrate	k _{cet} (s ⁻¹)			
Catalase	H ₂ O ₂	40,000,000			
Carbonic anhydrase	HCO ₃ -	400,000			
Acetylcholinesterase	Acetylcholine	14,000			
β-Lactamase	Benzylpenicillin	2,000			
Fumarase	Fumarate	800			
RecA protein (an ATPase)	ATP	0.5			

Catalytic Efficiency (k_{cat}/K_m) - The Best Enzyme Parameter


 k_{cat}/K_m is the best measure of enzyme efficiency. It considers both speed (k_{cat}) and binding strength (K_m) .

- High k_{cat}/K_m means an enzyme is fast and binds well (efficient even at low [S])
- Low k_{cat}/K_m means an enzyme is slow or binds poorly (inefficient at low [S])

When do we use k_{cat}/K_m ?

• When comparing enzymes that operate under non-saturating conditions, which is often the case in living cells where $[S] \ll K_m$

Diffusion-limited enzyme reactions: If k_{cat}/K_m approaches $10^8 - 10^9 M^{-1} s^{-1}$, the enzyme is operating at the **diffusion limit**, meaning every substrate molecule that collides with the enzyme is converted into product. These are often called "**perfect enzymes**".



k_{cat}/K_m : catalytic efficiency of the enzyme

High values of k_{cat}/K_m indicate a highly efficient enzyme, meaning it converts substrate to product quickly, even at low substrate concentrations

Enzymes for Which $k_{\rm cat}/K_{\rm m}$ Is Close to the Diffusion-Controlled Limit (10 8 to 10 9 M $^{-1}$ s $^{-1}$)					
Enzyme	Substrate	$k_{\rm cat}$ (s ⁻¹)	К _т (м)	$k_{\rm cat}/K_{\rm m}$ (M ⁻¹ s ⁻¹)	
Acetylcholinesterase	Acetylcholine	1.4×10 ⁴	9×10 ⁻⁵	1.6×10 ⁸	
Carbonic anhydrase	CO ₂ HCO ₃ ⁻	1×10 ⁶ 4×10 ⁵	1.2×10 ⁻² 2.6×10 ⁻²	8.3×10 ⁷ 1.5×10 ⁷	
Catalase	H ₂ O ₂	4×10 ⁷	1.1×10 ⁰	4×10 ⁷	
Crotonase	Crotonyl-CoA	5.7×10 ³	2×10 ⁻⁵	2.8×10 ⁸	
Fumarase	Fumarate Malate	8×10 ² 9×10 ²	5×10 ⁻⁶ 2.5×10 ⁻⁵	1.6×10 ⁸ 3.6×10 ⁷	
β-Lactamase	Benzylpenicill in	2.0×10 ³	2×10 ⁻⁵	1×10 ⁸	

Think of an Enzyme as a Worker on an Assembly Line:

- k_{cat} (turnover number) tells you how many products the worker can assemble per hour, assuming they always have enough materials (substrate) to work at full capacity
- k_{cat}/K_m (catalytic efficiency) tells you how good the worker is at both grabbing the materials and assembling them quickly. A worker who is both fast and good at picking materials from a moving belt is more efficient

Key takeaways

- k_{cat} is useful when substrate is abundant (measuring intrinsic catalytic power)
- k_{cat}/K_m is more useful under physiological conditions where substrate is often limiting
- Both parameters together give a complete picture of enzyme function one measures speed under saturation, the other measures efficiency under normal cellular conditions

Sumarry of k_{cat} and catalytic efficiency

• Turnover number (k_{cat}) is the maximal number of molecules of substrate converted to product per second that occurs for a single enzyme (more specifically, single active site)

$$k_{cat} = \frac{V_{max}}{[E_{tot}]}$$

- \bullet K_m is essentially the degree of attraction of the substrate to the active site
 - Lower K_m is higher attraction
- If we combine k_{cat} and K_m , we can get a measure for enzyme efficiency how able the enzyme is to take substrate and produce product quickly
- This is the catalytic efficiency

$$cat eff = \frac{K_{cat}}{K_m}$$


Enzyme Kinetics Helps Us Understand How Enzymes Function in Biological Systems

Key takeaways:

- 1. K_m measures substrate binding, not enzyme speed
- 2. V_{max} depends on enzyme concentration
- 3. K_{cat} measures how fast an enzyme converts substrate to product in saturating conditions
- 4. k_{cat}/K_m is the best parameter for enzyme efficiency
- 5. Inhibitors alter kinetics in predictable ways, crucial for drug development

Reversible Inhibition


- Enzyme inhibitors are molecules that interfere with substrate binding or catalysis, slowing or halting enzymatic reactions
 - Important pharmaceutical agents
- Reversible enzyme inhibitors are inhibitors that can bind reversibly to an enzyme
- In the context of reversible enzyme inhibition, α is a factor used in the Michaelis-Menten and Lineweaver-Burk equations to describe how inhibitors affect the kinetics of enzyme-catalyzed reactions. It represents the extent to which an inhibitor affects the binding of the substrate to the enzyme
 - $-\alpha$ affects the free enzyme in competitive and mixed inhibition
 - $-\alpha'$ affects the enzyme-substrate complex in uncompetitive and mixed inhibition



Transition state analogs are competitive inhibitors

- Unsurprisingly, molecules that mimic the transition state are able to bind to enzyme active sites, acting as strong inhibitors
- These transition state analogs mimic key structural features but are non-reactive
- We'll revisit this when we discuss inhibition...
- Transition state analogs bind the active site, and therefore compete with the substrate

Proline racemase (PR)



Pyrrole-2-carboxylate

Reversible Inhibition

Competitive	<u>Uncompetitive</u>	<u>Mixed</u>	Noncompetitive
- Non-allosteric	- Allosteric	- Allosteric	- Allosteric
- ${}^{\uparrow}K_{m}$, unaffected	- ΨK_m , ΨV_{max}	- \uparrow or \lor K _m , \lor V _{max}	- unaffected K_m ,
V_{max}	- ES+I ↔ ESI	- E+I ↔ EI	ΨV_{max}
- E+I ↔ EI		- ES+I ↔ ESI	- E+I ↔ EI
			- ES+I ↔ ESI
+1 -1 V _{max}	Increasing $\alpha' N_{max}$ $\alpha' = 2$ $\alpha' = 1.5$ $\alpha' = 1$ (no Stope $K_{to} N_{to}$ $\alpha' = 1 + \frac{1}{h}$	Increasing $\alpha = 1.5$ or $\alpha = 1.25$ (II) $\alpha = 1.25$ (III) $\alpha = 1.25$ (III) $\alpha = \alpha' = 1$ (no inhibitor) $\alpha = \alpha' = 1$ (no inhibitor) Slope $\alpha \neq \alpha' = 1$ (no inhibitor)	Increasing [1]