

GPU Teaching Kit

Accelerated Computing




Lecture 2.2 - Introduction to CUDA C

Memory Allocation and Data Movement API Functions

Objective

- To learn the basic API functions in CUDA host code
 - Device Memory Allocation
 - Host-Device Data Transfer

Data Parallelism - Vector Addition Example




3

Vector Addition – Traditional C Code


```
// Compute vector sum C = A + B
void vecAdd(float *h A, float *h B, float *h C, int n)
    int i;
    for (i = 0; i < n; i++) h C[i] = h A[i] + h B[i];
int main()
    // Memory allocation for h_A, h_B, and h_C
    // I/O to read h_A and h_B, N elements
   vecAdd(h A, h B, h C, N);
```

Heterogeneous Computing vecAdd CUDA Host Code



```
#include <cuda.h>
void vecAdd(float *h_A, float *h_B, float *h_C, int n)
  int size = n* sizeof(float);
 float *d A, *d B, *d C;
 // Part 1
 // Allocate device memory for A, B, and C
 // copy A and B to device memory
 // Part 2
 // Kernel launch code – the device performs the actual vector addition
 // Part 3
 // copy C from the device memory
 // Free device vectors
```


Partial Overview of CUDA Memories



- Device code can:
 - R/W per-thread registers
 - R/W all-shared global memory
- Host code can
 - Transfer data to/from per grid global memory

We will cover more memory types and more sophisticated memory models later.


CUDA Device Memory Management API functions



cudaMalloc()

- Allocates an object in the device global memory
- Two parameters
 - Address of a pointer to the allocated object
 - Size of allocated object in terms of bytes
- cudaFree()
 - Frees object from device global memory
 - One parameter
 - Pointer to freed object

Host-Device Data Transfer API functions



cudaMemcpy()

- memory data transfer
- Requires four parameters
 - Pointer to destination
 - Pointer to source
 - Number of bytes copied
 - Type/Direction of transfer
- Transfer to device is asynchronous

Vector Addition Host Code

```
void vecAdd(float *h_A, float *h_B, float *h_C, int n)
  int size = n * sizeof(float); float *d A, *d B, *d C;
  cudaMalloc((void **) &d_A, size);
  cudaMemcpy(d A, h A, size, cudaMemcpyHostToDevice);
  cudaMalloc((void **) &d B, size);
   cudaMemcpy(d B, h B, size, cudaMemcpyHostToDevice);
   cudaMalloc((void **) &d_C, size);
  // Kernel invocation code – to be shown later
   cudaMemcpy(h C, d C, size, cudaMemcpyDeviceToHost);
   cudaFree(d_A); cudaFree(d_B); cudaFree (d_C);
```

In Practice, Check for API Errors in Host Code

```
cudaError_t err = cudaMalloc((void **) &d_A, size);

if (err != cudaSuccess) {
   printf("%s in %s at line %d\n", cudaGetErrorString(err), __FILE__,
   __LINE__);
   exit(EXIT_FAILURE);
}
```



GPU Teaching Kit

Accelerated Computing





The GPU Teaching Kit is licensed by NVIDIA and the University of Illinois under the <u>Creative Commons Attribution-NonCommercial 4.0 International License.</u>