# **CS 343 - Operating Systems**

# Module-3A Inter Process Communication



Dr. John Jose

Associate Professor

Department of Computer Science & Engineering
Indian Institute of Technology Guwahati

#### **Session Outline**

- Multitasking/Multiprocessing Applications
- Review of process management functions
- Process creation and termination
- Inter Process Communication (IPC)
- **❖** Producer-Consumer problem
- ❖ IPC- shared memory
- ❖ IPC-message passing
- Direct vs indirect communication

# **Multitasking in Mobile Systems**

- Some mobile systems allow only one process to run, others suspended
- Due to screen space limits, processor limits, we have constraints
- Single foreground process- controlled via user interface
  - Multiple background processes— in memory, running, but not on the display, and with limits
  - Limits include single, short task, receiving notification of events, specific long-running tasks like audio playback
- Android runs foreground and background, with fewer limits
  - Background process uses a service to perform tasks
    - Service can keep running even if background process is suspended
    - Service has no user interface, small memory use

## **Process Management**

- Creating and deleting both user and system processes
- Suspending and resuming processes (context switching, scheduling)
- Providing mechanisms for process communication
- Providing mechanisms for process synchronization
- Providing mechanisms for deadlock handling

#### **Process Creation**

- Parent process create children processes, which, in turn create other processes, forming a tree of processes
- Generally, process identified and managed via a process identifier (pid)
- Resource sharing options
  - Parent and children share all resources
  - Children share subset of parent's resources
  - Parent and child share no resources
- Execution options
  - Parent and children execute concurrently
  - Parent waits until children terminate

#### **Process Termination**

- Process executes last statement and then asks the operating system to delete it using the exit() system call.
  - Returns status data from child to parent
  - Process' resources are deallocated by operating system
- Parent may terminate the execution of children processes using the abort() system call. Some reasons for doing so:
  - Child has exceeded allocated resources
  - Task assigned to child is no longer required
  - The parent is exiting and the operating systems does not allow a child to continue if its parent terminates

#### **Context Switch**

- When CPU switches to another process, the system must save the state of the old process and load the saved state for the new process via a context switch
- Context of a process represented in the PCB
- Context-switch time is overhead; the system does no useful work while switching
- Time dependent on hardware support

## **Process Management**

- Creating and deleting both user and system processes
- Suspending and resuming processes (context switching, scheduling)
- Providing mechanisms for process communication
- Providing mechanisms for process synchronization
- Providing mechanisms for deadlock handling


## **Inter-process Communication**

- Processes within a system may be independent or cooperating
- Independent process cannot affect or be affected by the execution of another process
- Cooperating process can affect or be affected by other processes, including sharing data
- Reasons for cooperating processes:
  - Information sharing
  - Computation speedup
  - Modularity
  - Convenience


#### **Communications Models**

- Cooperating processes need interprocess communication (IPC)
- ❖Two models of IPC:

#### Message passing



#### **Shared memory**



#### **Producer-Consumer Problem**

- Paradigm for cooperating processes, producer process produces information that is consumed by a consumer process
  - unbounded-buffer places no practical limit on the size of the buffer
  - bounded-buffer assumes that there is a fixed buffer size

#### Bounded-Buffer – Producer & Consumer


```
item buffer[BUFFER SIZE]; int in = 0; int out = 0;
        Producer
item next produced;
while (true)
       /* produce an item in next
       produced */
   while (((in + 1)% BUFFER SIZE)
   == out)
        ; /* do nothing */
   buffer[in] = next produced;
    in = (in + 1) % BUFFER SIZE;
```

#### Consumer

```
item next consumed;
while (true)
   while (in == out)
       ; /* do nothing */
   next consumed = buffer[out];
   out = (out + 1) % BUFFER SIZE;
   /* consume the item in next
consumed */
```


## **IPC – Shared Memory**

- An area of memory shared among the processes that wish to communicate
- The communication is under the control of the users processes not the operating system.
- Major issues is to provide mechanism that will allow the user processes to synchronize their actions when they access shared memory.



# **IPC – Message Passing**

- Mechanism for processes to communicate and to synchronize their actions
- Message system processes communicate with each other without resorting to shared variables
- IPC facility provides two operations:
  - send(message)
  - receive(message)
- ❖ The message size is either fixed or variable



## **IPC – Message Passing**

- ❖ If processes P and Q wish to communicate, they need to:
  - Establish a communication link between them
  - Exchange messages via send/receive
- Implementation issues:
  - How are links established?
  - Can a link be associated with more than two processes?
  - How many links between a pair of communicating processes?
  - What is the capacity of a link?
  - Unidirectional or bi-directional link?
  - Is the size of a message in the link fixed or variable?

# **IPC – Message Passing**

- Implementation of communication link
  - Physical:
    - Shared memory
    - Hardware bus
    - ❖ Network
  - ❖ Logical:
    - Direct or indirect
    - Synchronous or asynchronous
    - Automatic or explicit buffering

#### **Direct Communication**

- Processes must name each other explicitly:
  - ❖ send (P, message) send a message to process P
  - receive(Q, message) receive a message from process Q
- Properties of communication link
  - Links are established automatically
  - ❖ A link is associated with exactly one pair of communicating processes
  - ❖ Between each pair there exists exactly one link
  - The link may be unidirectional, but is usually bi-directional

#### **Indirect Communication**

- Messages are directed and received from mailboxes
  - Each mailbox has a unique id
  - Processes can communicate only if they share a mailbox
- Properties of communication link
  - Link established only if processes share a common mailbox
  - Each pair of processes may share several communication links
  - Link may be unidirectional or bi-directional

#### **Indirect Communication**

- Operations
  - create a new mailbox
  - send and receive messages through mailbox
  - destroy a mailbox
- Primitives are defined as:
- send(A, message) send a message to mailbox A
- receive(A, message) receive a message from mailbox A

#### **Indirect Communication**

- Mailbox sharing
  - ❖ P<sub>1</sub>, P<sub>2</sub>, and P<sub>3</sub> share mailbox A
  - ❖ P₁, sends; P₂ and P₃ receive
- Solutions
  - Allow a link to be associated with at most two processes
  - Allow only one process at a time to execute a receive operation
  - Allow the system to select arbitrarily the receiver. Sender is notified who the receiver was.

# **Synchronization**

- Message passing may be either blocking or non-blocking
- Blocking is considered synchronous
  - Blocking send -- the sender is blocked until the message is received
  - Blocking receive -- the receiver is blocked until a message is available

## **Synchronization**

- Message passing may be either blocking or non-blocking
- Non-blocking is considered asynchronous
  - Non-blocking send -- the sender sends the message and continue
  - ❖ Non-blocking receive -- the receiver receives:
    - ❖ A valid message, or
    - Null message

# **Buffering**

- Queue of messages attached to the link.
- Implemented in one of three ways
  - 1. Zero capacity no messages are queued on a link. Sender must wait for receiver
  - 2. Bounded capacity finite length of *n* messages Sender must wait if link full
  - 3. Unbounded capacity infinite length Sender never waits



johnjose@iitg.ac.in

http://www.iitg.ac.in/johnjose/