#### Documentation

# Dynamic Artillery Pieces (DAP)

Last update: v1.0

What is this

Video Tutorials

If you need an SQF editor

Run the script for a first look

Install the script in my mission ★★★

Choose which side(s) will use DAP

Select all artillery pieces you want

**Defining targets** 

**Defining triggers** 

**Defining fire missions** 

Testing your fire missions

Pocket guide: Artillery Piece Calibers

Pocket quide: Magazines (Ammo)

Fixing: a piece or ammunition is not recognized by DAP

Fixing: some artillery pieces are frozen

Fixing: investigate further what is happening (Debugging)

Contribute to the DAP script

**Author** 

#### What is this

**DAP** is an *Arma 3* script that allows the Mission Editor (you) to create real (or virtual) artillery/mortar fire missions faster and smarter for one or multiple sides, using *Eden* marker's positions and an external fire missions list where you plan the caliber, ammo type, rounds, cycle of repetition and more. *DAP* doesn't change any original *Arma* Al behavior, saving server performance, and preserving the *Arma* integrity and compatibility with any mod.

DAP supports the scheduling of unlimited fire missions per side, each of which can be configured separately:

#### Per fire-mission:

- 1. Real or virtual Virtual is WIP
- 2. The side that owns the fire mission;
- 3. Potential target sectors (Eden markers);
- 4. How much weaponry you want in the fire mission;
- 5. What caliber these weaponry will be (Light, Medium, Heavy, Super Heavy);
- 6. Ammunition type (HE, Cluster, Smoke, Flare etc);
- 7. Control the volume of rounds:
- 8. How many cycle repetitions;
- 9. Triggers that will trigger the fire mission (trigger activation, timer, kill/destruction).

#### **Global settings:**

- Custom callsign for artillery side;
- Which pieces can use CommandChat to report (On/Off)
- Infinite ammunition (On/Off);
- Fire mission areas visible on the player map (On/Off) WIP
- Custom cooldown between cycles of fire mission repetition;
- Pre-defined whitelist of weaponry working (Arma, DLCs, RHS, CUP, etc);
- Pre-defined whitelist of ammunition working (Arma, DLCs, RHS, CUP, etc);
- Pre-defined blacklist of currently bugged vehicles;
- Pre-defined blacklist of currently bugged ammunition;
- Debug mode;
- Etc...

**Creation concept:** make use of artillery pieces practical and fast for multiplayer or single-player missions.

#### For multiplayer and single-player

DAP works for all game purposes, including multiplayer and single-player.

#### For Hosted and Dedicated servers

DAP was built for both server types.

## Compatible with ACE, RHS, CUP, or any others

Yes! *DAP* has in its *fn\_DAP\_management.sqf* file a whitelist of vehicles and weapons that are considered Artillery Pieces, and this list contains assets from mods such as RHS and CUP that have already been tested with *DAP* and approved. The same occurs for each ammunition that these pieces employ.

#### Debug monitor and feedback available

*DAP* was built to make the Mission Editor life easier, so if you want to get to know the <u>debug</u> monitor now, check this out.

## Video Tutorials

Soon. But subscribe to my channel to be notified on the day I release the DAP video

tutorials: https://www.youtube.com/@thy1984



On YouTube, a playlist to help you too.

# **VIDEO TUTORIALS**

# lf you need an SQF editor

Sure, I'm using Visual Studio Code with this customs specific for Arma 3:

https://forums.bohemia.net/forums/topic/239960-vs-code-tutorial-how-to-config-vs-code-for-a rma-3-2023/

If you need something simpler:

https://notepad-plus-plus.org/, install it and, when you open some script file, go to Notepad++ main menu, "Language" and select "C" as file language. That's it.


## Run the script for a first look

- 1. Go to <a href="https://steamcommunity.com/sharedfiles/filedetails/?id=3371824030">https://steamcommunity.com/sharedfiles/filedetails/?id=3371824030</a>
- 2. Subscribe and wait for Steam to download it;
- 3. Open *Arma* 3, go to Multiplayer > Server browser > Host server > click Host Server button;
- 4. Select "Virtual Reality" map and, after that, select "DAP (...)";
- 5. Play.

Important: if you want to apply this script in your own missions, check this out.

#### Install the script in my mission $\star$ $\star$

- 1. Go to: https://github.com/aldolammel/Arma-3-Dynamic-Artillery-Pieces-Script
- 2. Download the zip and open it;



- 3. In zip, get in the "dap\_for\_your\_mission" folder;
- Copy all "dap\_for\_your\_mission" content to your mission folder root:
   <u>DRIVE:\Users\yourName\Documents\Arma 3\yourProfile\missions\yourMission\</u>
- 5. WARNING: in the mission folder root, if you already have a "description.ext" file, don't replace the current file with the new one. Just add the code below in the current file:

6. WARNING: still in the mission folder, if you already have an "init.sqf" file, don't replace the current file with the new one. Just add the code below in the current file:

```
// DAP > HIDE THE SCRIPT MARKERS:
if ( !DAP_isOn || !DAP_debug_isOn ) then {{private _mkr = toUpper _x; private _mkrChecking = _mkr splitString DAP_spacer; if (_mkrChecking find DAP_prefix isNotEqualTo -1) then {_x setMarkerAlpha 0}} forEach allMapMarkers};
```

7. WARNING: finally, in the mission folder, if you already have an "initPlayerLocal.sqf" file, don't replace the current file with the new one. Just add the code below in the current file:

// DAP: DYNAMIC ARTILLERY PIECES
[player] execVM "DynamicArtilleryPieces\fn\_DAP\_playerLocal.sqf";

8. Now, let's tell DAP what you want from it!

#### Choose which side(s) will use DAP

In *Arma 3* there are 4 sides available: Blufor, Opfor, Independent, and Civilian. Civilian is not an option for obvious reasons. That said, open the *DAP Management*:


\DynamicArtilleryPieces\fn\_DAP\_management.sqf

Set as *true* the side you want to build fire missions:

#### Select all artillery pieces you want

The next step is to set in your mission those vehicles and static/turret weapons (both are considered here "artillery pieces" or just "pieces") with artillery or mortar capacities. But let's start with just one to make the process easier.

Press "F" on Eden and keep the "Place vehicles with crew" checked:




DAP doesn't work with empty pieces.






Open the piece attributes and add this name or whatever you wish since it brings "dap" in its variable name, for example:

- dap\_1 (Recommended)
- an\_dap\_example
- an\_example\_dap




Notice the variable "dap\_..." is always in the piece and NOT in crew members. Eden will create some for them.

Once you named one piece, just *Copy and Paste* how much you want because *Eden* will follow the *DAP* naming logic, adding a different number for each new copied piece (below).




For another type of piece, again, create the first one and name it using a higher number to avoid duplicate (don't worry, *Eden* tells you if it happens):



Awesome, you got your fire support team! Let's set some targets now.

## Defining targets


Targets are *Eden* markers you will *Drag and Drop* in your mission. You will always use the "*Destroy*" marker for *DAP*, never another type.



Above, the Asset-Browser on Eden Editor.


Unlike piece naming, targets need to receive the side tag and a sector letter. Sounds weird but it's easy. Check these examples:

- dap\_blu\_a\_1
- dap\_blu\_a\_20
- dap\_blu\_z\_1
- dap\_blu\_z\_999



Above, editing a target-marker attributes on *Eden*. The name is telling DAP this target belongs to the BluFor fire teams and they calling this target sector "A".

Now, *Copy and Paste* how many targets "A" you want to give for BluFor attacks. After that, if you want, create some targets for sector "B" and so on, if needed.



Important: if you set a fire mission to hammer sector "A", *DAP* will look for artillery pieces you placed on the mission that better fit that request. Once *DAP* has the team to execute the fire mission, *DAP* will select randomly just one of those target markers of the sector "A". Use how many target markers you want. It doesn't affect any server performance.

Perfect! Before we jump into the coolest part, you need to <u>set a trigger for each fire mission you have</u> <u>in mind</u>.

#### Defining triggers


A fire mission doesn't take place out of the blue. You always need to tell *DAP* (NO EXCEPTION) what should initiate bombs being dropped from the sky.

There are 3 methods:

- by Eden trigger;
- by killing or destroying a target (unit, vehicle, building);
- by timer;
- and also you can combine them.


#### Fire mission released by Trigger

As any other trigger. You define what conditions will activate it. You only need to set a varname on it to use later.



#### Fire mission released by Target

You could start a fire mission if a unit dies or, for example, a vehicle blows up. Even a breakable structure collapse would release a fire mission with this method.



# Fire mission released by Timer

This method you do directly in the fire missions file you will see next.

# Combining all of them

And the combination you do also directly in the fire missions file.

Okay, so let's do it!

#### Defining fire missions

And then the fire missions, finally. Open your Fire Missions file:

\DynamicArtilleryPieces\fn\_DAP\_fireMissions.sqf

This row is literally a fire mission. You can create fire missions as much as you want or the server supports with no performance drops.

```
[BLUFOR, [DAP_targetMrksBLU, "A"], [5, _caliber_MEDIUM, _ammo_CLUSTER, 2, 2], [trg_fm_1, 5]] call THY_fnc_EBLUFOR, [DAP_targetMrksBLU, "B"], [5, _caliber_SUPERHEAVY, _ammo_HE, 12, 2], [trg_fm_2, unit_target_1]] [BLUFOR, [DAP_targetMrksBLU, "B"], [3, _caliber_LIGHT, _ammo_HE, 6, 1], [trg_fm_3]] call THY_fnc_DAP_add_fite [BLUFOR, [DAP_targetMrksBLU, "A"], [5, _caliber_ANY, _ammo_HE, 5, 2], [trg_fm_4]] call THY_fnc_DAP_add_fite [BLUFOR, [DAP_targetMrksBLU, "A"], [5, _caliber_ANY, _ammo_HE, 5, 2], [trg_fm_4]] call THY_fnc_DAP_add_fite [BLUFOR, [DAP_targetMrksBLU, "A"], [5, _caliber_ANY, _ammo_HE, 5, 2], [trg_fm_4]] call THY_fnc_DAP_add_fite [BLUFOR, [DAP_targetMrksBLU, "A"], [5, _caliber_ANY, _ammo_HE, 5, 2], [trg_fm_4]] call THY_fnc_DAP_add_fite [BLUFOR, [DAP_targetMrksBLU, "A"], [5, _caliber_ANY, _ammo_HE, 5, 2], [trg_fm_4]] call THY_fnc_DAP_add_fite [BLUFOR, [DAP_targetMrksBLU, "A"], [5, _caliber_ANY, _ammo_HE, 5, 2], [trg_fm_4]] call THY_fnc_DAP_add_fite [BLUFOR, [DAP_targetMrksBLU, "A"], [5, _caliber_ANY, _ammo_HE, 5, 2], [trg_fm_4]] call THY_fnc_DAP_add_fite [BLUFOR, [DAP_targetMrksBLU, "A"], [5, _caliber_ANY, _ammo_HE, 5, 2], [trg_fm_4]] call THY_fnc_DAP_add_fite [BLUFOR, [DAP_targetMrksBLU, "A"], [5, _caliber_ANY, _ammo_HE, 5, 2], [trg_fm_4]] call THY_fnc_DAP_add_fite [BLUFOR, [DAP_targetMrksBLU, "A"], [5, _caliber_ANY, _ammo_HE, 5, 2], [trg_fm_4]] call THY_fnc_DAP_add_fite [BLUFOR, [DAP_targetMrksBLU, "A"], [5, _caliber_ANY, _ammo_HE, 5, 2], [trg_fm_4]] call THY_fnc_DAP_add_fite [BLUFOR, [DAP_targetMrksBLU, "A"], [5, _caliber_ANY, _ammo_HE, 5, 2], [trg_fm_4]] call THY_fnc_DAP_targetMrksBLU, "A"], [5, _caliber_ANY, _ammo_HE, 5, 2], [trg_fm_4]] call THY_fnc_DAP_targetMrksBLU, "A"], [5, _caliber_ANY, _ammo_HE, 5, 2], [trg_fm_4]] call THY_fnc_DAP_targetMrksBLU, "A"], [5, _caliber_ANY, _ammo_HE, 5, 2], [trg_fm_4]] call THY_fnc_DAP_targetMrksBLU, "A"], [5, _caliber_ANY, _ammo_HE, 3, 2], [trg_fm_4]] call THY_fnc_DAP_targetMrksBLU, "A"], [5, _caliber_ANY, _ammo_HE, 3, 2], [trg_fm_4]] call THY_fnc_DAP_targetMrksBLU
```

Let's understand what each column of a fire mission row:

| Side               | Target markers and sector   | Num of pieces involved,<br>caliber of them, ammo<br>type, rounds per piece, and<br>repetition cycle   | Triggers   |
|--------------------|---|---|--|
| That side owns it. | Each side has just one target marker label, e.g. "DAP_targetMkrsBLU". Target segmentation is done through the use of a letter which is called a 'sector letter'. It means this fire mission will only consider targets from sector "A". | Number of pieces involved: You can request more than one artillery piece, but if you don't have enough in-game, DAP will use just those available that fit all fire mission requirements.  Caliber: In DAP the pieces are chosen by their calibers. If you ask for heavy caliber, DAP will investigate what howitzers, MRLs, and/or mortars fit with heavy calibers and are/still available in the mission.  Ammo type: If you request High Explosive ammo, DAP will filter the options, looking for just those pieces with this ammunition type. | Ways to release a fire mission. You must use at least one method for each fire mission:  Trigger  Target  Timer (in minutes)  If you combine methods, to release the fire mission just one of them needs to be reached, not all. |
|                    |   | Rounds per piece: You got it.  Repetition cycle: Hope you got it too.   |  |

# Testing your fire missions

But before that, I do advise you to check these pocket guides <u>right below</u> to make your fire mission planning faster.

## Pocket guide: Artillery Piece Calibers

Basically, the artillery is composed of 3 categories of pieces: Mortars, Howitzers, and MRLs (Multiple Rocket Launchers). Despite the mortars being those with lower calibers, sometimes you can find a mortar allowed to execute fire missions that ask for *\_caliber\_MEDIUM*. That said, let me present something easy to remember:

- (generally, lower calibers) Mortars
- (generally, average calibers) Howitzers
- (generally, greater calibers) MRLs

| <b>Calibers</b> Use this in fn_DAP_fireMissions.sqf | Description   |   |
|---|---|---|
| _caliber_LIGHT                                      | Only caliber less than 123mm,<br>regardless if it belongs to Howitzer,<br>MRL, or mortar.           |   |
|   |   |   |
|   |   | À |
| _caliber_MEDIUM                                     | Only caliber between 123mm and<br>159mm, regardless if it belongs to a<br>Howitzer, MRL, or mortar. |   |
|   |   |   |
|   |   |   |
| _caliber_HEAVY                                      | Only caliber between 160mm and 299mm, regardless if it belongs to Howitzer, MRL, or mortar.         |   |

| _caliber_SUPERHEAVY | Only caliber equal or greater than 300mm, regardless if it belongs to Howitzer, MRL, or mortar. |  |
|---------------------|---|--|
| _caliber_ANY        | Any caliber is applied.   |  |

Important 1: Arma 3 and its DLCs don't have howitzers and mortars able to perform for \_caliber\_HEAVY or \_caliber\_SUPERHEAVY fire missions, even RHS and CUP don't have functional examples. In this case, you can drop in your mission MRL.

Important 2: there's no point in asking for a \_caliber\_SUPERHEAVY fire mission, but only providing the DAP with 82mm mortars. The fire mission will never happen.

## Pocket guide: Magazines (Ammo)

Right after *DAP* gets to know what caliber the Editor wants to use (in other words, how destructive the fire mission needs to be), the script will try to connect that caliber with the ammunition type chosen by the editor too. *DAP* doesn't add any magazines to the game. The script just understands those the server/mission has loaded and checks if the pieces available can fire them in that range.

| Ammo magazines Use this in fn_DAP_fireMissions.sqf | Description  |   |
|--|--|---|
| _ammo_HE   | High Explosive ammo is a great choice against infantry, buildings, and light-medium armor vehicles.  DAP recommend                             |   |
| _ammo_CLUSTER                                      | Cluster ammo is the greatest choice against infantry in trenches and forests, spreading fragmentation grenades on a large area.  DAP recommend | *************************************** |
| _ammo_CLUSTER_MINE_AP                              | Cluster dropping<br>Anti-personnel-mines.  | *************************************** |
| _ammo_CLUSTER_MINE_AT                              | Cluster dropping<br>Anti-tank-mines.   | *************************************** |

| _ammo_GUIDED       | Commonly a HE ammunition with superior accuracy.   |  |
|--------------------|--|--|
| _ammo_GUIDED_LASER | Commonly a HE ammunition with maximum accurance.   |  |
| _ammo_SMOKE        | Smoke ammo, recommended choice to preserve structures but blinding the enemy for a while.  DAP recommend           |  |
| _ammo_FLARE        | Flare ammo, recommended choice to draw attention to a specific area or temporary light up the dark.  DAP recommend |  |

#### Fixing: a piece or ammunition is not recognized by DAP

In the <code>fn\_DAP\_management.sqf</code> file there is an extensive list of artillery pieces and magazines already tested with DAP and working, including some DLCs and mods. If you are facing issues with a magazine or piece, turn on the <code>DAP Debug Mode</code> so that the script will tell what's happening. If DAP asking you to register an artillery piece or a magazine, here (below) is the place to.

```
DAP_knownPieces_howitzer = [
    ["LIGHT", "RHS_M119_D", "RHS_M119_WD"]],
    ["MEDIUM", .....["B_D_MBT_01_arty_lxWS", "gm_ge_army_m109g", "gm_dk_army_m109", "g
    ["HEAVY", ·····[]],
//-Howitzer-Super-Heavy-(crucial: ->=-300mm)
    ["SUPERHEAVY", []]
];
DAP knownPieces_mrl = [
                   ["I_G_Pickup_mrl_rf","0_G_Pickup_mrl_rf","B_G_Pickup_mrl_rf","]
    ["MEDIUM", "["B_D_MBT_01_mlrs_lxWS", "0_SFIA_Truck_02_MRL_lxWS"]],
    ["HEAVY", "" ["rhsusf_M142_usmc_WD", "rhsusf_M142_usarmy_WD", "rhsusf_M142_usa
    ["SUPERHEAVY", ["I_Truck_02_MRL_F", "I_E_Truck_02_MRL_F", "B_MBT_01_mlrs_F", "B_
DAP_knownPieces_mortar = [
    ["LIGHT", "B_G_Mortar_01_F", "B_Mortar_01_F", "B_D_Mortar_01_lxWS", "B_T_Mo
    ["MEDIUM", "["CUP_B_M1129_MC_MK19_Desert", "CUP_B_M1129_MC_MK19_Woodland", "E
    ["HEAVY", []],
    ["SUPERHEAVY", []]
];
DAP_pieces_forbidden = ["CUP_B_FV432_Mortar","gm_ge_army_kat1_463_mlrs","gm_pl_arm
```

Always use classnames, checking first if the classname is not already in here.

#### How to know a vehicle or equipment classname:

On Eden, right-click over the object > Log > "Log classes to clipboard". Now, just paste it!;)

#### Fixing: some artillery pieces are frozen

Make sure you have this option as true in fn\_DAP\_management.sqf.

If the problem persists, it's because probably the piece has some ammunition issue or, in case the vehicle has no mobile turret, the vehicle is not aligned with the selected target (i'm working on it to find a fair solution).

# Fixing: investigate further what is happening (Debugging)

```
fn_DAP_management.sqf X

9    //*PARAMETERS*OF*EDITOR'S*OPTIONS:
10    DAP_isOn*=*true;
11    //*Debug:
12    //*Debug:
13    DAP_debug_isOn*****=*true;
14    DAP_debug_isOnAmmo****=*true;
15    DAP_debug_isOnSectors*=*false;
16    //*Sides*to*use:
```

DAP will tell you what is happening most part of the time.

# Contribute to the *DAP* script

#### Discussion on Bohemia Forums

https://forums.bohemia.net/forums/topic/290962-release-dynamic-artillery-pieces-dap/

# Changelog on GitHub

https://github.com/aldolammel/Arma-3-Dynamic-Artillery-Pieces-Script?tab=readme-ov-file#changelog

# Author

Based in Porto Alegre, Brazil



thy @aldolammel

# If you care

Just give a like for *DAP* on Workshop to spread the word :)

https://steamcommunity.com/sharedfiles/filedetails/?id=3371824030