Stingray Traffic Manager Control API and Reference

Version 8.1

January 2012



Copyright Notice

©2012 Riverbed Technology. All rights reserved. Riverbed and any Riverbed product or service name or logo used herein are trademarks of Riverbed Technology. All other trademarks used herein belong to their respective owners. The trademarks and logos displayed herein may not be used without the prior written consent of Riverbed Technology or their respective owners.

This documentation is furnished "AS IS" and is subject to change without notice and should not be construed as a commitment by Riverbed Technology. This documentation may not be copied, modified or distributed without the express authorization of Riverbed Technology and may be used only in connection with Riverbed products and services. Use, duplication, reproduction, release, modification, disclosure or transfer of this documentation is restricted in accordance with the Federal Acquisition Regulations as applied to civilian agencies and the Defense Federal Acquisition Regulation Supplement as applied to military agencies. This documentation qualifies as "commercial computer software documentation" and any use by the government shall be governed solely by these terms. All other use is prohibited. Riverbed Technology assumes no responsibility or liability for any errors or inaccuracies that may appear in this documentation.

For detailed copyright and license agreements or modified source code (where required), see the Riverbed Support site at https://support.riverbed.com. Certain libraries were used in the development of this software, as listed within the provided documentation set and on the Riverbed Support website at https://support.riverbed.com. You must log in to the support site to request modified source code.

Contents

CHAPTER 1 Introduction	7
Introducing the Stingray traffic management product family	7
Introducing the Control API	
Standards-conformant SOAP communications	
SOAP-based Architecture	8
Security Considerations	
CHAPTER 2 Code samples	10
Listing running virtual servers	
listVS.pl using Perl SOAP::Lite	
listVS.cs using C Sharp	
listVS.java using Java	
listVS.php using PHP 5	
Fault Handling	
Fault handling with SOAP::Lite	
Fault handling using C sharp	
Fault handling using Java	
CHAPTER 3 Using Perl SOAP::Lite	21
Control API methods	21
Control API Enumerations	
Control API Structures	
CHAPTER 4 Sample Control API applications	27
Blocking traffic from an IP address	27
Perl Example	
C# Example	
Adding a node to a pool	
Perl Example	
C# Example	
Reconfiguring your site based on Traffic Load	
Perl example	
C# Example	
CHAPTER 5 Troubleshooting	38
Overview	
Can't find the WSDL files?	
General Debugging Techniques	
Log Files	
Snooping the SOAP traffic	
Debugging with Perl	
Problems with WSDL interfaces	

Contents

Using a Fault Handler	39
Recent SOAP::Lite versions	40
Perl deserializer Example	40
Tracing	
Debugging with C#	
Fault Handlers	40
Permissions Problems	40
Debugging with Java	41
Fault Handlers	41
Tracing	41
CHAPTER 6 Function Reference	42
About the Stingray Control API functions	42
VirtualServer	43
Methods	43
Structures	
Enumerations	149
Pool	156
Methods	
Structures	220
Enumerations	221
TrafficIPGroups	223
Methods	223
Structures	
Enumerations	
Catalog.Rule	
Methods	
Structures	
Catalog.Monitor	
Methods	
Structures	
Enumerations	
Catalog.SSL.Certificates	
Methods	
Structures	
Catalog.SSL.CertificateAuthorities	
Methods	
Structures	
Catalog.SSL.ClientCertificates	
Methods	
Structures	
Catalog.SSL.DNSSEC	
Catalog.Protection	
Methods Catalog.Persistence	
Methods	
Enumerations	
Catalog.Bandwidth	
Methods	
Enumerations	

Catalog.SLM	316
Methods	316
Catalog.Rate	321
Methods	
Catalog.JavaExtension	325
Methods	
Structures	
Catalog.Authenticators	
Methods	
Enumerations	
GlobalSettings	341
Methods	
Enumerations	
Conf.Extra	439
Methods	
Diagnose	
Methods	
Structures	
Enumerations	
System.Backups	445
Methods	
Structures	446
Alerting.EventType	
Methods	
Structures	463
Enumerations	466
Alerting.Action	493
Methods	
Structures	
Enumerations	515
AlertCallback	
Methods	516
Structures	517
Enumerations	
System.AccessLogs	
Methods	
Structures	
System.Cache	
Methods	
Structures	
Enumerations	
System.Connections	
Methods	
Structures	
Enumerations	
System.LicenseKeys	
Methods	
Structures	
System.Log	
Methods	
Structures	

Contents

	Enumerations	
	System.MachineInfo	580
	Methods	580
	Structures	581
	System.RequestLogs	582
	Methods	582
	Structures	583
	System.Stats	583
	Methods	584
	Structures	635
	Enumerations	636
	System.Management	641
	Methods	641
	AFM	642
	Methods	642
	Structures	645
	Location	647
	Methods	647
	Structures	650
	Users	651
	Methods	651
	GLB.Service	652
	Methods	652
	Structures	668
	Enumerations	670
	System.CloudCredentials	671
	Methods	671
	Structures	678
	System.Steelhead	678
	Methods	679
	Enumerations	683
	SOAP Faults	685
	Faults	685
CHA	APTER 7 Further Information	690
	Stingray Manuals	400
	Information online	
	miormation ordine	090
СЦ /	ADTED 9 Index	604

CHAPTER 1 Introduction

Introducing the Stingray traffic management product family

Stingray traffic management products provide high-availability, application-centric traffic management and load balancing solutions. They provides control, intelligence, security and resilience for all your application traffic. These products are intended for organizations hosting valuable business-critical services, such as TCP and UDP-based services like HTTP (web) and media delivery, and XML-based services such as Web Services.

Introducing the Control API

A cluster of traffic mangers is normally managed using the web-based Admin Server on one of the machines.

Stingray's Control API provides an alternative means to remotely administer and configure a Stingray cluster. For example, when an Intrusion Detection System detects a remote attack attempt, it could use the Control API to configure the cluster to drop all connections from the suspect IP address.

A provisioning system could detect server overloading by monitoring the response times of the server nodes using Service Level Monitoring and the SNMP interface. Once it had provisioned additional servers, it could then reconfigure the server pools using the Stingray Control API.

Standards-conformant SOAP communications

The Control API is a standards-conformant SOAP-based API that provides the means for other applications to query and modify the configuration of the cluster.

SOAP is a lightweight protocol for exchange of information in a decentralized, distributed environment. It is an XML based protocol that consists of three parts: an envelope that defines a framework for describing what is in a message and how to process it, a set of encoding rules for expressing instances of application-defined datatypes, and a convention for representing remote procedure calls and responses.

Simple Object Access Protocol (SOAP), w3.org

Most importantly, SOAP is a commonly accepted standard that allows applications to communicate. Stingray's Control API is published in the form of WSDL (Web Services Description Language) files. These files document which methods (remote procedure calls) are available, what input parameters they take and the output they return.

The WSDL files are located in ZEUSHOME/zxtm/etc/wsdl, and can be downloaded from the SOAP API page in the online help.

A SOAP-compliant programming environment will parse the WSDL files to determine which remote methods can be called, and will then allow the application to call these methods much as if they were local functions. The SOAP environment insulates the application developer from the underlying

complexity – network connectivity, XML formatting, cross-platform compatibility, etc. The application developer can concentrate on implementing the control logic required to support the application they are building.

The Stingray Control API can be used by any programming language and application environment that supports SOAP services. C#, Perl, Java and Python are commonly used.

SOAP-based Architecture




Fig. 1. Arrangement of Management Server, Stingray Cluster and Server Nodes

A management application can issue a SOAP request to one of the traffic managers in a Stingray cluster. The application may be running on a stand-alone management server, one of the server nodes, or even on one of the traffic managers.

The application can issue the request to any of the Stingray traffic managers. The traffic managers automatically synchronize their configuration, so a configuration change sent to one machine is automatically replicated across the cluster.

Security Considerations

The SOAP-based management application communicates with a SOAP server running on the Stingray Admin Server, so the same security considerations apply:

- If a management network or IP-based access control is in use to secure the Admin Server, these will affect the locations that the management application can run from.
- SOAP traffic is automatically encrypted using SSL.
- The Stingray Admin Server will authenticate itself with its SSL certificate, which is generally self-signed.

You may need to ensure that your SOAP application accepts self-signed certificates, or install a trusted SSL certificate in your Stingray admin server.

SOAP-based Architecture Introduction

SOAP requests are authenticated using the credentials of a users who is a member of
a group with 'Control API' permissions in the Administration Server. Groups are
defined in the Stingray Administration Interface, in the System > Users > Groups
page.

By default, the 'admin' group (which includes the user named 'admin') is the only group that is permitted to use the Stingray Control API. You can add this permission to other groups as required.

You may wish to define a specific username for your management application to use, so that you can track its activity using traffic manager's Audit Log.

CHAPTER 2 Code samples

The following code samples demonstrate how to call the Stingray Control API from several different application environments. They are intended to illustrate the similarities, rather than the best practice for each language.

Listing running virtual servers

The examples connect to a traffic manager, retrieve a list of the virtual servers and then query whether each virtual server is enabled (i.e. running). They then print out the running virtual servers.

The code structure is as follows:

- Specify the location of the admin server, and the username and password of an account in the 'admin' group or another group with explicit 'Stingray Control API' permissions (see section 1.3.1).
- If necessary, configure the HTTPS layer to accept the Admin Server's self-signed certificate.
- Instantiate a means of calling the SOAP methods of the **latest version** of the VirtualServer interface, generally with reference to the WSDL specification¹.
- Invoke the VirtualServer:getVirtualServerNames() method, which returns an array of string values.
- Invoke the VirtualServer:getEnabled() method, providing an array of string values (the names) and obtaining an array of Boolean values.
- Iterate through the arrays, printing the names of the virtual servers which are enabled.

listVS.pl using Perl SOAP::Lite

```
#!/usr/bin/perl -w

use SOAP::Lite 0.60;

# This is the url of the Stingray admin server
my $admin_server = 'https://username:password@host:9090';

my $conn = SOAP::Lite
    -> ns('http://soap.zeus.com/zxtm/1.0/VirtualServer/')
    -> proxy("$admin_server/soap");
```

¹ Some environments, such as Perl's SOAP::Lite do not validate method calls against the WSDL specification.

```
# Get a list of virtual servers
my $res = $conn->getVirtualServerNames();
my @names = @{$res->result};

# Establish which are enabled
$res = $conn->getEnabled( \@names );
my @enabled = @{$res->result};

# Print those which are enabled
for( my $i = 0; $i <= $#names; $i++ ) {
   if( $enabled[$i] ) {
      print "$names[$i]\n";
   }
}</pre>
```

Run the example as follows:

```
$ ./listVS.pl
Main website
Mail servers
Test site
```

To run this example, you will need Perl, SOAP::Lite and IO::Socket::SSL.

- On Debian-based systems, install the packages libsoap-lite-perl and libio-socket-ssl-perl.
- On RedHat based systems, you'll need the perl-SOAP-Lite and perl-IO-Socket-SSL rpms
- Sites that use CPAN can obtain the modules from http://search.cpan.org/~byrne/SOAP-Lite-0.67/lib/OldDocs/SOAP/Lite.pm and http://search.cpan.org/~behroozi/IO-Socket-SSL-0.97/SSL.pm

Early versions of SOAP::Lite used a 'uri' method instead of the current 'ns' one. This affected versions prior to 0.65_5. If you are using a old SOAP::Lite, use the following code to create the SOAP::Lite connection instead:

```
my $conn = SOAP::Lite
   -> uri('http://soap.zeus.com/zxtm/1.0/VirtualServer/')
   -> proxy("$admin_server/soap");
```

Perl's SOAP::Lite module does not use the WSDL file to perform any type checking, so calling errors will be detected at runtime and SOAP structures and enumerations must be managed manually (see chapter 3). The SSL layer is happy to accept self-signed certificates.

listVS.cs using C Sharp

```
using System;
using System.Net;
using System.IO;
using System.Security.Cryptography.X509Certificates;
public class AllowSelfSignedCerts : IcertificatePolicy {
   public bool CheckValidationResult( ServicePoint sp,
         X509Certificate cert, WebRequest request, int problem )
     return true;
public class listVS {
   public static void Main( string [] args )
     System.Net.ServicePointManager.CertificatePolicy =
        new AllowSelfSignedCerts();
     string url= "https://host:9090/soap";
     string username = "username";
     string password = "password";
     try {
         Stingray.VirtualServer p = new Stingray.VirtualServer();
         p.Url = url;
         p.Credentials = new NetworkCredential( username, password
);
         string[] names = p.getVirtualServerNames();
         bool[] enabled = p.getEnabled( names );
         for ( int i = 0; i < names.Length; i++ ) {
           if( enabled[i] ) {
               Console.WriteLine( "{0}", names[i] );
      } catch ( Exception e ) {
         Console.WriteLine( "{0}", e );
   }
```

```
}
```

This code works with the .NET 1.1 SDK and with Mono².

Using .Net 1.1, compile and run this example as follows:

```
C:\> wsdl -o:VirtualServer.cs -n:Stingray
VirtualServer.wsdl

C:\> csc /out:listVS.exe VirtualServer.cs listVS.cs

C:\> listVS.exe

Main website

Mail servers

Test site
```

With Mono, compile and run as follows:

The WSDL interface specifications for the Stingray Control API are located in <code>ZEUSHOME/zxtm/etc/wsdl/</code>, and can be downloaded from the SOAP API page in the online help.

Note the use of the IcertificatePolicy derived class to override the default certificate checking method. This allows the application to accept the Stingray Admin Server's self-signed certificate.

listVS.java using Java

```
import com.Stingray.soap.zxtm._1_0.*;
import java.security.Security;
import java.security.KeyStore;
import java.security.Provider;
import java.security.cert.X509Certificate;
import javax.net.ssl.ManagerFactoryParameters;
```

² Use the most recent build of Mono from http://www.mono-project.com/.

```
import javax.net.ssl.TrustManager;
import javax.net.ssl.TrustManagerFactorySpi;
import javax.net.ssl.X509TrustManager;
public class listVS {
   public static void main( String[] args ) {
      // Install the all-trusting trust manager
      Security.addProvider( new MyProvider() );
      Security.setProperty( "ssl.TrustManagerFactory.algorithm",
         "TrustAllCertificates" );
      try {
         VirtualServerLocator vsl = new VirtualServerLocator();
         vsl.setVirtualServerPortEndpointAddress(
            "https://username:password@host:9090/soap");
         VirtualServerPort vsp = vsl.getVirtualServerPort();
         String[] vsnames = vsp.getVirtualServerNames();
         boolean[] vsenabled = vsp.getEnabled( vsnames );
         for( int i = 0; i < vsnames.length; i++ ) {</pre>
            if( vsenabled[i] ){
               System.out.println( vsnames[i] );
      } catch (Exception e) {
         System.out.println( e.toString() );
   }
   /* The following code disables certificate checking.
    * Use the Security.addProvider and Security.setProperty
    * calls to enable it */
   public static class MyProvider extends Provider {
      public MyProvider() {
         super( "MyProvider", 1.0, "Trust certificates" );
         put( "TrustManagerFactory.TrustAllCertificates",
            MyTrustManagerFactory.class.getName() );
      protected static class MyTrustManagerFactory
            extends TrustManagerFactorySpi {
         public MyTrustManagerFactory() {}
         protected void engineInit( KeyStore keystore ) {}
         protected void engineInit(
            ManagerFactoryParameters mgrparams ) {}
         protected TrustManager[] engineGetTrustManagers() {
            return new TrustManager[] {
               new MyX509TrustManager()
```

```
};

}

protected static class MyX509TrustManager
    implements X509TrustManager {
    public void checkClientTrusted(
        X509Certificate[] chain, String authType) {}
    public void checkServerTrusted(
        X509Certificate[] chain, String authType) {}
    public X509Certificate[] getAcceptedIssuers() {
        return null;
     }
}
```

The bulk of this code disables client certificate checking. Details of the code and surrounding infrastructure are at:

http://java.sun.com/j2se/1.5.0/docs/guide/security/jsse/JSSERefGuide.html

This code works with the Java 1.5 SDK/JRE. To build and run the code, you'll need to do the following:

- 1. Download axis from http://ws.apache.org/axis/. This provides the WSDL-to-Java converter. Copy all the .jar files from axis-<version>/libs/ to the JAVAHOME/jre/lib/ext/ directory, or add them to your CLASSPATH.
- 2. Install the Java Activation Framework and JavaMail libraries to avoid warnings when the code is run:
 - o Java Activation Framework

http://java.sun.com/products/javabeans/glasgow/jaf.html

o JavaMail

http://java.sun.com/products/javamail/

Copy the activation.jar and mail.jar files contained in these packages to the JAVAHOME/jre/lib/ext/ directory, or add them to your CLASSPATH.

3. In your build directory, convert the required WSDL files into java code as follows³:

\$ java org.apache.axis.wsdl.WSDL2Java
VirtualServer.wsdl

³ The WSDL interface specifications for the Stingray Control API are located in STINGRAYHOME/zxtm/etc/wsdl/.

4. Compile and run the example as follows:

```
$ javac listVS.java
$ java listVS
Main website
Mail servers
Test site
```

This code uses the functions within the VirtualServer interface. Other interfaces use a similar pattern.

For example, if you wished to access functions within the XXX interface, you would need to instantiate an XXXLocator object, declare the location of the traffic manager using the setXXXPortEndpointAddress() function and then create a connection using getXXXPort() to return an XXXPort object. You can then invoke methods using the XXXPort object. Java is verbose, but generally repetitive so the patterns can be copied thus:

```
SystemCacheLocator scl = new SystemCacheLocator();
scl.setSystemCachePortEndpointAddress(
   "https://username:password@host:9090/soap" );
SystemCachePort scp = scl.getSystemCachePort();

/* Invoke the methods on the SystemCachePort object */
scp.clearWebCache();
```

I.I.I listVS.py using Python

By default, most SOAP implementations read the location of the SOAP server from the WSDL file⁴. However, for security reasons, the location of the Stingray Admin Server (including the required administrator username and password) is not embedded in the Stingray WSDL files.

Most SOAP toolkits allow you to override the location specified in the WSDL file, but Python's SOAP.py module does not. Before you run this example, edit your WSDL files. Look for the soap:address node at the very end of each WSDL file and edit appropriately:

```
<service name="VirtualServer">
    <port name="VirtualServerPort"
        binding="Stingrayns:VirtualServerBinding">
        <soap:address
        location="https://username:password@host:9090/soap"
/>
    </port>
    </service>
```

Run the Python script as follows⁵:

```
$ ./listVS.py
Main website
Mail servers
Test site
```

listVS.php using PHP 5

```
#!/usr/bin/php5

<?
$conn = new SoapClient( "VirtualServer.wsdl",
    array('login' => "username", 'password' => "password") );

$names = $conn->getVirtualServerNames();
$enabled = $conn->getEnabled($names);

for ($i=0; $i < count( $names ); $i++) {
    if ( $enabled[$i] )
        print "$names[$i]\n";
}
?>
```

⁴ The WSDL interface specifications for the Stingray Control API are located in STINGRAYHOME/zxtm/etc/wsdl/.

 $^{^5}$ This example was tested with Python 2.3.5 and version 0.11.5 of the SOAP.py library. Earlier versions of SOAP.py (0.8.4) could not correctly parse the WSDL file.

Code samples Fault Handling

You may need to enable the SOAP extensions in your php.ini file; follow the instructions at http://www.php.net/soap if necessary.

Like Python, the PHP Soap toolkit expects to find the location of the SOAP server in the WSDL file, and does not provide any means to override it. However, you can specify the login details from your application, so these do not need to be embedded in the WSDL:

```
<service name="VirtualServer">
    <port name="VirtualServerPort"
        binding="Stingrayns:VirtualServerBinding">
        <soap:address location="https://host:9090/soap" />
        </port>
    </service>
```

Run the PHP script as follows

```
$ ./listVS.php
Main website
Mail servers
Test site
```

Fault Handling

The Stingray Control API uses standard SOAP fault handling to inform the client application of errors. The type of fault returned depends on the error that occurred; for instance an 'ObjectDoesNotExist' fault will be returned when trying to set a property for a Virtual Server that doesn't exist. Information contained inside the fault will help determine more information about the error.

In addition to the specific faults specified for the functions, applications should be written to handle generic failures for which a specific fault does not exist.

Fault handling differs depending on the API being used. You should refer to your API documentation for details on how best to handle faults.

The following examples show code snippets of how to handle faults with various standard libraries.

Fault handling with SOAP::Lite

As SOAP::Lite doesn't read the WSDL files, the fault handling code needs to process the fault structures manually:

```
# This is the url of the Stingray admin server
my $admin_server = 'https://<user>:<pass>@adminserver:9090';
```

Fault Handling Code samples

```
my $conn = SOAP::Lite
    -> ns('http://soap.zeus.com/zxtm/1.0/VirtualServer/')
    -> proxy("$admin server/soap")
    -> on fault( \&handle fault );
sub handle fault
   my(\$soap,\$res) = 0;
   if( ! $res ) die "A transport error occured\n";
   if(! ref $res) die $res;
   # $res is a SOAP fault - extract the information in it
   if($res->faultdetail) {
     my $detail = $res->faultdetail;
     my @elems = keys %$detail;
     my $fault = $elems[0];
      my $msg = "SOAP Fault: $fault\n";
      # Extract out the components of the fault
      foreach my $key( qw( errmsg object key value ) ) {
        if( defined $detail->{$fault}->{$key} ) {
            $msg .= " $key: " . $detail->{$fault}->{$key}
."\n";
         }
     }
    die $msg;
   } else {
     die "SOAP Fault: " . $res->faultcode . ": " .
         $res->faultstring . "\n";
}
# Could throw 'ObjectDoesNotExist'
$conn->setEnabled( [ "my-virtual-server" ], [ 1 ] );
```

Fault handling using C sharp

Like perl, the fault detail structure needs to be inspected manually:

Code samples Fault Handling

```
XmlNode detail = fault.Detail.FirstChild;
      // The SOAP fault is the name of the first child of the
      // fault detail
      msg += "SOAP Fault: " + detail.LocalName + "\n";
      // And the other members of the fault are children
      XmlNodeList children = detail.ChildNodes;
      for ( int i = 0 ; i < children.Count ; i++ ) {
         msg += " " + children[i].Name + ": " +
                       children[i].InnerText + "\n";
      }
   } else {
     // Otherwise this is a generic fault - just print the
fault
     msg = fault.ToString();
  Console.Write( msg );
}
```

Fault handling using Java

Fault handling is built into the Java AXIS libraries; the SOAP faults are translated into standard Java exceptions which make it very easy to handle faults:

CHAPTER 3 Using Perl SOAP::Lite

Unlike most other SOAP APIs, Perl's SOAP::Lite does not take regard of the WSDL specification for the Control API interface. Special measures must be taken to use the Control API accurately.

Control API methods

A method can be invoked from a SOAP::Lite connection object that specifies the appropriate interface:

```
# Create a connection object that uses the VirtualServer
interface
my $conn = SOAP::Lite
   -> ns('http://soap.zeus.com/zxtm/1.0/VirtualServer/')
   -> proxy("$admin_server/soap");

# You can invoke any of the methods of the VirtualServer
interface
my $res = $conn->getVirtualServerNames();
```

If you need to use several interfaces (for example, VirtualServer and Pool), you will need to construct a SOAP::Lite connection object for each.

If you attempt to invoke a method that does not exist for the interface, the method call will fail and the on fault fault handler (if specified) will be called.

Note that when a new version of Stingray Traffic Manager is released, individual interfaces might be changed in some way that alters their use or behavior. This could be in order to fix a bug or to provide additional functionality. If this situation occurs, instead of amending the existing interface, a new later version-numbered interface will be included with the release (which you should always try to use). However, previous versions are always preserved to ensure backwards compatibility with your existing applications. The interface version is identified in the ns string provided to the connection object, and the Function Reference contained in this document always refers to the latest version available.

Control API Enumerations

An Enumeration is a particular datatype with a restricted, named set of values. For example, a Pool has a limited set of load balancing algorithms that are represented by the Pool.LoadBalancingAlgorithm enumeration:

The enumeration is defined as follows:

Pool.LoadBalancingAlgorithm

```
enum Pool.LoadBalancingAlgorithm {
  roundrobin,  # Round Robin
  wroundrobin,  # Weighted Round Robin
```

```
cells,  # Perceptive
connections,  # Least Connections
wconnections,  # Weighted Least Connections
responsetimes,  # Fastest Response Time
random  # Random node
}
```

The Pool interface contains two methods that use that enumeration:

getLoadBalancingAlgorithm(names)

Get the load balancing algorithms that each of the named pools uses.

```
Pool.LoadBalancingAlgorithm[] getLoadBalancingAlgorithm(
    String[] names
)
```

setLoadBalancingAlgorithm(names, values)

Set the load balancing algorithms that each of the named pools uses.

```
void setLoadBalancingAlgorithm(
    String[] names
    Pool.LoadBalancingAlgorithm[] values
)
```

Perl's SOAP::Lite library correctly encodes enumerations in SOAP requests, so you can use them in a literal fashion:

```
$conn->setLoadBalancingAlgorithm( [ $poolName ],
['connections'] );
```

In a SOAP response, you need to provide a custom Deserializer so that the SOAP::Lite library can convert the values in the SOAP response into appropriate internal representations (i.e. literal strings):

```
BEGIN {
   package MyDeserializer;
   @MyDeserializer::ISA = 'SOAP::Deserializer';

   sub typecast {
      my($self, $val, $name, $attrs, $children, $type) =
   @_;
```

```
if( $type && $type =~ m@http://soap.zeus.com/zxtm/@ ) {
    return $val;
}
return undef;
};
}

my $conn = SOAP::Lite
-> ns('http://soap.zeus.com/zxtm/1.0/Pool/')
-> proxy("$admin_server/soap")
-> deserializer( MyDeserializer->new );
```

The following code sample illustrates how to use Control API methods that use Enumerations:

```
#!/usr/bin/perl -w
use SOAP::Lite 0.6;
# Provide our own Deserializer to deserialize enums correctly
   package MyDeserializer;
   @MyDeserializer::ISA = 'SOAP::Deserializer';
   sub typecast {
     my($self, $val, $name, $attrs, $children, $type) =
@ ;
      if( $type && $type =~ m@http://soap.zeus.com/zxtm/@ ) {
        return $val;
      return undef;
   };
# This is the url of the Stingray admin server
my $admin server = 'https://username:password@host:9090';
# The pool to edit
my $poolName = $ARGV[0] or die "No pool specified";
my $conn = SOAP::Lite
    -> ns('http://soap.zeus.com/zxtm/1.0/Pool/')
    -> proxy("$admin server/soap")
   -> deserializer( MyDeserializer->new )
    -> on fault( sub
         my(\$conn,\$res) = 0;
         die ref $res?$res->faultstring:$conn->transport-
>status; } );
# Get the load balancing algorithm
my $res = $conn->getLoadBalancingAlgorithm( [ $poolName ] );
```

```
my $alg = @{$res->result}[0];
print "Pool $poolName uses load balancing algorithm $alg\n";

# Change the algorithm to least connections, and check it worked
$conn->setLoadBalancingAlgorithm([$poolName],['connections']);
$res = $conn->getLoadBalancingAlgorithm([$poolName]);
print "Algorithm has been changed to @{$res->result}[0]\n";

# Now change it back again
$conn->setLoadBalancingAlgorithm([$poolName],[$alg]);
$res = $conn->getLoadBalancingAlgorithm([$poolName],[$alg]);
print "Algorithm changed back to @{$res->result}[0]\n";
```

Control API Structures

A Structure is a complex datatype that contains several parameters. For example, the key configuration settings for a Virtual Server are represented by a VirtualServer.BasicInfo structure that defines the port, protocol and default pool for that Virtual Server:

VirtualServer.BasicInfo

This structure contains the basic information for a virtual server. It is used when creating a server, or modifying the port, protocol or default pool of a server.

```
struct VirtualServer.BasicInfo {
    # The port to listen for incoming connections on.
    Integer port;

# The protocol that this virtual server handles.
    VirtualServer.Protocol protocol;

# The default pool that traffic to this virtual server will go
    # to.
    String default_pool;
}
```

This structure contains three elements; an Integer (the port number), an Enumeration (VirtualServer.Protocol – the protocol) and a string (the name of the default pool).

The method VirtualServer.addVirtualServer() takes a VirtualServer.BasicInfo structure which can be constructed as follows:

If you call the method VirtualServer.getBasicInfo(), it will return a corresponding array of VirtualServer.BasicInfo structures that can be unpacked as follows:

```
$res = $conn->getBasicInfo( [ $vsName ] );
my $r = @{$res->result}[0];

print "Virtual Server $vsName:\n";
print " port $r->{port}, protocol $r->{protocol}, " .
    "pool $r->{default_pool}\n";
```

The following code sample illustrates how to create a virtual server and manage the BasicInfo structure:

```
#!/usr/bin/perl -w
use SOAP::Lite 0.6;
# Provide our own Deserializer so to deserialize enums
correctly
BEGIN {
   package MyDeserializer;
   @MyDeserializer::ISA = 'SOAP::Deserializer';
   sub typecast {
     my($self, $val, $name, $attrs, $children, $type) =
@ ;
      if( $type && $type =~ m@http://soap.zeus.com/zxtm/@) {
         return $val;
      return undef;
   };
# This is the url of the Stingray admin server
my $admin server = 'https://user:password@hostname:9090';
# The virtual server to create
```

```
my $vsName = $ARGV[0] or die "No vs specified";
my $conn = SOAP::Lite
   -> ns('http://soap.zeus.com/zxtm/1.0/VirtualServer/')
   -> proxy("$admin_server/soap")
   -> deserializer( MyDeserializer->new )
   -> on fault( sub {
         my(\$conn,\$res) = 0;
         die ref $res?$res->faultstring:$conn->transport-
>status; } );
# Construct the basic info structure
my $basicInfo = {
  port => '443',
protocol => 'https',
  default_pool => 'discard'
};
$res = $conn->addVirtualServer( [ $vsName ], [ $basicInfo ]
$res = $conn->getBasicInfo( [ $vsName ] );
my r = \{\frac{sres}{0}\}
print "Virtual Server $vsName:\n";
print " port $r->{port}, protocol $r->{protocol}, " .
      "pool $r->{default_pool}\n";
```

CHAPTER 4 Sample Control API applications

The Stingray Control API can perform almost any configuration task that can be accomplished using the Stingray Admin Server. Its strength comes from how it can be driven by other management applications elsewhere in the network.

Blocking traffic from an IP address

An Intrusion Detection System (IDS) or a live log analysis tool may identify remote hosts which are sending undesired traffic – malicious requests, port scans, or simply excessive numbers of requests in an attempt to mount a denial-of-service attack.

The IDS may be located behind the traffic manager cluster, for example, if it needs to inspect SSL traffic that has been decrypted by the traffic managers. In this case, the IDS can use the Control API to update the traffic manager cluster to prevent it from accepting any more traffic from the suspected IP address.

The following Stingray Control API application modifies a named Service Protection Policy, adding an IP address to the list of banned IP addresses. The Service Protection Policy should be assigned to the appropriate Virtual Servers managing traffic in the cluster.

Perl Example

Notes

We are accessing the 'Catalog/Protection' uri to edit a service protection class. With a WSDL-based interface, we'd use the Catalog. Protection.wsdl interface.

We use the addBannedAddresses () function. Like most Control API functions, this takes a series of arrays as arguments:

- 1. A list of service protection policies
- 2. A list of lists of banned IP addresses

This means that the function can perform bulk updates, modifying several objects simultaneously.

This example includes a basic on_fault handler which is called if an error ever occurs. The handler will report a transport error if the SOAP application could not connect to the remote SOAP server. Otherwise, it will report a SOAP error.

For more a more sophisticated example of a Perl fault handler, refer to section 2.2.1.

C# Example

```
using System;
using System.Net;
using System.IO;
using System. Security. Cryptography. X509Certificates;
public class AllowSelfSignedCerts : ICertificatePolicy {
   public bool CheckValidationResult(
         ServicePoint sp, X509Certificate cert,
         WebRequest request, int problem )
   { return true; }
public class addBannedAddress {
   public static void Main( string [] args )
      System.Net.ServicePointManager.CertificatePolicy =
         new AllowSelfSignedCerts();
      string url= "https://host:9090/soap";
      string username = "username";
      string password = "password";
      string name = "My protection class";
      string badIP = "10.100.1.10";
      try {
         Stingray.CatalogProtection p =
                new Stingray.CatalogProtection();
         p.Url = url;
         p.Credentials = new NetworkCredential(
```

Adding a node to a pool

Provisioning systems can dynamically deploy applications across servers, perhaps in reaction to increased server load. This example demonstrates a Control API application that modifies the nodes that a pool balances traffic to.

If the pool is using the 'Perceptive' algorithm, then load will slowly be ramped up on newly introduced nodes, gauging their potential performance, until they run at the same speed as the other nodes in the pool. This 'Slow Start' capability ensures that new nodes are not immediately overloaded with a large burst of traffic.

Perl Example

```
#!/usr/bin/perl -w
use SOAP::Lite 0.60;
# This is the url of the Stingray admin server
my $admin server = 'https://username:password@host:9090';
# The pool to edit, and the node to add
my $poolName = "test pool";
my \ per = "10.100.1.10:80";
my $conn = SOAP::Lite
    -> uri('http://soap.zeus.com/zxtm/1.0/Pool/')
    -> proxy("$admin server/soap")
    -> on fault( sub {
        my(\$conn,\$res) = 0;
         die ref $res ? $res->faultstring :
             $conn->transport->status; } );
# Get a list of pools
my $res = $conn->getPoolNames();
my @names = @{$res->result};
# Get the nodes for each pool
$res = $conn->getNodes( \@names );
```

```
# Build a hash %nodes: pool->[ node list ]
my %nodes;
@nodes{@names} = @{$res->result};
if( !defined $nodes{$poolName} ) {
   die "Pool $poolName does not exist...";
if( grep { $ eq $newNode } @{$nodes{$poolName}} ) {
  die "Pool $poolName already contains $newNode";
# Add one node to the pool
$res = $conn->addNodes( [ $poolName ], [ [ $newNode ] ] );
# We're done! Verify that the node has been added
$res = $conn->getNodes( [ $poolName ] );
my @newnodes = @{\{\$\{\$res->result\}[0]\};}
my $expected = join " ",
  sort @{$nodes{$poolName}}, $newNode;
my $actual = join " ", sort @newnodes;
if ( $expected ne $actual ) {
  die "New node list is '$actual'; expected '$expected'";
}
```

Notes

This example uses careful error checking to make sure that the Control API methods are not called incorrectly. For example, if a method tries to add a node to a pool that did not exist, a SOAP fault will be raised. Perl's on fault handler will be called if this happens.

The example illustrates Perl's hash slice technique to quickly build an associative array, mapping pool name to a list of nodes:

```
my $res = $conn->getPoolNames();
my @names = @{$res->result};
$res = $conn->getNodes( \@names );
my %nodes;
@nodes{@names} = @{$res->result};
```

This is a very easy way to take advantage of the fact that the Stingray Control API methods are all bulk-enabled, i.e., they are designed to process lists of objects efficiently.

The listVS example could also use a hash slice, as follows:

```
my $res = $conn->getVirtualServerNames();
my @names = @{$res->result};
$res = $conn->getEnabled( \@names );
my %enabled;
@enabled{@names} = @{$res->result};
```

A Stingray Control API application could update the configuration by modifying the hash:

```
# Turn everything off...
foreach my $name( keys %enabled ) {
   $enabled{ $name } = 0;
}
```

It could then bulk-commit the new configuration with a single method call:

C# Example

```
using System;
using System.Net;
using System.IO;
using System. Security. Cryptography. X509Certificates;
public class AllowSelfSignedCerts : ICertificatePolicy {
   public bool CheckValidationResult(
         ServicePoint sp, X509Certificate cert,
         WebRequest request, int problem )
      return true;
public class addNode {
   public static void Main( string [] args )
      System.Net.ServicePointManager.CertificatePolicy =
         new AllowSelfSignedCerts();
      string url= "https://host:9090/soap";
      string username = "username";
      string password = "password";
      string poolName = "test pool";
      string newNode = "10.100.1.10:80";
      try {
         Stingray.Pool p = new Stingray.Pool();
         p.Url = url;
         p.Credentials = new NetworkCredential(
            username, password );
         string[] names = p.getPoolNames();
         string[][] allnodes = p.getNodes( names );
         string[] nodes = new string[]{};
         bool found = false;
         for ( int i = 0 ; i < names.Length ; i++ ) {
            if( names[i] == poolName ) {
               nodes = allnodes[i];
               found = true;
               break;
         }
         if(! found) {
            Console.WriteLine( "Pool {0} doesn't exist",
poolName );
            Environment.Exit( 1 );
```

```
found = false;
  for( int i = 0 ; i < nodes.Length ; i++ ) {
    if( nodes[i] == newNode ) {
      found = true;
    }
}
if( found ) {
    Console.WriteLine( "Pool {0} already contains

{1}",
    poolName, newNode );
    Environment.Exit( 1 );
}

// Add one node to the pool
    p.addNodes( new string[] { poolName },
      new string[][] { new string[] { newNode } } );
}
catch ( Exception e ) {
    Console.WriteLine( "{0}", e );
}
}</pre>
```

Reconfiguring your site based on Traffic Load

In this example, we'll monitor the performance of the JSP pages on a website. If the performance drops below an acceptable level, we'll use the Control API to enable a TrafficScript rule that prevents more users from logging into the website. Once performance climbs back to an acceptable level, the Control API application can disable the rule.

The TrafficScript Rule

To prevent users from logging into the site, we could use a TrafficScript rule similar to the following:

```
$path = http.getPath();
if( string.endsWith( $path, "login.jsp" ) ) {
   http.redirect( "/content/login_disabled.html" );
}
```

Add this rule to the Rules catalog, calling it 'Disable Login'. Configure it as a request rule for your virtual server, but set it to be disabled. The Stingray Control API application will use the Virtual Server getRules() and setRules() functions to modify the 'enabled' status of the rule.

Monitoring Performance

Performance of the web application can be monitored in a variety of ways:

- Using statistics gathered from the web application itself.
- Using an external monitoring tool to send probe requests.
- Monitoring the node response times using SNMP and the Service Level Monitoring capability.
- Using the SNMP or email alerts raised by Service Level Monitoring to drive the Control API applications directly.

Enabling and Disabling the Rule

The following Control API code retrieves the list of response rules that the named virtual server is using. It searches for the rule named 'Disable Login' and enables it. If the rule is not present, it adds it as the first rule to be executed.

Perl example

```
#!/usr/bin/perl -w
use SOAP::Lite 0.60;
# Provide our own Deserializer so to deserialize enums
correctly
BEGIN {
   package MyDeserializer;
   @MyDeserializer::ISA = 'SOAP::Deserializer';
   sub typecast {
     my($self, $val, $name, $attrs, $children, $type) =
@ ;
      if( $type && $type =~ m@http://soap.zeus.com/zxtm/@) {
         return $val;
     return undef;
   };
# This is the url of the Stingray admin server
my $admin server = 'https://username:password@host:9090';
# The virtual server to edit, and the rule to enable
my $vsName = "Main web site";
my $rule = "Disable Login";
my $conn = SOAP::Lite
    -> uri('http://soap.zeus.com/zxtm/1.0/VirtualServer/')
    -> proxy("$admin server/soap")
    -> deserializer( MyDeserializer->new )
    -> on fault( sub
     my( $conn, $res ) = @_;
      die ref $res ? $res->faultstring:conn->transport-
```

```
>status; } );
# Get a list of rules used by the named virtual server
my $res = $conn->getRules( [ $vsName ] );
my @rules = @{${$res->result}[0]};
my found = 0;
foreach my $f (@rules ) {
   if (f->\{name\} eq rule) {
      f->\{enabled\} = 1; found = 1; last;
if( !$found ) {
   # Add a new rule to the start of the list
   unshift @rules, {
     name => $rule,
     enabled \Rightarrow 1,
      run frequency => 'only first'
   };
$res = $conn->setRules( [ $vsName ], [ [ @rules ] ] );
```

Notes

The rules manipulation functions take a compound VirtualServer.Rule structure which uses an enumeration named 'RuleRunFlag'.

The SOAP::Lite interface presents this structure as a standard Perl hash, requiring a Deserializer to manage the enumeration.

C# presents it as an object of type Stingray.VirtualServerRule containing an enumeration of type Stingray.VirtualServerRuleRunFlag.

C# Example

```
public static void Main( string [] args )
   {
      System.Net.ServicePointManager.CertificatePolicy =
         new AllowSelfSignedCerts();
      string url= "https://host:9090/soap";
      string username = "username";
      string password = "password";
      string vsName = "Main web site";
      string rule = "Disable login";
      try {
         Stingray.VirtualServer p = new
Stingray.VirtualServer();
         p.Url = url;
         p.Credentials = new NetworkCredential(
            username, password );
         // Get a list of rules used by the named
         // virtual server
         Stingray.VirtualServerRule[][] rules =
            p.getRules( new string[] { vsName } );
         // Search for the rule to enable
         bool found = false;
         foreach( Stingray.VirtualServerRule r in rules[0] )
            if( r.name == rule ) {
               found = true; r.enabled = true;
         if(! found) {
            // Add a new rule to the start of the list
            Stingray.VirtualServerRule[] newrules = new
               Stingray.VirtualServerRule[rules[0].Length +
1];
            newrules[0] = new Stingray.VirtualServerRule();
            newrules[0].name = rule;
            newrules[0].enabled = true;
            newrules[0].run frequency =
               Stingray. Virtual Server Rule Run Flag. only first;
            Array.Copy( rules[0], 0, newrules, 1,
rules[0].Length );
            rules[0] = newrules;
         p.setRules( new string[] { vsName }, rules );
      } catch ( Exception e ) {
        Console.WriteLine( "{0}", e );
```

}

CHAPTER 5 Troubleshooting

Overview

Building Stingray Control API applications is an involved process. This chapter lists some useful techniques.

Can't find the WSDL files?

The WSDL interface specifications are located in:

ZEUSHOME/zxtm/etc/wsdl/

ZEUSHOME is the installation directory for your Stingray software, typically /usr/local/zeus.

You can also download them from the SOAP API page in the online help.

General Debugging Techniques

Log Files

In the event of a problem, review the following error logs:

• Stingray Software: ZEUSHOME/log/errors

Validation errors and incorrect configuration problems will be reported in this log file.

• Stingray Admin Server: ZEUSHOME/admin/log/errors

The Admin Server processes the SOAP requests and sends the new configuration to the Stingray software. Any SOAP protocol or transport errors will be reported here.

Snooping the SOAP traffic

Your Stingray Control API application will send SOAP requests to the Stingray Admin server, which typically listens using SSL on port 9090. If your SOAP toolkit does not support debugging or tracing, you can use a network snooping tool such as WireShark⁶ to inspect the SOAP request and response, to verify that the request is sent correctly, and that the response does not contain any errors messages that are not reported by your application's interface code.

Of course, if your SOAP transaction is encrypted with SSL, it will not be easy to inspect it:

1. Disable SSL on the Stingray Admin Server as follows:

⁶ http://www.wireshark.org/ WireShark is available for all major platforms, including Windows, Linux and Mac OS X.

Debugging with Perl Troubleshooting

a. Edit the file ZEUSHOME/admin/website, and comment out the line 'security!enabled yes' by prefixing it with a '#':

```
#security!enabled yes
```

b. Restart the software⁷:

```
# /usr/local/Stingray/restart-Stingray
```

2. Modify your Stingray Control API application to use an 'http://' url rather than an 'https://' one.

Debugging with Perl

Problems with WSDL interfaces

Because Perl's SOAP::Lite does not make explicit reference to the WSDL interface specification, it can be easy to make errors which are only detected at run time.

Ensure that the URI in the SOAP::Lite objects you construct in your application is correct. Refer to the URI tables in chapter 6.

For example, to reference methods in the VirtualServer interface, you should use the following URI:

```
http://soap.zeus.com/zxtm/1.0/VirtualServer/
```

For methods in the Service Protection catalog, use the following URI:

http://soap.zeus.com/zxtm/1.0/Catalogs/Protection/

Using a Fault Handler

Your Perl SOAP::Lite client application can determine whether server or transport errors have occurred by inspecting the SOAP Fault that is raised on an error.

Section 2.2 covers Fault Handlers in detail.

Set STINGRAYHOME to the correct installation directory for your configuration.

⁷ Alternatively, you can restart just the admin server component as follows:

[#] export STINGRAYHOME=/usr/local/Stingray

^{# \$}STINGRAYHOME/admin/rc restart

Troubleshooting Debugging with C#

Recent SOAP::Lite versions

Versions of SOAP::Lite on or after 0.65_5 have a slightly different interface. When creating a SOAP::Lite connection, you should use a new 'ns' method instead of the previous 'uri' method:

```
# Versions prior to 0.65_5
my $conn = SOAP::Lite
   -> uri('http://soap.zeus.com/zxtm/1.0/VirtualServer/')
   -> proxy("$admin_server/soap");
```

```
# Versions 0.65_5 and later
my $conn = SOAP::Lite
   -> ns('http://soap.zeus.com/zxtm/1.0/VirtualServer/')
   -> proxy("$admin_server/soap");
```

Perl deserializer Example

The SOAP::Lite module does not make use of Stingray's WSDL specification and so does not know how to deserialize some enumerations used. See chapter 3 for an example of this problem.

Tracing

When you import the SOAP::Lite module, use the following:

```
use SOAP::Lite 0.6 +trace => 'debug';
```

This will cause the SOAP::Lite module to output large amounts of debugging information.

The XML-messages you see after enabling the tracing are usually not formatted. To make them easier to read, set the readable flag on your connections:

```
my $conn = SOAP::Lite;
$conn->readable(1);
```

This will make the messages sent by the client more readable, but will not affect messages received from the server.

Debugging with C#

Fault Handlers

Pleae refer to section 2.2 for details on how to inspect any SOAP Faults that are raised as a result of a server or transport error.

Permissions Problems

The .NET environment enforces stringent security checks by default.

Debugging with Java Troubleshooting

For example, by default, your Control API application cannot generate an HTTP request to a foreign site (such as the Stingray Admin Server) unless the application is running from a 'trusted location'. Remote filesystems which are locally mounted are untrusted, whereas local filesystems are trusted.

The location of your Control API application may affect whether it functions correctly or not.

Debugging with Java

Fault Handlers

Pleae refer to section 2.2 for details on how to inspect any SOAP Faults that are raised as a result of a server or transport error.

Tracing

For full SOAP tracing, you can run your Stingray Control API application as follows:

```
$ java -Djavax.net.debug=all listVS
```

Alternatively, you can enable debugging within your application:

```
System.setProperty( "javax.net.debug", "all" );
```

CHAPTER 6 Function Reference

About the Stingray Control API functions

Stingray Control API functions generally operate on lists of configurations. For example, the VirtualServer getEnabled() function takes a list of virtual server names as its first argument, and returns a list of Boolean values, one for each named virtual server.

Some functions depend on compound structures for their arguments, and enumerated types are used to represent some configuration settings.

All of the methods, structures and enumerated types are specified in the WSDL interface files8.

The addRules () and getRules () VirtualServer functions are good examples:

```
VirtualServer.Rule[][] getRules(
    String[] names
)

void addRules(
    String[] names
    VirtualServer.Rule[][] rules
)
```

Method prototypes for the VirtualServer getRules and addRules methods

getRules () takes a list of virtual server names, returning a list of VirtualServer.Rule arrays:

```
struct VirtualServer.Rule {
    # The name of the rule.
    String name;

# Whether the rule is enabled or not.
    Boolean enabled;

# Whether the rule runs on every request response,
    # or just the first
    VirtualServer.RuleRunFlag run_frequency;
}
```

Definition of the VirtualServer.Rule structure

The VirtualServer.Rule structure includes an enumerated type:

```
enum VirtualServer.RuleRunFlag {
```

⁸ The WSDL interface specifications are located in STINGRAYHOME/zxtm/etc/wsdl/

```
# Run on every request or response
run_every,

# Run only on the first request or response
only_first
}
```

Definition of the VirtualServer.RuleRunFlag enumerated type

Your SOAP toolkit will represent these WSDL methods, structures and enumerated types in a form appropriate for the language in use:

- Perl uses methods in the SOAP::Lite object. Structures map straightforwardly onto Perl associative arrays. You need to provide an explicit deserializer to typecast enumerated type values into string values. See chapter 3 for details.
- The C# and Java toolkits provide a means to convert the WSDL files into C# or Java source files, with fully typed classes, structures and enumerations to represent the SOAP methods, structures and enumerated types.

Take a look at section 4.3 for a worked example that illustrates the use of the methods, structures and enumerations.

VirtualServer

```
URI: http://soap.zeus.com/zxtm/1.0/VirtualServer/
```

The VirtualServer interface allows management of Virtual Server objects. Using this interface, you can create, delete and rename virtual server objects, and manage their configuration.

Methods

addCompressionMIMETypes(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

For each named virtual server, add new MIME types to the list of types to compress.

```
void addCompressionMIMETypes(
    String[] names
    String[][] values
)
```

addCompressionMIMETypesByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

For each named virtual server, add new MIME types to the list of types to compress. This is a location specific function, any action will operate on the specified location.

```
void addCompressionMIMETypesByLocation(
   String location
   String[] names
   String[][] values
)
```

addResponseRules(names, rules) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Add new rules to be run on server responses for each of the named virtual servers. New rules are run after existing rules. If any of the rules are already configured to run, then they are enabled and flags are set to the values passed in.

```
void addResponseRules(
    String[] names
    VirtualServer.Rule[][] rules
)
```

addResponseRulesByLocation(location, names, rules) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Add new rules to be run on server responses for each of the named virtual servers. New rules are run after existing rules. If any of the rules are already configured to run, then they are enabled and flags are set to the values passed in. This is a location specific function, any action will operate on the specified location.

```
void addResponseRulesByLocation(
   String location
   String[] names
   VirtualServer.Rule[][] rules
)
```

addRules(names, rules) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Add new rules to be run on client requests for each of the named virtual servers. New rules are run after existing rules. If any of the rules are already configured to run, then they are enabled and flags are set to the values passed in.

```
void addRules(
    String[] names
    VirtualServer.Rule[][] rules
```

)

addRulesByLocation(location, names, rules) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Add new rules to be run on client requests for each of the named virtual servers. New rules are run after existing rules. If any of the rules are already configured to run, then they are enabled and flags are set to the values passed in. This is a location specific function, any action will operate on the specified location.

```
void addRulesByLocation(
   String location
   String[] names
   VirtualServer.Rule[][] rules
)
```

addSSLClientCertificateAuthorities(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Add new certificate authorities for validating client certificates for each of the named virtual servers.

```
void addSSLClientCertificateAuthorities(
    String[] names
    String[][] values
)
```

addSSLClientCertificateAuthoritiesByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Add new certificate authorities for validating client certificates for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void addSSLClientCertificateAuthoritiesByLocation(
   String location
   String[] names
   String[][] values
```

addSSLNeverExpiringClientCertificateAuthorities(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Add CAs for which any client certificate they validate is considered valid even if the client certificate's expiration date has passed, for each of the named virtual servers.

```
void addSSLNeverExpiringClientCertificateAuthorities(
   String[] names
   String[][] values
)
```

addSSLNeverExpiringClientCertificateAuthoritiesByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Add CAs for which any client certificate they validate is considered valid even if the client certificate's expiration date has passed, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void
addSSLNeverExpiringClientCertificateAuthoritiesByLoca
tion(
    String location
    String[] names
    String[][] values
)
```

addSSLOCSPIssuers(names, ssl_ocsp_issuers) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Adds mappings between Certificate Authorities and OCSP responder settings. Certificates issued by these authorities will be verified with OCSP using these settings.

```
void addSSLOCSPIssuers(
    String[] names
    VirtualServer.SSLOCSPIssuer[][] ssl_ocsp_issuers
)
```

addSSLOCSPIssuersByLocation(location, names, ssl_ocsp_issuers) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Adds mappings between Certificate Authorities and OCSP responder settings. Certificates issued by these authorities will be verified with OCSP using these settings. This is a location specific function, any action will operate on the specified location.

```
void addSSLOCSPIssuersByLocation(
```

```
String location
String[] names
VirtualServer.SSLOCSPIssuer[][] ssl_ocsp_issuers
)
```

addSSLSites(names, ssl_sites) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Adds the specified SSLSite objects to the named virtual servers. These objects are mappings between destination addresses and the certificate used for SSL decryption those addresses. Each certificate is the name of an item in the SSL Certificates Catalog.

```
void addSSLSites(
    String[] names
    VirtualServer.SSLSite[][] ssl_sites
)
```

addSSLSitesByLocation(location, names, ssl_sites) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Adds the specified SSLSite objects to the named virtual servers. These objects are mappings between destination addresses and the certificate used for SSL decryption those addresses. Each certificate is the name of an item in the SSL Certificates Catalog. This is a location specific function, any action will operate on the specified location.

```
void addSSLSitesByLocation(
   String location
   String[] names
   VirtualServer.SSLSite[][] ssl_sites
)
```

addVirtualServer(names, info) throws ObjectAlreadyExists, InvalidObjectName, DeploymentError, InvalidInput

Add each virtual servers, using the provided BasicInfo.

```
void addVirtualServer(
    String[] names
    VirtualServer.BasicInfo[] info
```

copyVirtualServer(names, new_names) throws ObjectAlreadyExists, ObjectDoesNotExist, InvalidObjectName, DeploymentError

Rename each of the named virtual servers.

```
void copyVirtualServer(
    String[] names
    String[] new_names
)
```

deleteSSLSites(names, site_ips) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Deletes the SSLSite objects that act on the IP addresses in the site_ips array for each of the named virtual servers. These objects are mappings between destination addresses and the certificate used for SSL decryption those addresses. Each certificate is the name of an item in the SSL Certificates Catalog.

```
void deleteSSLSites(
    String[] names
    String[][] site_ips
)
```

deleteSSLSitesByLocation(location, names, site_ips) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Deletes the SSLSite objects that act on the IP addresses in the site_ips array for each of the named virtual servers. These objects are mappings between destination addresses and the certificate used for SSL decryption those addresses. Each certificate is the name of an item in the SSL Certificates Catalog. This is a location specific function, any action will operate on the specified location.

```
void deleteSSLSitesByLocation(
   String location
   String[] names
   String[][] site_ips
)
```

deleteVirtualServer(names) throws ObjectDoesNotExist, DeploymentError

Delete each of the named virtual servers.

```
void deleteVirtualServer(
    String[] names
)
```

editSSLSites(names, site_ips, ssl_sites) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Edits the SSLSite objects that act on the IP addresses in the site_ips array for each of the named virtual servers. These objects are mappings between destination addresses and the certificate used for SSL decryption those addresses. Each certificate is the name of an item in the SSL Certificates Catalog.

```
void editSSLSites(
    String[] names
    String[][] site_ips
    VirtualServer.SSLSite[][] ssl_sites
)
```

editSSLSitesByLocation(location, names, site_ips, ssl_sites) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Edits the SSLSite objects that act on the IP addresses in the site_ips array for each of the named virtual servers. These objects are mappings between destination addresses and the certificate used for SSL decryption those addresses. Each certificate is the name of an item in the SSL Certificates Catalog. This is a location specific function, any action will operate on the specified location.

```
void editSSLSitesByLocation(
   String location
   String[] names
   String[][] site_ips
   VirtualServer.SSLSite[][] ssl_sites
)
```

getAddClusterClientIPHeader(names) throws ObjectDoesNotExist

Get whether a 'X-Cluster-Client-Ip' header should be added to each HTTP request, for each of the named virtual servers. The 'X-Cluster-Client-Ip' header contains the client's IP address.

```
Boolean[] getAddClusterClientIPHeader(
    String[] names
)
```

getAddClusterClientIPHeaderByLocation(location, names) throws ObjectDoesNotExist

Get whether a 'X-Cluster-Client-Ip' header should be added to each HTTP request, for each of the named virtual servers. The 'X-Cluster-Client-Ip' header contains the client's IP address. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getAddClusterClientIPHeaderByLocation(
   String location
   String[] names
)
```

getBandwidthClass(names) throws ObjectDoesNotExist

Get the Bandwidth Class that each of the named virtual servers uses.

```
String[] getBandwidthClass(
    String[] names
)
```

getBandwidthClassByLocation(location, names) throws ObjectDoesNotExist

Get the Bandwidth Class that each of the named virtual servers uses. This is a location specific function, any action will operate on the specified location.

```
String[] getBandwidthClassByLocation(
    String location
    String[] names
)
```

getBasicInfo(names) throws ObjectDoesNotExist

Get the basic information for each of the named virtual servers. This information includes the port, the protocol the virtual server handles and the default pool for the traffic.

```
VirtualServer.BasicInfo[] getBasicInfo(
    String[] names
)
```

getBasicInfoByLocation(location, names) throws ObjectDoesNotExist

Get the basic information for each of the named virtual servers. This information includes the port, the protocol the virtual server handles and the default pool for the traffic. This is a location specific function, any action will operate on the specified location.

```
VirtualServer.BasicInfo[] getBasicInfoByLocation(
    String location
    String[] names
)
```

getCompressUnknownSize(names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should compress documents with no given size.

```
Boolean[] getCompressUnknownSize(
    String[] names
)
```

getCompressUnknownSizeByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should compress documents with no given size. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getCompressUnknownSizeByLocation(
    String location
    String[] names
)
```

getCompressionEnabled(names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should compress web pages before sending to the client.

```
Boolean[] getCompressionEnabled(
    String[] names
)
```

getCompressionEnabledByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should compress web pages before sending to the client. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getCompressionEnabledByLocation(
    String location
    String[] names
```

)

getCompressionLevel(names) throws ObjectDoesNotExist

Get the gzip compression level, for each of the named virtual servers.

```
Unsigned Integer[] getCompressionLevel(
    String[] names
)
```

getCompressionLevelByLocation(location, names) throws ObjectDoesNotExist

Get the gzip compression level, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getCompressionLevelByLocation(
    String location
    String[] names
)
```

getCompressionMIMETypes(names) throws ObjectDoesNotExist

Get the list of MIME types to compress, for each of the named virtual servers.

```
String[][] getCompressionMIMETypes(
    String[] names
)
```

getCompressionMIMETypesByLocation(location, names) throws ObjectDoesNotExist

Get the list of MIME types to compress, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
String[][] getCompressionMIMETypesByLocation(
    String location
    String[] names
)
```

getCompressionMaxSize(names) throws ObjectDoesNotExist

Get the maximum document size to compress, in bytes, for each of the named virtual servers. A document size of '0' means 'unlimited'.

```
Unsigned Integer[] getCompressionMaxSize(
    String[] names
)
```

getCompressionMaxSizeByLocation(location, names) throws ObjectDoesNotExist

Get the maximum document size to compress, in bytes, for each of the named virtual servers. A document size of '0' means 'unlimited'. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getCompressionMaxSizeByLocation(
    String location
    String[] names
)
```

getCompressionMinSize(names) throws ObjectDoesNotExist

Get the minimum document size to compress, in bytes, for each of the named virtual servers.

```
Unsigned Integer[] getCompressionMinSize(
    String[] names
)
```

getCompressionMinSizeByLocation(location, names) throws ObjectDoesNotExist

Get the minimum document size to compress, in bytes, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getCompressionMinSizeByLocation(
   String location
   String[] names
)
```

getConnectTimeout(names) throws ObjectDoesNotExist

Get the time to wait for data from a new connection, in seconds, for each of the named virtual servers. If no data is received in this time, the connection will be closed.

```
Unsigned Integer[] getConnectTimeout(
    String[] names
)
```

getConnectTimeoutByLocation(location, names) throws ObjectDoesNotExist

Get the time to wait for data from a new connection, in seconds, for each of the named virtual servers. If no data is received in this time, the connection will be closed. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getConnectTimeoutByLocation(
    String location
    String[] names
)
```

getCookieDomainRewriteMode(names) throws ObjectDoesNotExist

Get how each of the named virtual servers should rewrite the domain portion of cookies set by a backend web server.

```
VirtualServer.CookieDomainRewriteMode[]
getCookieDomainRewriteMode(
    String[] names
)
```

getCookieDomainRewriteModeByLocation(location, names) throws ObjectDoesNotExist

Get how each of the named virtual servers should rewrite the domain portion of cookies set by a backend web server. This is a location specific function, any action will operate on the specified location.

```
VirtualServer.CookieDomainRewriteMode[]
getCookieDomainRewriteModeByLocation(
    String location
    String[] names
)
```

getCookieNamedDomain(names) throws ObjectDoesNotExist

Get the domain to use when rewriting cookie domains, for each of the named virtual servers.

```
String[] getCookieNamedDomain(
    String[] names
```

)

getCookieNamedDomainByLocation(location, names) throws ObjectDoesNotExist

Get the domain to use when rewriting cookie domains, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
String[] getCookieNamedDomainByLocation(
    String location
    String[] names
)
```

getCookiePathRewrite(names) throws ObjectDoesNotExist

For each of the named virtual servers, get the regex and replacement for rewriting the path portion of a cookie.

```
VirtualServer.RegexReplacement[]
getCookiePathRewrite(
    String[] names
)
```

getCookiePathRewriteByLocation(location, names) throws ObjectDoesNotExist

For each of the named virtual servers, get the regex and replacement for rewriting the path portion of a cookie. This is a location specific function, any action will operate on the specified location.

```
VirtualServer.RegexReplacement[]
getCookiePathRewriteByLocation(
    String location
    String[] names
)
```

getCookieSecureFlagRewriteMode(names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should modify the 'secure' tag of cookies set by a backend web server.

```
VirtualServer.CookieSecureFlagRewriteMode[]
getCookieSecureFlagRewriteMode(
    String[] names
)
```

getCookieSecureFlagRewriteModeByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should modify the 'secure' tag of cookies set by a backend web server. This is a location specific function, any action will operate on the specified location.

```
VirtualServer.CookieSecureFlagRewriteMode[]
getCookieSecureFlagRewriteModeByLocation(
    String location
    String[] names
```

getDefaultPool(names) throws ObjectDoesNotExist

Get the default Pool that traffic is sent to for each of the named virtual servers.

```
String[] getDefaultPool(
    String[] names
)
```

getDefaultPoolByLocation(location, names) throws ObjectDoesNotExist

Get the default Pool that traffic is sent to for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
String[] getDefaultPoolByLocation(
   String location
   String[] names
)
```

getEnabled(names) throws ObjectDoesNotExist

Get whether each of the named virtual servers is enabled (i.e. serving traffic).

```
Boolean[] getEnabled(
    String[] names
)
```

getEnabledByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named virtual servers is enabled (i.e. serving traffic). This is a location specific function, any action will operate on the specified location.

```
Boolean[] getEnabledByLocation(
    String location
    String[] names
)
```

getErrorFile(names) throws ObjectDoesNotExist

Get the file names of the error texts that each of the named virtual servers will send back to a client in case of back-end or internal errors.

```
String[] getErrorFile(
    String[] names
)
```

getErrorFileByLocation(location, names) throws ObjectDoesNotExist

Get the file names of the error texts that each of the named virtual servers will send back to a client in case of back-end or internal errors. This is a location specific function, any action will operate on the specified location.

```
String[] getErrorFileByLocation(
    String location
    String[] names
)
```

getFTPDataSourcePort(names) throws ObjectDoesNotExist

Get the source port each of the named virtual servers should use for active-mode FTP data connections. If 0, a random high port will be used, otherwise the specified port will be used. If a port below 1024 is required you must first explicitly permit use of low ports with the ftp_data_bind_low global setting.

```
Unsigned Integer[] getFTPDataSourcePort(
    String[] names
)
```

getFTPDataSourcePortByLocation(location, names) throws ObjectDoesNotExist

Get the source port each of the named virtual servers should use for active-mode FTP data connections. If 0, a random high port will be used, otherwise the specified port will be used. If a port below 1024 is required you must first explicitly permit use of low ports with the ftp_data_bind_low global setting. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getFTPDataSourcePortByLocation(
   String location
   String[] names
)
```

getFTPForceClientSecure(names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should require incoming FTP data connections (from clients) to originate from the same IP address as the corresponding control connection.

```
Boolean[] getFTPForceClientSecure(
    String[] names
)
```

getFTPForceClientSecureByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should require incoming FTP data connections (from clients) to originate from the same IP address as the corresponding control connection. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getFTPForceClientSecureByLocation(
    String location
    String[] names
)
```

getFTPForceServerSecure(names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should require incoming FTP data connections (from nodes) to originate from the same IP address as the corresponding control connection.

```
Boolean[] getFTPForceServerSecure(
    String[] names
)
```

getFTPForceServerSecureByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should require incoming FTP data connections (from nodes) to originate from the same IP address as the corresponding control connection. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getFTPForceServerSecureByLocation(
```

```
String location
String[] names
)
```

getFTPPortRange(names) throws ObjectDoesNotExist

Get the port range used for FTP data connections for each of the named virtual servers.

```
VirtualServer.FTPPortRange[] getFTPPortRange(
    String[] names
)
```

getFTPPortRangeByLocation(location, names) throws ObjectDoesNotExist

Get the port range used for FTP data connections for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
VirtualServer.FTPPortRange[]
getFTPPortRangeByLocation(
    String location
    String[] names
)
```

getFTPSSLData(names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should use SSL on the data connection as well as the control connection

```
Boolean[] getFTPSSLData(
    String[] names
)
```

getFTPSSLDataByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should use SSL on the data connection as well as the control connection This is a location specific function, any action will operate on the specified location.

```
Boolean[] getFTPSSLDataByLocation(
    String location
    String[] names
)
```

getKeepalive(names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should allow clients to maintain keepalive connections.

```
Boolean[] getKeepalive(
    String[] names
)
```

getKeepaliveByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should allow clients to maintain keepalive connections. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getKeepaliveByLocation(
    String location
    String[] names
)
```

getKeepaliveTimeout(names) throws ObjectDoesNotExist

Get the time that an idle keepalive connection should be kept open for, in seconds, for each of the named virtual servers.

```
Unsigned Integer[] getKeepaliveTimeout(
    String[] names
)
```

getKeepaliveTimeoutByLocation(location, names) throws ObjectDoesNotExist

Get the time that an idle keepalive connection should be kept open for, in seconds, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getKeepaliveTimeoutByLocation(
    String location
    String[] names
)
```

getListenAddresses(names) throws ObjectDoesNotExist

Get the specific IP addresses and hostnames that each of the named virtual servers are listening on. This will return an empty array for a virtual server if it is listening on all addresses.

```
String[][] getListenAddresses(
    String[] names
)
```

getListenAddressesByLocation(location, names) throws ObjectDoesNotExist

Get the specific IP addresses and hostnames that each of the named virtual servers are listening on. This will return an empty array for a virtual server if it is listening on all addresses. This is a location specific function, any action will operate on the specified location.

```
String[][] getListenAddressesByLocation(
    String location
    String[] names
)
```

getListenOnAllAddresses(names) throws ObjectDoesNotExist

For each of the named virtual servers, gets whether the virtual server is listening on all IP addresses

```
Boolean[] getListenOnAllAddresses(
    String[] names
)
```

getListenOnAllAddressesByLocation(location, names) throws ObjectDoesNotExist

For each of the named virtual servers, gets whether the virtual server is listening on all IP addresses. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getListenOnAllAddressesByLocation(
    String location
    String[] names
)
```

getListenTrafficIPGroups(names) throws ObjectDoesNotExist

Get the specific Traffic IP Groups that each named virtual server listens on. This will return an empty array for a virtual server if it is listening on all addresses.

```
String[][] getListenTrafficIPGroups(
    String[] names
)
```

getListenTrafficIPGroupsByLocation(location, names) throws ObjectDoesNotExist

Get the specific Traffic IP Groups that each named virtual server listens on. This will return an empty array for a virtual server if it is listening on all addresses. This is a location specific function, any action will operate on the specified location.

```
String[][] getListenTrafficIPGroupsByLocation(
    String location
    String[] names
)
```

getLocationDefaultRewriteMode(names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should rewrite the 'Location' header. The rewrite is only performed if the location rewrite regex didn't match.

```
VirtualServer.LocationDefaultRewriteMode[]
getLocationDefaultRewriteMode(
    String[] names
)
```

getLocationDefaultRewriteModeByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should rewrite the 'Location' header. The rewrite is only performed if the location rewrite regex didn't match. This is a location specific function, any action will operate on the specified location.

```
VirtualServer.LocationDefaultRewriteMode[]
getLocationDefaultRewriteModeByLocation(
    String location
    String[] names
)
```

getLocationRewrite(names) throws ObjectDoesNotExist

For each of the named virtual servers, get the regex, and replacement for rewriting any 'Location' headers.

```
VirtualServer.RegexReplacement[] getLocationRewrite(
    String[] names
)
```

getLocationRewriteByLocation(location, names) throws ObjectDoesNotExist

For each of the named virtual servers, get the regex, and replacement for rewriting any 'Location' headers. This is a location specific function, any action will operate on the specified location.

```
VirtualServer.RegexReplacement[]
getLocationRewriteByLocation(
    String location
    String[] names
)
```

getLogClientConnectionFailures(names) throws ObjectDoesNotExist

Get whether the virtual server will log client connection failures.

```
Boolean[] getLogClientConnectionFailures(
    String[] names
)
```

getLogClientConnectionFailuresByLocation(location, names) throws ObjectDoesNotExist

Get whether the virtual server will log client connection failures. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getLogClientConnectionFailuresByLocation(
   String location
   String[] names
)
```

getLogEnabled(names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should log each connection to a disk on the file system.

```
Boolean[] getLogEnabled(
    String[] names
)
```

getLogEnabledByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should log each connection to a disk on the file system. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getLogEnabledByLocation(
    String location
    String[] names
)
```

getLogFilename(names) throws ObjectDoesNotExist

Get the name of the file used to store request logs, for each of the named virtual servers.

```
String[] getLogFilename(
    String[] names
)
```

getLogFilenameByLocation(location, names) throws ObjectDoesNotExist

Get the name of the file used to store request logs, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
String[] getLogFilenameByLocation(
    String location
    String[] names
)
```

getLogFormat(names) throws ObjectDoesNotExist

Get the log file format for each of the named virtual servers.

```
String[] getLogFormat(
    String[] names
)
```

getLogFormatByLocation(location, names) throws ObjectDoesNotExist

Get the log file format for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
String[] getLogFormatByLocation(
    String location
    String[] names
)
```

getLogSSLFailures(names) throws ObjectDoesNotExist

Get whether the virtual server will log ssl failures.

```
Boolean[] getLogSSLFailures(
    String[] names
)
```

getLogSSLFailuresByLocation(location, names) throws ObjectDoesNotExist

Get whether the virtual server will log ssl failures. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getLogSSLFailuresByLocation(
    String location
    String[] names
)
```

getLogServerConnectionFailures(names) throws ObjectDoesNotExist

Get whether the virtual server will log server connection failures.

```
Boolean[] getLogServerConnectionFailures(
    String[] names
)
```

getLogServerConnectionFailuresByLocation(location, names) throws ObjectDoesNotExist

Get whether the virtual server will log server connection failures. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getLogServerConnectionFailuresByLocation(
   String location
   String[] names
)
```

getMIMEAutoDetect(names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should auto-detect MIME types if the server does not provide them.

```
Boolean[] getMIMEAutoDetect(
    String[] names
```

)

getMIMEAutoDetectByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should auto-detect MIME types if the server does not provide them. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getMIMEAutoDetectByLocation(
    String location
    String[] names
)
```

getMIMEDefaultType(names) throws ObjectDoesNotExist

Get the MIME type that the server uses as its 'default', for each of the named virtual servers. Responses with this mime type will be auto-corrected by the virtual server if this setting is enabled.

```
String[] getMIMEDefaultType(
    String[] names
)
```

getMIMEDefaultTypeByLocation(location, names) throws ObjectDoesNotExist

Get the MIME type that the server uses as its 'default', for each of the named virtual servers. Responses with this mime type will be auto-corrected by the virtual server if this setting is enabled. This is a location specific function, any action will operate on the specified location.

```
String[] getMIMEDefaultTypeByLocation(
    String location
    String[] names
)
```

getMaxClientBuffer(names) throws ObjectDoesNotExist

Get the amount of memory used to store data sent by the client, in bytes, for each of the named virtual servers.

```
Unsigned Integer[] getMaxClientBuffer(
    String[] names
)
```

getMaxClientBufferByLocation(location, names) throws ObjectDoesNotExist

Get the amount of memory used to store data sent by the client, in bytes, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getMaxClientBufferByLocation(
    String location
    String[] names
)
```

getMaxServerBuffer(names) throws ObjectDoesNotExist

Get the amount of memory used to store data returned by the server, in bytes, for each of the named virtual servers.

```
Unsigned Integer[] getMaxServerBuffer(
    String[] names
)
```

getMaxServerBufferByLocation(location, names) throws ObjectDoesNotExist

Get the amount of memory used to store data returned by the server, in bytes, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getMaxServerBufferByLocation(
    String location
    String[] names
)
```

getNote(names) throws ObjectDoesNotExist

Get the note for each of the named virtual servers.

```
String[] getNote(
    String[] names
)
```

getPort(names) throws ObjectDoesNotExist

Get the port that each of the named virtual servers listens on for incoming connections.

```
Unsigned Integer[] getPort(
    String[] names
```

)

getPortByLocation(location, names) throws ObjectDoesNotExist

Get the port that each of the named virtual servers listens on for incoming connections. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getPortByLocation(
    String location
    String[] names
)
```

getProtection(names) throws ObjectDoesNotExist

Get the Service Protection Settings that are used to protect each of the named virtual servers.

```
String[] getProtection(
    String[] names
)
```

getProtectionByLocation(location, names) throws ObjectDoesNotExist

Get the Service Protection Settings that are used to protect each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
String[] getProtectionByLocation(
    String location
    String[] names
)
```

getProtocol(names) throws ObjectDoesNotExist

Get the protocol that each of the named virtual servers uses.

```
VirtualServer.Protocol[] getProtocol(
    String[] names
)
```

getProxyClose(names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should send a FIN packet on to the back-end server when it is received from the client. The alternative is to close the connection to the client immediately.

If the traffic manager is responding to the request itself, enabling this setting will cause the traffic manager to continue writing the response even after it has received a FIN from the client.

```
Boolean[] getProxyClose(
    String[] names
)
```

getProxyCloseByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should send a FIN packet on to the back-end server when it is received from the client. The alternative is to close the connection to the client immediately. If the traffic manager is responding to the request itself, enabling this setting will cause the traffic manager to continue writing the response even after it has received a FIN from the client. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getProxyCloseByLocation(
    String location
    String[] names
)
```

getRTSPPortRange(names) throws ObjectDoesNotExist

Get the port range used for RTSP streaming data connections, for each of the named virtual servers.

```
VirtualServer.PortRange[] getRTSPPortRange(
    String[] names
```

getRTSPPortRangeByLocation(location, names) throws ObjectDoesNotExist

Get the port range used for RTSP streaming data connections, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
VirtualServer.PortRange[] getRTSPPortRangeByLocation(
    String location
    String[] names
)
```

getRTSPStreamingTimeout(names) throws ObjectDoesNotExist

Get the time, in seconds, after which data-streams associated with RTSP connections timeout if no data is transmitted.

```
Unsigned Integer[] getRTSPStreamingTimeout(
```

```
String[] names
)
```

getRTSPStreamingTimeoutByLocation(location, names) throws ObjectDoesNotExist

Get the time, in seconds, after which data-streams associated with RTSP connections timeout if no data is transmitted. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getRTSPStreamingTimeoutByLocation(
    String location
    String[] names
```

getRequestSyslogEnabled(names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should log each connection to a remote syslog server.

```
Boolean[] getRequestSyslogEnabled(
    String[] names
)
```

getRequestSyslogEnabledByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should log each connection to a remote syslog server. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getRequestSyslogEnabledByLocation(
    String location
    String[] names
)
```

getRequestSyslogFormat(names) throws ObjectDoesNotExist

Get the remote log line format for each of the named virtual servers.

```
String[] getRequestSyslogFormat(
    String[] names
)
```

getRequestSyslogFormatByLocation(location, names) throws ObjectDoesNotExist

Get the remote log line format for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
String[] getRequestSyslogFormatByLocation(
    String location
    String[] names
)
```

getRequestSyslogIPEndpoint(names) throws ObjectDoesNotExist

Get the remote syslog endpoint for each of the named virtual servers

```
String[] getRequestSyslogIPEndpoint(
    String[] names
)
```

getRequestSyslogIPEndpointByLocation(location, names) throws ObjectDoesNotExist

Get the remote syslog endpoint for each of the named virtual servers This is a location specific function, any action will operate on the specified location.

```
String[] getRequestSyslogIPEndpointByLocation(
    String location
    String[] names
)
```

getRequestTracingEnabled(names) throws ObjectDoesNotExist

Get whether to record a detailed list of processing history for each request.

```
Boolean[] getRequestTracingEnabled(
    String[] names
)
```

getRequestTracingEnabledByLocation(location, names) throws ObjectDoesNotExist

Get whether to record a detailed list of processing history for each request. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getRequestTracingEnabledByLocation(
   String location
   String[] names
)
```

getRequestTracingIO(names) throws ObjectDoesNotExist

Get whether to record a detailed list of every IO event in the processing history for each request.

```
Boolean[] getRequestTracingIO(
    String[] names
)
```

getRequestTracinglOByLocation(location, names) throws ObjectDoesNotExist

Get whether to record a detailed list of every IO event in the processing history for each request. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getRequestTracingIOByLocation(
    String location
    String[] names
)
```

getResponseRules(names) throws ObjectDoesNotExist

Get the rules that are run on server responses for each of the named virtual servers.

```
VirtualServer.Rule[][] getResponseRules(
    String[] names
)
```

getResponseRulesByLocation(location, names) throws ObjectDoesNotExist

Get the rules that are run on server responses for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
VirtualServer.Rule[][] getResponseRulesByLocation(
    String location
    String[] names
)
```

getRewriteSIPURI(names) throws ObjectDoesNotExist

Get whether the Request-URI of SIP requests will be replaced with the selected back-end node's address.

```
Boolean[] getRewriteSIPURI(
    String[] names
)
```

getRewriteSIPURIByLocation(location, names) throws ObjectDoesNotExist

Get whether the Request-URI of SIP requests will be replaced with the selected back-end node's address. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getRewriteSIPURIByLocation(
    String location
    String[] names
)
```

getRules(names) throws ObjectDoesNotExist

Get the rules that are run on client requests for each of the named virtual servers.

```
VirtualServer.Rule[][] getRules(
    String[] names
)
```

getRulesByLocation(location, names) throws ObjectDoesNotExist

Get the rules that are run on client requests for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
VirtualServer.Rule[][] getRulesByLocation(
    String location
    String[] names
)
```

getSIPDangerousRequestMode(names) throws ObjectDoesNotExist

Get what should be done with requests that contain body data and should be routed to an external IP.

```
VirtualServer.SIPDangerousRequestMode[]
getSIPDangerousRequestMode(
```

```
String[] names
)
```

getSIPDangerousRequestModeByLocation(location, names) throws ObjectDoesNotExist

Get what should be done with requests that contain body data and should be routed to an external IP. This is a location specific function, any action will operate on the specified location.

```
VirtualServer.SIPDangerousRequestMode[]
getSIPDangerousRequestModeByLocation(
    String location
    String[] names
)
```

getSIPFollowRoute(names) throws ObjectDoesNotExist

Get whether to follow routing information in SIP requests.

```
Boolean[] getSIPFollowRoute(
    String[] names
)
```

getSIPFollowRouteByLocation(location, names) throws ObjectDoesNotExist

Get whether to follow routing information in SIP requests. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getSIPFollowRouteByLocation(
   String location
   String[] names
)
```

getSIPMaxConnectionMemory(names) throws ObjectDoesNotExist

Get maximum memory per connection.

```
Unsigned Integer[] getSIPMaxConnectionMemory(
    String[] names
```

getSIPMaxConnectionMemoryByLocation(location, names) throws ObjectDoesNotExist

Get maximum memory per connection. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[]
getSIPMaxConnectionMemoryByLocation(
    String location
    String[] names
)
```

getSIPMode(names) throws ObjectDoesNotExist

Get which mode of operation the SIP virtual server should run in.

```
VirtualServer.SIPMode[] getSIPMode(
    String[] names
)
```

getSIPModeByLocation(location, names) throws ObjectDoesNotExist

Get which mode of operation the SIP virtual server should run in. This is a location specific function, any action will operate on the specified location.

```
VirtualServer.SIPMode[] getSIPModeByLocation(
    String location
    String[] names
)
```

getSIPPortRange(names) throws ObjectDoesNotExist

Get the port range used for SIP data connections, for each of the named virtual servers. This setting is only used when the SIP virtual server is using 'Full Gateway' mode.

```
VirtualServer.PortRange[] getSIPPortRange(
    String[] names
)
```

getSIPPortRangeByLocation(location, names) throws ObjectDoesNotExist

Get the port range used for SIP data connections, for each of the named virtual servers. This setting is only used when the SIP virtual server is using 'Full Gateway' mode. This is a location specific function, any action will operate on the specified location.

```
VirtualServer.PortRange[] getSIPPortRangeByLocation(
   String location
   String[] names
)
```

getSIPStreamingTimeout(names) throws ObjectDoesNotExist

Get the time, in seconds, after which a UDP stream will timeout if it has not seen any data.

```
Unsigned Integer[] getSIPStreamingTimeout(
    String[] names
)
```

getSIPStreamingTimeoutByLocation(location, names) throws ObjectDoesNotExist

Get the time, in seconds, after which a UDP stream will timeout if it has not seen any data. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getSIPStreamingTimeoutByLocation(
    String location
    String[] names
)
```

getSIPTimeoutMessages(names) throws ObjectDoesNotExist

Get send a timed out response to the client and CANCEL request to the server when a transaction times out.

```
Boolean[] getSIPTimeoutMessages(
    String[] names
)
```

getSIPTimeoutMessagesByLocation(location, names) throws ObjectDoesNotExist

Get send a timed out response to the client and CANCEL request to the server when a transaction times out. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getSIPTimeoutMessagesByLocation(
    String location
    String[] names
```

)

getSSLCertificate(names) throws ObjectDoesNotExist

Get the name of the default SSL Certificate that is used for SSL decryption for each of the named virtual servers. This is the name of an item in the SSL Certificates Catalog.

```
String[] getSSLCertificate(
    String[] names
)
```

getSSLCertificateByLocation(location, names) throws ObjectDoesNotExist

Get the name of the default SSL Certificate that is used for SSL decryption for each of the named virtual servers. This is the name of an item in the SSL Certificates Catalog. This is a location specific function, any action will operate on the specified location.

```
String[] getSSLCertificateByLocation(
    String location
    String[] names
)
```

getSSLClientCertificateAuthorities(names) throws ObjectDoesNotExist

Get the certificate authorities that are trusted for validating client certificates, for each of the named virtual servers.

```
String[][] getSSLClientCertificateAuthorities(
    String[] names
)
```

getSSLClientCertificateAuthoritiesByLocation(location, names) throws ObjectDoesNotExist

Get the certificate authorities that are trusted for validating client certificates, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
String[][]
getSSLClientCertificateAuthoritiesByLocation(
   String location
   String[] names
)
```

getSSLClientCertificateHeaders(names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should add HTTP headers to each request to show the data in the client certificate.

```
VirtualServer.SSLClientCertificateHeaders[]
getSSLClientCertificateHeaders(
    String[] names
)
```

getSSLClientCertificateHeadersByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should add HTTP headers to each request to show the data in the client certificate. This is a location specific function, any action will operate on the specified location.

```
VirtualServer.SSLClientCertificateHeaders[]
getSSLClientCertificateHeadersByLocation(
    String location
    String[] names
)
```

getSSLDecrypt(names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should decrypt SSL traffic.

```
Boolean[] getSSLDecrypt(
    String[] names
)
```

getSSLDecryptByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should decrypt SSL traffic. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getSSLDecryptByLocation(
    String location
    String[] names
)
```

getSSLExpectStartTLS(names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should upgrade SMTP connections to SSL using the STARTTLS command.

```
Boolean[] getSSLExpectStartTLS(
    String[] names
)
```

getSSLExpectStartTLSByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should upgrade SMTP connections to SSL using the STARTTLS command. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getSSLExpectStartTLSByLocation(
    String location
    String[] names
)
```

getSSLHeaders(names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should add HTTP headers to each request to show SSL connection parameters.

```
Boolean[] getSSLHeaders(
    String[] names
)
```

getSSLHeadersByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should add HTTP headers to each request to show SSL connection parameters. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getSSLHeadersByLocation(
    String location
    String[] names
)
```

getSSLLogEnabled(names) throws ObjectDoesNotExist

This method is now obsolete. SSL logging is now done if LogConnectionFailures is enabled. Use VirtualServer.getLogConnectionFailures and VirtualServer.getLogConnection failures to control this configuration.

```
Boolean[] getSSLLogEnabled(
    String[] names
)
```

getSSLNeverExpiringClientCertificateAuthorities(names) throws ObjectDoesNotExist

Get the CAs for which any client certificate they validate is considered valid even if the client certificate's expiration date has passed.

```
String[][]
getSSLNeverExpiringClientCertificateAuthorities(
    String[] names
)
```

getSSLNeverExpiringClientCertificateAuthoritiesByLocation(location, names) throws ObjectDoesNotExist

Get the CAs for which any client certificate they validate is considered valid even if the client certificate's expiration date has passed. This is a location specific function, any action will operate on the specified location.

```
String[][]
getSSLNeverExpiringClientCertificateAuthoritiesByLoca
tion(
    String location
    String[] names
)
```

getSSLOCSPDefaults(names) throws ObjectDoesNotExist

Get the default OCSP responder settings for all client certificates.

```
VirtualServer.SSLOCSPIssuer[] getSSLOCSPDefaults(
    String[] names
)
```

getSSLOCSPDefaultsByLocation(location, names) throws ObjectDoesNotExist

Get the default OCSP responder settings for all client certificates. This is a location specific function, any action will operate on the specified location.

```
VirtualServer.SSLOCSPIssuer[]
getSSLOCSPDefaultsByLocation(
    String location
    String[] names
)
```

getSSLOCSPIssuers(names) throws ObjectDoesNotExist

Gets a list of mappings between Certificate Authorities and OCSP responder settings. Certificates issued by these authorities will be verified with OCSP using these settings.

```
VirtualServer.SSLOCSPIssuer[][] getSSLOCSPIssuers(
    String[] names
)
```

getSSLOCSPIssuersByLocation(location, names) throws ObjectDoesNotExist

Gets a list of mappings between Certificate Authorities and OCSP responder settings. Certificates issued by these authorities will be verified with OCSP using these settings. This is a location specific function, any action will operate on the specified location.

```
VirtualServer.SSLOCSPIssuer[][]
getSSLOCSPIssuersByLocation(
    String location
    String[] names
)
```

getSSLOCSPMaxResponseAge(names) throws ObjectDoesNotExist

Get the number of seconds for which an OCSP response is considered valid if it has not yet exceeded the time specified in the 'nextUpdate' field

```
Unsigned Integer[] getSSLOCSPMaxResponseAge(
    String[] names
)
```

getSSLOCSPMaxResponseAgeByLocation(location, names) throws ObjectDoesNotExist

Get the number of seconds for which an OCSP response is considered valid if it has not yet exceeded the time specified in the 'nextUpdate' field This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[]
getSSLOCSPMaxResponseAgeByLocation(
   String location
   String[] names
)
```

getSSLOCSPTimeTolerance(names) throws ObjectDoesNotExist

Get the number of seconds outside the permitted range for which the 'thisUpdate' and 'nextUpdate' fields of an OCSP response are still considered valid

```
Unsigned Integer[] getSSLOCSPTimeTolerance(
    String[] names
)
```

getSSLOCSPTimeToleranceByLocation(location, names) throws ObjectDoesNotExist

Get the number of seconds outside the permitted range for which the 'thisUpdate' and 'nextUpdate' fields of an OCSP response are still considered valid This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getSSLOCSPTimeToleranceByLocation(
    String location
    String[] names
)
```

getSSLOCSPTimeout(names) throws ObjectDoesNotExist

Get the number of seconds after which OCSP requests will be timed out

```
Unsigned Integer[] getSSLOCSPTimeout(
    String[] names
)
```

getSSLOCSPTimeoutByLocation(location, names) throws ObjectDoesNotExist

Get the number of seconds after which OCSP requests will be timed out This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getSSLOCSPTimeoutByLocation(
    String location
    String[] names
)
```

getSSLPreferSSLv3(names) throws ObjectDoesNotExist

Get whether to prefer SSLv3 over TLS when the client appears to support both. SSLv3 is slightly faster, but some clients don't allow SSLv3 but still send the ClientHello inside SSLv2 or SSLv3 records.

```
Boolean[] getSSLPreferSSLv3(
    String[] names
)
```

getSSLPreferSSLv3ByLocation(location, names) throws ObjectDoesNotExist

Get whether to prefer SSLv3 over TLS when the client appears to support both. SSLv3 is slightly faster, but some clients don't allow SSLv3 but still send the ClientHello inside SSLv2 or SSLv3 records. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getSSLPreferSSLv3ByLocation(
    String location
    String[] names
)
```

getSSLRequestClientCertMode(names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should request (or require) an identifying certificate from each client.

```
VirtualServer.SSLRequestClientCertMode[]
getSSLRequestClientCertMode(
    String[] names
)
```

getSSLRequestClientCertModeByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should request (or require) an identifying certificate from each client. This is a location specific function, any action will operate on the specified location.

```
VirtualServer.SSLRequestClientCertMode[]
getSSLRequestClientCertModeByLocation(
    String location
    String[] names
)
```

getSSLSendCloseAlerts(names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should send a close alert when initiating SSL socket disconnections.

```
Boolean[] getSSLSendCloseAlerts(
    String[] names
)
```

getSSLSendCloseAlertsByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should send a close alert when initiating SSL socket disconnections. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getSSLSendCloseAlertsByLocation(
    String location
    String[] names
)
```

getSSLSites(names) throws ObjectDoesNotExist

Gets a list of mappings between destination addresses and the certificate used for SSL decryption those addresses, for each of the named virtual servers. Each certificate is the name of an item in the SSL Certificates Catalog.

```
VirtualServer.SSLSite[][] getSSLSites(
    String[] names
)
```

getSSLSitesByLocation(location, names) throws ObjectDoesNotExist

Gets a list of mappings between destination addresses and the certificate used for SSL decryption those addresses, for each of the named virtual servers. Each certificate is the name of an item in the SSL Certificates Catalog. This is a location specific function, any action will operate on the specified location.

```
VirtualServer.SSLSite[][] getSSLSitesByLocation(
    String location
    String[] names
)
```

getSSLTrustMagic(names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should decode extra information on the true origin of an SSL connection. This information is prefixed onto an incoming SSL connection from another traffic manager.

```
Boolean[] getSSLTrustMagic(
    String[] names
)
```

getSSLTrustMagicByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should decode extra information on the true origin of an SSL connection. This information is prefixed onto an incoming SSL connection from another traffic manager. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getSSLTrustMagicByLocation(
    String location
    String[] names
)
```

getSSLUseOCSP(names) throws ObjectDoesNotExist

Get whether or not the traffic manager should use OCSP to check the revocation status of client certificates

```
Boolean[] getSSLUseOCSP(
    String[] names
)
```

getSSLUseOCSPByLocation(location, names) throws ObjectDoesNotExist

Get whether or not the traffic manager should use OCSP to check the revocation status of client certificates This is a location specific function, any action will operate on the specified location.

```
Boolean[] getSSLUseOCSPByLocation(
    String location
    String[] names
)
```

getServerfirstBanner(names) throws ObjectDoesNotExist

Get the banner that each of the named virtual servers sends to clients for server-first protocols such as POP, SMTP and IMAP.

```
String[] getServerfirstBanner(
    String[] names
)
```

getServerfirstBannerByLocation(location, names) throws ObjectDoesNotExist

Get the banner that each of the named virtual servers sends to clients for server-first protocols such as POP, SMTP and IMAP. This is a location specific function, any action will operate on the specified location.

```
String[] getServerfirstBannerByLocation(
    String location
    String[] names
)
```

getServiceLevelMonitoring(names) throws ObjectDoesNotExist

Get the Service Level Monitoring class that each of the named virtual servers uses.

```
String[] getServiceLevelMonitoring(
    String[] names
)
```

getServiceLevelMonitoringByLocation(location, names) throws ObjectDoesNotExist

Get the Service Level Monitoring class that each of the named virtual servers uses. This is a location specific function, any action will operate on the specified location.

```
String[] getServiceLevelMonitoringByLocation(
   String location
   String[] names
)
```

getSipTransactionTimeout(names) throws ObjectDoesNotExist

Get the time after which an incomplete transaction should be discarded, in seconds, for each of the named virtual servers.

```
Unsigned Integer[] getSipTransactionTimeout(
    String[] names
)
```

getSipTransactionTimeoutByLocation(location, names) throws ObjectDoesNotExist

Get the time after which an incomplete transaction should be discarded, in seconds, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[]
getSipTransactionTimeoutByLocation(
    String location
    String[] names
)
```

getTimeout(names) throws ObjectDoesNotExist

Get the time to wait for data on an already established connection, in seconds, for each of the named virtual servers.

```
Unsigned Integer[] getTimeout(
    String[] names
)
```

getTimeoutByLocation(location, names) throws ObjectDoesNotExist

Get the time to wait for data on an already established connection, in seconds, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getTimeoutByLocation(
    String location
```

```
String[] names
)
```

getUDPResponseDatagramsExpected(names) throws ObjectDoesNotExist

Get the expected number of UDP datagrams in the response, for each of the named virtual servers. For simple request/response protocols a value of '1' should be used. If set to -1, the connection will not be discarded until the udp_timeout is reached.

```
Integer[] getUDPResponseDatagramsExpected(
    String[] names
)
```

getUDPResponseDatagramsExpectedByLocation(location, names) throws ObjectDoesNotExist

Get the expected number of UDP datagrams in the response, for each of the named virtual servers. For simple request/response protocols a value of '1' should be used. If set to -1, the connection will not be discarded until the udp_timeout is reached. This is a location specific function, any action will operate on the specified location.

```
Integer[] getUDPResponseDatagramsExpectedByLocation(
    String location
    String[] names
```

getUDPTimeout(names) throws ObjectDoesNotExist

Get the time after which an idle UDP connection should be discarded and resources reclaimed, in seconds, for each of the named virtual servers.

```
Unsigned Integer[] getUDPTimeout(
    String[] names
)
```

getUDPTimeoutByLocation(location, names) throws ObjectDoesNotExist

Get the time after which an idle UDP connection should be discarded and resources reclaimed, in seconds, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getUDPTimeoutByLocation(
    String location
```

```
String[] names
)
```

getUseNagle(names) throws ObjectDoesNotExist

Get whether Nagle's algorithm should be used for TCP connections.

```
Boolean[] getUseNagle(
    String[] names
)
```

getUseNagleByLocation(location, names) throws ObjectDoesNotExist

Get whether Nagle's algorithm should be used for TCP connections. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getUseNagleByLocation(
   String location
   String[] names
)
```

getVirtualServerNames()

Gets the names of all the configured virtual servers.

```
String[] getVirtualServerNames()
```

getWebcacheControlOut(names) throws ObjectDoesNotExist

Get the Cache-Control header that should be sent with cached HTTP responses.

```
String[] getWebcacheControlOut(
    String[] names
)
```

getWebcacheControlOutByLocation(location, names) throws ObjectDoesNotExist

Get the Cache-Control header that should be sent with cached HTTP responses. This is a location specific function, any action will operate on the specified location.

```
String[] getWebcacheControlOutByLocation(
    String location
```

```
String[] names
)
```

getWebcacheEnabled(names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should attempt to cache web server responses.

```
Boolean[] getWebcacheEnabled(
    String[] names
)
```

getWebcacheEnabledByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named virtual servers should attempt to cache web server responses. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getWebcacheEnabledByLocation(
    String location
    String[] names
)
```

getWebcacheErrorpageTime(names) throws ObjectDoesNotExist

Get the time periods that each of the named virtual servers should cache error pages for.

```
Unsigned Integer[] getWebcacheErrorpageTime(
    String[] names
)
```

getWebcacheErrorpageTimeByLocation(location, names) throws ObjectDoesNotExist

Get the time periods that each of the named virtual servers should cache error pages for. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[]
getWebcacheErrorpageTimeByLocation(
    String location
    String[] names
)
```

getWebcacheRefreshTime(names) throws ObjectDoesNotExist

Get the time periods that each of the named virtual servers should consider re-fetching cached pages in.

```
Unsigned Integer[] getWebcacheRefreshTime(
    String[] names
)
```

getWebcacheRefreshTimeByLocation(location, names) throws ObjectDoesNotExist

Get the time periods that each of the named virtual servers should consider re-fetching cached pages in. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getWebcacheRefreshTimeByLocation(
   String location
   String[] names
)
```

getWebcacheTime(names) throws ObjectDoesNotExist

Get the time periods that each of the named virtual servers should cache web pages for.

```
Unsigned Integer[] getWebcacheTime(
    String[] names
)
```

getWebcacheTimeByLocation(location, names) throws ObjectDoesNotExist

Get the time periods that each of the named virtual servers should cache web pages for. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getWebcacheTimeByLocation(
   String location
   String[] names
)
```

removeCompressionMIMETypes(names, values) throws ObjectDoesNotExist, DeploymentError

For each named virtual server, remove new MIME types from the list of types to compress.

```
void removeCompressionMIMETypes(
```

```
String[] names
String[][] values
)
```

removeCompressionMIMETypesByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError

For each named virtual server, remove new MIME types from the list of types to compress. This is a location specific function, any action will operate on the specified location.

```
void removeCompressionMIMETypesByLocation(
   String location
   String[] names
   String[][] values
)
```

removeFTPPortRange(names) throws ObjectDoesNotExist, DeploymentError

Allow FTP connections to use any free ports, for each of the named virtual servers.

```
void removeFTPPortRange(
    String[] names
)
```

removeFTPPortRangeByLocation(location, names) throws ObjectDoesNotExist, DeploymentError

Allow FTP connections to use any free ports, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void removeFTPPortRangeByLocation(
   String location
   String[] names
)
```

removeRTSPPortRange(names) throws ObjectDoesNotExist, DeploymentError

Allow any free ports to be used for RTSP connections, for each of the named virtual servers.

```
void removeRTSPPortRange(
    String[] names
```

)

removeRTSPPortRangeByLocation(location, names) throws ObjectDoesNotExist, DeploymentError

Allow any free ports to be used for RTSP connections, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void removeRTSPPortRangeByLocation(
    String location
    String[] names
)
```

removeResponseRules(names, rules) throws InvalidInput, ObjectDoesNotExist, DeploymentError

For each of the named virtual servers, remove rules from the list that are run on server responses.

```
void removeResponseRules(
    String[] names
    String[][] rules
)
```

removeResponseRulesByLocation(location, names, rules) throws InvalidInput, ObjectDoesNotExist, DeploymentError

For each of the named virtual servers, remove rules from the list that are run on server responses. This is a location specific function, any action will operate on the specified location.

```
void removeResponseRulesByLocation(
   String location
   String[] names
   String[][] rules
)
```

removeRules(names, rules) throws InvalidInput, ObjectDoesNotExist, DeploymentError

For each of the named virtual servers, remove rules from the list of rules that are run on client requests.

```
void removeRules(
    String[] names
```

```
String[][] rules
```

removeRulesByLocation(location, names, rules) throws InvalidInput, ObjectDoesNotExist, DeploymentError

For each of the named virtual servers, remove rules from the list of rules that are run on client requests. This is a location specific function, any action will operate on the specified location.

```
void removeRulesByLocation(
   String location
   String[] names
   String[][] rules
)
```

removeSIPPortRange(names) throws ObjectDoesNotExist, DeploymentError

Allow any free ports to be used for SIP connections, for each of the named virtual servers. This setting is only used when the SIP virtual server is using 'Full Gateway' mode.

```
void removeSIPPortRange(
    String[] names
)
```

removeSIPPortRangeByLocation(location, names) throws ObjectDoesNotExist, DeploymentError

Allow any free ports to be used for SIP connections, for each of the named virtual servers. This setting is only used when the SIP virtual server is using 'Full Gateway' mode. This is a location specific function, any action will operate on the specified location.

```
void removeSIPPortRangeByLocation(
   String location
   String[] names
)
```

removeSSLClientCertificateAuthorities(names, values) throws ObjectDoesNotExist, DeploymentError

Remove certificate authorities for validating client certificates for each of the named virtual servers.

```
void removeSSLClientCertificateAuthorities(
    String[] names
```

```
String[][] values
```

removeSSLClientCertificateAuthoritiesByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError

Remove certificate authorities for validating client certificates for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void removeSSLClientCertificateAuthoritiesByLocation(
   String location
   String[] names
   String[][] values
)
```

removeSSLNeverExpiringClientCertificateAuthorities(names, values) throws ObjectDoesNotExist, DeploymentError

Remove CAs for which any client certificate they validate is considered valid even if the client certificate's expiration date has passed, for each of the named virtual servers.

```
void
removeSSLNeverExpiringClientCertificateAuthorities(
   String[] names
   String[][] values
)
```

removeSSLNeverExpiringClientCertificateAuthoritiesByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError

Remove CAs for which any client certificate they validate is considered valid even if the client certificate's expiration date has passed, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void
removeSSLNeverExpiringClientCertificateAuthoritiesByL
ocation(
    String location
    String[] names
    String[][] values
)
```

removeSSLOCSPIssuers(names, cas) throws ObjectDoesNotExist, DeploymentError

Removes mappings between OCSP responder settings for the specified Certificate authorities

```
void removeSSLOCSPIssuers(
    String[] names
    String[][] cas
)
```

removeSSLOCSPIssuersByLocation(location, names, cas) throws ObjectDoesNotExist, DeploymentError

Removes mappings between OCSP responder settings for the specified Certificate authorities This is a location specific function, any action will operate on the specified location.

```
void removeSSLOCSPIssuersByLocation(
   String location
   String[] names
   String[][] cas
)
```

renameVirtualServer(names, new_names) throws ObjectDoesNotExist, InvalidObjectName, DeploymentError, InvalidOperation

Rename each of the named virtual servers.

```
void renameVirtualServer(
    String[] names
    String[] new_names
)
```

setAddClusterClientIPHeader(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether a 'X-Cluster-Client-Ip' header should be added to each HTTP request, for each of the named virtual servers. The 'X-Cluster-Client-Ip' header contains the client's IP address.

```
void setAddClusterClientIPHeader(
    String[] names
    Boolean[] values
)
```

setAddClusterClientIPHeaderByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether a 'X-Cluster-Client-Ip' header should be added to each HTTP request, for each of the named virtual servers. The 'X-Cluster-Client-Ip' header contains the client's IP address. This is a location specific function, any action will operate on the specified location.

```
void setAddClusterClientIPHeaderByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setApplicationFirewallEnabled(names, values) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, LicenseError

For each of the named virtual servers, enable or disable the Stingray Application Firewall.

```
void setApplicationFirewallEnabled(
   String[] names
   Boolean[] values
)
```

setApplicationFirewallEnabledByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, LicenseError

For each of the named virtual servers, enable or disable the Stingray Application Firewall. This is a location specific function, any action will operate on the specified location.

```
void setApplicationFirewallEnabledByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setBandwidthClass(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the Bandwidth Class that each of the named virtual servers uses.

```
void setBandwidthClass(
    String[] names
```

```
String[] values
```

setBandwidthClassByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the Bandwidth Class that each of the named virtual servers uses. This is a location specific function, any action will operate on the specified location.

```
void setBandwidthClassByLocation(
   String location
   String[] names
   String[] values
)
```

setCompressUnknownSize(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should compress documents with no given size.

```
void setCompressUnknownSize(
    String[] names
    Boolean[] values
)
```

setCompressUnknownSizeByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should compress documents with no given size. This is a location specific function, any action will operate on the specified location.

```
void setCompressUnknownSizeByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setCompressionEnabled(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should compress web pages before sending to the client.

```
void setCompressionEnabled(
   String[] names
   Boolean[] values
)
```

setCompressionEnabledByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should compress web pages before sending to the client. This is a location specific function, any action will operate on the specified location.

```
void setCompressionEnabledByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setCompressionLevel(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the gzip compression level, for each of the named virtual servers.

```
void setCompressionLevel(
    String[] names
    Unsigned Integer[] values
)
```

setCompressionLevelByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the gzip compression level, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void setCompressionLevelByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setCompressionMIMETypes(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the list of MIME types to compress, for each of the named virtual servers.

```
void setCompressionMIMETypes(
   String[] names
   String[][] values
)
```

setCompressionMIMETypesByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the list of MIME types to compress, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void setCompressionMIMETypesByLocation(
   String location
   String[] names
   String[][] values
)
```

setCompressionMaxSize(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the maximum document size to compress, in bytes, for each of the named virtual servers. A document size of '0' means 'unlimited'.

```
void setCompressionMaxSize(
    String[] names
    Unsigned Integer[] values
)
```

setCompressionMaxSizeByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the maximum document size to compress, in bytes, for each of the named virtual servers. A document size of '0' means 'unlimited'. This is a location specific function, any action will operate on the specified location.

```
void setCompressionMaxSizeByLocation(
   String location
   String[] names
```

```
Unsigned Integer[] values
```

setCompressionMinSize(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the minimum document size to compress, in bytes, for each of the named virtual servers.

```
void setCompressionMinSize(
    String[] names
    Unsigned Integer[] values
)
```

setCompressionMinSizeByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the minimum document size to compress, in bytes, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void setCompressionMinSizeByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setConnectTimeout(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the time to wait for data from a new connection, in seconds, for each of the named virtual servers. If no data is received in this time, the connection will be closed.

```
void setConnectTimeout(
   String[] names
   Unsigned Integer[] values
)
```

setConnectTimeoutByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the time to wait for data from a new connection, in seconds, for each of the named virtual servers. If no data is received in this time, the connection will be closed. This is a location specific function, any action will operate on the specified location.

```
void setConnectTimeoutByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setCookieDomainRewriteMode(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set how each of the named virtual servers should rewrite the domain portion of cookies set by a backend web server.

```
void setCookieDomainRewriteMode(
   String[] names
   VirtualServer.CookieDomainRewriteMode[] values
)
```

setCookieDomainRewriteModeByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set how each of the named virtual servers should rewrite the domain portion of cookies set by a backend web server. This is a location specific function, any action will operate on the specified location.

```
void setCookieDomainRewriteModeByLocation(
   String location
   String[] names
   VirtualServer.CookieDomainRewriteMode[] values
)
```

setCookieNamedDomain(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the domain to use when rewriting cookie domains, for each of the named virtual servers.

```
void setCookieNamedDomain(
    String[] names
    String[] values
)
```

setCookieNamedDomainByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the domain to use when rewriting cookie domains, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void setCookieNamedDomainByLocation(
   String location
   String[] names
   String[] values
)
```

setCookiePathRewrite(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

For each of the named virtual servers, set the regex, and replacement for rewriting the path portion of a cookie.

```
void setCookiePathRewrite(
    String[] names
    VirtualServer.RegexReplacement[] values
)
```

setCookiePathRewriteByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

For each of the named virtual servers, set the regex, and replacement for rewriting the path portion of a cookie. This is a location specific function, any action will operate on the specified location.

```
void setCookiePathRewriteByLocation(
   String location
   String[] names
   VirtualServer.RegexReplacement[] values
)
```

setCookieSecureFlagRewriteMode(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should modify the 'secure' tag of cookies set by a backend web server.

```
void setCookieSecureFlagRewriteMode(
    String[] names
```

```
VirtualServer.CookieSecureFlagRewriteMode[] values
)
```

setCookieSecureFlagRewriteModeByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should modify the 'secure' tag of cookies set by a backend web server. This is a location specific function, any action will operate on the specified location.

```
void setCookieSecureFlagRewriteModeByLocation(
   String location
   String[] names
   VirtualServer.CookieSecureFlagRewriteMode[] values
)
```

setDefaultPool(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the default Pool that traffic is sent to for each of the named virtual servers.

```
void setDefaultPool(
    String[] names
    String[] values
)
```

setDefaultPoolByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the default Pool that traffic is sent to for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void setDefaultPoolByLocation(
   String location
   String[] names
   String[] values
)
```

setEnabled(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers is enabled (i.e. serving traffic).

```
void setEnabled(
   String[] names
   Boolean[] values
)
```

setEnabledByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers is enabled (i.e. serving traffic). This is a location specific function, any action will operate on the specified location.

```
void setEnabledByLocation(
    String location
    String[] names
    Boolean[] values
)
```

setErrorFile(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the file names of the error texts that each of the named virtual servers will send back to a client in case of back-end or internal errors.

```
void setErrorFile(
    String[] names
    String[] values
)
```

setErrorFileByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the file names of the error texts that each of the named virtual servers will send back to a client in case of back-end or internal errors. This is a location specific function, any action will operate on the specified location.

```
void setErrorFileByLocation(
    String location
    String[] names
    String[] values
)
```

setFTPDataSourcePort(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the source port each of the named virtual servers should use for active-mode FTP data connections. If 0, a random high port will be used, otherwise the specified port will be used. If a port below 1024 is required you must first explicitly permit use of low ports with the ftp_data_bind_low global setting.

```
void setFTPDataSourcePort(
    String[] names
    Unsigned Integer[] values
)
```

setFTPDataSourcePortByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the source port each of the named virtual servers should use for active-mode FTP data connections. If 0, a random high port will be used, otherwise the specified port will be used. If a port below 1024 is required you must first explicitly permit use of low ports with the ftp_data_bind_low global setting. This is a location specific function, any action will operate on the specified location.

```
void setFTPDataSourcePortByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setFTPForceClientSecure(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should require incoming FTP data connections (from clients) to originate from the same IP address as the corresponding control connection.

```
void setFTPForceClientSecure(
   String[] names
   Boolean[] values
)
```

setFTPForceClientSecureByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should require incoming FTP data connections (from clients) to originate from the same IP address as the corresponding control connection. This is a location specific function, any action will operate on the specified location.

```
void setFTPForceClientSecureByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setFTPForceServerSecure(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should require incoming FTP data connections (from nodes) to originate from the same IP address as the corresponding control connection.

```
void setFTPForceServerSecure(
    String[] names
    Boolean[] values
)
```

setFTPForceServerSecureByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should require incoming FTP data connections (from nodes) to originate from the same IP address as the corresponding control connection. This is a location specific function, any action will operate on the specified location.

```
void setFTPForceServerSecureByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setFTPPortRange(names, range) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the port range used for FTP data connections for each of the named virtual servers.

```
void setFTPPortRange(
    String[] names
    VirtualServer.FTPPortRange[] range
)
```

setFTPPortRangeByLocation(location, names, range) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the port range used for FTP data connections for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void setFTPPortRangeByLocation(
   String location
   String[] names
   VirtualServer.FTPPortRange[] range
)
```

setFTPSSLData(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should use SSL on the data connection as well as the control connection

```
void setFTPSSLData(
    String[] names
    Boolean[] values
)
```

setFTPSSLDataByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should use SSL on the data connection as well as the control connection This is a location specific function, any action will operate on the specified location.

```
void setFTPSSLDataByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setKeepalive(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should allow clients to maintain keepalive connections.

```
void setKeepalive(
   String[] names
   Boolean[] values
```

)

setKeepaliveByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should allow clients to maintain keepalive connections. This is a location specific function, any action will operate on the specified location.

```
void setKeepaliveByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setKeepaliveTimeout(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the time that an idle keepalive connection should be kept open for, in seconds, for each of the named virtual servers.

```
void setKeepaliveTimeout(
    String[] names
    Unsigned Integer[] values
)
```

setKeepaliveTimeoutByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the time that an idle keepalive connection should be kept open for, in seconds, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void setKeepaliveTimeoutByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setListenAddresses(names, addresses) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the specific IP addresses and hostnames for each named virtual server to listen on.

```
void setListenAddresses(
    String[] names
    String[][] addresses
)
```

setListenAddressesByLocation(location, names, addresses) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the specific IP addresses and hostnames for each named virtual server to listen on. This is a location specific function, any action will operate on the specified location.

```
void setListenAddressesByLocation(
   String location
   String[] names
   String[][] addresses
)
```

setListenOnAllAddresses(names) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Make each of the named virtual servers listen on all IP addresses.

```
void setListenOnAllAddresses(
    String[] names
)
```

setListenOnAllAddressesByLocation(location, names) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Make each of the named virtual servers listen on all IP addresses. This is a location specific function, any action will operate on the specified location.

```
void setListenOnAllAddressesByLocation(
   String location
   String[] names
)
```

setListenTrafficIPGroups(names, groups) throws InvalidInput, ObjectDoesNotExist, DeploymentError

For each of the named virtual servers, set specific Traffic IP Groups for it to listen on.

```
void setListenTrafficIPGroups(
    String[] names
    String[][] groups
)
```

setListenTrafficIPGroupsByLocation(location, names, groups) throws InvalidInput, ObjectDoesNotExist, DeploymentError

For each of the named virtual servers, set specific Traffic IP Groups for it to listen on. This is a location specific function, any action will operate on the specified location.

```
void setListenTrafficIPGroupsByLocation(
    String location
    String[] names
    String[][] groups
)
```

setLocationDefaultRewriteMode(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should rewrite the 'Location' header. The rewrite is only performed if the location rewrite regex didn't match.

```
void setLocationDefaultRewriteMode(
    String[] names
    VirtualServer.LocationDefaultRewriteMode[] values
)
```

setLocationDefaultRewriteModeByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should rewrite the 'Location' header. The rewrite is only performed if the location rewrite regex didn't match. This is a location specific function, any action will operate on the specified location.

```
void setLocationDefaultRewriteModeByLocation(
   String location
   String[] names
   VirtualServer.LocationDefaultRewriteMode[] values
)
```

setLocationRewrite(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

For each of the named virtual servers, set the regex, and replacement for rewriting any 'Location' headers.

```
void setLocationRewrite(
   String[] names
   VirtualServer.RegexReplacement[] values
)
```

setLocationRewriteByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

For each of the named virtual servers, set the regex, and replacement for rewriting any 'Location' headers. This is a location specific function, any action will operate on the specified location.

```
void setLocationRewriteByLocation(
   String location
   String[] names
   VirtualServer.RegexReplacement[] values
)
```

setLogClientConnectionFailures(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether the virtual server will log client connection failures.

```
void setLogClientConnectionFailures(
   String[] names
   Boolean[] values
)
```

setLogClientConnectionFailuresByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether the virtual server will log client connection failures. This is a location specific function, any action will operate on the specified location.

```
void setLogClientConnectionFailuresByLocation(
   String location
   String[] names
   Boolean[] values
```

)

setLogEnabled(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should log each connection to a disk on the file system.

```
void setLogEnabled(
    String[] names
    Boolean[] values
)
```

setLogEnabledByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should log each connection to a disk on the file system. This is a location specific function, any action will operate on the specified location.

```
void setLogEnabledByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setLogFilename(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the name of the file used to store request logs, for each of the named virtual servers.

```
void setLogFilename(
    String[] names
    String[] values
)
```

setLogFilenameByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the name of the file used to store request logs, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void setLogFilenameByLocation(
    String location
```

```
String[] names
String[] values
)
```

setLogFormat(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the log file format for each of the named virtual servers.

```
void setLogFormat(
    String[] names
    String[] values
)
```

setLogFormatByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the log file format for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void setLogFormatByLocation(
    String location
    String[] names
    String[] values
)
```

setLogSSLFailures(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether the virtual server will log ssl failures.

```
void setLogSSLFailures(
    String[] names
    Boolean[] values
)
```

setLogSSLFailuresByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether the virtual server will log ssl failures. This is a location specific function, any action will operate on the specified location.

```
void setLogSSLFailuresByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setLogServerConnectionFailures(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether the virtual server will log server connection failures.

```
void setLogServerConnectionFailures(
    String[] names
    Boolean[] values
)
```

setLogServerConnectionFailuresByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether the virtual server will log server connection failures. This is a location specific function, any action will operate on the specified location.

```
void setLogServerConnectionFailuresByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setMIMEAutoDetect(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should auto-detect MIME types if the server does not provide them.

```
void setMIMEAutoDetect(
   String[] names
   Boolean[] values
)
```

setMIMEAutoDetectByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should auto-detect MIME types if the server does not provide them. This is a location specific function, any action will operate on the specified location.

```
void setMIMEAutoDetectByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setMIMEDefaultType(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the MIME type that the server uses as its 'default', for each of the named virtual servers. Responses with this mime type will be auto-corrected by the virtual server if this setting is enabled.

```
void setMIMEDefaultType(
    String[] names
    String[] values
)
```

setMIMEDefaultTypeByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the MIME type that the server uses as its 'default', for each of the named virtual servers. Responses with this mime type will be auto-corrected by the virtual server if this setting is enabled. This is a location specific function, any action will operate on the specified location.

```
void setMIMEDefaultTypeByLocation(
   String location
   String[] names
   String[] values
)
```

setMaxClientBuffer(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the amount of memory used to store data sent by the client, in bytes, for each of the named virtual servers.

```
void setMaxClientBuffer(
```

```
String[] names
Unsigned Integer[] values
)
```

setMaxClientBufferByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the amount of memory used to store data sent by the client, in bytes, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void setMaxClientBufferByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setMaxServerBuffer(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the amount of memory used to store data returned by the server, in bytes, for each of the named virtual servers.

```
void setMaxServerBuffer(
   String[] names
   Unsigned Integer[] values
)
```

setMaxServerBufferByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the amount of memory used to store data returned by the server, in bytes, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void setMaxServerBufferByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setNote(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the note for each of the named virtual servers.

```
void setNote(
   String[] names
   String[] values
)
```

setPort(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the port that each of the named virtual servers listens on for incoming connections.

```
void setPort(
    String[] names
    Unsigned Integer[] values
)
```

setPortByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the port that each of the named virtual servers listens on for incoming connections. This is a location specific function, any action will operate on the specified location.

```
void setPortByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setProtection(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the Service Protection Settings that are used to protect each of the named virtual servers.

```
void setProtection(
    String[] names
    String[] values
)
```

setProtectionByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the Service Protection Settings that are used to protect each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void setProtectionByLocation(
    String location
    String[] names
    String[] values
)
```

setProtocol(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the protocol that each of the named virtual servers uses.

```
void setProtocol(
    String[] names
    VirtualServer.Protocol[] values
)
```

setProxyClose(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should send a FIN packet on to the back-end server when it is received from the client. The alternative is to close the connection to the client immediately. If the traffic manager is responding to the request itself, enabling this setting will cause the traffic manager to continue writing the response even after it has received a FIN from the client.

```
void setProxyClose(
    String[] names
    Boolean[] values
)
```

setProxyCloseByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should send a FIN packet on to the back-end server when it is received from the client. The alternative is to close the connection to the client immediately. If the traffic manager is responding to the request itself, enabling this setting will cause the traffic manager to continue writing the response even after it has received a FIN from the client. This is a location specific function, any action will operate on the specified location.

```
void setProxyCloseByLocation(
```

```
String location
String[] names
Boolean[] values
```

setRTSPPortRange(names, range) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the port range used for RTSP streaming data connections for each of the named virtual servers.

```
void setRTSPPortRange(
    String[] names
    VirtualServer.PortRange[] range
)
```

setRTSPPortRangeByLocation(location, names, range) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the port range used for RTSP streaming data connections for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void setRTSPPortRangeByLocation(
   String location
   String[] names
   VirtualServer.PortRange[] range
)
```

setRTSPStreamingTimeout(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the time, in seconds, after which data-streams associated with RTSP connections timeout if no data is transmitted.

```
void setRTSPStreamingTimeout(
    String[] names
    Unsigned Integer[] values
)
```

setRTSPStreamingTimeoutByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the time, in seconds, after which data-streams associated with RTSP connections timeout if no data is transmitted. This is a location specific function, any action will operate on the specified location.

```
void setRTSPStreamingTimeoutByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setRequestSyslogEnabled(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should log each connection to a remote syslog server.

```
void setRequestSyslogEnabled(
   String[] names
   Boolean[] values
)
```

setRequestSyslogEnabledByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should log each connection to a remote syslog server. This is a location specific function, any action will operate on the specified location.

```
void setRequestSyslogEnabledByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setRequestSyslogFormat(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the remote log line format for each of the named virtual servers.

```
void setRequestSyslogFormat(
    String[] names
    String[] values
```

)

setRequestSyslogFormatByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the remote log line format for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void setRequestSyslogFormatByLocation(
   String location
   String[] names
   String[] values
)
```

setRequestSyslogIPEndpoint(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the remote syslog endpoint for each of the named virtual servers

```
void setRequestSyslogIPEndpoint(
    String[] names
    String[] values
)
```

setRequestSyslogIPEndpointByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the remote syslog endpoint for each of the named virtual servers This is a location specific function, any action will operate on the specified location.

```
void setRequestSyslogIPEndpointByLocation(
   String location
   String[] names
   String[] values
)
```

setRequestTracingEnabled(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether to record a detailed list of processing history for each request.

```
void setRequestTracingEnabled(
```

```
String[] names
Boolean[] values
)
```

setRequestTracingEnabledByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether to record a detailed list of processing history for each request. This is a location specific function, any action will operate on the specified location.

```
void setRequestTracingEnabledByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setRequestTracingIO(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether to record a detailed list of every IO event in the processing history for each request.

```
void setRequestTracingIO(
    String[] names
    Boolean[] values
)
```

setRequestTracinglOByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether to record a detailed list of every IO event in the processing history for each request. This is a location specific function, any action will operate on the specified location.

```
void setRequestTracingIOByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setResponseRules(names, rules) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the rules that are run on server responses for each of the named virtual servers.

```
void setResponseRules(
   String[] names
   VirtualServer.Rule[][] rules
)
```

setResponseRulesByLocation(location, names, rules) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the rules that are run on server responses for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void setResponseRulesByLocation(
   String location
   String[] names
   VirtualServer.Rule[][] rules
)
```

setRewriteSIPURI(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether the Request-URI of SIP requests will be replaced with the selected back-end node's address.

```
void setRewriteSIPURI(
    String[] names
    Boolean[] values
)
```

setRewriteSIPURIByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether the Request-URI of SIP requests will be replaced with the selected back-end node's address. This is a location specific function, any action will operate on the specified location.

```
void setRewriteSIPURIByLocation(
   String location
   String[] names
   Boolean[] values
```

)

setRules(names, rules) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the rules that are run on client requests for each of the named virtual servers.

```
void setRules(
    String[] names
    VirtualServer.Rule[][] rules
)
```

setRulesByLocation(location, names, rules) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the rules that are run on client requests for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void setRulesByLocation(
   String location
   String[] names
   VirtualServer.Rule[][] rules
)
```

setSIPDangerousRequestMode(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set what should be done with requests that contain body data and should be routed to an external IP.

```
void setSIPDangerousRequestMode(
   String[] names
   VirtualServer.SIPDangerousRequestMode[] values
)
```

setSIPDangerousRequestModeByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set what should be done with requests that contain body data and should be routed to an external IP. This is a location specific function, any action will operate on the specified location.

```
void setSIPDangerousRequestModeByLocation(
    String location
```

```
String[] names
VirtualServer.SIPDangerousRequestMode[] values
)
```

setSIPFollowRoute(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether to follow routing information in SIP requests.

```
void setSIPFollowRoute(
   String[] names
   Boolean[] values
)
```

setSIPFollowRouteByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether to follow routing information in SIP requests. This is a location specific function, any action will operate on the specified location.

```
void setSIPFollowRouteByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setSIPMaxConnectionMemory(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set maximum memory per connection.

```
void setSIPMaxConnectionMemory(
   String[] names
   Unsigned Integer[] values
)
```

setSIPMaxConnectionMemoryByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set maximum memory per connection. This is a location specific function, any action will operate on the specified location.

```
void setSIPMaxConnectionMemoryByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setSIPMode(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set which mode of operation the SIP virtual server should run in.

```
void setSIPMode(
    String[] names
    VirtualServer.SIPMode[] values
)
```

setSIPModeByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set which mode of operation the SIP virtual server should run in. This is a location specific function, any action will operate on the specified location.

```
void setSIPModeByLocation(
   String location
   String[] names
   VirtualServer.SIPMode[] values
)
```

setSIPPortRange(names, range) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the port range used for SIP data connections for each of the named virtual servers. This setting is only used when the SIP virtual server is using 'Full Gateway' mode.

```
void setSIPPortRange(
    String[] names
    VirtualServer.PortRange[] range
)
```

setSIPPortRangeByLocation(location, names, range) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the port range used for SIP data connections for each of the named virtual servers. This setting is only used when the SIP virtual server is using 'Full Gateway' mode. This is a location specific function, any action will operate on the specified location.

```
void setSIPPortRangeByLocation(
   String location
   String[] names
   VirtualServer.PortRange[] range
)
```

setSIPStreamingTimeout(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the time, in seconds, after which a UDP stream will timeout if it has not seen any data.

```
void setSIPStreamingTimeout(
    String[] names
    Unsigned Integer[] values
)
```

setSIPStreamingTimeoutByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the time, in seconds, after which a UDP stream will timeout if it has not seen any data. This is a location specific function, any action will operate on the specified location.

```
void setSIPStreamingTimeoutByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setSIPTimeoutMessages(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set send a timed out response to the client and CANCEL request to the server when a transaction times out.

```
void setSIPTimeoutMessages(
    String[] names
```

```
Boolean[] values
```

setSIPTimeoutMessagesByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set send a timed out response to the client and CANCEL request to the server when a transaction times out. This is a location specific function, any action will operate on the specified location.

```
void setSIPTimeoutMessagesByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setSSLCertificate(names, certs) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the name of the default SSL Certificate that is used for SSL decryption for each of the named virtual servers. This is the name of an item in the SSL Certificates Catalog. You must call this function to set an SSL Certificate before turning on SSL Decryption.

```
void setSSLCertificate(
    String[] names
    String[] certs
)
```

setSSLCertificateByLocation(location, names, certs) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the name of the default SSL Certificate that is used for SSL decryption for each of the named virtual servers. This is the name of an item in the SSL Certificates Catalog. You must call this function to set an SSL Certificate before turning on SSL Decryption. This is a location specific function, any action will operate on the specified location.

```
void setSSLCertificateByLocation(
   String location
   String[] names
   String[] certs
)
```

setSSLClientCertificateAuthorities(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the certificate authorities that are trusted for validating client certificates, for each of the named virtual servers.

```
void setSSLClientCertificateAuthorities(
   String[] names
   String[][] values
)
```

setSSLClientCertificateAuthoritiesByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the certificate authorities that are trusted for validating client certificates, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void setSSLClientCertificateAuthoritiesByLocation(
   String location
   String[] names
   String[][] values
)
```

setSSLClientCertificateHeaders(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should add HTTP headers to each request to show the data in the client certificate.

```
void setSSLClientCertificateHeaders(
   String[] names
   VirtualServer.SSLClientCertificateHeaders[] values
)
```

setSSLClientCertificateHeadersByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should add HTTP headers to each request to show the data in the client certificate. This is a location specific function, any action will operate on the specified location.

```
void setSSLClientCertificateHeadersByLocation(
    String location
```

```
String[] names
VirtualServer.SSLClientCertificateHeaders[] values
)
```

setSSLDecrypt(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Sets whether each of the named virtual servers should decrypt SSL traffic. This function will error unless an SSL Certificate has previously been set using setSSLCertificate.

```
void setSSLDecrypt(
    String[] names
    Boolean[] values
)
```

setSSLDecryptByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Sets whether each of the named virtual servers should decrypt SSL traffic. This function will error unless an SSL Certificate has previously been set using setSSLCertificate. This is a location specific function, any action will operate on the specified location.

```
void setSSLDecryptByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setSSLExpectStartTLS(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should upgrade SMTP connections to SSL using the STARTTLS command.

```
void setSSLExpectStartTLS(
    String[] names
    Boolean[] values
)
```

setSSLExpectStartTLSByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should upgrade SMTP connections to SSL using the STARTTLS command. This is a location specific function, any action will operate on the specified location.

```
void setSSLExpectStartTLSByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setSSLHeaders(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should add HTTP headers to each request to show SSL connection parameters.

```
void setSSLHeaders(
    String[] names
    Boolean[] values
)
```

setSSLHeadersByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should add HTTP headers to each request to show SSL connection parameters. This is a location specific function, any action will operate on the specified location.

```
void setSSLHeadersByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setSSLLogEnabled(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

This method is now obsolete. SSL logging is now done if LogConnectionFailures is enabled. Use VirtualServer.getLogConnectionFailures and VirtualServer.getLogConnection failures to control this configuration.

```
void setSSLLogEnabled(
    String[] names
    Boolean[] values
)
```

setSSLNeverExpiringClientCertificateAuthorities(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the CAs for which any client certificate they validate is considered valid even if the client certificate's expiration date has passed.

```
void setSSLNeverExpiringClientCertificateAuthorities(
    String[] names
    String[][] values
)
```

setSSLNeverExpiringClientCertificateAuthoritiesByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the CAs for which any client certificate they validate is considered valid even if the client certificate's expiration date has passed. This is a location specific function, any action will operate on the specified location.

```
void
setSSLNeverExpiringClientCertificateAuthoritiesByLoca
tion(
    String location
    String[] names
    String[][] values
)
```

setSSLOCSPDefaults(names, ssl_ocsp_issuers) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the default OCSP responder settings for all client certificates.

```
void setSSLOCSPDefaults(
    String[] names
    VirtualServer.SSLOCSPIssuer[] ssl_ocsp_issuers
)
```

setSSLOCSPDefaultsByLocation(location, names, ssl_ocsp_issuers) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the default OCSP responder settings for all client certificates. This is a location specific function, any action will operate on the specified location.

```
void setSSLOCSPDefaultsByLocation(
   String location
   String[] names
   VirtualServer.SSLOCSPIssuer[] ssl_ocsp_issuers
)
```

setSSLOCSPIssuers(names, ssl_ocsp_issuers) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Sets a list of mappings between Certificate Authorities and OCSP responder settings. Certificates issued by these authorities will be verified with OCSP using these settings.

```
void setSSLOCSPIssuers(
    String[] names
    VirtualServer.SSLOCSPIssuer[][] ssl_ocsp_issuers
)
```

setSSLOCSPIssuersByLocation(location, names, ssl_ocsp_issuers) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Sets a list of mappings between Certificate Authorities and OCSP responder settings. Certificates issued by these authorities will be verified with OCSP using these settings. This is a location specific function, any action will operate on the specified location.

```
void setSSLOCSPIssuersByLocation(
   String location
   String[] names
   VirtualServer.SSLOCSPIssuer[][] ssl_ocsp_issuers
)
```

setSSLOCSPMaxResponseAge(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the number of seconds for which an OCSP response is considered valid if it has not yet exceeded the time specified in the 'nextUpdate' field

```
void setSSLOCSPMaxResponseAge(
```

```
String[] names
Unsigned Integer[] values
)
```

setSSLOCSPMaxResponseAgeByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the number of seconds for which an OCSP response is considered valid if it has not yet exceeded the time specified in the 'nextUpdate' field This is a location specific function, any action will operate on the specified location.

```
void setSSLOCSPMaxResponseAgeByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setSSLOCSPTimeTolerance(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the number of seconds outside the permitted range for which the 'thisUpdate' and 'nextUpdate' fields of an OCSP response are still considered valid

```
void setSSLOCSPTimeTolerance(
    String[] names
    Unsigned Integer[] values
)
```

setSSLOCSPTimeToleranceByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the number of seconds outside the permitted range for which the 'thisUpdate' and 'nextUpdate' fields of an OCSP response are still considered valid This is a location specific function, any action will operate on the specified location.

```
void setSSLOCSPTimeToleranceByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setSSLOCSPTimeout(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the number of seconds after which OCSP requests will be timed out

```
void setSSLOCSPTimeout(
    String[] names
    Unsigned Integer[] values
)
```

setSSLOCSPTimeoutByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the number of seconds after which OCSP requests will be timed out This is a location specific function, any action will operate on the specified location.

```
void setSSLOCSPTimeoutByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setSSLPreferSSLv3(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether to prefer SSLv3 over TLS when the client appears to support both. SSLv3 is slightly faster, but some clients don't allow SSLv3 but still send the ClientHello inside SSLv2 or SSLv3 records.

```
void setSSLPreferSSLv3(
    String[] names
    Boolean[] values
)
```

setSSLPreferSSLv3ByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether to prefer SSLv3 over TLS when the client appears to support both. SSLv3 is slightly faster, but some clients don't allow SSLv3 but still send the ClientHello inside SSLv2 or SSLv3 records. This is a location specific function, any action will operate on the specified location.

```
void setSSLPreferSSLv3ByLocation(
    String location
    String[] names
```

```
Boolean[] values
```

setSSLRequestClientCertMode(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should request (or require) an identifying certificate from each client.

```
void setSSLRequestClientCertMode(
   String[] names
   VirtualServer.SSLRequestClientCertMode[] values
)
```

setSSLRequestClientCertModeByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should request (or require) an identifying certificate from each client. This is a location specific function, any action will operate on the specified location.

```
void setSSLRequestClientCertModeByLocation(
   String location
   String[] names
   VirtualServer.SSLRequestClientCertMode[] values
)
```

setSSLSendCloseAlerts(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should send a close alert when initiating SSL socket disconnections.

```
void setSSLSendCloseAlerts(
    String[] names
    Boolean[] values
)
```

setSSLSendCloseAlertsByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should send a close alert when initiating SSL socket disconnections. This is a location specific function, any action will operate on the specified location.

```
void setSSLSendCloseAlertsByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setSSLTrustMagic(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should decode extra information on the true origin of an SSL connection. This information is prefixed onto an incoming SSL connection from another traffic manager.

```
void setSSLTrustMagic(
    String[] names
    Boolean[] values
)
```

setSSLTrustMagicByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should decode extra information on the true origin of an SSL connection. This information is prefixed onto an incoming SSL connection from another traffic manager. This is a location specific function, any action will operate on the specified location.

```
void setSSLTrustMagicByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setSSLUseOCSP(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether or not the traffic manager should use OCSP to check the revocation status of client certificates

```
void setSSLUseOCSP(
    String[] names
    Boolean[] values
)
```

setSSLUseOCSPByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether or not the traffic manager should use OCSP to check the revocation status of client certificates This is a location specific function, any action will operate on the specified location.

```
void setSSLUseOCSPByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setServerfirstBanner(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the banner that each of the named virtual servers sends to clients for server-first protocols such as POP, SMTP and IMAP.

```
void setServerfirstBanner(
    String[] names
    String[] values
)
```

setServerfirstBannerByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the banner that each of the named virtual servers sends to clients for server-first protocols such as POP, SMTP and IMAP. This is a location specific function, any action will operate on the specified location.

```
void setServerfirstBannerByLocation(
   String location
   String[] names
   String[] values
)
```

setServiceLevelMonitoring(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the Service Level Monitoring class that each of the named virtual servers uses.

```
void setServiceLevelMonitoring(
```

```
String[] names
String[] values
)
```

setServiceLevelMonitoringByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the Service Level Monitoring class that each of the named virtual servers uses. This is a location specific function, any action will operate on the specified location.

```
void setServiceLevelMonitoringByLocation(
   String location
   String[] names
   String[] values
)
```

setSipTransactionTimeout(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the time after which an incomplete transaction should be discarded, in seconds, for each of the named virtual servers.

```
void setSipTransactionTimeout(
    String[] names
    Unsigned Integer[] values
)
```

setSipTransactionTimeoutByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the time after which an incomplete transaction should be discarded, in seconds, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void setSipTransactionTimeoutByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setTimeout(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the time to wait for data on an already established connection, in seconds, for each of the named virtual servers.

```
void setTimeout(
   String[] names
   Unsigned Integer[] values
)
```

setTimeoutByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the time to wait for data on an already established connection, in seconds, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void setTimeoutByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setUDPResponseDatagramsExpected(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the expected number of UDP datagrams in the response, for each of the named virtual servers. For simple request/response protocols a value of '1' should be used. If set to -1, the connection will not be discarded until the udp_timeout is reached.

```
void setUDPResponseDatagramsExpected(
   String[] names
   Integer[] values
)
```

setUDPResponseDatagramsExpectedByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the expected number of UDP datagrams in the response, for each of the named virtual servers. For simple request/response protocols a value of '1' should be used. If set to -1, the connection will not be discarded until the udp_timeout is reached. This is a location specific function, any action will operate on the specified location.

```
void setUDPResponseDatagramsExpectedByLocation(
```

```
String location
String[] names
Integer[] values
```

setUDPTimeout(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the time after which an idle UDP connection should be discarded and resources reclaimed, in seconds, for each of the named virtual servers.

```
void setUDPTimeout(
    String[] names
    Unsigned Integer[] values
)
```

setUDPTimeoutByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the time after which an idle UDP connection should be discarded and resources reclaimed, in seconds, for each of the named virtual servers. This is a location specific function, any action will operate on the specified location.

```
void setUDPTimeoutByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setUseNagle(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether Nagle's algorithm should be used for TCP connections.

```
void setUseNagle(
    String[] names
    Boolean[] values
)
```

setUseNagleByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether Nagle's algorithm should be used for TCP connections. This is a location specific function, any action will operate on the specified location.

```
void setUseNagleByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setWebcacheControlOut(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the Cache-Control header that should be sent with cached HTTP responses.

```
void setWebcacheControlOut(
    String[] names
    String[] values
)
```

setWebcacheControlOutByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the Cache-Control header that should be sent with cached HTTP responses. This is a location specific function, any action will operate on the specified location.

```
void setWebcacheControlOutByLocation(
   String location
   String[] names
   String[] values
)
```

setWebcacheEnabled(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should attempt to cache web server responses.

```
void setWebcacheEnabled(
   String[] names
   Boolean[] values
```

)

setWebcacheEnabledByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set whether each of the named virtual servers should attempt to cache web server responses. This is a location specific function, any action will operate on the specified location.

```
void setWebcacheEnabledByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setWebcacheErrorpageTime(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the time periods that each of the named virtual servers should cache error pages for.

```
void setWebcacheErrorpageTime(
    String[] names
    Unsigned Integer[] values
)
```

setWebcacheErrorpageTimeByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the time periods that each of the named virtual servers should cache error pages for. This is a location specific function, any action will operate on the specified location.

```
void setWebcacheErrorpageTimeByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setWebcacheRefreshTime(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the time periods that each of the named virtual servers should consider re-fetching cached pages in.

```
void setWebcacheRefreshTime(
```

VirtualServer Function Reference

```
String[] names
Unsigned Integer[] values
)
```

setWebcacheRefreshTimeByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the time periods that each of the named virtual servers should consider re-fetching cached pages in. This is a location specific function, any action will operate on the specified location.

```
void setWebcacheRefreshTimeByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setWebcacheTime(names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the time periods that each of the named virtual servers should cache web pages for.

```
void setWebcacheTime(
    String[] names
    Unsigned Integer[] values
)
```

setWebcacheTimeByLocation(location, names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the time periods that each of the named virtual servers should cache web pages for. This is a location specific function, any action will operate on the specified location.

```
void setWebcacheTimeByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

Function Reference VirtualServer

Structures

VirtualServer.BasicInfo

This structure contains the basic information for a virtual server. It is used when creating a server, or modifying the port, protocol or default pool of a server.

```
struct VirtualServer.BasicInfo {
    # The port to listen for incoming connections on.
    Integer port;

# The protocol that this virtual server handles.
    VirtualServer.Protocol protocol;

# The default pool that traffic to this virtual server will go
    # to.
    String default_pool;
}
```

VirtualServer.FTPPortRange

This structure contains the range of ports that FTP data connections use.

```
struct VirtualServer.FTPPortRange {
    # The lower bound of the port range for FTP data
connections.
    Integer low;

    # The upper bound of the port range for FTP data
connections.
    Integer high;
}
```

VirtualServer.PortRange

This structure contains the range of ports.

```
struct VirtualServer.PortRange {
    # The lower bound of the port range.
    Integer low;
```

VirtualServer Function Reference

```
# The upper bound of the port range.
Integer high;
}
```

VirtualServer.RegexReplacement

This structure contains a regex and a replacement string.

```
struct VirtualServer.RegexReplacement {
    # The regular expression used to match against.
    String regex;

# The replacement string if the regular expression matches.

# Parameters $1-$9 can be used to represent bracketed parts of

# the regular expression.

String replacement;
}
```

VirtualServer.Rule

This structure contains the information on how a rule is assigned to a virtual server.

```
struct VirtualServer.Rule {
    # The name of the rule.
    String name;

# Whether the rule is enabled or not.
    Boolean enabled;

# Whether the rule runs on every request/response, or just the
    # first
    VirtualServer.RuleRunFlag run_frequency;
}
```

Function Reference VirtualServer

VirtualServer.SSLOCSPIssuer

This object represents a mapping between a Certificate Authority (this is the name of an item in the Certificate Authorities Catalog) and configuration for an OCSP responder. Certificates issued by the Certificate Authority will use these OCSP responder settings.

```
struct VirtualServer.SSLOCSPIssuer {
   # The Certificate Authority for whic these
settings apply.
   # This is the name of an item in the Certificate
Authorities
   # Catalog.
   String ca;
   # The URL of the OCSP responder that should be
used to check
   # the revocation status of certificates issued by
the
   # Certificate Authority.
   String url;
   # Is OCSP required for certificates signed by this
CA?
  VirtualServer.SSLOCSPCheck required;
   # If set to true the Authority Information Access
X509
   # extension will be used to determine the OCSP
server's URL
   Boolean aia;
   # Should an OCSP nonce be added to each request to
protect
   # against replay attacks. Not all OCSP servers
support nonces.
   VirtualServer.SSLOCSPNonce nonce;
   # Should we sign OCSP requests?
   VirtualServer.SSLOCSPSignMode sign mode;
```

VirtualServer Function Reference

```
# The key pair used to sign OCSP requests. If not
set OCSP

# requests will not be signed. Must be an entry in
the SSL

# Certificates Catalog.

String signer;

# The expected certificate that the OCSP responder
should

# provide. Must be in the Certificate Authority
catalog.

String responder_cert;
}
```

VirtualServer.SSLSite

This object represents a mapping between a destination address and an SSL certificate (this is the name of an item in the SSL Certificates Catalog). Clients connecting to the SSL Site's address will be sent the associated certificate.

```
struct VirtualServer.SSLSite {
    # The destination address that this site handles.
    String dest_address;

# The certificate that will be sent when clients connect to

# the destination address. This is a certificate name from the

# SSL Certificates Catalog.
    String certificate;
}
```

Enumerations

VirtualServer.CookieDomainRewriteMode

```
enum VirtualServer.CookieDomainRewriteMode {
    # Do not rewrite the domain
    no rewrite,
```

Function Reference VirtualServer

```
# Rewrite the domain to the host header of the
request
set_to_request,

# Rewrite the domain to the named domain value
set_to_named
}
```

VirtualServer.CookieSecureFlagRewriteMode

```
enum VirtualServer.CookieSecureFlagRewriteMode {
    # Do not modify the 'secure' tag
    no_modify,

# Set the 'secure' tag
    set_secure,

# Unset the 'secure' tag
    unset_secure
}
```

VirtualServer.LocationDefaultRewriteMode

```
enum VirtualServer.LocationDefaultRewriteMode {
    # Nothing;
    never,

    # Rewrite the hostname to the request's "Host"
header, and
    # rewrite the protocol and port if necessary;
    always,

# Do not rewrite the hostname. Rewrite the
protocol and port

# if the hostname matches the request's "Host"
header.
```

VirtualServer Function Reference

```
if_host_matches
}
```

VirtualServer.Protocol

```
enum VirtualServer.Protocol {
   # HTTP
   http,
   # FTP
   ftp,
   # IMAPv2
   imapv2,
   # IMAPv3
   imapv3,
   # IMAPv4
   imapv4,
   # POP3
   pop3,
   # SMTP
   smtp,
   # LDAP
   ldap,
   # Telnet
   telnet,
   # SSL
```

Function Reference VirtualServer

```
ssl,
# SSL (HTTPS)
https,
# SSL (IMAPS)
imaps,
# SSL (POP3S)
pop3s,
# SSL (LDAPS)
ldaps,
# UDP - Streaming
udpstreaming,
# UDP
udp,
# DNS (UDP)
dns,
# DNS (TCP)
dns_tcp,
# SIP (UDP)
sipudp,
# SIP (TCP)
siptcp,
# RTSP
```

VirtualServer Function Reference

```
# Generic server first
server_first,

# Generic client first
client_first,

# Generic streaming
stream
}
```

VirtualServer.RuleRunFlag

This enumeration defines the run flags for a particular rule.

```
enum VirtualServer.RuleRunFlag {
    # Run on every request or response.
    run_every,

# Run only on the first request or response.
    only_first
}
```

VirtualServer.SIPDangerousRequestMode

```
enum VirtualServer.SIPDangerousRequestMode {
    # Send the request to a back-end node
    node,

# Send a 403 Forbidden response to the client
    forbid,

# Forward the request to its target URI
(dangerous)
    forward
```

Function Reference VirtualServer

}

VirtualServer.SIPMode

```
enum VirtualServer.SIPMode {
    # SIP Routing
    route,

# SIP Gateway
    sipgw,

# Full Gateway
    fullgw
}
```

VirtualServer.SSLClientCertificateHeaders

```
enum VirtualServer.SSLClientCertificateHeaders {
    # No data
    none,

# Certificate fields
    simple,

# Certificate fields and certificate text
    all
}
```

VirtualServer.SSLOCSPCheck

Different modes of OCSP checking for an issuer.

```
enum VirtualServer.SSLOCSPCheck {
    # Do not perform an OCSP check
    none,
```

VirtualServer Function Reference

```
# If an OCSP URL can be determined, perform an
OCSP check.

optional,

# If an OCSP URL can be determined, perform an
OCSP check. If

# not reject the connection.

strict
}
```

VirtualServer.SSLOCSPNonce

Should we include nonces in requests and how strict should we be when validating the response

```
enum VirtualServer.SSLOCSPNonce {
    # Do not use the nonce extension in OCSP requests,
ignore any
    # nonces in the response.
    off,

    # Use the nonce extension in requests. If the
response
    # contains a nonce validate it is correct.
    on,

    # Use the nonce extension in requests. The
response must
    # contain the correct nonce, otherwise it is
rejected.
    strict
}
```

VirtualServer.SSLOCSPSignMode

The diferent modes for OCSP request signing

```
enum VirtualServer.SSLOCSPSignMode {
    # Do not sign OCSP requests
    none,
```

```
# Use default OCSP settings for signing requests
use_default,

# Use a specific catalog certificate to sign
requests
   sign
}
```

VirtualServer.SSLRequestClientCertMode

```
enum VirtualServer.SSLRequestClientCertMode {
    # Do not request a client certificate
    dont_request,

# Request, but do not require a client certificate
    request,

# Require a client certificate
    require
}
```

Pool

URI: http://soap.zeus.com/zxtm/1.0/Pool/

The Pool interface allows management of Pool objects. Using this interface, you can create, delete and rename pool objects, and manage their configuration.

Methods

addAutoScaledPool(names, nodes) throws ObjectAlreadyExists, InvalidObjectName, InvalidInput, DeploymentError

Add each of the named auto-scaled pools, using the node lists for each. The node lists can be empty

```
void addAutoScaledPool(
   String[] names
   String[][] nodes
```

)

addDrainingNodes(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Add nodes to the lists of draining nodes, for each of the named pools.

```
void addDrainingNodes(
    String[] names
    String[][] values
)
```

addDrainingNodesByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Add nodes to the lists of draining nodes, for each of the named pools. This is a location specific function, any action will operate on the specified location.

```
void addDrainingNodesByLocation(
   String location
   String[] names
   String[][] values
)
```

addMonitors(names, values) throws ObjectDoesNotExist, InvalidInput, InvalidOperation, DeploymentError

Add monitors to each of the named pools.

```
void addMonitors(
    String[] names
    String[][] values
)
```

addMonitorsByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, InvalidOperation, DeploymentError

Add monitors to each of the named pools. This is a location specific function, any action will operate on the specified location.

```
void addMonitorsByLocation(
    String location
```

```
String[] names
String[][] values
)
```

addNodes(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Add nodes to each of the named pools.

```
void addNodes(
    String[] names
    String[][] values
)
```

addNodesByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Add nodes to each of the named pools. This is a location specific function, any action will operate on the specified location.

```
void addNodesByLocation(
   String location
   String[] names
   String[][] values
)
```

addPool(names, nodes) throws ObjectAlreadyExists, InvalidObjectName, InvalidInput, DeploymentError

Add each of the named pools, using the node lists for each.

```
void addPool(
   String[] names
   String[][] nodes
)
```

copyPool(names, new_names) throws ObjectAlreadyExists, ObjectDoesNotExist, InvalidObjectName, DeploymentError

Copy each of the named pools.

```
void copyPool(
```

```
String[] names
String[] new_names
)
```

deletePool(names) throws ObjectInUse, ObjectDoesNotExist, DeploymentError

Delete each of the named pools.

```
void deletePool(
    String[] names
)
```

disableNodes(names, nodes) throws ObjectDoesNotExist, InvalidInput, InvalidOperation, DeploymentError

For each of the named pools, disable the specified nodes in the pool.

```
void disableNodes(
    String[] names
    String[][] nodes
)
```

disableNodesByLocation(location, names, nodes) throws ObjectDoesNotExist, InvalidInput, InvalidOperation, DeploymentError

For each of the named pools, disable the specified nodes in the pool. This is a location specific function, any action will operate on the specified location.

```
void disableNodesByLocation(
    String location
    String[] names
    String[][] nodes
)
```

enableNodes(names, nodes) throws ObjectDoesNotExist, InvalidInput, InvalidOperation, DeploymentError

For each of the named pools, enable the specified nodes that are disabled in the pool.

```
void enableNodes(
    String[] names
```

```
String[][] nodes
)
```

enableNodesByLocation(location, names, nodes) throws ObjectDoesNotExist, InvalidInput, InvalidOperation, DeploymentError

For each of the named pools, enable the specified nodes that are disabled in the pool. This is a location specific function, any action will operate on the specified location.

```
void enableNodesByLocation(
    String location
    String[] names
    String[][] nodes
)
```

getAutoscaleCloudcredentials(names) throws ObjectDoesNotExist

Get the cloud credentials for this auto-scaled pool

```
String[] getAutoscaleCloudcredentials(
    String[] names
)
```

getAutoscaleCloudcredentialsByLocation(location, names) throws ObjectDoesNotExist

Get the cloud credentials for this auto-scaled pool This is a location specific function, any action will operate on the specified location.

```
String[] getAutoscaleCloudcredentialsByLocation(
   String location
   String[] names
)
```

getAutoscaleCluster(names) throws ObjectDoesNotExist

Get The ESX host or ESX cluster name to put the new virtual machine instances on.

```
String[] getAutoscaleCluster(
    String[] names
)
```

getAutoscaleClusterByLocation(location, names) throws ObjectDoesNotExist

Get The ESX host or ESX cluster name to put the new virtual machine instances on. This is a location specific function, any action will operate on the specified location.

```
String[] getAutoscaleClusterByLocation(
    String location
    String[] names
)
```

getAutoscaleDatacenter(names) throws ObjectDoesNotExist

Get The name of the logical datacenter on the vCenter server

```
String[] getAutoscaleDatacenter(
    String[] names
)
```

getAutoscaleDatacenterByLocation(location, names) throws ObjectDoesNotExist

Get The name of the logical datacenter on the vCenter server This is a location specific function, any action will operate on the specified location.

```
String[] getAutoscaleDatacenterByLocation(
    String location
    String[] names
)
```

getAutoscaleDatastore(names) throws ObjectDoesNotExist

Get The name of the datastore to be used by the newly created virtual machine.

```
String[] getAutoscaleDatastore(
    String[] names
)
```

getAutoscaleDatastoreByLocation(location, names) throws ObjectDoesNotExist

Get The name of the datastore to be used by the newly created virtual machine. This is a location specific function, any action will operate on the specified location.

```
String[] getAutoscaleDatastoreByLocation(
```

```
String location
String[] names
)
```

getAutoscaleEnabled(names) throws ObjectDoesNotExist

Get whether this pool uses auto-scaling.

```
Boolean[] getAutoscaleEnabled(
    String[] names
)
```

getAutoscaleEnabledByLocation(location, names) throws ObjectDoesNotExist

Get whether this pool uses auto-scaling. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getAutoscaleEnabledByLocation(
    String location
    String[] names
)
```

getAutoscaleExternal(names) throws ObjectDoesNotExist

Get whether autoscaling is handled externally or internally

```
Boolean[] getAutoscaleExternal(
    String[] names
)
```

getAutoscaleExternalByLocation(location, names) throws ObjectDoesNotExist

Get whether autoscaling is handled externally or internally This is a location specific function, any action will operate on the specified location.

```
Boolean[] getAutoscaleExternalByLocation(
    String location
    String[] names
)
```

getAutoscaleHysteresis(names) throws ObjectDoesNotExist

Get the hysteresis period for an auto-scaled pool

```
Unsigned Integer[] getAutoscaleHysteresis(
    String[] names
)
```

getAutoscaleHysteresisByLocation(location, names) throws ObjectDoesNotExist

Get the hysteresis period for an auto-scaled pool This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getAutoscaleHysteresisByLocation(
    String location
    String[] names
)
```

getAutoscaleImageid(names) throws ObjectDoesNotExist

Get the image identifier

```
String[] getAutoscaleImageid(
    String[] names
)
```

getAutoscaleImageidByLocation(location, names) throws ObjectDoesNotExist

Get the image identifier This is a location specific function, any action will operate on the specified location.

```
String[] getAutoscaleImageidByLocation(
    String location
    String[] names
)
```

getAutoscalelpstouse(names) throws ObjectDoesNotExist

Get whether to use the public or private IPs

```
Pool.AutoscaleIpstouse[] getAutoscaleIpstouse(
    String[] names
```

)

getAutoscaleIpstouseByLocation(location, names) throws ObjectDoesNotExist

Get whether to use the public or private IPs This is a location specific function, any action will operate on the specified location.

```
Pool.AutoscaleIpstouse[]
getAutoscaleIpstouseByLocation(
    String location
    String[] names
)
```

getAutoscaleLastnodeldletime(names) throws ObjectDoesNotExist

Get the idle time of the last node in an autoscaled pool before it can be destroyed

```
Unsigned Integer[] getAutoscaleLastnodeIdletime(
    String[] names
)
```

getAutoscaleLastnodeldletimeByLocation(location, names) throws ObjectDoesNotExist

Get the idle time of the last node in an autoscaled pool before it can be destroyed This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[]
getAutoscaleLastnodeIdletimeByLocation(
    String location
    String[] names
)
```

getAutoscaleMaxNodes(names) throws ObjectDoesNotExist

Get the maximum number of nodes in an auto-scaled pool

```
Unsigned Integer[] getAutoscaleMaxNodes(
    String[] names
)
```

getAutoscaleMaxNodesByLocation(location, names) throws ObjectDoesNotExist

Get the maximum number of nodes in an auto-scaled pool This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getAutoscaleMaxNodesByLocation(
    String location
    String[] names
)
```

getAutoscaleMinNodes(names) throws ObjectDoesNotExist

Get the minimum number of nodes in an auto-scaled pool

```
Unsigned Integer[] getAutoscaleMinNodes(
    String[] names
)
```

getAutoscaleMinNodesByLocation(location, names) throws ObjectDoesNotExist

Get the minimum number of nodes in an auto-scaled pool This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getAutoscaleMinNodesByLocation(
    String location
    String[] names
)
```

getAutoscaleName(names) throws ObjectDoesNotExist

Get the node name prefix for this auto-scaled pool

```
String[] getAutoscaleName(
    String[] names
)
```

getAutoscaleNameByLocation(location, names) throws ObjectDoesNotExist

Get the node name prefix for this auto-scaled pool This is a location specific function, any action will operate on the specified location.

```
String[] getAutoscaleNameByLocation(
```

```
String location
String[] names
)
```

getAutoscalePort(names) throws ObjectDoesNotExist

Get the port number for this auto-scaled pool

```
Unsigned Integer[] getAutoscalePort(
    String[] names
)
```

getAutoscalePortByLocation(location, names) throws ObjectDoesNotExist

Get the port number for this auto-scaled pool This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getAutoscalePortByLocation(
    String location
    String[] names
)
```

getAutoscaleRefractory(names) throws ObjectDoesNotExist

Get the refractory period for an auto-scaled pool

```
Unsigned Integer[] getAutoscaleRefractory(
    String[] names
)
```

getAutoscaleRefractoryByLocation(location, names) throws ObjectDoesNotExist

Get the refractory period for an auto-scaled pool This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getAutoscaleRefractoryByLocation(
    String location
    String[] names
)
```

getAutoscaleResponseTime(names) throws ObjectDoesNotExist

Get the expected node response time in milliseconds

```
Unsigned Integer[] getAutoscaleResponseTime(
    String[] names
)
```

getAutoscaleResponseTimeByLocation(location, names) throws ObjectDoesNotExist

Get the expected node response time in milliseconds This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[]
getAutoscaleResponseTimeByLocation(
    String location
    String[] names
)
```

getAutoscaleScaledownLevel(names) throws ObjectDoesNotExist

Get the threshold of conforming requests for scaling down

```
Unsigned Integer[] getAutoscaleScaledownLevel(
    String[] names
)
```

getAutoscaleScaledownLevelByLocation(location, names) throws ObjectDoesNotExist

Get the threshold of conforming requests for scaling down This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[]
getAutoscaleScaledownLevelByLocation(
    String location
    String[] names
)
```

getAutoscaleScaleupLevel(names) throws ObjectDoesNotExist

Get the acceptable lower percentage of conforming requests

```
Unsigned Integer[] getAutoscaleScaleupLevel(
    String[] names
)
```

getAutoscaleScaleupLevelByLocation(location, names) throws ObjectDoesNotExist

Get the acceptable lower percentage of conforming requests This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[]
getAutoscaleScaleupLevelByLocation(
    String location
    String[] names
)
```

getAutoscaleSizeid(names) throws ObjectDoesNotExist

Get the size identifier

```
String[] getAutoscaleSizeid(
    String[] names
)
```

getAutoscaleSizeidByLocation(location, names) throws ObjectDoesNotExist

Get the size identifier This is a location specific function, any action will operate on the specified location.

```
String[] getAutoscaleSizeidByLocation(
    String location
    String[] names
)
```

getBandwidthClass(names) throws ObjectDoesNotExist

Get the Bandwidth Classes that each of the named pools uses.

```
String[] getBandwidthClass(
    String[] names
)
```

getBandwidthClassByLocation(location, names) throws ObjectDoesNotExist

Get the Bandwidth Classes that each of the named pools uses. This is a location specific function, any action will operate on the specified location.

```
String[] getBandwidthClassByLocation(
    String location
    String[] names
)
```

getDisabledNodes(names) throws ObjectDoesNotExist

For each of the named pools, get the disabled nodes in the pool.

```
String[][] getDisabledNodes(
    String[] names
)
```

getDisabledNodesByLocation(location, names) throws ObjectDoesNotExist

For each of the named pools, get the disabled nodes in the pool. This is a location specific function, any action will operate on the specified location.

```
String[][] getDisabledNodesByLocation(
    String location
    String[] names
)
```

getDrainingNodes(names) throws ObjectDoesNotExist

Get the lists of draining nodes for each of the named pools.

```
String[][] getDrainingNodes(
    String[] names
)
```

getDrainingNodesByLocation(location, names) throws ObjectDoesNotExist

Get the lists of draining nodes for each of the named pools. This is a location specific function, any action will operate on the specified location.

```
String[][] getDrainingNodesByLocation(
    String location
```

```
String[] names
)
```

getErrorFile(names) throws ObjectDoesNotExist

This method is now obsolete and is replaced by VirtualServer.getErrorFile.

```
String[] getErrorFile(
    String[] names
)
```

getFTPSupportRfc2428(names) throws ObjectDoesNotExist

Get whether backend IPv4 nodes understand the FTP EPRT and EPSV commands.

```
Boolean[] getFTPSupportRfc2428(
    String[] names
)
```

getFTPSupportRfc2428ByLocation(location, names) throws ObjectDoesNotExist

Get whether backend IPv4 nodes understand the FTP EPRT and EPSV commands. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getFTPSupportRfc2428ByLocation(
    String location
    String[] names
)
```

getFailpool(names) throws ObjectDoesNotExist

Get the pool to use when all nodes in a pool fail, for each of the named pools.

```
String[] getFailpool(
    String[] names
)
```

getFailpoolByLocation(location, names) throws ObjectDoesNotExist

Get the pool to use when all nodes in a pool fail, for each of the named pools. This is a location specific function, any action will operate on the specified location.

```
String[] getFailpoolByLocation(
    String location
    String[] names
)
```

getKeepalive(names) throws ObjectDoesNotExist

Get whether each of the named pools should maintain HTTP keepalive connections to the nodes.

```
Boolean[] getKeepalive(
    String[] names
)
```

getKeepaliveByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named pools should maintain HTTP keepalive connections to the nodes. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getKeepaliveByLocation(
   String location
   String[] names
)
```

getKeepaliveNonIdempotent(names) throws ObjectDoesNotExist

Get whether each of the named pools should maintain HTTP keepalive connections to the nodes for non-idempotent requests.

```
Boolean[] getKeepaliveNonIdempotent(
    String[] names
)
```

getKeepaliveNonIdempotentByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named pools should maintain HTTP keepalive connections to the nodes for non-idempotent requests. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getKeepaliveNonIdempotentByLocation(
    String location
    String[] names
```

)

getLoadBalancingAlgorithm(names) throws ObjectDoesNotExist

Get the load balancing algorithms that each of the named pools uses.

```
Pool.LoadBalancingAlgorithm[]
getLoadBalancingAlgorithm(
    String[] names
)
```

getLoadBalancingAlgorithmByLocation(location, names) throws ObjectDoesNotExist

Get the load balancing algorithms that each of the named pools uses. This is a location specific function, any action will operate on the specified location.

```
Pool.LoadBalancingAlgorithm[]
getLoadBalancingAlgorithmByLocation(
    String location
    String[] names
)
```

getMaxConnectTime(names) throws ObjectDoesNotExist

Get the times that each of the named pools should wait for a connection to establish to a node before trying another node, in seconds.

```
Unsigned Integer[] getMaxConnectTime(
    String[] names
)
```

getMaxConnectTimeByLocation(location, names) throws ObjectDoesNotExist

Get the times that each of the named pools should wait for a connection to establish to a node before trying another node, in seconds. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getMaxConnectTimeByLocation(
    String location
    String[] names
)
```

getMaxConnectionsPernode(names) throws ObjectDoesNotExist

Get is the maximum number of conncurrent connections allowed to each node in the pool per machine.

```
Unsigned Integer[] getMaxConnectionsPernode(
    String[] names
)
```

getMaxConnectionsPernodeByLocation(location, names) throws ObjectDoesNotExist

Get is the maximum number of conncurrent connections allowed to each node in the pool per machine. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[]
getMaxConnectionsPernodeByLocation(
    String location
    String[] names
)
```

getMaxIdleConnectionsPerNode(names) throws ObjectDoesNotExist

Get the maximum numbers of unused HTTP keepalive connections that each of the named pools should maintain to an individual node.

```
Unsigned Integer[] getMaxIdleConnectionsPerNode(
    String[] names
)
```

getMaxIdleConnectionsPerNodeByLocation(location, names) throws ObjectDoesNotExist

Get the maximum numbers of unused HTTP keepalive connections that each of the named pools should maintain to an individual node. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[]
getMaxIdleConnectionsPerNodeByLocation(
    String location
    String[] names
)
```

getMaxKeepalivesPerNode(names) throws ObjectDoesNotExist

getMaxKeepalivesPerNode is deprecated, please use getMaxIdleConnectionsPerNode instead.

```
Unsigned Integer[] getMaxKeepalivesPerNode(
    String[] names
)
```

getMaxKeepalivesPerNodeByLocation(location, names) throws ObjectDoesNotExist

getMaxKeepalivesPerNode is deprecated, please use getMaxIdleConnectionsPerNode instead. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getMaxKeepalivesPerNodeByLocation(
    String location
    String[] names
)
```

getMaxQueueSize(names) throws ObjectDoesNotExist

Get is the maximum number of connections that can be queued due to connection limits.

```
Unsigned Integer[] getMaxQueueSize(
    String[] names
)
```

getMaxQueueSizeByLocation(location, names) throws ObjectDoesNotExist

Get is the maximum number of connections that can be queued due to connection limits. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getMaxQueueSizeByLocation(
    String location
    String[] names
)
```

getMaxReplyTime(names) throws ObjectDoesNotExist

Get the time that each of the named pools should wait for a response from a node before either discarding the request or trying another node, in seconds (retryable requests only).

```
Unsigned Integer[] getMaxReplyTime(
    String[] names
```

)

getMaxReplyTimeByLocation(location, names) throws ObjectDoesNotExist

Get the time that each of the named pools should wait for a response from a node before either discarding the request or trying another node, in seconds (retryable requests only). This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getMaxReplyTimeByLocation(
    String location
    String[] names
)
```

getMonitors(names) throws ObjectDoesNotExist

Get the list of all monitors.

```
String[][] getMonitors(
    String[] names
)
```

getMonitorsByLocation(location, names) throws ObjectDoesNotExist

Get the list of all monitors. This is a location specific function, any action will operate on the specified location.

```
String[][] getMonitorsByLocation(
    String location
    String[] names
)
```

getNodeConnClose(names) throws ObjectDoesNotExist

Get whether all connections that have been sent to a node are closed when that node is marked as dead.

```
Boolean[] getNodeConnClose(
    String[] names
)
```

getNodeConnCloseByLocation(location, names) throws ObjectDoesNotExist

Get whether all connections that have been sent to a node are closed when that node is marked as dead. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getNodeConnCloseByLocation(
    String location
    String[] names
)
```

getNodeConnectionAttempts(names) throws ObjectDoesNotExist

Get the number of times your traffic manager should try and connect to a node before registering it as failed when passive monitoring is enabled.

```
Unsigned Integer[] getNodeConnectionAttempts(
    String[] names
)
```

getNodeConnectionAttemptsByLocation(location, names) throws ObjectDoesNotExist

Get the number of times your traffic manager should try and connect to a node before registering it as failed when passive monitoring is enabled. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[]
getNodeConnectionAttemptsByLocation(
    String location
    String[] names
)
```

getNodeFailTime(names) throws ObjectDoesNotExist

Get the length of time a failed node should be isolated for before testing it with new traffic, in seconds

```
Unsigned Integer[] getNodeFailTime(
    String[] names
)
```

getNodeFailTimeByLocation(location, names) throws ObjectDoesNotExist

Get the length of time a failed node should be isolated for before testing it with new traffic, in seconds This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getNodeFailTimeByLocation(
    String location
    String[] names
)
```

getNodeUseNagle(names) throws ObjectDoesNotExist

Get whether Nagle's algorithm should be used for TCP connections to the back-end nodes.

```
Boolean[] getNodeUseNagle(
    String[] names
)
```

getNodeUseNagleByLocation(location, names) throws ObjectDoesNotExist

Get whether Nagle's algorithm should be used for TCP connections to the back-end nodes. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getNodeUseNagleByLocation(
   String location
   String[] names
)
```

getNodes(names) throws ObjectDoesNotExist

Get the lists of nodes for each of the named pools.

```
String[][] getNodes(
    String[] names
)
```

getNodesByLocation(location, names) throws ObjectDoesNotExist

Get the lists of nodes for each of the named pools. This is a location specific function, any action will operate on the specified location.

```
String[][] getNodesByLocation(
    String location
    String[] names
)
```

getNodesConnectionCounts(nodes)

Get the number of active connections to each of the specified nodes.

```
Integer[] getNodesConnectionCounts(
    String[] nodes
)
```

getNodesLastUsed(nodes)

Get the number of seconds since each of the specified nodes was last used.

```
Integer[] getNodesLastUsed(
    String[] nodes
)
```

getNodesPriorityValue(names, nodes) throws ObjectDoesNotExist

For each of the named pools, get the priority values for the named nodes in each pool.

```
Pool.PriorityValueDefinition[][]
getNodesPriorityValue(
    String[] names
    String[][] nodes
)
```

getNodesPriorityValueByLocation(location, names, nodes) throws ObjectDoesNotExist

For each of the named pools, get the priority values for the named nodes in each pool. This is a location specific function, any action will operate on the specified location.

```
Pool.PriorityValueDefinition[][]
getNodesPriorityValueByLocation(
    String location
    String[] names
    String[][] nodes
)
```

getNodesWeightings(names, nodes) throws ObjectDoesNotExist

For each of the named pools, get the weighting values for the specified nodes in this pool.

```
Pool.WeightingsDefinition[][] getNodesWeightings(
```

```
String[] names
String[][] nodes
)
```

getNodesWeightingsByLocation(location, names, nodes) throws ObjectDoesNotExist

For each of the named pools, get the weighting values for the specified nodes in this pool. This is a location specific function, any action will operate on the specified location.

```
Pool.WeightingsDefinition[][]
getNodesWeightingsByLocation(
    String location
    String[] names
    String[][] nodes
)
```

getNote(names) throws ObjectDoesNotExist

Get the note for each of the named pools.

```
String[] getNote(
    String[] names
)
```

getPassiveMonitoring(names) throws ObjectDoesNotExist

Get whether this pool uses passive monitoring.

```
Boolean[] getPassiveMonitoring(
    String[] names
)
```

getPassiveMonitoringByLocation(location, names) throws ObjectDoesNotExist

Get whether this pool uses passive monitoring. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getPassiveMonitoringByLocation(
    String location
    String[] names
```

)

getPersistence(names) throws ObjectDoesNotExist

Get the default Session Persistence classes that each of the named pools uses.

```
String[] getPersistence(
    String[] names
)
```

getPersistenceByLocation(location, names) throws ObjectDoesNotExist

Get the default Session Persistence classes that each of the named pools uses. This is a location specific function, any action will operate on the specified location.

```
String[] getPersistenceByLocation(
   String location
   String[] names
)
```

getPoolNames()

Get the names of all of the configured pools.

```
String[] getPoolNames()
```

getPriorityEnabled(names) throws ObjectDoesNotExist

Get whether each of the named pools uses priority lists.

```
Boolean[] getPriorityEnabled(
    String[] names
)
```

getPriorityEnabledByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named pools uses priority lists. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getPriorityEnabledByLocation(
    String location
    String[] names
)
```

getPriorityNodes(names) throws ObjectDoesNotExist

Get the minimum number of highest-priority active nodes, for each of the named pools.

```
Unsigned Integer[] getPriorityNodes(
    String[] names
)
```

getPriorityNodesByLocation(location, names) throws ObjectDoesNotExist

Get the minimum number of highest-priority active nodes, for each of the named pools. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getPriorityNodesByLocation(
    String location
    String[] names
)
```

getPriorityValues(names) throws ObjectDoesNotExist

For each of the named pools, get the priority values for each of the nodes in each pool.

```
Pool.PriorityValueDefinition[][] getPriorityValues(
    String[] names
)
```

getPriorityValuesByLocation(location, names) throws ObjectDoesNotExist

For each of the named pools, get the priority values for each of the nodes in each pool. This is a location specific function, any action will operate on the specified location.

```
Pool.PriorityValueDefinition[][]
getPriorityValuesByLocation(
    String location
    String[] names
)
```

getQueueTimeout(names) throws ObjectDoesNotExist

Get is the maximum time to keep a connections queued in seconds. A value of 0 will not timeout queued connections.

```
Unsigned Integer[] getQueueTimeout(
```

```
String[] names
)
```

getQueueTimeoutByLocation(location, names) throws ObjectDoesNotExist

Get is the maximum time to keep a connections queued in seconds. A value of 0 will not timeout queued connections. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getQueueTimeoutByLocation(
    String location
    String[] names
)
```

getSMTPSendStartTLS(names) throws ObjectDoesNotExist

Get whether each of the named pools should upgrade SMTP connections to SSL using STARTTLS (the alternative is to encrypt the entire connection).

```
Boolean[] getSMTPSendStartTLS(
    String[] names
)
```

getSMTPSendStartTLSByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named pools should upgrade SMTP connections to SSL using STARTTLS (the alternative is to encrypt the entire connection). This is a location specific function, any action will operate on the specified location.

```
Boolean[] getSMTPSendStartTLSByLocation(
    String location
    String[] names
)
```

getSSLClientAuth(names) throws ObjectDoesNotExist

Get whether each of the named pools should use client authentication. If client authentication is enabled and a back-end node asks for a client authentication, a suitable certificate and private key will be used from the SSL Client Certificates catalog.

```
Boolean[] getSSLClientAuth(
    String[] names
```

)

getSSLClientAuthByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named pools should use client authentication. If client authentication is enabled and a back-end node asks for a client authentication, a suitable certificate and private key will be used from the SSL Client Certificates catalog. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getSSLClientAuthByLocation(
    String location
    String[] names
```

getSSLEncrypt(names) throws ObjectDoesNotExist

Get whether each of the named pools should encrypt data to the back-end nodes using SSL.

```
Boolean[] getSSLEncrypt(
    String[] names
)
```

getSSLEncryptByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named pools should encrypt data to the back-end nodes using SSL. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getSSLEncryptByLocation(
    String location
    String[] names
)
```

getSSLEnhance(names) throws ObjectDoesNotExist

Get whether each of the named pools should use SSL protocol enhancements. These enhancements allow Riverbed Web Servers to run multiple SSL sites, and to discover the client's IP address. Only use enable this if, for this pool, you are using Riverbed Web Servers or Stingray Traffic Managers whose virtual servers have the 'ssl_trust_magic' setting enabled.

```
Boolean[] getSSLEnhance(
    String[] names
)
```

getSSLEnhanceByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named pools should use SSL protocol enhancements. These enhancements allow Riverbed Web Servers to run multiple SSL sites, and to discover the client's IP address. Only use enable this if, for this pool, you are using Riverbed Web Servers or Stingray Traffic Managers whose virtual servers have the 'ssl_trust_magic' setting enabled. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getSSLEnhanceByLocation(
    String location
    String[] names
)
```

getSSLSendCloseAlerts(names) throws ObjectDoesNotExist

Get whether each of the named pools should send a close alert when they initiate socket disconnections.

```
Boolean[] getSSLSendCloseAlerts(
    String[] names
)
```

getSSLSendCloseAlertsByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named pools should send a close alert when they initiate socket disconnections. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getSSLSendCloseAlertsByLocation(
    String location
    String[] names
)
```

getSSLServerNameExtension(names) throws ObjectDoesNotExist

Get if we should send the server_name extension to the back-end node. This setting forces the use of at least TLS 1.0.

```
Boolean[] getSSLServerNameExtension(
    String[] names
)
```

getSSLServerNameExtensionByLocation(location, names) throws ObjectDoesNotExist

Get if we should send the server_name extension to the back-end node. This setting forces the use of at least TLS 1.0. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getSSLServerNameExtensionByLocation(
    String location
    String[] names
)
```

getSSLStrictVerify(names) throws ObjectDoesNotExist

Get whether each of the named pools should perform strict certificate validation on SSL certificates from the back-end nodes.

```
Boolean[] getSSLStrictVerify(
    String[] names
)
```

getSSLStrictVerifyByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named pools should perform strict certificate validation on SSL certificates from the back-end nodes. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getSSLStrictVerifyByLocation(
    String location
    String[] names
)
```

getTransparent(names) throws ObjectDoesNotExist

Get whether each of the named pools should make connections to the back-ends appear to originate from the source client IP address.

```
Boolean[] getTransparent(
    String[] names
)
```

getTransparentByLocation(location, names) throws ObjectDoesNotExist

Get whether each of the named pools should make connections to the back-ends appear to originate from the source client IP address. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getTransparentByLocation(
    String location
    String[] names
)
```

getUDPAcceptFrom(names) throws ObjectDoesNotExist

Get what sets of IP addresses and ports from which we should accept UDP responses.

```
Pool.UDPAcceptFrom[] getUDPAcceptFrom(
    String[] names
)
```

getUDPAcceptFromByLocation(location, names) throws ObjectDoesNotExist

Get what sets of IP addresses and ports from which we should accept UDP responses. This is a location specific function, any action will operate on the specified location.

```
Pool.UDPAcceptFrom[] getUDPAcceptFromByLocation(
    String location
    String[] names
)
```

getUDPAcceptFromIPMask(names) throws ObjectDoesNotExist

Get the mask to validate the IP of UDP responses with. Only used if UDPAcceptFromIP is set to 'ip_mask'.

```
String[] getUDPAcceptFromIPMask(
    String[] names
)
```

getUDPAcceptFromIPMaskByLocation(location, names) throws ObjectDoesNotExist

Get the mask to validate the IP of UDP responses with. Only used if UDPAcceptFromIP is set to 'ip_mask'. This is a location specific function, any action will operate on the specified location.

```
String[] getUDPAcceptFromIPMaskByLocation(
    String location
    String[] names
)
```

getWeightings(names) throws ObjectDoesNotExist

For each of the named pools, get the weightings for each of the nodes in each pool.

```
Pool.WeightingsDefinition[][] getWeightings(
    String[] names
)
```

getWeightingsByLocation(location, names) throws ObjectDoesNotExist

For each of the named pools, get the weightings for each of the nodes in each pool. This is a location specific function, any action will operate on the specified location.

```
Pool.WeightingsDefinition[][]
getWeightingsByLocation(
    String location
    String[] names
)
```

removeDrainingNodes(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Remove nodes from the lists of draining nodes, for each of the named pools.

```
void removeDrainingNodes(
    String[] names
    String[][] values
)
```

removeDrainingNodesByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Remove nodes from the lists of draining nodes, for each of the named pools. This is a location specific function, any action will operate on the specified location.

```
void removeDrainingNodesByLocation(
    String location
```

```
String[] names
String[][] values
)
```

removeMonitors(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Remove monitors from each of the named pools.

```
void removeMonitors(
    String[] names
    String[][] values
)
```

removeMonitorsByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Remove monitors from each of the named pools. This is a location specific function, any action will operate on the specified location.

```
void removeMonitorsByLocation(
   String location
   String[] names
   String[][] values
)
```

removeNodes(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Remove nodes from each of the named pools.

```
void removeNodes(
    String[] names
    String[][] values
)
```

removeNodesByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Remove nodes from each of the named pools. This is a location specific function, any action will operate on the specified location.

```
void removeNodesByLocation(
    String location
    String[] names
    String[][] values
)
```

renamePool(names, new_names) throws ObjectDoesNotExist, ObjectAlreadyExists, InvalidObjectName, DeploymentError, InvalidOperation

Rename each of the named pools.

```
void renamePool(
    String[] names
    String[] new_names
)
```

setAutoscaleCloudcredentials(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the cloud credentials for this auto-scaled pool

```
void setAutoscaleCloudcredentials(
    String[] names
    String[] values
)
```

setAutoscaleCloudcredentialsByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the cloud credentials for this auto-scaled pool This is a location specific function, any action will operate on the specified location.

```
void setAutoscaleCloudcredentialsByLocation(
   String location
   String[] names
   String[] values
)
```

setAutoscaleCluster(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set The ESX host or ESX cluster name to put the new virtual machine instances on.

```
void setAutoscaleCluster(
   String[] names
   String[] values
)
```

setAutoscaleClusterByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set The ESX host or ESX cluster name to put the new virtual machine instances on. This is a location specific function, any action will operate on the specified location.

```
void setAutoscaleClusterByLocation(
   String location
   String[] names
   String[] values
)
```

setAutoscaleDatacenter(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set The name of the logical datacenter on the vCenter server

```
void setAutoscaleDatacenter(
    String[] names
    String[] values
)
```

setAutoscaleDatacenterByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set The name of the logical datacenter on the vCenter server This is a location specific function, any action will operate on the specified location.

```
void setAutoscaleDatacenterByLocation(
   String location
   String[] names
   String[] values
```

)

setAutoscaleDatastore(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set The name of the datastore to be used by the newly created virtual machine.

```
void setAutoscaleDatastore(
    String[] names
    String[] values
)
```

setAutoscaleDatastoreByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set The name of the datastore to be used by the newly created virtual machine. This is a location specific function, any action will operate on the specified location.

```
void setAutoscaleDatastoreByLocation(
   String location
   String[] names
   String[] values
)
```

setAutoscaleEnabled(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether this pool uses auto-scaling.

```
void setAutoscaleEnabled(
   String[] names
   Boolean[] values
)
```

setAutoscaleEnabledByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether this pool uses auto-scaling. This is a location specific function, any action will operate on the specified location.

```
void setAutoscaleEnabledByLocation(
    String location
```

```
String[] names
Boolean[] values
)
```

setAutoscaleExternal(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether autoscaling is handled externally or internally

```
void setAutoscaleExternal(
   String[] names
   Boolean[] values
)
```

setAutoscaleExternalByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether autoscaling is handled externally or internally This is a location specific function, any action will operate on the specified location.

```
void setAutoscaleExternalByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setAutoscaleHysteresis(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the hysteresis period for an auto-scaled pool

```
void setAutoscaleHysteresis(
    String[] names
    Unsigned Integer[] values
)
```

setAutoscaleHysteresisByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the hysteresis period for an auto-scaled pool This is a location specific function, any action will operate on the specified location.

```
void setAutoscaleHysteresisByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setAutoscaleImageid(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the image identifier

```
void setAutoscaleImageid(
    String[] names
    String[] values
)
```

setAutoscaleImageidByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the image identifier This is a location specific function, any action will operate on the specified location.

```
void setAutoscaleImageidByLocation(
   String location
   String[] names
   String[] values
)
```

setAutoscaleIpstouse(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether to use the public or private IPs

```
void setAutoscaleIpstouse(
    String[] names
    Pool.AutoscaleIpstouse[] values
)
```

setAutoscaleIpstouseByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether to use the public or private IPs This is a location specific function, any action will operate on the specified location.

```
void setAutoscaleIpstouseByLocation(
   String location
   String[] names
   Pool.AutoscaleIpstouse[] values
)
```

setAutoscaleLastnodeldletime(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the idle time of the last node in an autoscaled pool before it can be destroyed

```
void setAutoscaleLastnodeIdletime(
   String[] names
   Unsigned Integer[] values
)
```

setAutoscaleLastnodeldletimeByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the idle time of the last node in an autoscaled pool before it can be destroyed This is a location specific function, any action will operate on the specified location.

```
void setAutoscaleLastnodeIdletimeByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setAutoscaleMaxNodes(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the maximum number of nodes in an auto-scaled pool

```
void setAutoscaleMaxNodes(
    String[] names
    Unsigned Integer[] values
```

)

setAutoscaleMaxNodesByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the maximum number of nodes in an auto-scaled pool This is a location specific function, any action will operate on the specified location.

```
void setAutoscaleMaxNodesByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setAutoscaleMinNodes(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the minimum number of nodes in an auto-scaled pool

```
void setAutoscaleMinNodes(
    String[] names
    Unsigned Integer[] values
)
```

setAutoscaleMinNodesByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the minimum number of nodes in an auto-scaled pool This is a location specific function, any action will operate on the specified location.

```
void setAutoscaleMinNodesByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setAutoscaleName(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the node name prefix for this auto-scaled pool

```
void setAutoscaleName(
```

```
String[] names
String[] values
)
```

setAutoscaleNameByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the node name prefix for this auto-scaled pool This is a location specific function, any action will operate on the specified location.

```
void setAutoscaleNameByLocation(
   String location
   String[] names
   String[] values
)
```

setAutoscalePort(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the port number for this auto-scaled pool

```
void setAutoscalePort(
    String[] names
    Unsigned Integer[] values
)
```

setAutoscalePortByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the port number for this auto-scaled pool This is a location specific function, any action will operate on the specified location.

```
void setAutoscalePortByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setAutoscaleRefractory(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the refractory period for an auto-scaled pool

```
void setAutoscaleRefractory(
    String[] names
    Unsigned Integer[] values
)
```

setAutoscaleRefractoryByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the refractory period for an auto-scaled pool This is a location specific function, any action will operate on the specified location.

```
void setAutoscaleRefractoryByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setAutoscaleResponseTime(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the expected node response time in milliseconds

```
void setAutoscaleResponseTime(
    String[] names
    Unsigned Integer[] values
)
```

setAutoscaleResponseTimeByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the expected node response time in milliseconds This is a location specific function, any action will operate on the specified location.

```
void setAutoscaleResponseTimeByLocation(
   String location
   String[] names
   Unsigned Integer[] values
```

)

setAutoscaleScaledownLevel(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the threshold of conforming requests for scaling down

```
void setAutoscaleScaledownLevel(
    String[] names
    Unsigned Integer[] values
)
```

setAutoscaleScaledownLevelByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the threshold of conforming requests for scaling down This is a location specific function, any action will operate on the specified location.

```
void setAutoscaleScaledownLevelByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setAutoscaleScaleupLevel(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the acceptable lower percentage of conforming requests

```
void setAutoscaleScaleupLevel(
   String[] names
   Unsigned Integer[] values
)
```

setAutoscaleScaleupLevelByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the acceptable lower percentage of conforming requests This is a location specific function, any action will operate on the specified location.

```
void setAutoscaleScaleupLevelByLocation(
    String location
```

```
String[] names
Unsigned Integer[] values
)
```

setAutoscaleSizeid(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the size identifier

```
void setAutoscaleSizeid(
   String[] names
   String[] values
)
```

setAutoscaleSizeidByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the size identifier This is a location specific function, any action will operate on the specified location.

```
void setAutoscaleSizeidByLocation(
   String location
   String[] names
   String[] values
)
```

setBandwidthClass(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the Bandwidth Classes that each of the named pools uses.

```
void setBandwidthClass(
    String[] names
    String[] values
)
```

setBandwidthClassByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the Bandwidth Classes that each of the named pools uses. This is a location specific function, any action will operate on the specified location.

```
void setBandwidthClassByLocation(
   String location
   String[] names
   String[] values
)
```

setDisabledNodes(names, nodes) throws ObjectDoesNotExist, InvalidInput, DeploymentError

For each of the named pools, set the specified nodes to be disabled in the pool (all other nodes will remain in their existing state).

```
void setDisabledNodes(
    String[] names
    String[][] nodes
)
```

setDisabledNodesByLocation(location, names, nodes) throws ObjectDoesNotExist, InvalidInput, DeploymentError

For each of the named pools, set the specified nodes to be disabled in the pool (all other nodes will remain in their existing state). This is a location specific function, any action will operate on the specified location.

```
void setDisabledNodesByLocation(
   String location
   String[] names
   String[][] nodes
)
```

setDrainingNodes(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the lists of draining nodes for each of the named pools.

```
void setDrainingNodes(
    String[] names
    String[][] values
)
```

setDrainingNodesByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the lists of draining nodes for each of the named pools. This is a location specific function, any action will operate on the specified location.

```
void setDrainingNodesByLocation(
   String location
   String[] names
   String[][] values
)
```

setErrorFile(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

This method is now obsolete and is replaced by VirtualServer.setErrorFile.

```
void setErrorFile(
    String[] names
    String[] values
)
```

setFTPSupportRfc2428(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether backend IPv4 nodes understand the FTP EPRT and EPSV commands.

```
void setFTPSupportRfc2428(
    String[] names
    Boolean[] values
)
```

setFTPSupportRfc2428ByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether backend IPv4 nodes understand the FTP EPRT and EPSV commands. This is a location specific function, any action will operate on the specified location.

```
void setFTPSupportRfc2428ByLocation(
   String location
   String[] names
   Boolean[] values
```

)

setFailpool(names, values) throws ObjectDoesNotExist, InvalidInput, InvalidOperation, DeploymentError

Set the pool to use when all nodes in a pool fail, for each of the named pools.

```
void setFailpool(
    String[] names
    String[] values
)
```

setFailpoolByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, InvalidOperation, DeploymentError

Set the pool to use when all nodes in a pool fail, for each of the named pools. This is a location specific function, any action will operate on the specified location.

```
void setFailpoolByLocation(
    String location
    String[] names
    String[] values
)
```

setKeepalive(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether each of the named pools should maintain HTTP keepalive connections to the nodes.

```
void setKeepalive(
   String[] names
   Boolean[] values
)
```

setKeepaliveByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether each of the named pools should maintain HTTP keepalive connections to the nodes. This is a location specific function, any action will operate on the specified location.

```
void setKeepaliveByLocation(
    String location
```

```
String[] names
Boolean[] values
)
```

setKeepaliveNonIdempotent(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether each of the named pools should maintain HTTP keepalive connections to the nodes for non-idempotent requests.

```
void setKeepaliveNonIdempotent(
   String[] names
   Boolean[] values
)
```

setKeepaliveNonIdempotentByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether each of the named pools should maintain HTTP keepalive connections to the nodes for non-idempotent requests. This is a location specific function, any action will operate on the specified location.

```
void setKeepaliveNonIdempotentByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setLoadBalancingAlgorithm(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the load balancing algorithms that each of the named pools uses.

```
void setLoadBalancingAlgorithm(
    String[] names
    Pool.LoadBalancingAlgorithm[] values
)
```

setLoadBalancingAlgorithmByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the load balancing algorithms that each of the named pools uses. This is a location specific function, any action will operate on the specified location.

```
void setLoadBalancingAlgorithmByLocation(
   String location
   String[] names
   Pool.LoadBalancingAlgorithm[] values
)
```

setMaxConnectTime(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the times that each of the named pools should wait for a connection to establish to a node before trying another node, in seconds.

```
void setMaxConnectTime(
   String[] names
   Unsigned Integer[] values
)
```

setMaxConnectTimeByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the times that each of the named pools should wait for a connection to establish to a node before trying another node, in seconds. This is a location specific function, any action will operate on the specified location.

```
void setMaxConnectTimeByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setMaxConnectionsPernode(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set is the maximum number of conncurrent connections allowed to each node in the pool per machine.

```
void setMaxConnectionsPernode(
```

```
String[] names
Unsigned Integer[] values
)
```

setMaxConnectionsPernodeByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set is the maximum number of conncurrent connections allowed to each node in the pool per machine. This is a location specific function, any action will operate on the specified location.

```
void setMaxConnectionsPernodeByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setMaxIdleConnectionsPerNode(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the maximum numbers of unused HTTP keepalive connections that each of the named pools should maintain to an individual node.

```
void setMaxIdleConnectionsPerNode(
    String[] names
    Unsigned Integer[] values
)
```

setMaxIdleConnectionsPerNodeByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the maximum numbers of unused HTTP keepalive connections that each of the named pools should maintain to an individual node. This is a location specific function, any action will operate on the specified location.

```
void setMaxIdleConnectionsPerNodeByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setMaxKeepalivesPerNode(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

setMaxKeepalivesPerNode is deprecated, please use setMaxIdleConnectionsPerNode instead.

```
void setMaxKeepalivesPerNode(
    String[] names
    Unsigned Integer[] values
)
```

setMaxKeepalivesPerNodeByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

setMaxKeepalivesPerNode is deprecated, please use setMaxIdleConnectionsPerNode instead. This is a location specific function, any action will operate on the specified location.

```
void setMaxKeepalivesPerNodeByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setMaxQueueSize(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set is the maximum number of connections that can be queued due to connection limits.

```
void setMaxQueueSize(
   String[] names
   Unsigned Integer[] values
)
```

setMaxQueueSizeByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set is the maximum number of connections that can be queued due to connection limits. This is a location specific function, any action will operate on the specified location.

```
void setMaxQueueSizeByLocation(
   String location
   String[] names
   Unsigned Integer[] values
```

)

setMaxReplyTime(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the time that each of the named pools should wait for a response from a node before either discarding the request or trying another node, in seconds (retryable requests only).

```
void setMaxReplyTime(
   String[] names
   Unsigned Integer[] values
)
```

setMaxReplyTimeByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the time that each of the named pools should wait for a response from a node before either discarding the request or trying another node, in seconds (retryable requests only). This is a location specific function, any action will operate on the specified location.

```
void setMaxReplyTimeByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setMonitors(names, values) throws ObjectDoesNotExist, InvalidInput, InvalidOperation, DeploymentError

Set the list of all monitors.

```
void setMonitors(
   String[] names
   String[][] values
)
```

setMonitorsByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, InvalidOperation, DeploymentError

Set the list of all monitors. This is a location specific function, any action will operate on the specified location.

```
void setMonitorsByLocation(
```

```
String location
String[] names
String[][] values
```

setNodeConnClose(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether all connections that have been sent to a node are closed when that node is marked as dead.

```
void setNodeConnClose(
    String[] names
    Boolean[] values
)
```

setNodeConnCloseByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether all connections that have been sent to a node are closed when that node is marked as dead. This is a location specific function, any action will operate on the specified location.

```
void setNodeConnCloseByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setNodeConnectionAttempts(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the number of times your traffic manager should try and connect to a node before registering it as failed when passive monitoring is enabled.

```
void setNodeConnectionAttempts(
    String[] names
    Unsigned Integer[] values
)
```

setNodeConnectionAttemptsByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the number of times your traffic manager should try and connect to a node before registering it as failed when passive monitoring is enabled. This is a location specific function, any action will operate on the specified location.

```
void setNodeConnectionAttemptsByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setNodeFailTime(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the length of time a failed node should be isolated for before testing it with new traffic, in seconds

```
void setNodeFailTime(
   String[] names
   Unsigned Integer[] values
)
```

setNodeFailTimeByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the length of time a failed node should be isolated for before testing it with new traffic, in seconds This is a location specific function, any action will operate on the specified location.

```
void setNodeFailTimeByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setNodeUseNagle(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether Nagle's algorithm should be used for TCP connections to the back-end nodes.

```
void setNodeUseNagle(
    String[] names
    Boolean[] values
```

)

setNodeUseNagleByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether Nagle's algorithm should be used for TCP connections to the back-end nodes. This is a location specific function, any action will operate on the specified location.

```
void setNodeUseNagleByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setNodes(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the lists of nodes for each of the named pools.

```
void setNodes(
    String[] names
    String[][] values
)
```

setNodesByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the lists of nodes for each of the named pools. This is a location specific function, any action will operate on the specified location.

```
void setNodesByLocation(
    String location
    String[] names
    String[][] values
)
```

setNodesPriorityValue(names, node_values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

For each of the named pools, set the priority values for the named nodes in each pool.

```
void setNodesPriorityValue(
```

```
String[] names
Pool.PriorityValueDefinition[][] node_values
)
```

setNodesPriorityValueByLocation(location, names, node_values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

For each of the named pools, set the priority values for the named nodes in each pool. This is a location specific function, any action will operate on the specified location.

```
void setNodesPriorityValueByLocation(
   String location
   String[] names
   Pool.PriorityValueDefinition[][] node_values
)
```

setNodesWeightings(names, nodes_values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

For each of the named pools, set the weighting (for the Weighted Round Robin algorithm) for each node in that pool.

```
void setNodesWeightings(
    String[] names
    Pool.WeightingsDefinition[][] nodes_values
)
```

setNodesWeightingsByLocation(location, names, nodes_values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

For each of the named pools, set the weighting (for the Weighted Round Robin algorithm) for each node in that pool. This is a location specific function, any action will operate on the specified location.

```
void setNodesWeightingsByLocation(
   String location
   String[] names
   Pool.WeightingsDefinition[][] nodes_values
)
```

setNote(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the note for each of the named pools.

```
void setNote(
   String[] names
   String[] values
)
```

setPassiveMonitoring(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether this pool uses passive monitoring.

```
void setPassiveMonitoring(
    String[] names
    Boolean[] values
)
```

setPassiveMonitoringByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether this pool uses passive monitoring. This is a location specific function, any action will operate on the specified location.

```
void setPassiveMonitoringByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setPersistence(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the default Session Persistence classes that each of the named pools uses.

```
void setPersistence(
    String[] names
    String[] values
)
```

setPersistenceByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the default Session Persistence classes that each of the named pools uses. This is a location specific function, any action will operate on the specified location.

```
void setPersistenceByLocation(
   String location
   String[] names
   String[] values
)
```

setPriorityEnabled(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether each of the named pools uses priority lists.

```
void setPriorityEnabled(
    String[] names
    Boolean[] values
)
```

setPriorityEnabledByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether each of the named pools uses priority lists. This is a location specific function, any action will operate on the specified location.

```
void setPriorityEnabledByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setPriorityNodes(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the minimum number of highest-priority active nodes, for each of the named pools.

```
void setPriorityNodes(
    String[] names
    Unsigned Integer[] values
```

)

setPriorityNodesByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the minimum number of highest-priority active nodes, for each of the named pools. This is a location specific function, any action will operate on the specified location.

```
void setPriorityNodesByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setQueueTimeout(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set is the maximum time to keep a connections queued in seconds. A value of 0 will not timeout queued connections.

```
void setQueueTimeout(
   String[] names
   Unsigned Integer[] values
)
```

setQueueTimeoutByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set is the maximum time to keep a connections queued in seconds. A value of 0 will not timeout queued connections. This is a location specific function, any action will operate on the specified location.

```
void setQueueTimeoutByLocation(
   String location
   String[] names
   Unsigned Integer[] values
```

setSMTPSendStartTLS(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether each of the named pools should upgrade SMTP connections to SSL using STARTTLS (the alternative is to encrypt the entire connection).

```
void setSMTPSendStartTLS(
    String[] names
    Boolean[] values
)
```

setSMTPSendStartTLSByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether each of the named pools should upgrade SMTP connections to SSL using STARTTLS (the alternative is to encrypt the entire connection). This is a location specific function, any action will operate on the specified location.

```
void setSMTPSendStartTLSByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setSSLClientAuth(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether each of the named pools should use client authentication. If client authentication is enabled and a back-end node asks for a client authentication, a suitable certificate and private key will be used from the SSL Client Certificates catalog.

```
void setSSLClientAuth(
    String[] names
    Boolean[] values
)
```

setSSLClientAuthByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether each of the named pools should use client authentication. If client authentication is enabled and a back-end node asks for a client authentication, a suitable certificate and private key will be used from the SSL Client Certificates catalog. This is a location specific function, any action will operate on the specified location.

```
void setSSLClientAuthByLocation(
```

```
String location
String[] names
Boolean[] values
```

setSSLEncrypt(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether each of the named pools should encrypt data to the back-end nodes using SSL.

```
void setSSLEncrypt(
    String[] names
    Boolean[] values
)
```

setSSLEncryptByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether each of the named pools should encrypt data to the back-end nodes using SSL. This is a location specific function, any action will operate on the specified location.

```
void setSSLEncryptByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setSSLEnhance(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether each of the named pools should use SSL protocol enhancements. These enhancements allow Riverbed Web Servers to run multiple SSL sites, and to discover the client's IP address. Only use enable this if, for this pool, you are using Riverbed Web Servers or Stingray Traffic Managers whose virtual servers have the 'ssl_trust_magic' setting enabled.

```
void setSSLEnhance(
    String[] names
    Boolean[] values
)
```

Pool Function Reference

setSSLEnhanceByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether each of the named pools should use SSL protocol enhancements. These enhancements allow Riverbed Web Servers to run multiple SSL sites, and to discover the client's IP address. Only use enable this if, for this pool, you are using Riverbed Web Servers or Stingray Traffic Managers whose virtual servers have the 'ssl_trust_magic' setting enabled. This is a location specific function, any action will operate on the specified location.

```
void setSSLEnhanceByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setSSLSendCloseAlerts(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether each of the named pools should send a close alert when they initiate socket disconnections.

```
void setSSLSendCloseAlerts(
    String[] names
    Boolean[] values
)
```

setSSLSendCloseAlertsByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether each of the named pools should send a close alert when they initiate socket disconnections. This is a location specific function, any action will operate on the specified location.

```
void setSSLSendCloseAlertsByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setSSLServerNameExtension(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set if we should send the server_name extension to the back-end node. This setting forces the use of at least TLS 1.0.

Function Reference Pool

```
void setSSLServerNameExtension(
   String[] names
   Boolean[] values
)
```

setSSLServerNameExtensionByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set if we should send the server_name extension to the back-end node. This setting forces the use of at least TLS 1.0. This is a location specific function, any action will operate on the specified location.

```
void setSSLServerNameExtensionByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setSSLStrictVerify(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether each of the named pools should perform strict certificate validation on SSL certificates from the back-end nodes.

```
void setSSLStrictVerify(
   String[] names
   Boolean[] values
)
```

setSSLStrictVerifyByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether each of the named pools should perform strict certificate validation on SSL certificates from the back-end nodes. This is a location specific function, any action will operate on the specified location.

```
void setSSLStrictVerifyByLocation(
   String location
   String[] names
   Boolean[] values
)
```

Pool Function Reference

setTransparent(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether each of the named pools should make connections to the back-ends appear to originate from the source client IP address.

```
void setTransparent(
    String[] names
    Boolean[] values
)
```

setTransparentByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether each of the named pools should make connections to the back-ends appear to originate from the source client IP address. This is a location specific function, any action will operate on the specified location.

```
void setTransparentByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setUDPAcceptFrom(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set what sets of IP addresses and ports from which we should accept UDP responses.

```
void setUDPAcceptFrom(
   String[] names
   Pool.UDPAcceptFrom[] values
)
```

setUDPAcceptFromByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set what sets of IP addresses and ports from which we should accept UDP responses. This is a location specific function, any action will operate on the specified location.

```
void setUDPAcceptFromByLocation(
   String location
   String[] names
```

Function Reference Pool

```
Pool.UDPAcceptFrom[] values
)
```

setUDPAcceptFromIPMask(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the mask to validate the IP of UDP responses with. Only used if UDPAcceptFromIP is set to 'ip_mask'.

```
void setUDPAcceptFromIPMask(
    String[] names
    String[] values
)
```

setUDPAcceptFromIPMaskByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the mask to validate the IP of UDP responses with. Only used if UDPAcceptFromIP is set to 'ip_mask'. This is a location specific function, any action will operate on the specified location.

```
void setUDPAcceptFromIPMaskByLocation(
   String location
   String[] names
   String[] values
)
```

Structures

Pool.PriorityValueDefinition

This structure contains the priority for a particular node. The priority is used when using the priority lists functionality.

```
struct Pool.PriorityValueDefinition {
    # The name of the node.
    String node;

# The priority value.
    Integer priority;
}
```

Pool Function Reference

Pool.WeightingsDefinition

This structure contains the weighting for a particular node. The weighting is used when using the Weighted Round Robin algorithm functionality.

```
struct Pool.WeightingsDefinition {
    # The name of the node.
    String node;

# The weighting value.
    Integer weighting;
}
```

Enumerations

Pool.Autoscalelpstouse

```
enum Pool.AutoscaleIpstouse {
    # Public IP addresses
    publicips,

# Private IP addresses
    privateips
}
```

Pool.LoadBalancingAlgorithm

```
enum Pool.LoadBalancingAlgorithm {
    # Round Robin
    roundrobin,

# Weighted Round Robin
    wroundrobin,

# Perceptive
    cells,
```

Function Reference Pool

```
# Least Connections
connections,

# Weighted Least Connections
wconnections,

# Fastest Response Time
responsetimes,

# Random Node
random
}
```

Pool.UDPAcceptFrom

```
enum Pool.UDPAcceptFrom {
    # Only the IP address and port to which the request was sent
    dest_only,

# Only the IP address to which the request was sent, but from
    # any port
    dest_ip_only,

# Only a specific set of IP addresses, but from any port
    ip_mask,

# Any IP address and any port
    all
}
```

TrafficIPGroups Function Reference

TrafficIPGroups

```
URI: http://soap.zeus.com/zxtm/1.0/TrafficIPGroups/
```

The TrafficIPGroup interface allows management of Traffic IP Group objects. Using this interface, you can create, delete and rename Traffic IP Group objects, and manage their configuration.

Methods

addIPAddresses(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Add new IP addresses to each of the named traffic IP groups.

```
void addIPAddresses(
    String[] names
    String[][] values
)
```

addPassiveMachine(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Add machines to the lists of passive machines, for each of the named traffic IP groups.

```
void addPassiveMachine(
    String[] names
    String[][] values
)
```

addTrafficIPGroup(names, details) throws ObjectAlreadyExists, InvalidObjectName, DeploymentError, InvalidInput, InvalidOperation

Add the new named Traffic IP Groups, using the provided details.

```
void addTrafficIPGroup(
    String[] names
    TrafficIPGroups.Details[] details
)
```

addTrafficManager(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Add new traffic managers to each of the named traffic IP groups.

Function Reference TrafficIPGroups

```
void addTrafficManager(
    String[] names
    String[][] values
)
```

deleteSpecificSubnetMappings(mappings) throws InvalidInput

Delete specified interface network mappings.

```
void deleteSpecificSubnetMappings(
    TrafficIPGroups.SubnetMappingPerHost[] mappings
)
```

deleteSubnetMappings()

Delete all interface network mappings.

```
void deleteSubnetMappings()
```

deleteTrafficIPGroup(names) throws ObjectDoesNotExist, ObjectInUse, DeploymentError, InvalidOperation

Delete the named Traffic IP Groups.

```
void deleteTrafficIPGroup(
    String[] names
)
```

getAvailableTrafficManagers()

Get the names of all of the Traffic Managers in the cluster.

```
String[] getAvailableTrafficManagers()
```

getEnabled(names) throws ObjectDoesNotExist

Get whether this traffic IP group is enabled or not.

```
Boolean[] getEnabled(
    String[] names
)
```

TrafficIPGroups Function Reference

getIPAddresses(names) throws ObjectDoesNotExist

Get the IP addresses that are managed by each of the named traffic IP groups.

```
String[][] getIPAddresses(
    String[] names
)
```

getIPDistributionMode(names) throws ObjectDoesNotExist

Get how traffic IPs will be distributed across the machines in the cluster. If "multihosted" mode is used, the multicast IP must be set first.

```
TrafficIPGroups.IPDistributionMode[]
getIPDistributionMode(
    String[] names
)
```

getKeepTogether(names) throws ObjectDoesNotExist

Get the KeepTogether attribute for each of the named traffic IP groups.

```
Boolean[] getKeepTogether(
    String[] names
)
```

getMulticastIP(names) throws ObjectDoesNotExist

Get the multicast IP group that is used to share data across machines in the cluster. This setting is only used if the traffic IP is using 'multihosted' distribution mode.

```
String[] getMulticastIP(
    String[] names
)
```

getNetworkInterfaces()

Get a list of network interfaces for all machines in the cluster.

```
TrafficIPGroups.NetworkInterface[]
getNetworkInterfaces()
```

getNote(names) throws ObjectDoesNotExist

Get the note for each of the named traffic IP groups.

Function Reference TrafficIPGroups

```
String[] getNote(
    String[] names
)
```

getPassiveMachine(names) throws ObjectDoesNotExist

Get the lists of passive machines in each of the named traffic IP groups.

```
String[][] getPassiveMachine(
    String[] names
)
```

getSubnetMappings(hostnames) throws InvalidInput

Get interface to CIDR subnet mappings.

```
TrafficIPGroups.SubnetMappingPerHost[]
getSubnetMappings(
    String[] hostnames
)
```

getTrafficIPGroupNames()

Get the names of all of the configured Traffic IP Groups.

```
String[] getTrafficIPGroupNames()
```

getTrafficManager(names) throws ObjectDoesNotExist

Get the traffic managers that manage the IP addresses in each of the named traffic IP groups.

```
String[][] getTrafficManager(
    String[] names
)
```

getUseClientSourcePort(names) throws ObjectDoesNotExist

Get whether the source port is taken into account when deciding which traffic manager should handle the request. This setting is only used if the Traffic IP is using 'multihosted' distribution mode.

```
Boolean[] getUseClientSourcePort(
    String[] names
)
```

TrafficIPGroups Function Reference

removeIPAddresses(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Remove the named IP addresses from each of the named traffic IP groups.

```
void removeIPAddresses(
    String[] names
    String[][] values
)
```

removePassiveMachine(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Remove the named machines from the list of passive machines, for each of the named traffic IP groups.

```
void removePassiveMachine(
    String[] names
    String[][] values
)
```

removeTrafficManager(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidOperation

Remove the named traffic managers from each named traffic IP group.

```
void removeTrafficManager(
    String[] names
    String[][] values
)
```

renameTrafficIPGroup(names, new_names) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Rename each of the named Traffic IP Groups.

```
void renameTrafficIPGroup(
    String[] names
    String[] new_names
)
```

Function Reference TrafficIPGroups

setEnabled(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set whether this traffic IP group is enabled or not.

```
void setEnabled(
   String[] names
   Boolean[] values
)
```

setIPAddresses(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the IP addresses that are managed by each of the named traffic IP groups.

```
void setIPAddresses(
    String[] names
    String[][] values
)
```

setIPDistributionMode(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set how traffic IPs will be distributed across the machines in the cluster. If "multihosted" mode is used, the multicast IP must be set first.

```
void setIPDistributionMode(
    String[] names
    TrafficIPGroups.IPDistributionMode[] values
)
```

setKeepTogether(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the KeepTogether attribute for each of the named traffic IP groups.

```
void setKeepTogether(
   String[] names
   Boolean[] values
)
```

TrafficIPGroups Function Reference

setMulticastIP(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the multicast IP group that is used to share data across machines in the cluster. This setting is only used if the traffic IP is using 'multihosted' distribution mode.

```
void setMulticastIP(
    String[] names
    String[] values
)
```

setNote(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the note for each of the named traffic IP groups.

```
void setNote(
   String[] names
   String[] values
)
```

setPassiveMachine(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the lists of passive machines in each of the named traffic IP groups.

```
void setPassiveMachine(
    String[] names
    String[][] values
)
```

setSubnetMappings(mappings) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Update interface to CIDR subnet mappings.

```
void setSubnetMappings(
    TrafficIPGroups.SubnetMappingPerHost[] mappings
)
```

Function Reference TrafficIPGroups

setTrafficManager(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the traffic managers that manage the IP addresses in each of the named traffic IP groups.

```
void setTrafficManager(
    String[] names
    String[][] values
)
```

setUseClientSourcePort(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set whether the source port is taken into account when deciding which traffic manager should handle the request. This setting is only used if the Traffic IP is using 'multihosted' distribution mode.

```
void setUseClientSourcePort(
    String[] names
    Boolean[] values
)
```

Structures

TrafficIPGroups.Details

This structure contains the basic details of a Traffic IP Group: the nodes, and the traffic managers that the Traffic IP group spans. It is used when creating a new Traffic IP Group.

```
struct TrafficIPGroups.Details {
    # The IP addresses in the Traffic IP Group.
    String[] ipaddresses;

# The names of the traffic managers that will manage the IP
    # Addresses.
    String[] machines;
}
```

TrafficIPGroups.NetworkInterface

This structure displays the network interfaces of all machines in the cluster.

TrafficIPGroups Function Reference

```
struct TrafficIPGroups.NetworkInterface {
    # The traffic manager in the cluster.
    String hostname;

    # The network interfaces configured in this traffic manager.
    String[] interfaces;
}
```

TrafficIPGroups.SubnetMapping

This structure contains mappings of network interface to CIDR subnets. These mappings are used to raise a TrafficIP on a desired interface.

```
struct TrafficIPGroups.SubnetMapping {
    # The interface on the system.
    String interface;

# The subnets mappings for the interface.
    String[] subnets;
}
```

TrafficIPGroups.SubnetMappingPerHost

This structure shows the traffic IP subnet mapping per host machine in the cluster.

```
struct TrafficIPGroups.SubnetMappingPerHost {
    # The traffic manager in the cluster.
    String hostname;

# The subnets mappings for this traffic manager.
    TrafficIPGroups.SubnetMapping[] subnetmappings;
}
```

Enumerations

TrafficIPGroups.IPDistributionMode

```
enum TrafficIPGroups.IPDistributionMode {
```

Function Reference Catalog.Rule

```
# Raise each address on a single machine (Single-
Hosted mode)
singlehosted,

# Raise each address on every machine in the group
# (Multi-Hosted mode) - IPv4 only
multihosted,

# Use an EC2 Elastic IP address.
ec2elastic
}
```

Catalog.Rule

URI: http://soap.zeus.com/zxtm/1.0/Catalog/Rule/

The Catalog.Rule interface allows management of TrafficScript Rules. Using this interface, you can create, delete and rename rules, and manage their configuration. You can also syntax-check rule fragments.

Methods

addRule(names, texts) throws InvalidObjectName, ObjectAlreadyExists, DeploymentError

Add new rules to the catalog.

```
void addRule(
   String[] names
   String[] texts
)
```

checkSyntax(rule_text)

Check the syntax of each of the supplied TrafficScript rule texts. This method does not modify any configuration.

```
Catalog.Rule.SyntaxCheck[] checkSyntax(
    String[] rule_text
)
```

Catalog.Rule Function Reference

copyRule(names, new_names) throws InvalidObjectName, ObjectAlreadyExists, ObjectDoesNotExist, DeploymentError

Copy the named rules in the catalog.

```
void copyRule(
   String[] names
   String[] new_names
)
```

deleteRule(names) throws ObjectInUse, ObjectDoesNotExist, DeploymentError, InvalidOperation

Delete the named rules from the catalog.

```
void deleteRule(
    String[] names
)
```

getRuleDetails(names) throws ObjectDoesNotExist, DeploymentError

Get the rule text and notes (if any), for each of the named rules.

```
Catalog.Rule.RuleInfo[] getRuleDetails(
    String[] names
)
```

getRuleNames()

Get the names of all rules in the catalog.

```
String[] getRuleNames()
```

renameRule(names, new_names) throws InvalidObjectName, ObjectAlreadyExists, ObjectDoesNotExist, DeploymentError, InvalidOperation

Rename the named rules in the catalog.

```
void renameRule(
   String[] names
   String[] new_names
)
```

Function Reference Catalog.Rule

setRuleNotes(names, notes) throws ObjectDoesNotExist, DeploymentError

Sets the descriptive notes for each of the named rules in the catalog.

```
void setRuleNotes(
    String[] names
    String[] notes
)
```

setRuleText(names, text) throws ObjectDoesNotExist, DeploymentError

Set the TrafficScript text for each of the named rules in the catalog.

```
void setRuleText(
    String[] names
    String[] text
)
```

Structures

Catalog.Rule.RuleInfo

This structure contains basic information for a rule in the catalog.

```
struct Catalog.Rule.RuleInfo {
    # The rule text
    String rule_text;

# The descriptive notes for the rule.
    String rule_notes;
}
```

Catalog.Rule.SyntaxCheck

This structure contains the results of a rule syntax check against a rule in the catalog.

```
struct Catalog.Rule.SyntaxCheck {
    # Whether the rule text is valid or not.
    Boolean valid;
```

```
# Any warnings (such as deprecated functions)
associated with

# the rule text.
String warnings;

# Any errors (such as syntax errors) associated
with the rule

# text.
String errors;
}
```

Catalog.Monitor

URI: http://soap.zeus.com/zxtm/1.0/Catalog/Monitor/

The Catalog.Monitor interface allows management of Custom Monitors. Using this interface, you can create, delete and rename custom monitors, and manage their configuration.

Methods

addMonitors(names) throws ObjectAlreadyExists, InvalidObjectName, DeploymentError

Add new monitors (defaults to TCP transaction monitor, monitoring each node separately).

```
void addMonitors(
    String[] names
)
```

addProgramArguments(names, arguments) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Adds a set of arguments to the specified monitors. The monitors specified must be of type 'program'.

```
void addProgramArguments(
    String[] names
    Catalog.Monitor.Argument[][] arguments
)
```

copyMonitors(names, new_names) throws ObjectDoesNotExist, ObjectAlreadyExists, InvalidObjectName, DeploymentError

Copy the named monitors.

```
void copyMonitors(
    String[] names
    String[] new_names
)
```

deleteMonitorProgram(names) throws ObjectDoesNotExist, DeploymentError, ObjectInUse

Delete the named monitor programs.

```
void deleteMonitorProgram(
    String[] names
)
```

deleteMonitors(names) throws ObjectDoesNotExist, InvalidOperation, DeploymentError, ObjectInUse

Delete these monitors.

```
void deleteMonitors(
    String[] names
)
```

downloadMonitorProgram(name) throws ObjectDoesNotExist

Download the named monitor program.

```
Binary Data downloadMonitorProgram(
    String name
)
```

getAllMonitorNames()

Get the names of all monitors.

```
String[] getAllMonitorNames()
```

getAuthentication(names) throws ObjectDoesNotExist, InvalidOperation

Get the authentication (user:password) that each of the named monitors should use in the test HTTP request.

```
String[] getAuthentication(
    String[] names
)
```

getAuthenticationByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get the authentication (user:password) that each of the named monitors should use in the test HTTP request. This is a location specific function, any action will operate on the specified location.

```
String[] getAuthenticationByLocation(
    String location
    String[] names
)
```

getBackOff(names) throws ObjectDoesNotExist, InvalidOperation

Get whether each of the named monitors should back-off after it has failed.

```
Boolean[] getBackOff(
    String[] names
)
```

getBackOffByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get whether each of the named monitors should back-off after it has failed. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getBackOffByLocation(
    String location
    String[] names
)
```

getBodyRegex(names) throws ObjectDoesNotExist, InvalidOperation

Get the body regular expression that that each of the named monitors' HTTP response must match.

```
String[] getBodyRegex(
```

```
String[] names
```

getBodyRegexByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get the body regular expression that that each of the named monitors' HTTP response must match. This is a location specific function, any action will operate on the specified location.

```
String[] getBodyRegexByLocation(
   String location
   String[] names
)
```

getCloseString(names) throws ObjectDoesNotExist, InvalidOperation

Get an optional string that each of the named monitors should write to the server before closing the connection.

```
String[] getCloseString(
    String[] names
)
```

getCloseStringByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get an optional string that each of the named monitors should write to the server before closing the connection. This is a location specific function, any action will operate on the specified location.

```
String[] getCloseStringByLocation(
    String location
    String[] names
)
```

getCustomMonitorNames()

Get the names of all the custom monitors.

```
String[] getCustomMonitorNames()
```

getDelay(names) throws ObjectDoesNotExist, InvalidOperation

Get the minimum time between calls to each of the named monitors (in seconds).

```
Unsigned Integer[] getDelay(
    String[] names
)
```

getDelayByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get the minimum time between calls to each of the named monitors (in seconds). This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getDelayByLocation(
    String location
    String[] names
)
```

getFailures(names) throws ObjectDoesNotExist, InvalidOperation

Get the number of failures required, by each of the named monitors, before a node is classed as unavailable.

```
Unsigned Integer[] getFailures(
    String[] names
)
```

getFailuresByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get the number of failures required, by each of the named monitors, before a node is classed as unavailable. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getFailuresByLocation(
    String location
    String[] names
)
```

getHealthOnly(names) throws ObjectDoesNotExist, InvalidOperation

Get whether each of the named monitors should monitor health only (ignore load).

```
Boolean[] getHealthOnly(
    String[] names
)
```

getHealthOnlyByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get whether each of the named monitors should monitor health only (ignore load). This is a location specific function, any action will operate on the specified location.

```
Boolean[] getHealthOnlyByLocation(
    String location
    String[] names
)
```

getHostHeader(names) throws ObjectDoesNotExist, InvalidOperation

Get the host header that each of the named monitors should use in the test HTTP request.

```
String[] getHostHeader(
    String[] names
)
```

getHostHeaderByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get the host header that each of the named monitors should use in the test HTTP request. This is a location specific function, any action will operate on the specified location.

```
String[] getHostHeaderByLocation(
   String location
   String[] names
)
```

getMachine(names) throws ObjectDoesNotExist, InvalidOperation

Get the machine that each of the named monitors should monitor (must be a valid hostname:port or a hostname for Ping monitors).

```
String[] getMachine(
    String[] names
)
```

getMachineByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get the machine that each of the named monitors should monitor (must be a valid hostname:port or a hostname for Ping monitors). This is a location specific function, any action will operate on the specified location.

```
String[] getMachineByLocation(
    String location
    String[] names
)
```

getMaxResponseLen(names) throws ObjectDoesNotExist, InvalidOperation

Get the maximum amount of data (in bytes) that each of the named monitors should read back from a server (0 = unlimited).

```
Unsigned Integer[] getMaxResponseLen(
    String[] names
)
```

getMaxResponseLenByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get the maximum amount of data (in bytes) that each of the named monitors should read back from a server (0 = unlimited). This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getMaxResponseLenByLocation(
    String location
    String[] names
)
```

getMonitorProgramNames()

Get the names of all the uploaded monitor programs. These are the programs that can be executed by custom program monitors.

```
String[] getMonitorProgramNames()
```

getNote(names) throws ObjectDoesNotExist, InvalidOperation

Get the note for each of the named Monitors.

```
String[] getNote(
```

```
String[] names
)
```

getPath(names) throws ObjectDoesNotExist, InvalidOperation

Get the path that each of the named monitors should use in the test HTTP request.

```
String[] getPath(
    String[] names
)
```

getPathByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get the path that each of the named monitors should use in the test HTTP request. This is a location specific function, any action will operate on the specified location.

```
String[] getPathByLocation(
    String location
    String[] names
)
```

getProgram(names) throws ObjectDoesNotExist, InvalidOperation

Get the name of the program that each named monitor runs.

```
String[] getProgram(
    String[] names
)
```

getProgramArguments(names) throws ObjectDoesNotExist, InvalidOperation

Gets all arguments for the specified monitors. The monitors specified must be of type 'program'.

```
Catalog.Monitor.Argument[][] getProgramArguments(
    String[] names
)
```

getResponseRegex(names) throws ObjectDoesNotExist, InvalidOperation

Get the regular expression that each of the named monitors should match against the server response.

```
String[] getResponseRegex(
```

```
String[] names
)
```

getResponseRegexByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get the regular expression that each of the named monitors should match against the server response. This is a location specific function, any action will operate on the specified location.

```
String[] getResponseRegexByLocation(
   String location
   String[] names
)
```

getRtspBodyRegex(names) throws ObjectDoesNotExist, InvalidOperation

Get the body regular expression that each of the named monitors' RTSP response must match.

```
String[] getRtspBodyRegex(
    String[] names
)
```

getRtspBodyRegexByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get the body regular expression that each of the named monitors' RTSP response must match. This is a location specific function, any action will operate on the specified location.

```
String[] getRtspBodyRegexByLocation(
   String location
   String[] names
)
```

getRtspPath(names) throws ObjectDoesNotExist, InvalidOperation

Get the path that each of the named monitors should use in the test RTSP request.

```
String[] getRtspPath(
    String[] names
)
```

getRtspPathByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get the path that each of the named monitors should use in the test RTSP request. This is a location specific function, any action will operate on the specified location.

```
String[] getRtspPathByLocation(
    String location
    String[] names
)
```

getRtspStatusRegex(names) throws ObjectDoesNotExist, InvalidOperation

Get the status code regular expression that each of the named monitors' RTSP response must match.

```
String[] getRtspStatusRegex(
    String[] names
)
```

getRtspStatusRegexByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get the status code regular expression that each of the named monitors' RTSP response must match. This is a location specific function, any action will operate on the specified location.

```
String[] getRtspStatusRegexByLocation(
    String location
    String[] names
)
```

getScope(names) throws ObjectDoesNotExist, InvalidOperation

Get the scope of each named monitor.

```
Catalog.Monitor.Scope[] getScope(
    String[] names
)
```

getSipBodyRegex(names) throws ObjectDoesNotExist, InvalidOperation

Get the body regular expression that that each of the named monitors' SIP response must match.

```
String[] getSipBodyRegex(
    String[] names
```

)

getSipBodyRegexByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get the body regular expression that that each of the named monitors' SIP response must match. This is a location specific function, any action will operate on the specified location.

```
String[] getSipBodyRegexByLocation(
   String location
   String[] names
)
```

getSipStatusRegex(names) throws ObjectDoesNotExist, InvalidOperation

Get the status code regular expression that that each of the named monitors' SIP response must match.

```
String[] getSipStatusRegex(
    String[] names
)
```

getSipStatusRegexByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get the status code regular expression that that each of the named monitors' SIP response must match. This is a location specific function, any action will operate on the specified location.

```
String[] getSipStatusRegexByLocation(
    String location
    String[] names
)
```

getSipTransport(names) throws ObjectDoesNotExist, InvalidOperation

Get the transport protocol that the monitor will use

```
Catalog.Monitor.SipTransport[] getSipTransport(
    String[] names
)
```

getSipTransportByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get the transport protocol that the monitor will use This is a location specific function, any action will operate on the specified location.

```
Catalog.Monitor.SipTransport[]
getSipTransportByLocation(
    String location
    String[] names
)
```

getStatusRegex(names) throws ObjectDoesNotExist, InvalidOperation

Get the status code regular expression that that each of the named monitors' HTTP response must match.

```
String[] getStatusRegex(
    String[] names
)
```

getStatusRegexByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get the status code regular expression that that each of the named monitors' HTTP response must match. This is a location specific function, any action will operate on the specified location.

```
String[] getStatusRegexByLocation(
    String location
    String[] names
)
```

getTimeout(names) throws ObjectDoesNotExist, InvalidOperation

Get the maximum time that an individual instance, of each of the named monitors, is allowed to run for (in seconds).

```
Unsigned Integer[] getTimeout(
    String[] names
)
```

getTimeoutByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get the maximum time that an individual instance, of each of the named monitors, is allowed to run for (in seconds). This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getTimeoutByLocation(
    String location
    String[] names
)
```

getType(names) throws ObjectDoesNotExist, InvalidOperation

Get the internal monitor type to use for each named monitor.

```
Catalog.Monitor.Type[] getType(
    String[] names
)
```

getUDPAcceptAll(names) throws ObjectDoesNotExist, InvalidOperation

Get if the monitor should accept responses from any IP and port. UDP monitors only.

```
Boolean[] getUDPAcceptAll(
    String[] names
)
```

getUDPAcceptAllByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get if the monitor should accept responses from any IP and port. UDP monitors only. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getUDPAcceptAllByLocation(
   String location
   String[] names
)
```

getUseSSL(names) throws ObjectDoesNotExist, InvalidOperation

Get whether each of the named monitors can connect using SSL.

```
Boolean[] getUseSSL(
    String[] names
```

)

getUseSSLByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get whether each of the named monitors can connect using SSL. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getUseSSLByLocation(
    String location
    String[] names
)
```

getVerbose(names) throws ObjectDoesNotExist, InvalidOperation

Get whether each of the named monitors should emit verbose logging (useful for diagnostics).

```
Boolean[] getVerbose(
    String[] names
)
```

getVerboseByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get whether each of the named monitors should emit verbose logging (useful for diagnostics). This is a location specific function, any action will operate on the specified location.

```
Boolean[] getVerboseByLocation(
    String location
    String[] names
)
```

getWriteString(names) throws ObjectDoesNotExist, InvalidOperation

Get the string that each of the named monitors should write down the TCP connection.

```
String[] getWriteString(
    String[] names
)
```

getWriteStringByLocation(location, names) throws ObjectDoesNotExist, InvalidOperation

Get the string that each of the named monitors should write down the TCP connection. This is a location specific function, any action will operate on the specified location.

```
String[] getWriteStringByLocation(
    String location
    String[] names
)
```

removeProgramArguments(names, arguments) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Removes a set of arguments from the specified monitors. The monitors specified must be of type 'program'.

```
void removeProgramArguments(
    String[] names
    String[][] arguments
)
```

renameMonitors(names, new_names) throws ObjectDoesNotExist, ObjectAlreadyExists, InvalidObjectName, DeploymentError, InvalidOperation

Rename these monitors.

```
void renameMonitors(
    String[] names
    String[] new_names
)
```

setAuthentication(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the authentication (user:password) that each of the named monitors should use in the test HTTP request.

```
void setAuthentication(
    String[] names
    String[] values
)
```

setAuthenticationByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the authentication (user:password) that each of the named monitors should use in the test HTTP request. This is a location specific function, any action will operate on the specified location.

```
void setAuthenticationByLocation(
   String location
   String[] names
   String[] values
)
```

setBackOff(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set whether each of the named monitors should back-off after it has failed.

```
void setBackOff(
    String[] names
    Boolean[] values
)
```

setBackOffByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set whether each of the named monitors should back-off after it has failed. This is a location specific function, any action will operate on the specified location.

```
void setBackOffByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setBodyRegex(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the body regular expression that that each of the named monitors' HTTP response must match.

```
void setBodyRegex(
    String[] names
    String[] values
```

)

setBodyRegexByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the body regular expression that that each of the named monitors' HTTP response must match. This is a location specific function, any action will operate on the specified location.

```
void setBodyRegexByLocation(
   String location
   String[] names
   String[] values
)
```

setCloseString(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set an optional string that each of the named monitors should write to the server before closing the connection.

```
void setCloseString(
    String[] names
    String[] values
)
```

setCloseStringByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set an optional string that each of the named monitors should write to the server before closing the connection. This is a location specific function, any action will operate on the specified location.

```
void setCloseStringByLocation(
    String location
    String[] names
    String[] values
)
```

setDelay(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the minimum time between calls to each of the named monitors (in seconds).

```
void setDelay(
```

```
String[] names
Unsigned Integer[] values
)
```

setDelayByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the minimum time between calls to each of the named monitors (in seconds). This is a location specific function, any action will operate on the specified location.

```
void setDelayByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setFailures(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the number of failures required, by each of the named monitors, before a node is classed as unavailable.

```
void setFailures(
    String[] names
    Unsigned Integer[] values
)
```

setFailuresByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the number of failures required, by each of the named monitors, before a node is classed as unavailable. This is a location specific function, any action will operate on the specified location.

```
void setFailuresByLocation(
    String location
    String[] names
    Unsigned Integer[] values
)
```

Catalog.Monitor Function Reference

setHealthOnly(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set whether each of the named monitors should monitor health only (ignore load).

```
void setHealthOnly(
    String[] names
    Boolean[] values
)
```

setHealthOnlyByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set whether each of the named monitors should monitor health only (ignore load). This is a location specific function, any action will operate on the specified location.

```
void setHealthOnlyByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setHostHeader(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the host header that each of the named monitors should use in the test HTTP request.

```
void setHostHeader(
    String[] names
    String[] values
)
```

setHostHeaderByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the host header that each of the named monitors should use in the test HTTP request. This is a location specific function, any action will operate on the specified location.

```
void setHostHeaderByLocation(
   String location
   String[] names
   String[] values
```

Function Reference Catalog.Monitor

)

setMachine(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the machine that each of the named monitors should monitor (must be a valid hostname:port or a hostname for Ping monitors).

```
void setMachine(
    String[] names
    String[] values
)
```

setMachineByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the machine that each of the named monitors should monitor (must be a valid hostname:port or a hostname for Ping monitors). This is a location specific function, any action will operate on the specified location.

```
void setMachineByLocation(
    String location
    String[] names
    String[] values
)
```

setMaxResponseLen(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the maximum amount of data (in bytes) that each of the named monitors should read back from a server (0 = unlimited).

```
void setMaxResponseLen(
    String[] names
    Unsigned Integer[] values
)
```

setMaxResponseLenByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the maximum amount of data (in bytes) that each of the named monitors should read back from a server (0 = unlimited). This is a location specific function, any action will operate on the specified location.

Catalog.Monitor Function Reference

```
void setMaxResponseLenByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setNote(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the note for each of the named Monitors.

```
void setNote(
   String[] names
   String[] values
)
```

setPath(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the path that each of the named monitors should use in the test HTTP request.

```
void setPath(
    String[] names
    String[] values
)
```

setPathByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the path that each of the named monitors should use in the test HTTP request. This is a location specific function, any action will operate on the specified location.

```
void setPathByLocation(
    String location
    String[] names
    String[] values
)
```

Function Reference Catalog.Monitor

setProgram(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the name of the program that each named monitor runs.

```
void setProgram(
    String[] names
    String[] values
)
```

setResponseRegex(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the regular expression that each of the named monitors should match against the server response.

```
void setResponseRegex(
    String[] names
    String[] values
)
```

setResponseRegexByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the regular expression that each of the named monitors should match against the server response. This is a location specific function, any action will operate on the specified location.

```
void setResponseRegexByLocation(
   String location
   String[] names
   String[] values
)
```

setRtspBodyRegex(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the body regular expression that each of the named monitors' RTSP response must match.

```
void setRtspBodyRegex(
    String[] names
    String[] values
)
```

Catalog.Monitor Function Reference

setRtspBodyRegexByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the body regular expression that each of the named monitors' RTSP response must match. This is a location specific function, any action will operate on the specified location.

```
void setRtspBodyRegexByLocation(
   String location
   String[] names
   String[] values
)
```

setRtspPath(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the path that each of the named monitors should use in the test RTSP request.

```
void setRtspPath(
    String[] names
    String[] values
)
```

setRtspPathByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the path that each of the named monitors should use in the test RTSP request. This is a location specific function, any action will operate on the specified location.

```
void setRtspPathByLocation(
    String location
    String[] names
    String[] values
)
```

setRtspStatusRegex(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the status code regular expression that each of the named monitors' RTSP response must match.

```
void setRtspStatusRegex(
    String[] names
    String[] values
```

Function Reference Catalog.Monitor

)

setRtspStatusRegexByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the status code regular expression that each of the named monitors' RTSP response must match. This is a location specific function, any action will operate on the specified location.

```
void setRtspStatusRegexByLocation(
   String location
   String[] names
   String[] values
)
```

setScope(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the scope of each named monitor.

```
void setScope(
    String[] names
    Catalog.Monitor.Scope[] values
)
```

setSipBodyRegex(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the body regular expression that that each of the named monitors' SIP response must match.

```
void setSipBodyRegex(
    String[] names
    String[] values
)
```

setSipBodyRegexByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the body regular expression that that each of the named monitors' SIP response must match. This is a location specific function, any action will operate on the specified location.

```
void setSipBodyRegexByLocation(
   String location
```

Catalog.Monitor Function Reference

```
String[] names
String[] values
)
```

setSipStatusRegex(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the status code regular expression that that each of the named monitors' SIP response must match.

```
void setSipStatusRegex(
    String[] names
    String[] values
)
```

setSipStatusRegexByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the status code regular expression that that each of the named monitors' SIP response must match. This is a location specific function, any action will operate on the specified location.

```
void setSipStatusRegexByLocation(
   String location
   String[] names
   String[] values
)
```

setSipTransport(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the transport protocol that the monitor will use

```
void setSipTransport(
    String[] names
    Catalog.Monitor.SipTransport[] values
)
```

setSipTransportByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the transport protocol that the monitor will use This is a location specific function, any action will operate on the specified location.

Function Reference Catalog.Monitor

```
void setSipTransportByLocation(
   String location
   String[] names
   Catalog.Monitor.SipTransport[] values
)
```

setStatusRegex(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the status code regular expression that that each of the named monitors' HTTP response must match.

```
void setStatusRegex(
    String[] names
    String[] values
)
```

setStatusRegexByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the status code regular expression that that each of the named monitors' HTTP response must match. This is a location specific function, any action will operate on the specified location.

```
void setStatusRegexByLocation(
   String location
   String[] names
   String[] values
)
```

setTimeout(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the maximum time that an individual instance, of each of the named monitors, is allowed to run for (in seconds).

```
void setTimeout(
   String[] names
   Unsigned Integer[] values
)
```

Catalog.Monitor Function Reference

setTimeoutByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the maximum time that an individual instance, of each of the named monitors, is allowed to run for (in seconds). This is a location specific function, any action will operate on the specified location.

```
void setTimeoutByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

setType(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the internal monitor type to use for each named monitor.

```
void setType(
    String[] names
    Catalog.Monitor.Type[] values
)
```

setUDPAcceptAll(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set if the monitor should accept responses from any IP and port. UDP monitors only.

```
void setUDPAcceptAll(
    String[] names
    Boolean[] values
)
```

setUDPAcceptAllByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set if the monitor should accept responses from any IP and port. UDP monitors only. This is a location specific function, any action will operate on the specified location.

```
void setUDPAcceptAllByLocation(
   String location
   String[] names
   Boolean[] values
```

Function Reference Catalog.Monitor

)

setUseSSL(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set whether each of the named monitors can connect using SSL.

```
void setUseSSL(
    String[] names
    Boolean[] values
)
```

setUseSSLByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set whether each of the named monitors can connect using SSL. This is a location specific function, any action will operate on the specified location.

```
void setUseSSLByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setVerbose(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set whether each of the named monitors should emit verbose logging (useful for diagnostics).

```
void setVerbose(
   String[] names
   Boolean[] values
)
```

setVerboseByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set whether each of the named monitors should emit verbose logging (useful for diagnostics). This is a location specific function, any action will operate on the specified location.

```
void setVerboseByLocation(
    String location
```

Catalog.Monitor Function Reference

```
String[] names
Boolean[] values
)
```

setWriteString(names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the string that each of the named monitors should write down the TCP connection.

```
void setWriteString(
    String[] names
    String[] values
)
```

setWriteStringByLocation(location, names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Set the string that each of the named monitors should write down the TCP connection. This is a location specific function, any action will operate on the specified location.

```
void setWriteStringByLocation(
    String location
    String[] names
    String[] values
)
```

updateProgramArguments(names, argument_names, new_arguments) throws ObjectDoesNotExist, DeploymentError, InvalidInput, InvalidOperation

Allows arguments for the the specified monitors to be changed. The monitors specified must be of type 'program'.

```
void updateProgramArguments(
    String[] names
    String[][] argument_names
    Catalog.Monitor.Argument[][] new_arguments
)
```

Function Reference Catalog.Monitor

uploadMonitorProgram(name, content) throws InvalidObjectName, DeploymentError

Uploads a monitor program, overwriting the file if it already exists.

```
void uploadMonitorProgram(
    String name
    Binary Data content
)
```

Structures

Catalog.Monitor.Argument

An argument that is added to the command line when the monitor program is run

```
struct Catalog.Monitor.Argument {
    # The name of the argument.
    String name;

# The value of the argument.
    String value;

# A description of the argument.
    String description;
}
```

Enumerations

Catalog.Monitor.Scope

```
enum Catalog.Monitor.Scope {
    # Node: Monitor each node in the pool separately
    pernode,

# Pool/GLB: Monitor a specified machine
    poolwide
}
```

Catalog.Monitor Function Reference

Catalog.Monitor.SipTransport

```
enum Catalog.Monitor.SipTransport {
    # UDP
    udp,

# TCP
    tcp
}
```

Catalog.Monitor.Type

```
enum Catalog.Monitor.Type {
   # Ping monitor
   ping,
   # TCP Connect monitor
   connect,
   # HTTP monitor
   http,
   # TCP transaction monitor
   tcp_transaction,
   # External program monitor
   program,
   # SIP monitor
   sip,
   # RTSP monitor
   rtsp
}
```

Catalog.SSL.Certificates

URI: http://soap.zeus.com/zxtm/1.0/Catalog/SSL/Certificates/

The Catalog.SSL.Certificates interface allows management of SSL Certificates which are used for SSL decryption of services. Using this interface, you can create, delete and rename SSL Certificate objects.

Methods

createSelfSignedCertificate(names, details) throws InvalidObjectName, ObjectAlreadyExists, InvalidInput, DeploymentError

Create new self-signed certificates.

```
void createSelfSignedCertificate(
    String[] names
    Catalog.SSL.Certificates.CertificateDetails[]
details
)
```

deleteCertificate(names) throws InvalidObjectName, ObjectDoesNotExist

Delete the named certificates.

```
void deleteCertificate(
    String[] names
)
```

getCertificateInfo(names) throws ObjectDoesNotExist

Get the information about the named certificates.

```
Certificate[] getCertificateInfo(
    String[] names
)
```

getCertificateNames()

Get the names of the installed certificates.

```
String[] getCertificateNames()
```

getCertificateRequest(names) throws ObjectDoesNotExist

Get Certificate signing requests for the named certificates.

```
String[] getCertificateRequest(
    String[] names
)
```

getRawCertificate(names) throws ObjectDoesNotExist

Get the raw (PEM-encoded) certificates.

```
String[] getRawCertificate(
    String[] names
)
```

importCertificate(names, keys) throws InvalidObjectName, ObjectAlreadyExists, InvalidInput

Create a new certificate, importing the certificate and private key.

```
void importCertificate(
    String[] names
    CertificateFiles[] keys
)
```

renameCertificate(names, new_names) throws InvalidObjectName, ObjectAlreadyExists, ObjectDoesNotExist

Rename the named certificates.

```
void renameCertificate(
    String[] names
    String[] new_names
)
```

setRawCertificate(names, certs) throws ObjectDoesNotExist

Set the (PEM-encoded) certificate. This should be used after getting a Certificate request signed by a certificate authority.

```
void setRawCertificate(
   String[] names
   String[] certs
)
```

Structures

Catalog.SSL.Certificates.CertificateDetails

This structure contains the information used when generating self-signed test certificates.

```
struct Catalog.SSL.Certificates.CertificateDetails {
   # The subject of the new certificate. The
common_name of the
   # subject should match the DNS name of the service
this
   # certificate is to be used for.
   X509Name subject;
   # The number of days this certificate should be
value for
   # (e.g. 365 for 1 years validity)
   Integer valid days;
   # The size of the generated private key. Use 1024
for normal
   # use, or 2048 for more security
   Integer key size;
}
```

Certificate

This structure contains information (such as the subject and issuer) about a certificate.

```
struct Certificate {
    # The version of the X509 Certificate
    Integer version;

# The serial number of the Certificate
    String serial;

# The issuer (i.e. who signed it) of the
Certificate
```

```
X509Name issuer;
   # The subject (i.e. who it is for) of the
Certificate
   X509Name subject;
   # The time the certificate is valid from.
   Time valid from;
   # The time the certificate is valid to.
   Time valid to;
   # The modulus of the certificate.
   String modulus;
   # The exponent of the certificate.
  String exponent;
   # Whether the certificate is self-signed (i.e. the
issuer is
   # the same as the subject)
  Boolean self signed;
}
```

CertificateFiles

This structure contains a public certificate and private key. It is used when importing certificates into the traffic manager.

```
struct CertificateFiles {
    # The PEM-encoded public certificate (containing
the BEGIN
    # CERTIFICATE and END CERTIFICATE tags)
    String public_cert;

# The PEM-encoded private key (containing the
BEGIN RSA
```

```
# PRIVATE KEY and END RSA PRIVATE KEY tags)
String private_key;
}
```

X509Name

This structure contains a representation of an X509 Name object. These are used inside Certificate objects to represent the issuer and subject of the certificate.

```
struct X509Name {
   # The common name (CN). This is usually the name
of the site
   # the certificate is issued to (e.g.
"secure.example.com")
   String common name;
   # The two-letter country code.
   String country;
   # The location (town or city).
   String location;
   # The state, this is only needed if the country is
'US'.
   String state;
   # The name of the organisation
   String organisation;
   # The unit inside the organisation
   String unit;
   # An email address. This is usually empty.
   String email;
}
```

Catalog.SSL.CertificateAuthorities

URI: http://soap.zeus.com/zxtm/1.0/Catalog/SSL/CertificateAuthorities/

The Catalog.SSL.CertificateAuthorities interface allows management of SSL Certificate Authorities which are used to authenticate back-end nodes when doing SSL encryption.

Methods

deleteCertificateAuthority(names) throws ObjectDoesNotExist

Delete the named Certificate Authority and associated Revocation list.

```
void deleteCertificateAuthority(
    String[] names
)
```

getCertificateAuthorityInfo(names) throws ObjectDoesNotExist

Get the Certificate Information, and the revoked certificates.

```
Catalog.SSL.CertificateAuthorities.Details[]
getCertificateAuthorityInfo(
    String[] names
)
```

getCertificateAuthorityNames()

Get the names of the configured Certificate Authorities.

```
String[] getCertificateAuthorityNames()
```

getRawCertificate(names) throws ObjectDoesNotExist

Get the raw PEM encoded Certificate for the named Certificate Authorities.

```
String[] getRawCertificate(
    String[] names
)
```

importCRL(crls) throws InvalidInput, ObjectDoesNotExist

Import Certificate Revocation Lists. The associated Certificate Authority certificates should already be imported.

```
void importCRL(
```

```
String[] crls
)
```

importCertificateAuthority(names, certs) throws InvalidObjectName, ObjectAlreadyExists, InvalidInput

Import new Certificate Authorities.

```
void importCertificateAuthority(
    String[] names
    String[] certs
)
```

renameCertificateAuthority(names, new_names) throws InvalidObjectName, ObjectDoesNotExist, ObjectAlreadyExists, InvalidOperation

Rename the named Certificate Authorities.

```
void renameCertificateAuthority(
    String[] names
    String[] new_names
)
```

Structures

Catalog.SSL.CertificateAuthorities.CRL

This structure contains the information about a Certificate Revocation list.

```
# The time when the CRL was updated
Time update;

# The time that the CRL will next be updated.
Time next_update;

# The list of revoked certificates
Catalog.SSL.CertificateAuthorities.RevokedCert[]
revoked_certs;
```

Catalog.SSL.CertificateAuthorities.Details

This structure contains the information about a Certificate Authority. It contains both the Certificate, and the list of revoked Certificates contained in the associated CRL.

```
struct Catalog.SSL.CertificateAuthorities.Details {
    # The Certificate Authority certificate
    Certificate certificate;

# If set to 'true' then there is an associated
CRL, otherwise

# the CRL structure contains no useful information
Boolean have_crl;

# The associated CRL.
Catalog.SSL.CertificateAuthorities.CRL crl;
}
```

Catalog.SSL.CertificateAuthorities.RevokedCert

This structure contains the information about a revoked Certificate.

```
struct Catalog.SSL.CertificateAuthorities.RevokedCert
{
    # The serial number of the revoked certificate
    String serial;

# The time that the certificate was revoked
    Time revocation_date;
}
```

Certificate

This structure contains information (such as the subject and issuer) about a certificate.

```
struct Certificate {
    # The version of the X509 Certificate
    Integer version;
```

```
# The serial number of the Certificate
   String serial;
   # The issuer (i.e. who signed it) of the
Certificate
   X509Name issuer;
   # The subject (i.e. who it is for) of the
Certificate
  X509Name subject;
   # The time the certificate is valid from.
   Time valid from;
   # The time the certificate is valid to.
   Time valid to;
   # The modulus of the certificate.
   String modulus;
   # The exponent of the certificate.
   String exponent;
   # Whether the certificate is self-signed (i.e. the
issuer is
   # the same as the subject)
   Boolean self signed;
}
```

CertificateFiles

This structure contains a public certificate and private key. It is used when importing certificates into the traffic manager.

```
struct CertificateFiles {
    # The PEM-encoded public certificate (containing
the BEGIN
```

```
# CERTIFICATE and END CERTIFICATE tags)
String public_cert;

# The PEM-encoded private key (containing the BEGIN RSA
# PRIVATE KEY and END RSA PRIVATE KEY tags)
String private_key;
}
```

X509Name

This structure contains a representation of an X509 Name object. These are used inside Certificate objects to represent the issuer and subject of the certificate.

```
struct X509Name {
   # The common name (CN). This is usually the name
   # the certificate is issued to (e.g.
"secure.example.com")
   String common name;
   # The two-letter country code.
   String country;
   # The location (town or city).
   String location;
   # The state, this is only needed if the country is
'US'.
   String state;
   # The name of the organisation
   String organisation;
   # The unit inside the organisation
   String unit;
```

```
# An email address. This is usually empty.
String email;
}
```

Catalog.SSL.ClientCertificates

URI: http://soap.zeus.com/zxtm/1.0/Catalog/SSL/ClientCertificates/

The Catalog.SSL.ClientCertificates interface allows management of SSL Client Certificates which are for authentication with back-end nodes when encrypting services. This interfaces allows you to import, retrieve, rename and delete the SSL Client Certificate objects

Methods

deleteClientCertificate(names) throws ObjectDoesNotExist

Delete the named client certificates.

```
void deleteClientCertificate(
    String[] names
)
```

getClientCertificateInfo(names) throws ObjectDoesNotExist

Gets the information about the named client certificates.

```
Certificate[] getClientCertificateInfo(
    String[] names
)
```

getClientCertificateNames()

Get the names of the installed client certificates.

```
String[] getClientCertificateNames()
```

importClientCertificate(names, keys) throws InvalidObjectName, ObjectAlreadyExists, InvalidInput

Import client certificates and associated private keys.

```
void importClientCertificate(
    String[] names
```

```
CertificateFiles[] keys
)
```

renameClientCertificate(names, new_names) throws ObjectAlreadyExists, ObjectDoesNotExist, DeploymentError

Rename the named client certificates.

```
void renameClientCertificate(
    String[] names
    String[] new_names
)
```

Structures

Certificate

This structure contains information (such as the subject and issuer) about a certificate.

```
struct Certificate {
    # The version of the X509 Certificate
    Integer version;

# The serial number of the Certificate
    String serial;

# The issuer (i.e. who signed it) of the
Certificate
    X509Name issuer;

# The subject (i.e. who it is for) of the
Certificate
    X509Name subject;

# The time the certificate is valid from.
    Time valid_from;

# The time the certificate is valid to.
```

```
Time valid_to;

# The modulus of the certificate.
String modulus;

# The exponent of the certificate.
String exponent;

# Whether the certificate is self-signed (i.e. the issuer is

# the same as the subject)
Boolean self_signed;
}
```

CertificateFiles

This structure contains a public certificate and private key. It is used when importing certificates into the traffic manager.

```
# The PEM-encoded public certificate (containing
the BEGIN

# CERTIFICATE and END CERTIFICATE tags)

String public_cert;

# The PEM-encoded private key (containing the
BEGIN RSA

# PRIVATE KEY and END RSA PRIVATE KEY tags)

String private_key;
}
```

X509Name

This structure contains a representation of an X509 Name object. These are used inside Certificate objects to represent the issuer and subject of the certificate.

```
# the certificate is issued to (e.g.
"secure.example.com")
  String common name;
  # The two-letter country code.
  String country;
   # The location (town or city).
  String location;
  # The state, this is only needed if the country is
'US'.
  String state;
   # The name of the organisation
  String organisation;
   # The unit inside the organisation
  String unit;
  # An email address. This is usually empty.
  String email;
}
```

Catalog.SSL.DNSSEC

URI: http://soap.zeus.com/zxtm/1.0/Catalog/SSL/DNSSEC/

The Catalog.SSL.DNSSEC interface allows management of the DNSSEC private keys used to alter signed GLB DNS responses.

Methods

addKeysWithManualIDs(names, keys, ids) throws ObjectAlreadyExists, InvalidObjectName, InvalidInput

Upload a DNSSEC private key to the traffic manager's catalog. Each key string should be the contents of your private key file. The ID of the key is the third set of parameters.

```
void addKeysWithManualIDs(
    String[] names
    String[] keys
    Integer[] ids
)
```

addStandardKeys(names, keys) throws ObjectAlreadyExists, InvalidObjectName, InvalidInput

Upload a DNSSEC private key to the traffic manager's catalog. Each key string should be the contents of your private key file. The ID of the key will be calculated assuming it is a standard ZSK.

```
void addStandardKeys(
    String[] names
    String[] keys
)
```

deleteKeys(names) throws ObjectInUse, ObjectDoesNotExist, DeploymentError

Delete the specified DNSSEC keys.

```
void deleteKeys(
    String[] names
)
```

getKeyIDs(names) throws ObjectDoesNotExist

Get the IDs of the specified DNSSEC private keys.

```
Integer[] getKeyIDs(
    String[] names
)
```

getKeyNames()

Get the names of the installed DNSSEC private keys.

```
String[] getKeyNames()
```

Catalog.Protection Function Reference

renameKeys(names, new_names) throws ObjectDoesNotExist, InvalidInput, InvalidObjectName, ObjectAlreadyExists, DeploymentError

Rename the specified DNSSEC keys.

```
void renameKeys(
    String[] names
    String[] new_names
)
```

Catalog.Protection

```
URI: http://soap.zeus.com/zxtm/1.0/Catalog/Protection/
```

The Catalog. Protection interface allows management of Service Protection classes. Using this interface, you can create, delete and rename Protection classes, and manage their configuration.

Methods

addAllowedAddresses(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Add new IP addresses and CIDR IP subnets to the list of machines that are always allowed access.

```
void addAllowedAddresses(
    String[] class_names
    String[][] values
)
```

addAllowedAddressesByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Add new IP addresses and CIDR IP subnets to the list of machines that are always allowed access. This is a location specific function, any action will operate on the specified location.

```
void addAllowedAddressesByLocation(
   String location
   String[] class_names
   String[][] values
)
```

Function Reference Catalog.Protection

addBannedAddresses(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Add new IP addresses and CIDR IP subnets to the list of machines that aren't allowed access.

```
void addBannedAddresses(
    String[] class_names
    String[][] values
)
```

addBannedAddressesByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Add new IP addresses and CIDR IP subnets to the list of machines that aren't allowed access. This is a location specific function, any action will operate on the specified location.

```
void addBannedAddressesByLocation(
   String location
   String[] class_names
   String[][] values
)
```

addProtection(class_names) throws ObjectAlreadyExists, InvalidObjectName, DeploymentError

Add new Protection classes.

```
void addProtection(
    String[] class_names
)
```

copyProtection(class_names, new_names) throws ObjectDoesNotExist, ObjectAlreadyExists, InvalidObjectName, DeploymentError

Copy the named Protection classes.

```
void copyProtection(
    String[] class_names
    String[] new_names
)
```

Catalog.Protection Function Reference

deleteProtection(class_names) throws ObjectInUse, ObjectDoesNotExist, DeploymentError

Delete the named Protection classes.

```
void deleteProtection(
    String[] class_names
)
```

getAllowedAddresses(class_names) throws ObjectDoesNotExist

Get the list of IP addresses and CIDR IP subnets that are always allowed access.

```
String[][] getAllowedAddresses(
    String[] class_names
)
```

getAllowedAddressesByLocation(location, class_names) throws ObjectDoesNotExist

Get the list of IP addresses and CIDR IP subnets that are always allowed access. This is a location specific function, any action will operate on the specified location.

```
String[][] getAllowedAddressesByLocation(
    String location
    String[] class_names
)
```

getBannedAddresses(class_names) throws ObjectDoesNotExist

Get the list of IP addresses and CIDR IP subnets that aren't allowed access.

```
String[][] getBannedAddresses(
    String[] class_names
)
```

getBannedAddressesByLocation(location, class_names) throws ObjectDoesNotExist

Get the list of IP addresses and CIDR IP subnets that aren't allowed access. This is a location specific function, any action will operate on the specified location.

```
String[][] getBannedAddressesByLocation(
    String location
```

Function Reference Catalog.Protection

```
String[] class_names
)
```

getDebug(class_names) throws ObjectDoesNotExist

Get whether the service protection classes are in debug mode. When in debug mode, verbose log messages are written.

```
Boolean[] getDebug(
    String[] class_names
)
```

getDebugByLocation(location, class_names) throws ObjectDoesNotExist

Get whether the service protection classes are in debug mode. When in debug mode, verbose log messages are written. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getDebugByLocation(
    String location
    String[] class_names
)
```

getEnabled(class_names) throws ObjectDoesNotExist

Get whether the service protection classes are enabled.

```
Boolean[] getEnabled(
    String[] class_names
)
```

getEnabledByLocation(location, class_names) throws ObjectDoesNotExist

Get whether the service protection classes are enabled. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getEnabledByLocation(
    String location
    String[] class_names
)
```

Catalog.Protection Function Reference

getHTTPCheckRfc2396(class_names) throws ObjectDoesNotExist

Get whether requests with poorly-formed URLs (as specified in RFC 2396) should be rejected.

```
Boolean[] getHTTPCheckRfc2396(
    String[] class_names
)
```

getHTTPCheckRfc2396ByLocation(location, class_names) throws ObjectDoesNotExist

Get whether requests with poorly-formed URLs (as specified in RFC 2396) should be rejected. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getHTTPCheckRfc2396ByLocation(
    String location
    String[] class_names
)
```

getHTTPRejectBinary(class_names) throws ObjectDoesNotExist

Get whether requests containing binary data (after decoding) should be rejected.

```
Boolean[] getHTTPRejectBinary(
    String[] class_names
)
```

getHTTPRejectBinaryByLocation(location, class_names) throws ObjectDoesNotExist

Get whether requests containing binary data (after decoding) should be rejected. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getHTTPRejectBinaryByLocation(
    String location
    String[] class_names
)
```

getHTTPSendErrorPage(class_names) throws ObjectDoesNotExist

Get whether an HTTP error message should be sent when a connection is dropped, rather than just dropping the connection.

```
Boolean[] getHTTPSendErrorPage(
```

Function Reference Catalog.Protection

```
String[] class_names
)
```

getHTTPSendErrorPageByLocation(location, class_names) throws ObjectDoesNotExist

Get whether an HTTP error message should be sent when a connection is dropped, rather than just dropping the connection. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getHTTPSendErrorPageByLocation(
    String location
    String[] class_names
)
```

getLogInterval(class_names) throws ObjectDoesNotExist

Get the interval between logging service protection messages (in seconds).

```
Unsigned Integer[] getLogInterval(
    String[] class_names
)
```

getLogIntervalByLocation(location, class_names) throws ObjectDoesNotExist

Get the interval between logging service protection messages (in seconds). This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getLogIntervalByLocation(
    String location
    String[] class_names
)
```

getMax10Connections(class_names) throws ObjectDoesNotExist

Get the maximum number of simultaneous connections allowed from the 10 busiest IP addresses.

```
Unsigned Integer[] getMax10Connections(
    String[] class_names
)
```

Catalog.Protection Function Reference

getMax10ConnectionsByLocation(location, class_names) throws ObjectDoesNotExist

Get the maximum number of simultaneous connections allowed from the 10 busiest IP addresses. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getMax10ConnectionsByLocation(
    String location
    String[] class_names
)
```

getMax1Connections(class_names) throws ObjectDoesNotExist

Get the maximum number of simultaneous connections allowed from an individual IP address.

```
Unsigned Integer[] getMax1Connections(
    String[] class_names
)
```

getMax1ConnectionsByLocation(location, class_names) throws ObjectDoesNotExist

Get the maximum number of simultaneous connections allowed from an individual IP address. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getMax1ConnectionsByLocation(
    String location
    String[] class_names
)
```

getMaxConnectionRate(class_names) throws ObjectDoesNotExist

Get the maximum number of connections and HTTP keepalive requests allowed from 1 IP address in the 'rate_timer' interval (0 means unlimited).

```
Unsigned Integer[] getMaxConnectionRate(
    String[] class_names
)
```

Function Reference Catalog.Protection

getMaxConnectionRateByLocation(location, class_names) throws ObjectDoesNotExist

Get the maximum number of connections and HTTP keepalive requests allowed from 1 IP address in the 'rate_timer' interval (0 means unlimited). This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getMaxConnectionRateByLocation(
    String location
    String[] class_names
)
```

getMaxHTTPBodyLength(class_names) throws ObjectDoesNotExist

Get the maximum size of the HTTP request body data (in bytes, 0 means no limit).

```
Unsigned Integer[] getMaxHTTPBodyLength(
    String[] class_names
)
```

getMaxHTTPBodyLengthByLocation(location, class_names) throws ObjectDoesNotExist

Get the maximum size of the HTTP request body data (in bytes, 0 means no limit). This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getMaxHTTPBodyLengthByLocation(
    String location
    String[] class_names
)
```

getMaxHTTPHeaderLength(class_names) throws ObjectDoesNotExist

Get the maximum size of a single HTTP request header (in bytes, 0 means no limit).

```
Unsigned Integer[] getMaxHTTPHeaderLength(
    String[] class_names
)
```

getMaxHTTPHeaderLengthByLocation(location, class_names) throws ObjectDoesNotExist

Get the maximum size of a single HTTP request header (in bytes, 0 means no limit). This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getMaxHTTPHeaderLengthByLocation(
    String location
    String[] class_names
)
```

getMaxHTTPRequestLength(class_names) throws ObjectDoesNotExist

Get the maximum size of all the HTTP request headers (in bytes, 0 means no limit).

```
Unsigned Integer[] getMaxHTTPRequestLength(
    String[] class_names
)
```

getMaxHTTPRequestLengthByLocation(location, class_names) throws ObjectDoesNotExist

Get the maximum size of all the HTTP request headers (in bytes, 0 means no limit). This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getMaxHTTPRequestLengthByLocation(
    String location
    String[] class_names
)
```

getMaxHTTPURLLength(class names) throws ObjectDoesNotExist

Get the maximum size of the request URL (in bytes, 0 means no limit).

```
Unsigned Integer[] getMaxHTTPURLLength(
    String[] class_names
)
```

getMaxHTTPURLLengthByLocation(location, class_names) throws ObjectDoesNotExist

Get the maximum size of the request URL (in bytes, 0 means no limit). This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getMaxHTTPURLLengthByLocation(
    String location
    String[] class_names
)
```

Function Reference Catalog.Protection

getMinConnections(class_names) throws ObjectDoesNotExist

Get the number of simultaneous connections that are always allowed from each IP address (0 means unlimited).

```
Unsigned Integer[] getMinConnections(
    String[] class_names
)
```

getMinConnectionsByLocation(location, class_names) throws ObjectDoesNotExist

Get the number of simultaneous connections that are always allowed from each IP address (0 means unlimited). This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getMinConnectionsByLocation(
    String location
    String[] class_names
)
```

getNote(class_names) throws ObjectDoesNotExist

Get the note for each of the named Protection classes

```
String[] getNote(
    String[] class_names
)
```

getProtectionNames()

Get the names of all the configured Protection classes.

```
String[] getProtectionNames()
```

getRateTimer(class_names) throws ObjectDoesNotExist

Get how frequently the max_connection_rate is assessed. For example, a value of 1 second will impose a limit of max connections/second; a value of 60 will impose a limit of max connections/minute controlling how our connection rates are calculated.

```
Unsigned Integer[] getRateTimer(
    String[] class_names
)
```

getRateTimerByLocation(location, class_names) throws ObjectDoesNotExist

Get how frequently the max_connection_rate is assessed. For example, a value of 1 second will impose a limit of max connections/second; a value of 60 will impose a limit of max connections/minute controlling how our connection rates are calculated. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getRateTimerByLocation(
    String location
    String[] class_names
)
```

getRule(class_names) throws ObjectDoesNotExist

Get the TrafficScript rule to be applied to all connections.

```
String[] getRule(
    String[] class_names
)
```

getRuleByLocation(location, class_names) throws ObjectDoesNotExist

Get the TrafficScript rule to be applied to all connections. This is a location specific function, any action will operate on the specified location.

```
String[] getRuleByLocation(
    String location
    String[] class_names
)
```

getTesting(class_names) throws ObjectDoesNotExist

Get whether the service protection classes are in testing mode. When in testing mode the class logs when a connection would be dropped, but it allows all connections through.

```
Boolean[] getTesting(
    String[] class_names
)
```

Function Reference Catalog.Protection

getTestingByLocation(location, class_names) throws ObjectDoesNotExist

Get whether the service protection classes are in testing mode. When in testing mode the class logs when a connection would be dropped, but it allows all connections through. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getTestingByLocation(
    String location
    String[] class_names
)
```

removeAllowedAddresses(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Remove IP addresses and CIDR IP subnets from the list of machines that are always allowed access.

```
void removeAllowedAddresses(
    String[] class_names
    String[][] values
)
```

removeAllowedAddressesByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Remove IP addresses and CIDR IP subnets from the list of machines that are always allowed access. This is a location specific function, any action will operate on the specified location.

```
void removeAllowedAddressesByLocation(
   String location
   String[] class_names
   String[][] values
)
```

removeBannedAddresses(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Remove IP addresses and CIDR IP subnets from the list of machines that aren't allowed access.

```
void removeBannedAddresses(
    String[] class_names
    String[][] values
)
```

removeBannedAddressesByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Remove IP addresses and CIDR IP subnets from the list of machines that aren't allowed access. This is a location specific function, any action will operate on the specified location.

```
void removeBannedAddressesByLocation(
   String location
   String[] class_names
   String[][] values
)
```

renameProtection(class_names, new_names) throws ObjectDoesNotExist, ObjectAlreadyExists, InvalidObjectName, DeploymentError, InvalidOperation

Rename the named Protection classes.

```
void renameProtection(
    String[] class_names
    String[] new_names
)
```

setAllowedAddresses(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the list of IP addresses and CIDR IP subnets that are always allowed access.

```
void setAllowedAddresses(
    String[] class_names
    String[][] values
)
```

setAllowedAddressesByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the list of IP addresses and CIDR IP subnets that are always allowed access. This is a location specific function, any action will operate on the specified location.

```
void setAllowedAddressesByLocation(
    String location
    String[] class names
```

Function Reference Catalog.Protection

```
String[][] values
```

setBannedAddresses(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the list of IP addresses and CIDR IP subnets that aren't allowed access.

```
void setBannedAddresses(
    String[] class_names
    String[][] values
)
```

setBannedAddressesByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the list of IP addresses and CIDR IP subnets that aren't allowed access. This is a location specific function, any action will operate on the specified location.

```
void setBannedAddressesByLocation(
   String location
   String[] class_names
   String[][] values
)
```

setDebug(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set whether the service protection classes are in debug mode. When in debug mode, verbose log messages are written.

```
void setDebug(
    String[] class_names
    Boolean[] values
)
```

setDebugByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set whether the service protection classes are in debug mode. When in debug mode, verbose log messages are written. This is a location specific function, any action will operate on the specified location.

```
void setDebugByLocation(
   String location
   String[] class_names
   Boolean[] values
)
```

setEnabled(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set whether the service protection classes are enabled.

```
void setEnabled(
   String[] class_names
   Boolean[] values
)
```

setEnabledByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set whether the service protection classes are enabled. This is a location specific function, any action will operate on the specified location.

```
void setEnabledByLocation(
   String location
   String[] class_names
   Boolean[] values
)
```

setHTTPCheckRfc2396(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set whether requests with poorly-formed URLs (as specified in RFC 2396) should be rejected.

```
void setHTTPCheckRfc2396(
    String[] class_names
    Boolean[] values
)
```

Function Reference Catalog.Protection

setHTTPCheckRfc2396ByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set whether requests with poorly-formed URLs (as specified in RFC 2396) should be rejected. This is a location specific function, any action will operate on the specified location.

```
void setHTTPCheckRfc2396ByLocation(
   String location
   String[] class_names
   Boolean[] values
)
```

setHTTPRejectBinary(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set whether requests containing binary data (after decoding) should be rejected.

```
void setHTTPRejectBinary(
    String[] class_names
    Boolean[] values
)
```

setHTTPRejectBinaryByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set whether requests containing binary data (after decoding) should be rejected. This is a location specific function, any action will operate on the specified location.

```
void setHTTPRejectBinaryByLocation(
   String location
   String[] class_names
   Boolean[] values
)
```

setHTTPSendErrorPage(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set whether an HTTP error message should be sent when a connection is dropped, rather than just dropping the connection.

```
void setHTTPSendErrorPage(
    String[] class_names
    Boolean[] values
```

)

setHTTPSendErrorPageByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set whether an HTTP error message should be sent when a connection is dropped, rather than just dropping the connection. This is a location specific function, any action will operate on the specified location.

```
void setHTTPSendErrorPageByLocation(
   String location
   String[] class_names
   Boolean[] values
)
```

setLogInterval(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the interval between logging service protection messages (in seconds).

```
void setLogInterval(
    String[] class_names
    Unsigned Integer[] values
)
```

setLogIntervalByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the interval between logging service protection messages (in seconds). This is a location specific function, any action will operate on the specified location.

```
void setLogIntervalByLocation(
   String location
   String[] class_names
   Unsigned Integer[] values
)
```

setMax10Connections(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the maximum number of simultaneous connections allowed from the 10 busiest IP addresses.

```
void setMax10Connections(
```

Function Reference Catalog.Protection

```
String[] class_names
Unsigned Integer[] values
)
```

setMax10ConnectionsByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the maximum number of simultaneous connections allowed from the 10 busiest IP addresses. This is a location specific function, any action will operate on the specified location.

```
void setMax10ConnectionsByLocation(
   String location
   String[] class_names
   Unsigned Integer[] values
)
```

setMax1Connections(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the maximum number of simultaneous connections allowed from an individual IP address.

```
void setMax1Connections(
    String[] class_names
    Unsigned Integer[] values
)
```

setMax1ConnectionsByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the maximum number of simultaneous connections allowed from an individual IP address. This is a location specific function, any action will operate on the specified location.

```
void setMax1ConnectionsByLocation(
   String location
   String[] class_names
   Unsigned Integer[] values
)
```

setMaxConnectionRate(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the maximum number of connections and HTTP keepalive requests allowed from 1 IP address in the 'rate_timer' interval (0 means unlimited).

```
void setMaxConnectionRate(
    String[] class_names
    Unsigned Integer[] values
)
```

setMaxConnectionRateByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the maximum number of connections and HTTP keepalive requests allowed from 1 IP address in the 'rate_timer' interval (0 means unlimited). This is a location specific function, any action will operate on the specified location.

```
void setMaxConnectionRateByLocation(
   String location
   String[] class_names
   Unsigned Integer[] values
)
```

setMaxHTTPBodyLength(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the maximum size of the HTTP request body data (in bytes, 0 means no limit).

```
void setMaxHTTPBodyLength(
    String[] class_names
    Unsigned Integer[] values
)
```

setMaxHTTPBodyLengthByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the maximum size of the HTTP request body data (in bytes, 0 means no limit). This is a location specific function, any action will operate on the specified location.

```
void setMaxHTTPBodyLengthByLocation(
    String location
    String[] class_names
```

Function Reference Catalog.Protection

```
Unsigned Integer[] values
```

setMaxHTTPHeaderLength(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the maximum size of a single HTTP request header (in bytes, 0 means no limit).

```
void setMaxHTTPHeaderLength(
    String[] class_names
    Unsigned Integer[] values
)
```

setMaxHTTPHeaderLengthByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the maximum size of a single HTTP request header (in bytes, 0 means no limit). This is a location specific function, any action will operate on the specified location.

```
void setMaxHTTPHeaderLengthByLocation(
   String location
   String[] class_names
   Unsigned Integer[] values
)
```

setMaxHTTPRequestLength(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the maximum size of all the HTTP request headers (in bytes, 0 means no limit).

```
void setMaxHTTPRequestLength(
    String[] class_names
    Unsigned Integer[] values
)
```

setMaxHTTPRequestLengthByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the maximum size of all the HTTP request headers (in bytes, 0 means no limit). This is a location specific function, any action will operate on the specified location.

```
void setMaxHTTPRequestLengthByLocation(
```

```
String location

String[] class_names

Unsigned Integer[] values
```

setMaxHTTPURLLength(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the maximum size of the request URL (in bytes, 0 means no limit).

```
void setMaxHTTPURLLength(
    String[] class_names
    Unsigned Integer[] values
)
```

setMaxHTTPURLLengthByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the maximum size of the request URL (in bytes, 0 means no limit). This is a location specific function, any action will operate on the specified location.

```
void setMaxHTTPURLLengthByLocation(
   String location
   String[] class_names
   Unsigned Integer[] values
)
```

setMinConnections(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the number of simultaneous connections that are always allowed from each IP address (0 means unlimited).

```
void setMinConnections(
    String[] class_names
    Unsigned Integer[] values
)
```

Function Reference Catalog.Protection

setMinConnectionsByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the number of simultaneous connections that are always allowed from each IP address (0 means unlimited). This is a location specific function, any action will operate on the specified location.

```
void setMinConnectionsByLocation(
   String location
   String[] class_names
   Unsigned Integer[] values
)
```

setNote(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the note for each of the named Protection classes

```
void setNote(
    String[] class_names
    String[] values
)
```

setRateTimer(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set how frequently the max_connection_rate is assessed. For example, a value of 1 second will impose a limit of max connections/second; a value of 60 will impose a limit of max connections/minute controlling how our connection rates are calculated.

```
void setRateTimer(
    String[] class_names
    Unsigned Integer[] values
)
```

setRateTimerByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set how frequently the max_connection_rate is assessed. For example, a value of 1 second will impose a limit of max connections/second; a value of 60 will impose a limit of max connections/minute controlling how our connection rates are calculated. This is a location specific function, any action will operate on the specified location.

```
void setRateTimerByLocation(
    String location
```

```
String[] class_names
Unsigned Integer[] values
)
```

setRule(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the TrafficScript rule to be applied to all connections.

```
void setRule(
    String[] class_names
    String[] values
)
```

setRuleByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the TrafficScript rule to be applied to all connections. This is a location specific function, any action will operate on the specified location.

```
void setRuleByLocation(
    String location
    String[] class_names
    String[] values
)
```

setTesting(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set whether the service protection classes are in testing mode. When in testing mode the class logs when a connection would be dropped, but it allows all connections through.

```
void setTesting(
    String[] class_names
    Boolean[] values
)
```

Function Reference Catalog.Persistence

setTestingByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set whether the service protection classes are in testing mode. When in testing mode the class logs when a connection would be dropped, but it allows all connections through. This is a location specific function, any action will operate on the specified location.

```
void setTestingByLocation(
    String location
    String[] class_names
    Boolean[] values
)
```

Catalog.Persistence

URI: http://soap.zeus.com/zxtm/1.0/Catalog/Persistence/

The Catalog.Persistence interface allows management of Persistence classes. Using this interface, you can create, delete and rename persistence classes, and manage their configuration.

Methods

addPersistence(class_names) throws ObjectAlreadyExists, InvalidObjectName, DeploymentError

Add new persistence classes.

```
void addPersistence(
    String[] class_names
)
```

copyPersistence(class_names, new_names) throws ObjectDoesNotExist, ObjectAlreadyExists, InvalidObjectName, DeploymentError

Copy the named persistence classes.

```
void copyPersistence(
    String[] class_names
    String[] new_names
)
```

Catalog.Persistence Function Reference

deletePersistence(class_names) throws ObjectDoesNotExist, ObjectInUse, DeploymentError

Delete the named persistence classes.

```
void deletePersistence(
    String[] class_names
)
```

getCookie(class_names) throws ObjectDoesNotExist

Get the name of the cookie used to track session persistence.

```
String[] getCookie(
    String[] class_names
)
```

getCookieByLocation(location, class_names) throws ObjectDoesNotExist

Get the name of the cookie used to track session persistence. This is a location specific function, any action will operate on the specified location.

```
String[] getCookieByLocation(
    String location
    String[] class_names
)
```

getDelete(class names) throws ObjectDoesNotExist

Get whether the session should be deleted if a failure occurs.

```
Boolean[] getDelete(
    String[] class_names
)
```

getDeleteByLocation(location, class_names) throws ObjectDoesNotExist

Get whether the session should be deleted if a failure occurs. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getDeleteByLocation(
    String location
    String[] class names
```

Function Reference Catalog.Persistence

)

getFailureMode(class_names) throws ObjectDoesNotExist

Get the action that should be taken if the session data is invalid or the node specified cannot be contacted.

```
Catalog.Persistence.FailureMode[] getFailureMode(
    String[] class_names
)
```

getFailureModeByLocation(location, class_names) throws ObjectDoesNotExist

Get the action that should be taken if the session data is invalid or the node specified cannot be contacted. This is a location specific function, any action will operate on the specified location.

```
Catalog.Persistence.FailureMode[]
getFailureModeByLocation(
    String location
    String[] class_names
)
```

getNote(class_names) throws ObjectDoesNotExist

Get the note for each of the named Session Persistence classes.

```
String[] getNote(
    String[] class_names
)
```

getPersistenceNames()

Get the names of all the configured persistence classes.

```
String[] getPersistenceNames()
```

getType(class_names) throws ObjectDoesNotExist

Gets the session method type.

```
Catalog.Persistence.Type[] getType(
    String[] class_names
```

getTypeByLocation(location, class_names) throws ObjectDoesNotExist

Gets the session method type. This is a location specific function, any action will operate on the specified location.

```
Catalog.Persistence.Type[] getTypeByLocation(
    String location
    String[] class_names
)
```

getUrl(class_names) throws ObjectDoesNotExist

Get the URL to send to clients if the session persistence is configured to redirect users when a node dies.

```
String[] getUrl(
    String[] class_names
)
```

getUrlByLocation(location, class_names) throws ObjectDoesNotExist

Get the URL to send to clients if the session persistence is configured to redirect users when a node dies. This is a location specific function, any action will operate on the specified location.

```
String[] getUrlByLocation(
    String location
    String[] class_names
)
```

renamePersistence(class_names, new_names) throws ObjectDoesNotExist, ObjectAlreadyExists, InvalidObjectName, DeploymentError, InvalidOperation

Rename the named persistence classes.

```
void renamePersistence(
   String[] class_names
   String[] new_names
)
```

Function Reference Catalog.Persistence

setCookie(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the name of the cookie used to track session persistence.

```
void setCookie(
    String[] class_names
    String[] values
)
```

setCookieByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the name of the cookie used to track session persistence. This is a location specific function, any action will operate on the specified location.

```
void setCookieByLocation(
   String location
   String[] class_names
   String[] values
)
```

setDelete(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set whether the session should be deleted if a failure occurs.

```
void setDelete(
   String[] class_names
   Boolean[] values
)
```

setDeleteByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set whether the session should be deleted if a failure occurs. This is a location specific function, any action will operate on the specified location.

```
void setDeleteByLocation(
   String location
   String[] class_names
   Boolean[] values
```

)

setFailureMode(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the action that should be taken if the session data is invalid or the node specified cannot be contacted.

```
void setFailureMode(
    String[] class_names
    Catalog.Persistence.FailureMode[] values
)
```

setFailureModeByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the action that should be taken if the session data is invalid or the node specified cannot be contacted. This is a location specific function, any action will operate on the specified location.

```
void setFailureModeByLocation(
   String location
   String[] class_names
   Catalog.Persistence.FailureMode[] values
)
```

setNote(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the note for each of the named Session Persistence classes.

```
void setNote(
    String[] class_names
    String[] values
)
```

setType(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Sets the session method type.

```
void setType(
    String[] class names
```

Function Reference Catalog.Persistence

```
Catalog.Persistence.Type[] values
)
```

setTypeByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Sets the session method type. This is a location specific function, any action will operate on the specified location.

```
void setTypeByLocation(
   String location
   String[] class_names
   Catalog.Persistence.Type[] values
)
```

setUrl(class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the URL to send to clients if the session persistence is configured to redirect users when a node dies.

```
void setUrl(
    String[] class_names
    String[] values
)
```

setUrlByLocation(location, class_names, values) throws ObjectDoesNotExist, DeploymentError, InvalidInput

Set the URL to send to clients if the session persistence is configured to redirect users when a node dies. This is a location specific function, any action will operate on the specified location.

```
void setUrlByLocation(
    String location
    String[] class_names
    String[] values
)
```

Catalog.Persistence Function Reference

Enumerations

Catalog.Persistence.FailureMode

```
enum Catalog.Persistence.FailureMode {
    # Choose a new node to use
    newnode,

# Redirect the user to a given URL
    url,

# Close the connection (using error_file on
Virtual Servers >
    # Edit > Connection Management)
    close
}
```

Catalog.Persistence.Type

```
enum Catalog.Persistence.Type {
    # IP-based persistence
    ip,

    # Universal session persistence
    universal,

    # Named Node session persistence
    named,

    # Transparent session affinity
    transparent,

    # Monitor application cookies
    monitor-cookies,

# J2EE session persistence
```

Function Reference Catalog.Bandwidth

```
# ASP and ASP.NET session persistence
asp,

# X-Zeus-Backend cookies
x-zeus,

# SSL Session ID persistence
ssl,

# Deprecated. Use 'monitor-cookies' instead.
kipper,

# Deprecated. Use 'transparent' instead.
sardine
```

Catalog.Bandwidth

URI: http://soap.zeus.com/zxtm/1.0/Catalog/Bandwidth/

}

The Catalog.Bandwidth interface allows management of Bandwidth classes. Using this interface, you can create, delete and rename bandwidth classes, and manage their configuration.

Methods

addBandwidth(class_names) throws InvalidOperation, ObjectAlreadyExists, InvalidObjectName, LicenseError, DeploymentError

Add new bandwidth classes.

```
void addBandwidth(
    String[] class_names
```

Catalog.Bandwidth Function Reference

copyBandwidth(class_names, new_names) throws InvalidOperation, ObjectDoesNotExist, ObjectAlreadyExists, InvalidObjectName, DeploymentError, LicenseError

Copy the named bandwidth classes.

```
void copyBandwidth(
    String[] class_names
    String[] new_names
)
```

deleteBandwidth(class_names) throws ObjectDoesNotExist, ObjectInUse, LicenseError, DeploymentError

Delete the named bandwidth classes.

```
void deleteBandwidth(
    String[] class_names
)
```

getBandwidthNames() throws LicenseError

Get the names of all the configured bandwidth classes.

```
String[] getBandwidthNames()
```

getMaximum(class_names) throws ObjectDoesNotExist, LicenseError

Get the maximum bandwidth, in kbits/second.

```
Unsigned Integer[] getMaximum(
    String[] class_names
)
```

getMaximumByLocation(location, class_names) throws ObjectDoesNotExist, LicenseError

Get the maximum bandwidth, in kbits/second. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getMaximumByLocation(
    String location
    String[] class_names
)
```

Function Reference Catalog.Bandwidth

getNote(class_names) throws ObjectDoesNotExist, LicenseError

Get the note for each of the named Bandwidth classes.

```
String[] getNote(
    String[] class_names
)
```

getSharing(class_names) throws ObjectDoesNotExist, LicenseError

Get the bandwidth sharing mode

```
Catalog.Bandwidth.Sharing[] getSharing(
    String[] class_names
)
```

getSharingByLocation(location, class_names) throws ObjectDoesNotExist, LicenseError

Get the bandwidth sharing mode This is a location specific function, any action will operate on the specified location.

```
Catalog.Bandwidth.Sharing[] getSharingByLocation(
    String location
    String[] class_names
)
```

renameBandwidth(class_names, new_names) throws ObjectDoesNotExist, ObjectAlreadyExists, InvalidObjectName, DeploymentError, InvalidOperation, LicenseError

Rename the named bandwidth classes.

```
void renameBandwidth(
    String[] class_names
    String[] new_names
)
```

setMaximum(class_names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the maximum bandwidth, in kbits/second.

Catalog.Bandwidth Function Reference

```
void setMaximum(
    String[] class_names
    Unsigned Integer[] values
)
```

setMaximumByLocation(location, class_names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the maximum bandwidth, in kbits/second. This is a location specific function, any action will operate on the specified location.

```
void setMaximumByLocation(
   String location
   String[] class_names
   Unsigned Integer[] values
)
```

setNote(class_names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the note for each of the named Bandwidth classes.

```
void setNote(
    String[] class_names
    String[] values
)
```

setSharing(class_names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the bandwidth sharing mode

```
void setSharing(
    String[] class_names
    Catalog.Bandwidth.Sharing[] values
)
```

Function Reference Catalog.SLM

setSharingByLocation(location, class_names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the bandwidth sharing mode This is a location specific function, any action will operate on the specified location.

```
void setSharingByLocation(
   String location
   String[] class_names
   Catalog.Bandwidth.Sharing[] values
)
```

Enumerations

Catalog.Bandwidth.Sharing

```
enum Catalog.Bandwidth.Sharing {
    # Each connection can use the maximum rate
    connection,

    # Bandwidth is shared per traffic manager
    machine,

# Bandwidth is shared across all traffic managers
    cluster
}
```

Catalog.SLM

URI: http://soap.zeus.com/zxtm/1.0/Catalog/SLM/

The Catalog.SLM interface allows management of Service Level Monitoring classes. Using this interface, you can create, delete and rename SLM classes, and manage their configuration.

Methods

addSLM(class_names) throws InvalidObjectName, ObjectAlreadyExists, DeploymentError, LicenseError

Add new SLM classes.

Catalog.SLM Function Reference

```
void addSLM(
    String[] class_names
)
```

copySLM(class_names, new_names) throws ObjectAlreadyExists, InvalidObjectName, ObjectDoesNotExist, DeploymentError, LicenseError

Copy the named SLM classes.

```
void copySLM(
    String[] class_names
    String[] new_names
)
```

deleteSLM(class_names) throws ObjectDoesNotExist, ObjectInUse, DeploymentError, LicenseError

Delete the named SLM classes.

```
void deleteSLM(
    String[] class_names
)
```

getNote(class_names) throws ObjectDoesNotExist, LicenseError

Get the note for each of the named SLM classes.

```
String[] getNote(
    String[] class_names
)
```

getResponseTime(class_names) throws ObjectDoesNotExist, LicenseError

Get the time limit for a response to conform (in milliseconds).

```
Unsigned Integer[] getResponseTime(
    String[] class_names
)
```

Function Reference Catalog.SLM

getResponseTimeByLocation(location, class_names) throws ObjectDoesNotExist, LicenseError

Get the time limit for a response to conform (in milliseconds). This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getResponseTimeByLocation(
    String location
    String[] class_names
)
```

getSLMNames() throws LicenseError

Get the names of all the configured SLM classes.

```
String[] getSLMNames()
```

getSeriousThreshold(class_names) throws ObjectDoesNotExist, LicenseError

Get the percentage of conforming responses below which a serious error will be emitted.

```
Unsigned Integer[] getSeriousThreshold(
    String[] class_names
)
```

getSeriousThresholdByLocation(location, class_names) throws ObjectDoesNotExist, LicenseError

Get the percentage of conforming responses below which a serious error will be emitted. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getSeriousThresholdByLocation(
    String location
    String[] class_names
)
```

getWarningThreshold(class_names) throws ObjectDoesNotExist, LicenseError

Get the percentage of conforming responses below which a warning message will be triggered.

```
Unsigned Integer[] getWarningThreshold(
    String[] class_names
)
```

Catalog.SLM Function Reference

getWarningThresholdByLocation(location, class_names) throws ObjectDoesNotExist, LicenseError

Get the percentage of conforming responses below which a warning message will be triggered. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getWarningThresholdByLocation(
    String location
    String[] class_names
)
```

renameSLM(class_names, new_names) throws ObjectAlreadyExists, ObjectDoesNotExist, InvalidObjectName, InvalidOperation, DeploymentError, LicenseError

Rename the named SLM classes.

```
void renameSLM(
    String[] class_names
    String[] new_names
)
```

setNote(class_names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the note for each of the named SLM classes.

```
void setNote(
    String[] class_names
    String[] values
)
```

setResponseTime(class_names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the time limit for a response to conform (in milliseconds).

```
void setResponseTime(
    String[] class_names
    Unsigned Integer[] values
)
```

Function Reference Catalog.SLM

setResponseTimeByLocation(location, class_names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the time limit for a response to conform (in milliseconds). This is a location specific function, any action will operate on the specified location.

```
void setResponseTimeByLocation(
   String location
   String[] class_names
   Unsigned Integer[] values
)
```

setSeriousThreshold(class_names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the percentage of conforming responses below which a serious error will be emitted.

```
void setSeriousThreshold(
    String[] class_names
    Unsigned Integer[] values
)
```

setSeriousThresholdByLocation(location, class_names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the percentage of conforming responses below which a serious error will be emitted. This is a location specific function, any action will operate on the specified location.

```
void setSeriousThresholdByLocation(
   String location
   String[] class_names
   Unsigned Integer[] values
)
```

setWarningThreshold(class_names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the percentage of conforming responses below which a warning message will be triggered.

```
void setWarningThreshold(
    String[] class names
```

Catalog.Rate Function Reference

```
Unsigned Integer[] values
```

setWarningThresholdByLocation(location, class_names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the percentage of conforming responses below which a warning message will be triggered. This is a location specific function, any action will operate on the specified location.

```
void setWarningThresholdByLocation(
   String location
   String[] class_names
   Unsigned Integer[] values
)
```

Catalog.Rate

URI: http://soap.zeus.com/zxtm/1.0/Catalog/Rate/

The Catalog.Rate interface allows management of Rate classes. Using this interface, you can create, delete and rename rate classes, and manage their configuration.

Methods

addRate(class_names) throws ObjectAlreadyExists, InvalidObjectName, DeploymentError

Add new rate classes.

```
void addRate(
    String[] class_names
)
```

copyRate(class_names, new_names) throws ObjectDoesNotExist, ObjectAlreadyExists, InvalidObjectName, DeploymentError

Copy the named rate classes.

```
void copyRate(
    String[] class_names
    String[] new_names
)
```

Function Reference Catalog.Rate

deleteRate(class_names) throws ObjectInUse, ObjectDoesNotExist, DeploymentError

Delete the named rate classes.

```
void deleteRate(
    String[] class_names
)
```

getMaxRatePerMinute(class_names) throws ObjectDoesNotExist

Get the maximum rate at which requests are allowed to be processed, in requests per minute.

```
Unsigned Integer[] getMaxRatePerMinute(
    String[] class_names
)
```

getMaxRatePerMinuteByLocation(location, class_names) throws ObjectDoesNotExist

Get the maximum rate at which requests are allowed to be processed, in requests per minute. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getMaxRatePerMinuteByLocation(
    String location
    String[] class_names
)
```

getMaxRatePerSecond(class_names) throws ObjectDoesNotExist

Get the maximum rate at which requests are allowed to be processed, in requests per second.

```
Unsigned Integer[] getMaxRatePerSecond(
    String[] class_names
)
```

getMaxRatePerSecondByLocation(location, class_names) throws ObjectDoesNotExist

Get the maximum rate at which requests are allowed to be processed, in requests per second. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getMaxRatePerSecondByLocation(
```

Catalog.Rate Function Reference

```
String location
String[] class_names
```

getNote(class_names) throws ObjectDoesNotExist

Get the note for each of the named Rate classes.

```
String[] getNote(
    String[] class_names
)
```

getRateNames()

Get the names of all the configured rate classes.

```
String[] getRateNames()
```

renameRate(class_names, new_names) throws ObjectDoesNotExist, ObjectAlreadyExists, InvalidObjectName, DeploymentError, InvalidOperation

Rename the named rate classes.

```
void renameRate(
    String[] class_names
    String[] new_names
)
```

setMaxRatePerMinute(class_names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the maximum rate at which requests are allowed to be processed, in requests per minute.

```
void setMaxRatePerMinute(
    String[] class_names
    Unsigned Integer[] values
)
```

Function Reference Catalog.Rate

setMaxRatePerMinuteByLocation(location, class_names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the maximum rate at which requests are allowed to be processed, in requests per minute. This is a location specific function, any action will operate on the specified location.

```
void setMaxRatePerMinuteByLocation(
   String location
   String[] class_names
   Unsigned Integer[] values
)
```

setMaxRatePerSecond(class_names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the maximum rate at which requests are allowed to be processed, in requests per second.

```
void setMaxRatePerSecond(
    String[] class_names
    Unsigned Integer[] values
)
```

setMaxRatePerSecondByLocation(location, class_names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the maximum rate at which requests are allowed to be processed, in requests per second. This is a location specific function, any action will operate on the specified location.

```
void setMaxRatePerSecondByLocation(
   String location
   String[] class_names
   Unsigned Integer[] values
)
```

setNote(class_names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError

Set the note for each of the named Rate classes.

```
void setNote(
    String[] class_names
    String[] values
```

)

Catalog.JavaExtension

URI: http://soap.zeus.com/zxtm/1.0/Catalog/JavaExtension/

The Catalog.JavaExtension interface allows management of Java Extensions. Using this interface you can retrieve information on each extension in the system, and set the initialisation properties to alter their behaviour.

Methods

addProperties(class_names, properties) throws LicenseError, ObjectDoesNotExist, InvalidInput

Adds initialisation properties for each of the specified extensions.

```
void addProperties(
    String[] class_names
    Catalog.JavaExtension.Property[][] properties
)
```

deleteJavaExtensionFile(names) throws LicenseError, ObjectDoesNotExist, ObjectInUse

Delete the named Java Extension files.

```
void deleteJavaExtensionFile(
    String[] names
)
```

downloadJavaExtensionFile(name) throws LicenseError, ObjectDoesNotExist

Download the named Java Extension File.

```
Binary Data downloadJavaExtensionFile(
    String name
)
```

editProperties(class_names, properties_being_edited, properties) throws LicenseError, ObjectDoesNotExist, InvalidInput

Edits the initialisation properties for each of the specified extensions.

```
void editProperties(
   String[] class_names
   String[][] properties_being_edited
   Catalog.JavaExtension.Property[][] properties
)
```

getExtensionClassNames() throws LicenseError

Gets the class names of all the extensions currently in the system.

```
String[] getExtensionClassNames()
```

getExtensionErrors(class_names) throws LicenseError, ObjectDoesNotExist

Gets the errors for each of the specified extensions.

```
String[][] getExtensionErrors(
    String[] class_names
)
```

getExtensionInfo(class_names) throws LicenseError, ObjectDoesNotExist

Gets information on each of the specified extensions.

```
Catalog.JavaExtension.Info[] getExtensionInfo(
    String[] class_names
)
```

getJavaExtensionFileNames() throws LicenseError

Get the names of Java Extension files on the traffic manager. This list includes files that contain Java Extension and non-Java Extension files, such as other .jar files.

```
String[] getJavaExtensionFileNames()
```

getProperties(class_names) throws LicenseError, ObjectDoesNotExist

Gets the initialisation properties for each of the specified extensions.

```
Catalog.JavaExtension.Property[][] getProperties(
    String[] class_names
)
```

removeProperties(class_names, prop_names) throws LicenseError, ObjectDoesNotExist, InvalidInput

Removes initialisation properties for each of the specified extensions.

```
void removeProperties(
    String[] class_names
    String[][] prop_names
)
```

uploadJavaExtensionFile(name, content) throws InvalidObjectName, LicenseError, InvalidInput

Uploads a new file that may contain a Java Extension. This will overwrite the file if it already exists.

```
void uploadJavaExtensionFile(
    String name
    Binary Data content
)
```

Structures

Catalog. Java Extension. Info

This structure contains basic information about a Java Extension in the catalog.

```
struct Catalog.JavaExtension.Info {
    # The Java class name of the extension.
    String class_name;

# The location of the Java extension class.
    String path;

# The virtual servers that use this extension.
    String[] virtual_servers;

# The rules that use this extension.
    String[] rules;
```

}

Catalog. Java Extension. Property

Represents an initialisation property for an extension.

```
struct Catalog.JavaExtension.Property {
    # The name of this property
    String name;

# The value of this property
    String value;
}
```

Catalog. Authenticators

 $URI: \verb|http://soap.zeus.com/zxtm/1.0/Catalog/Authenticators/|$

The Catalog. Authenticator interface allows management of authenticator information, which are used by TrafficScript to communicate with an authentication service.

Methods

addAuthenticator(class_names) throws InvalidObjectName, ObjectAlreadyExists, DeploymentError, LicenseError

Add new Authenticator classes.

```
void addAuthenticator(
    String[] class_names
)
```

addLDAPSearchAttr(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Add the attributes to return from the search.

```
void addLDAPSearchAttr(
    String[] names
    String[][] values
)
```

addLDAPSearchAttrByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Add the attributes to return from the search. This is a location specific function, any action will operate on the specified location.

```
void addLDAPSearchAttrByLocation(
   String location
   String[] names
   String[][] values
)
```

copyAuthenticator(class_names, new_names) throws ObjectAlreadyExists, InvalidObjectName, ObjectDoesNotExist, DeploymentError, LicenseError

Copy the named Authenticator classes.

```
void copyAuthenticator(
    String[] class_names
    String[] new_names
)
```

deleteAuthenticator(class_names) throws ObjectDoesNotExist, ObjectInUse, DeploymentError, LicenseError

Delete the named Authenticator classes.

```
void deleteAuthenticator(
    String[] class_names
)
```

getAuthenticatorNames() throws LicenseError

Get the names of all the configured Authenticator classes.

```
String[] getAuthenticatorNames()
```

getHost(names) throws ObjectDoesNotExist, LicenseError

Get the hostname of the remote authenticator.

```
String[] getHost(
```

```
String[] names
)
```

getHostByLocation(location, names) throws ObjectDoesNotExist, LicenseError

Get the hostname of the remote authenticator. This is a location specific function, any action will operate on the specified location.

```
String[] getHostByLocation(
    String location
    String[] names
)
```

getLDAPBindDN(names) throws ObjectDoesNotExist, LicenseError

Get the user used to connect to the LDAP server for each of the named Authenticators

```
String[] getLDAPBindDN(
    String[] names
)
```

getLDAPBindDNByLocation(location, names) throws ObjectDoesNotExist, LicenseError

Get the user used to connect to the LDAP server for each of the named Authenticators This is a location specific function, any action will operate on the specified location.

```
String[] getLDAPBindDNByLocation(
   String location
   String[] names
)
```

getLDAPFilter(names) throws ObjectDoesNotExist, LicenseError

Get the filter used to identify user records. Any occurences of '%u' in the filter will be replaced by the name of the user being authenticated.

```
String[] getLDAPFilter(
    String[] names
)
```

getLDAPFilterBaseDN(names) throws ObjectDoesNotExist, LicenseError

Get the DN that we will search for user records under.

```
String[] getLDAPFilterBaseDN(
    String[] names
)
```

getLDAPFilterBaseDNByLocation(location, names) throws ObjectDoesNotExist, LicenseError

Get the DN that we will search for user records under. This is a location specific function, any action will operate on the specified location.

```
String[] getLDAPFilterBaseDNByLocation(
    String location
    String[] names
)
```

getLDAPFilterByLocation(location, names) throws ObjectDoesNotExist, LicenseError

Get the filter used to identify user records. Any occurences of '%u' in the filter will be replaced by the name of the user being authenticated. This is a location specific function, any action will operate on the specified location.

```
String[] getLDAPFilterByLocation(
    String location
    String[] names
)
```

getLDAPSSLCertificate(names) throws ObjectDoesNotExist, LicenseError

Get the SSL certificate in the CA catalog used to authenticate the remote LDAP server.

```
String[] getLDAPSSLCertificate(
    String[] names
)
```

getLDAPSSLCertificateByLocation(location, names) throws ObjectDoesNotExist, LicenseError

Get the SSL certificate in the CA catalog used to authenticate the remote LDAP server. This is a location specific function, any action will operate on the specified location.

```
String[] getLDAPSSLCertificateByLocation(
    String location
    String[] names
)
```

getLDAPSSLEnabled(names) throws ObjectDoesNotExist, LicenseError

Get if SSL should be used to connect to the LDAP server.

```
Boolean[] getLDAPSSLEnabled(
    String[] names
)
```

getLDAPSSLEnabledByLocation(location, names) throws ObjectDoesNotExist, LicenseError

Get if SSL should be used to connect to the LDAP server. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getLDAPSSLEnabledByLocation(
    String location
    String[] names
)
```

getLDAPSSLType(names) throws ObjectDoesNotExist, LicenseError

Get how a SSL connection should be established.

```
Catalog.Authenticators.LDAPSSLType[] getLDAPSSLType(
    String[] names
)
```

getLDAPSSLTypeByLocation(location, names) throws ObjectDoesNotExist, LicenseError

Get how a SSL connection should be established. This is a location specific function, any action will operate on the specified location.

```
Catalog.Authenticators.LDAPSSLType[]
getLDAPSSLTypeByLocation(
    String location
    String[] names
```

)

getLDAPSearchAttr(names) throws ObjectDoesNotExist, LicenseError

Get the attributes to return from the search.

```
String[][] getLDAPSearchAttr(
    String[] names
)
```

getLDAPSearchAttrByLocation(location, names) throws ObjectDoesNotExist, LicenseError

Get the attributes to return from the search. This is a location specific function, any action will operate on the specified location.

```
String[][] getLDAPSearchAttrByLocation(
    String location
    String[] names
)
```

getNote(names) throws ObjectDoesNotExist, LicenseError

Get the note for each of the named Authenticators

```
String[] getNote(
    String[] names
)
```

getPort(names) throws ObjectDoesNotExist, LicenseError

Get the port of the remote authenticator.

```
Unsigned Integer[] getPort(
    String[] names
)
```

getPortByLocation(location, names) throws ObjectDoesNotExist, LicenseError

Get the port of the remote authenticator. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getPortByLocation(
    String location
    String[] names
)
```

removeLDAPSearchAttr(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Remove the attributes to return from the search.

```
void removeLDAPSearchAttr(
    String[] names
    String[][] values
)
```

removeLDAPSearchAttrByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Remove the attributes to return from the search. This is a location specific function, any action will operate on the specified location.

```
void removeLDAPSearchAttrByLocation(
   String location
   String[] names
   String[][] values
)
```

renameAuthenticator(class_names, new_names) throws ObjectAlreadyExists, ObjectDoesNotExist, InvalidObjectName, InvalidOperation, DeploymentError, LicenseError

Rename the named Authenticator classes.

```
void renameAuthenticator(
    String[] class_names
    String[] new_names
)
```

setHost(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the hostname of the remote authenticator.

```
void setHost(
    String[] names
    String[] values
)
```

setHostByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the hostname of the remote authenticator. This is a location specific function, any action will operate on the specified location.

```
void setHostByLocation(
   String location
   String[] names
   String[] values
)
```

setLDAPBindDN(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the user used to connect to the LDAP server for each of the named Authenticators

```
void setLDAPBindDN(
    String[] names
    String[] values
)
```

setLDAPBindDNByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the user used to connect to the LDAP server for each of the named Authenticators This is a location specific function, any action will operate on the specified location.

```
void setLDAPBindDNByLocation(
   String location
   String[] names
   String[] values
```

)

setLDAPBindPassword(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the password of the bind user.

```
void setLDAPBindPassword(
    String[] names
    String[] values
)
```

setLDAPBindPasswordByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the password of the bind user. This is a location specific function, any action will operate on the specified location.

```
void setLDAPBindPasswordByLocation(
   String location
   String[] names
   String[] values
)
```

setLDAPFilter(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the filter used to identify user records. Any occurences of '%u' in the filter will be replaced by the name of the user being authenticated.

```
void setLDAPFilter(
    String[] names
    String[] values
)
```

setLDAPFilterBaseDN(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the DN that we will search for user records under.

```
void setLDAPFilterBaseDN(
    String[] names
```

```
String[] values
)
```

setLDAPFilterBaseDNByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the DN that we will search for user records under. This is a location specific function, any action will operate on the specified location.

```
void setLDAPFilterBaseDNByLocation(
   String location
   String[] names
   String[] values
)
```

setLDAPFilterByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the filter used to identify user records. Any occurences of '%u' in the filter will be replaced by the name of the user being authenticated. This is a location specific function, any action will operate on the specified location.

```
void setLDAPFilterByLocation(
    String location
    String[] names
    String[] values
)
```

setLDAPSSLCertificate(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the SSL certificate in the CA catalog used to authenticate the remote LDAP server.

```
void setLDAPSSLCertificate(
    String[] names
    String[] values
)
```

setLDAPSSLCertificateByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the SSL certificate in the CA catalog used to authenticate the remote LDAP server. This is a location specific function, any action will operate on the specified location.

```
void setLDAPSSLCertificateByLocation(
   String location
   String[] names
   String[] values
)
```

setLDAPSSLEnabled(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set if SSL should be used to connect to the LDAP server.

```
void setLDAPSSLEnabled(
   String[] names
   Boolean[] values
)
```

setLDAPSSLEnabledByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set if SSL should be used to connect to the LDAP server. This is a location specific function, any action will operate on the specified location.

```
void setLDAPSSLEnabledByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setLDAPSSLType(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set how a SSL connection should be established.

```
void setLDAPSSLType(
    String[] names
    Catalog.Authenticators.LDAPSSLType[] values
```

)

setLDAPSSLTypeByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set how a SSL connection should be established. This is a location specific function, any action will operate on the specified location.

```
void setLDAPSSLTypeByLocation(
   String location
   String[] names
   Catalog.Authenticators.LDAPSSLType[] values
)
```

setLDAPSearchAttr(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the attributes to return from the search.

```
void setLDAPSearchAttr(
    String[] names
    String[][] values
)
```

setLDAPSearchAttrByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the attributes to return from the search. This is a location specific function, any action will operate on the specified location.

```
void setLDAPSearchAttrByLocation(
   String location
   String[] names
   String[][] values
)
```

setNote(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the note for each of the named Authenticators

```
void setNote(
```

```
String[] names
String[] values
)
```

setPort(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the port of the remote authenticator.

```
void setPort(
    String[] names
    Unsigned Integer[] values
)
```

setPortByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the port of the remote authenticator. This is a location specific function, any action will operate on the specified location.

```
void setPortByLocation(
   String location
   String[] names
   Unsigned Integer[] values
)
```

Enumerations

Catalog.Authenticators.LDAPSSLType

```
enum Catalog.Authenticators.LDAPSSLType {
    # LDAPS
    ldaps,

# Start TLS
    starttls
}
```

GlobalSettings

URI: http://soap.zeus.com/zxtm/1.0/GlobalSettings/

The Global Settings interface allows management of the traffic manager settings.

Methods

addFlipperFrontendCheckAddresses(values) throws InvalidInput, DeploymentError

Add new IP addresses to the list that should be used to check front-end connectivity

```
void addFlipperFrontendCheckAddresses(
    String[] values
)
```

addFlipperFrontendCheckAddressesByLocation(location, values) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Add new IP addresses to the list that should be used to check front-end connectivity This is a location specific function, any action will operate on the specified location.

```
void addFlipperFrontendCheckAddressesByLocation(
    String location
    String[] values
)
```

getASPSessionCacheSize()

Get the maximum number of entries in the ASP session cache.

```
Unsigned Integer getASPSessionCacheSize()
```

getASPSessionCacheSizeByLocation(location) throws ObjectDoesNotExist

Get the maximum number of entries in the ASP session cache. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getASPSessionCacheSizeByLocation(
    String location
)
```

getAcceptingDelay()

Get how often each traffic manager child process checks whether it should be accepting new connections.

Unsigned Integer getAcceptingDelay()

getAcceptingDelayByLocation(location) throws ObjectDoesNotExist

Get how often each traffic manager child process checks whether it should be accepting new connections. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getAcceptingDelayByLocation(
    String location
)
```

getAdminAllowRehandshake()

Get whether SSL / TLS re-handshakes are supported.

GlobalSettings.AdminAllowRehandshake
getAdminAllowRehandshake()

getAdminDiffieHellmanKeyLength()

Get the number of bits to use for Diffie-Hellman keys

```
GlobalSettings.AdminDiffieHellmanKeyLength getAdminDiffieHellmanKeyLength()
```

getAdminSSLCiphers()

Get the list of configured SSL ciphers for admin server and internal connections (available ciphers can be displayed using the command \$ZEUSHOME/zxtm/bin/zeus.zxtm -s).

```
String getAdminSSLCiphers()
```

getAdminSSLSupportTLS11()

Get whether TLSv1.1 support is enabled for admin server and internal connections.

```
Boolean getAdminSSLSupportTLS11()
```

getAdminSupportSSL2()

Get whether SSLv2 support is enabled for admin server and internal connections.

```
Boolean getAdminSupportSSL2()
```

getAdminSupportSSL3()

Get whether SSLv3 support is enabled for admin server and internal connections.

```
Boolean getAdminSupportSSL3()
```

getAdminSupportTLS1()

Get whether TLSv1 support is enabled for admin server and internal connections.

```
Boolean getAdminSupportTLS1()
```

getAlertEmailInterval()

Get the length of time between alert emails, in seconds. Several alert messages will be stored up and sent in one email.

```
Unsigned Integer getAlertEmailInterval()
```

getAlertEmailIntervalByLocation(location) throws ObjectDoesNotExist

Get the length of time between alert emails, in seconds. Several alert messages will be stored up and sent in one email. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getAlertEmailIntervalByLocation(
    String location
)
```

getAlertEmailMaxAttempts()

Get the number of times to attempt sending an email before giving up.

```
Unsigned Integer getAlertEmailMaxAttempts()
```

getAlertEmailMaxAttemptsByLocation(location) throws ObjectDoesNotExist

Get the number of times to attempt sending an email before giving up. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getAlertEmailMaxAttemptsByLocation(
    String location
)
```

getAllowConsecutiveChars()

Get whether the same character can appear consecutively in passwords.

```
Boolean getAllowConsecutiveChars()
```

getAutoscalerVerbose()

Get detailed logging of autoscaler status and actions

```
Boolean getAutoscalerVerbose()
```

getAutoscalerVerboseByLocation(location) throws ObjectDoesNotExist

Get detailed logging of autoscaler status and actions This is a location specific function, any action will operate on the specified location.

```
Boolean getAutoscalerVerboseByLocation(
    String location
)
```

getBackendKeepaliveTimeout()

 $getBackendKeepaliveTimeout\ is\ deprecated,\ please\ use\ getIdleConnectionTimeout\ instead.$

```
Unsigned Integer getBackendKeepaliveTimeout()
```

getBackendKeepaliveTimeoutByLocation(location) throws ObjectDoesNotExist

getBackendKeepaliveTimeout is deprecated, please use getIdleConnectionTimeout instead. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer
getBackendKeepaliveTimeoutByLocation(
    String location
)
```

getBandwidthSharing()

This method is now obsolete and is replaced by Catalog.Bandwidth.getSharing.

```
Boolean getBandwidthSharing()
```

getBannerAccept()

Get whether or not users must explicitly agree to the displayed login_banner text before logging in to the Admin Server.

```
Boolean getBannerAccept()
```

getChunkSize()

Get the default chunk size for reading and writing data, in bytes.

```
Unsigned Integer getChunkSize()
```

getChunkSizeByLocation(location) throws ObjectDoesNotExist

Get the default chunk size for reading and writing data, in bytes. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getChunkSizeByLocation(
    String location
)
```

getClientFirstOpt()

Get whether client-first network socket optimisations should be used.

```
Boolean getClientFirstOpt()
```

getClientFirstOptByLocation(location) throws ObjectDoesNotExist

Get whether client-first network socket optimisations should be used. This is a location specific function, any action will operate on the specified location.

```
Boolean getClientFirstOptByLocation(
    String location
)
```

getControlAllowHosts()

Get the hosts that are allowed to contact the internal administration port on each traffic manager.

```
String getControlAllowHosts()
```

getControlAllowHostsByLocation(location) throws ObjectDoesNotExist

Get the hosts that are allowed to contact the internal administration port on each traffic manager. This is a location specific function, any action will operate on the specified location.

```
String getControlAllowHostsByLocation(
    String location
)
```

getControlCanUpdateDefault()

Get the value of the control!canupdate key for new cluster members.

```
Boolean getControlCanUpdateDefault()
```

getDNSCacheExpiryTime()

Get the time entries are stored in the DNS cache for, in seconds.

```
Unsigned Integer getDNSCacheExpiryTime()
```

getDNSCacheExpiryTimeByLocation(location) throws ObjectDoesNotExist

Get the time entries are stored in the DNS cache for, in seconds. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getDNSCacheExpiryTimeByLocation(
    String location
)
```

getDNSCacheNegativeExpiryTime()

Get the time failed lookups are stored in the DNS cache for, in seconds.

```
Unsigned Integer getDNSCacheNegativeExpiryTime()
```

getDNSCacheNegativeExpiryTimeByLocation(location) throws ObjectDoesNotExist

Get the time failed lookups are stored in the DNS cache for, in seconds. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer
getDNSCacheNegativeExpiryTimeByLocation(
    String location
)
```

getDNSCacheSize()

Get the maximum number of entries in the DNS cache.

```
Unsigned Integer getDNSCacheSize()
```

getDNSCacheSizeByLocation(location) throws ObjectDoesNotExist

Get the maximum number of entries in the DNS cache. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getDNSCacheSizeByLocation(
    String location
)
```

getDNSTimeout()

Get the timeout for receiving a response from a DNS Server, in seconds.

```
Unsigned Integer getDNSTimeout()
```

getDNSTimeoutByLocation(location) throws ObjectDoesNotExist

Get the timeout for receiving a response from a DNS Server, in seconds. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getDNSTimeoutByLocation(
    String location
)
```

getDeadTime()

This method is now obsolete and is replaced by Pool.getNodeFailTime.

```
Unsigned Integer getDeadTime()
```

getEC2AccessKeyID()

Get the Access Key ID used for interacting with the EC2 API.

```
String getEC2AccessKeyID()
```

getEC2AccessKeyIDByLocation(location) throws ObjectDoesNotExist

Get the Access Key ID used for interacting with the EC2 API. This is a location specific function, any action will operate on the specified location.

```
String getEC2AccessKeyIDByLocation(
    String location
)
```

getErrorLevel()

Get the minimum severity of events that should be logged to disk.

```
GlobalSettings.ErrorLevel getErrorLevel()
```

getErrorLevelByLocation(location) throws ObjectDoesNotExist

Get the minimum severity of events that should be logged to disk. This is a location specific function, any action will operate on the specified location.

```
GlobalSettings.ErrorLevel getErrorLevelByLocation(
    String location
)
```

getErrorLogFile()

Get the filename that errors are logged to.

```
String getErrorLogFile()
```

getErrorLogFileByLocation(location) throws ObjectDoesNotExist

Get the filename that errors are logged to. This is a location specific function, any action will operate on the specified location.

```
String getErrorLogFileByLocation(
    String location
)
```

getFTPDataBindLow()

Get whether your traffic manager should permit use of FTP data connection source ports lower than 1024. If 'No' your traffic manager can completely drop root privileges, if 'Yes' some or all privileges may be retained in order to bind to low ports.

```
Boolean getFTPDataBindLow()
```

getFTPDataBindLowByLocation(location) throws ObjectDoesNotExist

Get whether your traffic manager should permit use of FTP data connection source ports lower than 1024. If 'No' your traffic manager can completely drop root privileges, if 'Yes' some or all privileges may be retained in order to bind to low ports. This is a location specific function, any action will operate on the specified location.

```
Boolean getFTPDataBindLowByLocation(
    String location
)
```

getFlipperArpCount()

Get the number of ARP packets each traffic manager sends when an interface is raised.

```
Unsigned Integer getFlipperArpCount()
```

getFlipperArpCountByLocation(location) throws ObjectDoesNotExist

Get the number of ARP packets each traffic manager sends when an interface is raised. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getFlipperArpCountByLocation(
    String location
)
```

getFlipperAutofailback()

Get whether Traffic IPs should automatically failback to recovered machines.

```
Boolean getFlipperAutofailback()
```

getFlipperAutofailbackByLocation(location) throws ObjectDoesNotExist

Get whether Traffic IPs should automatically failback to recovered machines. This is a location specific function, any action will operate on the specified location.

```
Boolean getFlipperAutofailbackByLocation(
    String location
)
```

getFlipperFrontendCheckAddresses()

Get the IP addresses that should be used to check front-end connectivity.

```
String[] getFlipperFrontendCheckAddresses()
```

getFlipperFrontendCheckAddressesByLocation(location) throws ObjectDoesNotExist

Get the IP addresses that should be used to check front-end connectivity. This is a location specific function, any action will operate on the specified location.

```
String[] getFlipperFrontendCheckAddressesByLocation(
    String location
```

getFlipperHeartbeatMethod()

Get the method used to exchange cluster heartbeat messages.

```
GlobalSettings.FlipperHeartbeatMethod
getFlipperHeartbeatMethod()
```

getFlipperHeartbeatMethodByLocation(location) throws ObjectDoesNotExist

Get the method used to exchange cluster heartbeat messages. This is a location specific function, any action will operate on the specified location.

```
GlobalSettings.FlipperHeartbeatMethod
getFlipperHeartbeatMethodByLocation(
    String location
)
```

getFlipperMonitorInterval()

Get how frequently (in milliseconds) each traffic manager checks and announces its connectivity.

```
Unsigned Integer getFlipperMonitorInterval()
```

getFlipperMonitorIntervalByLocation(location) throws ObjectDoesNotExist

Get how frequently (in milliseconds) each traffic manager checks and announces its connectivity. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getFlipperMonitorIntervalByLocation(
    String location
)
```

getFlipperMonitorTimeout()

Get how long (in seconds) each traffic manager waits for a response from its connectivity tests or from other traffic managers before registering a failure.

```
Unsigned Integer getFlipperMonitorTimeout()
```

getFlipperMonitorTimeoutByLocation(location) throws ObjectDoesNotExist

Get how long (in seconds) each traffic manager waits for a response from its connectivity tests or from other traffic managers before registering a failure. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getFlipperMonitorTimeoutByLocation(
    String location
)
```

getFlipperMulticastAddress()

Get the multicast address and port used to announce connectivity (e.g. 239.100.1.1:9090).

```
String getFlipperMulticastAddress()
```

getFlipperMulticastAddressByLocation(location) throws ObjectDoesNotExist

Get the multicast address and port used to announce connectivity (e.g. 239.100.1.1:9090). This is a location specific function, any action will operate on the specified location.

```
String getFlipperMulticastAddressByLocation(
    String location
)
```

getFlipperUnicastPort()

Get the unicast UDP port used to announce connectivity (e.g. 9090)

```
Unsigned Integer getFlipperUnicastPort()
```

getFlipperUnicastPortByLocation(location) throws ObjectDoesNotExist

Get the unicast UDP port used to announce connectivity (e.g. 9090) This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getFlipperUnicastPortByLocation(
    String location
)
```

getFlipperUseBindip()

Get whether the heartbeat messages used for fault tolerance are only sent over the management network.

```
Boolean getFlipperUseBindip()
```

getFlipperUseBindipByLocation(location) throws ObjectDoesNotExist

Get whether the heartbeat messages used for fault tolerance are only sent over the management network. This is a location specific function, any action will operate on the specified location.

```
Boolean getFlipperUseBindipByLocation(
    String location
)
```

getFlipperVerbose()

Get whether the traffic manager should logs all the connectivity tests.

```
Boolean getFlipperVerbose()
```

getFlipperVerboseByLocation(location) throws ObjectDoesNotExist

Get whether the traffic manager should logs all the connectivity tests. This is a location specific function, any action will operate on the specified location.

```
Boolean getFlipperVerboseByLocation(
    String location
)
```

getGLBLoadChangeLimit()

Get the maximum change per second to load.

```
Unsigned Integer getGLBLoadChangeLimit()
```

getGLBLoadChangeLimitByLocation(location) throws ObjectDoesNotExist

Get the maximum change per second to load. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getGLBLoadChangeLimitByLocation(
String location
```

)

getGLBVerbose()

Get whether GSLB should log all DNS queries

```
Boolean getGLBVerbose()
```

getGLBVerboseByLocation(location) throws ObjectDoesNotExist

Get whether GSLB should log all DNS queries This is a location specific function, any action will operate on the specified location.

```
Boolean getGLBVerboseByLocation(
    String location
)
```

getHistoricalTrafficDays()

Get the length of time historical traffic information is kept for, in days (0=keep indefinitely).

```
Unsigned Integer getHistoricalTrafficDays()
```

getHistoricalTrafficDaysByLocation(location) throws ObjectDoesNotExist

Get the length of time historical traffic information is kept for, in days (0=keep indefinitely). This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getHistoricalTrafficDaysByLocation(
    String location
)
```

getIPSessionCacheSize()

Get the maximum number of entries in the IP session cache.

```
Unsigned Integer getIPSessionCacheSize()
```

getIPSessionCacheSizeByLocation(location) throws ObjectDoesNotExist

Get the maximum number of entries in the IP session cache. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getIPSessionCacheSizeByLocation(
    String location
```

)

getIdleConnectionTimeout()

Get how long unused HTTP keepalive connections should be kept before being discarded, in seconds.

```
Unsigned Integer getIdleConnectionTimeout()
```

getIdleConnectionTimeoutByLocation(location) throws ObjectDoesNotExist

Get how long unused HTTP keepalive connections should be kept before being discarded, in seconds. This is a location specific function, any action will operate on the specified location.

getJ2EESessionCacheSize()

Get the maximum number of entries in the J2EE session cache.

```
Unsigned Integer getJ2EESessionCacheSize()
```

getJ2EESessionCacheSizeByLocation(location) throws ObjectDoesNotExist

Get the maximum number of entries in the J2EE session cache. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getJ2EESessionCacheSizeByLocation(
    String location
)
```

getJavaClasspath()

Get extra Java CLASSPATH settings required for servlets.

```
String getJavaClasspath()
```

getJavaClasspathByLocation(location) throws ObjectDoesNotExist

Get extra Java CLASSPATH settings required for servlets. This is a location specific function, any action will operate on the specified location.

```
String getJavaClasspathByLocation(
String location
```

)

getJavaCommand()

Get the command (and arguments) used to start Java.

```
String getJavaCommand()
```

getJavaCommandByLocation(location) throws ObjectDoesNotExist

Get the command (and arguments) used to start Java. This is a location specific function, any action will operate on the specified location.

```
String getJavaCommandByLocation(
    String location
)
```

getJavaEnabled()

Get whether to enable Java support.

```
Boolean getJavaEnabled()
```

getJavaEnabledByLocation(location) throws ObjectDoesNotExist

Get whether to enable Java support. This is a location specific function, any action will operate on the specified location.

```
Boolean getJavaEnabledByLocation(
    String location
)
```

getJavaLib()

Get the location of the java library directory

```
String getJavaLib()
```

getJavaLibByLocation(location) throws ObjectDoesNotExist

Get the location of the java library directory This is a location specific function, any action will operate on the specified location.

```
String getJavaLibByLocation(
String location
```

)

getJavaMaxConns()

Get the maximum number of Java threads

```
Unsigned Integer getJavaMaxConns()
```

getJavaMaxConnsByLocation(location) throws ObjectDoesNotExist

Get the maximum number of Java threads This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getJavaMaxConnsByLocation(
    String location
)
```

getJavaSessionAge()

Get the default maximum age of Java session persistence

```
Unsigned Integer getJavaSessionAge()
```

getJavaSessionAgeByLocation(location) throws ObjectDoesNotExist

Get the default maximum age of Java session persistence This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getJavaSessionAgeByLocation(
    String location
)
```

getListenQueueSize()

Get the size of the listen queue for managing incoming connections.

```
Unsigned Integer getListenQueueSize()
```

getListenQueueSizeByLocation(location) throws ObjectDoesNotExist

Get the size of the listen queue for managing incoming connections. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getListenQueueSizeByLocation(
    String location
```

)

getLogFlushFlushTime()

Get the length of time to wait before flushing the request log files for each virtual server, in seconds.

```
Unsigned Integer getLogFlushFlushTime()
```

getLogFlushFlushTimeByLocation(location) throws ObjectDoesNotExist

Get the length of time to wait before flushing the request log files for each virtual server, in seconds. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getLogFlushFlushTimeByLocation(
    String location
)
```

getLogInterval()

Get the length of time between log messages for log intensive features e.g. SLM, in seconds.

```
Unsigned Integer getLogInterval()
```

getLogIntervalByLocation(location) throws ObjectDoesNotExist

Get the length of time between log messages for log intensive features e.g. SLM, in seconds. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getLogIntervalByLocation(
    String location
)
```

getLogRate()

Get is the maximum number of connection errors logged per second.

```
Unsigned Integer getLogRate()
```

getLogRateByLocation(location) throws ObjectDoesNotExist

Get is the maximum number of connection errors logged per second. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getLogRateByLocation(
    String location
```

)

getLogReopenTime()

Get the length of time to wait before re-opening request log files, to handle log file rotation, in seconds.

```
Unsigned Integer getLogReopenTime()
```

getLogReopenTimeByLocation(location) throws ObjectDoesNotExist

Get the length of time to wait before re-opening request log files, to handle log file rotation, in seconds. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getLogReopenTimeByLocation(
    String location
)
```

getLoginBanner()

Get the banner text to be shown on the Admin Server login page and before logging in to appliance SSH servers.

```
String getLoginBanner()
```

getLoginDelay()

Get the number of seconds before another login attempt can be made after a failed attempt.

```
Unsigned Integer getLoginDelay()
```

getMaxAccepting()

Get how many traffic manager child processes accept new connections.

```
Unsigned Integer getMaxAccepting()
```

getMaxAcceptingByLocation(location) throws ObjectDoesNotExist

Get how many traffic manager child processes accept new connections. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getMaxAcceptingByLocation(
    String location
)
```

getMaxIdleConnections()

Get the maximum number of unused HTTP keepalive connections to all nodes that should maintained for re-use.

```
Unsigned Integer getMaxIdleConnections()
```

getMaxIdleConnectionsByLocation(location) throws ObjectDoesNotExist

Get the maximum number of unused HTTP keepalive connections to all nodes that should maintained for re-use. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getMaxIdleConnectionsByLocation(
    String location
)
```

getMaxKeepalives()

getMaxKeepalives is deprecated, please use getMaxIdleConnections instead.

```
Unsigned Integer getMaxKeepalives()
```

getMaxKeepalivesByLocation(location) throws ObjectDoesNotExist

getMaxKeepalives is deprecated, please use getMaxIdleConnections instead. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getMaxKeepalivesByLocation(
    String location
)
```

getMaxLoginAttempts()

Get the number of sequential failed login attempts that will cause a user account to be suspended. Setting this to 0 disables this feature.

```
Unsigned Integer getMaxLoginAttempts()
```

getMaxLoginExternal()

Get whether or not usernames blocked due to the max_login_attempts limit should also be blocked from authentication against external services (such as LDAP and RADIUS).

```
Boolean getMaxLoginExternal()
```

getMaxLoginSuspensionTime()

Get number of minutes to suspend users who have exceeded the max_login_attempts limit.

```
Unsigned Integer getMaxLoginSuspensionTime()
```

getMaxRetries()

This method is now obsolete and is replaced by Pool.getNodeConnectionAttempts.

```
Unsigned Integer getMaxRetries()
```

getMaximumFDCount()

Get the maximum number of file descriptors that your traffic manager will allocate

```
Unsigned Integer getMaximumFDCount()
```

getMaximumFDCountByLocation(location) throws ObjectDoesNotExist

Get the maximum number of file descriptors that your traffic manager will allocate This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getMaximumFDCountByLocation(
    String location
)
```

getMinAlphaChars()

Get the minimum number of alphabetic characters in a password.

```
Unsigned Integer getMinAlphaChars()
```

getMinNumericChars()

Get the minimum number of numeric characters in a password.

```
Unsigned Integer getMinNumericChars()
```

getMinPasswordLength()

Get the minimum number of characters a password must contain.

```
Unsigned Integer getMinPasswordLength()
```

getMinSpecialChars()

Get the minimum number of special characters in a password.

```
Unsigned Integer getMinSpecialChars()
```

getMinUppercaseChars()

Get the minimum number of uppercase characters in a password.

```
Unsigned Integer getMinUppercaseChars()
```

getMonitorNumNodes()

Get the maximum number of nodes that can be monitored.

```
Unsigned Integer getMonitorNumNodes()
```

getMonitorNumNodesByLocation(location) throws ObjectDoesNotExist

Get the maximum number of nodes that can be monitored. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getMonitorNumNodesByLocation(
    String location
)
```

getMultipleAccept()

Get whether your traffic manager should try and read multiple new connections each time a new client connects.

```
Boolean getMultipleAccept()
```

getMultipleAcceptByLocation(location) throws ObjectDoesNotExist

Get whether your traffic manager should try and read multiple new connections each time a new client connects. This is a location specific function, any action will operate on the specified location.

```
Boolean getMultipleAcceptByLocation(
    String location
)
```

getNodeConnectionAttempts()

This method is now obsolete and is replaced by Pool.getNodeConnectionAttempts.

```
Unsigned Integer getNodeConnectionAttempts()
```

getNodeFailTime()

This method is now obsolete and is replaced by Pool.getNodeFailTime.

```
Unsigned Integer getNodeFailTime()
```

getOCSPCacheSize()

Get the maximum number of entries in the OCSP cache. This is used to speed up OCSP checks by caching results

```
Unsigned Integer getOCSPCacheSize()
```

getOCSPCacheSizeByLocation(location) throws ObjectDoesNotExist

Get the maximum number of entries in the OCSP cache. This is used to speed up OCSP checks by caching results This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getOCSPCacheSizeByLocation(
    String location
)
```

getPasswordChangesPerDay()

Get the maximum number of times a password can be changed every 24 hours.

```
Unsigned Integer getPasswordChangesPerDay()
```

getPasswordReuseAfter()

Get the number of times a password must have been changed before it can be reused.

```
Unsigned Integer getPasswordReuseAfter()
```

getPostLoginBanner()

Get the banner text to be displayed on the appliance console after login.

```
String getPostLoginBanner()
```

getRateClassLimit()

Get the maximum number of Rate classes allowed.

```
Unsigned Integer getRateClassLimit()
```

getRateClassLimitByLocation(location) throws ObjectDoesNotExist

Get the maximum number of Rate classes allowed. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getRateClassLimitByLocation(
    String location
)
```

getRecentConns()

Get the details of how many recently closed connections each traffic manager process should save for use with the Connections page.

```
Unsigned Integer getRecentConns()
```

getRecentConnsByLocation(location) throws ObjectDoesNotExist

Get the details of how many recently closed connections each traffic manager process should save for use with the Connections page. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getRecentConnsByLocation(
    String location
)
```

getRecentConnsRetainTime()

Get for how long a snapshot should be retained on the Connections page.

```
Unsigned Integer getRecentConnsRetainTime()
```

getRecentConnsRetainTimeByLocation(location) throws ObjectDoesNotExist

Get for how long a snapshot should be retained on the Connections page. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getRecentConnsRetainTimeByLocation(
    String location
)
```

getRecentConnsSnapshotSize()

Get the maximum number of connections each traffic manager process should show for a snapshot on the Connections page.

```
Unsigned Integer getRecentConnsSnapshotSize()
```

getRecentConnsSnapshotSizeByLocation(location) throws ObjectDoesNotExist

Get the maximum number of connections each traffic manager process should show for a snapshot on the Connections page. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer
getRecentConnsSnapshotSizeByLocation(
    String location
)
```

getSLMClassLimit()

Get the maximum number of SLM classes allowed.

```
Unsigned Integer getSLMClassLimit()
```

getSLMClassLimitByLocation(location) throws ObjectDoesNotExist

Get the maximum number of SLM classes allowed. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getSLMClassLimitByLocation(
    String location
)
```

getSNMPUserCounters()

Get the number of user defined SNMP counters (this single parameter dictates the numbers of both 32- and 64-bit user counters - there is always the same number of counters of each type).

```
Unsigned Integer getSNMPUserCounters()
```

getSNMPUserCountersByLocation(location) throws ObjectDoesNotExist

Get the number of user defined SNMP counters (this single parameter dictates the numbers of both 32- and 64-bit user counters - there is always the same number of counters of each type). This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getSNMPUserCountersByLocation(
    String location
)
```

getSSL3AllowRehandshake()

Get whether SSL / TLS re-handshakes are supported.

```
GlobalSettings.SSL3AllowRehandshake
getSSL3AllowRehandshake()
```

getSSL3AllowRehandshakeByLocation(location) throws ObjectDoesNotExist

Get whether SSL / TLS re-handshakes are supported. This is a location specific function, any action will operate on the specified location.

```
GlobalSettings.SSL3AllowRehandshake
getSSL3AllowRehandshakeByLocation(
    String location
)
```

getSSL3Ciphers()

Get the list of configured SSL ciphers (available ciphers can be displayed using the command \$ZEUSHOME/zxtm/bin/zeus.zxtm -s).

```
String getSSL3Ciphers()
```

getSSL3CiphersByLocation(location) throws ObjectDoesNotExist

Get the list of configured SSL ciphers (available ciphers can be displayed using the command \$ZEUSHOME/zxtm/bin/zeus.zxtm -s). This is a location specific function, any action will operate on the specified location.

```
String getSSL3CiphersByLocation(
    String location
)
```

getSSL3DiffieHellmanKeyLength()

Get the number of bits to use for Diffie-Hellman keys

```
GlobalSettings.SSL3DiffieHellmanKeyLength
getSSL3DiffieHellmanKeyLength()
```

getSSL3DiffieHellmanKeyLengthByLocation(location) throws ObjectDoesNotExist

Get the number of bits to use for Diffie-Hellman keys This is a location specific function, any action will operate on the specified location.

```
GlobalSettings.SSL3DiffieHellmanKeyLength
getSSL3DiffieHellmanKeyLengthByLocation(
    String location
)
```

getSSLDFailureCount()

getSSLDFailureCount is deprecated, please use getSSLHardwareFailureCount instead.

```
Unsigned Integer getSSLDFailureCount()
```

getSSLDFailureCountByLocation(location) throws ObjectDoesNotExist

getSSLDFailureCount is deprecated, please use getSSLHardwareFailureCount instead. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getSSLDFailureCountByLocation(
    String location
)
```

getSSLDPKCS11Lib()

getSSLDPKCS11Lib is deprecated, please use getSSLHardwarePKCS11Lib instead.

```
String getSSLDPKCS11Lib()
```

getSSLDPKCS11LibByLocation(location) throws ObjectDoesNotExist

getSSLDPKCS11Lib is deprecated, please use getSSLHardwarePKCS11Lib instead. This is a location specific function, any action will operate on the specified location.

```
String getSSLDPKCS11LibByLocation(
    String location
)
```

getSSLHardwareAccelerator()

Get whether your traffic manager should always attempt to use SSL hardware.

```
Boolean getSSLHardwareAccelerator()
```

getSSLHardwareAcceleratorByLocation(location) throws ObjectDoesNotExist

Get whether your traffic manager should always attempt to use SSL hardware. This is a location specific function, any action will operate on the specified location.

```
Boolean getSSLHardwareAcceleratorByLocation(
    String location
)
```

getSSLHardwareFailureCount()

Get the number of consecutive failures from the SSL hardware that will be tolerated before your traffic manager tries to log in again.

```
Unsigned Integer getSSLHardwareFailureCount()
```

getSSLHardwareFailureCountByLocation(location) throws ObjectDoesNotExist

Get the number of consecutive failures from the SSL hardware that will be tolerated before your traffic manager tries to log in again. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer
getSSLHardwareFailureCountByLocation(
    String location
)
```

getSSLHardwarePKCS11Lib()

Get the location of the PKCS#11 library supplied by your hardware vendor.

```
String getSSLHardwarePKCS11Lib()
```

getSSLHardwarePKCS11LibByLocation(location) throws ObjectDoesNotExist

Get the location of the PKCS#11 library supplied by your hardware vendor. This is a location specific function, any action will operate on the specified location.

```
String getSSLHardwarePKCS11LibByLocation(
    String location
```

getSSLHardwarePKCS11SlotLabel()

Get the label of the SSL hardware slot to use.

String getSSLHardwarePKCS11SlotLabel()

getSSLHardwarePKCS11SlotLabelByLocation(location) throws ObjectDoesNotExist

Get the label of the SSL hardware slot to use. This is a location specific function, any action will operate on the specified location.

```
String getSSLHardwarePKCS11SlotLabelByLocation(
    String location
)
```

getSSLHardwarePKCS11SlotType()

Get the type of PKCS11 slot to use. Only used for PKCS11.

```
GlobalSettings.SSLHardwarePKCS11SlotType
getSSLHardwarePKCS11SlotType()
```

getSSLHardwarePKCS11SlotTypeByLocation(location) throws ObjectDoesNotExist

Get the type of PKCS11 slot to use. Only used for PKCS11. This is a location specific function, any action will operate on the specified location.

```
GlobalSettings.SSLHardwarePKCS11SlotType
getSSLHardwarePKCS11SlotTypeByLocation(
    String location
)
```

getSSLHardwareType()

Get the device driver library name.

```
GlobalSettings.SSLHardwareType getSSLHardwareType()
```

getSSLHardwareTypeByLocation(location) throws ObjectDoesNotExist

Get the device driver library name. This is a location specific function, any action will operate on the specified location.

```
GlobalSettings.SSLHardwareType
getSSLHardwareTypeByLocation(
```

```
String location
```

getSSLSessionCacheSize()

Get the maximum number of entries in the SSL session cache. This is used to provide persistence based on SSL session IDs.

```
Unsigned Integer getSSLSessionCacheSize()
```

getSSLSessionCacheSizeByLocation(location) throws ObjectDoesNotExist

Get the maximum number of entries in the SSL session cache. This is used to provide persistence based on SSL session IDs. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getSSLSessionCacheSizeByLocation(
    String location
)
```

getSSLSessionIDCacheExpiryTime()

Get the length of time that SSL session IDs are stored, in seconds.

```
Unsigned Integer getSSLSessionIDCacheExpiryTime()
```

getSSLSessionIDCacheExpiryTimeByLocation(location) throws ObjectDoesNotExist

Get the length of time that SSL session IDs are stored, in seconds. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer
getSSLSessionIDCacheExpiryTimeByLocation(
    String location
)
```

getSSLSessionIDCacheSize()

Get the number of entries in the SSL session ID cache.

```
Unsigned Integer getSSLSessionIDCacheSize()
```

getSSLSessionIDCacheSizeByLocation(location) throws ObjectDoesNotExist

Get the number of entries in the SSL session ID cache. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getSSLSessionIDCacheSizeByLocation(
    String location
)
```

getSSLSupportSSL2()

Get whether SSLv2 support is enabled.

```
Boolean getSSLSupportSSL2()
```

getSSLSupportSSL2ByLocation(location) throws ObjectDoesNotExist

Get whether SSLv2 support is enabled. This is a location specific function, any action will operate on the specified location.

```
Boolean getSSLSupportSSL2ByLocation(
    String location
)
```

getSSLSupportSSL3()

Get whether SSLv3 support is enabled.

```
Boolean getSSLSupportSSL3()
```

getSSLSupportSSL3ByLocation(location) throws ObjectDoesNotExist

Get whether SSLv3 support is enabled. This is a location specific function, any action will operate on the specified location.

```
Boolean getSSLSupportSSL3ByLocation(
    String location
)
```

getSSLSupportTLS1()

Get whether TLSv1 support is enabled.

```
Boolean getSSLSupportTLS1()
```

getSSLSupportTLS11()

Get whether TLSv1.1 support is enabled.

```
Boolean getSSLSupportTLS11()
```

getSSLSupportTLS11ByLocation(location) throws ObjectDoesNotExist

Get whether TLSv1.1 support is enabled. This is a location specific function, any action will operate on the specified location.

```
Boolean getSSLSupportTLS11ByLocation(
    String location
)
```

getSSLSupportTLS1ByLocation(location) throws ObjectDoesNotExist

Get whether TLSv1 support is enabled. This is a location specific function, any action will operate on the specified location.

```
Boolean getSSLSupportTLS1ByLocation(
    String location
)
```

getSharedPoolSize()

Get is the size of shared memory pool to be used for shared storage across worker processes.

```
String getSharedPoolSize()
```

getSharedPoolSizeByLocation(location) throws ObjectDoesNotExist

Get is the size of shared memory pool to be used for shared storage across worker processes. This is a location specific function, any action will operate on the specified location.

```
String getSharedPoolSizeByLocation(
    String location
)
```

getSoapIdleMinutes()

Get the number of minutes the SOAP server remain idle before exiting

```
Unsigned Integer getSoapIdleMinutes()
```

getSoapIdleMinutesByLocation(location) throws ObjectDoesNotExist

Get the number of minutes the SOAP server remain idle before exiting This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getSoapIdleMinutesByLocation(
    String location
)
```

getSocketOptimizations()

Get whether potential network socket optimisations should be used.

```
GlobalSettings.SocketOptimizations
getSocketOptimizations()
```

getSocketOptimizationsByLocation(location) throws ObjectDoesNotExist

Get whether potential network socket optimisations should be used. This is a location specific function, any action will operate on the specified location.

```
GlobalSettings.SocketOptimizations
getSocketOptimizationsByLocation(
    String location
)
```

getSsIdAccel()

getSsldAccel is deprecated, please use getSSLHardwareAccelerator instead.

```
Boolean getSsldAccel()
```

getSsIdAccelByLocation(location) throws ObjectDoesNotExist

getSsldAccel is deprecated, please use getSSLHardwareAccelerator instead. This is a location specific function, any action will operate on the specified location.

```
Boolean getSsldAccelByLocation(
    String location
)
```

getSsldLibrary()

getSsldLibrary is deprecated, please use getSSLHardwareType instead.

```
GlobalSettings.SsldLibrary getSsldLibrary()
```

getSsIdLibraryByLocation(location) throws ObjectDoesNotExist

getSsldLibrary is deprecated, please use getSsLHardwareType instead. This is a location specific function, any action will operate on the specified location.

```
GlobalSettings.SsldLibrary getSsldLibraryByLocation(
    String location
)
```

getStateSyncTime()

Get how often the cache state is propagated to other traffic managers in the cluster, in seconds.

```
Unsigned Integer getStateSyncTime()
```

getStateSyncTimeByLocation(location) throws ObjectDoesNotExist

Get how often the cache state is propagated to other traffic managers in the cluster, in seconds. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getStateSyncTimeByLocation(
    String location
)
```

getStateSyncTimeout()

Get the timeout for state propagation between cluster members, in seconds

```
Unsigned Integer getStateSyncTimeout()
```

getStateSyncTimeoutByLocation(location) throws ObjectDoesNotExist

Get the timeout for state propagation between cluster members, in seconds This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getStateSyncTimeoutByLocation(
    String location
)
```

getSystemReadBufferSize()

Get the size of the operating system's read buffer, in bytes (0 means use the system default).

```
Unsigned Integer getSystemReadBufferSize()
```

getSystemReadBufferSizeByLocation(location) throws ObjectDoesNotExist

Get the size of the operating system's read buffer, in bytes (0 means use the system default). This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getSystemReadBufferSizeByLocation(
    String location
)
```

getSystemWriteBufferSize()

Get the size of the operating system's write buffer, in bytes (0 means use the system default).

```
Unsigned Integer getSystemWriteBufferSize()
```

getSystemWriteBufferSizeByLocation(location) throws ObjectDoesNotExist

Get the size of the operating system's write buffer, in bytes (0 means use the system default). This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getSystemWriteBufferSizeByLocation(
    String location
)
```

getTrafficIPGroupLimit()

Get the maximum number of Traffic IP Groups allowed.

```
Unsigned Integer getTrafficIPGroupLimit()
```

getTrafficIPGroupLimitByLocation(location) throws ObjectDoesNotExist

Get the maximum number of Traffic IP Groups allowed. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getTrafficIPGroupLimitByLocation(
    String location
)
```

getTrafficScriptMemoryWarning()

Get the amount of buffered network data a TrafficScript rule can buffer before a warning is logged, in bytes.

```
Unsigned Integer getTrafficScriptMemoryWarning()
```

getTrafficScriptMemoryWarningByLocation(location) throws ObjectDoesNotExist

Get the amount of buffered network data a TrafficScript rule can buffer before a warning is logged, in bytes. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer
getTrafficScriptMemoryWarningByLocation(
    String location
```

getTrafficscriptArrayElements()

Get the number of array elements that can be stored before additional memory is allocated.

```
Unsigned Integer getTrafficscriptArrayElements()
```

getTrafficscriptArrayElementsByLocation(location) throws ObjectDoesNotExist

Get the number of array elements that can be stored before additional memory is allocated. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer
getTrafficscriptArrayElementsByLocation(
    String location
)
```

getTrafficscriptDataSize()

Get the maximum size of the TrafficScript shared data pool (specified as a percentage of system RAM, e.g. '5%', or an absolute size, e.g. 200MB)

```
String getTrafficscriptDataSize()
```

getTrafficscriptDataSizeByLocation(location) throws ObjectDoesNotExist

Get the maximum size of the TrafficScript shared data pool (specified as a percentage of system RAM, e.g. '5%', or an absolute size, e.g. 200MB) This is a location specific function, any action will operate on the specified location.

```
String getTrafficscriptDataSizeByLocation(
String location
```

)

getTrafficscriptMaxInstr()

Get the maximum number of instructions a TrafficScript rule will run before being aborted.

```
Unsigned Integer getTrafficscriptMaxInstr()
```

getTrafficscriptMaxInstrByLocation(location) throws ObjectDoesNotExist

Get the maximum number of instructions a TrafficScript rule will run before being aborted. This is a location specific function, any action will operate on the specified location.

getTrafficscriptRegexCacheSize()

Get the number of regular expressions to cache

```
Unsigned Integer getTrafficscriptRegexCacheSize()
```

getTrafficscriptRegexCacheSizeByLocation(location) throws ObjectDoesNotExist

Get the number of regular expressions to cache This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer
getTrafficscriptRegexCacheSizeByLocation(
    String location
)
```

getTrafficscriptRegexMatchLimit()

Get the maximum number of ways TrafficScript will attempt to match a regular expression at each position in the subject string, before it aborts the rule and reports a TrafficScript error.

```
Unsigned Integer getTrafficscriptRegexMatchLimit()
```

getTrafficscriptRegexMatchLimitByLocation(location) throws ObjectDoesNotExist

Get the maximum number of ways TrafficScript will attempt to match a regular expression at each position in the subject string, before it aborts the rule and reports a TrafficScript error. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer
getTrafficscriptRegexMatchLimitByLocation(
    String location
)
```

getTrafficscriptRegexMatchWarnPerc()

Get the percentage of trafficscript!regex_match_limit at which TrafficScript reports a performance warning.

Unsigned Integer getTrafficscriptRegexMatchWarnPerc()

getTrafficscriptRegexMatchWarnPercByLocation(location) throws ObjectDoesNotExist

Get the percentage of trafficscript!regex_match_limit at which TrafficScript reports a performance warning. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer
getTrafficscriptRegexMatchWarnPercByLocation(
    String location
)
```

getTrafficscriptVariablePoolUse()

Get whether the 'pool.use' and 'pool.select' TrafficScript functions accept variables as well as literal strings.

```
Boolean getTrafficscriptVariablePoolUse()
```

getTrafficscriptVariablePoolUseByLocation(location) throws ObjectDoesNotExist

Get whether the 'pool.use' and 'pool.select' TrafficScript functions accept variables as well as literal strings. This is a location specific function, any action will operate on the specified location.

```
Boolean getTrafficscriptVariablePoolUseByLocation(
    String location
)
```

getUipageBanner()

Get the banner text to be displayed on all Admin Server pages.

```
String getUipageBanner()
```

getUniversalSessionCacheSize()

Get the maximum number of entries in the universal session cache.

```
Unsigned Integer getUniversalSessionCacheSize()
```

getUniversalSessionCacheSizeByLocation(location) throws ObjectDoesNotExist

Get the maximum number of entries in the universal session cache. This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer
getUniversalSessionCacheSizeByLocation(
    String location
)
```

getWebcacheDisk()

Get whether the webcache is stored on disk

```
Boolean getWebcacheDisk()
```

getWebcacheDiskByLocation(location) throws ObjectDoesNotExist

Get whether the webcache is stored on disk This is a location specific function, any action will operate on the specified location.

```
Boolean getWebcacheDiskByLocation(
    String location
)
```

getWebcacheDiskDir()

Get the disk cache location

```
String getWebcacheDiskDir()
```

getWebcacheDiskDirByLocation(location) throws ObjectDoesNotExist

Get the disk cache location This is a location specific function, any action will operate on the specified location.

```
String getWebcacheDiskDirByLocation(
    String location
)
```

getWebcacheMaxFileNum()

Get the maximum number of files that can be stored in the web cache

```
Unsigned Integer getWebcacheMaxFileNum()
```

getWebcacheMaxFileNumByLocation(location) throws ObjectDoesNotExist

Get the maximum number of files that can be stored in the web cache This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer getWebcacheMaxFileNumByLocation(
    String location
)
```

getWebcacheMaxFileSize()

Get the largest size of a cacheable object, relative to the total cache size, e.g. '2%', or as an absolute size in kB (default), MB or GB, e.g. '20MB'.

```
String getWebcacheMaxFileSize()
```

getWebcacheMaxFileSizeByLocation(location) throws ObjectDoesNotExist

Get the largest size of a cacheable object, relative to the total cache size, e.g. '2%', or as an absolute size in kB (default), MB or GB, e.g. '20MB'. This is a location specific function, any action will operate on the specified location.

```
String getWebcacheMaxFileSizeByLocation(
    String location
)
```

getWebcacheNormalizeQuery()

Get whether the assignment sub-strings in the parameter string are put into alphabetical order.

```
Boolean getWebcacheNormalizeQuery()
```

getWebcacheNormalizeQueryByLocation(location) throws ObjectDoesNotExist

Get whether the assignment sub-strings in the parameter string are put into alphabetical order. This is a location specific function, any action will operate on the specified location.

```
Boolean getWebcacheNormalizeQueryByLocation(
    String location
)
```

getWebcacheSize()

Get the maximum size of the HTTP web page cache, (specified as a percentage of system RAM, e.g. '20%', or an absolute size, e.g. 200MB)

```
String getWebcacheSize()
```

getWebcacheSizeByLocation(location) throws ObjectDoesNotExist

Get the maximum size of the HTTP web page cache, (specified as a percentage of system RAM, e.g. '20%', or an absolute size, e.g. 200MB) This is a location specific function, any action will operate on the specified location.

```
String getWebcacheSizeByLocation(
    String location
)
```

getWebcacheVerbose()

Get whether an X-Cache-Info header to show cacheability should be added.

```
Boolean getWebcacheVerbose()
```

getWebcacheVerboseByLocation(location) throws ObjectDoesNotExist

Get whether an X-Cache-Info header to show cacheability should be added. This is a location specific function, any action will operate on the specified location.

```
Boolean getWebcacheVerboseByLocation(
    String location
```

removeFlipperFrontendCheckAddresses(values) throws InvalidInput, DeploymentError

Remove IP addresses from the list that should be used to check front-end connectivity

```
void removeFlipperFrontendCheckAddresses(
    String[] values
)
```

removeFlipperFrontendCheckAddressesByLocation(location, values) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Remove IP addresses from the list that should be used to check front-end connectivity This is a location specific function, any action will operate on the specified location.

```
void removeFlipperFrontendCheckAddressesByLocation(
   String location
   String[] values
)
```

setASPSessionCacheSize(value) throws InvalidInput, DeploymentError

Set the maximum number of entries in the ASP session cache.

```
void setASPSessionCacheSize(
    Unsigned Integer value
)
```

setASPSessionCacheSizeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the maximum number of entries in the ASP session cache. This is a location specific function, any action will operate on the specified location.

```
void setASPSessionCacheSizeByLocation(
   String location
   Unsigned Integer value
)
```

setAcceptingDelay(value) throws InvalidInput, DeploymentError

Set how often each traffic manager child process checks whether it should be accepting new connections.

```
void setAcceptingDelay(
    Unsigned Integer value
)
```

setAcceptingDelayByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set how often each traffic manager child process checks whether it should be accepting new connections. This is a location specific function, any action will operate on the specified location.

```
void setAcceptingDelayByLocation(
    String location
    Unsigned Integer value
)
```

setAdminAllowRehandshake(value) throws InvalidInput, DeploymentError

Set whether SSL / TLS re-handshakes are supported.

```
void setAdminAllowRehandshake(
    GlobalSettings.AdminAllowRehandshake value
)
```

setAdminDiffieHellmanKeyLength(value) throws InvalidInput, DeploymentError

Set the number of bits to use for Diffie-Hellman keys

```
void setAdminDiffieHellmanKeyLength(
    GlobalSettings.AdminDiffieHellmanKeyLength value
)
```

setAdminSSLCiphers(value) throws InvalidInput, DeploymentError

Set the list of configured SSL ciphers for admin server and internal connections (available ciphers can be displayed using the command \$ZEUSHOME/zxtm/bin/zeus.zxtm -s).

```
void setAdminSSLCiphers(
    String value
)
```

setAdminSSLSupportTLS11(value) throws InvalidInput, DeploymentError

Set whether TLSv1.1 support is enabled for admin server and internal connections.

```
void setAdminSSLSupportTLS11(
    Boolean value
)
```

setAdminSupportSSL2(value) throws InvalidInput, DeploymentError

Set whether SSLv2 support is enabled for admin server and internal connections.

```
void setAdminSupportSSL2(
    Boolean value
)
```

setAdminSupportSSL3(value) throws InvalidInput, DeploymentError

Set whether SSLv3 support is enabled for admin server and internal connections.

```
void setAdminSupportSSL3(
    Boolean value
)
```

setAdminSupportTLS1(value) throws InvalidInput, DeploymentError

Set whether TLSv1 support is enabled for admin server and internal connections.

```
void setAdminSupportTLS1(
    Boolean value
)
```

setAlertEmailInterval(value) throws InvalidInput, DeploymentError

Set the length of time between alert emails, in seconds. Several alert messages will be stored up and sent in one email.

```
void setAlertEmailInterval(
    Unsigned Integer value
)
```

setAlertEmailIntervalByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the length of time between alert emails, in seconds. Several alert messages will be stored up and sent in one email. This is a location specific function, any action will operate on the specified location.

```
void setAlertEmailIntervalByLocation(
   String location
   Unsigned Integer value
)
```

setAlertEmailMaxAttempts(value) throws InvalidInput, DeploymentError

Set the number of times to attempt sending an email before giving up.

```
void setAlertEmailMaxAttempts(
    Unsigned Integer value
)
```

setAlertEmailMaxAttemptsByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the number of times to attempt sending an email before giving up. This is a location specific function, any action will operate on the specified location.

```
void setAlertEmailMaxAttemptsByLocation(
    String location
    Unsigned Integer value
)
```

setAllowConsecutiveChars(value) throws InvalidInput, DeploymentError

Set whether the same character can appear consecutively in passwords.

```
void setAllowConsecutiveChars(
    Boolean value
)
```

setAutoscalerVerbose(value) throws InvalidInput, DeploymentError

Set detailed logging of autoscaler status and actions

```
void setAutoscalerVerbose(
    Boolean value
```

)

setAutoscalerVerboseByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set detailed logging of autoscaler status and actions This is a location specific function, any action will operate on the specified location.

```
void setAutoscalerVerboseByLocation(
   String location
   Boolean value
)
```

setBackendKeepaliveTimeout(value) throws InvalidInput, DeploymentError

setBackendKeepaliveTimeout is deprecated, please use setIdleConnectionTimeout instead.

```
void setBackendKeepaliveTimeout(
    Unsigned Integer value
)
```

setBackendKeepaliveTimeoutByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

setBackendKeepaliveTimeout is deprecated, please use setIdleConnectionTimeout instead. This is a location specific function, any action will operate on the specified location.

```
void setBackendKeepaliveTimeoutByLocation(
    String location
    Unsigned Integer value
)
```

setBandwidthSharing(value) throws InvalidInput, DeploymentError

This method is now obsolete and is replaced by Catalog.Bandwidth.setSharing.

```
void setBandwidthSharing(
    Boolean value
)
```

setBannerAccept(value) throws InvalidInput, DeploymentError

Set whether or not users must explicitly agree to the displayed login_banner text before logging in to the Admin Server.

```
void setBannerAccept(
    Boolean value
)
```

setBootloaderPassword(password) throws InvalidInput, DeploymentError

Set the lists of nodes for each of the named pools.

```
void setBootloaderPassword(
    String password
)
```

setChunkSize(value) throws InvalidInput, DeploymentError

Set the default chunk size for reading and writing data, in bytes.

```
void setChunkSize(
    Unsigned Integer value
)
```

setChunkSizeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the default chunk size for reading and writing data, in bytes. This is a location specific function, any action will operate on the specified location.

```
void setChunkSizeByLocation(
    String location
    Unsigned Integer value
)
```

setClientFirstOpt(value) throws InvalidInput, DeploymentError

Set whether client-first network socket optimisations should be used.

```
void setClientFirstOpt(
    Boolean value
)
```

setClientFirstOptByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set whether client-first network socket optimisations should be used. This is a location specific function, any action will operate on the specified location.

```
void setClientFirstOptByLocation(
    String location
    Boolean value
)
```

setControlAllowHosts(value) throws InvalidInput, DeploymentError

Set the hosts that are allowed to contact the internal administration port on each traffic manager.

```
void setControlAllowHosts(
    String value
)
```

setControlAllowHostsByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the hosts that are allowed to contact the internal administration port on each traffic manager. This is a location specific function, any action will operate on the specified location.

```
void setControlAllowHostsByLocation(
   String location
   String value
)
```

setControlCanUpdateDefault(value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the value of the control!canupdate key for new cluster members.

```
void setControlCanUpdateDefault(
    Boolean value
)
```

setDNSCacheExpiryTime(value) throws InvalidInput, DeploymentError

Set the time entries are stored in the DNS cache for, in seconds.

```
void setDNSCacheExpiryTime(
    Unsigned Integer value
)
```

setDNSCacheExpiryTimeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the time entries are stored in the DNS cache for, in seconds. This is a location specific function, any action will operate on the specified location.

```
void setDNSCacheExpiryTimeByLocation(
   String location
   Unsigned Integer value
)
```

setDNSCacheNegativeExpiryTime(value) throws InvalidInput, DeploymentError

Set the time failed lookups are stored in the DNS cache for, in seconds.

```
void setDNSCacheNegativeExpiryTime(
    Unsigned Integer value
)
```

setDNSCacheNegativeExpiryTimeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the time failed lookups are stored in the DNS cache for, in seconds. This is a location specific function, any action will operate on the specified location.

```
void setDNSCacheNegativeExpiryTimeByLocation(
   String location
   Unsigned Integer value
)
```

setDNSCacheSize(value) throws InvalidInput, DeploymentError

Set the maximum number of entries in the DNS cache.

```
void setDNSCacheSize(
    Unsigned Integer value
)
```

setDNSCacheSizeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the maximum number of entries in the DNS cache. This is a location specific function, any action will operate on the specified location.

```
void setDNSCacheSizeByLocation(
    String location
    Unsigned Integer value
)
```

setDNSTimeout(value) throws InvalidInput, DeploymentError

Set the timeout for receiving a response from a DNS Server, in seconds.

```
void setDNSTimeout(
    Unsigned Integer value
)
```

setDNSTimeoutByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the timeout for receiving a response from a DNS Server, in seconds. This is a location specific function, any action will operate on the specified location.

```
void setDNSTimeoutByLocation(
    String location
    Unsigned Integer value
)
```

setDeadTime(value) throws InvalidInput, DeploymentError

This method is now obsolete and is replaced by Pool.setNodeFailTime.

```
void setDeadTime(
    Unsigned Integer value
)
```

setEC2AccessKeyID(value) throws InvalidInput, DeploymentError

Set the Access Key ID used for interacting with the EC2 API.

```
void setEC2AccessKeyID(
    String value
)
```

setEC2AccessKeyIDByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the Access Key ID used for interacting with the EC2 API. This is a location specific function, any action will operate on the specified location.

```
void setEC2AccessKeyIDByLocation(
    String location
    String value
)
```

setEC2SecretAccessKey(value) throws InvalidInput, DeploymentError

Set the Secret Access Key used for interacting with the EC2 API.

```
void setEC2SecretAccessKey(
    String value
)
```

setEC2SecretAccessKeyByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the Secret Access Key used for interacting with the EC2 API. This is a location specific function, any action will operate on the specified location.

```
void setEC2SecretAccessKeyByLocation(
   String location
   String value
)
```

setErrorLevel(value) throws InvalidInput, DeploymentError

Set the minimum severity of events that should be logged to disk.

```
void setErrorLevel(
    GlobalSettings.ErrorLevel value
)
```

setErrorLevelByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the minimum severity of events that should be logged to disk. This is a location specific function, any action will operate on the specified location.

```
void setErrorLevelByLocation(
    String location
    GlobalSettings.ErrorLevel value
)
```

setErrorLogFile(value) throws InvalidInput, DeploymentError

Set the filename that errors are logged to.

```
void setErrorLogFile(
    String value
)
```

setErrorLogFileByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the filename that errors are logged to. This is a location specific function, any action will operate on the specified location.

```
void setErrorLogFileByLocation(
    String location
    String value
)
```

setFTPDataBindLow(value) throws InvalidInput, DeploymentError

Set whether your traffic manager should permit use of FTP data connection source ports lower than 1024. If 'No' your traffic manager can completely drop root privileges, if 'Yes' some or all privileges may be retained in order to bind to low ports.

```
void setFTPDataBindLow(
    Boolean value
)
```

setFTPDataBindLowByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set whether your traffic manager should permit use of FTP data connection source ports lower than 1024. If 'No' your traffic manager can completely drop root privileges, if 'Yes' some or all privileges may be retained in order to bind to low ports. This is a location specific function, any action will operate on the specified location.

```
void setFTPDataBindLowByLocation(
   String location
   Boolean value
)
```

setFlipperArpCount(value) throws InvalidInput, DeploymentError

Set the number of ARP packets each traffic manager sends when an interface is raised.

```
void setFlipperArpCount(
    Unsigned Integer value
)
```

setFlipperArpCountByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the number of ARP packets each traffic manager sends when an interface is raised. This is a location specific function, any action will operate on the specified location.

```
void setFlipperArpCountByLocation(
    String location
    Unsigned Integer value
)
```

setFlipperAutofailback(value) throws InvalidInput, DeploymentError

Set whether Traffic IPs should automatically failback to recovered machines.

```
void setFlipperAutofailback(
    Boolean value
)
```

setFlipperAutofailbackByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set whether Traffic IPs should automatically failback to recovered machines. This is a location specific function, any action will operate on the specified location.

```
void setFlipperAutofailbackByLocation(
   String location
   Boolean value
)
```

setFlipperFrontendCheckAddresses(values) throws InvalidInput, DeploymentError

Set the IP addresses that should be used to check front-end connectivity.

```
void setFlipperFrontendCheckAddresses(
    String[] values
)
```

setFlipperFrontendCheckAddressesByLocation(location, values) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the IP addresses that should be used to check front-end connectivity. This is a location specific function, any action will operate on the specified location.

```
void setFlipperFrontendCheckAddressesByLocation(
   String location
   String[] values
)
```

setFlipperHeartbeatMethod(value) throws InvalidInput, DeploymentError

Set the method used to exchange cluster heartbeat messages.

```
void setFlipperHeartbeatMethod(
    GlobalSettings.FlipperHeartbeatMethod value
)
```

setFlipperHeartbeatMethodByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the method used to exchange cluster heartbeat messages. This is a location specific function, any action will operate on the specified location.

```
void setFlipperHeartbeatMethodByLocation(
    String location
    GlobalSettings.FlipperHeartbeatMethod value
)
```

setFlipperMonitorInterval(value) throws InvalidInput, DeploymentError

Set how frequently (in milliseconds) each traffic manager checks and announces its connectivity.

```
void setFlipperMonitorInterval(
    Unsigned Integer value
)
```

setFlipperMonitorIntervalByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set how frequently (in milliseconds) each traffic manager checks and announces its connectivity. This is a location specific function, any action will operate on the specified location.

```
void setFlipperMonitorIntervalByLocation(
    String location
    Unsigned Integer value
)
```

setFlipperMonitorTimeout(value) throws InvalidInput, DeploymentError

Set how long (in seconds) each traffic manager waits for a response from its connectivity tests or from other traffic managers before registering a failure.

```
void setFlipperMonitorTimeout(
    Unsigned Integer value
)
```

setFlipperMonitorTimeoutByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set how long (in seconds) each traffic manager waits for a response from its connectivity tests or from other traffic managers before registering a failure. This is a location specific function, any action will operate on the specified location.

```
void setFlipperMonitorTimeoutByLocation(
    String location
```

```
Unsigned Integer value
)
```

setFlipperMulticastAddress(value) throws InvalidInput, DeploymentError

Set the multicast address and port used to announce connectivity (e.g. 239.100.1.1:9090).

```
void setFlipperMulticastAddress(
    String value
)
```

setFlipperMulticastAddressByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the multicast address and port used to announce connectivity (e.g. 239.100.1.1:9090). This is a location specific function, any action will operate on the specified location.

```
void setFlipperMulticastAddressByLocation(
    String location
    String value
)
```

setFlipperUnicastPort(value) throws InvalidInput, DeploymentError

Set the unicast UDP port used to announce connectivity (e.g. 9090)

```
void setFlipperUnicastPort(
    Unsigned Integer value
)
```

setFlipperUnicastPortByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the unicast UDP port used to announce connectivity (e.g. 9090) This is a location specific function, any action will operate on the specified location.

```
void setFlipperUnicastPortByLocation(
    String location
    Unsigned Integer value
)
```

setFlipperUseBindip(value) throws InvalidInput, DeploymentError

Set whether the heartbeat messages used for fault tolerance are only sent over the management network.

```
void setFlipperUseBindip(
    Boolean value
)
```

setFlipperUseBindipByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set whether the heartbeat messages used for fault tolerance are only sent over the management network. This is a location specific function, any action will operate on the specified location.

```
void setFlipperUseBindipByLocation(
    String location
    Boolean value
)
```

setFlipperVerbose(value) throws InvalidInput, DeploymentError

Set whether the traffic manager should logs all the connectivity tests.

```
void setFlipperVerbose(
    Boolean value
)
```

setFlipperVerboseByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set whether the traffic manager should logs all the connectivity tests. This is a location specific function, any action will operate on the specified location.

```
void setFlipperVerboseByLocation(
   String location
   Boolean value
)
```

setGLBLoadChangeLimit(value) throws InvalidInput, DeploymentError

Set the maximum change per second to load.

```
void setGLBLoadChangeLimit(
```

```
Unsigned Integer value
)
```

setGLBLoadChangeLimitByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the maximum change per second to load. This is a location specific function, any action will operate on the specified location.

```
void setGLBLoadChangeLimitByLocation(
    String location
    Unsigned Integer value
)
```

setGLBVerbose(value) throws InvalidInput, DeploymentError

Set whether GSLB should log all DNS queries

```
void setGLBVerbose(
    Boolean value
)
```

setGLBVerboseByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set whether GSLB should log all DNS queries This is a location specific function, any action will operate on the specified location.

```
void setGLBVerboseByLocation(
    String location
    Boolean value
)
```

setHistoricalTrafficDays(value) throws InvalidInput, DeploymentError

Set the length of time historical traffic information is kept for, in days (0=keep indefinitely).

```
void setHistoricalTrafficDays(
    Unsigned Integer value
)
```

setHistoricalTrafficDaysByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the length of time historical traffic information is kept for, in days (0=keep indefinitely). This is a location specific function, any action will operate on the specified location.

```
void setHistoricalTrafficDaysByLocation(
    String location
    Unsigned Integer value
)
```

setIPSessionCacheSize(value) throws InvalidInput, DeploymentError

Set the maximum number of entries in the IP session cache.

```
void setIPSessionCacheSize(
    Unsigned Integer value
)
```

setIPSessionCacheSizeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the maximum number of entries in the IP session cache. This is a location specific function, any action will operate on the specified location.

```
void setIPSessionCacheSizeByLocation(
    String location
    Unsigned Integer value
)
```

setIdleConnectionTimeout(value) throws InvalidInput, DeploymentError

Set how long unused HTTP keepalive connections should be kept before being discarded, in seconds.

```
void setIdleConnectionTimeout(
    Unsigned Integer value
)
```

setIdleConnectionTimeoutByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set how long unused HTTP keepalive connections should be kept before being discarded, in seconds. This is a location specific function, any action will operate on the specified location.

```
void setIdleConnectionTimeoutByLocation(
    String location
    Unsigned Integer value
)
```

setJ2EESessionCacheSize(value) throws InvalidInput, DeploymentError

Set the maximum number of entries in the J2EE session cache.

```
void setJ2EESessionCacheSize(
    Unsigned Integer value
)
```

setJ2EESessionCacheSizeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the maximum number of entries in the J2EE session cache. This is a location specific function, any action will operate on the specified location.

```
void setJ2EESessionCacheSizeByLocation(
    String location
    Unsigned Integer value
)
```

setJavaClasspath(value) throws InvalidInput, DeploymentError

Set extra Java CLASSPATH settings required for servlets.

```
void setJavaClasspath(
    String value
)
```

setJavaClasspathByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set extra Java CLASSPATH settings required for servlets. This is a location specific function, any action will operate on the specified location.

```
void setJavaClasspathByLocation(
   String location
   String value
)
```

setJavaCommand(value) throws InvalidInput, DeploymentError

Set the command (and arguments) used to start Java.

```
void setJavaCommand(
    String value
)
```

setJavaCommandByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the command (and arguments) used to start Java. This is a location specific function, any action will operate on the specified location.

```
void setJavaCommandByLocation(
    String location
    String value
)
```

setJavaEnabled(value) throws InvalidInput, DeploymentError

Set whether to enable Java support.

```
void setJavaEnabled(
    Boolean value
)
```

setJavaEnabledByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set whether to enable Java support. This is a location specific function, any action will operate on the specified location.

```
void setJavaEnabledByLocation(
   String location
   Boolean value
)
```

setJavaLib(value) throws InvalidInput, DeploymentError

Set the location of the java library directory

```
void setJavaLib(
    String value
)
```

setJavaLibByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the location of the java library directory This is a location specific function, any action will operate on the specified location.

```
void setJavaLibByLocation(
    String location
    String value
)
```

setJavaMaxConns(value) throws InvalidInput, DeploymentError

Set the maximum number of Java threads

```
void setJavaMaxConns(
    Unsigned Integer value
)
```

setJavaMaxConnsByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the maximum number of Java threads This is a location specific function, any action will operate on the specified location.

```
void setJavaMaxConnsByLocation(
   String location
   Unsigned Integer value
)
```

setJavaSessionAge(value) throws InvalidInput, DeploymentError

Set the default maximum age of Java session persistence

```
void setJavaSessionAge(
    Unsigned Integer value
)
```

setJavaSessionAgeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the default maximum age of Java session persistence This is a location specific function, any action will operate on the specified location.

```
void setJavaSessionAgeByLocation(
   String location
   Unsigned Integer value
)
```

setListenQueueSize(value) throws InvalidInput, DeploymentError

Set the size of the listen queue for managing incoming connections.

```
void setListenQueueSize(
    Unsigned Integer value
)
```

setListenQueueSizeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the size of the listen queue for managing incoming connections. This is a location specific function, any action will operate on the specified location.

```
void setListenQueueSizeByLocation(
    String location
    Unsigned Integer value
)
```

setLogFlushFlushTime(value) throws InvalidInput, DeploymentError

Set the length of time to wait before flushing the request log files for each virtual server, in seconds.

```
void setLogFlushFlushTime(
    Unsigned Integer value
)
```

setLogFlushFlushTimeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the length of time to wait before flushing the request log files for each virtual server, in seconds. This is a location specific function, any action will operate on the specified location.

```
void setLogFlushFlushTimeByLocation(
    String location
    Unsigned Integer value
)
```

setLogInterval(value) throws InvalidInput, DeploymentError

Set the length of time between log messages for log intensive features e.g. SLM, in seconds.

```
void setLogInterval(
    Unsigned Integer value
)
```

setLogIntervalByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the length of time between log messages for log intensive features e.g. SLM, in seconds. This is a location specific function, any action will operate on the specified location.

```
void setLogIntervalByLocation(
    String location
    Unsigned Integer value
)
```

setLogRate(value) throws InvalidInput, DeploymentError

Set is the maximum number of connection errors logged per second.

```
void setLogRate(
    Unsigned Integer value
)
```

setLogRateByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set is the maximum number of connection errors logged per second. This is a location specific function, any action will operate on the specified location.

```
void setLogRateByLocation(
    String location
    Unsigned Integer value
)
```

setLogReopenTime(value) throws InvalidInput, DeploymentError

Set the length of time to wait before re-opening request log files, to handle log file rotation, in seconds.

```
void setLogReopenTime(
    Unsigned Integer value
)
```

setLogReopenTimeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the length of time to wait before re-opening request log files, to handle log file rotation, in seconds. This is a location specific function, any action will operate on the specified location.

```
void setLogReopenTimeByLocation(
    String location
    Unsigned Integer value
)
```

setLoginBanner(value) throws InvalidInput, DeploymentError

Set the banner text to be shown on the Admin Server login page and before logging in to appliance SSH servers.

```
void setLoginBanner(
    String value
)
```

setLoginDelay(value) throws InvalidInput, DeploymentError

Set the number of seconds before another login attempt can be made after a failed attempt.

```
void setLoginDelay(
    Unsigned Integer value
)
```

setMaxAccepting(value) throws InvalidInput, DeploymentError

Set how many traffic manager child processes accept new connections.

```
void setMaxAccepting(
    Unsigned Integer value
```

)

setMaxAcceptingByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set how many traffic manager child processes accept new connections. This is a location specific function, any action will operate on the specified location.

```
void setMaxAcceptingByLocation(
    String location
    Unsigned Integer value
)
```

setMaxIdleConnections(value) throws InvalidInput, DeploymentError

Set the maximum number of unused HTTP keepalive connections to all nodes that should maintained for re-use.

```
void setMaxIdleConnections(
    Unsigned Integer value
)
```

setMaxIdleConnectionsByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the maximum number of unused HTTP keepalive connections to all nodes that should maintained for re-use. This is a location specific function, any action will operate on the specified location.

```
void setMaxIdleConnectionsByLocation(
   String location
   Unsigned Integer value
)
```

setMaxKeepalives(value) throws InvalidInput, DeploymentError

setMaxKeepalives is deprecated, please use setMaxIdleConnections instead.

```
void setMaxKeepalives(
    Unsigned Integer value
)
```

setMaxKeepalivesByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

setMaxKeepalives is deprecated, please use setMaxIdleConnections instead. This is a location specific function, any action will operate on the specified location.

```
void setMaxKeepalivesByLocation(
   String location
   Unsigned Integer value
)
```

setMaxLoginAttempts(value) throws InvalidInput, DeploymentError

Set the number of sequential failed login attempts that will cause a user account to be suspended. Setting this to 0 disables this feature.

```
void setMaxLoginAttempts(
    Unsigned Integer value
)
```

setMaxLoginExternal(value) throws InvalidInput, DeploymentError

Set whether or not usernames blocked due to the max_login_attempts limit should also be blocked from authentication against external services (such as LDAP and RADIUS).

```
void setMaxLoginExternal(
    Boolean value
)
```

setMaxLoginSuspensionTime(value) throws InvalidInput, DeploymentError

Set number of minutes to suspend users who have exceeded the max_login_attempts limit.

```
void setMaxLoginSuspensionTime(
    Unsigned Integer value
)
```

setMaxRetries(value) throws InvalidInput, DeploymentError

This method is now obsolete and is replaced by Pool.setNodeConnectionAttempts.

```
void setMaxRetries(
    Unsigned Integer value
)
```

setMaximumFDCount(value) throws InvalidInput, DeploymentError

Set the maximum number of file descriptors that your traffic manager will allocate

```
void setMaximumFDCount(
    Unsigned Integer value
)
```

setMaximumFDCountByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the maximum number of file descriptors that your traffic manager will allocate This is a location specific function, any action will operate on the specified location.

```
void setMaximumFDCountByLocation(
    String location
    Unsigned Integer value
)
```

setMinAlphaChars(value) throws InvalidInput, DeploymentError

Set the minimum number of alphabetic characters in a password.

```
void setMinAlphaChars(
    Unsigned Integer value
)
```

setMinNumericChars(value) throws InvalidInput, DeploymentError

Set the minimum number of numeric characters in a password.

```
void setMinNumericChars(
    Unsigned Integer value
)
```

setMinPasswordLength(value) throws InvalidInput, DeploymentError

Set the minimum number of characters a password must contain.

```
void setMinPasswordLength(
    Unsigned Integer value
)
```

setMinSpecialChars(value) throws InvalidInput, DeploymentError

Set the minimum number of special characters in a password.

```
void setMinSpecialChars(
    Unsigned Integer value
)
```

setMinUppercaseChars(value) throws InvalidInput, DeploymentError

Set the minimum number of uppercase characters in a password.

```
void setMinUppercaseChars(
    Unsigned Integer value
)
```

setMonitorNumNodes(value) throws InvalidInput, DeploymentError

Set the maximum number of nodes that can be monitored.

```
void setMonitorNumNodes(
    Unsigned Integer value
)
```

setMonitorNumNodesByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the maximum number of nodes that can be monitored. This is a location specific function, any action will operate on the specified location.

```
void setMonitorNumNodesByLocation(
    String location
    Unsigned Integer value
)
```

setMultipleAccept(value) throws InvalidInput, DeploymentError

Set whether your traffic manager should try and read multiple new connections each time a new client connects.

```
void setMultipleAccept(
    Boolean value
```

)

setMultipleAcceptByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set whether your traffic manager should try and read multiple new connections each time a new client connects. This is a location specific function, any action will operate on the specified location.

```
void setMultipleAcceptByLocation(
    String location
    Boolean value
)
```

setNodeConnectionAttempts(value) throws InvalidInput, DeploymentError

This method is now obsolete and is replaced by Pool.setNodeConnectionAttempts.

```
void setNodeConnectionAttempts(
    Unsigned Integer value
)
```

setNodeFailTime(value) throws InvalidInput, DeploymentError

This method is now obsolete and is replaced by Pool.setNodeFailTime.

```
void setNodeFailTime(
    Unsigned Integer value
)
```

setOCSPCacheSize(value) throws InvalidInput, DeploymentError

Set the maximum number of entries in the OCSP cache. This is used to speed up OCSP checks by caching results

```
void setOCSPCacheSize(
    Unsigned Integer value
)
```

setOCSPCacheSizeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the maximum number of entries in the OCSP cache. This is used to speed up OCSP checks by caching results This is a location specific function, any action will operate on the specified location.

```
void setOCSPCacheSizeByLocation(
   String location
   Unsigned Integer value
)
```

setPasswordChangesPerDay(value) throws InvalidInput, DeploymentError

Set the maximum number of times a password can be changed every 24 hours.

```
void setPasswordChangesPerDay(
    Unsigned Integer value
)
```

setPasswordReuseAfter(value) throws InvalidInput, DeploymentError

Set the number of times a password must have been changed before it can be reused.

```
void setPasswordReuseAfter(
    Unsigned Integer value
)
```

setPostLoginBanner(value) throws InvalidInput, DeploymentError

Set the banner text to be displayed on the appliance console after login.

```
void setPostLoginBanner(
    String value
)
```

setRateClassLimit(value) throws InvalidInput, DeploymentError

Set the maximum number of Rate classes allowed.

```
void setRateClassLimit(
    Unsigned Integer value
)
```

setRateClassLimitByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the maximum number of Rate classes allowed. This is a location specific function, any action will operate on the specified location.

```
void setRateClassLimitByLocation(
   String location
   Unsigned Integer value
)
```

setRecentConns(value) throws InvalidInput, DeploymentError

Set the details of how many recently closed connections each traffic manager process should save for use with the Connections page.

```
void setRecentConns(
    Unsigned Integer value
)
```

setRecentConnsByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the details of how many recently closed connections each traffic manager process should save for use with the Connections page. This is a location specific function, any action will operate on the specified location.

```
void setRecentConnsByLocation(
    String location
    Unsigned Integer value
)
```

setRecentConnsRetainTime(value) throws InvalidInput, DeploymentError

Set for how long a snapshot should be retained on the Connections page.

```
void setRecentConnsRetainTime(
    Unsigned Integer value
)
```

setRecentConnsRetainTimeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set for how long a snapshot should be retained on the Connections page. This is a location specific function, any action will operate on the specified location.

```
void setRecentConnsRetainTimeByLocation(
    String location
```

```
Unsigned Integer value
)
```

setRecentConnsSnapshotSize(value) throws InvalidInput, DeploymentError

Set the maximum number of connections each traffic manager process should show for a snapshot on the Connections page.

```
void setRecentConnsSnapshotSize(
    Unsigned Integer value
)
```

setRecentConnsSnapshotSizeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the maximum number of connections each traffic manager process should show for a snapshot on the Connections page. This is a location specific function, any action will operate on the specified location.

```
void setRecentConnsSnapshotSizeByLocation(
    String location
    Unsigned Integer value
)
```

setSLMClassLimit(value) throws InvalidInput, DeploymentError

Set the maximum number of SLM classes allowed.

```
void setSLMClassLimit(
    Unsigned Integer value
)
```

setSLMClassLimitByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the maximum number of SLM classes allowed. This is a location specific function, any action will operate on the specified location.

```
void setSLMClassLimitByLocation(
    String location
    Unsigned Integer value
)
```

setSNMPUserCounters(value) throws InvalidInput, DeploymentError

Set the number of user defined SNMP counters (this single parameter dictates the numbers of both 32-and 64-bit user counters - there is always the same number of counters of each type).

```
void setSNMPUserCounters(
    Unsigned Integer value
)
```

setSNMPUserCountersByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the number of user defined SNMP counters (this single parameter dictates the numbers of both 32-and 64-bit user counters - there is always the same number of counters of each type). This is a location specific function, any action will operate on the specified location.

```
void setSNMPUserCountersByLocation(
    String location
    Unsigned Integer value
)
```

setSSL3AllowRehandshake(value) throws InvalidInput, DeploymentError

Set whether SSL / TLS re-handshakes are supported.

```
void setSSL3AllowRehandshake(
    GlobalSettings.SSL3AllowRehandshake value
)
```

setSSL3AllowRehandshakeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set whether SSL / TLS re-handshakes are supported. This is a location specific function, any action will operate on the specified location.

```
void setSSL3AllowRehandshakeByLocation(
   String location
   GlobalSettings.SSL3AllowRehandshake value
)
```

setSSL3Ciphers(value) throws InvalidInput, DeploymentError

Set the list of configured SSL ciphers (available ciphers can be displayed using the command \$ZEUSHOME/zxtm/bin/zeus.zxtm -s).

```
void setSSL3Ciphers(
    String value
)
```

setSSL3CiphersByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the list of configured SSL ciphers (available ciphers can be displayed using the command \$ZEUSHOME/zxtm/bin/zeus.zxtm -s). This is a location specific function, any action will operate on the specified location.

```
void setSSL3CiphersByLocation(
    String location
    String value
)
```

setSSL3DiffieHellmanKeyLength(value) throws InvalidInput, DeploymentError

Set the number of bits to use for Diffie-Hellman keys

```
void setSSL3DiffieHellmanKeyLength(
    GlobalSettings.SSL3DiffieHellmanKeyLength value
)
```

setSSL3DiffieHellmanKeyLengthByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the number of bits to use for Diffie-Hellman keys This is a location specific function, any action will operate on the specified location.

```
void setSSL3DiffieHellmanKeyLengthByLocation(
    String location
    GlobalSettings.SSL3DiffieHellmanKeyLength value
)
```

setSSLDFailureCount(value) throws InvalidInput, DeploymentError

 $set SSLD Failure Count\ is\ deprecated,\ please\ use\ set SSLH ardware Failure Count\ instead.$

```
void setSSLDFailureCount(
    Unsigned Integer value
)
```

setSSLDFailureCountByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

setSSLDFailureCount is deprecated, please use setSSLHardwareFailureCount instead. This is a location specific function, any action will operate on the specified location.

```
void setSSLDFailureCountByLocation(
    String location
    Unsigned Integer value
)
```

setSSLDPKCS11Lib(value) throws InvalidInput, DeploymentError

setSSLDPKCS11Lib is deprecated, please use setSSLHardwarePKCS11Lib instead.

```
void setSSLDPKCS11Lib(
    String value
)
```

setSSLDPKCS11LibByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

setSSLDPKCS11Lib is deprecated, please use setSSLHardwarePKCS11Lib instead. This is a location specific function, any action will operate on the specified location.

```
void setSSLDPKCS11LibByLocation(
    String location
    String value
)
```

setSSLDPKCS11UserPIN(value) throws InvalidInput, DeploymentError

setSSLDPKCS11UserPIN is deprecated, please use setSSLHardwarePKCS11UserPIN instead.

```
void setSSLDPKCS11UserPIN(
    String value
)
```

setSSLDPKCS11UserPINByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

setSSLDPKCS11UserPIN is deprecated, please use setSSLHardwarePKCS11UserPIN instead. This is a location specific function, any action will operate on the specified location.

```
void setSSLDPKCS11UserPINByLocation(
   String location
   String value
)
```

setSSLHardwareAccelerator(value) throws InvalidInput, DeploymentError

Set whether your traffic manager should always attempt to use SSL hardware.

```
void setSSLHardwareAccelerator(
    Boolean value
)
```

setSSLHardwareAcceleratorByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set whether your traffic manager should always attempt to use SSL hardware. This is a location specific function, any action will operate on the specified location.

```
void setSSLHardwareAcceleratorByLocation(
    String location
    Boolean value
)
```

setSSLHardwareFailureCount(value) throws InvalidInput, DeploymentError

Set the number of consecutive failures from the SSL hardware that will be tolerated before your traffic manager tries to log in again.

```
void setSSLHardwareFailureCount(
    Unsigned Integer value
)
```

setSSLHardwareFailureCountByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the number of consecutive failures from the SSL hardware that will be tolerated before your traffic manager tries to log in again. This is a location specific function, any action will operate on the specified location.

```
void setSSLHardwareFailureCountByLocation(
    String location
    Unsigned Integer value
)
```

setSSLHardwarePKCS11Lib(value) throws InvalidInput, DeploymentError

Set the location of the PKCS#11 library supplied by your hardware vendor.

```
void setSSLHardwarePKCS11Lib(
    String value
)
```

setSSLHardwarePKCS11LibByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the location of the PKCS#11 library supplied by your hardware vendor. This is a location specific function, any action will operate on the specified location.

```
void setSSLHardwarePKCS11LibByLocation(
    String location
    String value
)
```

setSSLHardwarePKCS11SlotLabel(value) throws InvalidInput, DeploymentError

Set the label of the SSL hardware slot to use.

```
void setSSLHardwarePKCS11SlotLabel(
    String value
)
```

setSSLHardwarePKCS11SlotLabelByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the label of the SSL hardware slot to use. This is a location specific function, any action will operate on the specified location.

```
void setSSLHardwarePKCS11SlotLabelByLocation(
   String location
   String value
)
```

setSSLHardwarePKCS11SlotType(value) throws InvalidInput, DeploymentError

Set the type of PKCS11 slot to use. Only used for PKCS11.

```
void setSSLHardwarePKCS11SlotType(
    GlobalSettings.SSLHardwarePKCS11SlotType value
)
```

setSSLHardwarePKCS11SlotTypeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the type of PKCS11 slot to use. Only used for PKCS11. This is a location specific function, any action will operate on the specified location.

```
void setSSLHardwarePKCS11SlotTypeByLocation(
    String location
    GlobalSettings.SSLHardwarePKCS11SlotType value
)
```

setSSLHardwarePKCS11UserPIN(value) throws InvalidInput, DeploymentError

Set the user PIN for the PKCS token (PKCS#11 devices only)

```
void setSSLHardwarePKCS11UserPIN(
    String value
)
```

setSSLHardwarePKCS11UserPINByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the user PIN for the PKCS token (PKCS#11 devices only) This is a location specific function, any action will operate on the specified location.

```
void setSSLHardwarePKCS11UserPINByLocation(
   String location
   String value
)
```

setSSLHardwareType(value) throws InvalidInput, DeploymentError

Set the device driver library name.

```
void setSSLHardwareType(
    GlobalSettings.SSLHardwareType value
)
```

setSSLHardwareTypeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the device driver library name. This is a location specific function, any action will operate on the specified location.

```
void setSSLHardwareTypeByLocation(
    String location
    GlobalSettings.SSLHardwareType value
)
```

setSSLSessionCacheSize(value) throws InvalidInput, DeploymentError

Set the maximum number of entries in the SSL session cache. This is used to provide persistence based on SSL session IDs.

```
void setSSLSessionCacheSize(
    Unsigned Integer value
)
```

setSSLSessionCacheSizeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the maximum number of entries in the SSL session cache. This is used to provide persistence based on SSL session IDs. This is a location specific function, any action will operate on the specified location.

```
void setSSLSessionCacheSizeByLocation(
   String location
```

```
Unsigned Integer value
)
```

setSSLSessionIDCacheExpiryTime(value) throws InvalidInput, DeploymentError

Set the length of time that SSL session IDs are stored, in seconds.

```
void setSSLSessionIDCacheExpiryTime(
    Unsigned Integer value
)
```

setSSLSessionIDCacheExpiryTimeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the length of time that SSL session IDs are stored, in seconds. This is a location specific function, any action will operate on the specified location.

```
void setSSLSessionIDCacheExpiryTimeByLocation(
    String location
    Unsigned Integer value
)
```

setSSLSessionIDCacheSize(value) throws InvalidInput, DeploymentError

Set the number of entries in the SSL session ID cache.

```
void setSSLSessionIDCacheSize(
    Unsigned Integer value
)
```

setSSLSessionIDCacheSizeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the number of entries in the SSL session ID cache. This is a location specific function, any action will operate on the specified location.

```
void setSSLSessionIDCacheSizeByLocation(
    String location
    Unsigned Integer value
)
```

setSSLSupportSSL2(value) throws InvalidInput, DeploymentError

Set whether SSLv2 support is enabled.

```
void setSSLSupportSSL2(
    Boolean value
)
```

setSSLSupportSSL2ByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set whether SSLv2 support is enabled. This is a location specific function, any action will operate on the specified location.

```
void setSSLSupportSSL2ByLocation(
    String location
    Boolean value
)
```

setSSLSupportSSL3(value) throws InvalidInput, DeploymentError

Set whether SSLv3 support is enabled.

```
void setSSLSupportSSL3(
    Boolean value
)
```

setSSLSupportSSL3ByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set whether SSLv3 support is enabled. This is a location specific function, any action will operate on the specified location.

```
void setSSLSupportSSL3ByLocation(
    String location
    Boolean value
)
```

setSSLSupportTLS1(value) throws InvalidInput, DeploymentError

Set whether TLSv1 support is enabled.

```
void setSSLSupportTLS1(
    Boolean value
```

)

setSSLSupportTLS11(value) throws InvalidInput, DeploymentError

Set whether TLSv1.1 support is enabled.

```
void setSSLSupportTLS11(
    Boolean value
)
```

setSSLSupportTLS11ByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set whether TLSv1.1 support is enabled. This is a location specific function, any action will operate on the specified location.

```
void setSSLSupportTLS11ByLocation(
    String location
    Boolean value
)
```

setSSLSupportTLS1ByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set whether TLSv1 support is enabled. This is a location specific function, any action will operate on the specified location.

```
void setSSLSupportTLS1ByLocation(
    String location
    Boolean value
)
```

setSharedPoolSize(value) throws InvalidInput, DeploymentError

Set is the size of shared memory pool to be used for shared storage across worker processes.

```
void setSharedPoolSize(
    String value
)
```

setSharedPoolSizeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set is the size of shared memory pool to be used for shared storage across worker processes. This is a location specific function, any action will operate on the specified location.

```
void setSharedPoolSizeByLocation(
    String location
    String value
)
```

setSoapIdleMinutes(value) throws InvalidInput, DeploymentError

Set the number of minutes the SOAP server remain idle before exiting

```
void setSoapIdleMinutes(
    Unsigned Integer value
)
```

setSoapIdleMinutesByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the number of minutes the SOAP server remain idle before exiting This is a location specific function, any action will operate on the specified location.

```
void setSoapIdleMinutesByLocation(
    String location
    Unsigned Integer value
)
```

setSocketOptimizations(value) throws InvalidInput, DeploymentError

Set whether potential network socket optimisations should be used.

```
void setSocketOptimizations(
    GlobalSettings.SocketOptimizations value
)
```

setSocketOptimizationsByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set whether potential network socket optimisations should be used. This is a location specific function, any action will operate on the specified location.

```
void setSocketOptimizationsByLocation(
   String location
   GlobalSettings.SocketOptimizations value
)
```

setSsIdAccel(value) throws InvalidInput, DeploymentError

setSsldAccel is deprecated, please use setSSLHardwareAccelerator instead.

```
void setSsldAccel(
    Boolean value
)
```

setSsIdAccelByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

setSsldAccel is deprecated, please use setSSLHardwareAccelerator instead. This is a location specific function, any action will operate on the specified location.

```
void setSsldAccelByLocation(
    String location
    Boolean value
)
```

setSsldLibrary(value) throws InvalidInput, DeploymentError

setSsldLibrary is deprecated, please use setSSLHardwareType instead.

```
void setSsldLibrary(
    GlobalSettings.SsldLibrary value
)
```

setSsIdLibraryByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

setSsldLibrary is deprecated, please use setSSLHardwareType instead. This is a location specific function, any action will operate on the specified location.

```
void setSsldLibraryByLocation(
    String location
    GlobalSettings.SsldLibrary value
)
```

setStateSyncTime(value) throws InvalidInput, DeploymentError

Set how often the cache state is propagated to other traffic managers in the cluster, in seconds.

```
void setStateSyncTime(
    Unsigned Integer value
)
```

setStateSyncTimeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set how often the cache state is propagated to other traffic managers in the cluster, in seconds. This is a location specific function, any action will operate on the specified location.

```
void setStateSyncTimeByLocation(
    String location
    Unsigned Integer value
)
```

setStateSyncTimeout(value) throws InvalidInput, DeploymentError

Set the timeout for state propagation between cluster members, in seconds

```
void setStateSyncTimeout(
    Unsigned Integer value
)
```

setStateSyncTimeoutByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the timeout for state propagation between cluster members, in seconds This is a location specific function, any action will operate on the specified location.

```
void setStateSyncTimeoutByLocation(
   String location
   Unsigned Integer value
)
```

setSystemReadBufferSize(value) throws InvalidInput, DeploymentError

Set the size of the operating system's read buffer, in bytes (0 means use the system default).

```
void setSystemReadBufferSize(
    Unsigned Integer value
)
```

setSystemReadBufferSizeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the size of the operating system's read buffer, in bytes (0 means use the system default). This is a location specific function, any action will operate on the specified location.

```
void setSystemReadBufferSizeByLocation(
    String location
    Unsigned Integer value
)
```

setSystemWriteBufferSize(value) throws InvalidInput, DeploymentError

Set the size of the operating system's write buffer, in bytes (0 means use the system default).

```
void setSystemWriteBufferSize(
    Unsigned Integer value
)
```

setSystemWriteBufferSizeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the size of the operating system's write buffer, in bytes (0 means use the system default). This is a location specific function, any action will operate on the specified location.

```
void setSystemWriteBufferSizeByLocation(
    String location
    Unsigned Integer value
)
```

setTrafficIPGroupLimit(value) throws InvalidInput, DeploymentError

Set the maximum number of Traffic IP Groups allowed.

```
void setTrafficIPGroupLimit(
    Unsigned Integer value
)
```

setTrafficIPGroupLimitByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the maximum number of Traffic IP Groups allowed. This is a location specific function, any action will operate on the specified location.

```
void setTrafficIPGroupLimitByLocation(
   String location
   Unsigned Integer value
)
```

setTrafficScriptMemoryWarning(value) throws InvalidInput, DeploymentError

Set the amount of buffered network data a TrafficScript rule can buffer before a warning is logged, in bytes.

```
void setTrafficScriptMemoryWarning(
    Unsigned Integer value
)
```

setTrafficScriptMemoryWarningByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the amount of buffered network data a TrafficScript rule can buffer before a warning is logged, in bytes. This is a location specific function, any action will operate on the specified location.

```
void setTrafficScriptMemoryWarningByLocation(
    String location
    Unsigned Integer value
)
```

setTrafficscriptArrayElements(value) throws InvalidInput, DeploymentError

Set the number of array elements that can be stored before additional memory is allocated.

```
void setTrafficscriptArrayElements(
    Unsigned Integer value
)
```

setTrafficscriptArrayElementsByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the number of array elements that can be stored before additional memory is allocated. This is a location specific function, any action will operate on the specified location.

```
void setTrafficscriptArrayElementsByLocation(
   String location
   Unsigned Integer value
)
```

setTrafficscriptDataSize(value) throws InvalidInput, DeploymentError

Set the maximum size of the TrafficScript shared data pool (specified as a percentage of system RAM, e.g. '5%', or an absolute size, e.g. 200MB)

```
void setTrafficscriptDataSize(
    String value
)
```

setTrafficscriptDataSizeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the maximum size of the TrafficScript shared data pool (specified as a percentage of system RAM, e.g. '5%', or an absolute size, e.g. 200MB) This is a location specific function, any action will operate on the specified location.

```
void setTrafficscriptDataSizeByLocation(
    String location
    String value
)
```

setTrafficscriptMaxInstr(value) throws InvalidInput, DeploymentError

Set the maximum number of instructions a TrafficScript rule will run before being aborted.

```
void setTrafficscriptMaxInstr(
    Unsigned Integer value
)
```

setTrafficscriptMaxInstrByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the maximum number of instructions a TrafficScript rule will run before being aborted. This is a location specific function, any action will operate on the specified location.

```
void setTrafficscriptMaxInstrByLocation(
    String location
```

```
Unsigned Integer value
)
```

setTrafficscriptRegexCacheSize(value) throws InvalidInput, DeploymentError

Set the number of regular expressions to cache

```
void setTrafficscriptRegexCacheSize(
    Unsigned Integer value
)
```

setTrafficscriptRegexCacheSizeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the number of regular expressions to cache This is a location specific function, any action will operate on the specified location.

```
void setTrafficscriptRegexCacheSizeByLocation(
    String location
    Unsigned Integer value
)
```

setTrafficscriptRegexMatchLimit(value) throws InvalidInput, DeploymentError

Set the maximum number of ways TrafficScript will attempt to match a regular expression at each position in the subject string, before it aborts the rule and reports a TrafficScript error.

```
void setTrafficscriptRegexMatchLimit(
    Unsigned Integer value
)
```

setTrafficscriptRegexMatchLimitByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the maximum number of ways TrafficScript will attempt to match a regular expression at each position in the subject string, before it aborts the rule and reports a TrafficScript error. This is a location specific function, any action will operate on the specified location.

```
void setTrafficscriptRegexMatchLimitByLocation(
    String location
    Unsigned Integer value
)
```

setTrafficscriptRegexMatchWarnPerc(value) throws InvalidInput, DeploymentError

Set the percentage of trafficscript!regex_match_limit at which TrafficScript reports a performance warning.

```
void setTrafficscriptRegexMatchWarnPerc(
    Unsigned Integer value
)
```

setTrafficscriptRegexMatchWarnPercByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the percentage of trafficscript!regex_match_limit at which TrafficScript reports a performance warning. This is a location specific function, any action will operate on the specified location.

```
void setTrafficscriptRegexMatchWarnPercByLocation(
   String location
   Unsigned Integer value
)
```

setTrafficscriptVariablePoolUse(value) throws InvalidInput, DeploymentError

Set whether the 'pool.use' and 'pool.select' TrafficScript functions accept variables as well as literal strings.

```
void setTrafficscriptVariablePoolUse(
   Boolean value
)
```

setTrafficscriptVariablePoolUseByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set whether the 'pool.use' and 'pool.select' TrafficScript functions accept variables as well as literal strings. This is a location specific function, any action will operate on the specified location.

```
void setTrafficscriptVariablePoolUseByLocation(
    String location
    Boolean value
)
```

setUipageBanner(value) throws InvalidInput, DeploymentError

Set the banner text to be displayed on all Admin Server pages.

```
void setUipageBanner(
    String value
)
```

setUniversalSessionCacheSize(value) throws InvalidInput, DeploymentError

Set the maximum number of entries in the universal session cache.

```
void setUniversalSessionCacheSize(
    Unsigned Integer value
)
```

setUniversalSessionCacheSizeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the maximum number of entries in the universal session cache. This is a location specific function, any action will operate on the specified location.

```
void setUniversalSessionCacheSizeByLocation(
    String location
    Unsigned Integer value
)
```

setWebcacheDisk(value) throws InvalidInput, DeploymentError

Set whether the webcache is stored on disk

```
void setWebcacheDisk(
    Boolean value
)
```

setWebcacheDiskByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set whether the webcache is stored on disk This is a location specific function, any action will operate on the specified location.

```
void setWebcacheDiskByLocation(
    String location
    Boolean value
```

)

setWebcacheDiskDir(value) throws InvalidInput, DeploymentError

Set the disk cache location

```
void setWebcacheDiskDir(
    String value
)
```

setWebcacheDiskDirByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the disk cache location This is a location specific function, any action will operate on the specified location.

```
void setWebcacheDiskDirByLocation(
    String location
    String value
)
```

setWebcacheMaxFileNum(value) throws InvalidInput, DeploymentError

Set the maximum number of files that can be stored in the web cache

```
void setWebcacheMaxFileNum(
    Unsigned Integer value
)
```

setWebcacheMaxFileNumByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the maximum number of files that can be stored in the web cache This is a location specific function, any action will operate on the specified location.

```
void setWebcacheMaxFileNumByLocation(
   String location
   Unsigned Integer value
)
```

GlobalSettings Function Reference

setWebcacheMaxFileSize(value) throws InvalidInput, DeploymentError

Set the largest size of a cacheable object, relative to the total cache size, e.g. '2%', or as an absolute size in kB (default), MB or GB, e.g. '20MB'.

```
void setWebcacheMaxFileSize(
    String value
)
```

setWebcacheMaxFileSizeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the largest size of a cacheable object, relative to the total cache size, e.g. '2%', or as an absolute size in kB (default), MB or GB, e.g. '20MB'. This is a location specific function, any action will operate on the specified location.

```
void setWebcacheMaxFileSizeByLocation(
    String location
    String value
)
```

setWebcacheNormalizeQuery(value) throws InvalidInput, DeploymentError

Set whether the assignment sub-strings in the parameter string are put into alphabetical order.

```
void setWebcacheNormalizeQuery(
    Boolean value
)
```

setWebcacheNormalizeQueryByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set whether the assignment sub-strings in the parameter string are put into alphabetical order. This is a location specific function, any action will operate on the specified location.

```
void setWebcacheNormalizeQueryByLocation(
    String location
    Boolean value
)
```

setWebcacheSize(value) throws InvalidInput, DeploymentError

Set the maximum size of the HTTP web page cache, (specified as a percentage of system RAM, e.g. '20%', or an absolute size, e.g. 200MB)

Function Reference GlobalSettings

```
void setWebcacheSize(
    String value
)
```

setWebcacheSizeByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set the maximum size of the HTTP web page cache, (specified as a percentage of system RAM, e.g. '20%', or an absolute size, e.g. 200MB) This is a location specific function, any action will operate on the specified location.

```
void setWebcacheSizeByLocation(
   String location
   String value
)
```

setWebcacheVerbose(value) throws InvalidInput, DeploymentError

Set whether an X-Cache-Info header to show cacheability should be added.

```
void setWebcacheVerbose(
   Boolean value
)
```

setWebcacheVerboseByLocation(location, value) throws InvalidInput, DeploymentError, ObjectDoesNotExist

Set whether an X-Cache-Info header to show cacheability should be added. This is a location specific function, any action will operate on the specified location.

```
void setWebcacheVerboseByLocation(
   String location
   Boolean value
)
```

Enumerations

GlobalSettings.AdminAllowRehandshake

```
enum GlobalSettings.AdminAllowRehandshake {
    # Always allow
```

GlobalSettings Function Reference

```
always,

# Allow safe re-handshakes
safe,

# Only if client uses RFC 5746 (Secure
Renegotiation

# Extension)
rfc5746,

# Never allow
never
}
```

GlobalSettings.AdminDiffieHellmanKeyLength

```
enum GlobalSettings.AdminDiffieHellmanKeyLength {
    # 1024
    dh_1024,

    # 2048
    dh_2048,

# 3072
    dh_3072,

# 4096
    dh_4096
}
```

GlobalSettings.ErrorLevel

```
enum GlobalSettings.ErrorLevel {
    # ERR_FATAL
    fatal,
```

Function Reference GlobalSettings

```
# ERR_SERIOUS
serious,

# ERR_WARN
warn,

# ERR_INFO
info
```

GlobalSettings.FlipperHeartbeatMethod

```
enum GlobalSettings.FlipperHeartbeatMethod {
    # multicast
    multicast,

# unicast
    unicast
}
```

GlobalSettings.SSL3AllowRehandshake

```
enum GlobalSettings.SSL3AllowRehandshake {
    # Always allow
    always,

# Allow safe re-handshakes
    safe,

# Only if client uses RFC 5746 (Secure
Renegotiation
    # Extension)
    rfc5746,
```

GlobalSettings Function Reference

```
# Never allow
never
}
```

GlobalSettings.SSL3DiffieHellmanKeyLength

```
enum GlobalSettings.SSL3DiffieHellmanKeyLength {
    # 1024
    dh_1024,

    # 2048
    dh_2048,

# 3072
    dh_3072,

# 4096
    dh_4096
}
```

GlobalSettings.SSLHardwarePKCS11SlotType

```
enum GlobalSettings.SSLHardwarePKCS11SlotType {
    # Operator Card Set
    operator,

# Soft Card
    softcard,

# Local Module
    module
}
```

GlobalSettings.SSLHardwareType

```
enum GlobalSettings.SSLHardwareType {
```

Function Reference GlobalSettings

```
# None
none,

# PKCS#11 (e.g. nCipher NetHSM, Sun SCA 6000)
pkcs11,

# Cavium Networks CN1000
cn1000,

# Cavium Networks CN2000
cn2000
}
```

GlobalSettings.SocketOptimizations

```
enum GlobalSettings.SocketOptimizations {
    # auto
    auto,

# Yes
    Yes,

# No
    No
}
```

GlobalSettings.SsldLibrary

```
enum GlobalSettings.SsldLibrary {
    # None
    none,

# PKCS#11 (e.g. nCipher NetHSM, Sun SCA 6000)
    pkcs11,
```

Conf.Extra Function Reference

```
# Cavium Networks CN1000
cn1000,

# Cavium Networks CN2000
cn2000
}
```

Conf.Extra

URI: http://soap.zeus.com/zxtm/1.1/Conf/Extra/

The Conf.Extra interface allows management of the files stored in the conf/extra directory. These files can be read in by rules, and used as error pages to be sent to clients. This interface allows creating, deleting and retrieving the files.

Methods

deleteFile(names) throws ObjectDoesNotExist

Delete the named files from the conf/extra directory.

```
void deleteFile(
    String[] names
)
```

downloadFile(name) throws ObjectDoesNotExist

Download the named from from the conf/extra directory

```
Binary Data downloadFile(
    String name
)
```

getFileNames()

Get the names of all the files stored in the conf/extra directory.

```
String[] getFileNames()
```

uploadFile(name, content) throws InvalidObjectName

Uploads a new file into the conf/extra, overwriting the file if it already exists.

Function Reference Diagnose

```
void uploadFile(
    String name
    Binary Data content
)
```

Diagnose

URI: http://soap.zeus.com/zxtm/1.1/Diagnose/

The Diagnose interface provides information about errors and problems in the system.

Methods

activateTrafficManagers(hostnames) throws InvalidInput

Activate traffic managers that have recovered from failures and are ready to start taking Traffic IPs.

```
void activateTrafficManagers(
    String[] hostnames
)
```

diagnoseSystem()

Provides all diagnostic information about the system.

```
Diagnose.ErrorInfo diagnoseSystem()
```

getInactiveTrafficManagers()

List the traffic managers that have recovered from failures and are ready to start taking Traffic IPs.

```
String[] getInactiveTrafficManagers()
```

getTechnicalSupportReport()

Download a technical support report suitable for providing to your support provider to help diagnose problems.

```
Binary Data getTechnicalSupportReport()
```

Diagnose Function Reference

Structures

Diagnose.AgeError

This structure combines an error message with its age in seconds

```
struct Diagnose.AgeError {
    # Seconds since the error occurred
    Integer age;

# error message
    String error;
}
```

Diagnose.ConfigError

This structure contains information about configuration errors.

```
struct Diagnose.ConfigError {
    # The file where the error has occurred.
    String filename;

# The faulty configuration key
    String ConfigKey;

# Severity of the error
    Diagnose.ErrLevel severity;

# Date when the error occurred
    Time DetectionDate;

# A human readable description of the error
    String description;
}
```

Function Reference Diagnose

Diagnose. ErrorInfo

This structure combines configuration, node, and flipper errors as well as a list of statuses (for an appliance).

```
# The list of traffic managers that could not be
contacted.

String[] NotReachableTrafficManagers;

# The list of configuration errors.

Diagnose.ConfigError[] ConfigErrors;

# The list of flipper errors.

Diagnose.FlipperError[] FlipperErrors;

# The list of failed nodes.

Diagnose.FailedNode[] FailedNodes;

# The list of system status values.

Diagnose.SystemStatus[] SystemStatuses;
}
```

Diagnose.FailedNode

This structure contains information about Flipper errors.

```
struct Diagnose.FailedNode {
    # The name of the node that has failed.
    String node;

# IP address in standard IPv4 or IPv6 notation.
    String IPAddress;

# The port number of the node that has failed.
    Integer port;
```

Diagnose Function Reference

```
# The pool in which this node exists.
String pool;

# Time that the failure first occurred.
Time InitialFailureTime;

# The last time an attempt was made to connect to the node.
Time LastConnectionAttempt;

# The last received error message.
String ErrorMessage;
}
```

Diagnose.FlipperError

This structure contains information about Flipper errors.

```
struct Diagnose.FlipperError {
    # The name of the affected machine.
    String machine;

# IP address in standard IPv4 or IPv6 notation.
    String IPAddress;

# All error messages for that machine.
    Diagnose.AgeError[] errors;
}
```

Diagnose.SystemStatus

Status information about the hardware in an appliance is reported by instances of this structure.

```
struct Diagnose.SystemStatus {
    # The component this object refers to
    String component;
```

Function Reference Diagnose

```
# The severity level
Diagnose.ErrLevel severity;

# Human-readable description of the status
String message;
}
```

Enumerations

Diagnose.ErrLevel

This enumeration defines the possible severity levels of an error.

```
enum Diagnose.ErrLevel {
   # A fatal error, causes program to die/crash/fail
to startup.
  ERR FATAL,
   # A serious, unexpected error that shouldn't occur
under
  # normal conditions. Conditions which will prevent
the server
   # from operating properly and should be brought to
the
   # webmaster's attention immediately
  ERR SERIOUS,
   # something which should be brought to the
attention of the
   # webmaster, but not immediately.
  ERR WARN,
   # Minor things that might be of interest e.g.
access denied.
  ERR INFO
```

System.Backups Function Reference

System.Backups

URI: http://soap.zeus.com/zxtm/1.0/System/Backups/

The Backups interfaces provide operations on saved configuration backup archives.

Methods

createBackup(name, description) throws ObjectAlreadyExists, InvalidObjectName

Create backup archive based on the current configuration

```
void createBackup(
    String name
    String description
)
```

deleteAllBackups()

Delete all the backups

```
void deleteAllBackups()
```

deleteBackups(names) throws ObjectDoesNotExist

Delete one or more backups

```
void deleteBackups(
    String[] names
)
```

downloadBackup(name) throws ObjectDoesNotExist

Download a named backup archive

```
Binary Data downloadBackup(
    String name
)
```

getBackupDetails(names)

Get details for one or more backups.

```
System.Backups.Backup[] getBackupDetails(
```

Function Reference System.Backups

```
String[] names
)
```

listAllBackups()

List the details for all backup archives.

```
System.Backups.Backup[] listAllBackups()
```

restoreBackup(name) throws ObjectDoesNotExist

Restore the named backup archive to be the current configuration

```
void restoreBackup(
    String name
)
```

uploadBackup(name, backup) throws InvalidObjectName, ObjectAlreadyExists, InvalidInput

Upload a backup archive

```
void uploadBackup(
    String name
    Binary Data backup
)
```

Structures

System.Backups.Backup

This structure contains the information for each configuration backup archive.

```
struct System.Backups.Backup {
    # The backup filename.
    String name;

# The description for this backup.
    String description;

# The date this backup was created.
```

```
Time date;

# The version of this backup archive.
String version;
}
```

Alerting.EventType

```
URI: http://soap.zeus.com/zxtm/1.0/Alerting/EventType/
```

Alerting. Event Type is an interface that allows you to manage event types. Event Types are groups of events and are associated with a list of actions that are invoked when one of the events in the Event Type is triggered.

Methods

addCloudcredentialNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Add the names of Cloud Credentials that will trigger the specified event types. If the event type has no Cloud Credentials names configured, all objects of this type will match.

```
void addCloudcredentialNames(
    String[] names
    String[][] objects
)
```

addCustomEvents(names, events) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Adds custom events the specified event types will trigger on. Custom events are generated by TrafficScript using the event.emit function. To match all custom events, include '*' in the passed array.

```
void addCustomEvents(
    String[] names
    String[][] events
)
```

addEventType(names, eventtypes) throws ObjectAlreadyExists, InvalidObjectName, InvalidInput, DeploymentError

Add an event type that will cause an action to be triggered when its conditions are met.

```
void addEventType(
    String[] names
    Alerting.EventType.EventType[] eventtypes
)
```

addEvents(names, events) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Adds events to an event type. An event is something that must occur for the associated actions to be triggered (only one event needs to happen to trigger the actions). At least one event must be specified.

```
void addEvents(
    String[] names
    Alerting.EventType.Event[][] events
)
```

addLicensekeyNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Add the names of License Key that will trigger the specified event types. If the event type has no License Key names configured, all objects of this type will match.

```
void addLicensekeyNames(
    String[] names
    String[][] objects
)
```

addLocationNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Add the names of Location that will trigger the specified event types. If the event type has no Location names configured, all objects of this type will match.

```
void addLocationNames(
    String[] names
    String[][] objects
)
```

addMappedActions(names, values) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Add an action that will be run when this event type is triggered.

```
void addMappedActions(
    String[] names
    String[][] values
)
```

addMonitorNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Add the names of Monitor that will trigger the specified event types. If the event type has no Monitor names configured, all objects of this type will match.

```
void addMonitorNames(
    String[] names
    String[][] objects
)
```

addNodeNames(names, events) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Add the names of Node that will trigger the specified event types. If the event type has no Node names configured, all objects of this type will match.

```
void addNodeNames(
    String[] names
    String[][] events
)
```

addPoolNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Add the names of Pool that will trigger the specified event types. If the event type has no Pool names configured, all objects of this type will match.

```
void addPoolNames(
    String[] names
    String[][] objects
)
```

addProtectionNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Add the names of Service Protection Class that will trigger the specified event types. If the event type has no Service Protection Class names configured, all objects of this type will match.

```
void addProtectionNames(
    String[] names
    String[][] objects
)
```

addRuleNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Add the names of Rule that will trigger the specified event types. If the event type has no Rule names configured, all objects of this type will match.

```
void addRuleNames(
    String[] names
    String[][] objects
)
```

addServiceNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Add the names of GLB Service that will trigger the specified event types. If the event type has no GLB Service names configured, all objects of this type will match.

```
void addServiceNames(
    String[] names
    String[][] objects
)
```

addSImNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Add the names of SLM Class that will trigger the specified event types. If the event type has no SLM Class names configured, all objects of this type will match.

```
void addSlmNames(
    String[] names
    String[][] objects
)
```

addVserverNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Add the names of Virtual Server that will trigger the specified event types. If the event type has no Virtual Server names configured, all objects of this type will match.

```
void addVserverNames(
    String[] names
    String[][] objects
)
```

addZxtmNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Add the names of Traffic Manager that will trigger the specified event types. If the event type has no Traffic Manager names configured, all objects of this type will match.

```
void addZxtmNames(
    String[] names
    String[][] objects
)
```

copyEventType(names, new_names) throws ObjectAlreadyExists, ObjectDoesNotExist, InvalidObjectName, DeploymentError

Copy each of the named event types.

```
void copyEventType(
    String[] names
    String[] new_names
)
```

deleteEventType(names) throws ObjectDoesNotExist, DeploymentError

Removes one or more event types.

```
void deleteEventType(
    String[] names
)
```

getCloudcredentialNames(names) throws ObjectDoesNotExist

Get the names of Cloud Credentials that will trigger the specified event types. If the event type has no Cloud Credentials names configured, all objects of this type will match.

```
String[][] getCloudcredentialNames(
    String[] names
)
```

getCustomEvents(names) throws ObjectDoesNotExist

Gets the custom events of the specified event types. Custom events are generated by TrafficScript using the event.emit function. If '*' is returned, all custom events will trigger this event type.

```
String[][] getCustomEvents(
    String[] names
)
```

getEventType(names) throws ObjectDoesNotExist

Returns a set of event type objects for the specified names.

```
Alerting.EventType.EventType[] getEventType(
    String[] names
)
```

getEventTypeNames()

Returns the names of all event types in the system.

```
String[] getEventTypeNames()
```

getEvents(names) throws ObjectDoesNotExist

Gets an event type's events. An event is something that must occur for the associated actions to be triggered (only one event needs to happen to trigger the actions). At least one event must be specified.

```
Alerting.EventType.Event[][] getEvents(
    String[] names
)
```

getLicensekeyNames(names) throws ObjectDoesNotExist

Get the names of License Key that will trigger the specified event types. If the event type has no License Key names configured, all objects of this type will match.

```
String[][] getLicensekeyNames(
    String[] names
)
```

getLocationNames(names) throws ObjectDoesNotExist

Get the names of Location that will trigger the specified event types. If the event type has no Location names configured, all objects of this type will match.

```
String[][] getLocationNames(
    String[] names
)
```

getMappedActions(names) throws ObjectDoesNotExist

Get an action that will be run when this event type is triggered.

```
String[][] getMappedActions(
    String[] names
)
```

getMonitorNames(names) throws ObjectDoesNotExist

Get the names of Monitor that will trigger the specified event types. If the event type has no Monitor names configured, all objects of this type will match.

```
String[][] getMonitorNames(
    String[] names
)
```

getNodeNames(names) throws ObjectDoesNotExist

Get the names of Node that will trigger the specified event types. If the event type has no Node names configured, all objects of this type will match.

```
String[][] getNodeNames(
    String[] names
)
```

getNote(names) throws ObjectDoesNotExist

Get the note for each of the named Event Types.

```
String[] getNote(
    String[] names
)
```

getPoolNames(names) throws ObjectDoesNotExist

Get the names of Pool that will trigger the specified event types. If the event type has no Pool names configured, all objects of this type will match.

```
String[][] getPoolNames(
    String[] names
)
```

getProtectionNames(names) throws ObjectDoesNotExist

Get the names of Service Protection Class that will trigger the specified event types. If the event type has no Service Protection Class names configured, all objects of this type will match.

```
String[][] getProtectionNames(
    String[] names
)
```

getRuleNames(names) throws ObjectDoesNotExist

Get the names of Rule that will trigger the specified event types. If the event type has no Rule names configured, all objects of this type will match.

```
String[][] getRuleNames(
    String[] names
)
```

getServiceNames(names) throws ObjectDoesNotExist

Get the names of GLB Service that will trigger the specified event types. If the event type has no GLB Service names configured, all objects of this type will match.

```
String[][] getServiceNames(
    String[] names
)
```

getSImNames(names) throws ObjectDoesNotExist

Get the names of SLM Class that will trigger the specified event types. If the event type has no SLM Class names configured, all objects of this type will match.

```
String[][] getSlmNames(
    String[] names
)
```

getVserverNames(names) throws ObjectDoesNotExist

Get the names of Virtual Server that will trigger the specified event types. If the event type has no Virtual Server names configured, all objects of this type will match.

```
String[][] getVserverNames(
    String[] names
)
```

getZxtmNames(names) throws ObjectDoesNotExist

Get the names of Traffic Manager that will trigger the specified event types. If the event type has no Traffic Manager names configured, all objects of this type will match.

```
String[][] getZxtmNames(
    String[] names
)
```

removeCloudcredentialNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Remove the names of Cloud Credentials that will trigger the specified event types. If the event type has no Cloud Credentials names configured, all objects of this type will match.

```
void removeCloudcredentialNames(
   String[] names
   String[][] objects
)
```

removeCustomEvents(names, events) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Removes custom events from the specified event types. Custom events are generated by TrafficScript using the event.emit function. If you pass '*', all custom events will be removed.

```
void removeCustomEvents(
```

```
String[] names
String[][] events
)
```

removeEvents(names, events) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Removes events from the event type. An event is something that must occur for the associated actions to be triggered (only one event needs to happen to trigger the actions). At least one event must be specified.

```
void removeEvents(
    String[] names
    Alerting.EventType.Event[][] events
)
```

removeLicensekeyNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Remove the names of License Key that will trigger the specified event types. If the event type has no License Key names configured, all objects of this type will match.

```
void removeLicensekeyNames(
    String[] names
    String[][] objects
)
```

removeLocationNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Remove the names of Location that will trigger the specified event types. If the event type has no Location names configured, all objects of this type will match.

```
void removeLocationNames(
    String[] names
    String[][] objects
)
```

removeMappedActions(names, values) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Remove an action that will be run when this event type is triggered.

```
void removeMappedActions(
    String[] names
    String[][] values
)
```

removeMonitorNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Remove the names of Monitor that will trigger the specified event types. If the event type has no Monitor names configured, all objects of this type will match.

```
void removeMonitorNames(
    String[] names
    String[][] objects
)
```

removeNodeNames(names, events) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Remove the names of Node that will trigger the specified event types. If the event type has no Node names configured, all objects of this type will match.

```
void removeNodeNames(
    String[] names
    String[][] events
)
```

removePoolNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Remove the names of Pool that will trigger the specified event types. If the event type has no Pool names configured, all objects of this type will match.

```
void removePoolNames(
    String[] names
    String[][] objects
)
```

removeProtectionNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Remove the names of Service Protection Class that will trigger the specified event types. If the event type has no Service Protection Class names configured, all objects of this type will match.

```
void removeProtectionNames(
    String[] names
    String[][] objects
)
```

removeRuleNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Remove the names of Rule that will trigger the specified event types. If the event type has no Rule names configured, all objects of this type will match.

```
void removeRuleNames(
    String[] names
    String[][] objects
)
```

removeServiceNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Remove the names of GLB Service that will trigger the specified event types. If the event type has no GLB Service names configured, all objects of this type will match.

```
void removeServiceNames(
    String[] names
    String[][] objects
)
```

removeSImNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Remove the names of SLM Class that will trigger the specified event types. If the event type has no SLM Class names configured, all objects of this type will match.

```
void removeSlmNames(
    String[] names
    String[][] objects
)
```

removeVserverNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Remove the names of Virtual Server that will trigger the specified event types. If the event type has no Virtual Server names configured, all objects of this type will match.

```
void removeVserverNames(
    String[] names
    String[][] objects
)
```

removeZxtmNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Remove the names of Traffic Manager that will trigger the specified event types. If the event type has no Traffic Manager names configured, all objects of this type will match.

```
void removeZxtmNames(
    String[] names
    String[][] objects
)
```

renameEventType(names, new_names) throws ObjectAlreadyExists, ObjectDoesNotExist, InvalidObjectName, DeploymentError, InvalidOperation

Rename each of the named event types.

```
void renameEventType(
    String[] names
    String[] new_names
)
```

setCloudcredentialNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Set the names of Cloud Credentials that will trigger the specified event types. If the event type has no Cloud Credentials names configured, all objects of this type will match.

```
void setCloudcredentialNames(
    String[] names
    String[][] objects
)
```

setCustomEvents(names, events) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Gets the custom events the specified event types will trigger on. Custom events are generated by TrafficScript using the event.emit function. To match all custom events, include '*' in the passed array.

```
void setCustomEvents(
    String[] names
    String[][] events
)
```

setEvents(names, events) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Sets an event type's events (all old events will be removed). An event is something that must occur for the associated actions to be triggered (only one event needs to happen to trigger the actions). At least one event must be specified.

```
void setEvents(
    String[] names
    Alerting.EventType.Event[][] events
)
```

setLicensekeyNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Set the names of License Key that will trigger the specified event types. If the event type has no License Key names configured, all objects of this type will match.

```
void setLicensekeyNames(
   String[] names
   String[][] objects
)
```

setLocationNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Set the names of Location that will trigger the specified event types. If the event type has no Location names configured, all objects of this type will match.

```
void setLocationNames(
   String[] names
```

```
String[][] objects
)
```

setMappedActions(names, values) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Set an action that will be run when this event type is triggered.

```
void setMappedActions(
    String[] names
    String[][] values
)
```

setMonitorNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Set the names of Monitor that will trigger the specified event types. If the event type has no Monitor names configured, all objects of this type will match.

```
void setMonitorNames(
    String[] names
    String[][] objects
)
```

setNodeNames(names, events) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Set the names of Node that will trigger the specified event types. If the event type has no Node names configured, all objects of this type will match.

```
void setNodeNames(
    String[] names
    String[][] events
)
```

setNote(names, values) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Set the note for each of the named Event Types.

```
void setNote(
    String[] names
```

```
String[] values
```

setPoolNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Set the names of Pool that will trigger the specified event types. If the event type has no Pool names configured, all objects of this type will match.

```
void setPoolNames(
    String[] names
    String[][] objects
)
```

setProtectionNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Set the names of Service Protection Class that will trigger the specified event types. If the event type has no Service Protection Class names configured, all objects of this type will match.

```
void setProtectionNames(
   String[] names
   String[][] objects
)
```

setRuleNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Set the names of Rule that will trigger the specified event types. If the event type has no Rule names configured, all objects of this type will match.

```
void setRuleNames(
    String[] names
    String[][] objects
)
```

setServiceNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Set the names of GLB Service that will trigger the specified event types. If the event type has no GLB Service names configured, all objects of this type will match.

```
void setServiceNames(
```

```
String[] names
String[][] objects
)
```

setSImNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Set the names of SLM Class that will trigger the specified event types. If the event type has no SLM Class names configured, all objects of this type will match.

```
void setSlmNames(
    String[] names
    String[][] objects
)
```

setVserverNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Set the names of Virtual Server that will trigger the specified event types. If the event type has no Virtual Server names configured, all objects of this type will match.

```
void setVserverNames(
    String[] names
    String[][] objects
)
```

setZxtmNames(names, objects) throws InvalidInput, ObjectDoesNotExist, InvalidOperation, DeploymentError

Set the names of Traffic Manager that will trigger the specified event types. If the event type has no Traffic Manager names configured, all objects of this type will match.

```
void setZxtmNames(
    String[] names
    String[][] objects
)
```

Structures

Alerting.EventType.EventType

A set of conditions that when met causes an action to be run.

```
struct Alerting.EventType.EventType {
   # The events that will trigger the associated
  Alerting.EventType.Event[] events;
   # The names of all the custom events you want to
trigger this
   # event type.
   String[] customEvents;
   # The names of all the actions mapped to this
custom event.
  String[] mappedActions;
   # The names of all the Service Protection Classes
that should
   # trigger this event type. If this is an empty
array all
   # objects of this type will be matched.
   String[] protectionNames;
   # The names of all the Virtual Servers that should
trigger
   # this event type. If this is an empty array all
objects of
   # this type will be matched.
   String[] vserverNames;
   # The names of all the SLM Classes that should
trigger this
   # event type. If this is an empty array all
objects of this
   # type will be matched.
   String[] slmNames;
   # The names of all the Locations that should
trigger this
```

```
# event type. If this is an empty array all
objects of this
   # type will be matched.
   String[] locationNames;
   # The names of all the Monitors that should
trigger this event
   # type. If this is an empty array all objects of
this type
   # will be matched.
   String[] monitorNames;
   # The names of all the GLB Services that should
trigger this
   # event type. If this is an empty array all
objects of this
   # type will be matched.
   String[] serviceNames;
   # The names of all the Rules that should trigger
this event
   # type. If this is an empty array all objects of
this type
   # will be matched.
  String[] ruleNames;
   # The names of all the Cloud Credentials that
should trigger
   # this event type. If this is an empty array all
objects of
   # this type will be matched.
   String[] cloudcredentialNames;
   # The names of all the License Keys that should
trigger this
   # event type. If this is an empty array all
objects of this
   # type will be matched.
```

```
# The names of all the Traffic Managers that
should trigger

# this event type. If this is an empty array all
objects of

# this type will be matched.

String[] zxtmNames;

# The names of all the Pools that should trigger
this event

# type. If this is an empty array all objects of
this type

# will be matched.

String[] poolNames;
```

Enumerations

Alerting.EventType.Event

```
enum Alerting.EventType.Event {
    # This event matches all events.
    ALL,

# Special value that matches all events of type
Cloud
    # Credentials.
    cloudcredentials_ALL,

# Cloud Credentials - A cloud API process querying changes to
    # cloud instances is hanging
    cloudcredentials_apistatusprocesshanging,

# Cloud Credentials - An API call made by the autoscaler
```

```
# process has returned a response that could not
be parsed
   cloudcredentials autoscaleresponseparseerror,
   # Cloud Credentials - An API call made by the
autoscaler
   # process has reported an error
   cloudcredentials autoscalestatusupdateerror,
   # Cloud Credentials - A cloud API process has
timed out
   cloudcredentials autoscalingprocesstimedout,
   # Cloud Credentials - A Cloud Credentials object
has been
   # deleted but it was still in use
   cloudcredentials usedcredsdeleted,
   # Special value that matches all events of type
Configuration
   # Files.
   config ALL,
   # Configuration Files - Configuration file added
   config confadd,
   # Configuration Files - Configuration file deleted
   config confdel,
   # Configuration Files - Configuration file
modified
   config confmod,
   # Configuration Files - Configuration file now OK
   config_confok,
```

```
Fault
   # Tolerance.
   faulttolerance ALL,
   # Fault Tolerance - Activating this machine
automatically
   # because it is the only working machine in its
Traffic IP
   # Groups
   faulttolerance activatealldead,
   # Fault Tolerance - Machine has recovered and been
activated
   # automatically because it would cause no service
disruption
   faulttolerance activatedautomatically,
   # Fault Tolerance - All machines are working
   faulttolerance allmachinesok,
   # Fault Tolerance - Removing EC2 Elastic IP
Address from all
   # machines; it is no longer a part of any Traffic
IP Groups
   faulttolerance dropec2ipwarn,
  # Fault Tolerance - Dropping Traffic IP Address
due to a
   # configuration change or traffic manager recovery
   faulttolerance_dropipinfo,
   # Fault Tolerance - Dropping Traffic IP Address
due to an
   # error
   faulttolerance dropipwarn,
```

Special value that matches all events of type

Alerting.EventType Function Reference

```
# Fault Tolerance - Moving EC2 Elastic IP Address;
local
   # machine is working
   faulttolerance ec2flipperraiselocalworking,
   # Fault Tolerance - Moving EC2 Elastic IP Address;
other
   # machines have failed
   faulttolerance ec2flipperraiseothersdead,
   # Fault Tolerance - Problem occurred when managing
an Elastic
   # IP address
   faulttolerance ec2iperr,
   # Fault Tolerance - Cannot raise Elastic IP on
this machine
   # until EC2 provides it with a public IP address
   faulttolerance ec2nopublicip,
   # Fault Tolerance - Back-end nodes are now working
   faulttolerance flipperbackendsworking,
   # Fault Tolerance - Re-raising Traffic IP Address;
Operating
   # system did not fully raise the address
   faulttolerance flipperdadreraise,
   # Fault Tolerance - Frontend machines are now
working
   faulttolerance flipperfrontendsworking,
   # Fault Tolerance - Failed to raise Traffic IP
Address; the
   # address exists elsewhere on your network and
cannot be
```

```
# raised
   faulttolerance flipperipexists,
   # Fault Tolerance - Raising Traffic IP Address;
local machine
   # is working
   faulttolerance flipperraiselocalworking,
   # Fault Tolerance - Raising Traffic IP Address;
Operating
   # System had dropped this IP address
   faulttolerance flipperraiseosdrop,
   # Fault Tolerance - Raising Traffic IP Address;
other machines
   # have failed
   faulttolerance flipperraiseothersdead,
   # Fault Tolerance - This Traffic Manager has re-
raised traffic
   # IP addresses as the remote machine which was
hosting them
   # has dropped them
   faulttolerance_flipperraiseremotedropped,
   # Fault Tolerance - Machine is ready to raise
Traffic IP
   # addresses
   faulttolerance flipperrecovered,
   # Fault Tolerance - Remote machine has failed
   faulttolerance machinefail,
   # Fault Tolerance - Remote machine is now working
   faulttolerance machineok,
```

```
and can raise
   # Traffic IP addresses
   faulttolerance machinerecovered,
   # Fault Tolerance - Remote machine has timed out
and been
   # marked as failed
   faulttolerance machinetimeout,
   # Fault Tolerance - The amount of load handled by
the local
   # machine destined for this Traffic IP has changed
   faulttolerance multihostload,
   # Fault Tolerance - Failed to ping back-end nodes
   faulttolerance pingbackendfail,
   # Fault Tolerance - Failed to ping any of the
machines used to
   # check the front-end connectivity
   faulttolerance pingfrontendfail,
   # Fault Tolerance - Failed to ping default gateway
   faulttolerance_pinggwfail,
   # Fault Tolerance - Received an invalid response
from another
   # cluster member
   faulttolerance statebaddata,
   # Fault Tolerance - Failed to connect to another
cluster
   # member for state sharing
   faulttolerance stateconnfail,
```

Fault Tolerance - Remote machine has recovered

```
# Fault Tolerance - Successfully connected to
another cluster
   # member for state sharing
   faulttolerance stateok,
   # Fault Tolerance - Reading state data from
another cluster
   # member failed
   faulttolerance statereadfail,
   # Fault Tolerance - Timeout while sending state
data to
   # another cluster member
   faulttolerance statetimeout,
   # Fault Tolerance - Received unexpected state data
from
   # another cluster member
   faulttolerance stateunexpected,
   # Fault Tolerance - Writing state data to another
cluster
   # member failed
   faulttolerance_statewritefail,
   # Fault Tolerance - An error occurred when using
the zcluster
   # Multi-Hosted IP kernel module
   faulttolerance_zclustermoderr,
   # Special value that matches all events of type
General.
   general ALL,
   # General - An error occurred during user
authentication
```

```
general autherror,
   # General - Autoscaling not permitted by licence
key
   general autoscalinglicenseerror,
   # General - Replication of configuration has
failed
   general confrepfailed,
   # General - Replication of configuration has timed
out
   general confreptimeout,
   # General - Running out of free file descriptors
   general fewfreefds,
   # General - Failed to load geolocation data
   general_geodataloadfail,
   # General - Appliance hardware notification
   general_hardware,
   # General - A location has been disabled because
you have
   # exceeded the licence limit
   general_licensetoomanylocations,
   # General - Log disk partition full
   general logdiskfull,
   # General - Log disk partition usage has exceeded
threshold
   general logdiskoverload,
```

```
# General - Software must be restarted to apply
configuration
   # changes
   general restartrequired,
   # General - Software is running
   general_running,
   # General - Time has been moved back
   general timemovedback,
   # General - The number of simultaneously active
connections
   # has reached a level that the software cannot
process in due
   # time; there is a high risk of connections timing
out
   general zxtmhighload,
   # General - Stingray Traffic Manager software
problem
   general_zxtmswerror,
   # Special value that matches all events of type
Java.
   java ALL,
   # Java - Java runner died
   java_javadied,
   # Java - Cannot start Java runner, program not
found
   java javanotfound,
   # Java - Java runner started
   java_javastarted,
```

```
# Java - Java runner failed to start
   java javastartfail,
   # Java - Java support has stopped
   java javastop,
   # Java - Java runner failed to terminate
   java javaterminatefail,
   # Java - Servlet encountered an error
   java servleterror,
   # Special value that matches all events of type
License Keys.
   licensekeys ALL,
   # License Keys - Realtime Analytics support has
been disabled
   licensekeys analyticslicensedisabled,
   # License Keys - Realtime Analytics support has
been enabled
   licensekeys_analyticslicenseenabled,
   # License Keys - Autoscaling support has been
disabled
   licensekeys autoscalinglicensedisabled,
   # License Keys - Autoscaling support has been
enabled
   licensekeys_autoscalinglicenseenabled,
   # License Keys - License key bandwidth limit has
been hit
   licensekeys bwlimited,
```

```
# License Keys - Configured cache size exceeds
license limit,
   # only using amount allowed by license
   licensekeys cachesizereduced,
   # License Keys - License key has expired
   licensekeys expired,
   # License Keys - License key expires within 7 days
   licensekeys expiresoon,
   # License Keys - License allows less memory for
caching
   licensekeys_lessmemallowed,
   # License Keys - License key authorized
   licensekeys license-authorized,
   # License Keys - License key authorized by
authorization code
   licensekeys_license-authorized-ts,
   # License Keys - Unable to authorize license key
   licensekeys license-graceperiodexpired,
   # License Keys - Unable to authorize license key
   licensekeys license-graceperiodexpired-ts,
   # License Keys - License server rejected license
key; key
   # remains authorized
   licensekeys license-rejected-authorized,
```

```
# License Keys - License key rejected from
authorization code;
   # key remains authorized
   licensekeys license-rejected-authorized-ts,
   # License Keys - License server rejected license
key; key is
   # not authorized
   licensekeys license-rejected-unauthorized,
   # License Keys - License key rejected from
authorization code
   licensekeys license-rejected-unauthorized-ts,
   # License Keys - Unable to contact license server;
license key
   # remains authorized
   licensekeys_license-timedout-authorized,
   # License Keys - Unable to run authorization code
to
   # completion; key remains valid
   licensekeys license-timedout-authorized-ts,
   # License Keys - Unable to contact license server;
license key
   # is not authorized
   licensekeys license-timedout-unauthorized,
   # License Keys - Unable to run authorization code
to
   # completion
   licensekeys license-timedout-unauthorized-ts,
   # License Keys - License key is not authorized
   licensekeys license-unauthorized,
```

```
# License Keys - Cluster size exceeds license key
limit
   licensekeys licenseclustertoobig,
   # License Keys - License key is corrupt
   licensekeys licensecorrupt,
   # License Keys - License allows more memory for
caching
   licensekeys morememallowed,
   # License Keys - License key SSL transactions-per-
second limit
   # has been hit
   licensekeys ssltpslimited,
   # License Keys - License key transactions-per-
second limit has
   # been hit
   licensekeys_tpslimited,
   # License Keys - Started without a license
   licensekeys unlicensed,
   # License Keys - Using a development license
   licensekeys usingdevlicense,
   # License Keys - Using license key
   licensekeys usinglicense,
   # Special value that matches all events of type
Locations.
  locations_ALL,
```

```
# Locations - Location has failed for GLB Service
   locations_locationfail,
   # Locations - A monitor has detected a failure in
this
   # location
   locations locationmonitorfail,
   # Locations - A monitor has indicated this
location is now
   # working
   locations locationmonitorok,
   # Locations - Location is now working for GLB
Service
   locations locationok,
   # Locations - An external SOAP agent has detected
a failure in
   # this location
   locations_locationsoapfail,
   # Locations - An external SOAP agent indicates
this location
   # is now working
   locations_locationsoapok,
   # Locations - Location no longer contains any
machines
   locations locempty,
   # Locations - Machine now in location
   locations_locmovemachine,
   # Special value that matches all events of type
Monitors.
```

```
monitors ALL,
   # Monitors - Monitor has detected a failure
  monitors_monitorfail,
   # Monitors - Monitor is working
  monitors monitorok,
   # Special value that matches all events of type
Pools.
  pools ALL,
   # Pools - API change process still running after
refractory
   # period is over
  pools apichangeprocesshanging,
   # Pools - The creation of a new node requested by
an
   # autoscaled pool is now complete
   pools autonodecreationcomplete,
   # Pools - Creation of new node instigated
  pools_autonodecreationstarted,
   # Pools - A cloud API call to destroy a node has
been started
  pools_autonodedestroyed,
   # Pools - The destruction of a node in an
autoscaled pool is
   # now complete
   pools autonodedestructioncomplete,
   # Pools - A node in an autoscaled pool has
disappeared from
```

```
# the cloud
  pools autonodedisappeared,
   # Pools - IP address of newly created instance
already existed
   # in pool's node list
  pools autonodeexisted,
   # Pools - The status of a node in an autoscaled
pool has
   # changed
   pools autonodestatuschange,
   # Pools - Two pools are trying to use the same
instance
   pools autoscalednodecontested,
   # Pools - An autoscaled pool is now refractory
  pools autoscaledpoolrefractory,
   # Pools - Over maximum size - shrinking
   pools_autoscaledpooltoobig,
   # Pools - Minimum size undercut - growing
  pools_autoscaledpooltoosmall,
   # Pools - The 'imageid' was empty when attempting
to create a
   # node in an autoscaled pool
  pools autoscaleinvalidargforcreatenode,
   # Pools - 'unique id' was empty when attempting to
destroy a
   # node in an autoscaled pool
   pools autoscaleinvalidargfordeletenode,
```

```
# Pools - A pool config file has been updated by
the
   # autoscaler process
  pools autoscalepoolconfupdate,
   # Pools - A node created by the autoscaler has the
wrong
   # imageid
   pools autoscalewrongimageid,
   # Pools - A node created by the autoscaler has a
non-matching
   # name
  pools autoscalewrongname,
   # Pools - A node created by the autoscaler has the
wrong
   # sizeid
  pools autoscalewrongsizeid,
   # Pools - An API process that should have created
or destroyed
   # a node has failed to produce the expected result
   pools autoscalingchangeprocessfailure,
   # Pools - Autoscaling for a pool has been disabled
due to
   # errors communicating with the cloud API
  pools autoscalingdisabled,
   # Pools - Minimum size reached, cannot shrink
further
   pools_autoscalinghitfloor,
```

```
# Pools - Maximum size reached by autoscaled pool,
cannot grow
   # further
   pools_autoscalinghitroof,
   # Pools - An autoscaled pool is waiting to grow
   pools autoscalinghysteresiscantgrow,
   # Pools - An autoscaled pool is waiting to shrink
   pools autoscalinghysteresiscantshrink,
   # Pools - An autoscaled pool's state has changed
   pools autoscalingpoolstatechange,
   # Pools - An autoscaled pool has failed completely
   pools_autoscalingresuscitatepool,
   # Pools - HTTP response contained an invalid
Content-Length
   # header
   pools_badcontentlen,
   # Pools - Attempt to scale down a pool that only
had pending
   # nodes or none at all
   pools cannotshrinkemptypool,
   # Pools - Node returned invalid EHLO response
  pools ehloinvalid,
   # Pools - Node has failed
   pools nodefail,
   # Pools - Failed to resolve node address
```

```
pools noderesolvefailure,
   # Pools - Node resolves to multiple IP addresses
   pools noderesolvemultiple,
   # Pools - Node is working again
   pools nodeworking,
   # Pools - Node doesn't provide STARTTLS support
  pools nostarttls,
   # Pools - Pool has no back-end nodes responding
  pools_pooldied,
   # Pools - Pool configuration contains no valid
backend nodes
  pools poolnonodes,
   # Pools - Pool now has working nodes
  pools poolok,
   # Pools - Node returned invalid STARTTLS response
  pools_starttlsinvalid,
   # Special value that matches all events of type
Service
   # Protection Classes.
  protection ALL,
   # Service Protection Classes - Summary of recent
service
   # protection events
   protection_triggersummary,
```

484

```
# Special value that matches all events of type
Rules.
  rules ALL,
   # Rules - data.set() has run out of space
   rules datastorefull,
   # Rules - Rule selected an unresolvable host
   rules forwardproxybadhost,
   # Rules - Rule used event.emit() with an invalid
custom event
  rules invalidemit,
   # Rules - Rule selected an unknown rate shaping
class
  rules_norate,
   # Rules - Rule references an unknown pool via
pool.activenodes
   rules_poolactivenodesunknown,
   # Rules - Rule selected an unknown pool
   rules pooluseunknown,
   # Rules - Rule aborted during execution
   rules_ruleabort,
   # Rules - Rule encountered invalid data while
uncompressing
   # response
  rules_rulebodycomperror,
   # Rules - Rule has buffered more data than
expected
   rules rulebufferlarge,
```

```
# Rules - Rule logged an info message using
log.info
   rules rulelogmsginfo,
   # Rules - Rule logged an error message using
log.error
   rules rulelogmsgserious,
   # Rules - Rule logged a warning message using
log.warn
  rules rulelogmsgwarn,
   # Rules - Rule selected an unknown session
persistence class
  rules rulenopersistence,
   # Rules - Client sent invalid HTTP request body
   rules rulesinvalidrequestbody,
   # Rules - Attempt to use http.getResponse or
   # http.getResponseBody after
http.stream.startResponse
   rules_rulestreamerrorgetresponse,
   # Rules - Internal error while processing HTTP
stream
  rules rulestreamerrorinternal,
   # Rules - Rule did not supply enough data in HTTP
stream
   rules rulestreamerrornotenough,
   # Rules - Attempt to initialize HTTP stream before
previous
   # stream had finished
```

486

rules rulestreamerrornotfinished,

- # streaming had been initialized
- rules rulestreamerrornotstarted,
- # Rules Data supplied to HTTP stream could not be processed
 - rules rulestreamerrorprocessfailure,
- # Rules Rule supplied too much data in HTTP stream
 - rules rulestreamerrortoomuch,
 - # Rules Rule encountered an XML error
 rules rulexmlerr,
- # Rules GLB service rule aborted during
 execution
 - rules_serviceruleabort,
- # Rules GLB service rule specified a location that has
- - # configuration
 - rules servicerulelocdead,
- - # configured for the service
 - rules_servicerulelocnotconfigured,
- # Rules GLB service rule specified an unknown location

rules servicerulelocunknown,

```
# Special value that matches all events of type
GLB Services.
  services ALL,
   # GLB Services - A DNS Query returned IP addresses
that are
   # not configured for any location that is
currently alive
  services glbdeadlocmissingips,
   # GLB Services - Failed to alter DNS packet for
global load
   # balancing
   services glbfailalter,
   # GLB Services - Failed to write log file for GLB
service
   services glblogwritefail,
   # GLB Services - A DNS Query returned IP addresses
that are
   # not configured in any location
  services_glbmissingips,
   # GLB Services - A location has been set as master
for a GLB
   # service
   services_glbnewmaster,
   # GLB Services - No valid location could be chosen
for Global
   # Load Balancing
   services_glbnolocations,
```

Alerting.EventType Function Reference

```
# GLB Services - GLB Service has no working
locations
   services_glbservicedied,
   # GLB Services - GLB Service has recovered
   services glbserviceok,
   # Special value that matches all events of type
SLM Classes.
   slm ALL,
   # SLM Classes - SLM shared memory limit exceeded
  slm slmclasslimitexceeded,
   # SLM Classes - SLM has fallen below serious
threshold
   slm slmfallenbelowserious,
   # SLM Classes - SLM has fallen below warning
threshold
   slm_slmfallenbelowwarn,
   # SLM Classes - Node information when SLM is non-
conforming
   # (no SNMP trap)
  slm_slmnodeinfo,
   # SLM Classes - SLM has risen above the serious
threshold
   slm slmrecoveredserious,
   # SLM Classes - SLM has recovered
   slm_slmrecoveredwarn,
   # Special value that matches all events of type
SSL Hardware.
```

```
sslhw ALL,
   # SSL Hardware - SSL hardware support failed
   sslhw_sslhwfail,
   # SSL Hardware - SSL hardware support restarted
   sslhw sslhwrestart,
   # SSL Hardware - SSL hardware support started
   sslhw sslhwstart,
   # All custom TrafficScript events.
   trafficscript_ALL,
   # Special value that matches all events of type
Virtual
   # Servers.
   vservers_ALL,
   # Virtual Servers - A protocol error has occurred
   vservers_connerror,
   # Virtual Servers - A socket connection failure
has occurred
   vservers_connfail,
   # Virtual Servers - A virtual server request log
file was
   # deleted (Stingray Appliances only)
   vservers_logfiledeleted,
   # Virtual Servers - Dropped connection, request
exceeded
   # max client buffer limit
   vservers maxclientbufferdrop,
```

```
# Virtual Servers - Pool uses a session
persistence class that
   # does not work with this virtual server's
protocol
   vservers poolpersistencemismatch,
   # Virtual Servers - Private key now OK (hardware
available)
   vservers privkeyok,
   # Virtual Servers - Error compressing HTTP
response
   vservers respcompfail,
   # Virtual Servers - Response headers from
webserver too large
   vservers responsetoolarge,
   # Virtual Servers - No suitable ports available
for streaming
   # data connection
   vservers rtspstreamnoports,
   # Virtual Servers - No suitable ports available
for streaming
   # data connection
   vservers_sipstreamnoports,
   # Virtual Servers - Request(s) received while SSL
   # configuration invalid, connection closed
   vservers_ssldrop,
   # Virtual Servers - One or more SSL connections
from clients
   # failed recently
```

```
vservers sslfail,
   # Virtual Servers - Certificate Authority
certificate expired
  vservers_vscacertexpired,
   # Virtual Servers - Certificate Authority
certificate will
   # expire within seven days
  vservers vscacerttoexpire,
   # Virtual Servers - CRL for a Certificate
Authority is out of
   # date
  vservers vscrloutofdate,
   # Virtual Servers - Failed to write log file for
virtual
   # server
  vservers vslogwritefail,
   # Virtual Servers - Public SSL certificate expired
  vservers_vssslcertexpired,
   # Virtual Servers - Public SSL certificate will
expire within
   # seven days
  vservers vssslcerttoexpire,
   # Virtual Servers - Virtual server started
  vservers vsstart,
   # Virtual Servers - Virtual server stopped
   vservers_vsstop,
```

```
# Special value that matches all events of type
Traffic

# Managers.

zxtms_ALL,

# Traffic Managers - Configuration update refused:
traffic

# manager version mismatch

zxtms_versionmismatch
}
```

Alerting.Action

URI: http://soap.zeus.com/zxtm/1.0/Alerting/Action/

Alerting. Action is an interface that allows you to add actions that are run by event types.

Methods

addAction(names, types) throws InvalidInput, ObjectAlreadyExists, InvalidObjectName, DeploymentError

Add a action that can be run by an event.

```
void addAction(
    String[] names
    Alerting.Action.Type[] types
)
```

addScriptArguments(names, arguments) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Adds a set of arguments to the specified actions. The actions specified must be of type 'program'.

```
void addScriptArguments(
    String[] names
    Alerting.Action.Argument[][] arguments
)
```

copyAction(names, new_names) throws ObjectDoesNotExist, ObjectAlreadyExists, InvalidObjectName, DeploymentError

Copy each of the named actions.

```
void copyAction(
   String[] names
   String[] new_names
)
```

deleteAction(names) throws ObjectDoesNotExist, ObjectInUse, DeploymentError

Deletes each of the named actions.

```
void deleteAction(
    String[] names
)
```

deleteActionProgram(names) throws ObjectDoesNotExist, DeploymentError, ObjectInUse

Delete the named action programs.

```
void deleteActionProgram(
    String[] names
)
```

downloadActionProgram(name) throws ObjectDoesNotExist

Download the named action program.

```
Binary Data downloadActionProgram(
    String name
)
```

getActionNames()

Get the names of all available actions.

```
String[] getActionNames()
```

getActionNamesOfType(type)

Get the names of all actions of the specified type.

```
String[] getActionNamesOfType(
    Alerting.Action.Type type
)
```

getActionProgramNames()

Get the names of all the uploaded action programs. These are the programs that can be executed by custom program actions.

```
String[] getActionProgramNames()
```

getActionType(names) throws InvalidOperation, ObjectDoesNotExist

Returns the type of each of the named actions.

```
Alerting.Action.Type[] getActionType(
    String[] names
)
```

getEmailRecipients(names) throws InvalidOperation, ObjectDoesNotExist

Get the address the alert emails are sent from.

```
String[] getEmailRecipients(
    String[] names
)
```

getEmailRecipientsByLocation(location, names) throws InvalidOperation, ObjectDoesNotExist

Get the address the alert emails are sent from. This is a location specific function, any action will operate on the specified location.

```
String[] getEmailRecipientsByLocation(
    String location
    String[] names
)
```

getEmailSMTPServer(names) throws InvalidOperation, ObjectDoesNotExist

Get the SMTP server used to send alert emails for the specified actions.

```
String[] getEmailSMTPServer(
    String[] names
)
```

getEmailSMTPServerByLocation(location, names) throws InvalidOperation, ObjectDoesNotExist

Get the SMTP server used to send alert emails for the specified actions. This is a location specific function, any action will operate on the specified location.

```
String[] getEmailSMTPServerByLocation(
    String location
    String[] names
)
```

getEmailSender(names) throws InvalidOperation, ObjectDoesNotExist

Get the specified email addresses to the recipient list for the specified actions.

```
String[] getEmailSender(
    String[] names
)
```

getEmailSenderByLocation(location, names) throws InvalidOperation, ObjectDoesNotExist

Get the specified email addresses to the recipient list for the specified actions. This is a location specific function, any action will operate on the specified location.

```
String[] getEmailSenderByLocation(
    String location
    String[] names
)
```

getLogFilePath(names) throws InvalidOperation, ObjectDoesNotExist

Get the file this action logs to.

```
String[] getLogFilePath(
    String[] names
```

)

getLogFilePathByLocation(location, names) throws InvalidOperation, ObjectDoesNotExist

Get the file this action logs to. This is a location specific function, any action will operate on the specified location.

```
String[] getLogFilePathByLocation(
    String location
    String[] names
)
```

getSNMPHashAlg(names) throws InvalidOperation, ObjectDoesNotExist

Get the SNMP hash algorithm for sending the Notify over SNMPv3. Valid values are "md5" and "sha1". The actions specified must be of type 'trap'.

```
Alerting.Action.SNMPHashAlg[] getSNMPHashAlg(
    String[] names
)
```

getSNMPHashAlgByLocation(location, names) throws InvalidOperation, ObjectDoesNotExist

Get the SNMP hash algorithm for sending the Notify over SNMPv3. Valid values are "md5" and "sha1". The actions specified must be of type 'trap'. This is a location specific function, any action will operate on the specified location.

```
Alerting.Action.SNMPHashAlg[]
getSNMPHashAlgByLocation(
    String location
    String[] names
)
```

getSNMPUsername(names) throws InvalidOperation, ObjectDoesNotExist

Get the SNMP username for sending the Notify over SNMPv3. The actions specified must be of type 'trap'.

```
String[] getSNMPUsername(
    String[] names
)
```

getSNMPUsernameByLocation(location, names) throws InvalidOperation, ObjectDoesNotExist

Get the SNMP username for sending the Notify over SNMPv3. The actions specified must be of type 'trap'. This is a location specific function, any action will operate on the specified location.

```
String[] getSNMPUsernameByLocation(
    String location
    String[] names
)
```

getSNMPVersion(names) throws InvalidOperation, ObjectDoesNotExist

Get the SNMP version used to send the trap/notify. The actions specified must be of type 'trap'.

```
Alerting.Action.SNMPVersion[] getSNMPVersion(
    String[] names
)
```

getSNMPVersionByLocation(location, names) throws InvalidOperation, ObjectDoesNotExist

Get the SNMP version used to send the trap/notify. The actions specified must be of type 'trap'. This is a location specific function, any action will operate on the specified location.

```
Alerting.Action.SNMPVersion[]
getSNMPVersionByLocation(
    String location
    String[] names
)
```

getSOAPAdditional(names) throws InvalidOperation, ObjectDoesNotExist

Get the additional information to send with the SOAP alert call.

```
String[] getSOAPAdditional(
    String[] names
)
```

getSOAPAdditionalByLocation(location, names) throws InvalidOperation, ObjectDoesNotExist

Get the additional information to send with the SOAP alert call. This is a location specific function, any action will operate on the specified location.

```
String[] getSOAPAdditionalByLocation(
    String location
    String[] names
)
```

getSOAPAuthentication(names) throws InvalidOperation, ObjectDoesNotExist

Gets the username used to log in with HTTP basic authentication. The actions specified must be of type 'soap'. Note that the password field is always returned as an empty string.

```
Alerting.Action.Login[] getSOAPAuthentication(
    String[] names
)
```

getSOAPAuthenticationByLocation(location, names) throws InvalidOperation, ObjectDoesNotExist

Gets the username used to log in with HTTP basic authentication. The actions specified must be of type 'soap'. Note that the password field is always returned as an empty string. This is a location specific function, any action will operate on the specified location.

```
Alerting.Action.Login[]
getSOAPAuthenticationByLocation(
    String location
    String[] names
)
```

getSOAPProxy(names) throws InvalidOperation, ObjectDoesNotExist

Get the server the SOAP event call will be made to for each of the specified SOAP events.

```
String[] getSOAPProxy(
    String[] names
)
```

getSOAPProxyByLocation(location, names) throws InvalidOperation, ObjectDoesNotExist

Get the server the SOAP event call will be made to for each of the specified SOAP events. This is a location specific function, any action will operate on the specified location.

```
String[] getSOAPProxyByLocation(
   String location
   String[] names
)
```

getScriptArguments(names) throws InvalidOperation, ObjectDoesNotExist

Gets all arguments for the specified script actions. The actions specified must be of type 'program'.

```
Alerting.Action.Argument[][] getScriptArguments(
    String[] names
)
```

getScriptProgram(names) throws InvalidOperation, ObjectDoesNotExist

Get the program to run including its command line arguments. The actions specified must be of type 'program'.

```
String[] getScriptProgram(
    String[] names
)
```

getSyslogHost(names) throws InvalidOperation, ObjectDoesNotExist

Get the host to send syslog messages to (if empty, messages will be sent to localhost). The actions specified must be of type 'syslog'.

```
String[] getSyslogHost(
    String[] names
)
```

getSyslogHostByLocation(location, names) throws InvalidOperation, ObjectDoesNotExist

Get the host to send syslog messages to (if empty, messages will be sent to localhost). The actions specified must be of type 'syslog'. This is a location specific function, any action will operate on the specified location.

```
String[] getSyslogHostByLocation(
```

```
String location
String[] names
)
```

getTimeout(names) throws InvalidOperation, ObjectDoesNotExist

Get how long an action has to run, in seconds (set to 0 disable timing out).

```
Unsigned Integer[] getTimeout(
    String[] names
)
```

getTimeoutByLocation(location, names) throws InvalidOperation, ObjectDoesNotExist

Get how long an action has to run, in seconds (set to 0 disable timing out). This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getTimeoutByLocation(
    String location
    String[] names
)
```

getTrapCommunity(names) throws InvalidOperation, ObjectDoesNotExist

Get the SNMP community string for the SNMP trap. The actions specified must be of type 'trap'.

```
String[] getTrapCommunity(
    String[] names
)
```

getTrapCommunityByLocation(location, names) throws InvalidOperation, ObjectDoesNotExist

Get the SNMP community string for the SNMP trap. The actions specified must be of type 'trap'. This is a location specific function, any action will operate on the specified location.

```
String[] getTrapCommunityByLocation(
    String location
    String[] names
)
```

getTrapHost(names) throws InvalidOperation, ObjectDoesNotExist

Get the hostname or IPv4 address and optional port number that should receive the SNMP trap. The actions specified must be of type 'trap'.

```
String[] getTrapHost(
    String[] names
)
```

getTrapHostByLocation(location, names) throws InvalidOperation, ObjectDoesNotExist

Get the hostname or IPv4 address and optional port number that should receive the SNMP trap. The actions specified must be of type 'trap'. This is a location specific function, any action will operate on the specified location.

```
String[] getTrapHostByLocation(
    String location
    String[] names
)
```

getVerbose(names) throws InvalidOperation, ObjectDoesNotExist

Get if verbose logging is enabled for this action.

```
Boolean[] getVerbose(
    String[] names
)
```

getVerboseByLocation(location, names) throws InvalidOperation, ObjectDoesNotExist

Get if verbose logging is enabled for this action. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getVerboseByLocation(
    String location
    String[] names
)
```

removeSOAPAuthentication(names) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Disables using HTTP basic authentication with the SOAP Call. The actions specified must be of type 'soap'.

```
void removeSOAPAuthentication(
    String[] names
)
```

removeSOAPAuthenticationByLocation(location, names) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Disables using HTTP basic authentication with the SOAP Call. The actions specified must be of type 'soap'. This is a location specific function, any action will operate on the specified location.

```
void removeSOAPAuthenticationByLocation(
   String location
   String[] names
)
```

removeScriptArguments(names, arguments) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Removes a set of arguments from the specified script actions. The actions specified must be of type 'program'.

```
void removeScriptArguments(
    String[] names
    String[][] arguments
)
```

renameAction(names, new_names) throws ObjectDoesNotExist, ObjectAlreadyExists, InvalidObjectName, DeploymentError, InvalidOperation

Rename each of the named actions.

```
void renameAction(
    String[] names
    String[] new_names
)
```

setEmailRecipients(names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the address the alert emails are sent from.

```
void setEmailRecipients(
   String[] names
   String[] values
)
```

setEmailRecipientsByLocation(location, names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the address the alert emails are sent from. This is a location specific function, any action will operate on the specified location.

```
void setEmailRecipientsByLocation(
   String location
   String[] names
   String[] values
)
```

setEmailSMTPServer(names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the SMTP server used to send alert emails for the specified actions.

```
void setEmailSMTPServer(
   String[] names
   String[] values
)
```

setEmailSMTPServerByLocation(location, names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the SMTP server used to send alert emails for the specified actions. This is a location specific function, any action will operate on the specified location.

```
void setEmailSMTPServerByLocation(
   String location
   String[] names
   String[] values
```

Alerting.Action Function Reference

)

setEmailSender(names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the specified email addresses to the recipient list for the specified actions.

```
void setEmailSender(
    String[] names
    String[] values
)
```

setEmailSenderByLocation(location, names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the specified email addresses to the recipient list for the specified actions. This is a location specific function, any action will operate on the specified location.

```
void setEmailSenderByLocation(
    String location
    String[] names
    String[] values
)
```

setLogFilePath(names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the file this action logs to.

```
void setLogFilePath(
    String[] names
    String[] values
)
```

setLogFilePathByLocation(location, names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the file this action logs to. This is a location specific function, any action will operate on the specified location.

```
void setLogFilePathByLocation(
    String location
```

Function Reference Alerting.Action

```
String[] names
String[] values
)
```

setSNMPAuthPassword(names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the SNMP password for sending the Notify over SNMPv3. The actions specified must be of type 'trap'.

```
void setSNMPAuthPassword(
    String[] names
    String[] values
)
```

setSNMPAuthPasswordByLocation(location, names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the SNMP password for sending the Notify over SNMPv3. The actions specified must be of type 'trap'. This is a location specific function, any action will operate on the specified location.

```
void setSNMPAuthPasswordByLocation(
   String location
   String[] names
   String[] values
)
```

setSNMPHashAlg(names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the SNMP hash algorithm for sending the Notify over SNMPv3. Valid values are "md5" and "sha1". The actions specified must be of type 'trap'.

```
void setSNMPHashAlg(
    String[] names
    Alerting.Action.SNMPHashAlg[] values
)
```

Alerting.Action Function Reference

setSNMPHashAlgByLocation(location, names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the SNMP hash algorithm for sending the Notify over SNMPv3. Valid values are "md5" and "sha1". The actions specified must be of type 'trap'. This is a location specific function, any action will operate on the specified location.

```
void setSNMPHashAlgByLocation(
   String location
   String[] names
   Alerting.Action.SNMPHashAlg[] values
)
```

setSNMPPrivPassword(names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the SNMP encryption key to encrpt SNMPv3 Notify messages. The actions specified must be of type 'trap'.

```
void setSNMPPrivPassword(
    String[] names
    String[] values
)
```

setSNMPPrivPasswordByLocation(location, names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the SNMP encryption key to encrpt SNMPv3 Notify messages. The actions specified must be of type 'trap'. This is a location specific function, any action will operate on the specified location.

```
void setSNMPPrivPasswordByLocation(
   String location
   String[] names
   String[] values
)
```

setSNMPUsername(names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the SNMP username for sending the Notify over SNMPv3. The actions specified must be of type 'trap'.

```
void setSNMPUsername(
```

Function Reference Alerting.Action

```
String[] names
String[] values
)
```

setSNMPUsernameByLocation(location, names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the SNMP username for sending the Notify over SNMPv3. The actions specified must be of type 'trap'. This is a location specific function, any action will operate on the specified location.

```
void setSNMPUsernameByLocation(
   String location
   String[] names
   String[] values
)
```

setSNMPVersion(names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the SNMP version used to send the trap/notify. The actions specified must be of type 'trap'.

```
void setSNMPVersion(
    String[] names
    Alerting.Action.SNMPVersion[] values
)
```

setSNMPVersionByLocation(location, names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the SNMP version used to send the trap/notify. The actions specified must be of type 'trap'. This is a location specific function, any action will operate on the specified location.

```
void setSNMPVersionByLocation(
   String location
   String[] names
   Alerting.Action.SNMPVersion[] values
)
```

Alerting.Action Function Reference

setSOAPAdditional(names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the additional information to send with the SOAP alert call.

```
void setSOAPAdditional(
   String[] names
   String[] values
)
```

setSOAPAdditionalByLocation(location, names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the additional information to send with the SOAP alert call. This is a location specific function, any action will operate on the specified location.

```
void setSOAPAdditionalByLocation(
   String location
   String[] names
   String[] values
)
```

setSOAPAuthentication(names, credentials) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Sets the username and password to use to log in with HTTP basic authentication. The actions specified must be of type 'soap'.

```
void setSOAPAuthentication(
   String[] names
   Alerting.Action.Login[] credentials
)
```

setSOAPAuthenticationByLocation(location, names, credentials) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Sets the username and password to use to log in with HTTP basic authentication. The actions specified must be of type 'soap'. This is a location specific function, any action will operate on the specified location.

```
void setSOAPAuthenticationByLocation(
   String location
   String[] names
```

Function Reference Alerting.Action

```
Alerting.Action.Login[] credentials
)
```

setSOAPProxy(names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the server the SOAP event call will be made to for each of the specified SOAP events.

```
void setSOAPProxy(
    String[] names
    String[] values
)
```

setSOAPProxyByLocation(location, names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the server the SOAP event call will be made to for each of the specified SOAP events. This is a location specific function, any action will operate on the specified location.

```
void setSOAPProxyByLocation(
   String location
   String[] names
   String[] values
)
```

setScriptProgram(names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the program to run including its command line arguments. The actions specified must be of type 'program'.

```
void setScriptProgram(
    String[] names
    String[] values
)
```

setSyslogHost(names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the host to send syslog messages to (if empty, messages will be sent to localhost). The actions specified must be of type 'syslog'.

```
void setSyslogHost(
```

Alerting.Action Function Reference

```
String[] names
String[] values
)
```

setSyslogHostByLocation(location, names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the host to send syslog messages to (if empty, messages will be sent to localhost). The actions specified must be of type 'syslog'. This is a location specific function, any action will operate on the specified location.

```
void setSyslogHostByLocation(
   String location
   String[] names
   String[] values
)
```

setTimeout(names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set how long an action has to run, in seconds (set to 0 disable timing out).

```
void setTimeout(
    String[] names
    Unsigned Integer[] values
)
```

setTimeoutByLocation(location, names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set how long an action has to run, in seconds (set to 0 disable timing out). This is a location specific function, any action will operate on the specified location.

```
void setTimeoutByLocation(
    String location
    String[] names
    Unsigned Integer[] values
)
```

Function Reference Alerting.Action

setTrapCommunity(names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the SNMP community string for the SNMP trap. The actions specified must be of type 'trap'.

```
void setTrapCommunity(
    String[] names
    String[] values
)
```

setTrapCommunityByLocation(location, names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the SNMP community string for the SNMP trap. The actions specified must be of type 'trap'. This is a location specific function, any action will operate on the specified location.

```
void setTrapCommunityByLocation(
   String location
   String[] names
   String[] values
)
```

setTrapHost(names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the hostname or IPv4 address and optional port number that should receive the SNMP trap. The actions specified must be of type 'trap'.

```
void setTrapHost(
    String[] names
    String[] values
)
```

setTrapHostByLocation(location, names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set the hostname or IPv4 address and optional port number that should receive the SNMP trap. The actions specified must be of type 'trap'. This is a location specific function, any action will operate on the specified location.

```
void setTrapHostByLocation(
    String location
    String[] names
```

Alerting.Action Function Reference

```
String[] values
)
```

setVerbose(names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set if verbose logging is enabled for this action.

```
void setVerbose(
   String[] names
   Boolean[] values
)
```

setVerboseByLocation(location, names, values) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Set if verbose logging is enabled for this action. This is a location specific function, any action will operate on the specified location.

```
void setVerboseByLocation(
   String location
   String[] names
   Boolean[] values
)
```

testAction(names) throws ObjectDoesNotExist

Sends a test event to the named actions to confirm that they are working as expected.

```
void testAction(
    String[] names
)
```

updateScriptArguments(names, argument_names, new_arguments) throws InvalidOperation, ObjectDoesNotExist, InvalidInput, DeploymentError

Allows arguments for the the specified script actions to be changed. The actions specified must be of type 'program'.

```
void updateScriptArguments(
    String[] names
    String[][] argument_names
```

Function Reference Alerting.Action

```
Alerting.Action.Argument[][] new_arguments
```

uploadActionProgram(name, content) throws InvalidObjectName, DeploymentError

Uploads an action program, overwriting the file if it already exists.

```
void uploadActionProgram(
    String name
    Binary Data content
)
```

Structures

Alerting.Action.Argument

An argument that is added to the command line when the script is run

```
struct Alerting.Action.Argument {
    # The name of the argument.
    String name;

# The value of the argument.
    String value;

# A description of the argument.
    String description;
}
```

Alerting.Action.Login

An argument that is added to the command line when the script is run

```
struct Alerting.Action.Login {
    # The username for basic SOAP authentication
    String username;

# The username for basic SOAP authentication
```

Alerting.Action Function Reference

```
String password;
}
```

Enumerations

Alerting.Action.SNMPHashAlg

```
enum Alerting.Action.SNMPHashAlg {
    # MD5
    md5,

# SHA-1
    sha1
}
```

Alerting.Action.SNMPVersion

```
enum Alerting.Action.SNMPVersion {
    # SNMPv1
    snmpv1,

# SNMPv2c
    snmpv2c,

# SNMPv3
    snmpv3
}
```

Alerting.Action.Type

```
enum Alerting.Action.Type {
    # Sends e-mails to a set of e-mail addresses.
    email,

    # Reports event information to a remote server using the SOAP
```

```
# protocol.
soap,

# Sends an SNMP message to a remote server.
trap,

# Writes a log line in the syslog.
syslog,

# Writes a log line in a named file.
log,

# Executes an external program.
program
```

AlertCallback

URI: http://soap.zeus.com/zxtm/1.0/AlertCallback/

}

AlertCallback is a callback interface that can be implemented on a separate server to receive events via SOAP from the traffic manager. This interface is not implemented by traffic manager itself.

Methods

eventOccurred(zxtm, time, severity, primary_tag, tags, objects, description, additional, event_type)

This function is used by the traffic manager to report an event using a SOAP call. You can easily identify the event being reported using the primary_tag field, which is the event's unique identifier. The tags array is reserved for future use, and will be empty.

```
void eventOccurred(
   String zxtm
   Time time
   AlertCallback.Severity severity
   AlertCallback.Tag primary_tag
   AlertCallback.Tag[] tags
```

```
AlertCallback.Object[] objects
String description
String additional
String event_type
)
```

Structures

AlertCallback.Object

Information on an object that triggered this event.

```
# The type of the object
AlertCallback.ObjectType type;
# The name of the object.
String name;
}
```

Enumerations

AlertCallback.ObjectType

```
enum AlertCallback.ObjectType {
    # An unexpected type
    Unknown,

# Actions
actions,

# Authenticators
auth,

# Bandwidth Classes
bandwidth,
```

```
# Cloud Credentials
cloudcredentials,
# Configuration Files
config,
# DNS Lookup
dns,
# Event Types
events,
# TrafficScript Resources
extra,
# Fault Tolerance
faulttolerance,
# Traffic IPs
flipper,
# General
general,
# HTTP Events
http,
# Java Resources
jars,
# Java
java,
```

```
# License Keys
licensekeys,
# Locations
locations,
# Monitors
monitors,
# Nodes
nodes,
# Session Persistence Classes
persistence,
# Processes
pids,
# Pools
pools,
# Service Protection Classes
protection,
# Rate Classes
rate,
# RTSP Events
rtsp,
# Rules
rules,
```

```
# GLB Services
services,
servlet,
# Java Servlets
servlets,
# SIP Events
sip,
# SLM Classes
slm,
# SMTP Events
smtp,
# SSL Hardware
sslhw,
# SIP/RTSP
streaming,
# Traffic IPs
tips,
# Custom Events
trafficscript,
# Virtual Servers
vservers,
```

```
# Traffic Managers
zxtms
}
```

AlertCallback.Severity

```
enum AlertCallback.Severity {
    # Denial of Service Event
    DOS,

# Fatal Error Event
    FATAL,

# Information Event
    INFO,

# Serious Error Event
    SERIOUS,

# SSL Error Event
    SSL,

# Warning Event
    WARN
}
```

AlertCallback.Tag

```
enum AlertCallback.Tag {
    # This tag is used to with emitting a custom event
generated
    # with the TrafficScript function 'event.emit'.
Look at the
    # object that came with the callback to see the
name of the
    # custom event
```

```
CustomEvent,
   # An unknown tag
   Unknown,
   # Cloud Credentials - A cloud API process querying
changes to
   # cloud instances is hanging
   cloudcredentials apistatusprocesshanging,
   # Cloud Credentials - An API call made by the
autoscaler
   # process has returned a response that could not
be parsed
   cloudcredentials autoscaleresponseparseerror,
   # Cloud Credentials - An API call made by the
autoscaler
   # process has reported an error
   cloudcredentials autoscalestatusupdateerror,
   # Cloud Credentials - A cloud API process has
timed out
   \verb|cloudcredentials_autoscaling| process time dout,\\
   # Cloud Credentials - A Cloud Credentials object
has been
   # deleted but it was still in use
   cloudcredentials_usedcredsdeleted,
   # Configuration Files - Configuration file added
   config confadd,
   # Configuration Files - Configuration file deleted
   config_confdel,
```

```
# Configuration Files - Configuration file
modified
   config confmod,
   # Configuration Files - Configuration file now OK
   config confok,
   # Fault Tolerance - Activating this machine
automatically
   # because it is the only working machine in its
Traffic IP
   # Groups
   faulttolerance activatealldead,
   # Fault Tolerance - Machine has recovered and been
activated
   # automatically because it would cause no service
disruption
   faulttolerance activatedautomatically,
   # Fault Tolerance - All machines are working
   faulttolerance allmachinesok,
   # Fault Tolerance - Removing EC2 Elastic IP
Address from all
   # machines; it is no longer a part of any Traffic
IP Groups
   faulttolerance_dropec2ipwarn,
   # Fault Tolerance - Dropping Traffic IP Address
due to a
   # configuration change or traffic manager recovery
   faulttolerance dropipinfo,
   # Fault Tolerance - Dropping Traffic IP Address
due to an
   # error
```

faulttolerance_dropipwarn,

```
# Fault Tolerance - Moving EC2 Elastic IP Address;
local
# machine is working
```

faulttolerance ec2flipperraiselocalworking,

- $\mbox{\#}$ Fault Tolerance Moving EC2 Elastic IP Address; other
 - # machines have failed
 faulttolerance ec2flipperraiseothersdead,
- # Fault Tolerance Problem occurred when managing an Elastic
 - # IP address
 faulttolerance ec2iperr,
- # Fault Tolerance Cannot raise Elastic IP on
 this machine
 - # until EC2 provides it with a public IP address
 faulttolerance_ec2nopublicip,
 - # Fault Tolerance Back-end nodes are now working
 faulttolerance flipperbackendsworking,
- # Fault Tolerance Re-raising Traffic IP Address;
 Operating
 - # system did not fully raise the address
 faulttolerance_flipperdadreraise,
- # Fault Tolerance Frontend machines are now
 working

faulttolerance_flipperfrontendsworking,

Fault Tolerance - Failed to raise Traffic IP
Address; the

```
# address exists elsewhere on your network and
cannot be
   # raised
   faulttolerance flipperipexists,
   # Fault Tolerance - Raising Traffic IP Address;
local machine
   # is working
   faulttolerance flipperraiselocalworking,
   # Fault Tolerance - Raising Traffic IP Address;
Operating
   # System had dropped this IP address
   faulttolerance flipperraiseosdrop,
   # Fault Tolerance - Raising Traffic IP Address;
other machines
   # have failed
   faulttolerance flipperraiseothersdead,
   # Fault Tolerance - This Traffic Manager has re-
raised traffic
   # IP addresses as the remote machine which was
hosting them
   # has dropped them
   faulttolerance flipperraiseremotedropped,
   # Fault Tolerance - Machine is ready to raise
Traffic IP
   # addresses
   faulttolerance flipperrecovered,
   # Fault Tolerance - Remote machine has failed
   faulttolerance_machinefail,
   # Fault Tolerance - Remote machine is now working
```

faulttolerance machineok,

```
# Fault Tolerance - Remote machine has recovered
and can raise
   # Traffic IP addresses
   faulttolerance machinerecovered,
   # Fault Tolerance - Remote machine has timed out
and been
   # marked as failed
   faulttolerance machinetimeout,
   # Fault Tolerance - The amount of load handled by
the local
   # machine destined for this Traffic IP has changed
   faulttolerance multihostload,
   # Fault Tolerance - Failed to ping back-end nodes
   faulttolerance pingbackendfail,
   # Fault Tolerance - Failed to ping any of the
machines used to
   # check the front-end connectivity
   faulttolerance pingfrontendfail,
   # Fault Tolerance - Failed to ping default gateway
   faulttolerance_pinggwfail,
   # Fault Tolerance - Received an invalid response
from another
   # cluster member
   faulttolerance_statebaddata,
   # Fault Tolerance - Failed to connect to another
```

cluster

member for state sharing

faulttolerance stateconnfail, # Fault Tolerance - Successfully connected to another cluster # member for state sharing faulttolerance stateok, # Fault Tolerance - Reading state data from another cluster # member failed faulttolerance statereadfail, # Fault Tolerance - Timeout while sending state data to # another cluster member faulttolerance statetimeout, # Fault Tolerance - Received unexpected state data from # another cluster member faulttolerance_stateunexpected, # Fault Tolerance - Writing state data to another cluster # member failed faulttolerance_statewritefail, # Fault Tolerance - An error occurred when using the zcluster # Multi-Hosted IP kernel module faulttolerance_zclustermoderr, # General - An error occurred during user

authentication

general autherror,

```
# General - Autoscaling not permitted by licence
key
   general autoscalinglicenseerror,
   # General - Replication of configuration has
failed
   general confrepfailed,
   # General - Replication of configuration has timed
out
   general confreptimeout,
   # General - Running out of free file descriptors
   general fewfreefds,
   # General - Failed to load geolocation data
   general_geodataloadfail,
   # General - Appliance hardware notification
   general_hardware,
   # General - A location has been disabled because
you have
   # exceeded the licence limit
   general_licensetoomanylocations,
   # General - Log disk partition full
   general_logdiskfull,
   # General - Log disk partition usage has exceeded
threshold
   general_logdiskoverload,
   # General - Software must be restarted to apply
configuration
   # changes
```

```
general restartrequired,
   # General - Software is running
   general_running,
   # General - Time has been moved back
   general timemovedback,
   # General - The number of simultaneously active
connections
   # has reached a level that the software cannot
process in due
   # time; there is a high risk of connections timing
out
   general zxtmhighload,
   # General - Stingray Traffic Manager software
problem
   general zxtmswerror,
   # Java - Java runner died
   java javadied,
   # Java - Cannot start Java runner, program not
found
   java_javanotfound,
   # Java - Java runner started
   java javastarted,
   # Java - Java runner failed to start
   java_javastartfail,
   # Java - Java support has stopped
   java javastop,
```

Java - Java runner failed to terminate

```
java javaterminatefail,
   # Java - Servlet encountered an error
   java servleterror,
   # License Keys - Realtime Analytics support has
been disabled
   licensekeys analyticslicensedisabled,
   # License Keys - Realtime Analytics support has
been enabled
   licensekeys analyticslicenseenabled,
   # License Keys - Autoscaling support has been
disabled
   licensekeys autoscalinglicensedisabled,
   # License Keys - Autoscaling support has been
enabled
   licensekeys autoscalinglicenseenabled,
   # License Keys - License key bandwidth limit has
been hit
   licensekeys_bwlimited,
   # License Keys - Configured cache size exceeds
license limit,
   # only using amount allowed by license
   licensekeys cachesizereduced,
   # License Keys - License key has expired
   licensekeys expired,
   # License Keys - License key expires within 7 days
```

licensekeys expiresoon, # License Keys - License allows less memory for caching licensekeys lessmemallowed, # License Keys - License key authorized licensekeys license-authorized, # License Keys - License key authorized by authorization code licensekeys license-authorized-ts, # License Keys - Unable to authorize license key licensekeys_license-graceperiodexpired, # License Keys - Unable to authorize license key licensekeys license-graceperiodexpired-ts, # License Keys - License server rejected license key; key # remains authorized licensekeys license-rejected-authorized, # License Keys - License key rejected from authorization code; # key remains authorized licensekeys license-rejected-authorized-ts, # License Keys - License server rejected license key; key is # not authorized licensekeys license-rejected-unauthorized, # License Keys - License key rejected from authorization code

```
licensekeys license-rejected-unauthorized-ts,
   # License Keys - Unable to contact license server;
license key
   # remains authorized
   licensekeys license-timedout-authorized,
   # License Keys - Unable to run authorization code
to
   # completion; key remains valid
   licensekeys license-timedout-authorized-ts,
   # License Keys - Unable to contact license server;
license key
   # is not authorized
   licensekeys license-timedout-unauthorized,
   # License Keys - Unable to run authorization code
to
   # completion
   licensekeys license-timedout-unauthorized-ts,
   # License Keys - License key is not authorized
   licensekeys license-unauthorized,
   # License Keys - Cluster size exceeds license key
limit
   licensekeys licenseclustertoobig,
   # License Keys - License key is corrupt
   licensekeys licensecorrupt,
   # License Keys - License allows more memory for
caching
   licensekeys morememallowed,
```

```
# License Keys - License key SSL transactions-per-
second limit
   # has been hit
   licensekeys ssltpslimited,
   # License Keys - License key transactions-per-
second limit has
   # been hit.
   licensekeys tpslimited,
   # License Keys - Started without a license
   licensekeys unlicensed,
   # License Keys - Using a development license
   licensekeys_usingdevlicense,
   # License Keys - Using license key
   licensekeys usinglicense,
   # Locations - Location has failed for GLB Service
   locations_locationfail,
   # Locations - A monitor has detected a failure in
this
   # location
   locations locationmonitorfail,
   # Locations - A monitor has indicated this
location is now
   # working
   locations locationmonitorok,
   # Locations - Location is now working for GLB
Service
   locations locationok,
```

```
# Locations - An external SOAP agent has detected
a failure in
   # this location
   locations locationsoapfail,
   # Locations - An external SOAP agent indicates
this location
   # is now working
   locations locationsoapok,
   # Locations - Location no longer contains any
machines
  locations locempty,
   # Locations - Machine now in location
   locations_locmovemachine,
   # Monitors - Monitor has detected a failure
  monitors_monitorfail,
   # Monitors - Monitor is working
  monitors monitorok,
   # Pools - API change process still running after
refractory
   # period is over
  pools_apichangeprocesshanging,
   # Pools - The creation of a new node requested by
an
   # autoscaled pool is now complete
   pools autonodecreationcomplete,
   # Pools - Creation of new node instigated
```

```
pools autonodecreationstarted,
   # Pools - A cloud API call to destroy a node has
been started
  pools autonodedestroyed,
   # Pools - The destruction of a node in an
autoscaled pool is
   # now complete
   pools autonodedestructioncomplete,
   # Pools - A node in an autoscaled pool has
disappeared from
   # the cloud
  pools autonodedisappeared,
   # Pools - IP address of newly created instance
already existed
   # in pool's node list
  pools autonodeexisted,
   # Pools - The status of a node in an autoscaled
pool has
   # changed
   pools autonodestatuschange,
   # Pools - Two pools are trying to use the same
instance
   pools_autoscalednodecontested,
   # Pools - An autoscaled pool is now refractory
   pools autoscaledpoolrefractory,
   # Pools - Over maximum size - shrinking
   pools autoscaledpooltoobig,
```

```
# Pools - Minimum size undercut - growing
  pools autoscaledpooltoosmall,
   # Pools - The 'imageid' was empty when attempting
to create a
   # node in an autoscaled pool
  pools autoscaleinvalidargforcreatenode,
   # Pools - 'unique id' was empty when attempting to
destroy a
   # node in an autoscaled pool
   pools autoscaleinvalidargfordeletenode,
   # Pools - A pool config file has been updated by
the
   # autoscaler process
  pools autoscalepoolconfupdate,
   # Pools - A node created by the autoscaler has the
wrong
   # imageid
   pools autoscalewrongimageid,
   # Pools - A node created by the autoscaler has a
non-matching
   # name
  pools autoscalewrongname,
   # Pools - A node created by the autoscaler has the
wrong
   # sizeid
   pools autoscalewrongsizeid,
   # Pools - An API process that should have created
or destroyed
   # a node has failed to produce the expected result
```

```
pools autoscalingchangeprocessfailure,
   # Pools - Autoscaling for a pool has been disabled
due to
   # errors communicating with the cloud API
   pools autoscalingdisabled,
   # Pools - Minimum size reached, cannot shrink
further
   pools autoscalinghitfloor,
   # Pools - Maximum size reached by autoscaled pool,
cannot grow
   # further
   pools autoscalinghitroof,
   # Pools - An autoscaled pool is waiting to grow
   pools_autoscalinghysteresiscantgrow,
   # Pools - An autoscaled pool is waiting to shrink
   pools autoscalinghysteresiscantshrink,
   # Pools - An autoscaled pool's state has changed
   pools_autoscalingpoolstatechange,
   # Pools - An autoscaled pool has failed completely
  pools autoscalingresuscitatepool,
   # Pools - HTTP response contained an invalid
Content-Length
   # header
   pools badcontentlen,
   # Pools - Attempt to scale down a pool that only
had pending
```

```
# nodes or none at all
   pools_cannotshrinkemptypool,
   # Pools - Node returned invalid EHLO response
   pools ehloinvalid,
   # Pools - Node has failed
   pools nodefail,
   # Pools - Failed to resolve node address
   pools noderesolvefailure,
   # Pools - Node resolves to multiple IP addresses
   pools noderesolvemultiple,
   # Pools - Node is working again
   pools nodeworking,
   # Pools - Node doesn't provide STARTTLS support
   pools_nostarttls,
   # Pools - Pool has no back-end nodes responding
   pools pooldied,
   # Pools - Pool configuration contains no valid
backend nodes
   pools_poolnonodes,
   # Pools - Pool now has working nodes
   pools poolok,
   # Pools - Node returned invalid STARTTLS response
   pools starttlsinvalid,
```

```
# Service Protection Classes - Summary of recent
service
   # protection events
   protection_triggersummary,
   # Rules - data.set() has run out of space
   rules datastorefull,
   # Rules - Rule selected an unresolvable host
  rules forwardproxybadhost,
   # Rules - Rule used event.emit() with an invalid
custom event
  rules_invalidemit,
   # Rules - Rule selected an unknown rate shaping
class
  rules norate,
   # Rules - Rule references an unknown pool via
pool.activenodes
  rules_poolactivenodesunknown,
   # Rules - Rule selected an unknown pool
   rules pooluseunknown,
   # Rules - Rule aborted during execution
   rules ruleabort,
   # Rules - Rule encountered invalid data while
uncompressing
   # response
   rules rulebodycomperror,
```

```
# Rules - Rule has buffered more data than
expected
  rules rulebufferlarge,
   # Rules - Rule logged an info message using
log.info
   rules rulelogmsginfo,
   # Rules - Rule logged an error message using
log.error
  rules rulelogmsgserious,
   # Rules - Rule logged a warning message using
log.warn
  rules rulelogmsgwarn,
   # Rules - Rule selected an unknown session
persistence class
   rules rulenopersistence,
   # Rules - Client sent invalid HTTP request body
   rules rulesinvalidrequestbody,
   # Rules - Attempt to use http.getResponse or
   # http.getResponseBody after
http.stream.startResponse
   rules_rulestreamerrorgetresponse,
   # Rules - Internal error while processing HTTP
stream
   rules rulestreamerrorinternal,
   # Rules - Rule did not supply enough data in HTTP
stream
   rules_rulestreamerrornotenough,
```

AlertCallback Function Reference

```
# Rules - Attempt to initialize HTTP stream before
previous
   # stream had finished
   rules rulestreamerrornotfinished,
   # Rules - Attempt to stream data or finish a
stream before
   # streaming had been initialized
   rules rulestreamerrornotstarted,
   # Rules - Data supplied to HTTP stream could not
be processed
   rules rulestreamerrorprocessfailure,
   # Rules - Rule supplied too much data in HTTP
stream
   rules rulestreamerrortoomuch,
   # Rules - Rule encountered an XML error
   rules rulexmlerr,
   # Rules - GLB service rule aborted during
execution
   rules_serviceruleabort,
   # Rules - GLB service rule specified a location
that has
   # either failed or been marked as draining in the
service
   # configuration
   rules servicerulelocdead,
   # Rules - GLB service rule specified a location
that is not
   # configured for the service
   rules servicerulelocnotconfigured,
```

Function Reference AlertCallback

```
# Rules - GLB service rule specified an unknown
location
  rules servicerulelocunknown,
   # GLB Services - A DNS Query returned IP addresses
that are
   # not configured for any location that is
currently alive
   services glbdeadlocmissingips,
   # GLB Services - Failed to alter DNS packet for
global load
   # balancing
  services glbfailalter,
   # GLB Services - Failed to write log file for GLB
service
  services glblogwritefail,
   # GLB Services - A DNS Query returned IP addresses
that are
   # not configured in any location
   services_glbmissingips,
   # GLB Services - A location has been set as master
for a GLB
   # service
   services glbnewmaster,
   # GLB Services - No valid location could be chosen
for Global
   # Load Balancing
   services glbnolocations,
   # GLB Services - GLB Service has no working
locations
```

AlertCallback Function Reference

```
services glbservicedied,
   # GLB Services - GLB Service has recovered
   services_glbserviceok,
   # SLM Classes - SLM shared memory limit exceeded
   slm slmclasslimitexceeded,
   # SLM Classes - SLM has fallen below serious
threshold
  slm slmfallenbelowserious,
   # SLM Classes - SLM has fallen below warning
threshold
  slm_slmfallenbelowwarn,
   # SLM Classes - Node information when SLM is non-
conforming
   # (no SNMP trap)
   slm_slmnodeinfo,
   # SLM Classes - SLM has risen above the serious
threshold
   slm slmrecoveredserious,
   # SLM Classes - SLM has recovered
   slm_slmrecoveredwarn,
   # SSL Hardware - SSL hardware support failed
   sslhw sslhwfail,
   # SSL Hardware - SSL hardware support restarted
   sslhw sslhwrestart,
   # SSL Hardware - SSL hardware support started
```

Function Reference AlertCallback

```
sslhw sslhwstart,
   # Test event generated from the Stingray
Administration
   # Server.
   testaction,
   # Virtual Servers - A protocol error has occurred
   vservers connerror,
   # Virtual Servers - A socket connection failure
has occurred
  vservers connfail,
   # Virtual Servers - A virtual server request log
file was
   # deleted (Stingray Appliances only)
   vservers logfiledeleted,
   # Virtual Servers - Dropped connection, request
exceeded
   # max client buffer limit
   vservers_maxclientbufferdrop,
   # Virtual Servers - Pool uses a session
persistence class that
   # does not work with this virtual server's
protocol
   vservers poolpersistencemismatch,
   # Virtual Servers - Private key now OK (hardware
available)
   vservers privkeyok,
   # Virtual Servers - Error compressing HTTP
response
```

AlertCallback Function Reference

vservers respcompfail, # Virtual Servers - Response headers from webserver too large vservers responsetoolarge, # Virtual Servers - No suitable ports available for streaming # data connection vservers rtspstreamnoports, # Virtual Servers - No suitable ports available for streaming # data connection vservers sipstreamnoports, # Virtual Servers - Request(s) received while SSL # configuration invalid, connection closed vservers ssldrop, # Virtual Servers - One or more SSL connections from clients # failed recently vservers sslfail, # Virtual Servers - Certificate Authority certificate expired vservers vscacertexpired, # Virtual Servers - Certificate Authority certificate will # expire within seven days vservers_vscacerttoexpire, # Virtual Servers - CRL for a Certificate Authority is out of

Function Reference System.AccessLogs

```
# date
   vservers_vscrloutofdate,
   # Virtual Servers - Failed to write log file for
virtual
   # server
   vservers_vslogwritefail,
   # Virtual Servers - Public SSL certificate expired
   vservers vssslcertexpired,
   # Virtual Servers - Public SSL certificate will
expire within
   # seven days
   vservers_vssslcerttoexpire,
   # Virtual Servers - Virtual server started
   vservers_vsstart,
   # Virtual Servers - Virtual server stopped
   vservers_vsstop,
   # Traffic Managers - Configuration update refused:
traffic
   # manager version mismatch
   zxtms versionmismatch
}
```

System.AccessLogs

URI: http://soap.zeus.com/zxtm/1.0/System/AccessLogs/

The AccessLogs interfaces provide operations on saved virtual server access logs for a Stingray Appliance. This interface is only available on a Stingray Appliance and is deprecated; use the System.RequestLogs interface instead.

System.AccessLogs Function Reference

Methods

deleteAllVSAccessLogs() throws InvalidOperation

Delete all the access logs for all virtual servers.

```
void deleteAllVSAccessLogs()
```

deleteVSAccessLog(logfiles) throws InvalidOperation, InvalidInput

Delete the specified access logs.

```
void deleteVSAccessLog(
    String[] logfiles
)
```

deleteVSAccessLogs(vservers) throws InvalidOperation

Delete the access logs for specific virtual servers.

```
void deleteVSAccessLogs(
    String[] vservers
)
```

getAllVSAccessLogs() throws InvalidOperation

Get the access logs for all virtual servers.

```
System.AccessLogs.VSAccessLog[] getAllVSAccessLogs()
```

getVSAccessLogs(vservers) throws InvalidOperation

Get the access logs for specific virtual servers.

```
System.AccessLogs.VSAccessLog[][] getVSAccessLogs(
    String[] vservers
)
```

Structures

System.AccessLogs.VSAccessLog

This structure contains the information for each virtual server access log.

```
struct System.AccessLogs.VSAccessLog {
```

Function Reference System.Cache

```
# The log filename.
String filename;

# The virtual server for this logfile.
String virtual_server;

# The date this logfile was created.
Time logdate;

# The size (in bytes) of this logfile.
Integer filesize;
```

System.Cache

URI: http://soap.zeus.com/zxtm/1.2/System/Cache/

The System. Cache interface provides information about the content cache for a machine. Using this interface, you can retrieve both individual cache entries and global cache data, delete all entries in the cache, delete entries matching wildcards or delete individual entries.

Methods

clearCacheContentItems(virtual_servers, protocols, hosts, items)

Delete individual items from the Web Cache. All input arguments are arrays of strings and only those items are deleted whose virtual server, protocol, host and path attribute match all the corresponding values for a given index into the arguments.

```
void clearCacheContentItems(
    String[] virtual_servers
    System.Cache.Protocol[] protocols
    String[] hosts
    String[] items
)
```

clearMatchingCacheContent(protocol, host_wildcard, path_wildcard)

Delete the Web Cache entries matching the input arguments.

System.Cache Function Reference

```
void clearMatchingCacheContent(
    System.Cache.Protocol protocol
    String host_wildcard
    String path_wildcard
)
```

clearWebCache()

Clear all entries from the Web Cache for this machine.

```
void clearWebCache()
```

getCacheContent(protocol, host_wildcard, path_wildcard, max_entries)

Get information about the Web Cache entries matching the input arguments.

```
System.Cache.CacheContentInfo getCacheContent(
    System.Cache.Protocol protocol
    String host_wildcard
    String path_wildcard
    Integer max_entries
)
```

getGlobalCacheInfo()

Get the size of the Web Cache, the number of Web Cache entries and the percentage memory used by the Web Cache for this machine.

```
System.Cache.GlobalInfo getGlobalCacheInfo()
```

Structures

System.Cache.CacheContent

This structure contains the basic information about an individual cache entry for a machine.

```
struct System.Cache.CacheContent {
    # The virtual server hosting the entry.
    String virtual_server;

# The protocol of the entry: http or https.
```

Function Reference System.Cache

```
System.Cache.Protocol protocol;
   # The host name of the entry.
   String host;
   # The path of the entry.
   String path;
   # The time that the entry was last used.
   Time time used;
   # The time that the entry expires.
  Time time_expires;
   # The number of hits for the entry.
  Long hits;
   # The number of variants of this entry in the
cache.
   Integer num_variants;
   # The HTTP response code for this entry in the
cache.
  Integer response_code;
   # The HTTP versions the entry is cached for.
  String[] versions;
   # The set of request-header fields that determine
   # entry may be used for a particular request.
   String[] varys;
```

}

System.Cache Function Reference

System.Cache.CacheContentInfo

This structure contains the information about the cache content.

```
struct System.Cache.CacheContentInfo {
    # The total number of items matching the wildcards
in a query.
    Integer number_matching_items;

# The total size of the items matching the
wildcards in a
    # query.
    Long size_matching_items;

# The set of individual entries in the cache that
matched the
    # query.
    System.Cache.CacheContent[] matching_items;
}
```

System.Cache.GlobalInfo

This structure contains the basic information about the content cache for a machine.

```
struct System.Cache.GlobalInfo {
    # The number of bytes of memory used by the cache.
    Long bytes_used;

# The percentage of the cache used.
Float percent_used;

# The number of entries in the cache.
Integer entries;

# The number of times a request has tried to get a page from
    # the cache.
Long num lookups;
```

```
# The number of times a request has successfully
been served

# from the cache.
Long num_hits;
}
```

Enumerations

System.Cache.Protocol

This enumeration defines the possible protocols for cache entries.

```
enum System.Cache.Protocol {
    # The hypertext transfer protocol (port 80 by
default).
    http,

    # The hypertext transfer protocol secure (port 443
by
    # default).
    https,

# This special value can be used as wildcard to
match both
    # http and https. It is never returned by the
methods in this
    # interface.
    both
}
```

System.Connections

URI: http://soap.zeus.com/zxtm/1.0/System/Connections/

The System.Connections interface provides information about the current and recent connections for this machine. Using this interface you can retrieve a list of all connections.

System.Connections Function Reference

Methods

getAllConnections()

Get a list of all connections, current and recent, for this machine.

```
System.Connections.Connection[] getAllConnections()
```

Structures

System.Connections.Connection

This structure contains the basic information about a Connection. It is used when retrieving the current and recent connections for a machine.

```
struct System.Connections.Connection {
   # The source IP address and port for connection.
   String from;
   # The local IP address and port for connection.
   String via;
   # The destination node for the connection.
   String to;
   # The connection state.
   System.Connections.ConnectionState state;
   # The virtual server handling the request.
   String vserver;
   # The rule being executed.
   String rule;
   # The pool being used.
   String pool;
```

Function Reference System.Connections

```
# The number of bytes that were received from the
client.
  Integer bytes in;
   # The number of bytes that were sent to the
client.
   Integer bytes out;
   # The length of time that the connection has been
established,
   # in seconds.
   Integer time_est;
   # The length of time since receiving the last
client data, in
   # seconds.
  Integer time client;
   # The length of time since receiving the last
server data, in
   # seconds.
   Integer time server;
   # The number of times that the connection to the
node has been
   # retried.
   Integer retries;
   # The Service Level Monitoring class being used.
   String slm class;
   # The Virtual Server Bandwidth class being used.
   String vs_bwclass;
   # The Pool Bandwidth class being used.
   String pool_bwclass;
```

System.Connections Function Reference

```
# The status code in the HTTP response.
String code;

# The host header/URL in the HTTP request.
String request;
}
```

Enumerations

System.Connections.ConnectionState

This enumeration defines the possible states for a particular connection.

```
enum System.Connections.ConnectionState {
   # Current connection: reading data from the client
('R').
   reading from client,
   # Current connection: writing data to the client
('W').
  writing_to_client,
   # Current connection: executing rules against
client request
   # ('X').
   executing rule,
   # Current connection: connecting to a node ('c').
   connecting_to_node,
   # Current connection: writing data to a node
('w').
  writing to node,
   # Current connection: reading data from a node
('r').
```

```
# Current connection: closing connection with
client ('C').
    closing_client_connection,

# Current connection: holding connection with
client in
    # keepalive state ('K').
    holding_client_connection,

# Recent connection that is no longer active.
    recent_connection
```

System.LicenseKeys

URI: http://soap.zeus.com/zxtm/1.0/System/LicenseKeys/

The System.LicenseKeys interface provides license key information for this machine. Using this interface, you can add and delete license keys, and retrieve both the license key currently in use and a list of all existing license keys.

Methods

addLicenseKeys(license_texts) throws ObjectAlreadyExists, InvalidInput

Create and add each of the named license keys.

```
Integer[] addLicenseKeys(
    String[] license_texts
)
```

deleteLicenseKeys(serials) throws ObjectDoesNotExist

Delete each of the named license keys.

```
void deleteLicenseKeys(
    Integer[] serials
)
```

System.LicenseKeys Function Reference

getAllLicenseKeys()

Get a list of all the serial numbers of the existing license keys.

```
Integer[] getAllLicenseKeys()
```

getCurrentLicenseKey()

Get the serial number of the license key currently being used by this machine.

```
Integer getCurrentLicenseKey()
```

getLicenseKeys(serials) throws ObjectDoesNotExist

For each of the named license keys, get the license key structure.

```
System.LicenseKeys.LicenseKey[] getLicenseKeys(
    Integer[] serials
)
```

getRawLicenseKeys(serials) throws ObjectDoesNotExist

For each of the named license keys, get the raw license key text.

```
String[] getRawLicenseKeys(
    Integer[] serials
)
```

Structures

System.LicenseKeys.LicenseKey

This structure contains the basic information for a license key. It is used when adding, deleting or retrieving license keys.

```
struct System.LicenseKeys.LicenseKey {
    # The name of the product the license is for.
    String product;

# The traffic manager software version for this machine.
    String version;
```

```
# The list of platforms that the software may run
   String[] platforms;
   # The maximum number of CPUs that the software may
run on.
   # Note that this field may not exist for all
license keys in
   # which case its value will be '0'.
   Integer maxcpus;
   # The IP addresses of the machines that the
software may run
   # on. Note that this field may not exist for all
license keys
   # in which case its value will be the empty array.
   String[] ip address;
   # The MAC addresses of the machines that the
software may run
   # on. Note that this field may not exist for all
license keys
   # in which case its value will be the empty array.
   String[] mac address;
  # The features that are supported by the license
key.
  String[] features;
   # The maximum number of backends supported by the
license key.
   # Note that this field may not exist for all
license keys in
   # which case its value will be '0'.
   Integer max backends;
```

```
# Additional customer information for the license
key. Note
   # that this field may not exist for all license
keys in which
   # case its value will be "".
  String customer info;
   # The customer ID for the license key. Note that
this field
   # may not exist for all license keys in which case
its value
   # will be "".
   String customer id;
   # The serial number of the license key.
   Integer serial;
   # The time at which the license key will expire.
   Time expires;
   # The time at which the license key was issued.
   Time issued;
   # The time at which the support contract for the
license key
   # expires. Note that this field is for future use
so may not
   # exist for all license keys, in which case its
value will be
   # equal to '01/01/1970 00:00:00'.
  Time maintenance;
   # The hardware serial number for the appliance
with this
   # license key. Note that this field is only
applicable to
```

```
# Stingray Appliances and otherwise will have the
value "".

String hwserial;

# The maximum cluster size supported by the
license key. Note

# that this field may not exist for all license
keys in which

# case its value will be equal to '0'.

Integer cluster_size;
}
```

System.Log

URI: http://soap.zeus.com/zxtm/1.0/System/Log/

The System.Log interface provides audit log and error log information for this machine. Using this interface, you can retrieve the error log as a string, get a list of individual entries in the audit log and clear the error log.

Methods

clearErrorLog()

Clear the error log for this machine.

```
void clearErrorLog()
```

getAuditLog()

Get a list of the most recent elements of the audit log for this machine.

```
System.Log.AuditItem[] getAuditLog()
```

getAuditLogLines(max_lines)

Get a maximum of max_lines lines of the audit log for this machine.

```
System.Log.AuditItem[] getAuditLogLines(
    Integer max_lines
)
```

getErrorLogLines(max_lines)

Get a maximum of max_lines lines of the error log for this machine as a string, if max_lines is 0 then 1024 lines are returned.

```
String getErrorLogLines(
    Integer max_lines
)
```

getErrorLogString()

Get the error log for this machine as a string.

```
String getErrorLogString()
```

Structures

System.Log.AccessDenied

This is the operation parameters structure for 'accessdenied' operations (host denied by access restrictions). It is used when getting Audit Log data.

```
struct System.Log.AccessDenied implements
System.Log.OpParam {
    # A host value.
    String host;
}
```

System.Log.AddAuthenticator

This is the operation parameters structure for 'addauth' operations (authenticator added). It is used when getting Audit Log data.

```
struct System.Log.AddAuthenticator implements
System.Log.OpParam {
    # An authenticator being modified.
    String modauth;

# Type of an authenticator being modified.
    String authtype;
}
```

System.Log.AddFile

This is the operation parameters structure for 'addfile' operations (file added). It is used when getting Audit Log data.

```
struct System.Log.AddFile implements
System.Log.OpParam {
    # A file on the filesystem being modified.
    String file;
}
```

System.Log.AddGroup

This is the operation parameters structure for 'addgroup' operations (group added). It is used when getting Audit Log data.

```
struct System.Log.AddGroup implements
System.Log.OpParam {
    # A group being modified.
    String modgroup;
}
```

System.Log.AddUser

This is the operation parameters structure for 'adduser' operations (user added). It is used when getting Audit Log data.

```
struct System.Log.AddUser implements
System.Log.OpParam {
    # A user being modified.
    String moduser;

# A group being modified.
    String modgroup;
}
```

System.Log.Adhoc

This is the operation parameters structure for 'adhoc' operations (a custom event). It is used when getting Audit Log data.

```
struct System.Log.Adhoc implements System.Log.OpParam
{
    # Arbitrary text.
```

```
String text;

# An arbitrary object.
String obj;
}
```

System.Log.AuditItem

This structure contains the information about an event in the Audit Log file. It is used when getting Audit Log information.

```
struct System.Log.AuditItem {
   # The date and time at which the event occurred.
   Time date;
   # The name of the user who caused the event.
   String user;
   # The group of the user who caused the event.
   String group;
   # The authenticator that authorised the user who
caused the
   # event.
   String auth;
   # The IP address of the user.
   String ip;
   # The type of operation that occurred.
   System.Log.OperationType op type;
   # The list of parameters used in the operation.
This list is
   # required for all operations with the exception
of operations
```

```
# for which there are no additional parameters.
System.Log.OpParam op_params;
}
```

System.Log.CopyAuthenticator

This is the operation parameters structure for 'copyauth' operations (authenticator copied). It is used when getting Audit Log data.

```
struct System.Log.CopyAuthenticator implements
System.Log.OpParam {
    # An authenticator being modified.
    String modauth;

    # An authenticator that was copied.
    String oldauth;

# Type of an authenticator being modified.
    String authtype;
}
```

System.Log.CopyFile

This is the operation parameters structure for 'copyfile' operations (file copied). It is used when getting Audit Log data.

```
struct System.Log.CopyFile implements
System.Log.OpParam {
    # A file that was copied or renamed.
    String oldfile;

# A file on the filesystem being modified.
    String file;
}
```

System.Log.CopyGroup

This is the operation parameters structure for 'copygroup' operations (group copied). It is used when getting Audit Log data.

```
struct System.Log.CopyGroup implements
System.Log.OpParam {
    # A group being modified.
    String modgroup;

# A group that was copied.
    String oldgroup;
}
```

System.Log.DeleteAuthenticator

This is the operation parameters structure for 'delauth' operations (authenticator deleted). It is used when getting Audit Log data.

```
struct System.Log.DeleteAuthenticator implements
System.Log.OpParam {
    # An authenticator being modified.
    String modauth;

# Type of an authenticator being modified.
    String authtype;
}
```

System.Log.DeleteFile

This is the operation parameters structure for 'delfile' operations (file deleted). It is used when getting Audit Log data.

```
struct System.Log.DeleteFile implements
System.Log.OpParam {
    # A file on the filesystem being modified.
    String file;
}
```

System.Log.DeleteGroup

This is the operation parameters structure for 'delgroup' operations (group deleted). It is used when getting Audit Log data.

```
struct System.Log.DeleteGroup implements
System.Log.OpParam {
```

```
# A group being modified.
String modgroup;
}
```

System.Log.DeleteUser

This is the operation parameters structure for 'deluser' operations (user deleted). It is used when getting Audit Log data.

```
struct System.Log.DeleteUser implements
System.Log.OpParam {
    # A user being modified.
    String moduser;

# A file on the filesystem being modified.
    String file;
}
```

System.Log.Login

This is the operation parameters structure for 'login' operations (logged in). It is used when getting Audit Log data.

```
struct System.Log.Login implements System.Log.OpParam
{
    # A login type, i.e. UI, basicauth, or SSH.
    String logintype;

# A login timeout value.
    String timeout;
}
```

System.Log.LoginFail

This is the operation parameters structure for 'loginfail' operations (failed login attempt). It is used when getting Audit Log data.

```
struct System.Log.LoginFail implements
System.Log.OpParam {
    # A login type, i.e. UI, basicauth, or SSH.
    String logintype;
```

```
# Resource being accessed.
String resource;
}
```

System.Log.LoginLimitHit

This is the operation parameters structure for 'loginlockout' operations (user account disabled). It is used when getting Audit Log data.

```
struct System.Log.LoginLimitHit implements
System.Log.OpParam {
    # Arbitrary text.
    String text;
}
```

System.Log.LoginSuspended

This is the operation parameters structure for 'loginsusp' operations (suspended user login attempt). It is used when getting Audit Log data.

```
struct System.Log.LoginSuspended implements
System.Log.OpParam {
    # A login type, i.e. UI, basicauth, or SSH.
    String logintype;
}
```

System.Log.MaintenanceCLICmd

This is the operation parameters structure for 'maintclicmd' operations (maintenance CLI command). It is used when getting Audit Log data.

```
struct System.Log.MaintenanceCLICmd implements
System.Log.OpParam {
    # The command being run.
    String cmd;

# The arguments for the command being run.
    String args;
}
```

System.Log.ModifyFile

This is the operation parameters structure for 'filemod' operations (file modified). It is used when getting Audit Log data.

```
struct System.Log.ModifyFile implements
System.Log.OpParam {
    # A file on the filesystem being modified.
    String file;
}
```

System.Log.ModifyKey

This is the operation parameters structure for 'keymod' operations (config modified). It is used when getting Audit Log data.

```
struct System.Log.ModifyKey implements
System.Log.OpParam {
    # A configuration key.
    String key;

    # A configuration value.
    String value;

# A value that was changed.
    String oldval;

# A file on the filesystem being modified.
    String file;
}
```

System.Log.ModifyRule

This is the operation parameters structure for 'rulemod' operations (modified rule). It is used when getting Audit Log data.

```
struct System.Log.ModifyRule implements
System.Log.OpParam {
    # A file on the filesystem being modified.
    String file;
}
```

System.Log.ModifyUser

This is the operation parameters structure for 'usermod' operations (user modified). It is used when getting Audit Log data.

```
struct System.Log.ModifyUser implements
System.Log.OpParam {
    # A user being modified.
    String moduser;
}
```

System.Log.NoAccessPermission

This is the operation parameters structure for 'noperm' operations (user was refused permission whilst accessing section/item). It is used when getting Audit Log data.

```
struct System.Log.NoAccessPermission implements
System.Log.OpParam {
    # A section.
    String sec;
}
```

System.Log.NoChangePermission

This is the operation parameters structure for 'nopostperm' operations (user was refused permission to update data in section). It is used when getting Audit Log data.

```
struct System.Log.NoChangePermission implements
System.Log.OpParam {
    # A section.
    String sec;
}
```

System.Log.OpParam

This is the base type structure for operation parameters. It is used when getting Audit Log data.

```
struct System.Log.OpParam {
}
```

System.Log.PasswordExpired

This is the operation parameters structure for 'passwordexpired' operations (user's password has expired.). It is used when getting Audit Log data.

```
struct System.Log.PasswordExpired implements
System.Log.OpParam {
    # A login type, i.e. UI, basicauth, or SSH.
    String logintype;

# Resource being accessed.
    String resource;
}
```

System.Log.RemoveKey

This is the operation parameters structure for 'removekey' operations (removed config key). It is used when getting Audit Log data.

```
struct System.Log.RemoveKey implements
System.Log.OpParam {
    # A configuration key.
    String key;

    # A value that was changed.
    String oldval;

# A file on the filesystem being modified.
    String file;
}
```

System.Log.RenameFile

This is the operation parameters structure for 'renfile' operations (file renamed). It is used when getting Audit Log data.

```
struct System.Log.RenameFile implements
System.Log.OpParam {
    # A file that was copied or renamed.
    String oldfile;
```

```
# A file on the filesystem being modified.
String file;
}
```

System.Log.SessionTerminated

This is the operation parameters structure for 'terminated' operations (user session terminated). It is used when getting Audit Log data.

```
struct System.Log.SessionTerminated implements
System.Log.OpParam {
    # Arbitrary text.
    String text;
}
```

System.Log.StartVS

This is the operation parameters structure for 'startvs' operations (virtual server started). It is used when getting Audit Log data.

```
struct System.Log.StartVS implements
System.Log.OpParam {
    # A virtual server.
    String vs;
}
```

System.Log.StopVS

This is the operation parameters structure for 'stopvs' operations (virtual server stopped). It is used when getting Audit Log data.

```
struct System.Log.StopVS implements
System.Log.OpParam {
    # A virtual server.
    String vs;
}
```

System.Log.TrafficManagerActivated

This is the operation parameters structure for 'activated' operations (traffic manager activated). It is used when getting Audit Log data.

```
struct System.Log.TrafficManagerActivated implements
System.Log.OpParam {
```

```
# A host value.
String host;
}
```

Enumerations

System.Log.OperationType

This enumeration defines the possible types of operations that may exist in the audit log.

```
enum System.Log.OperationType {
   # An AccessDenied operation occurs when a user is
denied
   # access to the Admin Server due to access
restrictions which
   # are in place. It appears as an 'accessdenied'
operation in
   # the Audit Log.
  AccessDenied,
   # A TrafficManagerActivated operation occurs when
a traffic
   # manager is restored from a pending state after a
failure has
   # occured. This results in the traffic manager's
Traffic IPs
   # being restored to it. It appears as an
'activated' operation
   # in the Audit Log.
   TrafficManagerActivated,
   # An AddAuthenticator operation type occurs when a
new
   # authenticator is created. It appears as a
'addauth'
   # operation in the Audit Log.
   AddAuthenticator,
   # An AddFile operation occurs when a file is
added. This
```

```
# operation is caused by a user creating a new
object such as
   # a Virtual Server, Pool, etc. It appears as an
'addfile'
   # operation in the Audit Log.
  AddFile,
   # An AddGroup operation occurs when a new group of
users is
   # created. It appears as an 'addgroup' operation
in the Audit
   # Log.
  AddGroup,
   # An AddUser operation occurs when a new user is
added. It
   # appears as an 'adduser' operation in the Audit
Log.
  AddUser,
   # An Adhoc operation represents a custom event
which does not
   # fit any of the other Operation Types. For
example, it occurs
   # when a user is adding or deleting a License Key
or modifying
   # the Security settings. It appears as an 'adhoc'
operation
   # the Audit Log.
  Adhoc,
   # The admin user's password has been reset from
the system
   # console.
  AdminPasswordReset,
   # A CopyAuthenticator operation type occurs when a
new
```

```
# authenticator is created by saving an existing
authenticator
   # to a new name. It appears as a 'copyauth'
operation in the
   # Audit Log.
   CopyAuthenticator,
   # A CopyFile operation occurs when a file is
copied. This
   # operation is caused by the user saving an object
as a new
   # name, for example a Rule or an SSL Certificate.
It appears
   # as a 'copyfile' operation in the Audit Log.
   CopyFile,
   # A CopyGroup operation occurs when a user group
is saved with
   # a new group name. It appears as an 'copygroup'
operation in
   # the Audit Log.
   CopyGroup,
   # A DeleteAuthenticator operation type occurs when
an existing
   # authenticator is deleted. It appears as a
'delauth'
   # operation in the Audit Log.
  DeleteAuthenticator,
   # A DeleteFile operation occurs when a file is
deleted. This
   # operation is caused by a user deleting an
existing object
   # such as a Virtual Server, Pool, etc. It appears
as a
   # 'delfile' operation in the Audit Log.
   DeleteFile,
```

```
# A DeleteGroup operation occurs when a group of
   # deleted. It appears as an 'delgroup' operation
in the Audit
   # Log.
   DeleteGroup,
   # A DeleteUser operation occurs when an existing
   # deleted. It appears as an 'deluser' operation in
the Audit
   # Log.
  DeleteUser,
   # A ModifyFile operation occurs when the contents
of a
   # non-config file are modified. This differs from
a ModifyKey
   # operation in that ModifyFile operations are
caused by the
   # modification of non-config files which are not
managed by
   # the traffic manager, for example changing the
settings of an
   # SSL Certificate. It appears as a 'filemod'
operation in the
   # Audit Log.
  ModifyFile,
   # A ModifyKey operation occurs when the value of a
config file
   # is modified. This operation is caused by a user
changing the
   # settings for an existing object such as a
Virtual Server,
   # Pool, etc. It appears as a 'keymod' operation in
the Audit
   # Log.
```

ModifyKey,

```
# A Login operation occurs when a user
successfully logs on to
   # the admin server. It appears as a 'login'
operation in the
   # Audit Log.
  Login,
   # A LoginFail operation occurs when a user tries
and fails to
   # log on to the admin server. This type of
operation does not
   # have any additional parameters to log therefore
the
   # 'op params' field does not exist. It appears as
   # 'loginfail' operation in the Audit Log.
  LoginFail,
   # A LoginLimitHit operation occurs when the limit
on login
   # attempts is hit for a particular user . It
appears as an
   # 'loginlockout' operation in the Audit Log.
  LoginLimitHit,
   # A LoginSuspended operation occurs when suspended
user
   # attempts to login. It appears as an 'loginsusp'
operation in
   # the Audit Log.
  LoginSuspended,
```

- # A Logout operation occurs when a user successfully logs out

System.Log Function Reference

any additional parameters to log therefore the
'op params'

- # field does not exist. It appears as a 'logout'
 operation in
 - # the Audit Log.

Logout,

- $\mbox{\#}$ in the appliance maintenance CLI. It appears as an
 - # 'maintclicmd' operation in the Audit Log.

MaintenanceCLICmd,

- $\mbox{\#}$ permission whist accessing a section of the Admin Server. It
- $\mbox{\tt\#}$ appears as a 'noperm' operation in the Audit Log.

NoAccessPermission,

- $\mbox{\#}$ permission to update data in a section of the Admin Server.
- $\mbox{\tt\#}$ It appears as a 'nopostperm' operation in the Audit Log.

NoChangePermission,

- # A PasswordExpired operation occurs when a user's password is
- # too old and expires. It appears as an
 'passwordexpired'
 - # operation in the Audit Log.

PasswordExpired,

Function Reference System.Log

```
# system configuration is reapplied on an
appliance. It
   # appears as an 'reapplynetwork' operation in the
Audit Log.
   SystemSettingsReapplied,
   # A RemoveKey operation type occurs when a key is
removed from
   # a config file, usually because a key is being
made location
   # specific. It appears as a 'removekey' operation
in the Audit
   # Log.
   RemoveKey,
   # A RenameFile operation occurs when a file is
renamed. This
   # operation is caused by a user renaming an
existing object
   # such as a Virtual Server, Pool, etc. It appears
   # 'renfile' operation in the Audit Log.
   RenameFile,
   # A ConfigRefreshed operation occurs when the
configuration is
   # forcably reloaded. It appears as an 'revalidate'
operation
   # in the Audit Log.
   ConfigRefreshed,
   # A ModifyRule operation occurs when the contents
of a rule
   # are modified. This operation is caused by a user
editing an
   # existing rule. It appears as a 'rulemod'
operation in the
   # Audit Log.
   ModifyRule,
```

System.Log Function Reference

```
# A StartVS operation type occurs when a user
starts an
   # existing virtual server. It appears as a
'startvs' operation
   # in the Audit Log.
   StartVS,
   # A StopVS operation type occurs when a user stops
an existing
   # virtual server. It appears as a 'stopvs'
operation in the
   # Audit Log.
   StopVS,
   # A SuspensionExpired operation occurs when a
users suspension
   # expires, restoring them to active status. This
usually
   # occurs when after too many attempts have been
made to login
   # to an account. It appears as an
'suspensionexpired'
   # operation in the Audit Log.
   SuspensionExpired,
   # A Synchronise operation type occurs when
configuration is
   # replicated from one machine across the cluster,
for example
   # in order to resolve a conflict arising from one
machine
   # being unavailable at the time when a
configuration change
   # was made. It appears as a 'synchronise'
operation in the
   # Audit Log.
   Synchronise,
```

Function Reference System.MachineInfo

```
# A SessionTerminated operation occurs when a
users session is
   # terminated externally. It appears as an
'terminated'
   # operation in the Audit Log.
   SessionTerminated,
   # A Timeout operation occurs when a user session
times out.
   # This type of operation does not have any
additional
   # parameters to log therefore the 'op params'
field does not
   # exist. It appears as a 'timeout' operation in
the Audit Log.
   Timeout,
   # A ModifyUser operation occurs when an existing
user is
   # modified. It appears as an 'usermod' operation
in the Audit
   # Log.
   ModifyUser
}
```

System.MachineInfo

URI: http://soap.zeus.com/zxtm/1.0/System/MachineInfo/

The System.MachineInfo interface provides information about the IP addresses, MAC addresses and traffic manager software version for this machine.

Methods

getAllClusterMachines()

Gets all of the machines in this traffic manager's cluster.

System.MachineInfo.Machine[] getAllClusterMachines()

System.MachineInfo Function Reference

getIPAddresses()

Get a list of IP addresses for this machine.

```
String[] getIPAddresses()
```

getMACAddresses()

Get a list of MAC addresses for this machine.

```
String[] getMACAddresses()
```

getProductVersion()

Get the traffic manager software version for this machine.

```
String getProductVersion()
```

getTrafficManagerUptime()

Get the time (in seconds) that the traffic manager has been running for.

```
Unsigned Integer getTrafficManagerUptime()
```

getZeusHome()

Get the install location of the traffic manager software (ZEUSHOME).

```
String getZeusHome()
```

isIPv6Enabled()

Check whether IPv6 is enabled on this system and supported by the traffic manager

```
Boolean isIPv6Enabled()
```

Structures

System.MachineInfo.Machine

This structure contains information about a traffic manager in the cluster.

```
struct System.MachineInfo.Machine {
    # The hostname of this machine
    String hostname;
```

```
# The IP address of this machine.
String ipaddress;

# The URL of the admin server for this traffic manager.
String admin_server;

# The install path of the traffic manager on this machine.
String zeushome;
}
```

System.RequestLogs

URI: http://soap.zeus.com/zxtm/1.0/System/RequestLogs/

The RequestLogs interfaces provide operations on saved virtual server request logs for a Stingray Appliance. This interface is only available on a Stingray Appliance.

Methods

deleteAllVSRequestLogs() throws InvalidOperation

Delete all the request logs for all virtual servers.

```
void deleteAllVSRequestLogs()
```

deleteVSRequestLog(logfiles) throws InvalidInput, InvalidOperation

Delete the specified request logs.

```
void deleteVSRequestLog(
    String[] logfiles
)
```

deleteVSRequestLogs(vservers) throws InvalidOperation

Delete the request logs for specific virtual servers.

```
void deleteVSRequestLogs(
    String[] vservers
)
```

getAllVSRequestLogs() throws InvalidOperation

Get the request logs for all virtual servers.

```
System.RequestLogs.VSRequestLog[]
getAllVSRequestLogs()
```

getVSRequestLogs(vservers) throws InvalidOperation

Get the request logs for specific virtual servers.

```
System.RequestLogs.VSRequestLog[][] getVSRequestLogs(
    String[] vservers
)
```

Structures

System.RequestLogs.VSRequestLog

This structure contains the information for each virtual server request log.

```
struct System.RequestLogs.VSRequestLog {
    # The log filename.
    String filename;

# The virtual server for this logfile.
    String virtual_server;

# The date this logfile was created.
    Time logdate;

# The size (in bytes) of this logfile.
    Integer filesize;
}
```

System.Stats

URI: http://soap.zeus.com/zxtm/1.0/System/Stats/

The System.Stats interface retrieves statistical information about the system. This interface is essentially an implementation of part of the SNMP interface in SOAP.

Methods

getActionNumber()

The number of actions configured in the traffic manager.

```
Integer getActionNumber()
```

getActions()

Gets the list of Alerting Actions configured.

```
String[] getActions()
```

getActionsProcessed(names) throws InvalidInput, InvalidObjectName

Number of times this action has been processed, for each of the named Actions.

```
Integer[] getActionsProcessed(
    String[] names
)
```

getAspSessionCacheEntries()

The total number of ASP sessions stored in the cache.

```
Integer getAspSessionCacheEntries()
```

getAspSessionCacheEntriesMax()

The maximum number of ASP sessions in the cache.

```
Integer getAspSessionCacheEntriesMax()
```

getAspSessionCacheHitRate()

The percentage of ASP session lookups that succeeded.

```
Integer getAspSessionCacheHitRate()
```

getAspSessionCacheHits()

Number of times a ASP session entry has been successfully found in the cache.

```
Integer getAspSessionCacheHits()
```

getAspSessionCacheLookups()

Number of times a ASP session entry has been looked up in the cache.

```
Integer getAspSessionCacheLookups()
```

getAspSessionCacheMisses()

Number of times a ASP session entry has not been available in the cache.

```
Integer getAspSessionCacheMisses()
```

getAspSessionCacheOldest()

The age of the oldest ASP session in the cache (in seconds).

```
Integer getAspSessionCacheOldest()
```

getAuthenticatorErrors(names) throws InvalidInput, InvalidObjectName

Number of connection errors that have occured when trying to connect to an authentication server, for each of the named Authenticators.

```
Integer[] getAuthenticatorErrors(
    String[] names
)
```

getAuthenticatorFails(names) throws InvalidInput, InvalidObjectName

Number of times this Authenticator has failed to authenticate, for each of the named Authenticators.

```
Integer[] getAuthenticatorFails(
    String[] names
```

getAuthenticatorNumber()

The number of Authenticators.

```
Integer getAuthenticatorNumber()
```

getAuthenticatorPasses(names) throws InvalidInput, InvalidObjectName

Number of times this Authenticator has successfully authenticated, for each of the named Authenticators.

```
Integer[] getAuthenticatorPasses(
    String[] names
)
```

getAuthenticatorRequests(names) throws InvalidInput, InvalidObjectName

Number of times this Authenticator has been asked to authenticate, for each of the named Authenticators.

```
Integer[] getAuthenticatorRequests(
    String[] names
)
```

getAuthenticators()

Gets the list of Authenticators configured.

```
String[] getAuthenticators()
```

getBandwidthClassBytesOut(names) throws InvalidInput, InvalidObjectName

Bytes output by connections assigned to this bandwidth class, for each of the named BandwidthClasses.

```
Long[] getBandwidthClassBytesOut(
    String[] names
)
```

getBandwidthClassGuarantee(names) throws InvalidInput, InvalidObjectName

Guaranteed bandwidth class limit (kbits/s). Currently unused, for each of the named BandwidthClasses.

```
Integer[] getBandwidthClassGuarantee(
    String[] names
)
```

getBandwidthClassMaximum(names) throws InvalidInput, InvalidObjectName

Maximum bandwidth class limit (kbits/s), for each of the named BandwidthClasses.

```
Integer[] getBandwidthClassMaximum(
    String[] names
)
```

getBandwidthClassNumber()

The number of bandwidth classes defined.

```
Integer getBandwidthClassNumber()
```

getBandwidthClasses()

Gets the list of Bandwidth Classes configured.

```
String[] getBandwidthClasses()
```

getCloudcredentialsClassNumber()

The number of cloud credentials sets defined.

```
Integer getCloudcredentialsClassNumber()
```

getCloudcredentialsNodeCreations(names) throws InvalidInput, InvalidObjectName

The number of instance creation API requests made with this set of cloud credentials, for each of the named Cloudcredentialses.

```
Integer[] getCloudcredentialsNodeCreations(
    String[] names
)
```

getCloudcredentialsNodeDeletions(names) throws InvalidInput, InvalidObjectName

The number of instance destruction API requests made with this set of cloud credentials, for each of the named Cloudcredentialses.

```
Integer[] getCloudcredentialsNodeDeletions(
    String[] names
)
```

getCloudcredentialsStatusRequests(names) throws InvalidInput, InvalidObjectName

The number of status API requests made with this set of cloud credentials, for each of the named Cloudcredentialses.

```
Integer[] getCloudcredentialsStatusRequests(
    String[] names
)
```

getCloudcredentialses()

Gets the list of Cloud Credentials configured.

```
String[] getCloudcredentialses()
```

getDataEntries()

Number of entries in the TrafficScript data.get()/set() storage.

```
Integer getDataEntries()
```

getDataMemoryUsage()

Number of bytes used in the TrafficScript data.get()/set() storage.

```
Integer getDataMemoryUsage()
```

getEventNumber()

The number of event configurations.

```
Integer getEventNumber()
```

getEvents()

Gets the list of Event Types configured.

```
String[] getEvents()
```

getEventsMatched(names) throws InvalidInput, InvalidObjectName

Number of times this event configuration has matched, for each of the named Events.

```
Integer[] getEventsMatched(
```

```
String[] names
)
```

getEventsSeen()

Events seen by the traffic Manager's event handling process.

```
Integer getEventsSeen()
```

getGlbServiceDiscarded(names) throws InvalidInput, InvalidObjectName

Number of A records this GLB Service has discarded, for each of the named GlbServices.

```
Integer[] getGlbServiceDiscarded(
    String[] names
)
```

getGlbServiceNumber()

The number of GLB Services on this system.

```
Integer getGlbServiceNumber()
```

getGlbServiceResponses(names) throws InvalidInput, InvalidObjectName

Number of A records this GLB Service has altered, for each of the named GlbServices.

```
Integer[] getGlbServiceResponses(
    String[] names
)
```

getGlbServiceUnmodified(names) throws InvalidInput, InvalidObjectName

Number of A records this GLB Service has passed through unmodified, for each of the named GlbServices.

```
Integer[] getGlbServiceUnmodified(
    String[] names
)
```

getGlbServices()

Gets the list of GLB services configured.

```
String[] getGlbServices()
```

getInterfaceCollisions(names) throws InvalidInput, InvalidObjectName

The number of collisions reported by this interface, for each of the named Interfaces.

```
Integer[] getInterfaceCollisions(
    String[] names
)
```

getInterfaceNumber()

The number of network interfaces.

```
Integer getInterfaceNumber()
```

getInterfaceRxBytes(names) throws InvalidInput, InvalidObjectName

Bytes received by this interface, for each of the named Interfaces.

```
Long[] getInterfaceRxBytes(
    String[] names
)
```

getInterfaceRxErrors(names) throws InvalidInput, InvalidObjectName

The number of receive errors reported by this interface, for each of the named Interfaces.

```
Integer[] getInterfaceRxErrors(
    String[] names
)
```

getInterfaceRxPackets(names) throws InvalidInput, InvalidObjectName

The number of packets received by this interface, for each of the named Interfaces.

```
Integer[] getInterfaceRxPackets(
    String[] names
)
```

getInterfaceTxBytes(names) throws InvalidInput, InvalidObjectName

Bytes transmitted by this interface, for each of the named Interfaces.

```
Long[] getInterfaceTxBytes(
    String[] names
)
```

getInterfaceTxErrors(names) throws InvalidInput, InvalidObjectName

The number of transmit errors reported by this interface, for each of the named Interfaces.

```
Integer[] getInterfaceTxErrors(
    String[] names
)
```

getInterfaceTxPackets(names) throws InvalidInput, InvalidObjectName

The number of packets transmitted by this interface, for each of the named Interfaces.

```
Integer[] getInterfaceTxPackets(
    String[] names
```

getInterfaces()

Gets the list of Network Interfaces configured.

```
String[] getInterfaces()
```

getlpSessionCacheEntries()

The total number of IP sessions stored in the cache.

```
Integer getIpSessionCacheEntries()
```

getlpSessionCacheEntriesMax()

The maximum number of IP sessions in the cache.

```
Integer getIpSessionCacheEntriesMax()
```

getlpSessionCacheHitRate()

The percentage of IP session lookups that succeeded.

```
Integer getIpSessionCacheHitRate()
```

getlpSessionCacheHits()

Number of times a IP session entry has been successfully found in the cache.

Integer getIpSessionCacheHits()

getIpSessionCacheLookups()

Number of times a IP session entry has been looked up in the cache.

Integer getIpSessionCacheLookups()

getIpSessionCacheMisses()

Number of times a IP session entry has not been available in the cache.

Integer getIpSessionCacheMisses()

getlpSessionCacheOldest()

The age of the oldest IP session in the cache (in seconds).

Integer getIpSessionCacheOldest()

getJ2eeSessionCacheEntries()

The total number of J2EE sessions stored in the cache.

Integer getJ2eeSessionCacheEntries()

getJ2eeSessionCacheEntriesMax()

The maximum number of J2EE sessions in the cache.

Integer getJ2eeSessionCacheEntriesMax()

getJ2eeSessionCacheHitRate()

The percentage of J2EE session lookups that succeeded.

Integer getJ2eeSessionCacheHitRate()

getJ2eeSessionCacheHits()

Number of times a J2EE session entry has been successfully found in the cache.

Integer getJ2eeSessionCacheHits()

getJ2eeSessionCacheLookups()

Number of times a J2EE session entry has been looked up in the cache.

```
Integer getJ2eeSessionCacheLookups()
```

getJ2eeSessionCacheMisses()

Number of times a J2EE session entry has not been available in the cache.

```
Integer getJ2eeSessionCacheMisses()
```

getJ2eeSessionCacheOldest()

The age of the oldest J2EE session in the cache (in seconds).

```
Integer getJ2eeSessionCacheOldest()
```

getLicensekeyNumber()

The number of License keys.

```
Integer getLicensekeyNumber()
```

getListenIPBytesIn(listen_ip_addresses) throws InvalidInput, InvalidObjectName

Bytes sent to this listening IP, for each of the specified ListenIPs.

```
Long[] getListenIPBytesIn(
    String[] listen_ip_addresses
)
```

getListenIPBytesOut(listen_ip_addresses) throws InvalidInput, InvalidObjectName

Bytes sent from this listening IP, for each of the specified ListenIPs.

```
Long[] getListenIPBytesOut(
    String[] listen_ip_addresses
)
```

getListenIPCurrentConn(listen_ip_addresses) throws InvalidInput, InvalidObjectName

TCP connections currently established to this listening IP, for each of the specified ListenIPs.

```
Integer[] getListenIPCurrentConn(
    String[] listen_ip_addresses
)
```

getListenIPMaxConn(listen_ip_addresses) throws InvalidInput, InvalidObjectName

Maximum number of simultaneous TCP connections this listening IP has processed at any one time, for each of the specified ListenIPs.

```
Integer[] getListenIPMaxConn(
    String[] listen_ip_addresses
)
```

getListenIPTotalConn(listen_ip_addresses) throws InvalidInput, InvalidObjectName

Requests sent to this listening IP, for each of the specified ListenIPs.

```
Integer[] getListenIPTotalConn(
    String[] listen_ip_addresses
)
```

getListenIPs()

Gets the list of all IP addresses that Virtual Servers are listening on.

```
String[] getListenIPs()
```

getLocationLoad(names) throws InvalidInput, InvalidObjectName

The mean load metric for this location, for each of the named Locations.

```
Integer[] getLocationLoad(
    String[] names
)
```

getLocationResponses(names) throws InvalidInput, InvalidObjectName

Number of A records that have been altered to point to this location, for each of the named Locations.

```
Integer[] getLocationResponses(
    String[] names
```

)

getLocations()

Gets the list of Locations configured.

```
String[] getLocations()
```

getMonitorNumber()

The number of Monitors.

```
Integer getMonitorNumber()
```

getNodeBytesFromNode(nodes) throws InvalidInput, InvalidObjectName

Bytes received from this node, for each of the specified Nodes.

```
Long[] getNodeBytesFromNode(
          System.Stats.Node[] nodes
)
```

getNodeBytesToNode(nodes) throws InvalidInput, InvalidObjectName

Bytes sent to this node, for each of the specified Nodes.

getNodeCurrentConn(nodes) throws InvalidInput, InvalidObjectName

Current connections established to this node, includes idle connections, for each of the specified Nodes.

```
Integer[] getNodeCurrentConn(
          System.Stats.Node[] nodes
)
```

getNodeCurrentRequests(nodes) throws InvalidInput, InvalidObjectName

Active connections established to this node, does not include idle connections, for each of the specified Nodes.

```
Integer[] getNodeCurrentRequests(
```

```
System.Stats.Node[] nodes
)
```

getNodeErrors(nodes) throws InvalidInput, InvalidObjectName

Number of timeouts, connection problems and other errors for this node, for each of the specified Nodes.

```
Integer[] getNodeErrors(
          System.Stats.Node[] nodes
)
```

getNodeFailures(nodes) throws InvalidInput, InvalidObjectName

Failures of this node, for each of the specified Nodes.

```
Integer[] getNodeFailures(
          System.Stats.Node[] nodes
)
```

getNodeldleConns(nodes) throws InvalidInput, InvalidObjectName

Number of idle HTTP connections to this node, for each of the specified Nodes.

```
Integer[] getNodeIdleConns(
          System.Stats.Node[] nodes
)
```

getNodeNewConn(nodes) throws InvalidInput, InvalidObjectName

Requests that created a new connection to this node, for each of the specified Nodes.

```
Integer[] getNodeNewConn(
          System.Stats.Node[] nodes
)
```

getNodeNumber()

The number of nodes on this system (includes IPv4 and IPv6 nodes).

```
Integer getNodeNumber()
```

getNodePooledConn(nodes) throws InvalidInput, InvalidObjectName

Requests that reused an existing pooled/keepalive connection rather than creating a new TCP connection, for each of the specified Nodes.

```
Integer[] getNodePooledConn(
          System.Stats.Node[] nodes
)
```

getNodeResponseMax(nodes) throws InvalidInput, InvalidObjectName

Maximum response time (ms) in the last second for this node, for each of the specified Nodes.

getNodeResponseMean(nodes) throws InvalidInput, InvalidObjectName

Mean response time (ms) in the last second for this node, for each of the specified Nodes.

getNodeResponseMin(nodes) throws InvalidInput, InvalidObjectName

Minimum response time (ms) in the last second for this node, for each of the specified Nodes.

```
Integer[] getNodeResponseMin(
          System.Stats.Node[] nodes
)
```

getNodeState(nodes) throws InvalidInput, InvalidObjectName

The state of this node, for each of the specified Nodes.

```
System.Stats.NodeState[] getNodeState(
    System.Stats.Node[] nodes
)
```

getNodeTotalConn(nodes) throws InvalidInput, InvalidObjectName

Requests sent to this node, for each of the specified Nodes.

```
Integer[] getNodeTotalConn(
          System.Stats.Node[] nodes
)
```

getNodes()

Retrieves the list of available Nodes.

```
System.Stats.Node[] getNodes()
```

getNumIdleConnections()

Total number of idle HTTP connections to all nodes (used for future HTTP requests).

```
Integer getNumIdleConnections()
```

getNumberChildProcesses()

The number of traffic manager child processes.

```
Integer getNumberChildProcesses()
```

getNumberDNSACacheHits()

Requests for DNS A records resolved from the traffic manager's local cache.

```
Integer getNumberDNSACacheHits()
```

getNumberDNSARequests()

Requests for DNS A records (hostname->IP address) made by the traffic manager.

```
Integer getNumberDNSARequests()
```

getNumberDNSPTRCacheHits()

Requests for DNS PTR records resolved from the traffic manager's local cache.

```
Integer getNumberDNSPTRCacheHits()
```

getNumberDNSPTRRequests()

Requests for DNS PTR records (IP address->hostname) made by the traffic manager.

Integer getNumberDNSPTRRequests()

getNumberSNMPBadRequests()

Malformed SNMP requests received.

Integer getNumberSNMPBadRequests()

getNumberSNMPGetBulkRequests()

SNMP GetBulkRequests received.

Integer getNumberSNMPGetBulkRequests()

getNumberSNMPGetNextRequests()

SNMP GetNextRequests received.

Integer getNumberSNMPGetNextRequests()

getNumberSNMPGetRequests()

SNMP GetRequests received.

Integer getNumberSNMPGetRequests()

getNumberSNMPUnauthorisedRequests()

SNMP requests dropped due to access restrictions.

Integer getNumberSNMPUnauthorisedRequests()

getPerLocationServiceDraining(per_location_services) throws InvalidInput, InvalidObjectName

The draining state of this location for this GLB Service, for each of the specified PerLocationServices.

getPerLocationServiceFrontendState(per_location_services) throws InvalidInput, InvalidObjectName

The frontend state of this location for this GLB Service, for each of the specified PerLocationServices.

```
System.Stats.PerLocationServiceFrontendState[]
getPerLocationServiceFrontendState(
    System.Stats.PerLocationService[]
per_location_services
)
```

getPerLocationServiceLoad(per_location_services) throws InvalidInput, InvalidObjectName

The load metric for this location for this GLB Service, for each of the specified PerLocationServices.

```
Integer[] getPerLocationServiceLoad(
        System.Stats.PerLocationService[]
per_location_services
)
```

getPerLocationServiceMonitorState(per_location_services) throws InvalidInput, InvalidObjectName

The monitor state of this location for this GLB Service, for each of the specified PerLocationServices.

```
System.Stats.PerLocationServiceMonitorState[]
getPerLocationServiceMonitorState(
        System.Stats.PerLocationService[]
per_location_services
)
```

getPerLocationServiceResponses(per_location_services) throws InvalidInput, InvalidObjectName

Number of A records that have been altered to point to this location for this GLB Service, for each of the specified PerLocationServices.

```
Integer[] getPerLocationServiceResponses(
        System.Stats.PerLocationService[]
per_location_services
)
```

getPerLocationServiceState(per_location_services) throws InvalidInput, InvalidObjectName

The state of this location for this GLB Service, for each of the specified PerLocationServices.

```
System.Stats.PerLocationServiceState[]
getPerLocationServiceState(
    System.Stats.PerLocationService[]
per_location_services
)
```

getPerLocationServices()

Retrieves the list of available PerLocationServices.

```
System.Stats.PerLocationService[]
getPerLocationServices()
```

getPerNodeServiceLevelResponseMax(per_node_service_levels) throws InvalidInput, InvalidObjectName

Maximum response time (ms) in the last second for this SLM class to this node, for each of the specified PerNodeServiceLevels.

```
Integer[] getPerNodeServiceLevelResponseMax(
         System.Stats.PerNodeServiceLevel[]
per_node_service_levels
)
```

getPerNodeServiceLevelResponseMean(per_node_service_levels) throws InvalidInput, InvalidObjectName

Mean response time (ms) in the last second for this SLM class to this node, for each of the specified PerNodeServiceLevels.

```
Integer[] getPerNodeServiceLevelResponseMean(
        System.Stats.PerNodeServiceLevel[]
per_node_service_levels
)
```

getPerNodeServiceLevelResponseMin(per_node_service_levels) throws InvalidInput, InvalidObjectName

Minimum response time (ms) in the last second for this SLM class to this node, for each of the specified PerNodeServiceLevels.

```
Integer[] getPerNodeServiceLevelResponseMin(
```

```
System.Stats.PerNodeServiceLevel[]
per_node_service_levels
)
```

getPerNodeServiceLevelTotalConn(per_node_service_levels) throws InvalidInput, InvalidObjectName

Requests handled by this SLM class to this node, for each of the specified PerNodeServiceLevels.

```
Integer[] getPerNodeServiceLevelTotalConn(
         System.Stats.PerNodeServiceLevel[]
per_node_service_levels
)
```

getPerNodeServiceLevelTotalNonConf(per_node_service_levels) throws InvalidInput, InvalidObjectName

Non-conforming requests handled by this SLM class to this node, for each of the specified PerNodeServiceLevels.

```
Integer[] getPerNodeServiceLevelTotalNonConf(
        System.Stats.PerNodeServiceLevel[]
per_node_service_levels
)
```

getPerNodeServiceLevels()

Retrieves the list of available PerNodeServiceLevels.

```
System.Stats.PerNodeServiceLevel[]
getPerNodeServiceLevels()
```

getPerPoolNodeBytesFromNode(per_pool_nodes) throws InvalidInput, InvalidObjectName

Bytes received from this node, for each of the specified PerPoolNodes.

getPerPoolNodeBytesToNode(per_pool_nodes) throws InvalidInput, InvalidObjectName

Bytes sent to this node, for each of the specified PerPoolNodes.

```
Long[] getPerPoolNodeBytesToNode(
        System.Stats.PerPoolNode[] per_pool_nodes
)
```

getPerPoolNodeCurrentConn(per_pool_nodes) throws InvalidInput, InvalidObjectName

Current connections established to a node, includes idle connections, for each of the specified PerPoolNodes.

getPerPoolNodeCurrentRequests(per_pool_nodes) throws InvalidInput, InvalidObjectName

Active connections established to this node, does not include idle connections, for each of the specified PerPoolNodes.

getPerPoolNodeErrors(per_pool_nodes) throws InvalidInput, InvalidObjectName

Number of timeouts, connection problems and other errors for this node, for each of the specified PerPoolNodes.

```
Integer[] getPerPoolNodeErrors(
        System.Stats.PerPoolNode[] per_pool_nodes
)
```

getPerPoolNodeFailures(per_pool_nodes) throws InvalidInput, InvalidObjectName

Failures of this node, for each of the specified PerPoolNodes.

```
Integer[] getPerPoolNodeFailures(
        System.Stats.PerPoolNode[] per_pool_nodes
)
```

getPerPoolNodeldleConns(per_pool_nodes) throws InvalidInput, InvalidObjectName

Number of idle HTTP connections to this node, for each of the specified PerPoolNodes.

getPerPoolNodeNewConn(per_pool_nodes) throws InvalidInput, InvalidObjectName

Requests that created a new connection to this node, for each of the specified PerPoolNodes.

getPerPoolNodeNumber()

The number of nodes on this system.

```
Integer getPerPoolNodeNumber()
```

getPerPoolNodePooledConn(per_pool_nodes) throws InvalidInput, InvalidObjectName

Requests that reused an existing pooled/keepalive connection rather than creating a new TCP connection, for each of the specified PerPoolNodes.

getPerPoolNodeResponseMax(per_pool_nodes) throws InvalidInput, InvalidObjectName

Maximum response time (ms) in the last second for this node, for each of the specified PerPoolNodes.

getPerPoolNodeResponseMean(per_pool_nodes) throws InvalidInput, InvalidObjectName

Mean response time (ms) in the last second for this node, for each of the specified PerPoolNodes.

getPerPoolNodeResponseMin(per_pool_nodes) throws InvalidInput, InvalidObjectName

Minimum response time (ms) in the last second for this node, for each of the specified PerPoolNodes.

getPerPoolNodeState(per_pool_nodes) throws InvalidInput, InvalidObjectName

The state of this node, for each of the specified PerPoolNodes.

getPerPoolNodeTotalConn(per_pool_nodes) throws InvalidInput, InvalidObjectName

Requests sent to this node, for each of the specified PerPoolNodes.

getPerPoolNodes()

Retrieves the list of available PerPoolNodes.

```
System.Stats.PerPoolNode[] getPerPoolNodes()
```

getPoolAlgorithm(names) throws InvalidInput, InvalidObjectName

The load-balancing algorithm the pool uses, for each of the named Pools.

```
System.Stats.PoolAlgorithm[] getPoolAlgorithm(
    String[] names
)
```

getPoolBytesIn(names) throws InvalidInput, InvalidObjectName

Bytes received by this pool from nodes, for each of the named Pools.

```
Long[] getPoolBytesIn(
    String[] names
)
```

getPoolBytesOut(names) throws InvalidInput, InvalidObjectName

Bytes sent by this pool to nodes, for each of the named Pools.

```
Long[] getPoolBytesOut(
    String[] names
)
```

getPoolConnsQueued(names)

Total connections currently queued to this pool, for each of the named Pools.

```
Integer[] getPoolConnsQueued(
    String[] names
)
```

getPoolDisabled(names) throws InvalidInput, InvalidObjectName

The number of nodes in this pool that are disabled, for each of the named Pools.

```
Integer[] getPoolDisabled(
    String[] names
)
```

getPoolDraining(names) throws InvalidInput, InvalidObjectName

The number of nodes in this pool which are draining, for each of the named Pools.

```
Integer[] getPoolDraining(
    String[] names
)
```

getPoolMaxQueueTime(names)

Maximum time a connection was queued for, over the last second, for each of the named Pools.

```
Integer[] getPoolMaxQueueTime(
    String[] names
)
```

getPoolMeanQueueTime(names)

Mean time a connection was queued for, over the last second, for each of the named Pools.

```
Integer[] getPoolMeanQueueTime(
    String[] names
```

getPoolMinQueueTime(names)

Minimum time a connection was queued for, over the last second, for each of the named Pools.

```
Integer[] getPoolMinQueueTime(
    String[] names
)
```

getPoolNodes(names) throws InvalidInput, InvalidObjectName

The number of nodes registered with this pool, for each of the named Pools.

```
Integer[] getPoolNodes(
    String[] names
)
```

getPoolNumber()

The number of pools on this system.

```
Integer getPoolNumber()
```

getPoolPersistence(names) throws InvalidInput, InvalidObjectName

The session persistence method this pool uses, for each of the named Pools.

```
System.Stats.PoolPersistence[] getPoolPersistence(
    String[] names
)
```

getPoolQueueTimeouts(names)

Total connections that timed-out while queued, for each of the named Pools.

```
Integer[] getPoolQueueTimeouts(
    String[] names
)
```

getPoolSessionMigrated(names) throws InvalidInput, InvalidObjectName

Sessions migrated to a new node because the desired node was unavailable, for each of the named Pools.

```
Integer[] getPoolSessionMigrated(
    String[] names
)
```

getPoolState(names) throws InvalidInput, InvalidObjectName

The state of this pool, for each of the named Pools.

```
System.Stats.PoolState[] getPoolState(
    String[] names
)
```

getPoolTotalConn(names) throws InvalidInput, InvalidObjectName

Requests sent to this pool, for each of the named Pools.

```
Integer[] getPoolTotalConn(
    String[] names
)
```

getPools()

Gets the list of Pools configured.

```
String[] getPools()
```

getRateClassConnsEntered(names) throws InvalidInput, InvalidObjectName

Connections that have entered the rate class and have been queued, for each of the named RateClasses.

```
Integer[] getRateClassConnsEntered(
    String[] names
)
```

getRateClassConnsLeft(names) throws InvalidInput, InvalidObjectName

Connections that have left the rate class, for each of the named RateClasses.

```
Integer[] getRateClassConnsLeft(
    String[] names
)
```

getRateClassCurrentRate(names) throws InvalidInput, InvalidObjectName

The average rate that requests are passing through this rate class, for each of the named RateClasses.

```
Integer[] getRateClassCurrentRate(
    String[] names
)
```

getRateClassDropped(names) throws InvalidInput, InvalidObjectName

Requests dropped from this rate class without being processed (e.g. timeouts), for each of the named RateClasses.

```
Integer[] getRateClassDropped(
    String[] names
)
```

getRateClassMaxRatePerMin(names) throws InvalidInput, InvalidObjectName

The maximum rate that requests may pass through this rate class (requests/min), for each of the named RateClasses.

```
Integer[] getRateClassMaxRatePerMin(
    String[] names
)
```

getRateClassMaxRatePerSec(names) throws InvalidInput, InvalidObjectName

The maximum rate that requests may pass through this rate class (requests/sec), for each of the named RateClasses.

```
Integer[] getRateClassMaxRatePerSec(
    String[] names
)
```

getRateClassNumber()

The number of rate classes defined.

```
Integer getRateClassNumber()
```

getRateClassQueueLength(names) throws InvalidInput, InvalidObjectName

The current number of requests queued by this rate class, for each of the named RateClasses.

```
Integer[] getRateClassQueueLength(
    String[] names
)
```

getRateClasses()

Gets the list of Rate Classes configured.

```
String[] getRateClasses()
```

getRuleAborts(names) throws InvalidInput, InvalidObjectName

Number of times this TrafficScript rule has aborted, for each of the named Rules.

```
Integer[] getRuleAborts(
    String[] names
)
```

getRuleDiscards(names) throws InvalidInput, InvalidObjectName

Number of times this TrafficScript rule has discarded the connection, for each of the named Rules.

```
Integer[] getRuleDiscards(
    String[] names
)
```

getRuleExecutions(names) throws InvalidInput, InvalidObjectName

Number of times this TrafficScript rule has been executed, for each of the named Rules.

```
Integer[] getRuleExecutions(
    String[] names
)
```

getRuleNumber()

The number of TrafficScript rules.

```
Integer getRuleNumber()
```

getRulePoolSelect(names) throws InvalidInput, InvalidObjectName

Number of times this TrafficScript rule has selected a pool to use, for each of the named Rules.

```
Integer[] getRulePoolSelect(
    String[] names
)
```

getRuleResponds(names) throws InvalidInput, InvalidObjectName

Number of times this TrafficScript rule has responded directly to the client, for each of the named Rules.

```
Integer[] getRuleResponds(
    String[] names
)
```

getRuleRetries(names) throws InvalidInput, InvalidObjectName

Number of times this TrafficScript rule has forced the request to be retried, for each of the named Rules.

```
Integer[] getRuleRetries(
```

```
String[] names
)
```

getRules()

Gets the list of Rules configured.

```
String[] getRules()
```

getServiceLevelConforming(names) throws InvalidInput, InvalidObjectName

Percentage of requests associated with this SLM class that are conforming, for each of the named ServiceLevels.

```
Integer[] getServiceLevelConforming(
    String[] names
)
```

getServiceLevelCurrentConns(names) throws InvalidInput, InvalidObjectName

The number of connections currently associated with this SLM class, for each of the named ServiceLevels.

```
Integer[] getServiceLevelCurrentConns(
    String[] names
)
```

getServiceLevellsOK(names) throws InvalidInput, InvalidObjectName

Indicates if this SLM class is currently conforming, for each of the named ServiceLevels.

```
System.Stats.ServiceLevelIsOK[] getServiceLevelIsOK(
    String[] names
)
```

getServiceLevelNumber()

The number of SLM classes defined.

```
Integer getServiceLevelNumber()
```

getServiceLevelResponseMax(names) throws InvalidInput, InvalidObjectName

Maximum response time (ms) in the last second for this SLM class, for each of the named ServiceLevels.

```
Integer[] getServiceLevelResponseMax(
    String[] names
)
```

getServiceLevelResponseMean(names) throws InvalidInput, InvalidObjectName

Mean response time (ms) in the last second for this SLM class, for each of the named ServiceLevels.

```
Integer[] getServiceLevelResponseMean(
    String[] names
)
```

getServiceLevelResponseMin(names) throws InvalidInput, InvalidObjectName

Minimum response time (ms) in the last second for this SLM class, for each of the named ServiceLevels.

```
Integer[] getServiceLevelResponseMin(
    String[] names
)
```

getServiceLevelTotalConn(names) throws InvalidInput, InvalidObjectName

Requests handled by this SLM class, for each of the named ServiceLevels.

```
Integer[] getServiceLevelTotalConn(
    String[] names
)
```

getServiceLevelTotalNonConf(names) throws InvalidInput, InvalidObjectName

Non-conforming requests handled by this SLM class, for each of the named ServiceLevels.

```
Integer[] getServiceLevelTotalNonConf(
    String[] names
)
```

getServiceLevels()

Gets the list of Service Level Monitoring classes configured.

```
String[] getServiceLevels()
```

getServiceProtLastRefusalTime(names) throws InvalidInput, InvalidObjectName

The time (in hundredths of a second) since this service protection class last refused a connection (this value will wrap if no connections are refused in more than 497 days), for each of the named ServiceProts.

```
Integer[] getServiceProtLastRefusalTime(
    String[] names
)
```

getServiceProtNumber()

The number of service protection classes defined.

```
Integer getServiceProtNumber()
```

getServiceProtRefusalBinary(names) throws InvalidInput, InvalidObjectName

Connections refused by this service protection class because the request contained disallowed binary content, for each of the named ServiceProts.

```
Integer[] getServiceProtRefusalBinary(
    String[] names
)
```

getServiceProtRefusalConc10IP(names) throws InvalidInput, InvalidObjectName

Connections refused by this service protection class because the top 10 source IP addresses issued too many concurrent connections, for each of the named ServiceProts.

```
Integer[] getServiceProtRefusalConc10IP(
    String[] names
```

getServiceProtRefusalConc1IP(names) throws InvalidInput, InvalidObjectName

Connections refused by this service protection class because the source IP address issued too many concurrent connections, for each of the named ServiceProts.

```
Integer[] getServiceProtRefusalConc1IP(
    String[] names
)
```

getServiceProtRefusalConnRate(names) throws InvalidInput, InvalidObjectName

Connections refused by this service protection class because the source IP address issued too many connections within 60 seconds, for each of the named ServiceProts.

```
Integer[] getServiceProtRefusalConnRate(
    String[] names
)
```

getServiceProtRefusallP(names) throws InvalidInput, InvalidObjectName

Connections refused by this service protection class because the source IP address was banned, for each of the named ServiceProts.

```
Integer[] getServiceProtRefusalIP(
    String[] names
)
```

getServiceProtRefusalRFC2396(names) throws InvalidInput, InvalidObjectName

Connections refused by this service protection class because the HTTP request was not RFC 2396 compliant, for each of the named ServiceProts.

```
Integer[] getServiceProtRefusalRFC2396(
    String[] names
)
```

getServiceProtRefusalSize(names) throws InvalidInput, InvalidObjectName

Connections refused by this service protection class because the request was larger than the defined limits allowed, for each of the named ServiceProts.

```
Integer[] getServiceProtRefusalSize(
```

```
String[] names
)
```

getServiceProtTotalRefusal(names) throws InvalidInput, InvalidObjectName

Connections refused by this service protection class, for each of the named ServiceProts.

```
Integer[] getServiceProtTotalRefusal(
    String[] names
)
```

getServiceProts()

Gets the list of Service Protection Classes configured.

```
String[] getServiceProts()
```

getSslCacheEntries()

The total number of SSL sessions stored in the server cache.

```
Integer getSslCacheEntries()
```

getSslCacheEntriesMax()

The maximum number of SSL entries in the server cache.

```
Integer getSslCacheEntriesMax()
```

getSslCacheHitRate()

The percentage of SSL server cache lookups that succeeded.

```
Integer getSslCacheHitRate()
```

getSslCacheHits()

Number of times a SSL entry has been successfully found in the server cache.

```
Integer getSslCacheHits()
```

getSslCacheLookups()

Number of times a SSL entry has been looked up in the server cache.

```
Integer getSslCacheLookups()
```

getSslCacheMisses()

Number of times a SSL entry has not been available in the server cache.

Integer getSslCacheMisses()

getSslCacheOldest()

The age of the oldest SSL session in the server cache (in seconds).

Integer getSslCacheOldest()

getSslCipher3DESDecrypts()

Bytes decrypted with 3DES.

Integer getSslCipher3DESDecrypts()

getSslCipher3DESEncrypts()

Bytes encrypted with 3DES.

Integer getSslCipher3DESEncrypts()

getSslCipherAESDecrypts()

Bytes decrypted with AES.

Integer getSslCipherAESDecrypts()

getSslCipherAESEncrypts()

Bytes encrypted with AES.

Integer getSslCipherAESEncrypts()

getSslCipherDESDecrypts()

Bytes decrypted with DES.

Integer getSslCipherDESDecrypts()

getSslCipherDESEncrypts()

Bytes encrypted with DES.

Integer getSslCipherDESEncrypts()

getSslCipherDecrypts()

Bytes decrypted with a symmetric cipher.

Integer getSslCipherDecrypts()

getSslCipherEncrypts()

Bytes encrypted with a symmetric cipher.

Integer getSslCipherEncrypts()

getSslCipherRC4Decrypts()

Bytes decrypted with RC4.

Integer getSslCipherRC4Decrypts()

getSslCipherRC4Encrypts()

Bytes encrypted with RC4.

Integer getSslCipherRC4Encrypts()

getSslCipherRSADecrypts()

Number of RSA decrypts.

Integer getSslCipherRSADecrypts()

getSslCipherRSADecryptsExternal()

Number of external RSA decrypts.

Integer getSslCipherRSADecryptsExternal()

getSslCipherRSAEncrypts()

Number of RSA encrypts.

Integer getSslCipherRSAEncrypts()

getSslCipherRSAEncryptsExternal()

Number of external RSA encrypts.

Integer getSslCipherRSAEncryptsExternal()

getSslClientCertExpired()

Number of times a client certificate has expired.

Integer getSslClientCertExpired()

getSslClientCertInvalid()

Number of times a client certificate was invalid.

Integer getSslClientCertInvalid()

getSslClientCertNotSent()

Number of times a client certificate was required but not supplied.

Integer getSslClientCertNotSent()

getSslClientCertRevoked()

Number of times a client certificate was revoked.

Integer getSslClientCertRevoked()

getSsIConnections()

Number of SSL connections negotiated.

Integer getSslConnections()

getSslHandshakeSSLv2()

Number of SSLv2 handshakes.

Integer getSslHandshakeSSLv2()

getSsIHandshakeSSLv3()

Number of SSLv3 handshakes.

Integer getSslHandshakeSSLv3()

getSslHandshakeTLSv1()

Number of TLSv1.0 handshakes.

Integer getSslHandshakeTLSv1()

getSslHandshakeTLSv11()

Number of TLSv1.1 handshakes.

Integer getSslHandshakeTLSv11()

getSsISessionCacheEntries()

The total number of SSL session persistence entries stored in the cache.

Integer getSslSessionCacheEntries()

getSsISessionCacheEntriesMax()

The maximum number of SSL session persistence entries in the cache.

Integer getSslSessionCacheEntriesMax()

getSsISessionCacheHitRate()

The percentage of SSL session persistence lookups that succeeded.

Integer getSslSessionCacheHitRate()

getSslSessionCacheHits()

Number of times a SSL session persistence entry has been successfully found in the cache.

Integer getSslSessionCacheHits()

getSslSessionCacheLookups()

Number of times a SSL session persistence entry has been looked up in the cache.

Integer getSslSessionCacheLookups()

getSslSessionCacheMisses()

Number of times a SSL session persistence entry has not been available in the cache.

Integer getSslSessionCacheMisses()

getSslSessionCacheOldest()

The age of the oldest SSL session in the cache (in seconds).

Integer getSslSessionCacheOldest()

getSslSessionIDDiskCacheHit()

Number of times the SSL session id was found in the disk cache and reused (deprecated, will always return 0).

```
Integer getSslSessionIDDiskCacheHit()
```

getSslSessionIDDiskCacheMiss()

Number of times the SSL session id was not found in the disk cache (deprecated, will always return 0).

```
Integer getSslSessionIDDiskCacheMiss()
```

getSslSessionIDMemCacheHit()

Number of times the SSL session id was found in the cache and reused.

```
Integer getSslSessionIDMemCacheHit()
```

getSslSessionIDMemCacheMiss()

Number of times the SSL session id was not found in the cache.

```
Integer getSslSessionIDMemCacheMiss()
```

getSteelheadNumber()

The number of Steelheads.

```
Integer getSteelheadNumber()
```

getSteelheadOptimized(names) throws InvalidInput, InvalidObjectName

The current number of connections being forwarded to the Cloud Steelhead for optimization, for each of the named Steelheads.

```
Integer[] getSteelheadOptimized(
    String[] names
)
```

getSteelheads()

Gets the list of Cloud Steelheads configured.

```
String[] getSteelheads()
```

getSysCPUBusyPercent()

Percentage of time that the CPUs are busy.

Integer getSysCPUBusyPercent()

getSysCPUIdlePercent()

Percentage of time that the CPUs are idle.

Integer getSysCPUIdlePercent()

getSysCPUSystemBusyPercent()

Percentage of time that the CPUs are busy running system code.

Integer getSysCPUSystemBusyPercent()

getSysCPUUserBusyPercent()

Percentage of time that the CPUs are busy running user-space code.

Integer getSysCPUUserBusyPercent()

getSysFDsFree()

Number of free file descriptors.

Integer getSysFDsFree()

getSysMemBuffered()

Buffer memory (MBytes).

Integer getSysMemBuffered()

getSysMemFree()

Free memory (MBytes).

Integer getSysMemFree()

getSysMemInUse()

Memory used (MBytes).

Integer getSysMemInUse()

getSysMemSwapTotal()

Total swap space (MBytes).

Integer getSysMemSwapTotal()

getSysMemSwapped()

Amount of swap space in use (MBytes).

Integer getSysMemSwapped()

getSysMemTotal()

Total memory (MBytes).

Integer getSysMemTotal()

getTimeLastConfigUpdate()

The time (in hundredths of a second) since the configuration of traffic manager was updated (this value will wrap if no configuration changes are made for 497 days).

Integer getTimeLastConfigUpdate()

getTotalBackendServerErrors()

Total errors returned from the backend servers.

Integer getTotalBackendServerErrors()

getTotalBadDNSPackets()

Total number of malformed DNS response packets encountered from the backend servers.

Integer getTotalBadDNSPackets()

getTotalBytesIn()

Bytes received by the traffic manager from clients.

Long getTotalBytesIn()

getTotalBytesOut()

Bytes sent by the traffic manager to clients.

Long getTotalBytesOut()

getTotalConn()

Total number of TCP connections received.

Integer getTotalConn()

getTotalCurrentConn()

Number of TCP connections currently established.

Integer getTotalCurrentConn()

getTotalDNSResponses()

Total number of DNS response packets handled.

Integer getTotalDNSResponses()

getTotalRequests()

Total number of TCP requests recieved.

Integer getTotalRequests()

getTotalTransactions()

Total number of TCP requests being processed, after applying TPS limits.

Integer getTotalTransactions()

getTrafficIPARPMessage()

Number of ARP messages sent for raised Traffic IP Addresses.

Integer getTrafficIPARPMessage()

getTrafficIPGatewayPingRequests()

Number of ping requests sent to the gateway machine.

Integer getTrafficIPGatewayPingRequests()

getTrafficIPGatewayPingResponses()

Number of ping responses received from the gateway machine.

```
Integer getTrafficIPGatewayPingResponses()
```

getTrafficIPNodePingRequests()

Number of ping requests sent to the backend nodes.

```
Integer getTrafficIPNodePingRequests()
```

getTrafficIPNodePingResponses()

Number of ping responses received from the backend nodes.

```
Integer getTrafficIPNodePingResponses()
```

getTrafficIPNumber()

The number of traffic IP addresses on this system (includes IPv4 and IPv6 addresses).

```
Integer getTrafficIPNumber()
```

getTrafficIPNumberRaised()

The number of traffic IP addresses currently raised on this system (includes IPv4 and IPv6 addresses).

```
Integer getTrafficIPNumberRaised()
```

getTrafficIPPingResponseErrors()

Number of ping response errors.

```
Integer getTrafficIPPingResponseErrors()
```

getTrafficIPState(traffic_ip_addresses) throws InvalidInput, InvalidObjectName

Whether this traffic IP address is currently being hosted by this traffic manager, for each of the specified TrafficIPs.

```
System.Stats.TrafficIPState[] getTrafficIPState(
    String[] traffic_ip_addresses
)
```

getTrafficIPTime(traffic_ip_addresses) throws InvalidInput, InvalidObjectName

The time (in hundredths of a second) since trafficIPState last changed (this value will wrap if the state hasn't changed for 497 days), for each of the specified TrafficIPs.

```
Integer[] getTrafficIPTime(
    String[] traffic_ip_addresses
)
```

getTrafficIPs()

Gets the list of Traffic IP addresses configured.

```
String[] getTrafficIPs()
```

getUniSessionCacheEntries()

The total number of universal sessions stored in the cache.

```
Integer getUniSessionCacheEntries()
```

getUniSessionCacheEntriesMax()

The maximum number of universal sessions in the cache.

```
Integer getUniSessionCacheEntriesMax()
```

getUniSessionCacheHitRate()

The percentage of universal session lookups that succeeded.

```
Integer getUniSessionCacheHitRate()
```

getUniSessionCacheHits()

Number of times a universal session entry has been successfully found in the cache.

```
Integer getUniSessionCacheHits()
```

getUniSessionCacheLookups()

Number of times a universal session entry has been looked up in the cache.

```
Integer getUniSessionCacheLookups()
```

getUniSessionCacheMisses()

Number of times a universal session entry has not been available in the cache.

```
Integer getUniSessionCacheMisses()
```

getUniSessionCacheOldest()

The age of the oldest universal session in the cache (in seconds).

```
Integer getUniSessionCacheOldest()
```

getUpTime()

The time (in hundredths of a second) that Stingray software has been operational for (this value will wrap if it has been running for more than 497 days).

```
Integer getUpTime()
```

getUserCounter64Value(names) throws InvalidInput, InvalidObjectName

The value of the 64-bit user counter, for each of the named UserCounter64s.

```
Long[] getUserCounter64Value(
    String[] names
)
```

getUserCounter64s()

Gets the list of 64-bit User counters configured.

```
String[] getUserCounter64s()
```

getUserCounterNumber()

The number of user defined counters.

```
Integer getUserCounterNumber()
```

getUserCounterValue(names) throws InvalidInput, InvalidObjectName

The value of the user counter, for each of the named UserCounters.

```
Integer[] getUserCounterValue(
    String[] names
)
```

getUserCounters()

Gets the list of User counters configured.

```
String[] getUserCounters()
```

getVirtualserverBytesIn(names) throws InvalidInput, InvalidObjectName

Bytes received by this virtual server from clients, for each of the named Virtualservers.

```
Long[] getVirtualserverBytesIn(
    String[] names
)
```

getVirtualserverBytesOut(names) throws InvalidInput, InvalidObjectName

Bytes sent by this virtual server to clients, for each of the named Virtualservers.

```
Long[] getVirtualserverBytesOut(
    String[] names
)
```

getVirtualserverConnectTimedOut(names) throws InvalidInput, InvalidObjectName

Connections closed by this virtual server because the 'connect_timeout' interval was exceeded, for each of the named Virtualservers.

```
Integer[] getVirtualserverConnectTimedOut(
    String[] names
)
```

getVirtualserverConnectionErrors(names)

Number of transaction or protocol errors in this virtual server, for each of the named Virtualservers.

```
Integer[] getVirtualserverConnectionErrors(
    String[] names
)
```

getVirtualserverConnectionFailures(names)

Number of connection failures in this virtual server, for each of the named Virtualservers.

```
Integer[] getVirtualserverConnectionFailures(
    String[] names
)
```

getVirtualserverCurrentConn(names) throws InvalidInput, InvalidObjectName

TCP connections currently established to this virtual server, for each of the named Virtualservers.

```
Integer[] getVirtualserverCurrentConn(
    String[] names
)
```

getVirtualserverDataTimedOut(names) throws InvalidInput, InvalidObjectName

Connections closed by this virtual server because the 'timeout' interval was exceeded, for each of the named Virtualservers.

```
Integer[] getVirtualserverDataTimedOut(
    String[] names
)
```

getVirtualserverDirectReplies(names) throws InvalidInput, InvalidObjectName

Direct replies from this virtual server, without forwarding to a node, for each of the named Virtualservers.

```
Integer[] getVirtualserverDirectReplies(
    String[] names
)
```

getVirtualserverDiscard(names) throws InvalidInput, InvalidObjectName

Connections discarded by this virtual server, for each of the named Virtualservers.

```
Integer[] getVirtualserverDiscard(
    String[] names
```

getVirtualserverGzip(names) throws InvalidInput, InvalidObjectName

Responses which have been compressed by content compression, for each of the named Virtualservers.

```
Integer[] getVirtualserverGzip(
    String[] names
)
```

getVirtualserverGzipBytesSaved(names) throws InvalidInput, InvalidObjectName

Bytes of network traffic saved by content compression, for each of the named Virtualservers.

```
Long[] getVirtualserverGzipBytesSaved(
    String[] names
)
```

getVirtualserverHttpCacheHitRate(names) throws InvalidInput, InvalidObjectName

Percentage hit rate of the web cache for this virtual server, for each of the named Virtualservers.

```
Integer[] getVirtualserverHttpCacheHitRate(
    String[] names
)
```

getVirtualserverHttpCacheHits(names) throws InvalidInput, InvalidObjectName

HTTP responses sent directly from the web cache by this virtual server, for each of the named Virtualservers.

```
Integer[] getVirtualserverHttpCacheHits(
    String[] names
)
```

getVirtualserverHttpCacheLookups(names) throws InvalidInput, InvalidObjectName

HTTP requests that are looked up in the web cache by this virtual server, for each of the named Virtualservers.

```
Integer[] getVirtualserverHttpCacheLookups(
    String[] names
```

)

getVirtualserverHttpRewriteCookie(names) throws InvalidInput, InvalidObjectName

HTTP Set-Cookie headers, supplied by a node, that have been rewritten, for each of the named Virtualservers

```
Integer[] getVirtualserverHttpRewriteCookie(
    String[] names
)
```

getVirtualserverHttpRewriteLocation(names) throws InvalidInput, InvalidObjectName

HTTP Location headers, supplied by a node, that have been rewritten, for each of the named Virtualservers.

```
Integer[] getVirtualserverHttpRewriteLocation(
    String[] names
)
```

getVirtualserverKeepaliveTimedOut(names) throws InvalidInput, InvalidObjectName

Connections closed by this virtual server because the 'keepalive_timeout' interval was exceeded, for each of the named Virtualservers.

```
Integer[] getVirtualserverKeepaliveTimedOut(
    String[] names
)
```

getVirtualserverMaxConn(names) throws InvalidInput, InvalidObjectName

Maximum number of simultaneous TCP connections this virtual server has processed at any one time, for each of the named Virtualservers.

```
Integer[] getVirtualserverMaxConn(
    String[] names
)
```

getVirtualserverNumber()

The number of virtual servers.

```
Integer getVirtualserverNumber()
```

getVirtualserverPort(names) throws InvalidInput, InvalidObjectName

The port the virtual server listens on, for each of the named Virtualservers.

```
Integer[] getVirtualserverPort(
    String[] names
)
```

getVirtualserverProtocol(names) throws InvalidInput, InvalidObjectName

The protocol the virtual server is operating, for each of the named Virtualservers.

```
System.Stats.VirtualserverProtocol[]
getVirtualserverProtocol(
    String[] names
)
```

getVirtualserverSIPRejectedRequests(names) throws InvalidInput, InvalidObjectName

Number of SIP requests rejected due to them exceeding the maximum amount of memory allocated to the connection, for each of the named Virtualservers.

```
Integer[] getVirtualserverSIPRejectedRequests(
    String[] names
)
```

getVirtualserverSIPTotalCalls(names) throws InvalidInput, InvalidObjectName

Total number of SIP INVITE requests seen by this virtual server, for each of the named Virtualservers.

```
Integer[] getVirtualserverSIPTotalCalls(
    String[] names
)
```

getVirtualserverTotalConn(names) throws InvalidInput, InvalidObjectName

Requests received by this virtual server, for each of the named Virtualservers.

```
Integer[] getVirtualserverTotalConn(
    String[] names
)
```

getVirtualserverTotalDgram(names) throws InvalidInput, InvalidObjectName

UDP datagrams processed by this virtual server, for each of the named Virtualservers.

```
Integer[] getVirtualserverTotalDgram(
    String[] names
)
```

getVirtualserverUdpTimedOut(names) throws InvalidInput, InvalidObjectName

Connections closed by this virtual server because the 'udp_timeout' interval was exceeded, for each of the named Virtualservers.

```
Integer[] getVirtualserverUdpTimedOut(
    String[] names
)
```

getVirtualservers()

Gets the list of Virtual Servers configured and enabled.

```
String[] getVirtualservers()
```

getWebCacheEntries()

The number of items in the web cache.

```
Integer getWebCacheEntries()
```

getWebCacheHitRate()

The percentage of web cache lookups that succeeded.

```
Integer getWebCacheHitRate()
```

getWebCacheHits()

Number of times a page has been successfully found in the web cache.

```
Long getWebCacheHits()
```

getWebCacheLookups()

Number of times a page has been looked up in the web cache.

Long getWebCacheLookups()

getWebCacheMaxEntries()

The maximum number of items in the web cache.

Integer getWebCacheMaxEntries()

getWebCacheMemMaximum()

The maximum amount of memory the web cache can use in kilobytes.

Integer getWebCacheMemMaximum()

getWebCacheMemUsed()

Total memory used by the web cache in kilobytes.

Integer getWebCacheMemUsed()

getWebCacheMisses()

Number of times a page has not been found in the web cache.

Long getWebCacheMisses()

getWebCacheOldest()

The age of the oldest item in the web cache (in seconds).

Integer getWebCacheOldest()

getZxtmNumber()

The number of traffic managers in the cluster.

Integer getZxtmNumber()

Structures

System.Stats.Node

Represents a Node object.

```
struct System.Stats.Node {
    # The IPv4 or IPv6 address of this node.
    String Address;

# The port this node listens on.
    Integer Port;
}
```

System.Stats.PerLocationService

Represents a PerLocationService object.

```
struct System.Stats.PerLocationService {
    # The name of the location.
    String LocationName;

# The name of the GLB Service.
    String Name;
}
```

System.Stats.PerNodeServiceLevel

 $Represents\ a\ PerNode Service Level\ object.$

```
struct System.Stats.PerNodeServiceLevel {
    # The name of the SLM class.
    String SLMName;

# The IP address of this node.
    String NodeAddress;

# The port number of this node.
    Integer NodePort;
```

}

System.Stats.PerPoolNode

Represents a PerPoolNode object.

```
struct System.Stats.PerPoolNode {
    # The name of the pool that this node belongs to.
    String PoolName;

# The IPv4 or IPv6 address of this node.
    String NodeAddress;

# The port that this node listens on.
    Integer NodePort;
}
```

Enumerations

System.Stats.NodeState

```
enum System.Stats.NodeState {
   alive,
   dead,
   unknown
}
```

System.Stats.PerLocationServiceDraining

```
enum System.Stats.PerLocationServiceDraining {
   draining,
   active
```

System.Stats.PerLocationServiceFrontendState

```
enum System.Stats.PerLocationServiceFrontendState {
   alive,
   dead
}
```

System.Stats.PerLocationServiceMonitorState

```
enum System.Stats.PerLocationServiceMonitorState {
   alive,
   dead
}
```

System.Stats.PerLocationServiceState

```
enum System.Stats.PerLocationServiceState {
   alive,
   dead
}
```

System.Stats.PerPoolNodeState

```
enum System.Stats.PerPoolNodeState {
  alive,
  dead,
  unknown,
  draining
.
```

System.Stats.PoolAlgorithm

```
enum System.Stats.PoolAlgorithm {
   roundrobin,

   weightedRoundRobin,

   perceptive,

   leastConnections,

   fastestResponseTime,

   random,

   weightedLeastConnections
}
```

System.Stats.PoolPersistence

```
enum System.Stats.PoolPersistence {
   none,

   ip,

  rule,

  transparent,

  applicationCookie,

  xZeusBackend,

  ssl
}
```

System.Stats.PoolState

```
enum System.Stats.PoolState {
   active,

   disabled,

   draining,

   unused,

   unknown
}
```

System.Stats.ServiceLevellsOK

```
enum System.Stats.ServiceLevelIsOK {
   notok,
   ok
}
```

System.Stats.TrafficIPState

```
enum System.Stats.TrafficIPState {
   raised,
   lowered
}
```

System.Stats.VirtualserverProtocol

```
enum System.Stats.VirtualserverProtocol {
  http,
  https,
```

```
ftp,
imaps,
imapv2,
imapv3,
imapv4,
pop3,
pop3s,
smtp,
ldap,
ldaps,
telnet,
sslforwarding,
udpstreaming,
udp,
dns,
genericserverfirst,
```

System.Management Function Reference

```
genericclientfirst,

dnstcp,

sipudp,

siptcp,

rtsp
```

System.Management

URI: http://soap.zeus.com/zxtm/1.0/System/Management/

The System.Management interface provides methods to manage the traffic manager and the system, such as restarting the software.

Methods

rebootSystem()

Perform a system reboot.

void rebootSystem()

restartAFM() throws InvalidOperation, LicenseError

Restart the Stingray Application Firewall on all machines. Any connections currently using Stingray Application Firewall will be aborted.

```
void restartAFM()
```

restartJava()

Restart the Java Extension support. Any connections currently using a Java Extension will be aborted.

```
void restartJava()
```

restartTrafficManager()

Restarts the traffic manager software. Any connections currently being handled will be aborted.

Function Reference AFM

void restartTrafficManager()

shutdownSystem()

Perform a system shutdown.

void shutdownSystem()

AFM

URI: http://soap.zeus.com/zxtm/1.0/AFM/

The AFM interface allows management of the Stingray Application Firewall.

Methods

disable() throws InvalidOperation, LicenseError

Disables the Stingray Application Firewall on the traffic manager.

void disable()

enable() throws InvalidOperation, LicenseError

Enables the Stingray Application Firewall on the traffic manager.

void enable()

getAdminMasterPort() throws InvalidOperation

Get the Application Firewall XML Master port, this port is used on all IP addresses.

Unsigned Integer getAdminMasterPort()

getAdminServerPort() throws InvalidOperation

Get the Application Firewall Administration server port, this port is only open on localhost. For a change to this setting to take effect the Stingray administration server must be restarted on all cluster members.

Unsigned Integer getAdminServerPort()

getAdminSlavePort() throws InvalidOperation

Get the Application Firewall XML Slave port, this port is used on all IP addresses.

Unsigned Integer getAdminSlavePort()

AFM Function Reference

getClusterState()

Get state data for the Stingray Application Firewall across all machines in the cluster.

```
AFM.State[] getClusterState()
```

getDeciderBasePort() throws InvalidOperation

Get the Application Firewall base decider port. This port, plus one port per decider process above this port, will be used for the Application Firewall deciders. For example, if set to 8100 then ports 8100, 8101, and 8102 will be used.

```
Unsigned Integer getDeciderBasePort()
```

getInternalDeciderBasePort() throws InvalidOperation

Get the Application Firewall internal decider communication base port. The Application Firewall requires ports for internal communication, these ports are bound to localhost (127.0.0.1) only. This sets the base for these communication ports, when the Application Firewall is started it will start at this port and work its way up taking available ports until it has enough ports.

```
Unsigned Integer getInternalDeciderBasePort()
```

getNumberOfDeciders() throws InvalidOperation

Get the number of Application Firewall decider processes to run.

```
Unsigned Integer getNumberOfDeciders()
```

getVersion()

Get the version of the Stingray Application Firewall installed on the traffic manager. Returns an empty string if Stingray Application Firewall is not installed.

```
String getVersion()
```

setAdminMasterPort(value) throws InvalidOperation, InvalidInput

Set the Application Firewall XML Master port, this port is used on all IP addresses.

```
void setAdminMasterPort(
    Unsigned Integer value
)
```

Function Reference AFM

setAdminServerPort(value) throws InvalidOperation, InvalidInput

Set the Application Firewall Administration server port, this port is only open on localhost. For a change to this setting to take effect the Stingray administration server must be restarted on all cluster members.

```
void setAdminServerPort(
    Unsigned Integer value
)
```

setAdminSlavePort(value) throws InvalidOperation, InvalidInput

Set the Application Firewall XML Slave port, this port is used on all IP addresses.

```
void setAdminSlavePort(
    Unsigned Integer value
)
```

setDeciderBasePort(value) throws InvalidOperation, InvalidInput

Set the Application Firewall base decider port. This port, plus one port per decider process above this port, will be used for the Application Firewall deciders. For example, if set to 8100 then ports 8100, 8101, and 8102 will be used.

```
void setDeciderBasePort(
    Unsigned Integer value
)
```

setInternalDeciderBasePort(value) throws InvalidOperation, InvalidInput

Set the Application Firewall internal decider communication base port. The Application Firewall requires ports for internal communication, these ports are bound to localhost (127.0.0.1) only. This sets the base for these communication ports, when the Application Firewall is started it will start at this port and work its way up taking available ports until it has enough ports.

```
void setInternalDeciderBasePort(
    Unsigned Integer value
)
```

setNumberOfDeciders(value) throws InvalidOperation, InvalidInput

Set the number of Application Firewall decider processes to run.

```
void setNumberOfDeciders(
    Unsigned Integer value
```

AFM Function Reference

)

uninstall() throws InvalidOperation

Uninstalls the Stingray Application Firewall on the traffic manager.

```
void uninstall()
```

Structures

AFM.BasicStatus

Contains basic Stingray Application Firewall runtime status information.

```
struct AFM.BasicStatus {
    # Whether or not Stingray Application Firewall is
installed.
    String installed;

    # Whether or not Stingray Application Firewall is
running.
    String running;

# The version of Stingray Application Firewall
installed.
    String version;

# Whether or not the machine is clustered with the
local
    # Stingray Application Firewall.
    String clustered;
}
```

AFM.ClusterStatus

Contains a Stingray Application Firewall state message.

```
struct AFM.ClusterStatus {
    # Cluster member this status is for.
    String member;
```

Function Reference AFM

```
# Status of the cluster member.
String status;
}
```

AFM.State

Contains status information about a Stingray Application Firewall installation.

```
struct AFM.State {
   # Name of the machine this information is from.
   String machine;
   # Describes the basic runtime status of Stingray
Application
   # Firewall on a machine.
   AFM.BasicStatus basicstatus;
   # State messages from the Stingray Application
Firewall on the
   # machine.
  AFM.StateMessage[] messages;
   # Statuses for all Stingray Application Firewall
instances in
   # the cluster.
  AFM.ClusterStatus[] cluster;
   # Strings describing any general errors relating
to Stingray
   # Application Firewall.
   String[] errors;
}
```

AFM.StateMessage

Contains a Stingray Application Firewall state message.

```
struct AFM.StateMessage {
```

Location Function Reference

```
# State for this message, either OK or ERROR.
String state;

# Message describing the reason for the state.
String message;
}
```

Location

URI: http://soap.zeus.com/zxtm/1.0/Location/

The Location interface allows management of traffic manager locations. Using this interface, you can create, delete and rename Locations, and manage their configuration.

Methods

addLocation(locations, info) throws ObjectAlreadyExists, ObjectDoesNotExist, InvalidObjectName, InvalidInput, DeploymentError, LicenseError, InvalidOperation

Adds locations. Configuration for the new locations will be based on the specified locations

```
void addLocation(
    String[] locations
    Location.TypeInfo[] info
)
```

deleteLocation(locations) throws ObjectDoesNotExist, ObjectInUse, DeploymentError, LicenseError

Delete the named Location.

```
void deleteLocation(
    String[] locations
)
```

disable(location) throws InvalidInput, ObjectDoesNotExist, LicenseError

Disable support for configuration locations, setting all configuration values to those for the specified location.

```
void disable(
```

Function Reference Location

```
String location
```

enable() throws LicenseError, InvalidOperation

Enable support for configuration locations.

```
void enable()
```

getCoordinates(locations) throws ObjectDoesNotExist, LicenseError, InvalidOperation

Get the coordinates for the named locations.

```
Location.Coordinates[] getCoordinates(
    String[] locations
)
```

getLocations()

Get the names of all the configured locations.

```
String[] getLocations()
```

getNote(locations) throws ObjectDoesNotExist, LicenseError, InvalidOperation

Get the note for each of the named locations

```
String[] getNote(
    String[] locations
)
```

getTrafficManagerLocation(traffic_managers) throws ObjectDoesNotExist, LicenseError

Gets the location that the named traffic managers are in.

```
String[] getTrafficManagerLocation(
    String[] traffic_managers
)
```

Location Function Reference

getType(locations) throws ObjectDoesNotExist, LicenseError, InvalidOperation

Gets a location's type, either config or glb. GLB locations contain no traffic managers, and are only used for global load balancing.

```
String[] getType(
    String[] locations
)
```

renameLocation(locations, new_names) throws ObjectDoesNotExist, ObjectAlreadyExists, InvalidObjectName, DeploymentError, LicenseError

Rename the named Locations.

```
void renameLocation(
    String[] locations
    String[] new_names
)
```

setCoordinates (locations, coordinates) throws ObjectDoesNotExist, DeploymentError, LicenseError, InvalidOperation

Set the coordinates for the named locations. Coordinates are only needed for global load balancing.

```
void setCoordinates(
    String[] locations
    Location.Coordinates[] coordinates
)
```

setNote(locations, values) throws ObjectDoesNotExist, DeploymentError, LicenseError, InvalidOperation

Set the note for each of the named locations

```
void setNote(
    String[] locations
    String[] values
)
```

Function Reference Location

setTrafficManagerLocation(traffic_managers, locations) throws ObjectDoesNotExist, LicenseError, DeploymentError, InvalidOperation

Sets the location that the named traffic managers are in.

```
void setTrafficManagerLocation(
    String[] traffic_managers
    String[] locations
)
```

setType(locations, type_info) throws ObjectInUse, ObjectDoesNotExist, LicenseError, InvalidInput, InvalidOperation

Sets a location's type, either config or glb. GLB locations contain no traffic managers, and are only used for global load balancing.

```
void setType(
    String[] locations
    Location.TypeInfo[] type_info
)
```

Structures

Location.Coordinates

This structure contains the co-ordinates for a location.

```
# The longitude of the location.
Double longitude;

# The latitude of the location.
Double latitude;
}
```

Location. TypeInfo

This structure contains information required when adding a location.

```
struct Location.TypeInfo {
    # Location type, either config or glb. GLB
locations don't
```

Users Function Reference

```
# contain any traffic managers and are used for
global load

# balancing.
String type;

# If the location isn't of type GLB, this is the
location that

# the configuration will be be based on initially
String based_on;
}
```

Users

URI: http://soap.zeus.com/zxtm/1.0/Users/

The Users interface allows management of users of Stingray Traffic Manager. Using this interface, you can create and delete users, assign them to permission groups and manage their configuration.

Methods

addUser(user, password, group) throws ObjectAlreadyExists, ObjectDoesNotExist, InvalidInput

Add a new local user to Stingray Traffic Manager.

```
void addUser(
   String user
   String password
   String group
)
```

changePassword(user, newPassword) throws ObjectDoesNotExist, InvalidInput

Change password for a given user.

```
void changePassword(
    String user
    String newPassword
)
```

deleteUser(user) throws ObjectDoesNotExist, DeploymentError

Delete a local user from Stingray Traffic Manager.

```
void deleteUser(
    String user
)
```

listGroups()

List all groups of Stingray Traffic Manager.

```
String[] listGroups()
```

listUsers()

List all users of Stingray Traffic Manager.

```
String[] listUsers()
```

GLB.Service

URI: http://soap.zeus.com/zxtm/1.0/GLB/Service/

The GLB.Service interface allows management of Global Load Balancing Services. Using this interface, you can create, delete and rename pool objects, and manage their configuration.

Methods

addDNSSECMappings(names, mappings) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Add a set of DNSSEC domain to key mappings to the GLB services specified.

```
void addDNSSECMappings(
    String[] names
    GLB.Service.DNSSECMapping[][] mappings
)
```

addDomains(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

For each named GLB service, add new DNS domain names to the list of domains to load balance

```
void addDomains(
    String[] names
    String[][] values
)
```

addDraining(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Add the list of locations that are draining for this service.

```
void addDraining(
    String[] names
    String[][] values
)
```

addGLBService(names, domains) throws ObjectAlreadyExists, InvalidObjectName, DeploymentError, InvalidInput, LicenseError

Add each of the named GLB Services, using the domain lists for each.

```
void addGLBService(
    String[] names
    String[][] domains
)
```

addLocalIPAddresses(names, localips) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Add Local IPs to the named GLB Services

```
void addLocalIPAddresses(
    String[] names
    GLB.Service.LocalIPList[][] localips
)
```

addLocations(names, locations) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Add new locations to each of the named GLB services.

```
void addLocations(
```

```
String[] names
String[][] locations
)
```

addMonitors(names, monitors) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Add Monitors to the named GLB Services

```
void addMonitors(
    String[] names
    GLB.Service.MonitorList[][] monitors
)
```

addMonitorsByLocation(location, names, monitors) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Add Monitors to the named GLB Services This is a location specific function, any action will operate on the specified location.

```
void addMonitorsByLocation(
   String location
   String[] names
   GLB.Service.MonitorList[][] monitors
)
```

addRules(names, rules) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Add new rules to be run on DNS packets for each of the named GLB services. New rules are run after existing rules. If any of the rules are already configured to run, then they are enabled and flags are set to the values passed in.

```
void addRules(
    String[] names
    GLB.Service.Rule[][] rules
)
```

addRulesByLocation(location, names, rules) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Add new rules to be run on DNS packets for each of the named GLB services. New rules are run after existing rules. If any of the rules are already configured to run, then they are enabled and flags are set to the values passed in. This is a location specific function, any action will operate on the specified location.

```
void addRulesByLocation(
   String location
   String[] names
   GLB.Service.Rule[][] rules
)
```

deleteGLBService(names) throws ObjectDoesNotExist, DeploymentError

Delete each of the named GLB Services.

```
void deleteGLBService(
    String[] names
)
```

getAlgorithm(names) throws ObjectDoesNotExist, LicenseError

Get the load balancing algorithm to use.

```
GLB.Service.Algorithm[] getAlgorithm(
    String[] names
)
```

getAllMonitorsNeeded(names) throws ObjectDoesNotExist, LicenseError

Get whether all monitors are required to be working in a location for this service to be alive.

```
Boolean[] getAllMonitorsNeeded(
    String[] names
)
```

getAutoFailback(names) throws ObjectDoesNotExist, LicenseError

Get whether automatic failback mode is enabled.

```
Boolean[] getAutoFailback(
    String[] names
```

)

getDNSSECMappings(names) throws ObjectDoesNotExist, LicenseError

Get the load for the named GLB Services

```
GLB.Service.DNSSECMapping[][] getDNSSECMappings(
    String[] names
)
```

getDomains(names) throws ObjectDoesNotExist, LicenseError

Get the list of domain names to load balance, for each of the named GLB services

```
String[][] getDomains(
    String[] names
)
```

getDraining(names) throws ObjectDoesNotExist, LicenseError

Get the list of locations that are draining for this service.

```
String[][] getDraining(
    String[] names
)
```

getEnabled(names) throws ObjectDoesNotExist, LicenseError

Get whether we perform DNS manipulation.

```
Boolean[] getEnabled(
    String[] names
)
```

getGLBServiceNames()

Get the names of all of the configured GLB Services.

```
String[] getGLBServiceNames()
```

getGeoEffect(names) throws ObjectDoesNotExist, LicenseError

Get the influence of locality on location choice

```
Unsigned Integer[] getGeoEffect(
    String[] names
)
```

getLoad(names) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Get the load for the named GLB Services

```
GLB.Service.Load[][] getLoad(
    String[] names
)
```

getLocallPAddresses(names) throws ObjectDoesNotExist, LicenseError

Get the Local IPs configured for the named GLB Services

```
GLB.Service.LocalIPList[][] getLocalIPAddresses(
    String[] names
)
```

getLocations(names) throws ObjectDoesNotExist, LicenseError

Get the locations configured for the named GLB services.

```
String[][] getLocations(
    String[] names
)
```

getLogEnabled(names) throws ObjectDoesNotExist, LicenseError

Get whether each of the named GLB services should log each connection.

```
Boolean[] getLogEnabled(
    String[] names
)
```

getLogEnabledByLocation(location, names) throws ObjectDoesNotExist, LicenseError

Get whether each of the named GLB services should log each connection. This is a location specific function, any action will operate on the specified location.

```
Boolean[] getLogEnabledByLocation(
   String location
   String[] names
)
```

getLogFilename(names) throws ObjectDoesNotExist, LicenseError

Get the name of the file used to store query logs, for each of the named GLB services.

```
String[] getLogFilename(
    String[] names
)
```

getLogFilenameByLocation(location, names) throws ObjectDoesNotExist, LicenseError

Get the name of the file used to store query logs, for each of the named GLB services. This is a location specific function, any action will operate on the specified location.

```
String[] getLogFilenameByLocation(
   String location
   String[] names
)
```

getLogFormat(names) throws ObjectDoesNotExist, LicenseError

Get the log file format for each of the named GLB services.

```
String[] getLogFormat(
    String[] names
)
```

getLogFormatByLocation(location, names) throws ObjectDoesNotExist, LicenseError

Get the log file format for each of the named GLB services. This is a location specific function, any action will operate on the specified location.

```
String[] getLogFormatByLocation(
   String location
   String[] names
)
```

getMonitors(names) throws ObjectDoesNotExist, LicenseError

Get the Monitors configured for the named GLB Services

```
GLB.Service.MonitorList[][] getMonitors(
    String[] names
)
```

getMonitorsByLocation(location, names) throws ObjectDoesNotExist, LicenseError

Get the Monitors configured for the named GLB Services This is a location specific function, any action will operate on the specified location.

```
GLB.Service.MonitorList[][] getMonitorsByLocation(
    String location
    String[] names
```

getReturnIPsOnFail(names) throws ObjectDoesNotExist, LicenseError

Get whether to return all or no IP addresses on a complete failure

```
Boolean[] getReturnIPsOnFail(
    String[] names
)
```

getRules(names) throws ObjectDoesNotExist, LicenseError

Get the rules that are run on DNS packets for each of the named GLB services.

```
GLB.Service.Rule[][] getRules(
    String[] names
)
```

getRulesByLocation(location, names) throws ObjectDoesNotExist, LicenseError

Get the rules that are run on DNS packets for each of the named GLB services. This is a location specific function, any action will operate on the specified location.

```
GLB.Service.Rule[][] getRulesByLocation(
```

```
String location
String[] names
)
```

getTTL(names) throws ObjectDoesNotExist, LicenseError

Get the TTL used for domains handled by this config

```
Integer[] getTTL(
    String[] names
)
```

removeDNSSECMappings(names, mappings) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Remove the specified DNSSEC domain to key mappings.

```
void removeDNSSECMappings(
    String[] names
    GLB.Service.DNSSECMapping[][] mappings
)
```

removeDomains(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

For each named GLB service, remove DNS domain names from the list of domains to load balance

```
void removeDomains(
    String[] names
    String[][] values
)
```

removeDraining(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Remove the list of locations that are draining for this service.

```
void removeDraining(
    String[] names
    String[][] values
)
```

removeLocalIPAddresses(names, localips) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Remove Local IPs from the named GLB Services

```
void removeLocalIPAddresses(
    String[] names
    GLB.Service.LocalIPList[][] localips
)
```

removeLocations(names, locations) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

For each of the named GLB services, remove locations.

```
void removeLocations(
    String[] names
    String[][] locations
)
```

removeMonitors(names, monitors) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Remove Monitors from the named GLB Services

```
void removeMonitors(
    String[] names
    GLB.Service.MonitorList[][] monitors
)
```

removeMonitorsByLocation(location, names, monitors) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Remove Monitors from the named GLB Services This is a location specific function, any action will operate on the specified location.

```
void removeMonitorsByLocation(
   String location
   String[] names
   GLB.Service.MonitorList[][] monitors
)
```

removeRules(names, rules) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

For each of the named GLB services, remove rules from the list of rules that are run on DNS packets.

```
void removeRules(
    String[] names
    String[][] rules
)
```

removeRulesByLocation(location, names, rules) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

For each of the named GLB services, remove rules from the list of rules that are run on DNS packets. This is a location specific function, any action will operate on the specified location.

```
void removeRulesByLocation(
    String location
    String[] names
    String[][] rules
)
```

renameGLBService(names, new_names) throws ObjectDoesNotExist, InvalidInput, ObjectAlreadyExists, DeploymentError, LicenseError

Rename each of the named GLB Services.

```
void renameGLBService(
    String[] names
    String[] new_names
)
```

setAlgorithm(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the load balancing algorithm to use.

```
void setAlgorithm(
   String[] names
   GLB.Service.Algorithm[] values
)
```

setAllMonitorsNeeded(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set whether all monitors are required to be working in a location for this service to be alive.

```
void setAllMonitorsNeeded(
    String[] names
    Boolean[] values
)
```

setAutoFailback(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set whether automatic failback mode is enabled.

```
void setAutoFailback(
    String[] names
    Boolean[] values
)
```

setDNSSECMappings(names, mappings) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the DNSSEC domain to key mappings to the GLB services specified. All previous mappings for this service will be removed.

```
void setDNSSECMappings(
    String[] names
    GLB.Service.DNSSECMapping[][] mappings
)
```

setDomains(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the list of domain names to load balance, for each of the named GLB services

```
void setDomains(
   String[] names
   String[][] values
)
```

setDraining(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the list of locations that are draining for this service.

```
void setDraining(
   String[] names
   String[][] values
)
```

setEnabled(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set whether we perform DNS manipulation.

```
void setEnabled(
    String[] names
    Boolean[] values
)
```

setGeoEffect(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the influence of locality on location choice

```
void setGeoEffect(
    String[] names
    Unsigned Integer[] values
)
```

setLoad(names, loads) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the load for the named GLB Services

```
void setLoad(
   String[] names
   GLB.Service.Load[][] loads
)
```

setLocallPAddresses(names, localips) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the Local IPs configured for the named GLB Services

```
void setLocalIPAddresses(
    String[] names
    GLB.Service.LocalIPList[][] localips
)
```

setLocations(names, locations) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the locations configured for each of the named GLB services.

```
void setLocations(
    String[] names
    String[][] locations
)
```

setLogEnabled(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set whether each of the named GLB services should log each connection.

```
void setLogEnabled(
    String[] names
    Boolean[] values
)
```

setLogEnabledByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set whether each of the named GLB services should log each connection. This is a location specific function, any action will operate on the specified location.

```
void setLogEnabledByLocation(
   String location
   String[] names
   Boolean[] values
)
```

setLogFilename(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the name of the file used to store query logs, for each of the named GLB services.

```
void setLogFilename(
    String[] names
    String[] values
)
```

setLogFilenameByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the name of the file used to store query logs, for each of the named GLB services. This is a location specific function, any action will operate on the specified location.

```
void setLogFilenameByLocation(
   String location
   String[] names
   String[] values
)
```

setLogFormat(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the log file format for each of the named GLB services.

```
void setLogFormat(
    String[] names
    String[] values
)
```

setLogFormatByLocation(location, names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the log file format for each of the named GLB services. This is a location specific function, any action will operate on the specified location.

```
void setLogFormatByLocation(
    String location
    String[] names
    String[] values
```

)

setMonitors(names, monitors) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the Monitors configured for the named GLB Services

```
void setMonitors(
    String[] names
    GLB.Service.MonitorList[][] monitors
)
```

setMonitorsByLocation(location, names, monitors) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the Monitors configured for the named GLB Services This is a location specific function, any action will operate on the specified location.

```
void setMonitorsByLocation(
   String location
   String[] names
   GLB.Service.MonitorList[][] monitors
)
```

setReturnIPsOnFail(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set whether to return all or no IP addresses on a complete failure

```
void setReturnIPsOnFail(
    String[] names
    Boolean[] values
)
```

setRules(names, rules) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the rules that are run on DNS packets for each of the named GLB services.

```
void setRules(
   String[] names
   GLB.Service.Rule[][] rules
```

)

setRulesByLocation(location, names, rules) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the rules that are run on DNS packets for each of the named GLB services. This is a location specific function, any action will operate on the specified location.

```
void setRulesByLocation(
   String location
   String[] names
   GLB.Service.Rule[][] rules
)
```

setTTL(names, values) throws ObjectDoesNotExist, InvalidInput, DeploymentError, LicenseError

Set the TTL used for domains handled by this config

```
void setTTL(
    String[] names
    Integer[] values
)
```

Structures

GLB.Service.DNSSECMapping

This contains a mapping between DNS domains and DNSSEC keys used to alter signed responses.

```
struct GLB.Service.DNSSECMapping {
    # The domain of these keys sign.
    String domain;

# An array of DNSSEC key names.
    String[] keys;
}
```

GLB.Service.Load

This structure contains the load for a GLB location.

```
struct GLB.Service.Load {
    # The glb location.
    String location;

# The load metric at the corresponding location.
    Integer load;
}
```

GLB.Service.LocalIPList

This structure contains the list of IP addresses for a GLB location.

```
struct GLB.Service.LocalIPList {
    # The glb location.
    String location;

# The IP Addresses or IP Masks that are present at the
    # corresponding location.
    String[] addresses;
}
```

GLB.Service.MonitorList

This structure contains the list of monitors for a GLB location.

```
struct GLB.Service.MonitorList {
    # The glb location.
    String location;

# The monitors determining the health of the corresponding
    # location.
    String[] monitors;
}
```

GLB.Service.Rule

This structure contains the information on how a rule is assigned to a virtual server.

```
struct GLB.Service.Rule {
    # The name of the rule.
    String name;

# Whether the rule is enabled or not.
    Boolean enabled;
}
```

Enumerations

GLB.Service.Algorithm

```
enum GLB.Service.Algorithm {
    # Load
    load,

# Geographic
    geo,

# Adaptive
    hybrid,

# Round Robin
    roundrobin,

# Weighted Random
    weightedrandom,

# Active/Passive
    chained
}
```

System.CloudCredentials

URI: http://soap.zeus.com/zxtm/1.0/System/CloudCredentials/

The System.CloudCredentials interface allows management of Cloud Credentials. Using this interface, you can create, delete and rename sets of cloud credentials, and manage their configuration.

Methods

addCloudCredentials(class_names, class_values) throws ObjectAlreadyExists, InvalidInput

Add new sets of cloud credentials.

```
void addCloudCredentials(
    String[] class_names
    System.CloudCredentials.CredentialsData[]
class_values
)
```

copyCloudCredentials(class_names, new_names) throws ObjectAlreadyExists, ObjectDoesNotExist, InvalidObjectName, DeploymentError

Copy the named set of cloud credentials.

```
void copyCloudCredentials(
    String[] class_names
    String[] new_names
)
```

deleteCloudCredentials(class_names) throws ObjectDoesNotExist, DeploymentError

Delete the named sets of cloud credentials.

```
void deleteCloudCredentials(
    String[] class_names
)
```

getApiServer(class_names) throws ObjectDoesNotExist

Get the vcenter server hostname or IP address.

```
String[] getApiServer(
```

```
String[] class_names
)
```

getApiServerByLocation(location, class_names) throws ObjectDoesNotExist

Get the vcenter server hostname or IP address. This is a location specific function, any action will operate on the specified location.

```
String[] getApiServerByLocation(
    String location
    String[] class_names
)
```

getChangeProcessTimeout(class_names) throws ObjectDoesNotExist

Get the amount of time change calls are allowed to take

```
Unsigned Integer[] getChangeProcessTimeout(
    String[] class_names
)
```

getChangeProcessTimeoutByLocation(location, class_names) throws ObjectDoesNotExist

Get the amount of time change calls are allowed to take This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getChangeProcessTimeoutByLocation(
    String location
    String[] class_names
)
```

getCloudCredentialsNames()

Get the names of all the configured cloud credentials.

```
String[] getCloudCredentialsNames()
```

getCred1(class_names) throws ObjectDoesNotExist

Get the cloud user name

```
String[] getCred1(
```

```
String[] class_names
)
```

getCred1ByLocation(location, class_names) throws ObjectDoesNotExist

Get the cloud user name This is a location specific function, any action will operate on the specified location.

```
String[] getCred1ByLocation(
    String location
    String[] class_names
)
```

getScript(class_names) throws ObjectDoesNotExist

Get the script

```
String[] getScript(
    String[] class_names
)
```

getScriptByLocation(location, class_names) throws ObjectDoesNotExist

Get the script This is a location specific function, any action will operate on the specified location.

```
String[] getScriptByLocation(
    String location
    String[] class_names
)
```

getUpdateInterval(class_names) throws ObjectDoesNotExist

Get the interval at which cloud status is queried

```
Unsigned Integer[] getUpdateInterval(
    String[] class_names
)
```

getUpdateIntervalByLocation(location, class_names) throws ObjectDoesNotExist

Get the interval at which cloud status is queried This is a location specific function, any action will operate on the specified location.

```
Unsigned Integer[] getUpdateIntervalByLocation(
    String location
    String[] class_names
)
```

renameCloudCredentials(class_names, new_names) throws ObjectAlreadyExists, ObjectDoesNotExist, InvalidObjectName, DeploymentError

Rename the named sets of cloud credentials.

```
void renameCloudCredentials(
    String[] class_names
    String[] new_names
)
```

setApiServer(class_names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the vcenter server hostname or IP address.

```
void setApiServer(
    String[] class_names
    String[] values
)
```

setApiServerByLocation(location, class_names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the vcenter server hostname or IP address. This is a location specific function, any action will operate on the specified location.

```
void setApiServerByLocation(
    String location
    String[] class_names
    String[] values
)
```

setChangeProcessTimeout(class_names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the amount of time change calls are allowed to take

```
void setChangeProcessTimeout(
    String[] class_names
    Unsigned Integer[] values
)
```

setChangeProcessTimeoutByLocation(location, class_names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the amount of time change calls are allowed to take This is a location specific function, any action will operate on the specified location.

```
void setChangeProcessTimeoutByLocation(
   String location
   String[] class_names
   Unsigned Integer[] values
)
```

setCred1(class_names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the cloud user name

```
void setCred1(
    String[] class_names
    String[] values
)
```

setCred1ByLocation(location, class_names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the cloud user name This is a location specific function, any action will operate on the specified location.

```
void setCred1ByLocation(
    String location
    String[] class names
```

```
String[] values
)
```

setCred2(class_names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the cloud user password

```
void setCred2(
    String[] class_names
    String[] values
)
```

setCred2ByLocation(location, class_names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the cloud user password This is a location specific function, any action will operate on the specified location.

```
void setCred2ByLocation(
   String location
   String[] class_names
   String[] values
)
```

setCred3(class_names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the cloud user authentication token

```
void setCred3(
    String[] class_names
    String[] values
)
```

setCred3ByLocation(location, class_names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the cloud user authentication token This is a location specific function, any action will operate on the specified location.

```
void setCred3ByLocation(
```

```
String location

String[] class_names

String[] values
```

setScript(class_names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the script

```
void setScript(
    String[] class_names
    String[] values
)
```

setScriptByLocation(location, class_names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the script This is a location specific function, any action will operate on the specified location.

```
void setScriptByLocation(
   String location
   String[] class_names
   String[] values
)
```

setUpdateInterval(class_names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the interval at which cloud status is queried

```
void setUpdateInterval(
    String[] class_names
    Unsigned Integer[] values
)
```

setUpdateIntervalByLocation(location, class_names, values) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the interval at which cloud status is queried This is a location specific function, any action will operate on the specified location.

Function Reference System. Steelhead

```
void setUpdateIntervalByLocation(
   String location
   String[] class_names
   Unsigned Integer[] values
)
```

Structures

System.CloudCredentials.CredentialsData

This structure contains the information needed to create CloudCredentials

```
struct System.CloudCredentials.CredentialsData {
    # The user name (mandatory)
    String cred1;

# The password (mandatory)
    String cred2;

# The authorization token (can be empty)
    String cred3;

# The script to use for API calls (mandatory)
    String script;

# Time period to wait between status API calls in seconds
    Integer update_interval;
}
```

System.Steelhead

URI: http://soap.zeus.com/zxtm/1.0/System/Steelhead/

The System. Steelhead interface manages Riverbed Discovery Agent settings.

System.Steelhead Function Reference

Methods

getDiscoveryMode(traffic_managers) throws InvalidInput, ObjectDoesNotExist

Returns the mode used to discover Cloud Steelheads in the local data center or cloud for the supplied traffic managers.

```
System.Steelhead.DiscoveryMode[] getDiscoveryMode(
    String[] traffic_managers
)
```

getEnabled(traffic_managers) throws InvalidInput, ObjectDoesNotExist

Returns true if the Cloud Steelhead discovery agents on the provided traffic managers are enabled.

```
Boolean[] getEnabled(
    String[] traffic_managers
)
```

getLoadBalancingMethod(traffic_managers) throws InvalidInput, ObjectDoesNotExist

Returns the current load balancing method that each of the named traffic managers are using. Only required when using 'manual' mode.

```
System.Steelhead.SteelheadLB[]
getLoadBalancingMethod(
         String[] traffic_managers
)
```

getLogLevel(traffic_managers) throws InvalidInput, ObjectDoesNotExist

Returns the level of logging used on each of the named traffic managers.

```
System.Steelhead.LogLevel[] getLogLevel(
    String[] traffic_managers
)
```

getPortalClientID(traffic_managers) throws InvalidInput, ObjectDoesNotExist

Returns the string used to identify the supplied traffic managers to the cloud portal. Only required in 'portal' and 'local' discovery modes.

```
String[] getPortalClientID(
```

Function Reference System. Steelhead

```
String[] traffic_managers
)
```

getPortalClientKey(traffic_managers) throws InvalidInput, ObjectDoesNotExist

Returns the key used to authenticate the supplied traffic managers to the cloud portal. Only required in 'portal' and 'local' discovery modes.

```
String[] getPortalClientKey(
    String[] traffic_managers
)
```

getPortalHost(traffic_managers) throws InvalidInput, ObjectDoesNotExist

Returns the hostname or IP address of the cloud portal to use. Only required when using the 'local' discovery mode.

```
String[] getPortalHost(
    String[] traffic_managers
)
```

getProxyHost(traffic_managers) throws InvalidInput, ObjectDoesNotExist

Returns the hostname or IP address of the proxy that portal communication should go through, or the empty string if no proxy should be used. Configured per traffic manager.

```
String[] getProxyHost(
    String[] traffic_managers
)
```

getProxyPort(traffic_managers) throws InvalidInput, ObjectDoesNotExist

Gets the current proxy server port for each of the named traffic managers. Only used if a proxy host has been specified.

```
String[] getProxyPort(
    String[] traffic_managers
)
```

System.Steelhead Function Reference

getSteelheadIPs(traffic_managers) throws InvalidInput, ObjectDoesNotExist

Gets an array of Cloud Steelhead IP addresses that each of the named traffic managers is using. Only required when using the 'manual' discovery mode.

```
String[][] getSteelheadIPs(
    String[] traffic_managers
)
```

setDiscoveryMode(traffic_managers, modes) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Sets the mode used to discover Cloud Steelheads in the local data center or cloud for the supplied traffic managers.

```
void setDiscoveryMode(
    String[] traffic_managers
    System.Steelhead.DiscoveryMode[] modes
)
```

setEnabled(traffic_managers, enabled) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Enable or disable the Cloud Steelhead discovery agent on each of the provided traffic managers

```
void setEnabled(
    String[] traffic_managers
    Boolean[] enabled
)
```

setLoadBalancingMethod(traffic_managers, lbs) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Sets the load balancing method that each of the named traffic managers should use. Only required when using 'manual' mode.

```
void setLoadBalancingMethod(
    String[] traffic_managers
    System.Steelhead.SteelheadLB[] lbs
)
```

Function Reference System. Steelhead

setLogLevel(traffic_managers, levels) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Sets the level of logging used on each of the named traffic managers.

```
void setLogLevel(
    String[] traffic_managers
    System.Steelhead.LogLevel[] levels
)
```

setPortalClientID(traffic_managers, ids) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Sets the string used to identify the supplied traffic managers to the cloud portal. Only required in 'portal' and 'local' discovery modes.

```
void setPortalClientID(
    String[] traffic_managers
    String[] ids
)
```

setPortalClientKey(traffic_managers, keys) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Sets the key used to authenticate the supplied traffic managers to the cloud portal. Only required in 'portal' and 'local' discovery modes.

```
void setPortalClientKey(
    String[] traffic_managers
    String[] keys
)
```

setPortalHost(traffic_managers, hosts) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Sets the hostname or IP address of the cloud portal to use. Only required when using the 'local' discovery mode.

```
void setPortalHost(
    String[] traffic_managers
    String[] hosts
)
```

System.Steelhead Function Reference

setProxyHost(traffic_managers, hosts) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Set the hostname or IP address of the proxy that portal communication should go through. Set to the empty string to not use a proxy. Configured per traffic manager.

```
void setProxyHost(
    String[] traffic_managers
    String[] hosts
)
```

setProxyPort(traffic_managers, ports) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Sets the current proxy server port for each of the named traffic managers. Only used if a proxy host has been specified, can be set to the empty string otherwise.

```
void setProxyPort(
    String[] traffic_managers
    String[] ports
)
```

setSteelheadIPs(traffic_managers, ips) throws InvalidInput, ObjectDoesNotExist, DeploymentError

Sets an array of Cloud Steelhead IP addresses that each of the named traffic managers should use. Only required when using the 'manual' discovery mode.

```
void setSteelheadIPs(
    String[] traffic_managers
    String[][] ips
)
```

Enumerations

System.Steelhead.DiscoveryMode

The different modes for discovering Cloud Steelheads to forward optimized traffic to.

```
enum System.Steelhead.DiscoveryMode {
    # Use the standard Riverbed cloud portal to manage
your Cloud
    # Steelheads and connected servers.
```

Function Reference System. Steelhead

```
# Use a different portal to manager your Cloud
Steelheads.
local,

# Manually specify each Cloud Steelhead by IP
address.
manual
}
```

System.Steelhead.LogLevel

The different modes for discovering Cloud Steelheads to forward optimized traffic to.

```
enum System.Steelhead.LogLevel {
   # Only show critical errors
   critial,
   # Only show errors or higher
   serious,
   # Only show warnings or higher
   warning,
   # Only show notices or higher
   notice,
   # Only show info messages or higher
   info,
   # Show debug messages or higher. This is extremely
verbose and
   # should only be used for short periods.
   debug
}
```

SOAP Faults Function Reference

System.Steelhead.SteelheadLB

The different modes for discovering Cloud Steelheads to forward optimized traffic to.

```
enum System.Steelhead.SteelheadLB {
    # Use each Cloud Steelhead in turn.
    round_robin,

    # Use the last Cloud Steelhead in the list that is working
    # correctly. Cascades down the list if Cloud Steelheads fail.
    priority
}
```

SOAP Faults

When a function encounters an error it will emit a fault. Depending on the fault that occurred the fault structure will contain more information related to the fault. The documentation for individual functions lists the different types of faults that a function can emit.

Faults

DeploymentError

The DeploymentError fault is raised when a configuration change causes errors when attempting to apply the configuration to a running traffic manager. It would be raised in cases such as failing to bind to a port when enabling a Virtual Server.

```
struct DeploymentError {
    # A human readable string describing the error
    String errmsg;

# The name of the object that caused the fault (if
    # appropriate)
    String object;

# The configuration key that caused the fault (if
appropriate)
```

Function Reference SOAP Faults

```
String key;

# The value that caused the fault (if appropriate)
String value;
}
```

InvalidInput

The InvalidInput fault is raised when the input to a function is invalid, for example a number was out of range. This fault is also raised in cases such as VirtualServer.setPool() where the Pool doesn't exist The details in the fault contain the object, key and value that caused the fault. These might be blank if they are not relevant to the fault.

```
struct InvalidInput {
    # A human readable string describing the error
    String errmsg;

# The name of the object that caused the fault (if
    # appropriate)
    String object;

# The configuration key that caused the fault (if
appropriate)
    String key;

# The value that caused the fault (if appropriate)
    String value;
}
```

InvalidObjectName

The InvalidObjectName fault is raised when attempting to create a new object (e.g. via an add, rename or copy) and the name is invalid (e.g. it contains a '/').

```
struct InvalidObjectName {
    # A human readable string describing the error
    String errmsg;
```

SOAP Faults Function Reference

```
# The name of the object that caused the fault
String object;
}
```

InvalidOperation

The InvalidOperation fault is emitted when attempting an operation that doesn't make sense or is prohibited, for example deleting a built-in monitor, or attempting to rename an object twice in the same call.

```
struct InvalidOperation {
    # A human readable string describing the error
    String errmsg;

# The name of the object that caused the fault (if
    # appropriate)
    String object;

# The configuration key that caused the fault (if
appropriate)
    String key;

# The value that caused the fault (if appropriate)
    String value;
}
```

LicenseError

The LicenseError fault is emitted when attempting to use functionality that is disabled by the license key. You will need to contact your support provider to get a new license key with the required functionality. There may be a charge for this.

```
struct LicenseError {
    # A human readable string describing the error
    String errmsg;

# The license key feature that was missing
    String feature;
```

Function Reference SOAP Faults

}

ObjectAlreadyExists

The ObjectAlreadyExists fault is raised when attempting to create an object (such as a Virtual Server) that already exists. It will also be raised in cases such as renaming and copying objects.

```
struct ObjectAlreadyExists {
    # A human readable string describing the error
    String errmsg;

# The name of the object that caused the fault
    String object;
}
```

ObjectDoesNotExist

The ObjectDoesNotExist fault is raised when attempting to perform an operation on an object (such as Virtual Server) that doesn't exist. This fault will only be raised if the primary object in the call doesn't exist. For example if calling VirtualServer.setPool(), then this fault will be raised if the Virtual Server doesn't exist, but if the Pool doesn't exist then the "InvalidInput" fault will be raised.

```
struct ObjectDoesNotExist {
    # A human readable string describing the error
    String errmsg;

# The name of the object that caused the fault
    String object;
}
```

ObjectInUse

The ObjectInUse fault is raised when attempting to delete an object that is referenced by another object, for example deleting a Pool that is in use by a Virtual Server.

```
struct ObjectInUse {
    # A human readable string describing the error
    String errmsg;

# The name of the object that caused the fault
```

SOAP Faults Function Reference

```
String object;
}
```

Further Information Information online

CHAPTER 7 Further Information

Stingray Manuals

Your traffic management system includes an **Installation and Getting Started Guide**, intended to get you up and running quickly, and a more detailed **User Manual**. There are also full reference manuals for functionality such as the Java Extensions and TrafficScript.

You can access these manuals via the **Help** pages (described below), or download the most recent versions from the Riverbed Support website at:

https://support.riverbed.com/docs/stingray/index.htm

Information online

Product specifications can be found at:

http://www.riverbed.com/us/products/stingray/

Visit the Stingray Community website or Technical Blog for further documentation, examples, white papers and other resources:

http://community.riverbed.com

http://blogs.riverbed.com/stingray/

CHAPTER 8 Index

Control API	Using C, 12
Adding nodes to a pool, 29	Using Java, 13
code samples, 10	Using PHP, 17
Deserializing in Perl, 40	Using Python, 16
Functions, 42	SOAP
Overview, 7	Architecture based in, 8
Sample applications, 27	security considerations, 8 What is it, 7 Troubleshooting
adding nodes to a pool in C#, 32	
adding nodes to a pool in Perl, 29	
blocking traffic from an IP address in C#,	
28	Log files, 38
blocking traffic from an IP address in Perl,	Overview, 38
27	Problem with WSDL interfaces, 39
reconfiguring a site, 33	Snooping the SOAP traffic, 38
reconfiguring a site (in C#, 35	Stingray Traffic Manager
Function Reference, 42	Product family, 7
Getting Started Guide, 690	Stingray
Č	Information online, 690
listVS	Manuals, 690
In Perl, 10	