TOrPEDO Manual

1 Preliminaries

In this section we describe the steps required to prepare the system to run the TOrPEDO tool, namely installing JRE and Docker on Microsoft Windows, Mac OS X, and GNU/LINUX operating systems. The *torpedo.jar* application can be found in the same zip archive as this manual. Alternatively, if the user wishes to use TOrPEDO from an already installed and configured setting, a VirtualBox virtual machine with TOrPEDO is available at https://bit.ly/2K7DlNI (username: "ubuntu", password: "torpedo").

1.1 Microsoft Windows

1.1.1 Install JRE

- 1. Download from ¹ the JRE matching your system (we recommend using jre-8u162-windows-x64.exe/jre-8u162-windows-i586.exe for 64bit/32bit respectively).
- 2. Install the JRE from the downloaded installer.
- 3. Open a command prompt (usually, it is sufficient to open the Start menu and type cmd) and check that JRE is correctly installed by typing java -version. You should see something like Fig. 1.

 $^{^{1} \}verb|http://www.oracle.com/technetwork/java/javase/downloads/index.html|$




Figure 1: Sample of java version




Figure 2: Sample of docker run

1.1.2 Install Docker

In order to correctly run TOrPEDO you should install Docker. For Windows 10, a complete guide is available at 2 . For older versions of Windows, Docker Toolbox is required. The complete guide is available at 3 , here we summarize the main steps.

- 1. Download from ⁴ Docker Toolbox.
- 2. Install Docker Toolbox from the downloaded installer.
- 3. Launch Docker QuickStart from the Desktop icon. Wait until the booting process completes.
- 4. Check that Docker is correctly installed by typing in the terminal: docker run hello-world. You should see something like Fig. 2.

1.2 Mac OS X

1.2.1 Install JRE

1. Download from 5 the JRE matching your system (we recommend using jre-8u162-macosx-x64.dmg).

²https://docs.docker.com/docker-for-windows/install/

³https://docs.docker.com/toolbox/toolbox_install_windows/

 $^{^4 \}mathtt{https://download.docker.com/win/stable/DockerToolbox.exe}$

 $^{^{5}}$ http://www.oracle.com/technetwork/java/javase/downloads/index.html

2. Install the JRE from the downloaded installer.

1.2.2 Install Docker

In order to correctly run TOrPEDO you should install Docker. For Mac OS X 10.11 and later, a complete guide is available at 6 , we summarize here the main steps.

- 1. Download from ⁷ Docker.
- 2. Install Docker from the downloaded installer.
- 3. Drag Docker application to the Application folder.
- 4. Double-click the Docker application. Wait until a pop-up on the status bar notifies that Docker is correctly running.)
- 5. Check that Docker is correctly installed by typing in the terminal: docker run hello-world.

1.3 GNU/Linux

The steps to be followed depends on the considered distribution. The reported instructions refer to Ubuntu 17.10.

1.3.1 Install JRE

- 1. Open a terminal window.
- 2. Type: sudo apt install openjdk-8-jre.
- 3. Provide the user password.
- 4. Check that JRE is correctly installed by typing java -version.

1.3.2 Install Docker

- 1. Open a terminal window.
- 2. Type: sudo apt install docker.io.
- 3. Provide the user password.
- 4. Start the docker daemon, by typing: sudo systemctl start docker.service.
- Add the current user to the docker group by typing: sudo usermod -aG docker \$USER
- 6. Check that Docker is correctly running by typing docker run hello-world.

⁶https://docs.docker.com/docker-for-mac/install/

⁷https://download.docker.com/mac/stable/Docker.dmg

2 Running TOrPEDO

In this section we describe the steps required to run TOrPEDO .

2.1 Microsoft Windows

- 1. Launch Docker QuickStart from the Desktop icon. Wait until the prompt becomes available.
- 2. Change directory (using the cd command) to the one containing the torpedo.jar file.
- 3. Run TOrPEDO by typing:

2.2 Mac OS X

- 1. Make sure that the Docker daemon is running by checking the presence of the Docker icon in the status bar.
- 2. Open a terminal window.
- 3. Change directory (using the cd command) to the one containing the torpedo.jar file.
- 4. Run TOrPEDO by typing:

2.3 GNU/Linux

- 1. Open a terminal window.
- 2. Make sure that the Docker daemon is running. If not, start it with the appropriate command (for Ubuntu 17.10 sudo systemctl start docker.service).
- 3. Change directory (using the cd command) to the one containing the torpedo.jar file.
- 4. Run TOrPEDO by typing:

3 Basic TOrPEDO usage

TOrPEDO provides two functionalities: analysis and recheck. Analysis checks the satisfaction of a property in Linear-time Temporal Logic (LTL) on a Partial Kripke Structure (PKS) model. The property can be satisfied/possibly satisfied/not satisfied on the PKS. The tool eventually provides a proof of satisfaction or a counterexample showing a violation of the property. Recheck checks if a proof produced for a PKS M can still be applied to a new PKS M' derived from M.

3.1 Analysis

The simplest way to run TOrPEDO is the following:

```
java -jar torpedo.jar analysis <PKS XML file> <LTL property file>
```

With this command the tool is run on the PKS contained in <PKS XML file> for the properties contained in <LTL property file>.

The PKS is passed as an XML file in a format inspired by the one of tool χ Check. The property is provided in a textual file containing an LTL formula following the grammar shown in Fig. 3. In this grammar '&','l','~','<->','->' represent logical and, or, not, double implication, and implication respectively. Instead, 'B','U','W','X','F','G' represent temporal operators before, until, weak-until, next, eventually, and globally respectively.

The aforementioned usage provides only the verification result without producing either counterexample or proof. To obtain these, some options between analysis and <PKS XML file> must be added.

```
\langle expression \rangle ::= \langle implication \rangle \ (`<->` \langle implication \rangle)^* \\ \langle implication \rangle ::= \langle disjunction \rangle \ (`->` \langle disjunction \rangle)^* \\ \langle disjunction \rangle ::= \langle conjunction \rangle \ (`I` \langle conjunction \rangle)^* \\ \langle conjunction \rangle ::= \langle temporal \rangle \ (`\&` \langle temporal \rangle)^* \\ \langle temporal \rangle ::= \langle unary \rangle \ (`B'|`U'|`W') \ \langle temporal \rangle \ | \ \langle unary \rangle \\ \langle unary \rangle ::= (`X'|`F'|`G'|`~`) \ \langle unary \rangle \ | \ \langle atom \rangle \\ \langle atom \rangle ::= `(` \langle expression \rangle \ ')` \ | \ `True' \ | \ `False' \ | \ IDENTIFIER
```

Figure 3: Property grammar

To obtain a counterexample, add the option -c <ce file>. This option enables the counterexample generation; the counterexample will be placed in <ce file>.

Note that the first time the tool is run some Docker containers must be installed. Thus, the computer must be connected to the internet and the first run may take longer than the following ones.

3.2 Recheck

The usage of recheck functionality is the following:

```
java -jar torpedo.jar recheck <PKS XML file> <Slice XML file>
```

where <PKS XML file> contains the new PKS; <Slice XML file> contains the previously obtained proof as a PKS. There are no additional options.

4 Advanced TOrPEDO analysis options

We now describe some advanced options applicable for the analysis phase.

It is possible to specify which specific solver instance should be used to obtain the proof, by adding the option -s solver, where solver is the solver to be used. Currently two solvers are available: pltlmup and hybrid. The default one is hybrid.

It is possible, for debugging purposes, to obtain the input given to the external tools, with the option -i cprefix>. Using this option, the input of the external tools is saved in files starting with cprefix>.

It is possible, for debugging purposes, to obtain the whole output of the external tools, with the option <code>-l prefix></code>. Using this option, the output of the external tools is saved in files starting with cprefix>.