## 1. Magnetfeld eines Koaxialkabels

For  $r \leq R_1$ :

$$I_{in} = I \frac{r^2}{R_1^2}$$

$$I_{in}\mu_0 = \oint \vec{B}(\vec{r}) d\vec{s} = B(r) \oint ds = B(r)2r\pi$$

$$B(r) = \frac{I\mu_0}{2\pi R_1^2} r$$

For  $R_1 \leq r \leq R_2$ :

$$I_{in} = I$$

$$I_{in}\mu_0 = \oint \vec{B}(\vec{r}) \, d\vec{s} = B(r) \oint ds = B(r)2r\pi$$

$$B(r) = \frac{I\mu_0}{2\pi} \frac{1}{r}$$

For  $R_2 \le r \le R_3$ :

$$\begin{split} I_{in} &= I \left( 1 - \frac{r^2}{R_1^2} \right) \\ I_{in} \mu_0 &= \oint \vec{B}(\vec{r}) \, \mathrm{d}\vec{s} = B(r) \oint \mathrm{d}s = B(r) 2r\pi \\ B(r) &= \frac{I\mu_0}{2\pi} \, \frac{1}{r} \end{split}$$

For  $R_3 \leq r$ :

$$I_{in} = 0$$
$$B(r) = 0$$

$$B(r) = \begin{cases} 0 & \text{for } 0 < r \le R_i, \\ \frac{kQ}{R_a^3 - R_i^3} \left( r - \frac{R_i^3}{r^2} \right) & \text{for } R_i < r < R_a, \\ kQ\frac{1}{r^2} & \text{for } R_a \le r. \end{cases}$$

## 2. Anwendung des Gesetzes von Biot-Savart – "Haarnadel"

$$d\vec{B}_{1} = \frac{\mu_{0}I}{4\pi} \frac{d\vec{l} \times \vec{r}}{r^{3}} = \frac{\mu_{0}I}{4\pi} \frac{dI \sin(\theta)}{r^{2}} = \frac{\mu_{0}I}{4\pi} \frac{d\varphi R^{2}}{r^{3}}$$

$$B_1 = \frac{\mu_0 I}{4\pi} \frac{R^2}{r^3} \int_0^{\pi} 1 \, \mathrm{d}\varphi = \frac{\mu_0 I}{4} \frac{R^2}{r^3}$$

$$d\vec{B}_{2} = \frac{\mu_{0}I}{4\pi} \frac{d\vec{l} \times \vec{r}}{r^{3}} = \frac{\mu_{0}I}{4\pi} \frac{dl \sin(\theta)}{r^{2}} = \frac{\mu_{0}I}{4\pi} \frac{dlR}{r^{3}}$$

3. Drehmoment auf rechteckige Leiterschleife

a)

b)