## Add Noise Plugin

Add some noise

#### 1.1 Introduction

The purpose of the AddNoise plugin is to introduce random noise to Tellurium data.

Generation of actual noise is using the fact that a Rayleigh-distributed random variable R, with the probability distribution F(R) = 0 if R < 0 and  $F(R) = 1 - exp(-R^2/2 * \sigma^2)$  if R >= 0, is related to a pair of Gaussian variables C and D through the transformation  $C = R * cos(\theta)$  and  $D = R * sin(\theta)$ , where  $\theta$  is a uniformly distributed variable in the interval  $(0, 2 * \pi())^{-1}$ 

Currently only Gaussian noise is implemented.

#### 1.2 Plugin Parameters

In the following, plugin parameters available in the AddNoise plugin are discussed.

### 1.3 Plugin Callbacks

The AddNoiseplugin are using all of a plugins available plugin events, i.e. the *PluginStarted*, *PluginProgress* and the *PluginFinished* events.

The available data variables for each event are internally treated as pass trough variables, so

<sup>&</sup>lt;sup>1</sup>From Contemporary Communication Systems USING MATLAB(R), by John G. Proakis and Masoud Salehi, published by PWS Publishing Company, 1998, pp 49-50.

Parameter Name	Data Type	Purpose
$Sigma,(\sigma)$	double	Size of applied noise. Noise is generated
		for each single data value, with a probabil-
		ity corresponding to a Gaussian distribu-
		tion, centered around the value, and with
		a variance equal to $\sigma^2$ .
NoiseType	int	Type of noise generated. Only Gaussian
		noise is currently supported.
Progress	double	The progress property communicates the
		progress of Noise application.

Table 1.1: Add noise Plugin Parameters

any data, for any of the events, assigned prior to the plugins execute function (in the assingOn.. family of functions), can be retrieved *unmodified* in the corresponding event function.

Callback	Arguments	Purpose
PluginStarted	void*, void*	Signal to application that the plugin has started applying noise on data. Both parameters are <i>pass trough</i> parameters and are unused internally by the plugin.
PluginProgress	void*, void*	Communicating progress of noise generation. Both parameters are <i>pass trough</i> parameters and are unused internally by the plugin.
PluginFinished	void*, void*	Signals to application that execution of the plugin has finished. Both parameters are <i>pass trough</i> parameters and are unused internally by the plugin.

Table 1.2: AddNoise Plugin callbacks

#### 1.4 The execute(bool inThread) function

The execute() function will apply noise to all rows and columns of the assigned data, with one exception. Data not affected are data in the first column, and if, and only if, its column header equals "time" (case insensitive).

The execute (bool inThread), do support a boolean argument indicating if the execution of the plugin work will be done in a thread, or not. Threading is fully implemented in the AddNoise plugin.

The inThread argument defaults to false.

#### 1.5 Python examples

#### 1.5.1 Add noise to data acquired from RoadRunner

The python script below shows how to acquire simulation data from RoadRunner and pass it to he noise plugin. The format of the data that is obtained from the simulate() function (line 8), is not directly compatible with the Noise plugins InputData property. This incompatibility is handled by an intermediate data structure in Python, that is called DataSeries (line 14). The Plugins properties, InputData and Sigma, is assigned on line 17 and 20 respectively. Line 23 denote the execution of the noise plugin, and after that has finished, data can be visualized by using the plot function (line 26). The output is shown below the script.

```
import roadrunner
2
   import telplugins as tel
3
 4
   try:
        # Create a roadrunner instance and create some data
 5
 6
       rr = roadrunner.RoadRunner()
       rr.load("sbml_test_0001.xml")
 7
 8
       data = rr.simulate(0, 10, 511) # Want 512 points
9
10
        #Add noise to the data
       noisePlugin = tel.Plugin ("tel_add_noise")
11
12
13
        # Get the dataseries from data returned by roadrunner
14
       d = tel.getDataSeries (data)
15
        # Assign the dataseries to the plugin inputdata
16
       noisePlugin.InputData = d
17
18
19
        # Set parameter for the 'size' of the noise
20
       noisePlugin.Sigma = 3.e-6
21
22
        # Add the noise
23
       noisePlugin.execute()
24
25
        # Get the data to plot
26
       noisePlugin.InputData.plot()
27
28
   except Exception as e:
```

29 print 'Problem: ' + 'e'

Listing 1.1: Add noise example.




Figure 1.1: Output for the AddNoise python example script discussed above

# 1.5.2 Visualization of the noise distribution used in the AddNoise plugin

The Python script below demonstrate the actual distribution (Gaussian) of noise that is applied on data.

```
1 # Show that add noise plugin correctly computes Sigma (standard deviation)
   import matplotlib.pyplot as plt
   import scipy.stats as stats
  import telplugins as tel
  import numpy as np
   p = tel.Plugin ("tel_add_noise")
7
9 value = 2.34
                   #This will be the mean
10
   n = 80000
11 inputData = np.zeros (shape=(1,2))
  inputData[0] = [0, value]
13
14 data = tel.DataSeries.fromNumPy (inputData)
15
  p.Sigma = 0.25
16
17 \text{ outArray} = []
  for i in range(n):
18
19
       p.InputData = data
20
       p.execute()
       outValues = p.InputData.toNumpy
21
22
       outArray.append(outValues[0][1])
23
24 plt.hist(outArray, 200, normed=True)
25
26 # Overlay analytical solution
  aRange = np.arange(min(outArray), max(outArray), 0.001)
   plt.plot(aRange, stats.norm.pdf(aRange, value, p.Sigma), linestyle='--',
      linewidth='2', color='red')
29
30 plt.show()
```

Listing 1.2: Noise distribution example.




Figure 1.2: Output for the AddNoise python example script discussed above