FIT1047 - Week 3

Central Processing Units, Part 1



Recap

In Weeks 1 and 2 we have seen

- Number systems, binary
- Boolean logic
- Basic logic gates

Now let's put them together to build a computer.

Overview

- CPUs
- Machine code and assembly language
- Combinational circuits
 - Adders

CPUs

A Central Processing Unit is the "brain" of a computer.


- Built out of logic gates
- Executes instructions
- Connected to memory and Input/Output devices (I/O)

CPUs



A module from a IBM 700 series computer with eight vacuum tubes

CPUs



Zilog Z80 (popular in some 1980s home computers)

CPUs


Intel Core i7 (top and bottom view)





CPUs

ESP8266
Microcontroller with WiFi (\$2.50)
Can be used to build "smart things" (IoT)



```
public class HelloWorld {
    public static void main(String[] args) {
        System.out.println("Hello, World");
    }
}
```

```
import sys
name = sys.argv[1]
print 'Hello, ' + name + '!'
```

```
int: n;
array[0..n-1] of var 0..n: s;
constraint forall(i in 0..n-1) (
   s[i] = sum(j in 0..n-1)(s[j]=i)
);
solve satisfy;
```

What do all these have in common?

- None of them can be executed directly by the CPU
- They are *compiled* or *interpreted*.
- CPUs can only execute machine code.

Machine Code

- A very simple computer language.
- Different for each CPU architecture
 - E.g. different machine code in your smartphone, your laptop and your washing machine
- Machine code programs are
 - Sequences of instructions
 - Stored in memory
 - Each instruction is encoded into one or more words

Machine Code

The instructions that a particular type of CPU understands are called the


Instruction Set Architecture (ISA)

What does a CPU need to be able to do?

- Do some maths (add, subtract, multiply, compare, ...)
- Move data between memory, CPU and I/O
- Execute conditionals and loops

Memory

Think of it as a sequence of "boxes":



Each box contains a value (here: a 16-bit number).

This could be a machine code instruction, or data.

We give each box an address: the number of the box, starting from 0.

Registers

Very fast, very small memory inside the CPU

- Each register can store a single word (like one "box")
- General purpose (GP) register:
 - Used by CPU to store temporary values for calculations
 - Can be used like a variable in programs
- CPU contains fixed small number (e.g. 16 GP registers for Intel CPUs)
- Special purpose register:
 - Used internally to enable CPU operations
 - Cannot be used directly in programs

Assembly Language

Machine code is hard to write and read.

Example: what does 00100000000110 mean?

We use assembly language:

- Each instruction has a *mnemonic*, a word that is easy to remember
- Assembly language can be translated easily into machine code
 - o Each line in the program is one instruction in machine code

Assembly Instructions

These are not real instructions, just examples.

- Load 0xA003, R0
 Load the number stored in memory at address A003 into GP register R0
- Add R0, R1, R2
 Add the number stored in R0 to the number stored in R1, store the result in R2
- Store R0, 0xA004
 Store the number in R0 into memory address A004
- Jump 0x1000
 Continue program execution at address 1000

MARIE: A simple CPU

Very basic machine architecture:

- Each memory location ("box") holds a 16 bit word
- The CPU has only one GP register (called *AC*)
- Each instruction is a 16 bit word
 - Composed of an opcode (4 bits) and an address (12 bits)
 - Example: 0001000110001110

 Load 18E

"Load from memory address 18E into AC register"

FIT1047

MARIE instructions

Opcode	Assembly instruction	
0001	Load	
0010	Store	
0011	Add	
0100	Subt	
0111	Halt	
1000	Skipcond	
1001	Jump	

(we will see a few more instructions later)

MARIE programming

We use a *simulator* (see link on Moodle)

Let's write a small program that adds two numbers.

Pseudocode:

- 1. Load first number from memory into AC
- 2. Add second number from memory to AC
- 3. Store result from AC into memory
- 4. Stop


FIT1047

MARIE programming

Address	Memory contents	Instruction	Data (decimal)
000	000100000000100	Load 004	
001	001100000000101	Add 005	
002	001000000000110	Store 006	
003	011100000000000	Halt	
004	000000010001110		142
005	0000110110000000		3456
006	00000000000000		0

Monash University

Note: program and data share the same memory!



Constructing a MARIE CPU

Circuits required to build a MARIE CPU:

- Perform simple maths (addition, subtraction, comparison)
- Store and load data in registers and memory
- Fetch, decode and execute instructions


Let's start with the basics.


Combinational Circuits

(output is a function of the inputs)

Adders


Let's look at the most basic case: Adding two one-bit numbers.






Full Adders


Adding **three** one-bit numbers.





Ripple-Carry Adder

Add two 3-bit numbers (A+B=C):



Outlook

Tutorials this week:

- MARIE programming
- Circuits for adding and subtracting

Next lecture:

More circuits