
Bits, Bytes, and Integers

Today: Bits, Bytes, and Integers

- Representing information as bits
- e Bit-level manipulations
- Integers
 - Representation: unsigned and signed
 - Conversion, casting
 - Expanding, truncating
 - a Addition, negation, multiplication, shifting
 - Summary
- Representations in memory, pointers, strings

otes adapted from Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective, Third Edition

Everything is bits a Each bit is 0 or 1 by encoding/interpreting sets of bits in various ways c Computers determine what to do (instructions) mand represent and manipulate numbers, sets, strings, etc... Why bits? Electronic Implementation Easy to store with bistable elements Reliably transmitted on noisy and inaccurate wires 1.1V 0.9V 0.2V 0.0V



Encoding Byte Values Byte = 8 bits Binary 000000002 to 1111111112 Decimal: 0₁₀ to 255₁₀ Hexadecimal 00₁₆ to FF₁₆ Base 16 number representation Use characters '0' to '9' and 'A' to 'F' Write FA1D37B₁₆ in C as OKFA1D37B OXFA1D37B OXFA1D37B OXFA1D37B OXFA1D37B DXFA1D37B DXFA1D37B

C Data Type	Typical 32-bit	Typical 64-bit	x86-64
char	1	1	1
short	2	2	2
int	4	4	4
long	4	8	8
float	4	4	4
double	8	8	8
long double	-	-	10/16
pointer	4	8	8

Today: Bits, Bytes, and Integers

- e Representing information as bits
- Bit-level manipulations
- e Integers
 - Representation: unsigned and signed
 - Conversion, casting
 - Expanding, truncating
 - a Addition, negation, multiplication, shifting
 - Summary
- a Representations in memory, pointers, strings

Boolean Algebra Developed by George Boole in 19th Century Algebraic representation of logic e Encode "True" as 1 and "False" as 0 And ■ A&B = 1 when both A=1 and B=1 ■ A | B = 1 when either A=1 or B=1 & 0 1 1 0 1 0 0 0 0 0 1 1 0 1 1 1 1 Not Exclusive-Or (Xor) ■ ~A = 1 when A=0 ■ A^B = 1 when either A=1 or B=1, but not both ^ 0 1 0 0 1 0 1 1 0 1 1 0

General Boolean Algebras

- Operate on Bit Vectors
- Operations applied bitwise

01101001 01101001 01101001 <u>ε 01010101</u> | 01010101 ^ 01010101 ~ 01010101 01111101 00111100 01000001

All of the Properties of Boolean Algebra Apply

Example: Representing & Manipulating Sets


- Representation
 - Width w bit vector represents subsets of {0, ..., w-1}
 - $a_j = 1 \text{ if } j \in A$
 - 01101001 {0,3,5,6}
 - e 76543210
 - **0** 01010101 { 0, 2, 4, 6 }
 - o 76543210
- Operations
 - & Intersection 01000001 {0,6} • | Union 01111101 { 0, 2, 3, 4, 5, 6 } o ^ Symmetric difference 00111100 { 2, 3, 4, 5 } Complement 10101010 {1,3,5,7}


Bit-Level Operations in C


- Operations &, |, ~, ^ Available in C
- a Apply to any "integral" data type
- o long, int, short, char, unsigned
- View arguments as bit vectors
- Arguments applied bit-wise
- e Examples (Char data type)
- ~0x41 → 0xBE
 - ~01000001₂ → 10111110₂
- ~0x00 → 0xFF
- ~000000002 → 11111111₂
- $0x69 & 0x55 \rightarrow 0x41$
- 011010012 & 010101012 → 010000012
- $0x69 \mid 0x55 \rightarrow 0x7D$
- 01101001₂ | 01010101₂ → 01111101₂


Contrast: Logic Operations in C


- Contrast to Logical Operators
- e &&, ||, !
 - View 0 as "False"
 - Anything nonzero as "True"
 - e Always return 0 or 1
 - e Early termination
- Examples (char data type)
- !0x41 → 0x00 e !0x00 → 0x01
- e !!0x41 → 0x01
- o 0x69 && 0x55 → 0x01 0x69 || 0x55 → 0x01
- p && *p (avoids null pointer access)














Values for Different Word Sizes

	W				
	8	16	32	64	
UMax	255	65,535	4,294,967,295	18,446,744,073,709,551,615	
TMax	127	32,767	2,147,483,647	9,223,372,036,854,775,807	
TMin	-128	-32.768	-2.147.483.648	-9.223.372.036.854.775.808	

- Observations
 - e |TMin | = TMax + 1
 - e Asymmetric range
 - UMax = 2 * TMax + 1

■ C Programming

- #include limits.h>
- Declares constants, e.g.,
 - ULONG_MAXLONG_MAX
 - LONG_MIN
- Values platform specific

otes adapted from Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective, Third Edition

Unsigned & Signed Numeric Values Equivalence B2U(X) B2T(X) 0000 Same encodings for nonnegative 0001 values 0010 Uniqueness 0011 Every bit pattern represents 0100 unique integer value 0101 e Each representable integer has 0110 unique bit encoding 0111

- a ⇒ Can Invert Mappings
 - U2B(x) = B2U⁻¹(x)
 - Bit pattern for unsigned integer
 - \bullet T2B(x) = B2T⁻¹(x)
 - Bit pattern for two's comp integer

-8

-4

1000

1001

1010

1011

1100

1101

1110

1111

10

11

12


13


14


Today: Bits, Bytes, and Integers


- e Representing information as bits
- e Bit-level manipulations
- Integers
 - Representation: unsigned and signed
 - Conversion, casting
 - e Expanding, truncating
 - a Addition, negation, multiplication, shifting
 - Summary
- Representations in memory, pointers, strings


tes adapted from Bryant and O'Hallaron. Computer Systems: A Programmer's Perspective. Third Edition
















Summary Casting Signed ↔ Unsigned: Basic Rules Bit pattern is maintained But reinterpreted Can have unexpected effects: adding or subtracting 2^w Expression containing signed and unsigned int int is cast to unsigned!!

Today: Bits, Bytes, and Integers Representing information as bits Bit-level manipulations Integers Representation: unsigned and signed Conversion, casting Expanding, truncating Addition, negation, multiplication, shifting Summary Representations in memory, pointers, strings





Today: Bits, Bytes, and Integers

 Representing information as bits Bit-level manipulations

Conversion, casting

Expanding, truncating

Representation: unsigned and signed


e Addition, negation, multiplication, shifting


e Representations in memory, pointers, strings

Integers


Summary


Summary: Expanding, Truncating: Basic Rules Expanding (e.g., short int to int) Unsigned: zeros added e Signed: sign extension Both yield expected result Truncating (e.g., unsigned to unsigned short) Unsigned/signed: bits are truncated Result reinterpreted Unsigned: mod operation e Signed: similar to mod e For small numbers yields expected behavior







Visualizing Unsigned Addition © Wraps Around © If true sum ≥ 2^w © At most once True Sum 2^{w+1} Modular Sum Notes adapted from Bivant and O'lestanon, Computer Vertexenhand, Frequence - Perspectives. Third Edition










Multiplication Goal: Computing Product of w-bit numbers x, y Either signed or unsigned But, exact results can be bigger than w bits Unsigned: up to 2w bits Result range: 0 ≤ x * y ≤ (2^w − 1)² = 2^{2w} − 2^{w+1} + 1 Two's complement min (negative): Up to 2w-1 bits Result range: x * y ≥ (-2^{w-1})²(2^{w-1}-1) = -2^{2w-2} + 2^{w-1} Two's complement max (positive): Up to 2w bits, but only for (TMin_w)² Result range: x * y ≤ (-2^{w-1})² = 2^{2w-2} So, maintaining exact results... would need to keep expanding word size with each product computed is done in software, if needed e.g., by "arbitrary precision" arithmetic packages



Signed Multiplication in C Operands: w bits True Product: 2*w bits TMult_w(u, v) Discard w bits: w bits Standard Multiplication Function Ignores high order w bits Some of which are different for signed vs. unsigned multiplication Lower bits are the same







Arithmetic: Basic Rules a Addition: Unsigned/signed: Normal addition followed by truncate, same operation on bit level Unsigned: addition mod 2^w Mathematical addition + possible subtraction of 2^w Signed: modified addition mod 2^w (result in proper range) Mathematical addition + possible addition or subtraction of 2^w Multiplication: Multiplication: Unsigned/signed: Normal multiplication followed by truncate, same operation on bit level Unsigned: multiplication mod 2^w Signed: modified multiplication mod 2^w (result in proper range)

```
Why Should I Use Unsigned?

Don't use without understanding implications

Easy to make mistakes
unsigned i;
for (i = cnt-2; i >= 0; i--)
a[i] += a[i+1];

Can be very subtle
#define DELTA sizeof(int)
int i;
for (i = CNT; i-DELTA >= 0; i-= DELTA)
. . . .

Les address from Broant and C'hallison, Computer Systems. A Programmer's Perspective, Third Edition

4
```

Counting Down with Unsigned Proper way to use unsigned as loop index unsigned i; for (i = cnt-2; i < cnt; i--) a[i] += a[i+1]; See Robert Seacord, Secure Coding in C and C++

- C Standard guarantees that unsigned addition will behave like modular arithmetic
 - $0-1 \rightarrow UMax$
- Even better

```
size_t i;
for (i = cnt-2; i < cnt; i--)
a[i] += a[i+1];</pre>
```

- Data type size_t defined as unsigned value with length = word size
- Code will work even if cnt = UMax
- What if cnt is signed and < 0?</p>

Why Should I Use Unsigned? (cont.)


- Do Use When Performing Modular Arithmetic
 - Multiprecision arithmetic
- Do Use When Using Bits to Represent Sets
 - Logical right shift, no sign extension

Today: Bits, Bytes, and Integers

- e Representing information as bits
- Bit-level manipulations
- Integers
 - Representation: unsigned and signed
 - Conversion, casting
 - e Expanding, truncating
 - a Addition, negation, multiplication, shifting
 - Summary
- Representations in memory, pointers, strings

tes adapted from Bryant and O'Hallaron. Computer Systems: A Programmer's Perspective. Third Edition

Byte-Oriented Memory Organization



- Programs refer to data by address
 - Conceptually, envision it as a very large array of bytes
 - In reality, it's not, but can think of it that way
 - An address is like an index into that array
 - e and, a pointer variable stores an address
- Note: system provides private address spaces to each "process"
- Think of a process as a program being executed
- So, a program can clobber its own data, but not that of others


to test adapted from Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective, Third Edition and Programmer's Perspective, Third Edition (Computer Systems) and Programmer's Perspective (Computer Systems) and Perspective (Comput

Machine Words


- a Any given computer has a "Word Size"
- Nominal size of integer-valued data
 - and of addresses
- Until recently, most machines used 32 bits (4 bytes) as word size
 - e Limits addresses to 4GB (2³² bytes)
- a Increasingly, machines have 64-bit word size
 - Potentially, could have 18 EB (exabytes) of addressable memory
 - That's 18.4 X 10¹⁸
- Machines still support multiple data formats
- Fractions or multiples of word size
- Always integral number of bytes


Word-Oriented Memory Organization


- Addresses Specify Byte Locations
- Address of first byte in word
- Addresses of successive words differ by 4 (32-bit) or 8 (64-bit)




Notes adapted from Bryant and O'Hallaron, Computer Systems: A Programmer's Perspective,









Examining Data Representations • Code to Print Byte Representation of Data • Casting pointer to unsigned char * allows treatment as a byte array typedef unsigned char *pointer; void show bytes (pointer start, size_t len) { size_t i; for (i = 0; i < len; i++) printf("%p\t0x%.2x\n",start+i, start[i]); printf("\n"); } Printf directives: %p: Print pointer %x: Print Hexadecimal

```
show_bytes Execution Example

int a = 15213;
printf("int a = 15213;\n");
show_bytes((pointer) &a, sizeof(int));

Result (Linux x86-64):
int a = 15213;
0x7fffb7f71dbc 6d
0x7fffb7f71dbd 3b
0x7fffb7f71dbd 3b
0x7fffb7f71dbd 00
0x7fffb7f71dbf 00
```

