


HOUDINI 12.1 – Texturing & Render Passes


TEXTURING & RENDER PASS SETUP

Open `globe_scene_begin.hipnc`. This scene contains some simple objects, a camera and a three point lighting setup. This scene will be utilised for demonstrating Material Palette based texturing and a simple render pass setup.



CREATING A MANTRA OUTPUT DRIVER

From the main **Render Menu**, select **Create Render Node > Mantra - PBR**. This will create a **Mantra ROP** for **Physical Based Rendering** at the **Outputs** Level of Houdini. The newly created `mantra1` node can be verified in the **Operator Tree List** (with the mouse over the Network Editor) and can be found in the **Render Outputs Level** of Houdini (`/out`).



RMB on the **Viewer's Render Button** and choose **mantra1**. This will launch a MPlay Image Viewer to render the scene. By default, a Mantra ROP will automatically look for a Camera Object called `cam1` to render through, and will render images to **MPlay**, the Houdini image viewer.




When examined, the render has visible white speckles. This is an aspect of PBR (Physically Based Rendering). Fixing this aspect of the render will be

HOUDINI 12.1 – Texturing & Render Passes

tackled at the end of this example, when all the texturing and render pass setup has been completed.

Set the **Viewer** to the **Scene View Tab**, and using the **Network Editor Level Menu**, head to Outputs Level (/out) to see the Mantra ROP. Houdini has five Render Engines in total; **Micropolygon Rendering**, **Ray Tracing**, **Micropolygon Physically Based Rendering**, **Physically Based Rendering**, and a fifth non visual renderer for **Photon Map Generation**.



These can be found under the **Properties > Render > Render Engine** Parameter of the **mantra1** node. Each Mantra node also has a **Render Button** to initiate renders. This example will primarily be looking at the PBR Render Engine; however the aesthetics and behaviours of other Render Engines can also be explored using this example.


OVERRIDING THE CAMERA RESOLUTION

At present, the render size is **1920 x 1080**, the resolution of the scene camera. While this resolution is fine for the final output, a smaller

resolution of **640 x 360** can be set for testing renders. This can be done on the **mantra1 ROP** by activating the **Override Camera Resolution** parameter found in the **Properties > Output** area of the **mantra1 ROP**, and entering these new lower values.


THE MATERIAL PALETTE

Using the tabs at the top the Network View, activate the **Material Palette Tab**.




From the **All Galleries** list, **LMB DRAG** the **Checkerboard Material** directly onto the **ground object** in the **Viewer**. This will automatically create a Checkerboard Material node at the **SHOP Level** of Houdini, as well as creating a **Shader Ball Icon** in the **Material Palette**. Repeat this operation again, this time assigning a **Glass Material** to the **wine_glass object**, and a **Stainless Steel Material** onto the **trowel object**, a **Chrome Material** onto the **soup_tin object**, and a **Wood Material** onto the **globe object**.

HOUDINI 12.1 – Texturing & Render Passes




This will assign each material to an object through its Object Level Material parameter. This can be verified by switching back to the Network View and examining the parameters for one of the textured objects.

When the scene is rendered again, each object will display its assigned material.




THE SHOP LEVEL

Switch to the SHOP Level (Shader Operators Level) of Houdini to see the newly created material nodes.



The Viewer Pane can be switched between the Context View (revealing the giant Shader View Ball), and the Scene View (showing the Object Level scene through cam1). This can make refining the aesthetic easier, as both the material and how it renders can be examined. Pressing **m** on the keyboard with the mouse over the Viewer can also modify the Shader View. This will scroll through different geometry shapes allowing the aesthetic of the material to be examined.

HOUDINI 12.1 – Texturing & Render Passes



Simple backgrounds can also be activated in the **Shader View**.

REFINING THE SCENE AESTHETIC

The default parameters for each material get the scene somewhere in terms of rendering; however each material's parameters can be refined further. As many of the materials created are Glass or Metal based, the first step for the scene is to assign an Environment Map to the scene so that these reflective materials will have the appearance of reflecting a room.

ENVIRONMENT MAPS

An environment map is usually a polar-based flattened image of a real world location. When assigned as an environment map this image will be projected onto a large invisible sphere in the scene allowing reflective objects to reflect it. Environment Maps can also be HDRI (High Dynamic Range) images or standard background plates. These images are utilised in Environment Lights, with the image providing the reflection information for a scene.



IMPORTANT NOTE: Some Material Parameters at SHOP Level may have an Environment Map parameter that can be activated on the material node itself. **DO NOT USE THESE PARAMETERS. USE AN ENVIRONMENT LIGHT INSTEAD.** These parameters are currently being phased out of Houdini and should not be used.

ENVIRONMENT & TEXTURE MAP FORMATS



Houdini will accept a number of image formats; however for optimum rendering efficiency the Houdini native **.rat** file format should be used. Ordinary image files can be converted into **.rat** files, by opening them in MPlay and re-saving them using the **.rat** extension.

For 8 bit images with Gamma encoding:

1. Load the texture into a Compositor as a 16 bit floating point image
2. Use a Gamma node set to $1 / 2.2$ (or 0.454545) to remove the gamma
3. Re-Render the texture back out to disc as a 16 bit floating point **.rat** image


HOUDINI 12.1 – Texturing & Render Passes

NOTE: All colour textures for this lecture have been processed in this way to remove any embedded gamma, and re-saved as 16 bit floating point .rat files.



NOTE: A hip file called MacBethChart_Test.hipnc and associated files have been included in these lecture notes for reference.

Return to **Object Level**, and using the **Lights and Camera Shelf**, create an **Environment Light**. In the Light section of its Parameters, load in the **envmapsmall.rat** Environment Map image. A **Render Region Preview** in the **Viewer** reveals that the objects are now reflecting (or refracting) the room image.



As projected light caustics for the wine glass are also required, a **Caustics Light** can also be added to the scene using the **Lights and Camera Shelf**. By default this light will assign caustics to the entire scene. The parameters of both the **Environment Light** and the **Caustics Light** can be modified when all the texturing of the scene is complete.


NOTE: PBR Rendering automatically generates bounce light (Global Illumination). The GI Light button found on the Lights and Cameras Shelf will either add GI to a non-PBR render engine; or can be used to amplify the effect of GI for PBR Renders.

See file **globe_scene_stage1.hipnc**

HOUDINI 12.1 – Texturing & Render Passes


REFINING THE GLASS

At present the Glass Material assigned to the `wine_glass` object is creating a thick glass aesthetic. A more naturalised aesthetic can be achieved either by reversing the curve creating the `wine_glass` (by inserting a **Reverse SOP** in the `wine_glass` geometry network), or by swapping over the values of the **Inside and Outside Index of Refraction** parameter found in the Glass Material's parameters. Either solution will create a more naturalistic render for the `wine_glass`.




REFINING THE GROUND

At SHOP Level, locate the Parameters for the Checkerboard Material, and adjust the Secondary Color Parameter to a light blue.



The placement of the Checkerboard Material on the ground object has yielded good results; however at present there is no control over the

placement of the pattern itself. This can be rectified by projecting the ground geometry into UV Space, where the placement of the geometry relative to the pattern can be controlled.




Locate the **Grid SOP** inside the ground object, and with the mouse over the Context View, press TAB and type **UV Project**. This will append a **UV Project SOP** to the **Grid SOP** and activate interactive handles to control the placement of the UV Square over the grid geometry. If this operator is invoked through the Viewer, the UV Square (represented in the Viewer by the blue edge) will be automatically set to cover the entire grid projecting as Vertices rather than Points.



HOUDINI 12.1 – Texturing & Render Passes

A Render of the scene reveals that the Checkerboard pattern is now much larger than it was previously. Before initiating the UV Project, each primitive face of the grid was being textured by the (8x8 square) Checkerboard pattern. Now the entire grid is being textured by the (8x8 square) Checkerboard pattern. This is the reason the pattern now appears larger.

The hotkey e (with the mouse over the Viewer) can be used to activate the Scale handle of the UV Project SOP.



Switch back to the **Geometry Level** for the **ground object**, and press e with the mouse over the Viewer to switch the UV Project Handle to its **Scale Handle**. Interactively scale down the size of the Blue Edge UV Square so that it just encompasses the main geometry of the scene.



The parameters of the UV Project SOP can be played with further to improve the aesthetic. The Checkerboard Material parameters can also be adjusted to change the colour of the pattern as well as the size of the pattern.

REFINING THE TROWEL

At present the trowel object is entirely textured with the stainless_steel material. The handle however should be a different material. Switch once more to the **Material Palette** and **LMB drag and drop** a Mantra Surface Material into the /shop palette area. A **Mantra Surface Material** can be configured to represent a wide number of surfaces and aesthetics.



Switch back to a Network View, and at **SHOP Level** and rename the Mantra Surface Material to **trowel_handle**.


HOUDINI 12.1 – Texturing & Render Passes

ASSIGNING TEXTURES TO SPECIFIC GEOMETRY REGIONS

The handle of the trowel needs to be defined as a region for this new material. This can be done at SOP Level, by grouping the handle geometry and assigning the material accordingly. Inside the trowel object, locate the FINAL_HANDLE_GEOMETRY Null SOP. Append to this node a **Group SOP**. This will automatically group all of the input geometry.


This expression in the Group Name parameter will automatically name the grouped geometry with the name of the node (currently called group1). The expression is surround by backtick (`) characters. This tells Houdini to evaluate the result of the expression as a text based string.

Rename the group1 node to **trowel_handle_group**. When the MMB information card is activated on the node, the group list reveals that the group is now also called **trowel_handle_group**.




Append to the **Group SOP** a **Material SOP**. In the Parameters for it specify:

Group	trowel_handle_group
Material	/shop/trowel_handle



NOTE: Both the group and material can be set by using the corresponding button at the end of the parameter. The Group parameter button will reveal a drop down menu of possible groups. The Material Parameter button will activate an Operator Chooser window, from which the **trowel_handle** Material can be found.



HOUDINI 12.1 – Texturing & Render Passes


Reset the **Display/Render Flag** back to the final node of the trowel object. The effect of both materials can now be seen on the geometry both in the **Viewer** and a **Render Region Preview** of the scene.

Keep the **Viewer** set to the **Scene View**, with a **Render Region Preview** active within it. Switch the **Network Editor** to the **SHOP Level** of Houdini, and locate the **trowel_handle** material. Modify its parameters to:

Diffuse
Base Color 0.9 0.9 0.75


Reflect > Reflect Objects
 Reflect Objects
Reflection Intensity 0.5
Reflection Angle 20

This will create a suitably shiny ivory type material for the trowel handle.



THE RENDER VIEW

As well as a **Render Region Preview**, an interactive **Render View** can be activated as part of the **Viewer Tabs**. This view will continually render the scene, updating with any changes to the scene parameters. The **Render View** allows for efficient modification of material parameters as the results can be directly seen.




See **globe_scene_stage2.hip**

REFINING THE SOUP TIN

Locate the **FINAL_SOUP_TIN_GEOMETRY Null SOP**, and interactively in the **Viewer** invoke a **Group Geometry (Group SOP)** operation. Select the faces of the tin can that make up the label area and press **ENTER** to confirm the selection.

HOUDINI 12.1 – Texturing & Render Passes



Rename and the Group Node name to **soup_tin_label_group**. With this in place, switch over to the **Material Palette** and LMB drag and drop a **Mantra Surface Material** into the **/shop** palette area.



At **SHOP Level**, locate this new material and rename it to **soup_tin_label**. In its parameters specify:

Diffuse



Use Color Map


Base Color Map

\$HIP/Soup_square.rat

Reflect > Reflect Lights

Specular Intensity 0.25

Specular Angle 90



This will load into the Material an image that can be utilised as the label, and set the shininess of the material to a paper aesthetic.


\$HIP – This is a global variable in Houdini that will return the directory location of the current hip file. If textures are saved relative to this location (ie inside the same folder or in a subdirectory) \$HIP can be called in the file chooser path rather than writing the entire path location.

NOTE: Remember all texture files must be converted to .rat files before final rendering takes place.

HOUDINI 12.1 – Texturing & Render Passes

Return back to the **soup_tin** Geometry Level, and append to the **Group SOP** a **Material SOP**. In its Parameters specify:

Group	soup_tin_label_group
Material	/shop/soup_tin_label




This will assign the label material to the label geometry grouping. A Render Region reveals that each face of the soup tin label area is being textured with the soup tin label. This can be rectified by projecting the label region geometry into UV Space.

NOTE: For speed of a Render Region Preview, the Caustics Light can be temporarily deactivated to save it recalculating with each new region preview.


Using the Viewport Layout Button, assign Two Views Side by Side as the Viewer display. Activate the left hand side View to a UV Viewport by pressing **SPACEBAR + 5** with the mouse over the left hand side View. The

left hand side view itself can be set as the **active View** by pressing **n** with the mouse over the left hand side view.




Using the **Viewer's Display Options**, turn off the **Apply Operation to All Split Views**, and activate **Display Background Images**. The **Soup_square.tif** image can be loaded in as an image for the UV Square. Displaying the texture map within the UV Square will make creating the UVs more understandable.

HOUDINI 12.1 – Texturing & Render Passes



To the **Material SOP** append a **UV Project SOP**. By default this will produce an Orthographic projection of the geometry into the UV Square. In the parameters for the **UV Project SOP** specify:

Group	soup_tin_label_group
Group Type	Vertices
Projection	Cylindrical




From the Initialize section of the parameters LMB the Initialize button. This will move the projection to where Houdini thinks it should be based upon the grouped geometry.

When the **soup_tin** geometry is examined in the Perspective View, the texturing works; however the label is a little too stretched. This can be corrected by adjusting the U Range parameter of the UV Project to:



U Range	0.01	0.79
----------------	-------------	-------------

HOUDINI 12.1 – Texturing & Render Passes



Adjusting the upper **U Range Value** will have an effect on the geometry's projection into the UV Square. This parameter adjustment will refine the aesthetic of the label projection. When modifying this parameter be aware of the texturing seam generated at the back of the `soup_tin` geometry. This seam will be made invisible with the correct value assigned.

The **Rotate Y** Parameter located under the **Transformation** section of the **UV Project SOP** parameters can also be adjusted to rotate the scaled label into the correct position.



As before, a render of the scene can be generated to check the final aesthetic.


See `globe_scene_stage3.hip`

HOUDINI 12.1 – Texturing & Render Passes


REFINING THE GLOBE

A similar texturing challenge to the `soup_tin` is the globe. At present this object has a wood material uniformly assigned to it. As with the `soup_tin`, the region of the geometry representing the globe itself can be assigned a different texture than to the wood material assigned to the stand.


Go inside the globe object, and locate the **FINAL_GLOBE Null SOP**. Activate the **Display/Render flag** to this node. If necessary, set the Viewer only to Hide Other Objects, so that the geometry is clearly visible.



With the mouse over the Viewer, press **SPACEBAR + 3** to set the View to a **Front Orthographic View**. In this view, interactively drag select and group all of the faces of the globe itself (excluding the parts which fix the globe to the stand).



If any faces have been missed when creating this new group, the **Select** button has the **RMB** option to reselect the geometry for the current operation. Also, these **RMB select options** can control for example if a selection is added to, replaced or subtracted from the original selection. Rename the node in the Network Editor to **globe_group**




CREATING THE GLOBE MATERIAL


Switch over to the Material Palette and LMB drag and drop a Mantra Surface Material into the /shop palette area.



The Mantra Surface Material can be utilised for both surface and displacement shading. In the files for this lesson are two texture maps which can be assigned to the globe. One returns colour information for shading purposes, the other contains black and white information for displacement purposes.





globe_colour.rat




globe_displacement.rat

Locate this new Mantra Surface Material node in the SHOP Level of Houdini and rename it to **globe**. Under the Diffuse section of the parameters, activate the Use Color Map toggle option, and using the File Chooser button read in the **globe_colour.rat** image.



Under the **Displacement** section of the **parameters** activate the **Use Displacement Map** toggle option, and load into the **Displacement Map** parameter the **globe_displacement.tif** image file. Specify a Displace Direction of **up: black = no displace**, and specify an **Overall Scale** for the displacement of **-0.1**.




HOUDINI 12.1 – Texturing & Render Passes

The configured material can be examined in the Material Ball View to see the effect of combining both surface and displacement shading.

Return back to the **Geometry Level** of the **globe** object. Here append to the **globe Group SOP** a **Material SOP**. In the parameters for the **Material SOP** specify:


Group	globe_group
Material	/shop/globe

Use the **Operator Chooser button** to set the Material parameter to point to the globe material.



The globe_group geometry can now be projected into UV Space so that the material can be seen and rendered correctly. To the **Material SOP** append a **UV Project SOP**. In the **parameters** specify:

Group	globe_group
Group Type	Vertices
Projection	Polar




Under the **Initialize** section of the **parameters** specify:


Method	To XY Plane
---------------	--------------------

Finally press the **Initialize** button to map the projection onto the geometry.

HOUDINI 12.1 – Texturing & Render Passes



Examination of the **Viewer** reveals that there are two New Zealands... As with the placement of the `soup_tin` label, the **second U Range** parameter of the **UV Project SOP** can be modified to correct this.



As before, the materials of the globe can be refined to produce better aesthetics.


With the texturing of the globe complete, the scene can be rendered.

See `globe_scene_stage4.hip`

GENERATING RENDER PASSES

Materials created from the Material Palette can be directly outputted as render passes as well as the final image. A **Render Pass** contains one of the image elements, which make up the final image (for example a **Reflections** Render Pass would hold all of the reflection information of a scene or object).


When using **Mantra PBR (Physical Based Rendering)**, Houdini can output a number of render passes. This can be done on the **Mantra1 ROP** controlling the final output of the scene.



Under the **Properties > Output** section of the **mantra1** ROP's parameters, locate the **Extra Image Planes** activation parameter, and create one additional image plane for the rendered image. Using the drop down menu associated with the **VEX Variable** parameter, choose **direct_diffuse**. This will tell Houdini to output all the diffuse information of the scene into this new image plane.


Specify a **Channel Name of diffuse**. This will be the name of the render pass, as it will be seen on the rendered image.

Set the **Quantize Parameter** to **16-bit float**, and the **Pixel Filter Parameter** to **Gaussian 2 x 2**. This will ensure the image plane renders to the same settings as the main image (found at the top of these parameter listings).



When the scene is rendered again, the main image and the diffuse render pass image can be examined.

HOUDINI 12.1 – Texturing & Render Passes




The diffuse image pass by default holds the following image components:


- Geometry Colour
- Scene Lighting
- Scene Shadows
- Scene Caustics

The diffuse pass will allow a composite based recreation of the original scene when additional render passes are added using Image Planes.


Repeat this Additional Image Plane operation creating render passes for the following VEX Variables:



VEX Variable Pz
VEX Type Float Type
Channel Name Depth
Quantize 16 Bit Float
Pixel Filter none



VEX Variable Combined Refraction
VEX Type Vector Type
Channel Name Refractions
Quantize 16 Bit Float
Pixel Filter Gaussian 2 x 2




VEX Variable Indirect Reflect
VEX Type Vector Type
Channel Name Reflections
Quantize 16 Bit Float
Pixel Filter Gaussian 2 x 2




VEX Variable Direct Reflect
VEX Type Vector Type
Channel Name Specular
Quantize 16 Bit Float


HOUDINI 12.1 – Texturing & Render Passes



Pixel Filter	Gaussian 2 x 2
VEX Variable	Indirect Diffuse
VEX Type	Vector Type
Channel Name	Bounce Light
Quantize	16 Bit Float
Pixel Filter	Gaussian 2 x 2



VEX Variable	direct_shadow
VEX Type	Vector Type
Channel Name	Direct Shadows
Quantize	16 Bit Float
Pixel Filter	Gaussian 2 x 2



VEX Variable	indirect_shadow
VEX Type	Vector Type
Channel Name	Indirect Shadows
Quantize	16 Bit Float
Pixel Filter	Gaussian 2 x 2

NOTE: The Direct Shadow and Indirect Shadow Image planes are utility passes for controlling the shadows of the rebuilt image. They do not directly contribute to the rebuilding of the image from render passes.

NOTE: Physically Based Rendering and Micropolygon PBR render engines will generate these images planes. Micropolygon Rendering and Ray Trace

render engines will not output Refractions or Bounce Light using this method. See the Mantra ROP Help Card for more information about image planes relative to render engine.

CAUSTICS LIGHT PHOTON MAP GENERATION

At Object Level, reactivate the **Caustics Light** in order to generate the caustic information for the render. The Caustic Light parameters also contain controls for improving the caustics aesthetics. Please see the Caustic Light Help Card for more information.

In the **parameters** for the **Caustic Light** specify:

<input checked="" type="checkbox"/>	Auto-generate Photon Map
Photon Count	200000
Photon File	/transfer/caustics_\$F4.pmap
Filter Samples	10
<input checked="" type="checkbox"/>	Prefilter Photon Map
Prefilter Samples	200

At Outputs Level, create a new **Mantra ROP** named **caustics_photon_map** and in its **parameters** specify:

Properties > Render

Render Engine

Photon Map Generation

When the **Render** button is pressed, the photon map file will be generated on disk in accordance with the settings specified in the **Caustics Light**.

HOUDINI 12.1 – Texturing & Render Passes


Back at Object Level, deactivate the Auto-generate Photon Map option.

Now the photons will be read in from disk at render time.

IMPORTANT NOTE: Photon Maps should be seen as the same as Shadow Depth Maps, where for animated objects, these would need to be generated on a per frame basis.

EXAMINING PHOTON MAPS

The Houdini utility application gplay can be used to examine photon maps after they have been created. Open a Terminal Shell and type the command gplay to activate it.



As photon map data is essentially point data, Point Display of the gplay Viewer will need to be activated to see the photon data. This point data stores the additional caustics lighting information, which then gets transferred onto the geometry shading at render time.

REFINING THE RENDER AESTHETIC

At present the render still had white speckles and is of low quality.

Modifying certain parameters in the main Mantra node at Outputs Level can rectify this. These modifications can take place using the smaller resolution rendered image, before a full resolution image is outputted. In the parameters for the Mantra ROP, specify:

Properties > Sampling

Min Ray Samples	8
Max Ray Samples	12

This will reduce the white speckle artefacts and the level of render noise in the final image. The render time will however increase as a result of adjusting this parameter, and therefore experimenting with these values is necessary to find the optimum trade off between render time and render quality.

NOTE: There is also the Color Limit parameter located under the Properties > PBR section of the Mantra ROP parameters. Reducing this parameter can also reduce white speckles in the render.

NOTE: At present this scene has not been optimised for rendering, and therefore render times will be longer. Render Optimisation of scenes will take place in an upcoming lecture.

NOTE: The Environment Light also has its own Sampling parameter in case its quality needs to be increased.

IMPORTANT NOTE: There is also a Pixel Samples parameter (set to 3 x 3 by default). Increasing this parameter should be seen as a last resort when improving the quality of the image due to the increase in render times it produces. This parameter will globally increase the overall sampling of the scene. Increased value settings for this parameter might include 4 x 4, 8 x 8, or 16 x 16.

REFLECTION AND REFRACTION LIMITS


Under the Properties > Shading section of the parameters specify:

Reflect Limit	4
Refract Limit	4

This will reduce the number of times a ray will bounce off (reflection) or through (refraction) the scene geometry. The value for this was determined by the wine glass and the number of surfaces a ray would have to travel through it in order to penetrate fully through its surface. Modifying this parameter can help save rendering calculation time with only a negligible difference to the render quality.

RENDERING PASSES AS IMAGE FILES & SEQUENCES

As all of the render passes created have been done so using the Extra Image Plane Method, they can be rendered out to disk as a single .exr file image. The .exr format is similar in many ways to the **Adobe Photoshop .psd format** where the different layers of the image remain as individual separate layers.



In the **Output Picture** parameter of the **Mantra ROP**, rename the Output Picture parameter location from ip (the MPlay Viewer) to **/transfer2/globescene_.\$F4.exr**. This will output a file called simple_scene_0001.exr where \$F4 is replaced by a padded frame number (the current frame). With the current frame set to 1, \$F can be set to return the following padding options:

\$F 1 \$F2 01 \$F3 001 \$F4 0001

NOTE: single images with no Extra Image Planes set can be outputted as .tif files (these will render at 32bit even though 16bit is stated in the Mantra ROP). It is also possible to output Extra Image Planes as their own individual tif image files. It is simpler however to export a single .exr file.

A Frame Range can be created as well as a single image. To activate a frame range, modify the **Valid Frame Range** parameter to **Render Frame Range**. This will activate the **Start/End/Inc** parameter where the range of frames to be rendered can be set.

The \$F4 option should also be specified in photon map generation, and Shadow Depth Map generation for animated scenes and objects.

REMEMBER TO DEACTIVATE THE OVERRIDE CAMERA RESOLUTION
MANTRA OPTION TO GET THE FINAL FULL SIZE RENDER.

IMPORTANT NOTES:

FOR PRODUCTION RENDERING OF ANIMATED SEQUENCES, ALL FILES
SHOULD BE LOCATED ON /transfer2 (1TB Hard Drive).

WHILE THIS EXAMPLE DEMONSTRATES RENDERING DIRECTLY THROUGH
THE HOUDINI INTERFACE; RENDERING ANIMATED SEQUENCES SHOULD
NOT BE DONE WITH HOUDINI OPEN, BUT INSTEAD RENDERED USING THE
SHELL. THIS WILL BE DEMONSTRATED IN THE RENDER OPTIMISATION
LECTURE.

THIS LESSON WILL HOWEVER ALLOW YOU TO GENERATE A STILL FRAME
COMPOSITE IN NUKE FOR TESTING YOUR COMPOSITING NETWORK.

See file globe_scene_end.hipnc