#### VE216 Recitation Class 9

ZHU Yilun

UM-SJTU Joint Institute

VE216 SU20 TA Group

2020 Summer


#### Overview

- Chapter 8: Communications
  - Sinusoidal Amplitude Modulation (AM) Synchronous
  - Sinusoidal Amplitude Modulation (AM) Asynchronous
  - Frequency-division Multiplexing

Conclusion

#### Modulation

Modulation Property:



$$x(t) c(t) \stackrel{\mathcal{F}}{\longleftrightarrow} \frac{1}{2\pi} [X(\omega) * C(\omega)]$$

- pulse carrier
- sinusoidal carrier

$$c(t) = \cos(\omega_c t + \theta_c)$$

ZHU Yilun (SJTU) VE216 2020 Summer 3/19

### Sinusoidal Amplitude Modulation

Block diagram of modulation system:

$$x(t)$$
 - information,  $c(t)$  - carrier

$$egin{aligned} \mathit{x}(t) & + \bigotimes_{\uparrow} \rightarrow \mathit{y}(t) \rightarrow & \mathsf{antenna} \\ \cos(\omega_c t + heta_c) \end{aligned}$$

Notice: here we multiply the carrier signal rather than do convolution


• Transmitted signal (i.e., modulated output y(t)):

$$y(t) = x(t)c(t) = x(t)\cos(\omega_c t + \theta_c)$$

$$\longleftrightarrow Y(\omega) = \frac{1}{2}[e^{j\theta_c}X(\omega - \omega_c) + e^{-j\theta_c}X(\omega + \omega_c)]$$

4/19

### Sinusoidal Amplitude Modulation - Synchronous




4 D M 4 B M 4 E M

ZHU Yilun (SJTU) VE216 2020 Summer 5/19

# Synchronous Demodulation

• Block diagram of demodulation system:



• First multiply y(t) by another  $cos(\omega_c t + \theta_c)$  signal:


$$w(t) = y(t)\cos(\omega_c t + \theta_c)$$


$$W(\omega) = \frac{1}{2} [e^{j\theta_c} Y(\omega - \omega_c) + e^{-j\theta_c} Y(\omega + \omega_c)]$$
$$= \frac{1}{4} e^{2j\theta_c} X(\omega - 2\omega_c) + \frac{1}{2} X(\omega) + \frac{1}{4} e^{-2j\theta_c} X(\omega + 2\omega_c)$$

ullet Then followed by lowpass filtering to extract  $X(\omega)$ 

ZHU Yilun (SJTU) VE216 2020 Summer 6 / 19

# Synchronous Demodulation





 ZHU Yilun (SJTU)
 VE216
 2020 Summer 7 / 19


#### Asynchronous Demodulation: Motivation

- It seems to be harmless to write the way synchronous Demodulation works on paper, but up to now we haven't considered how to implement it to hardware.
- The bad news is that in practice, it is possible that both the frequency  $\omega_c$  the phase  $\theta_c$  are not available, therefore may need a sophisticated receiver
- But for commercial products like AM radio, one would expect the receivers to be simple and inexpensive.
- Therefore a different demodulation scheme is needed, which uses a more complicated and power inefficient transmitter, but a simple receiver.

◆ロト ◆個 ト ◆ 恵 ト ◆ 恵 ・ か Q (^\*)

# Asynchronous Demodulation: Modulated signal

- Now the modulated signal is:  $y(t) = (A + x(t))\cos(\omega_c t)$
- Often we choose A greater then the amplitude of x(t)
- The block diagram & how the output y(t) looks like:



◆ロト ◆個ト ◆差ト ◆差ト 差 めるの


9/19


ZHU Yilun (SJTU) VE216 2020 Summer

#### Asynchronous Demodulation: Frequency Domain

• In frequency domain:

$$Y(\omega) = A\pi[\delta(\omega - \omega_c) + \delta(\omega + \omega_c)] + \frac{1}{2}[X(\omega - \omega_c) + X(\omega + \omega_c)]$$






ZHU Yilun (SJTU) VE216 2020 Summer 10 / 19

### Asynchronous Demodulation

- Use a simple circuit to detect the envelop:  $m(t) = A + \hat{x}(t)$
- It works because  $\omega_c$  is much higher than frequency of x(t)



ZHU Yilun (SJTU) VE216 2020 Summer 11 / 19

### Asynchronous Demodulation

The envolope detector gives us:


$$y(t) = (A + x(t))\cos(\omega_c t)$$
$$m(t) = A + \hat{x}(t)$$

- Then eliminate the DC component (this is what we mean by "power inefficient") and you recover the orginal signal.
- The overall block diagram of demodulation:

$$y(t) 
ightarrow \boxed{ ext{Envelop detector}} 
ightarrow m(t) 
ightarrow \boxed{ ext{DC blocking filter}} 
ightarrow \hat{\chi}(t)$$

# Frequency-division Multiplexing

#### In time domain:






ZHU Yilun (SJTU) VE216 2020 Summer 13 / 19

# Frequency-division Multiplexing


#### In frequency domain:




14 / 19

### Demultiplexing and Demodulation

synchronous demodulation



asynchronous demodulation (using IF filter)



ZHU Yilun (SJTU) VE216 2020 Summer 15 / 19

#### Exercise

Consider the amplitude modulation and demodulation systems with  $\theta_c=0$  and with a change in the frequency of the modulator carrier so that

$$w(t) = y(t) \cos \omega_d t$$


where

$$y(t) = x(t) \cos \omega_c t$$

Let us denote the difference in frequency between the modulator and demodulator as  $\Delta\omega$  (i.e.,  $\omega_d - \omega_c = \Delta\omega$ ). Also assume that x(t) is band limited with  $X(j\omega) = 0$  for  $|\omega| \ge \omega_M$ , and assume that the cufoff frequency  $\omega_{co}$  of the lowpass filter in the demodulator satisfies the inequality

$$\omega_M + \Delta\omega < \omega_{co} < 2\omega_c + \Delta\omega - \omega_M$$

- (a) [5] Show that the output of the lowpass filter in the demodulator is proportional to  $x(t)\cos(\Delta\omega t)$ .
- (b) [5] If the spectrum of x(t) is that shown in figure below, sketch the spectrum of the output of the demodulator.



4□ > 4□ > 4 = > 4 = > = 9 Q €

16 / 19

ZHU Yilun (SJTU) VE216 2020 Summer

#### Lab2

- I am completely lost when I first learnt Chap.8 Communication
   System, it was only after completing Prelab2 that I finally understood.
- Please take a close look at Prelab2 Section 2.3 2.6




Figure 2.4.2: Using LO to Mix into IF Band when  $f_{LO}=f_c-f_{IF}$ 




Figure 2.4.3: Using LO to Mix into IF Band when  $f_{LO} = f_{IF} + f_c$ 

 Let's see a video on what really happens in real life - MIT Video Lecture 14 (30:10 – 33:00 min)

ZHU Yilun (SJTU) VE216 2020 Summer 17/19

#### Conclusion

- Have a close look at Prelab2 and Quiz7, then you'll be the expert to Chap. 8
- Get the big picture of mod. & demod.; solve problems graphically
- I guess at one time you may complain about why do we have to go through such a painful way just to get x(t).
- But in fact the task is not at all easy, given the constrain of physical laws and hardware implementation.
- Using Asynchronous way (against syn.) is the first time in my collage life that I saw how the real life implementation affects our design
- Therefore, to me, the outcomes of these issues are amazing, because Electrical Engineers not only managed to develop a brand new subject based on the fairly abstract mathematical property (associated with the Fourier transform), but also turn the theory into real life applications.

ZHU Yilun (SJTU) VE216 2020 Summer 18 / 19

# The End



19 / 19

ZHU Yilun (SJTU) VE216 2020 Summer