
#### CS162 **Operating Systems and** Systems Programming Lecture 13

#### Address Translation (Con't), Caching and TLBs

March 10<sup>th</sup>, 2020 Prof. John Kubiatowicz http://cs162.eecs.Berkelev.edu

## Recall: Implementation of Multi-Segment Model



Segment number mapped into base/limit pair

Error - Base added to offset to generate physical address

- Error check catches offset out of range

- · As many chunks of physical memory as entries
  - Segment addressed by portion of virtual address
  - However, could be included in instruction instead: » x86 Example: mov [es:bx],ax.
- What is "V/N" (valid / not valid)?
  - Can mark segments as invalid; requires check as well


3/10/20

Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.2

#### Recall: Problems with Segmentation

- Must fit variable-sized chunks into physical memory
- May move processes multiple times to fit everything




- Limited options for swapping to disk
- Fragmentation: wasted space
  - External: free gaps between allocated chunks
  - Internal: don't need all memory within allocated chunks

#### Paging: Physical Memory in Fixed Size Chunks

- Solution to fragmentation from segments?
  - Allocate physical memory in fixed size chunks ("pages")
  - Every chunk of physical memory is equivalent
    - » Can use simple vector of bits to handle allocation: 00110001110001101 ... 110010
    - » Each bit represents page of physical memory  $1 \Rightarrow$  allocated,  $0 \Rightarrow$  free
- Should pages be as big as our previous segments?
  - No: Could lead to lots of internal fragmentation
    - » Typically have small pages (1K-16K)
    - » Consequently: need multiple pages/segment
  - May selectively have very large pages for things that don't change much, like the kernel - more LATER!

#### How to Implement Simple Paging?



- Page Table (One per process)
  - Resides in physical memory
  - Contains physical page and permission for each virtual page
     Permissions include: Valid bits, Read, Write, etc
- Virtual address mapping
  - Offset from Virtual address copied to Physical Address
     » Example: 10 bit offset ⇒ 1024-byte pages
  - Virtual page # is all remaining bits
    - » Example for 32-bits: 32-10 = 22 bits, i.e. 4 million entries
    - » Physical page # copied from table into physical address
  - Check Page Table bounds and permissions


3/10/20 Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.5

3/10/20

3/10/20


#### Simple Page Table Example



Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.6

## What about Sharing?



## Where is page sharing used?


- The "kernel region" of every process has the same page table entries
  - The process cannot access it at user level
  - But on U->K switch, kernel code can access it AS WELL AS the region for THIS user
    - » What does the kernel need to do to access other user processes?
- Different processes running same binary!
  - Execute-only, but do not need to duplicate code segments
- User-level system libraries (execute only)
- Shared-memory segments between different processes
  - Can actually share objects directly between processes
    - » Must map page into same place in address space!
  - This is a limited form of the sharing that threads have within a single process

#### Some simple security measures

- Address Space Randomization: Limit the damage of buffer overflow attacks (e.g. overwriting stack to point to arbitrary code)
  - Position-Independent Code => can place user code region anywhere in the address space
    - » Random start address makes much harder for attacker to cause jump to code that it seeks to take over
  - Stack & Heap can start anywhere, so randomize placement
- · Kernel address space isolation

3/10/20


- Don't map whole kernel into each process (Provide separate kernel page table)
- Meltdown protection ⇒ map none of kernel into user mode!



Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.9

# Example: Memory Layout for Linux 32-bit (Pre-Meltdown patch!)




http://static.duartes.org/img/blogPosts/linuxFlexibleAddressSpaceLayout.png


3/10/20 Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.10


**Summary: Paging** 



**Summary: Paging** 



#### **Summary: Paging**



#### How big do things get?

- 32-bit address space => 2<sup>32</sup> bytes (4 GB)
  - Note: "b" = bit, and "B" = byte
  - And for memory:
    - » "K"(kilo) =  $2^{10}$  = 1024  $\approx 10^3$  (But not quite!)
    - » "M"(mega) =  $2^{20}$  =  $(1024)^2$  = 1,048,576  $\approx 10^6$  (But not quite!)
    - » "G"(giga) =  $2^{30}$  =  $(1024)^3$  = 1,073,741,824  $\approx 10^9$  (But not quite!)
- Typical page size: 4 KB
  - how many bits of the address is that ? (remember  $2^{10} = 1024$ )
  - Ans 4KB =  $4 \times 2^{10} = 2^{12} \Rightarrow 12$  bits of the address
- So how big is the simple page table for each process?
  - $-2^{32}/2^{12} = 2^{20}$  (that's about a million entries) x 4 bytes each => 4 MB
  - When 32-bit machines got started (vax 11/780, intel 80386), 16 MB was a LOT of memory
- How big is a simple page table on a 64-bit processor (x86\_64)?
  - $-2^{64}/2^{12}$  =  $2^{52}$ (that's 4.5×10<sup>15</sup> or 4.5 exa-entries)×8 bytes each =  $36\times10^{15}$  bytes or 36 exa-bytes!!!! This is a ridiculous amount of memory!
  - This is really a lot of space for only the page table!!!
- Mostly, the address space is sparse, i.e. has holes in it that are not mapped to physical memory
  - So, most of this space is taken up by page tables mapped to nothing

3/10/20

Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.14

#### Page Table Discussion

- What needs to be switched on a context switch?
  - Page table pointer and limit
- What provides protection here?
  - Translation (per process) and dual-mode!
  - Can't let process alter its own page table!
- Analysis
  - Pros
    - » Simple memory allocation
    - » Easy to share
  - Con: What if address space is sparse?
    - » E.g., on UNIX, code starts at 0, stack starts at (2<sup>31</sup>-1)
    - » With 1K pages, need 2 million page table entries!
  - Con: What if table really big?
    - » Not all pages used all the time ⇒ would be nice to have working set of page table in memory
- Simple Page table is way too big!
  - Does it all need to be in memory?
  - How about multi-level paging?
  - or combining paging and segmentation

#### Administrivia

- CS162 Went virtual today!
  - Lectures, Discussion Sections, Office Hours
  - We will be uploading videos of lecture somewhere
  - Live lectures will be captioned (eventually today?)
- Zoom links for discussion sections and office hours should be available off the group calendar
  - (At the bottom of the Class schedule page)
- · Discussion sections are semi-required again
  - Since they are entirely virtual, we would like you to start attending discussion sections again (unless you are sick)
  - Remember that your TA is there to help you navigate the class and to evaluate your performance

#### Fix for sparse address space: The two-level page table Physical Offset 10 bits 10 bits 12 bits Address: Virtual Offset Address: PageTablePtr → 4 bytes ← Tree of Page Tables - "Magic" 10b-10b-12b pattern! Tables fixed size (1024 entries) - On context-switch: save single PageTablePtr register (i.e. ČR3) Valid bits on Page Table Entries Don't need every 2<sup>nd</sup>-level table Even when exist, 2<sup>nd</sup>-level tables can → 4 bytes ← reside on disk if not in use

#### Example: x86 classic 32-bit address translation




Figure 42. Linear-Address Translation to a 4-KByte Page using 32-Bit Paging

- Intel terminology: Top-level page-table called a "Page Directory"
  - With "Page Directory Entries"
- CR3 provides physical address of the page directory
  - This is what we have called the "PageTablePtr" in previous slides
  - Change in CR3 changes the whole translation table!

3/10/20 Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.18

#### What is in a Page Table Entry (PTE)?

Kubiatowicz CS162 ©UCB Spring 2020

- What is in a Page Table Entry (or PTE)?
  - Pointer to next-level page table or to actual page
  - Permission bits: valid, read-only, read-write, write-only
- Example: Intel x86 architecture PTE:
  - Address same format previous slide (10, 10, 12-bit offset)
  - Intermediate page tables called "Directories"

Page Frame Number (Physical Page Number)	Free (OS)	0	PS	D	Α	PCD	PWT	U	W	Р
31-12	11-9	8	7	6	5	4	3	2	1	0

P: Present (same as "valid" bit in other architectures)

W: Writeable

U: User accessible

PWT: Page write transparent: external cache write-through

PCD: Page cache disabled (page cannot be cached)

A: Accessed: page has been accessed recently

D: Dirty (PTE only): page has been modified recently

PS: Page Size: PS=1⇒4MB page (directory only). Bottom 22 bits of virtual address serve as offset


#### Examples of how to use a PTE

- How do we use the PTE?
  - Invalid PTE can imply different things:
    - » Region of address space is actually invalid or
    - » Page/directory is just somewhere else than memory
  - Validity checked first
    - » OS can use other (say) 31 bits for location info
- Usage Example: Demand Paging
  - Keep only active pages in memory
  - Place others on disk and mark their PTEs invalid
- Usage Example: Copy on Write
  - UNIX fork gives copy of parent address space to child
    - » Address spaces disconnected after child created
  - How to do this cheaply?


3/10/20

- » Make copy of parent's page tables (point at same memory)
- » Mark entries in both sets of page tables as read-only
- » Page fault on write creates two copies
- Usage Example: Zero Fill On Demand
  - New data pages must carry no information (say be zeroed)
  - Mark PTEs as invalid; page fault on use gets zeroed page
  - Often, OS creates zeroed pages in background


#### Sharing with multilevel page tables



#### Summary: Two-Level Paging




#### Summary: Two-Level Paging




#### Multi-level Translation: Segments + Pages

- · What about a tree of tables?
  - Lowest level page table  $\Rightarrow$  memory still allocated with bitmap
  - Higher levels often segmented
- Could have any number of levels. Example (top segment):



- · What must be saved/restored on context switch?
  - Contents of top-level segment registers (for this example)
  - Pointer to top-level table (page table)

#### What about Sharing (Complete Segment)?



3/10/20

Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.25

#### Multi-level Translation Analysis

#### Pros:

- Only need to allocate as many page table entries as we need for application
  - » In other wards, sparse address spaces are easy
- Easy memory allocation
- Easy Sharing
  - » Share at segment or page level (need additional reference counting)

#### · Cons:

- One pointer per page (typically 4K 16K pages today)
- Page tables need to be contiguous
  - » However, the 10b-10b-12b configuration keeps tables to exactly one page in size
- Two (or more, if >2 levels) lookups per reference

» Seems very expensive!

3/10/20

3/10/20


Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.26

#### **Recall: Dual-Mode Operation**

- Can a process modify its own translation tables? NO!
  - If it could, could get access to all of physical memory (no protection!)
- To Assist with Protection. Hardware provides at least two modes (Dual-Mode Operation):
  - "Kernel" mode (or "supervisor" or "protected")
  - "User" mode (Normal program mode)
  - Mode set with bit(s) in control register only accessible in Kernel mode
  - Kernel can easily switch to user mode: User program must invoke an exception of some sort to get back to kernel mode (more in moment)
- Note that x86 model actually has more modes:
  - Traditionally, four "rings" representing priority; most OSes use only two:
    - » Ring  $0 \Rightarrow$  Kernel mode, Ring  $3 \Rightarrow$  User mode
    - » Called "Current Privilege Level" or CPL
  - Newer processors have additional mode for hypervisor ("Ring -1")
- Certain operations restricted to Kernel mode:
  - Modifying page table base (CR3 in x86), and segment descriptor tables
    - » Have to transition into Kernel mode before you can change them!
  - Also, all page-table pages must be mapped only in kernel mode

#### Making it real: X86 Memory model with segmentation (16/32-bit)



Kubiatowicz CS162 ©UCB Spring 2020 Lec 13.27

#### X86 Segment Descriptors (32-bit Protected Mode)


- Segments are either implicit in the instruction (say for code segments) or actually part of the instruction
  - There are 6 registers: SS, CS, DS, ES, FS, GS
- What is in a segment register?
  - A pointer to the actual segment description:

Seament selector [13 bits]

G/L selects between GDT and LDT tables (global vs local descriptor tables)

- RPL: Requestor's Privilege Level (RPL of CS ⇒ Current Privilege Level)
- Two registers: GDTR and LDTR hold pointers to the global and local descriptor tables in memory
  - Includes length of table (for < 2<sup>13</sup>) entries

Descriptor format (64 bits):



G: Granularity of segment [Limit Size] (0: 16bit, 1: 4KiB unit) DB: Default operand size (0: 16bit, 1: 32bit)

A: Freely available for use by software

P: Segment present
DPL: Descriptor Privilege Level: Access requires Max(CPL,RPL)≤DPL

S: System Segment (0: System, 1: code or data)

Type: Code, Data, Segment

Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.29

#### How are segments used?

- One set of global segments (GDT) for everyone, different set of local segments (LDT) for every process
- In legacy applications (16-bit mode):
  - Segments provide protection for different components of user programs
  - Separate segments for chunks of code, data, stacks
    - » RPL of Code Segment ⇒CPL (Current Privilege Level)
  - Limited to 64K segments
- Modern use in 32-bit Mode:
  - Even though there is full segment functionality, segments are set up as "flattened", i.e. every segment is 4GB in size
  - One exception: Use of GS (or FS) as a pointer to "Thread Local" Storage" (TLS)
    - » A thread can make accesses to TLS like this: mov eax, gs(0x0)
- Modern use in 64-bit ("long") mode
  - Most segments (SS, CS, DS, ES) have zero base and no length limits
  - Only FS and GS retain their functionality (for use in TLS)


3/10/20

3/10/20

Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.30

## X86 64: Four-level page table!



#### From x86 64 architecture specification





Figure 4-8. Linear-Address Translation to a 4-KByte Page using 4-Level Paging

- All current x86 processor support a 64 bit operation
- 64-bit words (so ints are 8 bytes) but 48-bit addresses

#### Larger page sizes supported as well




Or larger page sizes, memory is now cheap

3/10/20 Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.33

#### **Inverted Page Table**

- With all previous examples ("Forward Page Tables")
  - Size of page table is at least as large as amount of virtual memory allocated to processes
  - Physical memory may be much less » Much of process space may be out on disk or not in use



- Answer: use a hash table
  - Called an "Inverted Page Table"
  - Size is independent of virtual address space
  - Directly related to amount of physical memory
  - Very attractive option for 64-bit address spaces » PowerPC, UltraSPARC, IA64
- Cons:
  - Complexity of managing hash chains: Often in hardware!

- Poor cache locality of page table Spring 2020

#### Lec 13.35

3/10/20

#### Kubiatowicz CS162 ©UCB Spring 2020

#### Lec 13.36

Figure 4-10. Linear-Address Translation to a 1-GByte Page using 4-Level Paging

9 bits 9 bits 9 bits 9 bits 12 bits 7 bits 9 bits 64bit Virtual Address: Offset

IA64: 64bit addresses: Six-level page table?!?

No!

Too slow Too many almost-empty tables

3/10/20

Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.34


## **Address Translation Comparison**

Disadvantages

Advantage

	Advantages	Disadvantages
Simple Segmentation	Fast context switching: Segment mapping maintained by CPU	External fragmentation
Paging (single-level page)	No external fragmentation, fast easy allocation	Large table size ~ virtual memory Internal fragmentation
Paged segmentation	Table size ~ # of pages in virtual memory, fast easy allocation	Multiple memory references per page access
Two-level pages	allocation	
Inverted Table	Table size ~ # of pages in physical memory	Hash function more complex No cache locality of page table

#### Two Critical Issues in Address Translation




- How to translate addresses fast enough?
  - Every instruction fetch
  - Plus every load / store
  - EVERY MEMORY REFERENCE!
  - More than one translation for EVERY instruction
- What to do if the translation fails?
  - Page fault (Later!)

3/10/20 Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.37

#### How is the Translation Accomplished?



- What does the MMU need to do to translate an address?
- 1-level Page Table
  - Read PTE from memory, check valid, merge address
  - Set "accessed" bit in PTE, Set "dirty bit" on write
- · 2-level Page Table
  - Read and check first level
  - Read, check, and update PTE
- N-level Page Table ...
- MMU does page table Tree Traversal to translate each address
- How can we make this go REALLY fast?
  - Fraction of a processor cycle

3/10/20


3/10/20

Kubiatowicz CS162 ©UCB Spring 2020


Lec 13.38

#### Recall: Memory Hierarchy

· Large memories are slow, only small memory is fast



#### Where and What is the MMU?



- The processor requests READ Virtual-Address to memory system
  - Through the MMU to the cache (to the memory)
- Some time later, the memory system responds with the data stored at the physical address (resulting from virtual → physical) translation
  - Fast on a cache hit, slow on a miss
- So what is the MMU doing?
- On every reference (I-fetch, Load, Store) read (multiple levels of) page table entries to get physical frame or FAULT
  - Through the caches to the memory
  - Then read/write the physical location

#### Recall: CS61c Caching Concept



- Cache: a repository for copies that can be accessed more quickly than the original
  - Make frequent case fast and infrequent case less dominant
- Caching underlies many techniques used today to make computers fast
  - Can cache: memory locations, address translations, pages, file blocks, file names, network routes, etc...
- Only good if:
  - Frequent case frequent enough and
  - Infrequent case not too expensive
- Important measure: Average Access time = (Hit Rate x Hit Time) + (Miss Rate x Miss Time)

3/10/20


Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.41

Lec 13.43

#### Recall: In Machine Structures (eg. 61C) ...

· Caching is the key to memory system performance



Average Memory Access Time (AMAT)

= (Hit Rate x HitTime) + (Miss Rate x MissTime)

Where HitRate + MissRate = 1


HitRate = 90% => AMAT =  $(0.9 \times 1) + (0.1 \times 101) = 11.1 \text{ ns}$ 

HitRate = 99% => AMAT =  $(0.99 \times 1) + (0.01 \times 101) = 2.01 \text{ ns}$ 

MissTime<sub>1.1</sub> includes HitTime<sub>1.1</sub>+MissPenalty<sub>1.1</sub> ≡ HitTime<sub>1.1</sub> +AMAT<sub>1.2</sub>


3/10/20 Kubiatowicz CS162 ©UCB Spring 2020

#### Another Major Reason to Deal with Caching




- Cannot afford to translate on every access
  - At least three DRAM accesses per actual DRAM access
  - Or: perhaps I/O if page table partially on disk!
- Even worse: What if we are using caching to make memory access faster than DRAM access?
- Solution? Cache translations!
  - Translation Cache: TLB ("Translation Lookaside Buffer")

## Why Does Caching Help? Locality!




- Temporal Locality (Locality in Time):
  - Keep recently accessed data items closer to processor
- Spatial Locality (Locality in Space):
  - Move contiguous blocks to the upper levels



#### Recall: Memory Hierarchy

- Take advantage of the principle of locality to:
  - Present as much memory as in the cheapest technology
  - Provide access at speed offered by the fastest technology




3/10/20 Kubiatowicz CS162 ©UCB Spring 2020 Lec 13.45

#### **Translation Look-Aside Buffer**

- Record recent Virtual Page # to Physical Frame # translation
- If present, have the physical address without reading any of the page tables !!!
  - Even if the translation involved multiple levels
  - Caches the end-to-end result
- Was invented by Sir Maurice Wilkes prior to caches
  - People realized "if it's good for page tables, why not the rest of the data in memory?"
- On a TLB miss, the page tables may be cached, so only go to memory when both miss

#### How do we make Address Translation Fast?

- Cache results of recent translations!
  - Different from a traditional cache
  - Cache Page Table Entries using Virtual Page # as the key




3/10/20 Kubiat

Kubiatowicz CS162 ©UCB Spring 2020


Lec 13.46

#### Caching Applied to Address Translation



- · Question is one of page locality: does it exist?
  - Instruction accesses spend a lot of time on the same page (since accesses sequential)
  - Stack accesses have definite locality of reference
  - Data accesses have less page locality, but still some...
- Can we have a TLB hierarchy?
  - Sure: multiple levels at different sizes/speeds

#### What kind of Cache for TLB?



- Remember all those cache design parameters and trade-offs?
  - Amount of Data = N \* L \* K
  - Tag is portion of address that identifies line (w/o line offset)
  - Write Policy (write-thru, write-back), Eviction Policy (LRU, ...)

3/10/20

Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.49

# How might organization of TLB differ from that of a conventional instruction or data cache?

Let's do some review ...


3/10/20 Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.50

#### A Summary on Sources of Cache Misses

- Compulsory (cold start or process migration, first reference): first access to a block
  - "Cold" fact of life: not a whole lot you can do about it
  - Note: If you are going to run "billions" of instruction, Compulsory Misses are insignificant
- Capacity
  - Cache cannot contain all blocks access by the program
  - Solution: increase cache size
- Conflict (collision):
  - Multiple memory locations mapped to the same cache location
  - Solution 1: increase cache size
  - Solution 2: increase associativity
- Coherence (Invalidation): other process (e.g., I/O) updates memory

#### How is a Block found in a Cache?



**Data Select** 


- · Block is minimum quantum of caching
  - Data select field used to select data within block
  - Many caching applications don't have data select field
- Index Used to Lookup Candidates in Cache
  - Index identifies the set
- Tag used to identify actual copy
  - If no candidates match, then declare cache miss

#### Review: Direct Mapped Cache

- Direct Mapped 2<sup>N</sup> byte cache:
  - The uppermost (32 N) bits are always the Cache Tag
  - The lowest M bits are the Byte Select (Block Size = 2<sup>M</sup>)
- Example: 1 KB Direct Mapped Cache with 32 B Blocks
  - Index chooses potential block
  - Tag checked to verify block


3/10/20

- Byte select chooses byte within block




#### Review: Set Associative Cache

- N-way set associative: N entries per Cache Index
  - N direct mapped caches operates in parallel
- Example: Two-way set associative cache
  - Cache Index selects a "set" from the cache
  - Two tags in the set are compared to input in parallel
  - Data is selected based on the tag result




#### Review: Fully Associative Cache

- Fully Associative: Every block can hold any line
  - Address does not include a cache index
  - Compare Cache Tags of all Cache Entries in Parallel
- Example: Block Size=32B blocks
  - We need N 27-bit comparators
  - Still have byte select to choose from within block




#### Where does a Block Get Placed in a Cache?


Example: Block 12 placed in 8 block cache




Set associative:



3/10/20





Fully associative:

block 12 can go

Set Set Set Set 0 1 2 3

#### Which block should be replaced on a miss?

- · Easy for Direct Mapped: Only one possibility
- · Set Associative or Fully Associative:
  - Random
  - LRU (Least Recently Used)
- · Miss rates for a workload:

	2-	way	4-way		8-way		
Size	LRU	<u>Random</u>	LRU I	<u>Random</u>	LRU	<u>Random</u>	
16 KB	5.2%	5.7%	4.7%	5.3%	4.4%	5.0%	
64 KB	1.9%	2.0%	1.5%	1.7%	1.4%	1.5%	
256 KB	1.15%	1.17%	1.13%	1.13%	1.12%	1.12%	

3/10/20

Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.57

#### Review: What happens on a write?

- Write through: The information is written to both the block in the cache and to the block in the lower-level memory
- Write back: The information is written only to the block in the cache
  - Modified cache block is written to main memory only when it is replaced
  - Question is block clean or dirty?
- · Pros and Cons of each?
  - -WT:
    - » PRO: read misses cannot result in writes
    - » CON: Processor held up on writes unless writes buffered
  - -WB:
    - » PRO: repeated writes not sent to DRAM processor not held up on writes
    - » CON: More complex Read miss may require writeback of dirty data

3/10/20

3/10/20


Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.58

#### Questions about caches?

- How does operating system behavior affect cache performance?
- · Switching threads?
- Switching contexts?
- Cache design? What addresses are used?
- What does our understanding of caches tell us about TLB organization?

#### What TLB Organization Makes Sense?



- Needs to be really fast
  - Critical path of memory access
    - » In simplest view: before the cache
    - » Thus, this adds to access time (reducing cache speed)
  - Seems to argue for Direct Mapped or Low Associativity
- · However, needs to have very few conflicts!
  - With TLB, the Miss Time extremely high! (PT traversal)
  - Cost of Conflict (Miss Time) is high
  - Hit Time dictated by clock cycle
- Thrashing: continuous conflicts between accesses
  - What if use low order bits of page as index into TLB?
    - » First page of code, data, stack may map to same entry
    - » Need 3-way associativity at least?
  - What if use high order bits as index?
    - » TLB mostly unused for small programs

#### TLB organization: include protection

- How big does TLB actually have to be?
  - -Usually small: 128-512 entries (larger now)
  - -Not very big, can support higher associativity
- Small TLBs usually organized as fully-associative cache
  - -Lookup is by Virtual Address
  - -Returns Physical Address + other info
- What happens when fully-associative is too slow?
  - -Put a small (4-16 entry) direct-mapped cache in front
  - -Called a "TLB Slice"
- Example for MIPS R3000:

Virtual Address	Physical Address   Dirty		Ref	Valid	Access	ASID
0xFA00	0x0003	Y	N	Y	R/W	34
0x0040	0x0010	N	Y	Y	R	0
0x0041	0x0011	N	Y	Y	R	0

3/10/20

Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.61

#### Example: R3000 pipeline includes TLB "stages"


#### MIPS R3000 Pipeline

Inst Fetch	Dcd/ Reg	ALU / E.A	Memory	Write Reg	
TLB I-Cac	he RF	Operation		WB	
		E.A. TLB	D-Cache		

#### TLB

64 entry, on-chip, fully associative, software TLB fault handler

#### Virtual Address Space



Allows context switching among 64 user processes without TLB flush

3/10/20

Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.62


#### Example: Pentium-M TLBs (2003)

- Four different TLBs
  - Instruction TLB for 4K pages
    - » 128 entries, 4-way set associative
  - Instruction TLB for large pages
    - » 2 entries, fully associative
  - Data TLB for 4K pages
    - » 128 entries, 4-way set associative
  - Data TLB for large pages
    - » 8 entries, 4-way set associative
- All TLBs use LRU replacement policy
- Why different TLBs for instruction, data, and page sizes?

#### Intel Nahelem (2008)

- L1 DTLB
  - 64 entries for 4 K pages and
  - 32 entries for 2/4 M pages,
- L1 ITLB
  - 128 entries for 4 K pages using 4-way associativity and
  - 14 fully associative entries for 2/4 MiB pages
- unified 512-entry L2 TLB for 4 KiB pages, 4-way associative.

#### Current Intel x86 (Skylake, Cascade Lake)



t( Memory Subsystem (10 entries)

#### **Current Example: Memory Hierarchy**

- Caches (all 64 B line size)
  - L1 I-Cache: 32 <u>KiB</u>/core, 8-way set assoc.
  - L1 D Cache: 32 KiB/core, 8-way set assoc., 4-5 cycles load-to-use, Write-back policy
  - L2 Cache: 1 MiB/core, 16-way set assoc., Inclusive, Write-back policy, 14 cycles latency
  - L3 Cache: 1.375 MiB/core, 11-way set assoc., shared across cores, Non-inclusive victim cache, Write-back policy, 50-70 cycles latency
- TLB
  - L1 ITLB, 128 entries; 8-way set assoc. for 4 KB pages
    - » 8 entries per thread; fully associative, for 2 MiB / 4 MiB page
  - L1 DTLB 64 entries; 4-way set associative for 4 KB pages
    - » 32 entries; 4-way set associative, 2 MiB / 4 MiB page translations:
    - » 4 entries; 4-way associative, 1G page translations:
  - L2 STLB: 1536 entries; 12-way set assoc. 4 KiB + 2 MiB pages
    - » 16 entries; 4-way set associative, 1 GiB page translations:

3/10/20

3/10/20

Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.66


#### What happens on a Context Switch?

- Need to do something, since TLBs map virtual addresses to physical addresses
  - Address Space just changed, so TLB entries no longer valid!
- Options?


3/10/20

- Invalidate TLB: simple but might be expensive
  - » What if switching frequently between processes?
- Include ProcessID in TLB
  - » This is an architectural solution: needs hardware
- · What if translation tables change?
  - For example, to move page from memory to disk or vice versa...
  - Must invalidate TLB entry!
    - » Otherwise, might think that page is still in memory!
  - Called "TLB Consistency"


## Putting Everything Together: Address Translation




#### Putting Everything Together: TLB



#### Putting Everything Together: Cache



#### Two Critical Issues in Address Translation



- How to translate addresses fast enough?
  - Every instruction fetch
  - Plus every load / store
  - EVERY MEMORY REFERENCE!
  - More than one translation for EVERY instruction
- · Next: What to do if the translation fails?
  - Page fault! This is a synchronous exception!

# Recall: User→Kernel (Exceptions: Traps & Interrupts)

- A system call instruction causes a synchronous exception (or "trap")
  - In fact, often called a software "trap" instruction
- Other sources of Synchronous Exceptions ("Trap"):
  - Divide by zero, Illegal instruction, Bus error (bad address, e.g. unaligned access)
  - Segmentation Fault (address out of range)
  - Page Fault (for illusion of infinite-sized memory)
- Interrupts are Asynchronous Exceptions:
  - Examples: timer, disk ready, network, etc....
  - Interrupts can be disabled, traps cannot!
- On system call, exception, or interrupt:
  - Hardware enters kernel mode with interrupts disabled
  - Saves PC, then jumps to appropriate handler in kernel
  - Some processors (e.g. x86) also save registers, changes stack
- Handler does any required state preservation not done by CPU:
  - Might save registers, other CPU state, and switches to kernel stack

#### Page Fault


- The Virtual-to-Physical Translation fails
  - PTE marked invalid, Priv. Level Violation, Access violation, or does not exist
  - Causes an Fault / Trap
    - » Not an interrupt because synchronous to instruction execution
  - May occur on instruction fetch or data access
  - Protection violations typically terminate the instruction
- Other Page Faults engage operating system to fix the situation and retry the instruction
  - Allocate an additional stack page, or
  - Make the page accessible Copy on Write,
  - Bring page in from secondary storage to memory demand paging
- Fundamental inversion of the hardware / software boundary

3/10/20

Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.73

#### Next Up: What happens when ...



3/10/20 Kubiatowicz CS162 ©UCB Spring 2020

Lec 13.74

## Summary (1/3)

- Page Tables
  - Memory divided into fixed-sized chunks of memory
  - Virtual page number from virtual address mapped through page table to physical page number
  - Offset of virtual address same as physical address
  - Large page tables can be placed into virtual memory
- Multi-Level Tables
  - Virtual address mapped to series of tables
  - Permit sparse population of address space
- Inverted Page Table
  - Use of hash-table to hold translation entries
  - Size of page table ~ size of physical memory rather than size of virtual memory

## Summary (2/3)

- · The Principle of Locality:
  - Program likely to access a relatively small portion of the address space at any instant of time.
    - » Temporal Locality: Locality in Time
    - » Spatial Locality: Locality in Space
- Three (+1) Major Categories of Cache Misses:
  - Compulsory Misses: sad facts of life. Example: cold start misses.
  - Conflict Misses: increase cache size and/or associativity
  - Capacity Misses: increase cache size
  - Coherence Misses: Caused by external processors or I/O devices
- Cache Organizations:

- Direct Mapped: single block per set
- Set associative: more than one block per set
- Fully associative: all entries equivalent

### Summary (3/3)

- "Translation Lookaside Buffer" (TLB)
  - Small number of PTEs and optional process IDs (< 512)
  - Fully Associative (Since conflict misses expensive)
  - -On TLB miss, page table must be traversed and if located PTE is invalid, cause Page Fault
  - On change in page table, TLB entries must be invalidated
  - -TLB is logically in front of cache (need to overlap with cache access)
- Next Time: What to do on a page fault?

3/10/20

Kubiatowicz CS162 ©UCB Spring 2020

