# minIni

Version 0.3

MININI is a programmer's library to read and write "INI" files in embedded systems. MININI takes little resources and can be configured for various kinds of file I/O libraries.

The principal purpose for MININI is to be used on embedded systems that run on an RTOS (or even without any operating system). MININI requires that such a system provides a kind of storeage and file I/O system, but it does not require that this file I/O system is compatible with the standard  $C/C^{++}$  library —indeed, the standard library is often too big and resource-hungry for embedded systems.

### Contents

Introduction	
INI file syntax	1
Using minIni	2
The "glue" file	2
Unicode	
Line termination	
Multi-tasking	3
FUNCTION REFERENCE.	
Appendix — example glue files	7
stdio (standard $C/C^{++}$ library)	
EFSL (http://www.efsl.be/)	
FatFs & Tiny-FatFs (http://elm-chan.org/)	

#### License

The **software toolkit** "MININI" is copyright © 2008 by ITB CompuPhase. This software toolkit includes the source code of the library and the documentation.

MININI is distributed under the "zlib/libpng" license, which is reproduced below:

This software is provided "as-is", without any express or implied warranty. In no event will the authors be held liable for any damages arising from the use of this software.

Permission is granted to anyone to use this software for any purpose, including commercial applications, and to alter it and redistribute it freely, subject to the following restrictions:

- 1 The origin of this software must not be misrepresented; you must not claim that you wrote the original software. If you use this software in a product, an acknowledgement in the product documentation would be appreciated but is not required.
- 2 Altered source versions must be plainly marked as such, and must not be misrepresented as being the original software.
- 3 This notice may not be removed or altered from any source distribution.

The zlib/libpng license has been approved by the "Open Source Initiative" organization.

#### **Trademarks**

"Microsoft" and "Microsoft Windows" are a registered trademarks of Microsoft Corporation.

"Linux" is a registered trademark of Linus Torvalds.

"CompuPhase" is a registered trademark of ITB CompuPhase.

"Unicode" is a registered trademark of Unicode, Inc.

### Copyright

Copyright © 2008, ITB CompuPhase; Eerste Industriestraat 19–21 Bussum, The Netherlands (Pays Bas); voice: (+31)-(0)35 6939 261; fax: (+31)-(0)35 6939 293 e-mail: info@compuphase.com; homepage: http://www.compuphase.com

The MININI library was derived in part from the article "Multiplatform .INI Files" by Joseph J. Graf in the March 1994 issue of Dr. Dobb's Journal.

The examples and programs in this manual have been included for their instructional value. They have been tested with care, but are not guaranteed for any particular purpose.

## Introduction

MININI is a library to read and write simple configuration files with a format compatible with "INI" files. The MININI library features a small code size footprint and it requires little resources (e.g. RAM). It is therefore suitable for use in (small) embedded systems.

INI files are best known from the Microsoft Windows, where functions like GetProfileString and WriteProfileString read from and write to INI files. The functions in MININI are modelled after the functions of the Windows SDK, but they are not fully compatible with them.

Notable incompatibilities of MININI are:

- ♦ ini\_gets (replacement for GetProfileString) does not read all key names in a section when parameter Key is NULL. Similarly, ini\_gets does not read all sections names when parameter Section is NULL.
- ♦ The length of a line is limited to a maximum in MININI. The maximum length is configurable (at compile-time, not at run-time) and it may be short on embedded systems.
- ♦ Quoted values are currently not supported. That is, if a value behind a key is enclosed in quotes, ini\_gets will return that value with the quotes—it will not strip the quotes from the value, as the Microsoft Windows function GetProfileString does.

Although the main feature of MININI is that it is small and minimal, it has a few other features:

- ♦ MININI supports reading keys that are outside a section, and it thereby supports configuration files that do not use sections (but that are otherwise compatible with INI files).
- ♦ The colon is allowed as an alternative to the equal sign on keys. That is, the string "Name: Value" is equivalent to "Name=Value"
- ♦ Leading and trailing white space around key names and values is ignored.
- Section and key name comparisons are case insensitive (similar to Microsoft Windows).
- ♦ You can optionally set the line termination (for text files) that MININI will use.

## INI file syntax

INI files have a simple syntax with name/value pairs in a plain text file. The name must be unique (per section) and the value must fit on a single line. In the API and in this documentation, the "name" for a setting is denoted as the key for the setting. The key and the value are separated by an equal sign ("=").

INI files are commonly separated into sections —in MININI, this is optional. A section is a name between square brackets, like "[Recipes]".

There exists a few variations on INI files that MININI supports, and variations that MININI does not support. For example, MININI supports the colon (":") as an alternative to the equal sign for the key/value delimiter; it also ignores spaces around the "=" or ":" delimitor, but it does not ignore spaces between the brackets in a section name. In other words, it is best not to put spaces behind the opening bracket "[" or before the closing bracked "]" of a section name.

It is commonly advised to start comments with a seminolon (";") and to put any comments on a line by their own. MININI does not treat lines that start with a semicolon in a special way. That said, names of keys should not contain start a semicolon and a line that starts with a semicolon will thereby not match any valid key. Using a semicolon to add comments is therefore more a convention than part of the INI file format.

# Using minIni

The first step in using MININI is making sure that it compiles. The library consists of only one C file and two header files, so the amount of configuration to do is minimal. If you cannot use the standard C/C<sup>++</sup> library, there is, however, a configuration file (or "glue" file) that you must make or customize. This file is explained in the next section. The MININI distribution comes with a default configuration file that maps to the standard C library (specifically the file I/O functions from the "stdio" package) and example glue files for two embedded file system libaries for embedded systems —see the appendix of this manual.

Once you have a good glue file, you can add the source file of MININI to your project and include the header file "minIni.h" in your source code files. In your source code, you can then use the four functions that the MININI library provides to read text and values from INI files and to write text and values to an INI file. See the function reference for details.

When running in an Unicode environment or when moving the INI file across platforms, there may be other considerations concerning the use of MININI —see the relevant sections in this chapter.

## The "glue" file

The MININI library must be configured for a platform with the help of a so-called "glue file". This glue file contains macros (and possibly functions) that map file reading and writing functions used by the MININI library to those provided by the operating system. The glue file must be called "minGlue.h".

The MININI source code requires functions from a file I/O library to perform the actual reading and writing. This can be any library; MININI does not rely on the availability of a standard C library, because embedded operating systems may have limited support for file I/O. Even on full operating systems, separating the file I/O from the INI format parsing carries advantages, because it allows you to cache the INI file and thereby enhance performance.

If you are not using the standard C/C<sup>++</sup> file I/O library, chances are that you need a different handle or "structure" to identify the storeage than the ubiquitous "FILE\*" type. If this is the case, you must define the type that MININI uses in the glue file.

#define INI\_FILETYPE HANDLE

The MININI functions will declare variables of this type and pass these variables to sub-functions (including the glue interface functions) by reference.

Another item that needs to be configured is the buffer size. The functions in the MININI library allocate this buffer on the stack, so the buffer size is directly related to the stack usage. In addition, the buffer size determines the maximum line length that is supported in the INI file and the maximum path name length for the temporary file. For example, minGlue.h could contain the definition:

#define INI\_BUFFERSIZE 512

The above macro limits the line length of the INI files supported by MININI to 512 characters.

The temporary file is only used when writing to INI files. The MININI routines copy/change the INI file to a temporary file and then rename that temporary file to the original file. This approach uses the least amount of memory. The path name of the temporary file is the same as the input file, but with the last character set to a tilde ("~").

#### Unicode

MININI can be compiled with Unicode support, but it delegates storing the actual characters to the "glue" routines. Although you can use standard Unicode file reading and writing routines to create and query INI files in Unicode text format, it is advised to keep the INI file format as ASCII, for best compatibility with other implementations. To store Unicode characters in the ASCII file, convert the Unicode data to (and from) UTF-8.

It is advised to keep the section and key names as ASCII or ANSI Latin-1; only the "values" of each key should be encoded as UTF-8.

#### Line termination

On Microsoft and DOS, lines of text files are usually terminated by a CR-LF character pair (" $\r$ " in C/C<sup>++</sup> terminology). On Linux and Unix, the line terminator is only the LF character and on the Macintosh, it is only the CR character.

The line termination convention is not important when reading from INI files, because MININI strips off all trailing white space (and control characters such as carriage-return and line-feed are considered white space). The line termination convention is also not important when the INI file is only accessed by MININI. Finally, if you use the standard  $C/C^{++}$  library as the back-end for reading and writing files, this library already handles the platform-dependent line termination for you.

However, if you wish to read and adjust the INI files with other across platforms —e.g. edit the INI file with a simple text editor as Notepad on Microsoft Windows and then store it on an embedded device with a Linux-based operating system, then it may be advantageous to tell MININI the line termination characters to use. To do so, define the macro INI\_LINETERM in the file "minGlue.h" and set it to the character or characters to use. For example:

#define INI\_LINETERM "\r\n"

# Multi-tasking

The MININI library does not have any global variables and it does not use any dynamically allocated memory. Yet, the library should not be considered "thread-safe" or re-entrant, because it implicitly uses a particular shared resource: the file system.

Multiple tasks reading from an INI file do not pose a problem. However, when one task is writing to an INI file, no other tasks should access this INI file—neither for reading, nor for writing. It might be easier, in the implementation, to serialize *all* accesses of the INI file.

The first advise in protecting resources from concurrent access in a multi-tasking environment is to avoid sharing resources between tasks. If only a single task uses a resource, no semaphore

### 4 — Multi-tasking

protection is necessary and no priority inversion or deadlock problems can occur. This advise also applies to the MININI library. If possible, make a single task the "owner" of the INI file and create a client/server architecture for other tasks to query and adjust settings.

If the INI file must be shared between tasks (and at least one of the tasks writes to the INI file), you need to write wrappers around the functions of the MININI library that block on a mutex or binary semaphore.

### Function reference

ini\_getl Read a numeric value

ini\_get1 returns the numeric value that is found in the given section and at the given key.

Syntax: long ini\_getl(const char \*Section, const char \*Key, long DefValue, const char \*Filename)

Section The name of the section. If this parameter is *NULL* or an empty

string, the Key is searched outside any section.

Key The name of the key. This parameter may not be NULL.

DefValue The default value, which will be returned if the key is not present in

the INI file.

Filename The full path name of the INI file.

Returns: The value read at the given key, or DefValue if the key is not present in the given

section.

Notes: The number must be in decimal format. If the key is present, but it does not

represent a decimal number, this function may return zero or an incorrect value.

See also: ini\_gets, ini\_putl

ini\_gets Read a string

ini\_gets reads the textual value that is found in the given section and at the given key.

Syntax: int ini\_gets(const char \*Section, const char \*Key,

const char \*DefValue, char \*Buffer, int BufferSize,

const char \*Filename)

Section The name of the section. If this parameter is *NULL* or an empty

string, the Key is searched outside any section.

Key The name of the key. This parameter may not be *NULL*.

DefValue The default value, which will be returned (in parameter Buffer) if

the key is not present in the INI file.

Buffer The buffer into which this function will store the data read.

BufferSize The size of the buffer pointed at by parameter Buffer. This is the

maximum number of characters that will be read and stored.

Filename The full path name of the INI file.

Returns: The number of characters read into parameter Buffer.

See also: ini\_getl, ini\_puts

ini\_putl Store a numeric value

ini\_putl stores the numeric value that in the given section and at the given key.

Syntax: int ini\_putl(const char \*Section, const char \*Key, long Value, const char \*Filename)

Section The name of the section. If this parameter is *NULL* or an empty

string, the Key is stored outside any section (i.e. above the first

section, if the INI file has any sections).

Key The name of the key. This parameter may not be NULL.

Value The value to write at the key and the section.

Filename The full path name of the INI file.

Returns: 1 on success, 0 on failure.

See also: ini\_getl, ini\_puts

ini\_puts Store a string

ini\_puts stores the text parameter that in the given section and at the given key.

Syntax: int ini\_puts(const char \*Section, const char \*Key, const char \*Value, const char \*Filename)

Section The name of the section. If this parameter is NULL or an empty

string, the Key is stored outside any section (i.e. above the first

section, if the INI file has any sections).

Key The name of the key. If this parameter is *NULL*, the function erases

all keys (and their associated values) from the section.

Value The text to write at the key and the section. This string should

not contain any line breaking characters, such as carriage-return or line-feed characters. If this parameter is NULL, the function erases

the key/value pair.

Filename The full path name of the INI file.

Returns: 1 on success, 0 on failure.

Notes: This function can also be used to delete entries or sections, by setting the Key or

Value parameters to NULL.

See also: ini\_gets, ini\_putl

# Appendix — example glue files

## stdio (standard C/C++ library)

```
/* Glue functions for the minIni library, based on the C/C++ stdio library
    Or better said: this file contains macros that maps the function interface
    used by minIni to the standard C/C++ file I/O functions.
   Copyright (c) ITB CompuPhase, 2008
   This software is provided "as-is", without any express or implied warranty.
   In no event will the authors be held liable for any damages arising from
    the use of this software.
   Permission is granted to anyone to use this software for any purpose,
    including commercial applications, and to alter it and redistribute it
    freely, subject to the following restrictions:
   1. The origin of this software must not be misrepresented; you must not
        claim that you wrote the original software. If you use this software in
        a product, an acknowledgment in the product documentation would be
        appreciated but is not required.
    2. Altered source versions must be plainly marked as such, and must not be
        misrepresented as being the original software.
   3. This notice may not be removed or altered from any source distribution.
    Version: $Id: minGlue-stdio.h 3 2008-04-28 08:29:33Z thiadmer.riemersma $
#define INI_BUFFERSIZE 512
                                  /* maximum line length, maximum path length */
/* map required file I/O to the standard C library */
#include <stdio.h>
#define ini_openread(filename,file) ((*(file) = fopen((filename),"rt")) != NULL)
#define ini_openwrite(filename,file) ((*(file) = fopen((filename),"wt")) != NULL)
                                     fclose(*(file))
#define ini_close(file)
#define ini_read(buffer,size,file)
                                     fgets((buffer),(size),*(file))
#define ini write(buffer.file)
                                     fputs((buffer),*(file))
#define ini_rename(source,dest)
                                     rename((source),(dest))
#define ini_remove(filename)
                                     remove(filename)
```

## EFSL (http://www.efsl.be/)

```
/* Glue functions for the minIni library, based on the EFS Library, see
   http://www.efsl.be/
   Copyright (c) ITB CompuPhase, 2008
\boldsymbol{\ast} This software is provided "as-is", without any express or implied warranty.
   In no event will the authors be held liable for any damages arising from
   the use of this software.
   Permission is granted to anyone to use this software for any purpose,
   including commercial applications, and to alter it and redistribute it
   freely, subject to the following restrictions:
   1. The origin of this software must not be misrepresented; you must not
       claim that you wrote the original software. If you use this software in
       a product, an acknowledgment in the product documentation would be
       appreciated but is not required.
   2. Altered source versions must be plainly marked as such, and must not be
       misrepresented as being the original software.
   3. This notice may not be removed or altered from any source distribution.
   Version: $Id: minGlue-efsl.h 3 2008-04-28 08:29:33Z thiadmer.riemersma $
```

```
/* maximum line length, maximum path length */
#define INI_BUFFERSIZE 256
#include "efs.h"
#define INI_FILETYPE
                      EmbeddedFile
#define INI_LINETERM
                      "\r\n"
                              /* set line termination explicitly */
extern EmbeddedFileSystem g_efs;
#define ini_openread(filename,file)
                                   (file_fopen((file),&g_efs.myFs, \
                                     (char*)(filename),'r') == 0)
#define ini_openwrite(filename,file) (file_fopen((file),&g_efs.myFs, \
                                     (char*)(filename),'w') == 0)
#define ini_close(file)
                                   file_fclose(file)
#define ini_read(buffer,size,file) (file_read((file),(size),(buffer)) > 0)
                                 file_write((file),strlen(buffer),(char*)(buffer))
#define ini_write(buffer,file)
#define ini_remove(filename)
                                   rmfile(&g_efs.myFs,(char*)(filename))
/* EFSL lacks a rename function, so instead we copy the file to the new name
*/
static int ini_rename(char *source, const char *dest)
{
 EmbeddedFile fr, fw;
 int n;
  if (file_fopen(&fr, &g_efs.myFs, source, 'r') != 0)
   return 0;
 if (rmfile(&g_efs.myFs, (char*)dest) != 0)
 if (file_fopen(&fw, &g_efs.myFs, (char*)dest, 'w') != 0)
  /* With some "insider knowledge", we can save some memory: the
  * "dest" parameter. It was built in buffer and this buffer has
  * the size INI_BUFFERSIZE. We can reuse this buffer for copying
  * the file.
  */
 while (n=file_read(&fr, INI_BUFFERSIZE, source))
   file_write(&fw, n, source);
 file fclose(&fr):
 file fclose(&fw):
  /* Now we need to delete the source file. However, we have garbled
  * the buffer that held the filename of the source. So we need to
  * build it again.
 ini_tempname(source, dest, INI_BUFFERSIZE);
 return rmfile(&g_efs.myFs, source) == 0;
}
```

## FatFs & Tiny-FatFs (http://elm-chan.org/)

```
Glue functions for the minIni library, based on the FatFs and Tiny-FatFs
 libraries, see http://elm-chan.org/fsw/ff/00index_e.html
* Copyright (c) ITB CompuPhase, 2008
* This software is provided "as-is", without any express or implied warranty.
st In no event will the authors be held liable for any damages arising from
* the use of this software.
* Permission is granted to anyone to use this software for any purpose,
* including commercial applications, and to alter it and redistribute it
* freely, subject to the following restrictions:
st 1. The origin of this software must not be misrepresented; you must not
      claim that you wrote the original software. If you use this software in
       a product, an acknowledgment in the product documentation would be
```

```
appreciated but is not required.
   2. Altered source versions must be plainly marked as such, and must not be
        misrepresented as being the original software.
   \ensuremath{\mathtt{3}}. This notice may not be removed or altered from any source distribution.
    Version: $Id: minGlue-FatFs.h 3 2008-04-28 08:29:33Z thiadmer.riemersma $
#define INI_BUFFERSIZE 256
                                  /* maximum line length, maximum path length */
/* You must set _USE_STRFUNC to 1 or 2 in the include file ff.h (or tff.h)
 * to enable the "string functions" fgets() and fputs().
 */
#include "ff.h"
                                  /* include tff.h for Tiny-FatFs */
#define INI_FILETYPE
#define ini_openread(filename,file)
                                     (f_open((file),(filename), \
                                        FA_READ+FA_OPEN_EXISTING) == 0)
#define ini_openwrite(filename,file) (f_open((file),(filename), \
                                        FA_WRITE+FA_CREATE_ALWAYS) == 0)
#define ini_close(file)
                                      f_close(file)
#define ini_read(buffer,size,file)
                                      fgets((buffer),(size),(file))
#define ini_write(buffer,file)
                                      fputs((buffer),(file))
#define ini_rename(source,dest)
                                      f_rename((source),(dest))
                                      f_unlink(filename)
#define ini_remove(filename)
```