

Slony Guide Version slony

1	Installation	3
1.1	Installing Slony Replication on a RHEL/CentOS Host	3
1.2	Installing Slony Replication on a Debian or Ubuntu Host	6
1.3	Installing Slony Replication on a Windows Host	8
2	Configuring Slony Replication	14
3	Uninstalling Slony	15

## 1 Installation

This section walks you through installing Slony Replication on a RHEL/CentOS host, a Debian/Ubuntu host, and a Windows host.

The following table lists the Advanced Server versions and platforms supported by Slony Replication.

VersionAdvanced Server VersionsSupported PlatformsSlony Replication 2.2.8Advanced Server 11 and 12

# 1.1 Installing Slony Replication on a RHEL/CentOS Host

If you have used an RPM package to install Advanced Server on the host on which you will be installing Slony Replication, you have probably already created the EnterpriseDB repository configuration file and have EnterpriseDB credentials. If that is the case, you can install Slony Replication with the following command:

On RHEL/CentOS 6 and 7:

yum -y install edb-as12-slony-replication

On RHEL/CentOS 8:

dnf -y install edb-as12-slony-replication

If you have not previously created the repository configuration file, follow the steps given below to create the file and to install Slony Replication.

Before creating the repository configuration file, you must have credentials that allow access to the EnterpriseDB repository. For information about requesting credentials, visit the EnterpriseDB website.

1. To create the repository configuration file, assume superuser privileges, and invoke one of the following platform-specific commands:

On RHEL/CentOS 6 and 7:

yum -y install https://yum.enterprisedb.com/edb-repo-rpms/edb-repo-latest.noarch.rpm

On RHEL/CentOS 8:

dnf -y install https://yum.enterprisedb.com/edb-repo-rpms/edb-repo-latest.noarch.rpm

The repository configuration file is named <a href="edb.repo">edb.repo</a>; the file resides in <a href="/etc/yum.repos.d">/etc/yum.repos.d</a>.

2. After creating the edb.repo file, use your choice of editor to open this file. Ensure the enabled parameter value is 1, and replace the username and password placeholders in the baseurl specification with the credentials of a registered EnterpriseDB user.

#### [edb]

name=EnterpriseDB RPMs \$releasever - \$basearch

baseurl=https://<username>:

<password>@yum.enterprisedb.com/edb/redhat/rhel-\$releasever-\$basearch

enabled=1

gpgcheck=1

gpgkey=file:///etc/pki/rpm-gpg/ENTERPRISEDB-GPG-KEY

- 3. Save your changes to the configuration file and exit the editor.
- 4. Execute the following commands to update the metadata:

yum clean all

yum makecache

5. On RHEL/CentOS 8, you need to enable the PowerTools repo with the following command:

dnf config-manager --set-enabled PowerTools

6. Before installing Slony Replication, you must install the Extra Packages for Enterprise Linux (EPEL) release package by executing the following command:

On RHEL/CentOS 6 and 7:

yum -y install epel-release

On RHEL/CentOS 8:

dnf -y install epel-release

Note

You may need to enable the [extras] repository definition in the CentOS-Base.repo file (located in /etc/yum.repos.d).

7. Then, use one of the following platform-specific command to install Slony Replication.

On RHEL/CentOS 6 and 7:

yum -y install edb-as12-slony-replication

On a RHEL/CentOS 8:

dnf -y install edb-as12-slony-replication

The following table lists the path of the service, installation, and configuration files.

Platform Service File Path Installation Configuration
File Path File Path

Platform	Service File Path	Installation File Path	Configuration File Path
RHEL/CentOS 6	/etc/init.d/edb-slony- replication-12	/usr/edb/as12	The configuration file slony-replication.ini is located in /etc/edb/slony-replication12
RHEL/CentOS 7 and 8	/usr/lib/systemd/system/edb-slony-replication-12.service	/usr/edb/as12	The configuration file slony-replication.ini is located in /etc/edb/slony-replication12

# 1.2 Installing Slony Replication on a Debian or Ubuntu Host

You must install Advanced Server before installing Slony Replication. For details about installing and configuring Advanced Server, see the EDB Postgres Advanced Server Installation Guide. To install a package on a Debian or Ubuntu host, you must have credentials to access the EnterpriseDB repository. If you need EnterpriseDB credentials, visit the EnterpriseDB website.

The following steps will walk you through using the EnterpriseDB repository to install a DEB package. When using the commands, replace the username and password with the credentials provided by EnterpriseDB.

Please note that if you are using the pdf version of this document, using cut/paste to copy command may result in extra spaces or carriage returns in the pasted command. If a command fails, check the command carefully for additional characters.

1. Assume superuser privileges:

sudo su -

2. Configure the EnterpriseDB repository:

sh -c 'echo "deb https://<username>:
<password>@apt.enterprisedb.com/\$(lsb\_release -cs)-edb \$(lsb\_release -cs)
main" > /etc/apt/sources.list.d/edb-\$(lsb\_release -cs).list'

3. Add support to your system for secure APT repositories:

apt-get install apt-transport-https

4. Add the EDB signing key:

wget -q -O - https://<username>:<password>@apt.enterprisedb.com/edb-deb.gpg.key | apt-key add -

5. Update the repository metadata:

apt-get update

6. Install DEB package:

apt-get install edb-as12-slony-replication

The following table lists the path of the service, installation, and configuration path.

Service File Path	Installation File Path	Configuration File Path
/lib/systemd/system/edb- as12-slony- replication.service	/usr/lib/edb- as/12	The configuration file named slony- replication.ini is located in /etc/edb/slony-replication12

## 1.3 Installing Slony Replication on a Windows Host


Graphical installers for Slony Replication are available via StackBuilder Plus (for Advanced Server hosts) or Stack Builder (on PostgreSQL hosts). You can access StackBuilder Plus through your Windows start menu.

Perform the following steps to install Slony Replication:

1. Open StackBuilder Plus and select your Advanced Server installation from the drop-down list on the Welcome window. Click Next to continue to the application selection page.




2. Expand the Replication Solutions node, and check the box next to the Slony Replication version. Click Next to continue.




3. The selected packages and the default download directory are displayed. Change the download directory location if required. Click Next.




4. Once you have downloaded the installation files, a confirmation message is displayed. Click Next to start the Slony Replication installation.




5. Select an installation language and click OK.




6. The installer welcomes you to the setup wizard. Click Next.




7. Use the Installation Directory field to specify the directory in which you wish to install Slony Replication (the default installation directory is C:\Program Files\edb\as12) Then, click Next to continue.




8. The Ready to Install window notifies you when the installer has all of the information needed to install Slony Replication on your system. Click Next to install Slony Replication. Progress bars inform you as the installation progresses.



9. The installer notifies you when the setup wizard has completed the installation. Click Finish to exit the installer.



#### 10. Click Finish to exit the StackBuilder Plus.



## 2 Configuring Slony Replication

On a CentOS and Debian host, the configuration file (slony-replication.ini) is located in /etc/edb/slony-replication12/; use the configuration file to specify connection information for the master and standby nodes.

On a Windows host, the configuration files are named master.conf.sample and slave.conf.sample, and are located in the /etc directory, under the Advanced Server installation; before configuring Slony Replication, you must rename the configuration files to master.conf and slave.conf.

For information about configuring a Slony Replication environment, please refer to the Slony official project documentation.

After specifying configuration options, you must start the Slony Replication service on all nodes of the replication environment. For detailed information about controlling a service, see EDB Postgres Advanced Server Installation Guide.

After installing, configuring and starting the Slony Replication, on a Linux system, you must manually configure your system to autostart the service when your system reboots.

To configure a service to autostart on a Linux system, open a command line, assume superuser privileges, and enter the following command.

On a Redhat-compatible Linux system:

/sbin/chkconfig service\_name on

Where <a href="mailto:service\_name">service\_name</a> specifies the name of the service.

On a Debian-compatible Linux system, use the command:

/usr/sbin/update-rc.d service name enable

Where <a href="mailto:service\_name">service\_name</a> specifies the name of the service.

Please note that if you are using a Windows system, the Slony Replication service will be configured to autostart by default. On Windows, you can use the Service Properties dialog to control the service startup type.

# 3 Uninstalling Slony

This section walks you through uninstalling Slony Replication.

## Uninstalling Slony Replication on a RHEL/CentOS Host

To uninstall Slony Replication on a RHEL/CentOS host, assume identity of the root user and invoke the following command:

On RHEL/CentOS 6 and 7:

yum remove edb-as12-slony-replication\*

On RHEL/CentOS 8:

dnf remove edb-as12-slony-replication\*

#### Uninstalling Slony Replication on a Debian or Ubuntu Host

To uninstall Slony Replication on a Debian or Ubuntu host, invoke the following command:


apt-get remove edb-as12-slony-replication\*

### Uninstalling Slony Replication on a Windows Host

The Slony Replication graphical installer creates an uninstaller named uninstalledb-as12-slony-replication in the installation directory (the default location is C:\Program Files\edb\as12).

To uninstall Slony Replication on a Windows Host:

1. Navigate into the directory that contains the uninstaller and assume superuser privileges. Open the uninstaller uninstalled-as12-slony-replication and click Yes to begin uninstalling Slony Replication:



2. The uninstallation process begins. Click OK once the process completes.

