Tcl Variable Utilities

Version 3.1

Alex Baker

https://github.com/ambaker1/vutil

October 23, 2023

Abstract

The "vutil" package provides utilities such as read-only variables and TclOO garbage collection.

This package is also a Tin package, and can be loaded in as shown below:

Example 1: Installing and loading "vutil"

Code

package require tin
tin add -auto vutil https://github.com/ambaker1/vutil install.tcl 3.0tin import vutil

Default Variable Values

The command *default* assigns a default value to a variable if it does not exist. This can be used to write scripts that behave like procedures with default values.

default \$varName \$value

\$varNameName of variable to set\$valueDefault value for variable

The examples below shows how default values are only applied if the variables do not exist.

```
Example 2: Variable defaults

Code:

set a 5
default a 7
puts $a
unset a; # variable no longer exists
default a 7
puts $a

Coutput:

5
7
```

```
Example 3: Overriding default values in file 'putsMessage.tcl'

Code:

source putsMessage.tcl
set message {hello world}
source putsMessage.tcl

Output:
foo bar
hello world
```

```
Example 4: File 'putsMessage.tcl'

Code:

default message {foo bar}
puts $message
```

Read-Only Variables

The command *lock* uses Tcl variable traces to make a read-only variable. If attempting to modify a locked variable, it will throw a warning, but not an error. This can be used to override values in a script from a top-level, allowing the user to run a parameter study without modifying the source scripts.

lock \$varName <\$value>

\$varName Variable name to lock.

\$value Value to lock variable at. Default self-locks (uses current value).

The command *unlock* unlocks previously locked variables so that they can be modified again.

```
unlock $name1 $name2 ...
```

\$name1 \$name2 ... Variables to unlock.

```
Example 5: Variable locks

Code:

lock a 5
set a 7; # throws warning to stderr channel
puts $a
unlock a
set a 7
puts $a

Variable locks

Code:

lock a 5
set a 7; # throws warning to stderr channel
puts $a

Variable locks

Set a 7; # throws warning to stderr channel
puts $a

Coutput:

failed to modify "a": read-only
5
7
```

Note: You can lock array elements, but not an entire array.

Variable-Object Ties

As of Tcl version 8.6, there is no garbage collection for Tcl objects, they have to be removed manually with the *destroy* method. The command *tie* is a solution for this problem, using variable traces to destroy the corresponding object when the variable is unset or modified. For example, if an object is tied to a local procedure variable, the object will be destroyed when the procedure returns.

tie \$varName <\$object>

\$varName Name of variable for garbage collection.

\$object Object to tie variable to. Default self-ties (uses current value).

In similar fashion to unlock, tied variables can be untied with the command untie.

```
untie $name1 $name2 ...
```

\$name1 \$name2 ... Variables to untie.

```
Example 6: Variable-object ties
Code:
 oo::class create foo {
     method sayhello {} {
          puts {hello world}
 }
 tie a [foo create bar]
 set b $a; # object alias
 $a sayhello
 $b sayhello
 unset a; # destroys object
 $b sayhello; # throws error
Output:
 hello world
 hello world
 invalid command name "::bar"
```

Note: You can tie array elements, but not an entire array, and you cannot tie a locked variable.

Garbage Collection Superclass

The class ::vutil::GC is a TclOO superclass that includes garbage collection. This class is not exported, and not intended for direct use, as it is simply a template for classes with built-in garbage collection, by tying the object to a specified variable using tie. Below is the syntax for the superclass constructor.

```
::vutil::GC new $varName
```

::vutil::GC create \$name \$varName

\$varNameName of variable for garbage collection.\$nameName of object (for "create" method).

In addition to tying the object to a variable in the constructor, the ::vutil::GC superclass also provides a public copy method that sets up garbage collection: "-->", which calls the private method CopyObject

```
$gcObj --> $varName
```

```
my CopyObject $varName
```

\$varName

Name of variable for garbage collection.

Below is an example of how this superclass can be used to build garbage collection into a TclOO class.

```
Example 7: Simple container class
Code:
 oo::class create value {
      superclass ::vutil::GC
      variable myValue
      constructor {varName {value {}}} {
          set myValue $value
          next $varName
     method set {value} {set myValue $value}
     method value {} {return $myValue}
 }
 value new x {hello world}; # create new value, tie to x
  [$x --> y] set {foo bar}; # copy to y, set y to {foo bar}
 puts [$x value]
 puts [$y value]
Output:
 hello world
 foo bar
```

Container Superclass

The class ::vutil::Container is a TclOO superclass, built on-top of the ::vutil::GC superclass. In addition to the copy method "-->", this class stores a value in the variable "self", which can be accessed with the methods GetValue and SetValue. This class is not exported, and not intended for direct use, but rather is a template for container classes. Below is the syntax for the superclass constructor.

::vutil::Container new \$varName <\$value>

::vutil::Container create \$name \$varName <\$value>

\$varName
Name of variable for garbage collection.
\$value
Value to store in container. Default blank.
\$name
Name of object (for "create" method).

Calling a container object by itself calls the GetValue method, which queries the value in the container.

\$containerObj

my GetValue

The assignment operator, "=", calls the SetValue method, which sets the value in the container.

\$containerObj = \$value

my SetValue \$value

\$value

Value to store in container.

The pipe operator, "/", calls the *TempObject* method, which copies the object to a temporary object, evaluates the method, and returns the result, or the temporary object value if the result is the temporary object.

\$containerObj | \$method \$arg ...

my TempObject \$method \$arg ...

\$method Method to evaluate in temporary object.

\$arg ... Arguments for method.

Example 8: Advanced container class

```
Code:
 # Create a class for manipulating lists of floating point values
 oo::class create vector {
     superclass ::vutil::Container
     variable self; # Access the "self" variable from superclass
     method SetValue {value} {
         # Convert to double
         next [lmap x $value {::tcl::mathfunc::double $x}]
     }
     method print {args} {
         puts {*}$args $self
     method += {value} {
         set self [lmap x $self {expr {$x + $value}}]
         return [self]
     }
     method -= {value} {
         set self [lmap x $self {expr {$x - $value}}]
         return [self]
     }
     method *= {value} {
         set self [lmap x $self {expr {$x * $value}}]
         return [self]
     }
     method /= {value} {
         set self [lmap x $self {expr {$x / $value}}]
         return [self]
     }
     method @ {index args} {
         if {[llength $args] == 0} {
             return [lindex $self $index]
         } elseif {[llength $args] != 2 || [lindex $args 0] ne "="} {
             return -code error "wrong # args: should be\
                      \"[self] @ index ?= value?\""
         lset self $index [::tcl::mathfunc::double [lindex $args 1]]
         return [self]
     export += -= *= /= @
 vector new x \{1 2 3\}
 puts [$x | += 5]; # perform operation on temp object
 [$x += 5] print; # same operation, on main object
 puts [$x @ end]; # index into object
Output:
 6.0 7.0 8.0
 6.0 7.0 8.0
 8.0
```