- Examples

The following examples explain common usages of smart pointers in embedded programming.

WE'LL COVER THE FOLLOWING ^ Example 1 Explanation Example 2 Explanation

Example 1#

To get a visual idea of the life cycle of the resource, there is a short message in the constructor and destructor of MyInt (lines 8 - 16).

```
// sharedPtr.cpp
                                                                                 G
#include <iostream>
#include <memory>
using std::shared_ptr;
struct MyInt{
 MyInt(int v):val(v){
   std::cout << " Hello: " << val << std::endl;</pre>
 ~MyInt(){
   std::cout << " Good Bye: " << val << std::endl;</pre>
 int val;
};
int main(){
 std::cout << std::endl;</pre>
 shared_ptr<MyInt> sharPtr(new MyInt(1998));
 std::cout << "sharedPtr.use_count(): " << sharPtr.use_count() << std::endl;</pre>
```

```
shared_ptr<MyInt> locSharPtr(sharPtr);
    std::cout << "locSharPtr.use_count(): " << locSharPtr.use_count() << std::endl;
}
std::cout << "sharPtr.use_count(): " << sharPtr.use_count() << std::endl;

shared_ptr<MyInt> globSharPtr= sharPtr;
std::cout << "sharPtr.use_count(): " << sharPtr.use_count() << std::endl;
globSharPtr.reset();
std::cout << "sharPtr.use_count(): " << sharPtr.use_count() << std::endl;
sharPtr= shared_ptr<MyInt>(new MyInt(2011));
std::cout << std::endl;
}</pre>
```







[]

Explanation

- In line 22, we create MyInt(1998), which is the resource that the smart pointer should address. By using sharPtr->val, we have direct access to the resource (line 23).
- The output of the program shows the number of references counted. It starts in line 24 with 1. It then has a local copy shartPtr in line 28 and goes to 2. The program then returns to 1 after the block (lines 27-30).
- The copy assignment call in line 33 modifies the reference counter. The
 expression sharPtr= shared_ptr<MyInt>(new MyInt(2011) in line 38 is more
 interesting.
- First, the resource MyInt(2011) is created in line 38 and assigned to sharPtr. Consequently, the destructor of sharPtr is invoked. sharedPtr was the exclusive owner of the resource new MyInt(1998) (line 22).
- The last new resource MyInt(2011) will be destroyed at the end of main.

Example 2

We can quite easily push std::shared_ptr onto an
std::vector<std::shared_ptr<int>> with different deleters. The special deleter
will be stored in the control block.

In this example, we create a special std::shared_ptr that logs how much

memory has already been released.

```
// sharedPtrDeleter.cpp
#include <iostream>
#include <memory>
#include <random>
#include <typeinfo>
template <typename T>
class Deleter{
public:
  void operator()(T *ptr){
   ++Deleter::count;
    delete ptr;
  void getInfo(){
    std::string typeId{typeid(T).name()};
    size_t sz= Deleter::count * sizeof(T);
    std::cout << "Deleted " << Deleter::count << " objects of type: " << typeId << std::endl;</pre>
    std::cout <<"Freed size in bytes: " << sz << "." << std::endl;</pre>
    std::cout << std::endl;</pre>
private:
  static int count;
};
template <typename T>
int Deleter<T>::count=0;
typedef Deleter<int> IntDeleter;
typedef Deleter<double> DoubleDeleter;
void createRandomNumbers(){
  std::random_device seed;
  std::mt19937 engine(seed());
  std::uniform_int_distribution<int> thousand(1,1000);
  int ranNumber= thousand(engine);
  for ( int i=0 ; i <= ranNumber; ++i) std::shared_ptr<int>(new int(i),IntDeleter());
}
int main(){
  std::cout << std::endl;</pre>
    std::shared_ptr<int> sharedPtr1( new int,IntDeleter() );
    std::shared_ptr<int> sharedPtr2( new int,IntDeleter() );
    auto intDeleter= std::get_deleter<IntDeleter>(sharedPtr1);
    intDeleter->getInfo();
    sharedPtr2.reset();
    intDeleter->getInfo();
  createRandomNumbers();
  IntDeleter().getInfo();
```

```
{
    std::unique_ptr<double,DoubleDeleter > uniquePtr( new double, DoubleDeleter() );
    std::unique_ptr<double,DoubleDeleter > uniquePtr1( new double, DoubleDeleter() );
    std::shared_ptr<double> sharedPtr( new double, DoubleDeleter() );
    std::shared_ptr<double> sharedPtr4(std::move(uniquePtr));
    std::shared_ptr<double> sharedPtr5= std::move(uniquePtr1);
    DoubleDeleter().getInfo();
}

DoubleDeleter().getInfo();
}
```







[]

Explanation

- In lines 8 24, Deleter is the special deleter. The deleter is parametrized by the type T. It counts, alongside the static variable count (line 23), how often the call operator (lines 11 14) was used.
- Deleter returns all the information with getInfo (lines 15-21).
- The function createRandomNumbers (lines 32-42) creates between 1 to 1000
 std::shared_ptr (line 40) parametrized by the special deleter
 intDeleter().
- The first usage of intDeleter->getInfo() shows that no resource has been released. This changes with the call sharedPtr2.reset() in line 53.
- An int variable with 4 bytes has been released. The call createRandomNumbers(), in line 57, creates 74 std::shared_ptr<int>.
- Of course, we can use the deleter for an std::unique_ptr (line 60 68).
- The memory for the double objects will be released after the end of the block, in line 68.

The classic issue of smart pointers using a reference count is to have cyclic references. Therefore, std::weak_ptr solves our problems. In the next lesson, we will take a closer look at std::weak_ptr and show how to break cyclic references.