Feb 25, 11 15:18	book.txt	Page 1/393

```
book.txt
 Feb 25, 11 15:18
                                                                     Page 2/393
      File: Page: 639 include/ansi.h
include/ansi.h
00000 /* The <ansi.h> header attempts to decide whether the compiler has enough
       * conformance to Standard C for Minix to take advantage of. If so, the
       * symbol _ANSI is defined (as 31459). Otherwise _ANSI is not defined
00002
       * here, but it may be defined by applications that want to bend the rules.
       * The magic number in the definition is to inhibit unnecessary bending
00004
00005
       * of the rules. (For consistency with the new '#ifdef _ANSI" tests in
       * the headers, _ANSI should really be defined as nothing, but that would
       * break many library routines that use "#if _ANSI".)
00007
80000
       * If _ANSI ends up being defined, a macro
00009
00010
00011
              _PROTOTYPE(function, params)
00012
00013
       * is defined. This macro expands in different ways, generating either
       * ANSI Standard C prototypes or old-style K&R (Kernighan & Ritchie)
00014
       * prototypes, as needed. Finally, some programs use _CONST, _VOIDSTAR etc
00016
       * in such a way that they are portable over both ANSI and K&R compilers.
       * The appropriate macros are defined here.
00017
00018
00019
00020
      #ifndef _ANSI_H
00021 #define _ANSI_H
00022
00023
      #if __STDC__ == 1
00024 #define _ANSI
                             31459 /* compiler claims full ANSI conformance */
00025 #endif
00026
00027 #ifdef __GNUC__
00028
                             31459 /* gcc conforms enough even in non-ANSI mode */
      #define _ANSI
00029
      #endif
00030
00031 #ifdef _ANSI
00032
00033 /* Keep everything for ANSI prototypes. */
                                           function params
00034
      #define _PROTOTYPE(function, params)
00035
      #define _ARGS(params)
                                           params
00036
      #define _VOIDSTAR
#define _VOID
00037
                             void *
00038
                             void
00039 #define CONST
                             const
00040
      #define _VOLATILE
                             volatile
00041
      #define _SIZET
                             size_t
00042
00043 #else
00044
00045 /* Throw away the parameters for K&R prototypes. */
00046
      #define _PROTOTYPE(function, params)
                                           function()
00047 #define _ARGS(params)
00048
00049
      #define _VOIDSTAR
#define _VOID
                             void *
00050
                             void
00051 #define _CONST
      #define _VOLATILE
00052
00053
      #define _SIZET
                             int
00054
```

```
book.txt
Feb 25, 11 15:18
                                                                 Page 3/393
      File: Page: 640 include/ansi.h
00055 #endif /* ANSI */
00056
00058 #define _RESTRICT
00059
00060 /* Setting any of _MINIX, _POSIX_C_SOURCE or _POSIX2_SOURCE implies
00061
      * _POSIX_SOURCE. (Seems wrong to put this here in ANSI space.)
00062 */
00063 #if defined(_MINIX) | _POSIX_C_SOURCE > 0 | defined(_POSIX2_SOURCE)
00064 #undef _POSIX_SOURCE
00065 #define _POSIX_SOURCE 1
00066 #endif
00067
00068 #endif /* ANSI_H */
include/limits.h
00100 /* The <limits.h> header defines some basic sizes, both of the language types
00101 * (e.g., the number of bits in an integer), and of the operating system (e.g.
      * the number of characters in a file name.
00102
00103 */
00104
00105 #ifndef _LIMITS_H
00106 #define _LIMITS_H
00107
00108 /* Definitions about chars (8 bits in MINIX, and signed). */
00109 #define CHAR BIT
                       8 /* # bits in a char */
                           -128 /* minimum value of a char */
00110 #define CHAR MIN
00111 #define CHAR_MAX
                           127
                                 /* maximum value of a char */
00112 #define SCHAR_MIN
                                /* minimum value of a signed char */
00113 #define SCHAR_MAX
                                /* maximum value of a signed char */
/* maximum value of an unsigned char */
                           127
00114 #define UCHAR_MAX
                            255
00115 #define MB_LEN_MAX
                               /* maximum length of a multibyte char */
00116
00117 /* Definitions about shorts (16 bits in MINIX). */
00118 #define SHRT_MIN (-32767-1) /* minimum value of a short */
00119 #define SHRT MAX
                         32767
                                 /* maximum value of a short */
00120 #define USHRT MAX
                         0 \times FFFF
                                 /* maximum value of unsigned short */
00121
00122 /* _EM_WSIZE is a compiler-generated symbol giving the word size in bytes. */
00123 #define INT_MIN (-2147483647-1) /* minimum value of a 32-bit int */
00124 #define INT_MAX 2147483647 /* maximum value of a 32-bit int */
00125 #define UINT_MAX 0xffffffff /* maximum value of an unsigned 32-bit int */
00126
00127 /*Definitions about longs (32 bits in MINIX). */
00128 #define LONG_MIN (-2147483647L-1)/* minimum value of a long */
00129 #define LONG_MAX 2147483647L /* maximum value of a long */
00130 #define ULONG_MAX 0xffffffffL /* maximum value of an unsigned long */
00131
00132 #include <sys/dir.h>
00133
00135 #ifdef _POSIX_SOURCE
                               /* these are only visible for POSIX */
                             4096 /* exec() may have 4K worth of args */
00136 #define POSIX ARG MAX
00137 #define _POSIX_CHILD_MAX 6 /* a process may have 6 children */
                               8 /* a file may have 8 links */
00138 #define _POSIX_LINK_MAX
00139 #define POSIX MAX CANON 255 /* size of the canonical input queue */
```

```
book.txt
 Feb 25, 11 15:18
                                                                       Page 4/393
       File: Page: 641 include/limits.h
00140
      #define _POSIX_MAX_INPUT 255 /* you can type 255 chars ahead */
                                    /* a file name may have 14 chars */
00141
      #define _POSIX_NAME_MAX DIRSIZ
00142 #define _POSIX_NGROUPS_MAX 0
                                    /* supplementary group IDs are optional */
00143 #define _POSIX_OPEN_MAX
                                16 /* a process may have 16 files open */
                                255 /* a pathname may contain 255 chars */
00144 #define _POSIX_PATH_MAX
00145 #define _POSIX_PIPE_BUF
                                512 /* pipes writes of 512 bytes must be atomic */
                                8  /* at least 8 FILEs can be open at once */
3  /* time zone names can be at least 3 chars */
00146 #define _POSIX_STREAM_MAX
00147 #define _POSIX_TZNAME_MAX
00148 #define POSIX_SSIZE_MAX 32767 /* read() must support 32767 byte reads */
00149
00150 /* Values actually implemented by MINIX (Tables 2-4, 2-5, 2-6, and 2-7). */
00151 /* Some of these old names had better be defined when not POSIX. */
00152 #define _NO_LIMIT
                                100 /* arbitrary number; limit not enforced */
00153
00154 #define NGROUPS MAX
                                 0 /* supplemental group IDs not available */
00155 #define ARG MAX
                              16384 /* # bytes of args + environ for exec() */
00156 #define CHILD_MAX
                          _NO_LIMIT /* MINIX does not limit children */
                               20 /* # open files a process may have */
00157 #define OPEN_MAX
                           SHRT_MAX /* # links a file may have */
00158 #define LINK_MAX
                                255 /* size of the canonical input queue */
00159 #define MAX_CANON
00160 #define MAX_INPUT
                                255 /* size of the type-ahead buffer */
00161 #define NAME_MAX
                             DIRSIZ /* # chars in a file name */
                                255 /* # chars in a path name */
00162 #define PATH_MAX
                               7168 /* # bytes in atomic write to a pipe */
00163 #define PIPE BUF
                                 20 /* must be the same as FOPEN_MAX in stdio.h */
00164 #define STREAM_MAX
00165 #define TZNAME MAX
                                 3 /* maximum bytes in a time zone name is 3 */
                              32767 /* max defined byte count for read() */
00166 #define SSIZE MAX
00167
       #endif /* _POSIX_SOURCE */
00168
00169
00170 #endif /* LIMITS H */
include/errno.h
00200 /* The <errno.h> header defines the numbers of the various errors that can
00201 * occur during program execution. They are visible to user programs and
       * should be small positive integers. However, they are also used within
00202
00203
       * MINIX, where they must be negative. For example, the READ system call is
       * executed internally by calling do read(). This function returns either a
00205
       * (negative) error number or a (positive) number of bytes actually read.
00206
       * To solve the problem of having the error numbers be negative inside the
00207
00208
        * the system and positive outside, the following mechanism is used. All the
00209
        * definitions are are the form:
00210
                                     (_SIGN 1)
00211
              #define EPERM
00212
       * If the macro _SYSTEM is defined, then _SIGN is set to "-", otherwise it is
00213
       * set to "". Thus when compiling the operating system, the macro _SYSTEM
00214
00215
        * will be defined, setting EPERM to (- 1), whereas when when this
       * file is included in an ordinary user program, EPERM has the value ( 1).
00216
00217
00218
00219 #ifndef ERRNO H
                                     /* check if <errno.h> is already included */
```

```
Feb 25, 11 15:18
                                       book.txt
                                                                         Page 5/393
       File: Page: 642 include/errno.h
00220 #define ERRNO H
                                      /* it is not included; note that fact */
00221
00222 /* Now define _SIGN as "" or "-" depending on _SYSTEM. */
00223 #ifdef SYSTEM
00224 # define _SIGN
00225 #
          define OK
                               Ω
00226 #else
00227 # define _SIGN
00228 #endif
00229
00230 extern int errno;
                                       /* place where the error numbers go */
00231
00232 /* Here are the numerical values of the error numbers. */ 00233 #define _NERROR 70 /* number of errors */
00234
00235 #define EGENERIC
                         (_SIGN 99) /* generic error */
                           (_SIGN 1) /* operation not permitted */
00236 #define EPERM
                           (_SIGN 2) /* no such file or directory */
00237 #define ENOENT
                            (_SIGN 3) /* no such process */
00238 #define ESRCH
                            (_SIGN 4) /* interrupted function call */
00239 #define EINTR
00240 #define EIO
                            (_SIGN 5) /* input/output error */
                            (_SIGN 6) /* no such device or address */
00241 #define ENXIO
                            (_SIGN 7) /* arg list too long */
00242 #define E2BIG
                            (_SIGN 8) /* exec format error */
00243 #define ENOEXEC
00244 #define EBADF
                            (_SIGN 9) /* bad file descriptor */
                            (_SIGN 10) /* no child process */
00245 #define ECHILD
00246 #define EAGAIN
                            (_SIGN 11) /* resource temporarily unavailable */
00247 #define ENOMEM
                            (_SIGN 12) /* not enough space */
                            (_SIGN 13) /* permission denied */
00248 #define EACCES
                            (_SIGN 14) /* bad address */
00249 #define EFAULT
                            (_SIGN 15) /* Extension: not a block special file */
00250 #define ENOTBLK
00251 #define EBUSY
                            (_SIGN 16) /* resource busy */
00252 #define EEXIST
                            (_SIGN 17) /* file exists */
                            (_SIGN 18) /* improper link */
00253 #define EXDEV
                            (_SIGN 19) /* no such device */
00254 #define ENODEV
00255 #define ENOTDIR
                            (_SIGN 20) /* not a directory */
                            (_SIGN 21) /* is a directory */
00256 #define EISDIR
00257 #define EINVAL
                            (_SIGN 22) /* invalid argument */
00258 #define ENFILE
                            (_SIGN 23) /* too many open files in system */
00259 #define EMFILE
                            (_SIGN 24) /* too many open files */
                            (_SIGN 25) /* inappropriate I/O control operation */
00260 #define ENOTTY
                            (_SIGN 26) /* no longer used */
00261 #define ETXTBSY
                            (_SIGN 27) /* file too large */
00262 #define EFBIG
                            (_SIGN 28) /* no space left on device */
00263 #define ENOSPC
                            (_SIGN 29) /* invalid seek */
00264 #define ESPIPE
                            (_SIGN 30) /* read-only file system */
00265 #define EROFS
                            (_SIGN 31) /* too many links */
00266 #define EMLINK
                            (_SIGN 32) /* broken pipe */
00267 #define EPIPE
                            (_SIGN 33) /* domain error
00268 #define EDOM
                                                             (from ANSI C std) */
                            (_SIGN 34) /* result too large (from ANSI C std) */
00269 #define ERANGE
                            (_SIGN 35) /* resource deadlock avoided */
00270 #define EDEADLK
00271 #define ENAMETOOLONG (_SIGN 36) /* file name too long */
                            (_SIGN 37) /* no locks available */
00272 #define ENOLCK
                            (SIGN 38) /* function not implemented */
00273 #define ENOSYS
00274 #define ENOTEMPTY
                            (_SIGN 39) /* directory not empty */
00275
00276 /* The following errors relate to networking. */
00277 #define EPACKSIZE
                           (_SIGN 50) /* invalid packet size for some protocol */
(_SIGN 51) /* not enough buffers left */
00278 #define EOUTOFBUFS
00279 #define EBADIOCTL
                            (SIGN 52) /* illegal ioctl for device */
```

```
Feb 25, 11 15:18
                                       book.txt
                                                                       Page 6/393
       File: Page: 643 include/errno.h
                            (_SIGN 53) /* badmode in ioctl */
00280 #define EBADMODE
00281 #define EWOULDBLOCK
                            (_SIGN 54)
00282 #define EBADDEST
                           (_SIGN 55) /* not a valid destination address */
00283 #define EDSTNOTRCH
                            (_SIGN 56) /* destination not reachable */
                            (_SIGN 57) /* all ready connected */
00284 #define EISCONN
00285 #define EADDRINUSE
                         (_SIGN 58) /* address in use */
00286 #define ECONNREFUSED (_SIGN 59) /* connection refused */
00287 #define ECONNRESET (_SIGN 60) /* connection reset */
                            (SIGN 61) /* connection timed out */
00288 #define ETIMEDOUT
                            (_SIGN 62) /* urgent data present */
00289
       #define EURG
                            (_SIGN 63) /* no urgent data present */
00290 #define ENOURG
00291 #define ENOTCONN
                           (SIGN 64) /* no connection (yet or anymore) */
                         (_SIGN 65) /* a write call to a shutdown connection */
00292 #define ESHUTDOWN
                            (_SIGN 66) /* no such connection */
00293 #define ENOCONN
00294 #define EAFNOSUPPORT (SIGN 67) /* address family not supported */
00295 #define EPROTONOSUPPORT (_SIGN 68) /* protocol not supported by AF */
00296 #define EPROTOTYPE (_SIGN 69) /* Protocol wrong type for socket */
00297 #define EINPROGRESS (_SIGN 70) /* Operation now in progress */
00298 #define EADDRNOTAVAIL (_SIGN 71) /* Can't assign requested address */
                         (_SIGN 72) /* Connection already in progress */
00299 #define EALREADY
                            (_SIGN 73) /* Message too long */
00300 #define EMSGSIZE
00301
00302 /* The following are not POSIX errors, but they can still happen.
00303 * All of these are generated by the kernel and relate to message passing.
00304 */
00305 #define ELOCKED
                           (_SIGN 101) /* can't send message due to deadlock */
00306 #define EBADCALL
                          (_SIGN 102) /* illegal system call number */
00307 #define EBADSRCDST (_SIGN 103) /* bad source or destination process */
00308 #define ECALLDENIED (_SIGN 104) /* no permission for system call */
                           (SIGN 105) /* send destination is not alive */
00309 #define EDEADDST
                           (_SIGN 106) /* source or destination is not ready */
00310 #define ENOTREADY
00311 #define EBADREQUEST (_SIGN 107) /* destination cannot handle request */
00312 #define EDONTREPLY (_SIGN 201) /* pseudo-code: don't send a reply */
00313
00314 #endif /* _ERRNO_H */
include/unistd.h
00400 /* The <unistd.h> header contains a few miscellaneous manifest constants. */
00401
00402 #ifndef _UNISTD_H
00403 #define _UNISTD_H
00404
00405 #ifndef TYPES H
00406 #include <sys/types.h>
00407 #endif
00408
00409 /* Values used by access(). POSIX Table 2-8. */
00410 #define F_OK 0 /* test if file exists */
                               1 /* test if file is executable */
2 /* test if file is writable */
4 /* test if file is readable */
00411 #define X OK
00412 #define W_OK
00413 #define R OK
00414
00415 /* Values used for whence in lseek(fd, offset, whence). POSIX Table 2-9. */
00416 #define SEEK_SET 0 /* offset is absolute */
00417 #define SEEK_CUR 1 /* offset is relative to current position */
00418 #define SEEK_END 2 /* offset is relative to end of file */
00419
```

```
book.txt
Feb 25, 11 15:18
                                                                   Page 7/393
      File: Page: 644 include/unistd.h
00420 /* This value is required by POSIX Table 2-10. */
00421 #define _POSIX_VERSION 199009L /* which standard is being conformed to */
00423 /* These three definitions are required by POSIX Sec. 8.2.1.2. */
                           0 /* file descriptor for stdin */
00424 #define STDIN_FILENO
00425 #define STDOUT_FILENO
                                   /* file descriptor for stdout */
00426 #define STDERR_FILENO
                                  /* file descriptor for stderr */
00427
00428 #ifdef MINIX
00429 /* How to exit the system or stop a server process. */
00430 #define RBT HALT
00431 #define RBT REBOOT
                                  /* a server panics */
00432 #define RBT_PANIC
                                  /* let the monitor do this */
00433 #define RBT_MONITOR
                              3
00434 #define RBT RESET
                             4 /* hard reset the system */
00435 #endif
00436
00437 /* What system info to retrieve with sysgetinfo(). */
00440 #define SI_PROC_TAB 2
                                /* copy of entire process table */
00441 #define SI_DMAP_TAB
                            3 /* get device <-> driver mappings */
00442
00443 /* NULL must be defined in <unistd.h> according to POSIX Sec. 2.7.1. */
00444 #define NULL ((void *)0)
00445
00446 /* The following relate to configurable system variables. POSIX Table 4-2. */
00447 #define _SC_ARG_MAX
00448 #define _SC_CHILD_MAX
00449 #define _SC_CLOCKS_PER_SEC 3
00450 #define _SC_CLK_TCK
00451 #define _SC_NGROUPS_MAX
00452 #define _SC_OPEN_MAX
00453 #define _SC_JOB_CONTROL
00454 #define _SC_SAVED_IDS
00455 #define _SC_VERSION
00456 #define _SC_STREAM_MAX
00457 #define _SC_TZNAME_MAX
                             1.0
00458
1 /* link count */
00460 #define _PC_LINK_MAX
00461 #define PC MAX CANON
                                  /* size of the canonical input queue */
                              3 /* type-ahead buffer size */
4 /* file name size */
00462 #define _PC_MAX_INPUT
00463 #define _PC_NAME_MAX
00464 #define PC PATH MAX
                                 /* pathname size */
                                 /* pipe size */
00465 #define _PC_PIPE_BUF
                              6
                              7
00466 #define _PC_NO_TRUNC
                                  /* treatment of long name components */
                              8 /* tty disable */
00467 #define _PC_VDISABLE
00468 #define _PC_CHOWN_RESTRICTED 9 /* chown restricted or not */
00469
00470 /* POSIX defines several options that may be implemented or not, at the
00471
      * implementer's whim. This implementer has made the following choices:
00472
00473
         POSIX JOB CONTROL
                               not defined:
                                                  no job control
00474
         _POSIX_SAVED_IDS
                               not defined:
                                                  no saved uid/gid
00475
         POSIX NO TRUNC
                               defined as -1:
                                                  long path names are truncated
         POSIX CHOWN RESTRICTED
00476
                               defined:
                                                  you can't give away files
00477
         _POSIX_VDISABLE
                               defined:
                                                  tty functions can be disabled
00478
00479 #define POSIX NO TRUNC
```

```
Feb 25, 11 15:18
                                           book.txt
                                                                               Page 8/393
       File: Page: 645 include/unistd.h
00480 #define POSIX CHOWN RESTRICTED 1
00481
00482 /* Function Prototypes. */
00483 _PROTOTYPE( void _exit, (int _status)
                                                                                   );
00484 _PROTOTYPE( int access, (const char *_path, int _amode)
                                                                                   );
00485 _PROTOTYPE( unsigned int alarm, (unsigned int _seconds)
                                                                                   );
00486 _PROTOTYPE( int chdir, (const char *_path)
                                                                                   );
00487 _PROTOTYPE( int fchdir, (int fd)
                                                                                   );
00488 _PROTOTYPE( int chown, (const char *_path, _mnx_Uid_t _owner, _mnx_Gid_t _group)
00489 _PROTOTYPE( int close, (int _fd)
00490 _PROTOTYPE( char *ctermid, (char *_s)
                                                                                   );
00491 _PROTOTYPE( char *cuserid, (char *_s)
                                                                                   );
       _PROTOTYPE( int dup, (int _fd)
00492
                                                                                   );
00493 PROTOTYPE( int dup2, (int fd, int fd2)
                                                                                   );
00494 PROTOTYPE( int execl, (const char *_path, const char *_arg, ...)
00495 PROTOTYPE( int execle, (const char *_path, const char *_arg, ...)
00496 PROTOTYPE( int execle, (const char *_file, const char *arg, ...)
                                                                                   );
                                                                                   );
                                                                                   );
00497 _PROTOTYPE( int execv, (const char *_path, char *const _argv[])
00498 _PROTOTYPE( int execve, (const char *_path, char *const _argv[],
                                                                                   );
00499
                                                        char *const _envp[])
                                                                                   );
00500 _PROTOTYPE( int execvp, (const char *_file, char *const _argv[])
                                                                                   );
00501 _PROTOTYPE( pid_t fork, (void)
                                                                                   );
00502 _PROTOTYPE( long fpathconf, (int _fd, int _name)
                                                                                   );
00503 _PROTOTYPE( char *getcwd, (char *_buf, size_t _size)
                                                                                   );
00504
       _PROTOTYPE( gid_t getegid, (void)
                                                                                   );
00505 PROTOTYPE( uid t geteuid, (void)
                                                                                   );
00506
       _PROTOTYPE( gid_t getgid, (void)
                                                                                   );
00507
       _PROTOTYPE( int getgroups, (int _gidsetsize, gid_t _grouplist[])
                                                                                   );
00508 _PROTOTYPE( char *getlogin, (void)
                                                                                   );
00509 _PROTOTYPE( pid_t getpgrp, (void)
                                                                                   );
00510 _PROTOTYPE( pid_t getpid, (void)
                                                                                   );
00511 _PROTOTYPE( pid_t getppid, (void)
                                                                                   );
00512 _PROTOTYPE( uid_t getuid, (void)
                                                                                   );
00513 _PROTOTYPE( int isatty, (int _fd)
                                                                                   );
00514 _PROTOTYPE( int link, (const char *_existing, const char *_new)
00515 _PROTOTYPE( off_t lseek, (int _fd, off_t _offset, int _whence)
                                                                                   );
00516 _PROTOTYPE( long pathconf, (const char *_path, int _name)
                                                                                   );
00517 _PROTOTYPE( int pause, (void)
                                                                                   );
00518 _PROTOTYPE( int pipe, (int _fildes[2])
                                                                                   );
00519 _PROTOTYPE( ssize_t read, (int _fd, void *_buf, size_t _n)
                                                                                   );
00520 PROTOTYPE( int rmdir, (const char * path)
                                                                                   );
00521 _PROTOTYPE( int setgid, (_mnx_Gid_t _gid)
                                                                                   );
00522
       _PROTOTYPE( int setpgid, (pid_t _pid, pid_t _pgid)
                                                                                   );
00523 _PROTOTYPE( pid_t setsid, (void)
00524 _PROTOTYPE( int setuid, (_mnx_Uid_t _uid)
                                                                                   );
00525 _PROTOTYPE( unsigned int sleep, (unsigned int _seconds)
                                                                                   );
00526 _PROTOTYPE( long sysconf, (int _name)
                                                                                   );
00527 _PROTOTYPE( pid_t tcgetpgrp, (int _fd)
                                                                                   );
00528 _PROTOTYPE( int tcsetpgrp, (int _fd, pid_t _pgrp_id)
                                                                                   );
00529 _PROTOTYPE( char *ttyname, (int _fd)
                                                                                   );
00530 _PROTOTYPE( int unlink, (const char *_path)
                                                                                   );
       _PROTOTYPE( ssize_t write, (int _fd, const void *_buf, size_t _n)
00531
                                                                                   );
00532
00533 /* Open Group Base Specifications Issue 6 (not complete) */
00534
       _PROTOTYPE( int symlink, (const char *path1, const char *path2)
                                                                                   );
00535 _PROTOTYPE( int getopt, (int _argc, char **_argv, char *_opts)
                                                                                   );
00536 extern char *optarg;
00537 extern int optind, opterr, optopt;
00538 PROTOTYPE( int usleep, (useconds t useconds)
                                                                                   );
00539
```

```
book.txt
 Feb 25, 11 15:18
                                                                          Page 9/393
       File: Page: 646 include/unistd.h
00540 #ifdef _MINIX
00541 #ifndef _TYPE_H
00542 #include <minix/type.h>
00543 #endif
00544 _PROTOTYPE( int brk, (char *_addr)
                                                                              );
00545 _PROTOTYPE( int chroot, (const char *_name)
00546 PROTOTYPE( int mknod, (const char *_name, _mnx_Mode_t _mode, Dev_t _addr)
00547 _PROTOTYPE( int mknod4, (const char *_name, _mnx_Mode_t _mode, Dev_t _addr,
00548
                  long _size)
00549 _PROTOTYPE( char *mktemp, (char *_template)
00550 _PROTOTYPE( int mount, (char *_spec, char *_name, int _flag)
00551 _PROTOTYPE( long ptrace, (int _req, pid_t _pid, long _addr, long _data) );
00552 _PROTOTYPE( char *sbrk, (int _incr)
00553 _PROTOTYPE( int sync, (void)
00554 _PROTOTYPE( int fsync, (int fd)
00555 _PROTOTYPE( int umount, (const char *_name)
                                                                              );
00556 _PROTOTYPE( int reboot, (int _how, ...)
00557 _PROTOTYPE( int gethostname, (char *_hostname, size_t _len)
00558 _PROTOTYPE( int getdomainname, (char *_domain, size_t _len)
                                                                              );
                                                                              );
00559 _PROTOTYPE( int ttyslot, (void)
00560 _PROTOTYPE( int fttyslot, (int _fd)
00561 _PROTOTYPE( char *crypt, (const char *_key, const char *_salt)
                                                                              );
00562 _PROTOTYPE( int getsysinfo, (int who, int what, void *where)
                                                                              );
00563 _PROTOTYPE( int getprocnr, (void)
                                                                              );
00564 _PROTOTYPE( int findproc, (char *proc_name, int *proc_nr)
                                                                              );
00565 _PROTOTYPE( int allocmem, (phys_bytes size, phys_bytes *base)
00566 _PROTOTYPE( int freemem, (phys_bytes size, phys_bytes base)
00567 #define DEV_MAP 1
00568 #define DEV UNMAP 2
00569 #define mapdriver(driver, device, style) devctl(DEV_MAP, driver, device, style)
00570 #define unmapdriver(device) devctl(DEV_UNMAP, 0, device, 0)
00571 _PROTOTYPE( int devctl, (int ctl_req, int driver, int device, int style));
00572
00573 /* For compatibility with other Unix systems */
00574 _PROTOTYPE( int getpagesize, (void)
00575 _PROTOTYPE( int setgroups, (int ngroups, const gid_t *gidset)
00576
00577 #endif
00578
00579 _PROTOTYPE( int readlink, (const char *, char *, int));
00580 PROTOTYPE( int getopt, (int, char **, char *));
00581 extern int optind, opterr, optopt;
00582
00583 #endif /* UNISTD H */
include/string h
00600 /* The <string.h> header contains prototypes for the string handling
00601 * functions.
00602 */
00603
00604 #ifndef _STRING_H
00605 #define STRING H
00606
00607 #define NULL ((void *)0)
00609 #ifndef SIZE T
```

```
Feb 25, 11 15:18
                                                   book.txt
                                                                                             Page 10/393
         File: Page: 647 include/string.h
00610 #define _SIZE_T
00611 typedef unsigned int size_t; /* type returned by sizeof */
00612 #endif /*_SIZE_T */
00613
00614 /* Function Prototypes. */
00615 #ifndef _ANSI_H
00616 #include <ansi.h>
00617 #endif
00618
00619 _PROTOTYPE( void *memchr, (const void *_s, int _c, size_t _n)
00620 PROTOTYPE( int memcmp, (const void *_s1, const void *_s2, size_t _n)
00621 _PROTOTYPE( void *memcpy, (void *_s1, const void *_s2, size_t _n)
                                                                                                     );
U0621 _PROTOTYPE( void *memcpy, (void *_s1, const void *_s2, size_t _n)

00622 _PROTOTYPE( void *memmove, (void *_s1, const void *_s2, size_t _n)

00623 _PROTOTYPE( void *memset, (void *_s, int _c, size_t _n)

00624 _PROTOTYPE( char *strcat, (char *_s1, const char *_s2)

00625 _PROTOTYPE( char *strchr, (const char *_s, int _c)

00626 _PROTOTYPE( int strncmp, (const char *_s1, const char *_s2, size_t _n)
                                                                                                     );
                                                                                                     );
                                                                                                     );
                                                                                                     );
                                                                                                     );
00627 _PROTOTYPE( int strcmp, (const char *_s1, const char *_s2)
00628 _PROTOTYPE( int strcoll, (const char *_s1, const char *_s2)
                                                                                                     );
                                                                                                     );
00629 _PROTOTYPE( char *strcpy, (char *_s1, const char *_s2)
                                                                                                     );
00630 _PROTOTYPE( size_t strcspn, (const char *_s1, const char *_s2)
                                                                                                     );
00631 _PROTOTYPE( char *strerror, (int _ernum)
00632 _PROTOTYPE( size_t strlen, (const char *_s)
                                                                                                     );
                                                                                                     );
00633 _PROTOTYPE( char *strncat, (char *_s1, const char *_s2, size_t _n)
                                                                                                     );
00634 _PROTOTYPE( char *strncpy, (char *_s1, const char *_s2, size_t _n)
                                                                                                     );
00635 _PROTOTYPE( char *strpbrk, (const char *_s1, const char *_s2)
00636 _PROTOTYPE( char *strrchr, (const char *_s, int _c)
                                                                                                     );
                                                                                                     );
00637 _PROTOTYPE( size_t strspn, (const char *_s1, const char *_s2)
                                                                                                     );
00638 _PROTOTYPE( char *strstr, (const char *_s1, const char *_s2)
                                                                                                     );
00639 PROTOTYPE( char *strtok, (char * s1, const char * s2)
                                                                                                     );
00640 _PROTOTYPE( size_t strxfrm, (char *_s1, const char *_s2, size_t _n)
00641
00642 #ifdef _POSIX_SOURCE
00643 /* Open Group Base Specifications Issue 6 (not complete) */
00644 char *strdup(const char *_s1);
00645 #endif
00646
00647 #ifdef _MINIX
00648 /* For backward compatibility. */
00649 /POT Dataward Compactifity. / 00649 _PROTOTYPE( char *index, (const char *_s, int _charwanted) ); 00650 _PROTOTYPE( char *rindex, (const char *_s, int _charwanted) ); 00651 _PROTOTYPE( void bcopy, (const void *_src, void *_dst, size_t _length) );
00652 _PROTOTYPE( int bcmp, (const void *_s1, const void *_s2, size_t _length));
00653
         _PROTOTYPE( void bzero, (void *_dst, size_t _length)
00654 PROTOTYPE( void *memcopy, (char *_dst, const char *_src, int _ucharstop,
00655
                                                                           size_t _size)
00656
00657 /* Misc. extra functions */
00658 _PROTOTYPE( int strcasecmp, (const char *_s1, const char *_s2)
                                                                                                    );
00659 _PROTOTYPE( int strncasecmp, (const char *_s1, const char *_s2,
                                                                              size_t _len)
                                                                                                    );
00661 _PROTOTYPE( size_t strnlen, (const char *_s, size_t _n) 00662 #endif
                                                                                                    );
00663
00664 #endif /* _STRING_H */
```

```
book.txt
Feb 25, 11 15:18
                                                                   Page 11/393
      File: Page: 648 include/signal.h
include/signal.h
00700 /* The <signal.h> header defines all the ANSI and POSIX signals.
00701 * MINIX supports all the signals required by POSIX. They are defined below.
      * Some additional signals are also supported.
00702
00703 */
00704
00705 #ifndef _SIGNAL_H
00706 #define _SIGNAL_H
00707
00708 #ifndef _ANSI_H
00709 #include <ansi.h>
00710 #endif
00711 #ifdef _POSIX_SOURCE
00712 #ifndef _TYPES_H
00713 #include <sys/types.h>
00714 #endif
00715 #endif
00716
00717 /* Here are types that are closely associated with signal handling. */
00718 typedef int sig_atomic_t;
00719
00720 #ifdef _POSIX_SOURCE
00721 #ifndef _SIGSET_T
00722 #define _SIGSET_T
00723 typedef unsigned long sigset_t;
00724 #endif
00725 #endif
00726
00727 #define _NSIG
                                 /* number of signals used */
00728
00729 #define SIGHUP
                                   /* hangup */
00730 #define SIGINT
                                   /* interrupt (DEL) */
00731 #define SIGQUIT
                               3
                                   /* quit (ASCII FS) */
                                   /* illegal instruction */
00732 #define SIGILL
                               4
00733 #define SIGTRAP
                                 /* trace trap (not reset when caught) */
                                 /* IOT instruction */
00734 #define SIGABRT
                                   /* SIGABRT for people who speak PDP-11 */
00735 #define SIGIOT
                                  /* spare code */
00736 #define SIGUNUSED
                                 /* floating point exception */
00737 #define SIGFPE
                               8
00738 #define SIGKILL
                                   /* kill (cannot be caught or ignored) */
00739 #define SIGUSR1
                                 /* user defined signal # 1 */
00740 #define SIGSEGV
                                   /* segmentation violation */
                              11
00741 #define SIGUSR2
                                   /* user defined signal # 2 */
                                   /* write on a pipe with no one to read it */
00742 #define SIGPIPE
00743 #define SIGALRM
                                   /* alarm clock */
                              14
00744 #define SIGTERM
                              15
                                   /* software termination signal from kill */
00745 #define SIGCHLD
                                   /* child process terminated or stopped */
00746
00747 #define SIGEMT
                                   /* obsolete */
00748 #define SIGBUS
                              10
                                   /* obsolete */
00749
00750
      /* MINIX specific signals. These signals are not used by user proceses,
      * but meant to inform system processes, like the PM, about system events.
00752
00753 #define SIGKMESS
                                   /* new kernel message */
00754 #define SIGKSIG
                              19 /* kernel signal pending */
```

```
Feb 25, 11 15:18
                                       book.txt
                                                                         Page 12/393
       File: Page: 649 include/signal.h
00755 #define SIGKSTOP
                                      /* kernel shutting down */
                                2.0
00756
00757 /* POSIX requires the following signals to be defined, even if they are
00758
       * not supported. Here are the definitions, but they are not supported.
00759
00760 #define SIGCONT
                                      /* continue if stopped */
                                      /* stop signal */
00761
      #define SIGSTOP
                                19
                                      /* interactive stop signal */
00762
      #define SIGTSTP
                                2.0
                                      /* background process wants to read */
00763 #define SIGTTIN
                                21
00764
      #define SIGTTOU
                                      /* background process wants to write */
                                2.2
00765
00766
      /* The sighandler t type is not allowed unless POSIX SOURCE is defined. */
00767 typedef void _PROTOTYPE( (*__sighandler_t), (int) );
00768
00769
      /* Macros used as function pointers. */
00770 #define SIG_ERR ((__sighandler_t) -1)
                                                      /* error return */
00771 #define SIG_DFL
                         ((__sighandler_t) 0)
                                                      /* default signal handling */
                                                      /* ignore signal */
00772 #define SIG_IGN
                         ((__sighandler_t) 1)
                        ((__sighandler_t) 2)
00773 #define SIG_HOLD
                                                      /* block signal */
00774 #define SIG_CATCH
                         ((__sighandler_t) 3)
                                                      /* catch signal */
00775 #define SIG_MESS ((__sighandler_t) 4)
                                                      /* pass as message (MINIX) */
00776
00777
      #ifdef _POSIX_SOURCE
00778 struct sigaction {
00779
         __sighandler_t sa_handler;
                                      /* SIG_DFL, SIG_IGN, or pointer to function */
00780
         sigset_t sa_mask;
                                      /* signals to be blocked during handler */
00781
        int sa_flags;
                                      /* special flags */
00782 };
00783
      /* Fields for sa flags. */
00785 #define SA_ONSTACK 0x0001
                                      /* deliver signal on alternate stack */
00786
      #define SA_RESETHAND 0x0002
                                      /* reset signal handler when signal caught */
00787 #define SA_NODEFER 0x0004
                                      /* don't block signal while catching it */
00788
      #define SA_RESTART
                                      /* automatic system call restart */
                           0×0008
                                      /* extended signal handling */
00789
      #define SA_SIGINFO 0x0010
00790 #define SA_NOCLDWAIT 0x0020
                                      /* don't create zombies */
00791 #define SA_NOCLDSTOP 0x0040
                                      /* don't receive SIGCHLD when child stops */
00792
00793 /* POSIX requires these values for use with sigprocmask(2). */
00794
      #define SIG_BLOCK
                                      /* for blocking signals */
/* for unblocking signals */
                                 0
00795
      #define SIG_UNBLOCK
                                      /* for setting the signal mask */
      #define SIG SETMASK
                                      /* for internal use only */
00797
      #define SIG_INQUIRE
00798 #endif /* _POSIX_SOURCE */
00799
00800 /* POSIX and ANSI function prototypes. */
00801
      _PROTOTYPE( int raise, (int _sig)
                                                                              );
00802 _PROTOTYPE( __sighandler_t signal, (int _sig, __sighandler_t _func)
                                                                              );
00803
00804 #ifdef _POSIX_SOURCE
00805 _PROTOTYPE( int kill, (pid_t _pid, int _sig)
                                                                              );
       _PROTOTYPE( int sigaction,
00806
00807
           (int _sig, const struct sigaction *_act, struct sigaction *_oact)
                                                                              );
00808 _PROTOTYPE( int sigaddset, (sigset_t *_set, int _sig)
                                                                              );
00809
      _PROTOTYPE( int sigdelset, (sigset_t *_set, int _sig)
                                                                              );
00810
      _PROTOTYPE( int sigemptyset, (sigset_t *_set)
                                                                              );
00811 _PROTOTYPE( int sigfillset, (sigset_t *_set)
                                                                              );
00812 _PROTOTYPE( int sigismember, (const sigset_t *_set, int _sig)
                                                                              );
00813 _PROTOTYPE( int sigpending, (sigset_t *_set)
00814 _PROTOTYPE( int sigprocmask,
```

```
book.txt
 Feb 25, 11 15:18
                                                                             Page 13/393
       File: Page: 650 include/signal.h
00815
                    (int how, const sigset t * set, sigset t * oset)
00816 _PROTOTYPE( int sigsuspend, (const sigset_t *_sigmask)
                                                                                  );
00817 #endif
00818
00819 #endif /* _SIGNAL_H */
include/fcntl.h
00900 /* The <fcntl.h> header is needed by the open() and fcntl() system calls,
00901 * which have a variety of parameters and flags. They are described here.
       * The formats of the calls to each of these are:
00902
00903
00904
                open(path, oflag [,mode])
                                                 open a file
00905
               fcntl(fd, cmd [,arg])
                                              get or set file attributes
00906
00907 */
00908
00909 #ifndef _FCNTL_H
00910 #define _FCNTL_H
00911
00912 #ifndef _TYPES_H
00913 #include <sys/types.h>
00914 #endif
00915
00916 /* These values are used for cmd in fcntl(). POSIX Table 6-1. */
00916 /* These values are used for cmd in fcntl(). POSIX Table 6-1. */
00917 #define F_DUPFD 0 /* duplicate file descriptor */
00918 #define F_GETFD 1 /* get file descriptor flags */
00919 #define F_SETFD 2 /* set file descriptor flags */
00920 #define F_GETFL 3 /* get file status flags */
00921 #define F_SETFL 4 /* set file status flags */
00922 #define F_GETLK 5 /* get record locking information */
00923 #define F_SETLK 6 /* set record locking information */
00924 #define F_SETLKW 7 /* set record locking information */
00925
00926 /* File descriptor flags used for fcntl(). POSIX Table 6-2. */
00927 #define FD_CLOEXEC 1 /* close on exec flag for third arg of fcntl */
00928
00929 /* L_type values for record locking with fcntl(). POSIX Table 6-3. */
3 /* unlock */
00932 #define F_UNLCK
00933
00934 /* Oflag values for open(). POSIX Table 6-4. */
00400 /* do not assign a controlling terminal */
00937 #define O_NOCTTY
00938 #define O_TRUNC
                              01000 /* truncate flag */
00939
00940 /* File status flags for open() and fcntl(). POSIX Table 6-5. */
00941 #define O_APPEND 02000 /* set append mode */
00942 #define O_NONBLOCK 04000 /* no delay */
00943
00944 /* File access modes for open() and fcntl(). POSIX Table 6-6. */
/* open(name, O WRONLY) opens write only */
00946 #define O WRONLY
                                   1
                                   2 /* open(name, O_RDWR) opens read/write */
00947 #define O_RDWR
00948
00949 /* Mask for use with file access modes. POSIX Table 6-7. */
```

```
Feb 25, 11 15:18
                                       book.txt
                                                                       Page 14/393
       File: Page: 651 include/fcntl.h
                               03 /* mask for file access modes */
00950 #define O ACCMODE
00951
00952 /* Struct used for locking. POSIX Table 6-8. */
00953 struct flock {
                                      /* type: F_RDLCK, F_WRLCK, or F_UNLCK */
00954 short l_type;
00955
       short l_whence;
                                     /* flag for starting offset */
00956
        off_t l_start;
                                     /* relative offset in bytes */
                                     /* size; if 0, then until EOF */
00957
        off_t l_len;
                                     /* process id of the locks' owner */
00958
        pid_t l_pid;
00959 };
00960
00961 /* Function Prototypes. */
00962 _PROTOTYPE( int creat, (const char *_path, _mnx_Mode_t _mode)
                                                                             );
00963 _PROTOTYPE( int fcntl, (int _filedes, int _cmd, ...)
                                                                             );
00964 PROTOTYPE( int open, (const char *_path, int _oflag, ...)
00965
00966 #endif /* _FCNTL_H */
include/termios.h
01000 /* The <termios.h> header is used for controlling tty modes. */
01002 #ifndef _TERMIOS_H
01003 #define _TERMIOS_H
01004
01005 typedef unsigned short tcflag_t;
01006 typedef unsigned char cc_t;
01007 typedef unsigned int speed_t;
01008
01009 #define NCCS
                                 20 /* size of cc_c array, some extra space
01010
                                       * for extensions. */
01011
01012 /* Primary terminal control structure. POSIX Table 7-1. */
01013 struct termios {
        tcflag_t c_iflag;
                                     /* input modes */
01014
                                     /* output modes */
01015
         tcflag_t c_oflag;
         tcflag_t c_cflag;
                                    /* control modes */
01016
         tcflag_t c_lflag;
                                     /* local modes */
01017
01018
         speed_t c_ispeed;
                                     /* input speed */
        speed t c ospeed;
                                    /* output speed */
01019
        cc_t c_cc[NCCS];
01020
                                     /* control characters */
01021 };
01022
01023 /* Values for termios c_iflag bit map. POSIX Table 7-2. */ 01024 #define BRKINT 0x0001 /* signal interrupt on break */
                              0x0002 /* map CR to NL on input */
01025 #define ICRNL
                              0x0004 /* ignore break */
0x0008 /* ignore CR */
01026 #define IGNBRK
01027 #define IGNCR
01028 #define IGNPAR
                              0x0010 /* ignore characters with parity errors */
                              0x0020 /* map NL to CR on input */
0x0040 /* enable input parity check */
01029 #define INLCR
01030 #define INPCK
01031 #define ISTRIP
                              0x0080 /* mask off 8th bit */
                              0x0100 /* enable start/stop input control */
01032 #define TXOFF
                              0x0200 /* enable start/stop output control */
01033 #define IXON
01034 #define PARMRK
                              0x0400 /* mark parity errors in the input queue */
```

```
book.txt
Feb 25, 11 15:18
                                                                       Page 15/393
      File: Page: 652 include/termios.h
01035
01036 /* Values for termios c_oflag bit map. POSIX Sec. 7.1.2.3. */
                             0x0001 /* perform output processing */
01037 #define OPOST
01038
01039 /* Values for termios c_cflag bit map. POSIX Table 7-3. */
01040 #define CLOCAL
                              0x0001 /* ignore modem status lines */
01041 #define CREAD
                              0x0002 /* enable receiver */
                              0x000C /* number of bits per character */
01042 #define CSIZE
                              0x0000 /* if CSIZE is CS5, characters are 5 bits */
01043 #define
01044 #define
                              0x0004 /* if CSIZE is CS6, characters are 6 bits */
                              0x0008 /* if CSIZE is CS7, characters are 7 bits */
01045 #define
                      CS7
01046 #define
                              0x000C /* if CSIZE is CS8, characters are 8 bits */
01047 #define CSTOPB
                              0x0010 /* send 2 stop bits if set, else 1 */
                                     /* hang up on last close */
01048 #define HUPCL
                              0 \times 0.020
01049 #define PARENB
                              0x0040 /* enable parity on output */
01050 #define PARODD
                             0x0080 /* use odd parity if set, else even */
01051
01052 /* Values for termios c_lflag bit map. POSIX Table 7-4. */
01053 #define ECHO
                              0x0001 /* enable echoing of input characters */
                              0x0002 /* echo ERASE as backspace */
01054 #define ECHOE
01055 #define ECHOK
                              0x0004 /* echo KILL */
                             0x0008 /* echo NL */
01056 #define ECHONL
                             0x0010 /* canonical input (erase and kill enabled) */
01057 #define ICANON
01058 #define IEXTEN
                              0x0020 /* enable extended functions */
01059 #define ISIG
                              0x0040 /* enable signals */
                              0x0080 /* disable flush after interrupt or quit */
01060 #define NOFLSH
                       0x0100 /* send SIGTTOU (job control, not implemented*/
01061 #define TOSTOP
01062
01063 /* Indices into c_cc array. Default values in parentheses. POSIX Table 7-5. */
01064 #define VEOF
                                   0 /* cc c[VEOF] = EOF char (^D) */
                                   1 /* cc c[VEOL] = EOL char (undef) */
01065 #define VEOL
                                   2 /* cc_c[VERASE] = ERASE char (^H) */
01066 #define VERASE
                                3 /* cc_c[VINTR] = INTR char (DEL) */
01067 #define VINTR
                                4 /* cc_c[VKILL] = KILL char (^U) */
5 /* cc_c[VMIN] = MIN value for timer */
01068 #define VKILL
01069 #define VMIN
                               6 /* cc_c[VQUIT] = QUIT char (^\) */
7 /* cc_c[VTIME] = TIME value for timer */
8 /* cc_c[VSUSP] = SUSP (^Z, ignored) */
01070 #define VQUIT
01071 #define VTIME
01072 #define VSUSP
01073 #define VSTART
                                 9 /* cc_c[VSTART] = START char (^S) */
                                 10  /* cc_c[VSTOP] = STOP char (^Q) */
01074 #define VSTOP
01075
01076 #define POSIX VDISABLE (cc t)0xFF
                                             /* You can't even generate this
01077
                                              * character with 'normal' keyboards.
                                               * But some language specific keyboards
01078
01079
                                              * can generate 0xFF. It seems that all
01080
                                              * 256 are used, so cc_t should be a
01081
                                               * short...
01082
01083
01084 /* Values for the baud rate settings. POSIX Table 7-6. */
01086 #define B50
                              0x1000 /* 50 baud */
                             0x2000 /* 75 baud */
01087 #define B75
01088 #define B110
                             0x3000 /* 110 baud */
01089 #define B134
                             0x4000 /* 134.5 baud */
                              0x5000 /* 150 baud */
01090 #define B150
01091 #define B200
                              0x6000 /* 200 baud */
01092 #define B300
                              0x7000 /* 300 baud */
                             0x8000 /* 600 baud */
01093 #define B600
01094 #define B1200
                             0x9000 /* 1200 baud */
```

```
book.txt
 Feb 25, 11 15:18
                                                                                   Page 16/393
        File: Page: 653 include/termios.h
                                  0xA000 /* 1800 baud */
0xB000 /* 2400 baud */
        #define B1800
01096
        #define B2400
                                   0xC000 /* 4800 baud */
        #define B4800
01098
        #define B9600
                                   0xD000 /* 9600 baud */
0xE000 /* 19200 baud */
01099 #define B19200
01100 #define B38400
                                   0xF000 /* 38400 baud */
01101
01102 /* Optional actions for tcsetattr(). POSIX Sec. 7.2.1.2. */
        #define TCSANOW 1 /* changes take effect immediately */
01103
                                         /* changes take effect after output is done */
/* wait for output to finish and flush input */
01104
        #define TCSADRAIN
01105
        #define TCSAFLUSH
                                      3
01107 /* Queue_selector values for tcflush(). POSIX Sec. 7.2.2.2. */
01108 #define TCIFLUSH 1 /* flush accumulated input data */
01109 #define TCOFLUSH 2 /* flush accumulated output data */
01110 #define TCIOFLUSH
                                      3 /* flush accumulated input and output data */
01111
01112 /* Action values for tcflow(). POSIX Sec. 7.2.2.2. */
01113 #define TCOOFF 1 /* suspend output */
01114 #define TCOON 2 /* restart suspended output */
01115 #define TCIOFF
                                          /* transmit a STOP character on the line */
01116 #define TCION
                                      4 /* transmit a START character on the line */
01117
01118 /* Function Prototypes. */
01119 #ifndef _ANSI_H
01120 #include <ansi.h>
01121 #endif
01122
01123
       _PROTOTYPE( int tcsendbreak, (int _fildes, int _duration)
01124 _PROTOTYPE( int tcdrain, (int _filedes)
01125 _PROTOTYPE( int tcflush, (int _filedes, int _queue_selector)
01126 _PROTOTYPE( int tcflow, (int _filedes, int _action)
                                                                                               );
01127 _PROTOTYPE( speed_t cfgetispeed, (const struct termios *_termios_p)
01128
        _PROTOTYPE( speed_t cfgetospeed, (const struct termios *_termios_p)
                                                                                               );
01129 _PROTOTYPE( int cfsetispeed, (struct termios *_termios_p, speed_t _speed)
01130 _PROTOTYPE( int cfsetospeed, (struct termios *_termios_p, speed_t _speed)
                                                                                               );
01131 _PROTOTYPE( int tcgetattr, (int _filedes, struct termios *_termios_p)
01132 _PROTOTYPE( int tcsetattr, \
01133
                 (int _filedes, int _opt_actions, const struct termios *_termios_p)
01134
01135
        #define cfgetispeed(termios_p)
                                                     ((termios_p)->c_ispeed)
        #define cfgetospeed(termios p)
                                                     ((termios_p)->c_ospeed)
        #define cfsetispeed(termios_p, speed)
01137
                                                    ((termios_p)->c_ispeed = (speed), 0)
01138
        #define cfsetospeed(termios_p, speed)
                                                    ((termios_p)->c_ospeed = (speed), 0)
01139
01140
        #ifdef MINIX
01141
        /* Here are the local extensions to the POSIX standard for Minix. Posix
         * conforming programs are not able to access these, and therefore they are
01143
         * only defined when a Minix program is compiled.
01144
01145
01146
        /* Extensions to the termios c_iflag bit map. */
                                   0x0800 /* allow any key to continue ouptut */
01147 #define IXANY
01148
01149 /* Extensions to the termios c_oflag bit map. They are only active iff
        * OPOST is enabled. */
01150
        #define ONLCR
                                   0x0002 /* Map NL to CR-NL on output */
                                  0x0004 /* Expand tabs to spaces */
0x0008 /* discard EOT's (^D) on output) */
        #define XTABS
01152
01153 #define ONOEOT
01154
```

```
Feb 25, 11 15:18
                                       book.txt
                                                                        Page 17/393
      File: Page: 654 include/termios.h
01155 /* Extensions to the termios c_lflag bit map. */
01156 #define LFLUSHO
                             0x0200 /* Flush output. */
01158 /* Extensions to the c_cc array. */
                                     /* cc_c[VREPRINT] (^R) */
                               11
01159 #define VREPRINT
01160 #define VLNEXT
                                12
                                     /* cc_c[VLNEXT] (^V) */
01161 #define VDISCARD
                                13
                                     /* cc_c[VDISCARD] (^0) */
01162
01163 /* Extensions to baud rate settings. */
01164 #define B57600
                              0x0100 /* 57600 baud */
0x0200 /* 115200 baud */
01165 #define B115200
01166
01167 /* These are the default settings used by the kernel and by 'stty sane' */
01168
                              (CREAD | CS8 | HUPCL)
01169 #define TCTRL DEF
01170 #define TINPUT DEF
                              (BRKINT | ICRNL | IXON | IXANY)
01171 #define TOUTPUT_DEF
                              (OPOST | ONLCR)
01172 #define TLOCAL_DEF
                              (ISIG | IEXTEN | ICANON | ECHO | ECHOE)
01173 #define TSPEED_DEF
                              B9600
01174
01175 #define TEOF_DEF
                              '\4' /* ^D */
01176 #define TEOL DEF
                               _POSIX_VDISABLE
                              /\10' - /* ^H */
01177 #define TERASE_DEF
                                     /* ^C */
                              '\3'
01178 #define TINTR DEF
                                     /* ^[] */
01179 #define TKILL_DEF
                              '\25'
01180 #define TMIN_DEF
                              '\34'
                                     /* ^\ */
01181 #define TOUIT DEF
                              '\21' /* ^Q */
01182 #define TSTART DEF
                                     /* ^S */
                               ′\23′
01183 #define TSTOP_DEF
                                     /* ^Z */
01184 #define TSUSP DEF
                              '\32'
01185 #define TTIME DEF
                              0
                              '\22'
01186 #define TREPRINT_DEF
                                     /* ^R */
                              '\26' /* ^V */
01187 #define TLNEXT_DEF
01188 #define TDISCARD_DEF
                              '\17'
                                     /* ^0 */
01189
01190 /* Window size. This information is stored in the TTY driver but not used.
01191 * This can be used for screen based applications in a window environment.
01192 * The ioctls TIOCGWINSZ and TIOCSWINSZ can be used to get and set this
01193 * information.
01194 */
01195
01196 struct winsize
01197
01198
               unsigned short ws_row;
                                              /* rows, in characters */
                                              /* columns, in characters */
01199
               unsigned short ws col;
01200
                                              /* horizontal size, pixels */
              unsigned short ws_xpixel;
01201
              unsigned short ws_ypixel;
                                              /* vertical size, pixels */
01202
01203 #endif /* _MINIX */
01204
01205 #endif /* _TERMIOS_H */
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 18/393
       File: Page: 655 include/timers.h
include/timers.h
01300 /* This library provides generic watchdog timer management functionality.
01301 * The functions operate on a timer queue provided by the caller. Note that
       * the timers must use absolute time to allow sorting. The library provides:
01302
01303
01304
            tmrs_settimer:
                               (re)set a new watchdog timer in the timers queue
01305
            tmrs clrtimer:
                               remove a timer from both the timers queue
01306
            tmrs exptimers:
                               check for expired timers and run watchdog functions
01307
       * Author:
01308
            Jorrit N. Herder < jnherder@cs.vu.nl>
01309
01310
            Adapted from tmr_settimer and tmr_clrtimer in src/kernel/clock.c.
01311
            Last modified: September 30, 2004.
01312 */
01313
01314 #ifndef _TIMERS_H
01315 #define _TIMERS_H
01316
01317
      #include <limits.h>
01318 #include <sys/types.h>
01319
01320 struct timer;
01321 typedef void (*tmr func t)(struct timer *tp);
01322 typedef union { int ta_int; long ta_long; void *ta_ptr; } tmr_arg_t;
01323
01324 /* A timer t variable must be declare for each distinct timer to be used.
       * The timers watchdog function and expiration time are automatically set
01325
01326
       * by the library function tmrs_settimer, but its argument is not.
01327
01328 typedef struct timer
01329
01330
        struct timer *tmr_next;
                                    /* next in a timer chain */
01331
        clock t
                     tmr_exp_time;
                                    /* expiration time */
                                    /* function to call when expired */
01332
        tmr_func_t
                     tmr_func;
01333
        tmr arg t
                     tmr arg;
                                    /* random argument */
01334
      } timer_t;
01335
01336
       /* Used when the timer is not active. */
      #define TMR NEVER
01337
                         ((clock_t) -1 < 0)? ((clock_t) LONG_MAX): ((clock_t) -1)
01338 #undef TMR_NEVER
01339 #define TMR NEVER
                             ((clock t) LONG MAX)
01340
01341
       /st These definitions can be used to set or get data from a timer variable. st/
01342 #define tmr_arg(tp) (&(tp)->tmr_arg)
01343 #define tmr_exp_time(tp) (&(tp)->tmr_exp_time)
01344
01345 /* Timers should be initialized once before they are being used. Be careful
01346
       * not to reinitialize a timer that is in a list of timers, or the chain
       * will be broken.
01347
01348
01349 #define tmr_inittimer(tp) (void)((tp)->tmr_exp_time = TMR_NEVER, \
01350
              (tp)->tmr next = NULL)
01351
01352 /* The following generic timer management functions are available. They
01353 * can be used to operate on the lists of timers. Adding a timer to a list
01354 * automatically takes care of removing it.
```

```
book.txt
Feb 25, 11 15:18
                                                                  Page 19/393
      File: Page: 656 include/timers.h
01355
01356
      _PROTOTYPE( clock_t tmrs_clrtimer, (timer_t **tmrs, timer_t *tp, clock_t *new_he
ad)
      _PROTOTYPE( void tmrs_exptimers, (timer_t **tmrs, clock_t now, clock_t *new head
01357
      _PROTOTYPE( clock_t tmrs_settimer, (timer_t **tmrs, timer_t *tp,
01359
              clock_t exp_time, tmr_func_t watchdog, clock_t *new_head)
01360
      #endif /* _TIMERS_H */
01361
01362
include/sys/types.h
01400 /* The <sys/types.h> header contains important data type definitions.
01401 * It is considered good programming practice to use these definitions,
      * instead of the underlying base type. By convention, all type names end
01403
      * with _t.
01404
01405
01406 #ifndef _TYPES_H
01407 #define TYPES H
01408
01409 #ifndef _ANSI_H
01410 #include <ansi.h>
01411 #endif
01412
01413 /* The type size_t holds all results of the sizeof operator. At first glance,
01414 * it seems obvious that it should be an unsigned int, but this is not always
      * the case. For example, MINIX-ST (68000) has 32-bit pointers and 16-bit
01415
      * integers. When one asks for the size of a 70K struct or array, the result
01416
01417
      * requires 17 bits to express, so size_t must be a long type. The type
01418
       * ssize_t is the signed version of size_t.
01419 */
01420 #ifndef SIZE T
01421 #define _SIZE_T
01422 typedef unsigned int size_t;
01423 #endif
01424
01425 #ifndef _SSIZE_T
01426 #define SSIZE T
01427 typedef int ssize t;
01428 #endif
01429
01430 #ifndef _TIME_T
01431 #define _TIME_T
                                     /* time in sec since 1 Jan 1970 0000 GMT */
01432 typedef long time_t;
01433 #endif
01434
01435 #ifndef _CLOCK_T
01436 #define _CLOCK_T
01437 typedef long clock_t;
                                     /* unit for system accounting */
01438 #endif
01439
01440 #ifndef _SIGSET_T
01441 #define SIGSET T
01442 typedef unsigned long sigset_t;
01443 #endif
01444
```

```
Feb 25, 11 15:18
                                      book.txt
                                                                      Page 20/393
      File: Page: 657 include/sys/types.h
01445 /* Open Group Base Specifications Issue 6 (not complete) */
01446 typedef long useconds_t;
                                     /* Time in microseconds */
01447
01448
      /* Types used in disk, inode, etc. data structures. */
01449
      typedef short
                            dev_t;
                                        /* holds (major|minor) device pair */
01450 typedef char
                            gid_t;
                                        /* group id */
01451 typedef unsigned long ino_t;
                                        /* i-node number (V3 filesystem) */
                                        /* file type and permissions bits */
01452 typedef unsigned short mode_t;
                                        /* number of links to a file */
01453 typedef short
                         nlink t;
      typedef unsigned long off_t;
                                        /* offset within a file */
01454
                                        /* process id (must be signed) */
01455
      typedef int
                            pid t;
01456
      typedef short
                            uid t;
                                        /* user id */
                                        /* zone number */
01457
      typedef unsigned long zone_t;
                                        /* block number */
01458
      typedef unsigned long block_t;
      typedef unsigned long bit t;
                                        /* bit number in a bit map */
01459
      typedef unsigned short zonel_t;
                                        /* zone number for V1 file systems */
01460
01461
      typedef unsigned short bitchunk_t; /* collection of bits in a bitmap */
01462
01463 typedef unsigned char u8_t;
                                        /* 8 bit type */
                                        /* 16 bit type */
01464 typedef unsigned short u16_t;
01465 typedef unsigned long u32_t;
                                        /* 32 bit type */
01466
01467
      typedef char
                             i8_t;
                                        /* 8 bit signed type */
01468
      typedef short
                            i16 t;
                                        /* 16 bit signed type */
      typedef long
                                        /* 32 bit signed type */
01469
                            i32_t;
01470
01471 typedef struct { u32_t _[2]; } u64_t;
01472
* definitions (for maximum portability). When a short, such as dev t, is
01474
       * passed to a function with a K&R definition, the compiler automatically
01475
01476
       * promotes it to an int. The prototype must contain an int as the parameter,
01477
       * not a short, because an int is what an old-style function definition
01478
       * expects. Thus using dev_t in a prototype would be incorrect. It would be
       * sufficient to just use int instead of dev_t in the prototypes, but Dev_t
01479
01480
       * is clearer.
01481
       * /
01482 typedef int
                            Dev_t;
01483 typedef int
                        _mnx_Gid_t;
      typedef int
01484
                          Nlink_t;
01485
      typedef int
                        _mnx_Uid_t;
                             U8_t;
01486
      typedef int
01487
      typedef unsigned long U32_t;
01488
      typedef int
                             I8_t;
01489 typedef int
                             I16 t;
01490 typedef long
                            I32 t;
01491
01492 /* ANSI C makes writing down the promotion of unsigned types very messy. When
01493
       * sizeof(short) == sizeof(int), there is no promotion, so the type stays
01494
       * unsigned. When the compiler is not ANSI, there is usually no loss of
       * unsignedness, and there are usually no prototypes so the promoted type
01496
       * doesn't matter. The use of types like Ino_t is an attempt to use ints
       * (which are not promoted) while providing information to the reader.
01497
01498
01499
01500 typedef unsigned long Ino_t;
01501
01502
      #if _EM_WSIZE == 2
01503
      /*typedef unsigned int
                                 Ino_t; Ino_t is now 32 bits */
01504 typedef unsigned int Zonel t;
```

```
Feb 25, 11 15:18
                                    book.txt
                                                                  Page 21/393
      File: Page: 658 include/sys/types.h
01505 typedef unsigned int Bitchunk t;
01506 typedef unsigned int U16_t;
01507 typedef unsigned int _mnx_Mode_t;
01508
01509 #else /* _EM_WSIZE == 4, or _EM_WSIZE undefined */
01510 /*typedef int
                            Ino_t; Ino_t is now 32 bits */
01511 typedef int
                            Zonel t;
01512 typedef int
                         Bitchunk_t;
01513 typedef int
                         U16 t;
01514 typedef int
                        _mnx_Mode_t;
01515
01516 #endif /* _EM_WSIZE == 2, etc */
01517
01518 /* Signal handler type, e.g. SIG_IGN */
01519 typedef void _PROTOTYPE( (*sighandler_t), (int) );
01520
01521 /* Compatibility with other systems */
01522 typedef unsigned char u_char;
01523 typedef unsigned short u_short;
01524 typedef unsigned int u_int;
01525 typedef unsigned long
                            u_long;
01526 typedef char
                            *caddr t;
01527
01528 #endif /* _TYPES_H */
include/sys/sigcontext.h
01600 #ifndef _SIGCONTEXT_H
01601 #define _SIGCONTEXT_H
01603 /* The sigcontext structure is used by the sigreturn(2) system call.
01604 * sigreturn() is seldom called by user programs, but it is used internally
01605 * by the signal catching mechanism.
01606 */
01607
01608 #ifndef ANSI H
01609 #include <ansi.h>
01610 #endif
01611
01612 #ifndef _MINIX_SYS_CONFIG_H
01613 #include <minix/sys_config.h>
01614 #endif
01615
01616 #if !defined(_MINIX_CHIP)
01617 #include "error, configuration is not known"
01618 #endif
01619
01620 /* The following structure should match the stackframe_s structure used
01621 * by the kernel's context switching code. Floating point registers should 01622 * be added in a different struct.
01623 */
01624 struct sigregs {
01625
       short sr qs;
01626
        short sr fs;
01627
        short sr es;
01628
        short sr_ds;
01629
        int sr di;
```

```
Feb 25, 11 15:18
                                       book.txt
                                                                        Page 22/393
      File: Page: 659 include/sys/sigcontext.h
01630
        int sr si;
01631
        int sr_bp;
01632
        int sr_st;
                                      /* stack top -- used in kernel */
01633
        int sr_bx;
01634
        int sr_dx;
01635
        int sr_cx;
01636
        int sr_retreg;
                                      /* return address to caller of save -- used
01637
        int sr_retadr;
                                       * in kernel */
01638
01639
        int sr_pc;
01640
        int sr cs;
01641
        int sr psw;
01642
        int sr_sp;
01643
        int sr_ss;
01644 };
01645
01646 struct sigframe {
                                      /* stack frame created for signalled process */
       _PROTOTYPE( void (*sf_retadr), (void) );
01647
01648
        int sf_signo;
01649
       int sf_code;
01650
       struct sigcontext *sf_scp;
01651
        int sf fn;
01652
        _PROTOTYPE( void (*sf_retadr2), (void) );
01653
       struct sigcontext *sf_scpcopy;
01654 };
01655
01656 struct sigcontext {
01657
        int sc_flags;
                                      /* sigstack state to restore */
                                      /* signal mask to restore */
01658
        long sc_mask;
01659
                                     /* register set to restore */
        struct sigregs sc regs;
01660 };
01661
01662 #define sc_gs sc_regs.sr_gs
01663 #define sc_fs sc_regs.sr_fs
01664 #define sc_es sc_regs.sr_es
01665 #define sc_ds sc_regs.sr_ds
01666 #define sc_di sc_regs.sr_di
01667 #define sc_si sc_regs.sr_si
01668 #define sc_fp sc_regs.sr_bp
01669 #define sc_st sc_regs.sr_st
                                             /* stack top -- used in kernel */
01670 #define sc_bx sc_regs.sr_bx
01671 #define sc_dx sc_regs.sr_dx
01672 #define sc_cx sc_regs.sr_cx
01673 #define sc_retreg sc_regs.sr_retreg
                                              /* return address to caller of
01674 #define sc_retadr sc_regs.sr_retadr
01675
                                              save -- used in kernel */
01676
      #define sc_pc sc_regs.sr_pc
01677 #define sc_cs sc_regs.sr_cs
01678 #define sc_psw sc_regs.sr_psw
01679 #define sc_sp sc_regs.sr_sp
01680 #define sc_ss sc_regs.sr_ss
01681
01682 /* Values for sc_flags. Must agree with <minix/jmp_buf.h>. */
01683 #define SC SIGCONTEXT 2
                                     /* nonzero when signal context is included */
01684 #define SC_NOREGLOCALS 4
                                      /* nonzero when registers are not to be
01685
                                              saved and restored */
01686
01687 _PROTOTYPE( int sigreturn, (struct sigcontext *_scp)
                                                                             );
01688
01689 #endif /* SIGCONTEXT H */
```

```
book.txt
 Feb 25, 11 15:18
                                                                   Page 23/393
      File: Page: 660 include/sys/stat.h
include/sys/stat.h
01700 /* The <sys/stat.h> header defines a struct that is used in the stat() and
01701 * fstat functions. The information in this struct comes from the i-node of
01702
      * some file. These calls are the only approved way to inspect i-nodes.
01703 */
01704
01705 #ifndef _STAT_H
01706 #define _STAT_H
01707
01708 #ifndef _TYPES_H
01709 #include <sys/types.h>
01710 #endif
01711
01712 struct stat {
01713
        dev t st dev;
                                   /* major/minor device number */
                                   /* i-node number */
01714
        ino_t st_ino;
01715
        mode_t st_mode;
                                   /* file mode, protection bits, etc. */
01716
        short int st_nlink;
                                   /* # links; TEMPORARY HACK: should be nlink_t*/
                                   /* uid of the file's owner */
01717
        uid_t st_uid;
01718
        short int st gid;
                                   /* gid; TEMPORARY HACK: should be gid t */
        dev_t st_rdev;
01719
01720
        off_t st_size;
                                   /* file size */
                                   /* time of last access */
01721
        time t st atime;
01722
        time_t st_mtime;
                                   /* time of last data modification */
                                   /* time of last file status change */
01723
        time_t st_ctime;
01724 };
01725
01726 /* Traditional mask definitions for st_mode. */
01727 /* The ugly casts on only some of the definitions are to avoid suprising sign
01728 * extensions such as S_IFREG != (mode_t) S_IFREG when ints are 32 bits.
01729 */
01730 #define S_IFMT ((mode_t) 0170000)
                                          /* type of file */
                                         /* symbolic link, not implemented */
01731 #define S_IFLNK ((mode_t) 0120000)
                                          /* regular */
01732 #define S_IFREG ((mode_t) 0100000)
01733 #define S_IFBLK 0060000
                                 /* block special */
01734 #define S_IFDIR 0040000
                                   /* directory */
01735 #define S_IFCHR 0020000
                                   /* character special */
01736 #define S IFIFO 0010000
                                   /* this is a FIFO */
01737 #define S_ISUID 0004000
                                   /* set user id on execution */
01738 #define S_ISGID 0002000
                                   /* set group id on execution */
                                   /* next is reserved for future use */
01739
01740 #define S ISVTX 01000
                                   /* save swapped text even after use */
01741
01742 /* POSIX masks for st_mode. */
01743 #define S IRWXU 00700
                                   /* owner: rwx----- */
                                   /* owner: r---- */
01744 #define S_IRUSR
                       00400
01745 #define S_IWUSR
                       00200
                                   /* owner: -w---- */
01746 #define S_IXUSR
                       00100
                                   /* owner: --x---- */
01747
01748 #define S_IRWXG
                       00070
                                    /* group:
                                             ---rwx--- */
01749 #define S_IRGRP
                       00040
                                   /* group: ---r--- */
                                    /* group:
                                              ----w---- */
01750 #define S_IWGRP
                       00020
01751 #define S_IXGRP
                       00010
                                   /* group:
                                             ----×--- */
01752
                                   /* others: ----rwx */
01753
      #define S_IRWXO
                       00007
01754 #define S IROTH 00004
                                   /* others: -----*/
```

```
book.txt
 Feb 25, 11 15:18
                                                              Page 24/393
      File: Page: 661 include/sys/stat.h
01755 #define S_IWOTH 00002
                                 /* others: ----w- */
01756 #define S_IXOTH 00001
                                 /* others: ----x */
01757
01758
      /* The following macros test st_mode (from POSIX Sec. 5.6.1.1). */
01759 #define S_ISREG(m)
                                                    /* is a reg file */
                          (((m) & S_IFMT) == S_IFREG)
01760 #define S_ISDIR(m)
                          ((m) \& S_{IFMT}) == S_{IFDIR}
                                                     /* is a directory */
01761 #define S_ISCHR(m)
                          ((m) \& S_{IFMT}) == S_{IFCHR}
                                                     /* is a char spec */
                                                     /* is a block spec */
01762 #define S_ISBLK(m)
                          ((m) \& S_IFMT) == S_IFBLK)
                                                   /* is a pipe/FIFO */
01763 #define S ISFIFO(m)
                          ((m) \& S_{IFMT}) == S_{IFIFO}
                          (((m) & S_IFMT) == S_IFLNK)
                                                   /* is a sym link */
01764 #define S_ISLNK(m)
01765
01766 /* Function Prototypes. */
01767 _PROTOTYPE( int chmod, (const char *_path, _mnx_Mode_t _mode)
                                                                   );
      _PROTOTYPE( int fstat, (int _fildes, struct stat *_buf)
01768
                                                                   );
01769 _PROTOTYPE( int mkdir, (const char *_path, _mnx_Mode_t _mode)
                                                                   );
01770
     _PROTOTYPE( int mkfifo, (const char *_path, _mnx_Mode_t _mode)
                                                                   );
01771 _PROTOTYPE( int stat, (const char *_path, struct stat *_buf)
                                                                   );
01772 _PROTOTYPE( mode_t umask, (_mnx_Mode_t _cmask)
                                                                   );
01773
01774 /* Open Group Base Specifications Issue 6 (not complete) */
01775 _PROTOTYPE( int lstat, (const char *_path, struct stat *_buf)
                                                                   );
01776
01777 #endif /* _STAT_H */
include/svs/dir.h
01800 /* The <dir.h> header gives the layout of a directory. */
01801
01802 #ifndef _DIR_H
01803 #define _DIR_H
01804
01805 #include <sys/types.h>
01806
01807 #define DIRBLKSIZ
                               /* size of directory block */
                          512
01808
01809 #ifndef DIRSIZ
01810 #define DIRSIZ 60
01811 #endif
01812
01813 struct direct {
01814
      ino t d ino;
01815
       char d_name[DIRSIZ];
01816 };
01817
01818 #endif /* _DIR_H */
include/svs/wait.h
01900 /* The <sys/wait.h> header contains macros related to wait(). The value
01901 * returned by wait() and waitpid() depends on whether the process
      * terminated by an exit() call, was killed by a signal, or was stopped
01902
      * due to job control, as follows:
01903
01904
```

```
book.txt
Feb 25, 11 15:18
                                                                  Page 25/393
      File: Page: 662 include/sys/wait.h
01905
                                    High byte Low byte
01906
01907
             exit(status)
                                     status
                                                 0
01908
                                     0 | signal
01909
             killed by signal
01910
01911
             stopped (job control)
                                   | signal | 0177
01912
                                               -----
01913 */
01914
01915
      #ifndef _WAIT_H
01916 #define _WAIT_H
01917
01918 #ifndef _TYPES_H
01919 #include <sys/types.h>
01920 #endif
01921
                            ( (v) & 0377)
01922 #define _LOW(v)
01923 #define _HIGH(v)
                           ( ((v) >> 8) & 0377)
01924
01925 #define WNOHANG
                                   /* do not wait for child to exit */
01926 #define WUNTRACED
                                  /* for job control; not implemented */
01927
01928 #define WIFEXITED(s)
                            (LOW(s) == 0)
                                                            /* normal exit */
01929 #define WEXITSTATUS(s) (_HIGH(s))
                                                           /* exit status */
                                                            /* sig value */
01930 #define WTERMSIG(s)
                            ( LOW(s) & 0177)
                           (((unsigned int)(s)-1 & 0xFFFF) < 0xFF) /* signaled */
01931 #define WIFSIGNALED(s)
01932 #define WIFSTOPPED(s)
                           (LOW(s) == 0177)
                                                           /* stopped */
                                                           /* stop signal */
01933 #define WSTOPSIG(s)
                            (_HIGH(s) & 0377)
01934
01935 /* Function Prototypes. */
01936 _PROTOTYPE( pid_t wait, (int *_stat_loc)
01937 _PROTOTYPE( pid_t waitpid, (pid_t _pid, int *_stat_loc, int _options)
01938
01939 #endif /* _WAIT_H */
include/sys/ioctl.h
02000 /*
             sys/ioctl.h - All ioctl() command codes.
                                                        Author: Kees J. Bot
02001 *
                                                               23 Nov 2002
02002
02003
      * This header file includes all other ioctl command code headers.
02004
02005
02006 #ifndef _S_IOCTL_H
02007 #define _S_IOCTL_H
02008
02009 /* A driver that uses ioctls claims a character for its series of commands.
02010 * For instance: #define TCGETS _IOR('T', 8, struct termios)
02011 * This is a terminal ioctl that uses the character 'T'. The character(s)
02012 * used in each header file are shown in the comment following.
02013 */
02014
                                  /* 'T' 't' 'k'
02015 #include <sys/ioc_tty.h>
                                  /* 'd'
02016 #include <sys/ioc_disk.h>
                                  /* 'm'
02017 #include <sys/ioc_memory.h>
                                  /* 'C'
02018 #include <sys/ioc_cmos.h>
02019
```

```
Feb 25, 11 15:18
                                   book.txt
                                                                Page 26/393
      File: Page: 663 include/sys/ioctl.h
02020 #endif /* _S_IOCTL_H */
include/sys/ioc_disk.h
02100 /*
             sys/ioc_disk.h - Disk ioctl() command codes. Author: Kees J. Bot
02101
                                                              23 Nov 2002
02102
02103
02104
02105 #ifndef _S_I_DISK_H
02106 #define _S_I_DISK_H
02107
02108 #include <minix/ioctl.h>
02109
02110 #define DIOCSETP
                           _IOW('d', 3, struct partition)
02111 #define DIOCGETP
                          _IOR('d', 4, struct partition)
02112 #define DIOCEJECT
                           _IO ('d', 5)
02113 #define DIOCTIMEOUT
                           _IOW('d', 6, int)
02114 #define DIOCOPENCT
                           _IOR('d', 7, int)
02115
02116 #endif /* _S_I_DISK_H */
                                include/minix/ioctl.h
minix/ioctl.h - Ioctl helper definitions.
                                                       Author: Kees J. Bot
02201
                                                              23 Nov 2002
02202 *
02203 * This file is included by every header file that defines ioctl codes.
02204
02205
02206 #ifndef M IOCTL H
02207 #define _M_IOCTL_H
02208
02209 #ifndef TYPES H
02210 #include <sys/types.h>
02211 #endif
02212
02213 #if _EM_WSIZE >= 4
02214 /* Toctls have the command encoded in the low-order word, and the size
02215
       * of the parameter in the high-order word. The 3 high bits of the high-
02216
       * order word are used to encode the in/out/void status of the parameter.
02217 */
02218 #define _IOCPARM_MASK
                           0x1FFF
02219 #define _IOC_VOID
                           0x20000000
02220
      #define _IOCTYPE_MASK
                           0xFFFF
02221 #define _IOC_IN
                           0x40000000
02222
      #define _IOC_OUT
                           0x80000000
02223
      #define _IOC_INOUT
                           (_IOC_IN | _IOC_OUT)
02224
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                     Page 27/393
       File: Page: 664 include/minix/ioctl.h
                             ((x << 8) | y | _IOC_VOID)
((x << 8) | y | ((sizeof(t) & _IOCPARM_MASK) << 16) |\
02225 #define _IO(x,y)
02226 #define _{IOR(x,y,t)}
                                     _ioc_out)
02227
                             ((x << 8) | y | ((sizeof(t) & _IOCPARM_MASK) << 16) | 
02228 #define _IOW(x,y,t)
02229
                                     _IOC_IN)
02230 #define _IORW(x,y,t)
                             ((x << 8) | y | ((sizeof(t) & _IOCPARM_MASK) << 16) |\
02231
                                     _IOC_INOUT)
02232 #else
02233 /* No fancy encoding on a 16-bit machine. */
02234
02235 #define _IO(x,y)
                             ((x << 8) | y)
                             _IO(x,y)
02236 #define _IOR(x,y,t)
02237 #define _IOW(x,y,t)
                             _{IO(x,y)}
02238 #define _IORW(x,y,t)
                             IO(x,y)
02239 #endif
02240
02241 int ioctl(int _fd, int _request, void *_data);
02242
02243 #endif /* M IOCTL H */
include/minix/config.h
02300 #ifndef _CONFIG_H
02301 #define _CONFIG_H
02302
02303 /* Minix release and version numbers. */
02304 #define OS RELEASE "3"
02305 #define OS VERSION "1.0"
02306
02307 /* This file sets configuration parameters for the MINIX kernel, FS, and PM.
02308 * It is divided up into two main sections. The first section contains
       * user-settable parameters. In the second section, various internal system
02309
02310
       * parameters are set based on the user-settable parameters.
02311
02312
       * Parts of config.h have been moved to sys_config.h, which can be included
02313
       * by other include files that wish to get at the configuration data, but
        * don't want to pollute the users namespace. Some editable values have
02314
02315
        * gone there.
02316
       * This is a modified version of config.h for compiling a small Minix system
02317
02318
       * with only the options described in the text, Operating Systems Design and
       * Implementation, 3rd edition. See the version of config.h in the full
       * source code directory for information on alternatives omitted here.
02320
02321
02322
02323 /* The MACHINE (called _MINIX_MACHINE) setting can be done
02324 * in <minix/machine.h>.
02325 */
02326 #include <minix/sys_config.h>
02327
                          _MINIX_MACHINE
02328 #define MACHINE
02329
02330 #define IBM PC
                           MACHINE IBM PC
02331 #define SUN 4
                          MACHINE SUN 4
02332 #define SUN 4 60
                           _MACHINE_SUN_4_60
02333 #define ATARI
                           _MACHINE_ATARI
02334 #define MACINTOSH
                          MACHINE MACINTOSH
```

```
Feb 25, 11 15:18
                                    book.txt
                                                                  Page 28/393
       File: Page: 665 include/minix/config.h
02335
02336 /* Number of slots in the process table for non-kernel processes. The number
02337
       * of system processes defines how many processes with special privileges
       * there can be. User processes share the same properties and count for one.
02338
02339
02340
       * These can be changed in sys_config.h.
02341
02342 #define NR_PROCS
                              NR PROCS
02343 #define NR_SYS_PROCS
                              _NR_SYS_PROCS
02344
02345
       #define NR BUFS 128
02346
      #define NR BUF HASH 128
02347
02348 /* Number of controller tasks (/dev/cN device classes). */
02349 #define NR CTRLRS
02350
02351 /* Enable or disable the second level file system cache on the RAM disk. */
02352 #define ENABLE_CACHE2
02353
02354 /* Enable or disable swapping processes to disk. */
02355 #define ENABLE_SWAP
02356
02357 /* Include or exclude an image of /dev/boot in the boot image.
02358 * Please update the makefile in /usr/src/tools/ as well.
02359
02360
      #define ENABLE BOOTDEV
                             0 /* load image of /dev/boot at boot time */
02361
02362
      /* DMA_SECTORS may be increased to speed up DMA based drivers. */
                              1 /* DMA buffer size (must be >= 1) */
02363 #define DMA_SECTORS
02364
02365 /* Include or exclude backwards compatibility code. */
02366 #define ENABLE_BINCOMPAT 0 /* for binaries using obsolete calls */
02367 #define ENABLE_SRCCOMPAT 0 /* for sources using obsolete calls */
02368
02369 /* Which process should receive diagnostics from the kernel and system?
02370
       * Directly sending it to TTY only displays the output. Sending it to the
02371
       * log driver will cause the diagnostics to be buffered and displayed.
02372 */
02373 #define OUTPUT_PROC_NR LOG_PROC_NR /* TTY_PROC_NR or LOG_PROC_NR */
02374
02375
      /* NR CONS, NR RS LINES, and NR PTYS determine the number of terminals the
       * system can handle.
02376
       */
02377
02378 #define NR_CONS
                                   /* # system consoles (1 to 8) */
                                 /* # rs232 terminals (0 to 4) */
02379 #define NR RS LINES
                              0
02380 #define NR PTYS
                              0  /* # pseudo terminals (0 to 64) */
02381
02382 /*=========*
02383 * There are no user-settable parameters after this line
02385 /* Set the CHIP type based on the machine selected. The symbol CHIP is actually
02386
      * indicative of more than just the CPU. For example, machines for which
02387 * CHIP == INTEL are expected to have 8259A interrrupt controllers and the
02388 * other properties of IBM PC/XT/AT/386 types machines in general. */
02389 #define INTEL
                              _CHIP_INTEL /* CHIP type for PC, XT, AT, 386 and clo
nes */
02390 #define M68000
                              CHIP M68000 /* CHIP type for Atari, Amiga, Macintosh
02391
       #define SPARC
                              _CHIP_SPARC /* CHIP type for SUN-4 (e.g. SPARCstatio
n) */
02392
02394 #define FP_NONE _FP_NONE /* no floating point support
```

```
Feb 25, 11 15:18
                                  book.txt
                                                              Page 29/393
      File: Page: 666 include/minix/config.h
02395 #define FP_IEEE _FP_IEEE
                                 /* conform IEEE floating point standard
02396
02397 /* _MINIX_CHIP is defined in sys_config.h. */
02398 #define CHIP _MINIX_CHIP
02399
02400 /* _MINIX_FP_FORMAT is defined in sys_config.h. */
02401 #define FP_FORMAT
                         _MINIX_FP_FORMAT
02402
02403 /* _ASKDEV and _FASTLOAD are defined in sys_config.h. */
02404 #define ASKDEV _ASKDEV
02405 #define FASTLOAD FASTLOAD
02407 #endif /* _CONFIG_H */
include/minix/sys_config.h
02500 #ifndef _MINIX_SYS_CONFIG_H
02501 #define _MINIX_SYS_CONFIG_H 1
02502
02503 /* This is a modified sys_config.h for compiling a small Minix system
02504 * with only the options described in the text, Operating Systems Design and
02505 * Implementation, 3rd edition. See the sys_config.h in the full
02506 * source code directory for information on alternatives omitted here.
02507
02508
02509 /*=========*
02510 *
          This section contains user-settable parameters
02511 *=========*/
02512 #define _MINIX_MACHINE __MACHINE_IBM_PC
02513
02514 #define _MACHINE_IBM_PC 1 /* any 8088 or 80x86-based system */
02515
02516 /* Word size in bytes (a constant equal to sizeof(int)). */
02517 #if __ACK__ || __GNUC__
02518 #define WORD SIZE
                          EM WSIZE
02519 #define _PTR_SIZE
                          _EM_WSIZE
02520 #endif
02521
02522 #define _NR_PROCS
02523 #define _NR_SYS_PROCS
                          32
02524
02525 /* Set the CHIP type based on the machine selected. The symbol CHIP is actually
02526 * indicative of more than just the CPU. For example, machines for which
02527 * CHIP == INTEL are expected to have 8259A interrrupt controllers and the
02528 * other properties of IBM PC/XT/AT/386 types machines in general. */
02529 #define _CHIP_INTEL
                        1
                                /* CHIP type for PC, XT, AT, 386 and clones */
02530
02\bar{5}31 /* Set the FP_FORMAT type based on the machine selected, either hw or sw
02532 #define _FP_NONE
                          0 /* no floating point support
02533 #define _FP_IEEE
                          1
                                /* conform IEEE floating point standard
02534
02535 #define _MINIX_CHIP
                              CHIP INTEL
02536
02537 #define _MINIX_FP_FORMAT _FP_NONE
02538
02539 #ifndef MINIX MACHINE
```

```
Feb 25, 11 15:18
                                      book.txt
                                                                     Page 30/393
       File: Page: 667 include/minix/sys config.h
02540 error "In <minix/sys_config.h> please define _MINIX_MACHINE"
02541 #endif
02542
02543 #ifndef MINIX CHIP
02544 error "In <minix/sys_config.h> please define _MINIX_MACHINE to have a legal valu
02545 #endif
02546
02547 #if ( MINIX MACHINE == 0)
02548 error "_MINIX_MACHINE has incorrect value (0)"
02549 #endif
02550
02551 #endif /* _MINIX_SYS_CONFIG_H */
02552
02553
include/minix/const h
02600 /* Copyright (C) 2001 by Prentice-Hall, Inc. See the copyright notice in
02601 * the file /usr/src/LICENSE.
02602 */
02603
02604 #ifndef CHIP
02605 #error CHIP is not defined
02606 #endif
02607
02608 #define EXTERN
                           extern
                                     /* used in *.h files */
02609 #define PRIVATE
                           static /* PRIVATE x limits the scope of x */
02610 #define PUBLIC
                                     /* PUBLIC is the opposite of PRIVATE */
02611 #define FORWARD
                           static
                                  /* some compilers require this to be 'static'*/
02612
02613 #define TRUE
                               1 /* used for turning integers into Booleans */
02614 #define FALSE
                              0 /* used for turning integers into Booleans */
02615
                               60 /* clock freq (software settable on IBM-PC) */
02616 #define HZ
02617
02618 #define SUPER_USER (uid_t) 0 /* uid_t of superuser */
02619
02620 /* Devices. */
02621 #define MAJOR
                                8
                                    /* major device = (dev>>MAJOR) & 0377 */
02622 #define MINOR
                               0
                                  /* minor device = (dev>>MINOR) & 0377 */
02623
02623
02624 #define NULL ((void *)0) /* null pointer */
02625 #define CPVEC_NR 16 /* max # of entries in a SYS_VCOPY request */
02626 #define CPVVEC_NR 64 /* max # of entries in a SYS_VCOPY request */
02627 #define NR_IOREQS
                             MIN(NR_BUFS, 64)
02628
                                     /* maximum number of entries in an iorequest */
02629
02630 /* Message passing constants. */
02631 #define MESS_SIZE (sizeof(message)) /* might need usizeof from FS here */
02632 #define NIL_MESS ((message *) 0)
                                          /* null pointer */
02633
02634
      /* Memory related constants. */
02635 #define SEGMENT TYPE 0xFF00 /* bit mask to get segment type */
02636 #define SEGMENT_INDEX 0x00FF
                                  /* bit mask to get segment index */
02637
                           0x0000
                                  /* flags indicating local memory segment */
02639 #define NR LOCAL SEGS 3 /* # local segments per process (fixed) */
```

```
book.txt
Feb 25, 11 15:18
                                                                      Page 31/393
      File: Page: 668 include/minix/const.h
02640 #define T
                                    /* proc[i].mem map[T] is for text */
                                0
02641 #define D
                                1
                                     /* proc[i].mem_map[D] is for data */
                                    /* proc[i].mem_map[S] is for stack */
02642 #define S
02643
02644 #define REMOTE_SEG
                           0 \times 0100
                                     /* flags indicating remote memory segment */
02645 #define NR_REMOTE_SEGS
                                     /* # remote memory regions (variable) */
02646
                            0x0200
02647 #define BIOS_SEG
                                     /* flags indicating BIOS memory segment */
02648 #define NR_BIOS_SEGS
                              3
                                     /* # BIOS memory regions (variable) */
02649
02650 #define PHYS SEG
                           0 \times 0400
                                    /* flag indicating entire physical memory */
02651
02652 /* Labels used to disable code sections for different reasons. */
                                0 /* unused code in normal configuration */
02653 #define DEAD_CODE
                                    /* new code to be activated + tested later */
02654 #define FUTURE CODE
02655 #define TEMP CODE
                                1 /* active code to be removed later */
02656
02657 /* Process name length in the PM process table, including '\0'. */
02658 #define PROC NAME LEN 16
02659
02660 /* Miscellaneous */
02661 #define BYTE
                             0377
                                     /* mask for 8 bits */
                                    /* copy data to user */
02662 #define READING
                             0
                              1 /* copy data from user */
02663 #define WRITING
02664 #define NO_NUM
                           0x8000 /* used as numerical argument to panic() */
02665 #define NIL_PTR (char *) 0
                                    /* generally useful expression */
02666 #define HAVE_SCATTERED_IO 1 /* scattered I/O is now standard */
02667
02668 /* Macros. */
02669 #define MAX(a, b) ((a) > (b) ? (a) : (b))
02670 #define MIN(a, b) ((a) < (b) ? (a) : (b))
02671
02672 /* Memory is allocated in clicks. */
02673 #if (CHIP == INTEL)
                             1024
02674 #define CLICK_SIZE
                                   /* unit in which memory is allocated */
02675 #define CLICK_SHIFT
                             10 /* log2 of CLICK_SIZE */
02676 #endif
02677
02678 #if (CHIP == SPARC) | (CHIP == M68000)
02679 #define CLICK_SIZE
                             4096 /* unit in which memory is allocated */
                                    /* log2 of CLICK_SIZE */
02680 #define CLICK SHIFT
                              12
02681 #endif
02682
02683 /* Click to byte conversions (and vice versa). */
02684 #define HCLICK SHIFT 4 /* log2 of HCLICK SIZE */
                               16
                                     /* hardware segment conversion magic */
02685 #define HCLICK_SIZE
02686 #if CLICK_SIZE >= HCLICK_SIZE
02687 #define click_to_hclick(n) ((n) << (CLICK_SHIFT - HCLICK_SHIFT))
02688 #else
02689 #define click_to_hclick(n) ((n) >> (HCLICK_SHIFT - CLICK_SHIFT))
02690 #endif
02691 #define hclick_to_physb(n) ((phys_bytes) (n) << HCLICK_SHIFT)
02692 #define physb_to_hclick(n) ((n) >> HCLICK_SHIFT)
02693
02694 #define ABS
                             -999 /* this process means absolute memory */
02695
02696 /* Flag bits for i_mode in the inode. */
                             0170000 /* this field gives inode type */
02697 #define I_TYPE
                             0100000 /* regular file, not dir or special */
02698 #define I_REGULAR
02699 #define I BLOCK SPECIAL 0060000 /* block special file */
```

```
book.txt
 Feb 25, 11 15:18
                                                                     Page 32/393
       File: Page: 669 include/minix/const.h
                             0040000 /* file is a directory */
0020000 /* character special file */
02700 #define I_DIRECTORY
02701 #define I_CHAR_SPECIAL
                             0010000 /* named pipe (FIFO) */
02702 #define I_NAMED_PIPE
02703 #define I_SET_UID_BIT
                             0004000 /* set effective uid_t on exec */
                             0002000 /* set effective gid_t on exec */
02704 #define I_SET_GID_BIT
02705 #define ALL_MODES
                             0006777 /* all bits for user, group and others */
02706 #define RWX_MODES
                             0000777 /* mode bits for RWX only */
                             0000004 /* Rwx protection bit */
02707 #define R_BIT
                             0000002 /* rWx protection bit */
02708 #define W BIT
                             0000001 /* rwX protection bit */
02709
      #define X_BIT
                             00000000 /* this inode is free */
02710 #define I_NOT_ALLOC
02711
02712 /* Flag used only in flags argument of dev_open. */
                             0200000 /* Open device readonly; fail if writable. */
02713 #define RO_BIT
02714
02715 /* Some limits. */
02716 #define MAX_BLOCK_NR ((block_t) 077777777)
                                                   /* largest block number */
                                                   /* largest zone number */
02717 #define HIGHEST_ZONE ((zone_t) 077777777)
02718 #define MAX_INODE_NR ((ino_t) 03777777777)
                                                   /* largest inode number */
02719 #define MAX_FILE_POS ((off_t) 03777777777)
                                                   /* largest legal file offset */
02720
02721 #define NO_BLOCK
                                   ((block_t) 0)
                                                   /* absence of a block number */
                                                   /* absence of a dir entry */
02722 #define NO_ENTRY
                                    ((ino_t) 0)
                                                   /* absence of a zone number */
02723 #define NO ZONE
                                    ((zone t) 0)
                                                   /* absence of a device numb */
02724 #define NO_DEV
                                    ((dev_t) 0)
include/minix/type.h
02800 #ifndef _TYPE_H
02801 #define _TYPE_H
02802
02803 #ifndef _MINIX_SYS_CONFIG_H
02804 #include <minix/sys_config.h>
02805 #endif
02806
02807 #ifndef _TYPES_H
02808 #include <sys/types.h>
02809 #endif
02810
02811 /* Type definitions. */
02812 typedef unsigned int vir_clicks;
                                            /* virtual addr/length in clicks */
02813 typedef unsigned long phys_bytes;
                                            /* physical addr/length in bytes */
02814 typedef unsigned int phys_clicks;
                                            /* physical addr/length in clicks */
02815
02816
       #if (_MINIX_CHIP == _CHIP_INTEL)
02817 typedef unsigned int vir_bytes; /* virtual addresses and lengths in bytes */
02818 #endif
02819
02820 #if (_MINIX_CHIP == _CHIP_M68000)
02821 typedef unsigned long vir_bytes;/* virtual addresses and lengths in bytes */
02822 #endif
02823
02824
       #if (_MINIX_CHIP == _CHIP_SPARC)
02825
       typedef unsigned long vir_bytes;/* virtual addresses and lengths in bytes */
02826
02827
02828 /* Memory map for local text, stack, data segments. */
02829 struct mem map {
```

```
book.txt
Feb 25, 11 15:18
                                                                      Page 33/393
      File: Page: 670 include/minix/type.h
02830
        vir_clicks mem_vir;
                                     /* virtual address */
                                     /* physical address */
02831
        phys_clicks mem_phys;
02832
        vir_clicks mem_len;
                                     /* length */
02833 };
02834
02836 struct far_mem {
02837
                                     /* entry in use, unless zero */
       int in_use;
                                     /* physical address */
02838
        phys clicks mem phys;
                                     /* length */
02839
        vir_clicks mem_len;
02840 };
02841
02842 /* Structure for virtual copying by means of a vector with requests. */
02843 struct vir_addr {
02844
        int proc nr;
02845
        int segment;
02846
        vir_bytes offset;
02847 };
02848
02849 #define phys_cp_req vir_cp_req
02850 struct vir_cp_req {
02851
        struct vir_addr src;
02852
        struct vir_addr dst;
02853
        phys_bytes count;
02854 };
02855
02856 typedef struct {
02857
        vir_bytes iov_addr;
                                     /* address of an I/O buffer */
                                     /* sizeof an I/O buffer */
02858
        vir_bytes iov_size;
      } iovec_t;
02859
02860
02861 /* PM passes the address of a structure of this type to KERNEL when
02862 * sys_sendsig() is invoked as part of the signal catching mechanism.
02863
       * The structure contain all the information that KERNEL needs to build
      * the signal stack.
02864
02865 */
02866 struct sigmsg
02867
        int sm_signo;
                                     /* signal number being caught */
                                     /* mask to restore when handler returns */
02868
        unsigned long sm_mask;
02869
        vir_bytes sm_sighandler;
                                     /* address of handler */
02870
        vir_bytes sm_sigreturn;
                                     /* address of _sigreturn in C library */
                                     /* user stack pointer */
02871
        vir_bytes sm_stkptr;
02872 };
02873
02874 /* This is used to obtain system information through SYS GETINFO. */
02875 struct kinfo {
02876
        phys_bytes code_base;
                                     /* base of kernel code */
        phys_bytes code_size;
02877
02878
        phys_bytes data_base;
                                     /* base of kernel data */
02879
        phys_bytes data_size;
02880
        vir_bytes proc_addr;
                                     /* virtual address of process table */
02881
        phys_bytes kmem_base;
                                     /* kernel memory layout (/dev/kmem) */
02882
        phys_bytes kmem_size;
02883
        phys bytes bootdev base;
                                     /* boot device from boot image (/dev/boot) */
02884
        phys_bytes bootdev_size;
02885
        phys_bytes bootdev_mem;
02886
        phys bytes params base;
                                     /* parameters passed by boot monitor */
02887
        phys_bytes params_size;
02888
        int nr_procs;
                                     /* number of user processes */
02889
        int nr tasks;
                                     /* number of kernel tasks */
```

```
book.txt
 Feb 25, 11 15:18
                                                                    Page 34/393
      File: Page: 671 include/minix/type.h
02890
        char release[6];
                                    /* kernel release number */
                                    /* kernel version number */
02891
        char version[6];
02892
        int relocking;
                                    /* relocking check (for debugging) */
02893 };
02894
02895 struct machine {
02896
        int pc_at;
02897
        int ps_mca;
        int processor;
02898
        int protected;
02899
02900
        int vdu eqa;
02901
        int vdu vga;
02902
02903
02904 #endif /* TYPE H */
include/minix/ipc.h
03000 #ifndef _IPC_H
03001 #define _IPC_H
03002
03003 /*===========*
03004
       * Types relating to messages.
03005
       03006
03007
      #define M1
03008
      #define M3
                               3
03009
      #define M4
03010
      #define M3 STRING
                              14
03011
03012 typedef struct {int mli1, mli2, mli3; char *mlp1, *mlp2, *mlp3;} mess_1;
03013 typedef struct {int m2i1, m2i2, m2i3; long m2l1, m2l2; char *m2pl;} mess_2; 03014 typedef struct {int m3i1, m3i2; char *m3pl; char m3cal[M3_STRING];} mess_3;
03015 typedef struct {long m411, m412, m413, m414, m415;} mess_4;
03016 typedef struct {short m5c1, m5c2; int m5i1, m5i2; long m5l1, m5l2, m5l3;}mess_5; 03017 typedef struct {int m7i1, m7i2, m7i3, m7i4; char *m7p1, *m7p2;} mess_7;
03018 typedef struct {int m8i1, m8i2; char *m8p1, *m8p2, *m8p3, *m8p4;} mess_8;
03019
03020
       typedef struct {
03021
        int m source;
                                    /* who sent the message */
                                    /* what kind of message is it */
03022
        int m_type;
03023
        union {
              mess 1 m m1;
03024
03025
              mess_2 m_m2;
03026
              mess_3 m_m3;
03027
              mess_4 m_m4;
03028
              mess_5 m_m5;
03029
              mess_7 m_m7;
03030
              mess_8 m_m8;
03031
        } m 11;
      } message;
03032
03033
03034
       /* The following defines provide names for useful members. */
03035
      #define m1_i1 m_u.m_m1.m1i1
      #define m1 i2 m u.m m1.m1i2
03036
03037
      #define m1_i3 m_u.m_m1.m1i3
03038
      #define ml_pl m_u.m_ml.mlpl
03039 #define ml p2 m u.m ml.mlp2
```

```
Feb 25, 11 15:18
                                   book.txt
                                                                  Page 35/393
      File: Page: 672 include/minix/ipc.h
03040 #define m1_p3 m_u.m_m1.m1p3
03041
03042 #define m2_i1 m_u.m_m2.m2i1
03043 #define m2_i2 m_u.m_m2.m2i2
03044 #define m2_i3 m_u.m_m2.m2i3
03045 #define m2_11 m_u.m_m2.m211
03046 #define m2_12 m_u.m_m2.m212
03047 #define m2_p1 m_u.m_m2.m2p1
03048
03049 #define m3_i1 m_u.m_m3.m3i1
03050 #define m3_i2 m_u.m_m3.m3i2
03051 #define m3_p1 m_u.m_m3.m3p1
03052 #define m3_cal m_u.m_m3.m3cal
03053
03054 #define m4 11 m u.m m4.m411
03055 #define m4_12 m_u.m_m4.m412
03056 #define m4_13 m_u.m_m4.m413
03057 #define m4_14 m_u.m_m4.m414
03058 #define m4_15 m_u.m_m4.m415
03059
03060 #define m5_c1 m_u.m_m5.m5c1
03061 #define m5_c2 m_u.m_m5.m5c2
03062 #define m5_i1 m_u.m_m5.m5i1
03063 #define m5 i2 m u.m m5.m5i2
03064 #define m5_11 m_u.m_m5.m511
03065 #define m5_12 m_u.m_m5.m512
03066 #define m5_13 m_u.m_m5.m513
03067
03068 #define m7_i1 m_u.m_m7.m7i1
03069 #define m7 i2 m u.m m7.m7i2
03070 #define m7_i3 m_u.m_m7.m7i3
03071 #define m7_i4 m_u.m_m7.m7i4
03072 #define m7_p1 m_u.m_m7.m7p1
03073 #define m7_p2 m_u.m_m7.m7p2
03074
03075 #define m8_i1 m_u.m_m8.m8i1
03076 #define m8_i2 m_u.m_m8.m8i2
03077 #define m8_p1 m_u.m_m8.m8p1
03078 #define m8_p2 m_u.m_m8.m8p2
03079 #define m8_p3 m_u.m_m8.m8p3
03080 #define m8_p4 m_u.m_m8.m8p4
03081
03082 /*=========*
03083 * Minix run-time system (IPC).
03084 *=========*/
03085
03086 /* Hide names to avoid name space pollution. */
03087 #define echo
                       _echo
03088 #define notify
                           _notify
03089 #define sendrec
                           _sendrec
03090 #define receive
                           _receive
                           _send
03091 #define send
03092 #define nb_receive
                           _nb_receive
03093 #define nb_send
                           nb send
03094
03095 _PROTOTYPE( int echo, (message *m_ptr)
03096 _PROTOTYPE( int notify, (int dest)
03097 _PROTOTYPE( int sendrec, (int src_dest, message *m_ptr)
03098 _PROTOTYPE( int receive, (int src, message *m_ptr)
03099 PROTOTYPE( int send, (int dest, message *m ptr)
```

```
Feb 25, 11 15:18
                                    book.txt
                                                                  Page 36/393
      File: Page: 673 include/minix/ipc.h
03100 _PROTOTYPE( int nb_receive, (int src, message *m_ptr)
                                                                       );
03101 _PROTOTYPE( int nb_send, (int dest, message *m_ptr)
                                                                       );
03103 #endif /* _IPC_H */
include/minix/syslib.h
03200 /* Prototypes for system library functions. */
03201
03202 #ifndef _SYSLIB_H
03203 #define _SYSLIB_H
03204
03205 #ifndef _TYPES_H
03206 #include <sys/types.h>
03207 #endif
03208
03209 #ifndef _IPC_H
03210 #include <minix/ipc.h>
03211 #endif
03212
03213 #ifndef DEVIO H
03214 #include <minix/devio.h>
03215 #endif
03216
03217 /* Forward declaration */
03218 struct reg86u;
03219
03220 #define SYSTASK SYSTEM
03221
03222 /*========*
03223 * Minix system library.
03224 *========*/
03225 _PROTOTYPE( int _taskcall, (int who, int syscallnr, message *msgptr));
03226
03227 _PROTOTYPE( int sys_abort, (int how, ...));
03228 _PROTOTYPE( int sys_exec, (int proc, char *ptr,
03229
                                   char *aout, vir_bytes initpc));
03230
      _PROTOTYPE( int sys_fork, (int parent, int child));
03231 _PROTOTYPE( int sys_newmap, (int proc, struct mem_map *ptr));
03232
      _PROTOTYPE( int sys_exit, (int proc));
03233
      _PROTOTYPE( int sys_trace, (int req, int proc, long addr, long *data_p));
03234
03235
      _PROTOTYPE( int sys_svrctl, (int proc, int req, int priv, vir_bytes argp));
03236
      _PROTOTYPE( int sys_nice, (int proc, int priority));
03237
03238
      _PROTOTYPE( int sys_int86, (struct reg86u *reg86p));
03239
03240
      /* Shorthands for sys_sdevio() system call. */
03241 #define sys_insb(port, proc_nr, buffer, count) \
03242
             sys_sdevio(DIO_INPUT, port, DIO_BYTE, proc_nr, buffer, count)
03243 #define sys_insw(port, proc_nr, buffer, count) \
             sys_sdevio(DIO_INPUT, port, DIO_WORD, proc_nr, buffer, count)
03244
03245
      #define sys_outsb(port, proc_nr, buffer, count) \
             sys_sdevio(DIO_OUTPUT, port, DIO_BYTE, proc_nr, buffer, count)
03246
      #define sys_outsw(port, proc_nr, buffer, count) \
03247
03248
              sys_sdevio(DIO_OUTPUT, port, DIO_WORD, proc_nr, buffer, count)
      _PROTOTYPE( int sys_sdevio, (int req, long port, int type, int proc_nr,
```

```
book.txt
Feb 25, 11 15:18
                                                                          Page 37/393
       File: Page: 674 include/minix/syslib.h
03250
               void *buffer, int count));
03251
03252 /* Clock functionality: get system times or (un)schedule an alarm call. */
03253 _PROTOTYPE( int sys_times, (int proc_nr, clock_t *ptr));
03254 _PROTOTYPE(int sys_setalarm, (clock_t exp_time, int abs_time));
03255
03256 /* Shorthands for sys_irqctl() system call. */
03257 #define sys_irqdisable(hook_id) \
           sys_irqctl(IRQ_DISABLE, 0, 0, hook_id)
03258
03259 #define sys_irqenable(hook_id) \
03260
           sys_irqctl(IRQ_ENABLE, 0, 0, hook_id)
03261 #define sys_irqsetpolicy(irq_vec, policy, hook_id) \
           sys_irqctl(IRQ_SETPOLICY, irq_vec, policy, hook_id)
03262
03263 #define sys_irqrmpolicy(irq_vec, hook_id) \
           sys_irqctl(IRQ_RMPOLICY, irq_vec, 0, hook_id)
03264
03265
       _PROTOTYPE ( int sys_irqctl, (int request, int irq_vec, int policy,
03266
           int *irq_hook_id) );
03267
03268 /* Shorthands for sys_vircopy() and sys_physcopy() system calls. */
03269 #define sys_biosin(bios_vir, dst_vir, bytes) \
03270
               sys_vircopy(SELF, BIOS_SEG, bios_vir, SELF, D, dst_vir, bytes)
03271 #define sys_biosout(src_vir, bios_vir, bytes) \
03272
               sys_vircopy(SELF, D, src_vir, SELF, BIOS_SEG, bios_vir, bytes)
03273 #define sys_datacopy(src_proc, src_vir, dst_proc, dst_vir, bytes) \
03274
               sys_vircopy(src_proc, D, src_vir, dst_proc, D, dst_vir, bytes)
03275 #define sys_textcopy(src_proc, src_vir, dst_proc, dst_vir, bytes) \
3276 sys_vircopy(src_proc, T, src_vir, dst_proc, T, dst_vir, bytes)
03277 #define sys_stackcopy(src_proc, src_vir, dst_proc, dst_vir, bytes)
03278
               sys_vircopy(src_proc, S, src_vir, dst_proc, S, dst_vir, bytes)
03279
      _PROTOTYPE(int sys_vircopy, (int src_proc, int src_seg, vir_bytes src_vir,
03280
               int dst_proc, int dst_seg, vir_bytes dst_vir, phys_bytes bytes));
03281
03282 #define sys_abscopy(src_phys, dst_phys, bytes) \
               sys_physcopy(NONE, PHYS_SEG, src_phys, NONE, PHYS_SEG, dst_phys, bytes)
03283
03284 _PROTOTYPE(int sys_physcopy, (int src_proc, int src_seg, vir_bytes src_vir,
               int dst_proc, int dst_seg, vir_bytes dst_vir, phys_bytes bytes));
03285
03286 _PROTOTYPE(int sys_memset, (unsigned long pattern,
03287
                       phys_bytes base, phys_bytes bytes));
03288
03289 /* Vectored virtual / physical copy calls. */
03290 #if DEAD CODE
                               /* library part not yet implemented */
03291 _PROTOTYPE(int sys_virvcopy, (phys_cp_req *vec_ptr,int vec_size,int *nr_ok));
03292 _PROTOTYPE(int sys_physvcopy, (phys_cp_req *vec_ptr,int vec_size,int *nr_ok));
03293 #endif
03294
03295 _PROTOTYPE(int sys_umap, (int proc_nr, int seg, vir_bytes vir_addr,
03296
                vir_bytes bytes, phys_bytes *phys_addr));
03297 _PROTOTYPE(int sys_segctl, (int *index, u16_t *seg, vir_bytes *off,
03298
               phys_bytes phys, vir_bytes size));
03299
03300 /* Shorthands for sys_getinfo() system call. */
03301 #define sys_getkmessages(dst) sys_getinfo(GET_KMESSAGES, dst, 0,0,0)
03302 #define sys_getkinfo(dst)
                                       sys_getinfo(GET_KINFO, dst, 0,0,0)
                                       sys_getinfo(GET_MACHINE, dst, 0,0,0)
03303 #define sys_getmachine(dst)
                                       sys_getinfo(GET_PROCTAB, dst, 0,0,0)
03304 #define sys_getproctab(dst)
03305 #define sys_getprivtab(dst)
                                       sys_getinfo(GET_PRIVTAB, dst, 0,0,0)
                                       sys_getinfo(GET_PROC, dst, 0,0, nr)
03306 #define sys getproc(dst,nr)
                                       sys_getinfo(GET_RANDOMNESS, dst, 0,0,0)
03307 #define sys_getrandomness(dst)
03308 #define sys_getimage(dst)
                                       sys_getinfo(GET_IMAGE, dst, 0,0,0)
03309 #define sys getirghooks(dst)
                                       sys getinfo(GET IROHOOKS, dst, 0,0,0)
```

```
book.txt
 Feb 25, 11 15:18
                                                                    Page 38/393
       File: Page: 675 include/minix/syslib.h
      #define sys_getmonparams(v,vl) sys_getinfo(GET_MONPARAMS, v,vl, 0,0)
       #define sys_getschedinfo(v1,v2) sys_getinfo(GET_SCHEDINFO, v1,0, v2,0)
03312 #define sys_getlocktimings(dst) sys_getinfo(GET_LOCKTIMING, dst, 0,0,0)
03313 #define sys_getbiosbuffer(virp, sizep) sys_getinfo(GET_BIOSBUFFER, virp, \
              sizeof(*virp), sizep, sizeof(*sizep))
03314
03315 _PROTOTYPE(int sys_getinfo, (int request, void *val_ptr, int val_len,
03316
                                     void *val_ptr2, int val_len2)
                                                                         );
03317
03318 /* Signal control. */
03319 _PROTOTYPE(int sys_kill, (int proc, int sig) );
03320
      _PROTOTYPE(int sys_sigsend, (int proc_nr, struct sigmsg *sig_ctxt) );
03321 _PROTOTYPE(int sys_sigreturn, (int proc_nr, struct sigmsg *sig_ctxt) );
03322 _PROTOTYPE(int sys_getksig, (int *k_proc_nr, sigset_t *k_sig_map) );
03323 _PROTOTYPE(int sys_endksig, (int proc_nr));
03324
03325 /* NOTE: two different approaches were used to distinguish the device I/O
03326
      * types 'byte', 'word', 'long': the latter uses #define and results in a
03327
      * smaller implementation, but looses the static type checking.
03328
03329 _PROTOTYPE(int sys_voutb, (pvb_pair_t *pvb_pairs, int nr_ports)
03330 _PROTOTYPE(int sys_voutw, (pvw_pair_t *pvw_pairs, int nr_ports)
                                                                         );
03331 _PROTOTYPE(int sys_voutl, (pvl_pair_t *pvl_pairs, int nr_ports)
                                                                         );
03332 _PROTOTYPE(int sys_vinb, (pvb_pair_t *pvb_pairs, int nr_ports)
                                                                          );
03333 _PROTOTYPE(int sys_vinw, (pvw_pair_t *pvw_pairs, int nr_ports)
                                                                         );
03334 _PROTOTYPE(int sys_vinl, (pvl_pair_t *pvl_pairs, int nr_ports)
                                                                         );
03335
03336 /* Shorthands for sys_out() system call. */
03337
       #define sys_outb(p,v) sys_out((p), (unsigned long) (v), DIO_BYTE)
03338
      #define sys_outw(p,v) sys_out((p), (unsigned long) (v), DIO_WORD)
       #define sys_outl(p,v) sys_out((p), (unsigned long) (v), DIO_LONG)
03339
03340 _PROTOTYPE(int sys_out, (int port, unsigned long value, int type)
                                                                         );
03341
03342 /* Shorthands for sys_in() system call. */
03343 #define sys_inb(p,v) sys_in((p), (unsigned long*) (v), DIO_BYTE)
03344 #define sys_inw(p,v)
                             sys_in((p), (unsigned long*) (v), DIO_WORD)
                            sys_in((p), (unsigned long*) (v), DIO_LONG)
03345 #define sys_inl(p,v)
03346
      _PROTOTYPE(int sys_in, (int port, unsigned long *value, int type)
                                                                         );
03347
03348 #endif /* _SYSLIB_H */
03349
include/minix/sysutil.h
03400 #ifndef _EXTRALIB_H
03401 #define _EXTRALIB_H
03402
03403 /* Extra system library definitions to support device drivers and servers.
03404
03405 * Created:
03406
              Mar 15, 2004 by Jorrit N. Herder
03407
       * Changes:
03408
03409
              May 31, 2005: added printf, kputc (relocated from syslib)
03410
              May 31, 2005: added getuptime
03411
              Mar 18, 2005: added tickdelay
03412
              Oct 01, 2004:
                           added env_parse, env_prefix, env_panic
03413
              Jul 13, 2004: added fkey_ctl
03414
              Apr 28, 2004: added report, panic
```

```
Feb 25, 11 15:18
                                book.txt
                                                          Page 39/393
     File: Page: 676 include/minix/sysutil.h
           Mar 31, 2004: setup like other libraries, such as syslib
03415 *
03416 */
03418 /*========*
03419 * Miscellaneous helper functions.
03420 *==========*/
03421
03422 /* Environment parsing return values. */
03423 #define EP_BUF_SIZE 128 /* local buffer for env value */
03424 #define EP_UNSET 0
                               /* variable not set */
                              /* var = off */
03425 #define EP_OFF
                        1
03430 _PROTOTYPE( void env_setargs, (int argc, char *argv[])
03431 _PROTOTYPE( int env_get_param, (char *key, char *value, int max_size)
03432 _PROTOTYPE( int env_prefix, (char *env, char *prefix)
03433 _PROTOTYPE( void env_panic, (char *key)
                                                              );
03434 _PROTOTYPE( int env_parse, (char *env, char *fmt, int field, long *param,
03435
                             long min, long max)
03436
03437 #define fkey_map(fkeys, sfkeys) fkey_ctl(FKEY_MAP, (fkeys), (sfkeys))
03438 #define fkey_unmap(fkeys, sfkeys) fkey_ctl(FKEY_UNMAP, (fkeys), (sfkeys))
03439 #define fkey_events(fkeys, sfkeys) fkey_ctl(FKEY_EVENTS, (fkeys), (sfkeys))
03440 _PROTOTYPE( int fkey_ctl, (int req, int *fkeys, int *sfkeys)
03442 _PROTOTYPE( int printf, (const char *fmt, ...));
03443 _PROTOTYPE( void kputc, (int c));
03444 _PROTOTYPE( void report, (char *who, char *mess, int num));
03445 _PROTOTYPE( void panic, (char *who, char *mess, int num));
03446 _PROTOTYPE( int getuptime, (clock_t *ticks));
03447 _PROTOTYPE( int tickdelay, (clock_t ticks));
03448
03449 #endif /* _EXTRALIB_H */
03450
include/minix/callnr.h
03500 #define NCALLS
                        91 /* number of system calls allowed */
03501
03502 #define EXIT
03503 #define FORK
03504 #define READ
03505 #define WRITE
03506 #define OPEN
03507 #define CLOSE
03508 #define WAIT
03509 #define CREAT
03510 #define LINK
03511 #define UNLINK
03512 #define WAITPID
                          11
03513 #define CHDIR
                          12
03514 #define TIME
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 40/393
      File: Page: 677 include/minix/callnr.h
03515 #define MKNOD
                              14
03516 #define CHMOD
                              15
03517 #define CHOWN
03518 #define BRK
                              17
03519 #define STAT
                              18
03520 #define LSEEK
                              19
03521 #define GETPID
                               20
03522 #define MOUNT
                              21
03523 #define UMOUNT
                              22
03524 #define SETUID
                               23
03525 #define GETUID
03526 #define STIME
03527 #define PTRACE
                               26
                               27
03528 #define ALARM
03529 #define FSTAT
03530 #define PAUSE
                              29
03531 #define UTIME
                              30
03532 #define ACCESS
03533 #define SYNC
                              36
03534 #define KILL
                              37
03535 #define RENAME
03536 #define MKDIR
                               39
03537 #define RMDIR
                              40
03538 #define DUP
03539 #define PIPE
03540 #define TIMES
                               43
03541 #define SETGID
03542 #define GETGID
                               47
03543 #define SIGNAL
03544 #define IOCTL
03545 #define FCNTL
                              55
03546 #define EXEC
                              59
03547 #define UMASK
03548 #define CHROOT
                               61
03549 #define SETSID
                               62
03550 #define GETPGRP
03551
03552 /* The following are not system calls, but are processed like them. */
03553 #define UNPAUSE 65 /* to MM or FS: check for EINTR */
03554
      #define REVIVE
                              67
                                    /* to FS: revive a sleeping process */
                                  /* to FS: reply code from tty task */
03555 #define TASK_REPLY
                             68
03556
03557 /* Posix signal handling. */
03558 #define SIGACTION
                               71
03559 #define SIGSUSPEND
03560
      #define SIGPENDING
                               73
03561 #define SIGPROCMASK
                              74
03562 #define SIGRETURN
03563
03564 #define REBOOT
                              76 /* to PM */
03565
03566 /* MINIX specific calls, e.g., to support system services. */
03567 #define SVRCTL 77
03568
                                    /* unused */
                                 /* to PM or FS */
/* to PM */
03571 #define DEVCTL
03572 #define FSTATFS
                            82
                                  /* to FS */
/* to PM */
03573 #define ALLOCMEM
03574 #define FREEMEM
                              8.3
                                  /* to PM */
```

```
book.txt
 Feb 25, 11 15:18
                                                                         Page 41/393
       File: Page: 678 include/minix/callnr.h
 03575 #define SELECT 85 /* to FS */
 03576 #define FCHDIR
                                      /* to FS */
                                 86
                                    /* to FS */
 03577 #define FSYNC
                               87
 03578 #define GETPRIORITY
                              88  /* to PM */
89  /* to PM */
 03579 #define SETPRIORITY
 03580 #define GETTIMEOFDAY
                            90 /* to PM */
include/minix/com.h
03600 #ifndef _MINIX_COM_H
 03601 #define _MINIX_COM_H
 03603 /*========*
 03604 *
                       Magic process numbers
 03605 *===========*/
 03606
 03607 #define ANY
                               0x7ace /* used to indicate 'any process' */
 03600 #define NONE 0x6ace /* used to indicate 'any process' */
03608 #define SELF 0x8ace /* used to indicate 'any process' */
 03610
 03611 /*==========*
 03612 * Process numbers of processes in the system image *
 03613 *========*/
 03615 /* The values of several task numbers depend on whether they or other tasks
 03616 * are enabled. They are defined as (PREVIOUS_TASK - ENABLE_TASK) in general.
 03617 * ENABLE_TASK is either 0 or 1, so a task either gets a new number, or gets
 03618 * the same number as the previous task and is further unused. Note that the
 03619 * order should correspond to the order in the task table defined in table.c.
 03620 */
 03621
 03622 /* Kernel tasks. These all run in the same address space. */
03623 #define IDLE -4 /* runs when no one else can run */
03624 #define CLOCK -3 /* alarms and other clock functions *
                                      /* alarms and other clock functions */
03625 #define SYSTEM -2 /* request system functionality */
03626 #define KERNEL -1 /* pseudo-process for IPC and scheduling */
 03627 #define HARDWARE KERNEL
                                     /* for hardware interrupt handlers */
 03628
 03629 /* Number of tasks. Note that NR PROCS is defined in <minix/config.h>. */
 03630 #define NR TASKS 4
 03631
 03632 /* User-space processes, that is, device drivers, servers, and INIT. */
03633 #define rm_froc_

03634 #define FS_PROC_NR 1 // reincarnation server, // reincarnation server, // memory driver (RAM disk, nounce of the fine MEM_PROC_NR 2 /* reincarnation server, // memory driver (RAM disk, nounce of the fine MEM_PROC_NR 4 /* log device driver */ // 103638 #define LOG_PROC_NR 5 /* terminal (TTY) driver */ // 103639 #define DRVR_PROC_NR 6 /* device driver for boot med // init -- goes multiuser */
 03633 #define PM_PROC_NR 0 /* process manager */
                                    /* memory driver (RAM disk, null, etc.) */
/* log device driver */
                                   /* device driver for boot medium */
/* init -- goes multiuser */
 03642 /* Number of processes contained in the system image. */
 03643 #define NR_BOOT_PROCS (NR_TASKS + INIT_PROC_NR + 1)
 03644
```

```
book.txt
 Feb 25, 11 15:18
                                                                   Page 42/393
       File: Page: 679 include/minix/com.h
03645 /*=========*
03646 * Kernel notification types
03648
03649 /* Kernel notification types. In principle, these can be sent to any process,
03650 * so make sure that these types do not interfere with other message types.
03651
       * Notifications are prioritized because of the way they are unhold() and
03652 * blocking notifications are delivered. The lowest numbers go first. The
03653 * offset are used for the per-process notification bit maps.
03654 */
03655 #define NOTIFY_MESSAGE
                                     0 \times 1000
03656 #define NOTIFY_FROM(p_nr) (NOTIFY_MESSAGE | ((p_nr) + NR_TASKS))
03657 # define SYN_ALARM NOTIFY_FROM(CLOCK) /* synchronous alarm */
                                                  /* system signal */
                            NOTIFY_FROM(SYSTEM)
03658 # define SYS_SIG
03659 # define HARD_INT NOTIFY_FROM(HARDWARE) /* hardware interrupt */
03660 # define NEW KSIG NOTIFY_FROM(HARDWARE) /* new kernel signal */
03661 # define FKEY_PRESSED NOTIFY_FROM(TTY_PROC_NR)/* function key press */
03662
03663 /* Shorthands for message parameters passed with notifications. */
03664 #define NOTIFY_SOURCE
                                  m_source
03665 #define NOTIFY_TYPE
                                    m_type
03666 #define NOTIFY_ARG
                                    m2_11
03667 #define NOTIFY_TIMESTAMP
                                    m2_{12}
03668 #define NOTIFY FLAGS
                                    m2_i1
03669
03670 /*=========*
03671 * Messages for BLOCK and CHARACTER device drivers
03672
       03673
03674 /* Message types for device drivers. */
03675 #define DEV_RQ_BASE 0x400 /* base for device request types */
03676 #define DEV_RS_BASE 0x500
                                   /* base for device response types */
03677
03678 #define CANCEL
                           (DEV RQ_BASE + 0) /* general req to force a task to can
cel */
03679 #define DEV_READ
                            (DEV_RQ_BASE + 3) /* read from minor device */
                             (DEV_RO_BASE + 4) /* write to minor device */
03680 #define DEV_WRITE
                             (DEV_RQ_BASE + 5) /* I/O control code */
03681 #define DEV_IOCTL
03682 #define DEV OPEN
                             (DEV RO BASE + 6) /* open a minor device */
                             (DEV_RQ_BASE + 7) /* close a minor device */
(DEV_RQ_BASE + 8) /* write from a vector */
03683 #define DEV_CLOSE
03684 #define DEV SCATTER
                             (DEV RO BASE + 9) /* read into a vector */
03685 #define DEV GATHER
03686 #define TTY SETPGRP
                             (DEV_RQ_BASE + 10) /* set process group */
                             (DEV_RQ_BASE + 11) /* process group leader exited */
(DEV_RQ_BASE + 12) /* request select() attention */
03687 #define TTY_EXIT
03688 #define DEV SELECT
                             (DEV_RQ_BASE + 13) /* request driver status */
03689 #define DEV STATUS
03690
03691 #define DEV_REPLY
                             (DEV_RS_BASE + 0) /* general task reply */
03692 #define DEV_CLONED
                             (DEV_RS_BASE + 1) /* return cloned minor */
                             (DEV_RS_BASE + 2) /* driver revives process */
03693 #define DEV_REVIVE
                             (DEV_RS_BASE + 3) /* selected device ready */
03694 #define DEV_IO_READY
                            (DEV_RS_BASE + 4) /* empty status reply */
03695 #define DEV_NO_STATUS
03696
03697 /* Field names for messages to block and character device drivers. */
03698 #define DEVICE
                            m2_i1 /* major-minor device */
m2_i2 /* which (proc) wants I/O? */
03699 #define PROC NR
03700 #define COUNT
                            m2_i3 /* how many bytes to transfer */
                            m2_i3 /* ioctl request code */
03701 #define REQUEST
                            m2_l1 /* file offset */
03702 #define POSITION
03703 #define ADDRESS
                            m2 p1 /* core buffer address */
03704
```

```
book.txt
Feb 25, 11 15:18
                                                                   Page 43/393
      File: Page: 680 include/minix/com.h
     /* Field names for DEV SELECT messages to device drivers. */
03706 #define DEV_MINOR
                           m2_i1 /* minor device */
03707 #define DEV_SEL_OPS
                            m2_i2
                                   /* which select operations are requested */
03708 #define DEV_SEL_WATCH m2_i3 /* request notify if no operations are ready */
03709
03710 /* Field names used in reply messages from tasks. */
                            m2_i1 /* # of proc on whose behalf I/O was done */
03711 #define REP PROC NR
                                  /* bytes transferred or error number */
03712 #define REP_STATUS
                            m2_i2
                                  /* status to suspend caller, reply later */
03713 # define SUSPEND
03714
03715 /* Field names for messages to TTY driver. */
03716 #define TTY LINE
                            DEVICE /* message parameter: terminal line */
                            COUNT /* message parameter: ioctl request code */
03717 #define TTY REQUEST
                            POSITION/* message parameter: ioctl speed, erasing */
03718 #define TTY_SPEK
03719 #define TTY FLAGS
                            m2 12 /* message parameter: ioctl tty mode */
03720 #define TTY PGRP
                            m2_i3
                                  /* message parameter: process group */
03721
03722 /* Field names for the QIC 02 status reply from tape driver */
03723 #define TAPE_STAT0
                            m2_11
03724 #define TAPE_STAT1
                            m2_{12}
03725
03726 /*=========*
03727 * Messages for networking layer
03728 *==========*/
03729
03730 /* Message types for network layer requests. This layer acts like a driver. */
03731 #define NW OPEN
                            DEV OPEN
                            DEV_CLOSE
03732 #define NW CLOSE
03733 #define NW_READ
                            DEV_READ
03734 #define NW WRITE
                            DEV WRITE
03735 #define NW IOCTL
                            DEV IOCTL
03736 #define NW_CANCEL
                            CANCEL
03737
03738 /* Base type for data link layer requests and responses. */
03739 #define DL_RQ_BASE
                            0x800
03740 #define DL_RS_BASE
                            0x900
03741
03742 /* Message types for data link layer requests. */
03743 #define DL_WRITE
                            (DL RO BASE + 3)
03744 #define DL_WRITEV
                            (DL_RQ_BASE + 4)
03745 #define DL_READ
                            (DL_RQ_BASE + 5)
03746 #define DL READV
                            (DL RO BASE + 6)
03747 #define DL_INIT
                            (DL_RQ_BASE + 7)
03748 #define DL_STOP
                            (DL_RQ_BASE + 8)
03749 #define DL_GETSTAT
                            (DL RO BASE + 9)
03750
03751 /* Message type for data link layer replies. */
03752 #define DL_INIT_REPLY (DL_RS_BASE + 20)
03753 #define DL_TASK_REPLY (DL_RS_BASE + 21)
03754
03755 /* Field names for data link layer messages. */
                            m2_i1
03756 #define DL_PORT
03757 #define DL_PROC
                            m2_i2
03758 #define DL_COUNT
                            m2 i3
03759 #define DL_MODE
                            m2_11
03760 #define DL_CLCK
                            m2 12
03761 #define DL ADDR
                            m2 p1
03762 #define DL_STAT
                            m2_11
03763
03764 /* Bits in 'DL STAT' field of DL replies. */
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                     Page 44/393
      File: Page: 681 include/minix/com.h
      # define DL_PACK_SEND
                                     0 \times 0.1
03766 # define DL_PACK_RECV
                                     0 \times 0.2
03767 # define DL_READ_IP
                                     0 \times 04
03768
      /* Bits in 'DL_MODE' field of DL requests. */
03769
03770
      # define DL_NOMODE
03771 #
         define DL_PROMISC_REQ
                                     0x2
03772
      # define DL_MULTI_REQ
                                    0x4
03773
      # define DL_BROAD_REQ
                                    0x8
03774
03775 /*========*
03776
          SYSTASK request types and field names
03777
       03778
03779
      /* System library calls are dispatched via a call vector, so be careful when
03780
       * modifying the system call numbers. The numbers here determine which call
03781
       * is made from the call vector.
03782
03783 #define KERNEL CALL
                             0x600 /* base for kernel calls to SYSTEM */
03784
03785 # define SYS_FORK
                              (KERNEL_CALL + 0)
                                                    /* sys_fork() */
03786 # define SYS_EXEC
                              (KERNEL_CALL + 1)
                                                    /* sys_exec() */
                                                    /* sys_exit() */
03787 #
        define SYS_EXIT
                              (KERNEL_CALL + 2)
                                                    /* sys_nice() */
03788
         define SYS NICE
                              (KERNEL_CALL + 3)
                              (KERNEL_CALL + 4)
03789
         define SYS_PRIVCTL
                                                    /* sys_privctl() */
                                                    /* sys_trace() */
03790
      #
         define SYS_TRACE
                              (KERNEL_CALL + 5)
         define SYS_KILL
                              (KERNEL_CALL + 6)
                                                    /* sys_kill() */
03791 #
03792
03793
         define SYS_GETKSIG
                              (KERNEL_CALL + 7)
                                                    /* sys_getsig() */
03794 #
         define SYS ENDKSIG
                              (KERNEL CALL + 8)
                                                    /* sys endsig() */
03795 #
         define SYS_SIGSEND
                              (KERNEL_CALL + 9)
                                                    /* sys_sigsend() */
03796 #
         define SYS_SIGRETURN
                              (KERNEL_CALL + 10)
                                                    /* sys_sigreturn() */
03797
03798
         define SYS NEWMAP
                              (KERNEL_CALL + 11)
                                                    /* sys_newmap() */
                                                    /* sys_segctl() */
03799
         define SYS_SEGCTL
                              (KERNEL_CALL + 12)
03800 #
         define SYS_MEMSET
                              (KERNEL_CALL + 13)
                                                    /* sys_memset() */
03801
03802 # define SYS_UMAP
                              (KERNEL_CALL + 14)
                                                    /* sys_umap() */
03803 #
         define SYS VIRCOPY
                              (KERNEL_CALL + 15)
                                                    /* sys_vircopy() */
03804 #
         define SYS_PHYSCOPY
                              (KERNEL_CALL + 16)
                                                    /* sys_physcopy() */
                                                    /* sys_virvcopy() */
03805 #
        define SYS_VIRVCOPY
                              (KERNEL_CALL + 17)
         define SYS_PHYSVCOPY
                             (KERNEL CALL + 18)
03806 #
                                                    /* sys_physvcopy() */
03807
03808 #
         define SYS_IRQCTL
                              (KERNEL_CALL + 19)
                                                    /* sys_irqctl() */
03809 #
         define SYS INT86
                              (KERNEL_CALL + 20)
                                                    /* sys_int86() */
03810 #
         define SYS DEVIO
                              (KERNEL_CALL + 21)
                                                    /* sys_devio() */
03811 # define SYS_SDEVIO
                              (KERNEL_CALL + 22)
                                                    /* sys_sdevio() */
                                                    /* sys_vdevio() */
03812 # define SYS_VDEVIO
                              (KERNEL_CALL + 23)
03813
03814 # define SYS_SETALARM
                              (KERNEL_CALL + 24)
                                                    /* sys_setalarm() */
03815 # define SYS_TIMES
                              (KERNEL_CALL + 25)
                                                    /* sys_times() */
                                                    /* sys_getinfo() */
03816 # define SYS GETINFO
                              (KERNEL_CALL + 26)
                                                    /* sys_abort() */
03817 # define SYS_ABORT
                              (KERNEL_CALL + 27)
03818
03819 #define NR_SYS_CALLS
                                    /* number of system calls */
03820
03821 /* Field names for SYS MEMSET, SYS SEGCTL. */
      #define MEM PTR
03822
                             m2_p1
                                    /* base */
/* count */
03823
      #define MEM_COUNT
                             m2_{11}
03824 #define MEM PATTERN
                             m2 12 /* pattern to write */
```

```
book.txt
Feb 25, 11 15:18
                                                                       Page 45/393
       File: Page: 682 include/minix/com.h
03825 #define MEM_CHUNK_BASE m4_l1 /* physical base address */
                                     /* size of mem chunk */
03826 #define MEM_CHUNK_SIZE m4_12
03827 #define MEM_TOT_SIZE m4_13
                                     /* total memory size */
03828 #define MEM_CHUNK_TAG
                                     /* tag to identify chunk of mem */
                             m4_{14}
03829
03830 /* Field names for SYS_DEVIO, SYS_VDEVIO, SYS_SDEVIO. */
                             m2_i3 /* device in or output */
03831 #define DIO_REQUEST
                                     /* input */
03832 # define DIO_INPUT
                                 Ω
                                     /* output */
03833 #
          define DIO OUTPUT
                                 1
                                     /* flag indicating byte, word, or long */
03834 #define DIO_TYPE
                             m2_i1
                                     /* byte type values */
03835 #
          define DIO BYTE
                                'b'
          define DIO WORD
                                     /* word type values */
                                     /* long type values */
03837 #
          define DIO_LONG
                                     /* single port address */
03838 #define DIO_PORT
                              m2_{11}
03839 #define DIO VALUE
                             m2<sup>-</sup>12
                                     /* single I/O value */
03840 #define DIO_VEC_ADDR
                                     /* address of buffer or (p,v)-pairs */
                             m2_p1
03841 #define DIO_VEC_SIZE
                             m2_12
                                     /* number of elements in vector */
                                     /* number of process where vector is */
03842 #define DIO_VEC_PROC
                             m2_i2
03843
03844 /* Field names for SYS_SIGNARLM, SYS_FLAGARLM, SYS_SYNCALRM. */
03845 #define ALRM_EXP_TIME m2_11
                                    /* expire time for the alarm call */
03846 #define ALRM_ABS_TIME
                             m2_i2
                                     /* set to 1 to use absolute alarm time */
                                     /* how many ticks were remaining */
03847 #define ALRM_TIME_LEFT m2_l1
03848 #define ALRM_PROC_NR m2_i1
                                     /* which process wants the alarm? */
03849 #define ALRM_FLAG_PTR m2_p1
                                     /* virtual address of timeout flag */
03850
03851 /* Field names for SYS_IRQCTL. */
                             m5_c1 /* what to do? */
03852 #define IRQ_REQUEST
03853 # define IRQ_SETPOLICY
                                     /* manage a slot of the IRQ table */
03854 # define IRO RMPOLICY
                                     /* remove a slot of the IRO table */
03855 # define IRQ_ENABLE
                                     /* enable interrupts */
                                 3
03856 # define IRQ_DISABLE
                                 4
                                     /* disable interrupts */
03857 #define IRQ_VECTOR
                             m5_c2 /* irg vector */
03858 #define IRQ_POLICY
                             m5_i1
                                     /* options for IRQCTL request */
                                     /* reenable IRQ line after interrupt */
03859 # define IRQ_REENABLE 0x001
03860 # define IRQ_BYTE
                                     /* byte values */
03861 # define IRQ_WORD
                              0x200
                                     /* word values */
03862 # define IRQ_LONG
                                     /* long values */
                             0x400
                                     /* process number, SELF, NONE */
03863 #define IRO PROC NR
                             m5 i2
03864 #define IRQ_HOOK_ID
                                     /* id of irq hook at kernel */
                             m5_13
03865
03866
      /* Field names for SYS_SEGCTL. */
      #define SEG_SELECT
                             m4_11
                                    /* segment selector returned */
03867
03868 #define SEG_OFFSET
                             m4_{12}
                                     /* offset in segment returned */
                                     /* physical address of segment */
03869 #define SEG PHYS
                             m4 13
03870 #define SEG_SIZE
                                     /* segment size */
                             m4_{14}
03871 #define SEG_INDEX
                             m4_{15}
                                     /* segment index in remote map */
03872
03873 /* Field names for SYS VIDCOPY. */
03874 #define VID_REQUEST m4_1 /* what to do? */
03875 # define VID_VID_COPY
                                     /* request vid_vid_copy() */
03876 # define MEM_VID_COPY
                                     /* request mem_vid_copy() */
03877 #define VID_SRC_ADDR m4_12
                                     /* virtual address in memory */
                                     /* offset in video memory */
03878 #define VID_SRC_OFFSET m4_13
03879 #define VID_DST_OFFSET m4_14
                                     /* offset in video memory */
03880 #define VID_CP_COUNT
                             m4 15
                                     /* number of words to be copied */
03882
      /* Field names for SYS_ABORT. */
                             ml_il /* RBT_REBOOT, RBT_HALT, etc. */
03883 #define ABRT_HOW
03884 #define ABRT MON PROC ml i2 /* process where monitor params are */
```

```
Feb 25, 11 15:18
                                      book.txt
                                                                       Page 46/393
       File: Page: 683 include/minix/com.h
      03886
      03888
       /* Field names for _UMAP, _VIRCOPY, _PHYSCOPY. */
      #define CP_SRC_SPACE m5_c1
                                    /* T or D space (stack is also D) */
03889
03890
      #define CP_SRC_PROC_NR m5_i1
                                     /* process to copy from */
                                     /* address where data come from */
03891
      #define CP_SRC_ADDR
                             m5_11
                                     /* T or D space (stack is also D) */
03892
      #define CP_DST_SPACE
                             m5_c2
03893
      #define CP_DST_PROC_NR m5_i2
                                     /* process to copy to */
03894
      #define CP_DST_ADDR
                                     /* address where data go to */
                             m5_{12}
                                     /* number of bytes to copy */
03895
      #define CP_NR_BYTES
                             m5 13
03896
       /* Field names for SYS_VCOPY and SYS_VVIRCOPY. */
03897
                             m1_i2  /* number of successfull copies */
m1_i3  /* size of copy vector */
      #define VCP_NR_OK
03898
      #define VCP VEC SIZE
      #define VCP_VEC_ADDR
                             m1_p1
                                     /* pointer to copy vector */
03900
03901
03902
      /* Field names for SYS_GETINFO. */
03903 #define I REOUEST
                                     /* what info to get */
                            m7_i3
                                     /* get kernel information structure */
03904 #
         define GET_KINFO
                                     /* get system image table */
03905 #
          define GET_IMAGE
03906 #
          define GET_PROCTAB
                                     /* get kernel process table */
                                     /* get randomness buffer */
03907 #
          define GET_RANDOMNESS 3
                                     /* get monitor parameters */
03908 #
          define GET_MONPARAMS 4
03909 #
          define GET_KENV
                                     /* get kernel environment string */
                                     /* get the IRQ table */
03910 #
          define GET_IRQHOOKS
          define GET KMESSAGES
                                     /* get kernel messages */
03911 #
03912 #
          define GET_PRIVTAB
                                     /* get kernel privileges table */
                                     /* get various kernel addresses */
03913 #
          define GET_KADDRESSES
          define GET SCHEDINFO 10
                                     /* get scheduling queues */
03914 #
03915 #
          define GET_PROC
                               11
                                     /* get process slot if given process */
                                     /* get machine information */
03916 #
          define GET_MACHINE
03917 #
          define GET_LOCKTIMING 13
                                     /* get lock()/unlock() latency timing */
03918 #
          define GET_BIOSBUFFER 14
                                     /* get a buffer for BIOS calls */
                                      /* calling process */
03919
      #define I_PROC_NR
                            m7_i4
                                      /* virtual address at caller */
03920
      #define I_VAL_PTR
                            m7_p1
03921
      #define I_VAL_LEN
                            m7_i1
                                     /* max length of value */
                                     /* second virtual address */
03922 #define I_VAL_PTR2
                            m7_p2
03923 #define I_VAL_LEN2
                            m7_i2
                                     /* second length, or proc nr */
03924
03925
       /* Field names for SYS_TIMES. */
      #define T PROC NR
03926
                            m4 11
                                     /* process to request time info for */
      #define T_USER_TIME
                                     /* user time consumed by process */
03927
                            m4_11
03928
      #define T_SYSTEM_TIME m4_12
                                     /* system time consumed by process */
      #define T CHILD UTIME m4 13
                                     /* user time consumed by process' children */
03929
03930
      #define T_CHILD_STIME m4_14
                                     /* sys time consumed by process' children */
03931
      #define T_BOOT_TICKS
                           m4_15
                                     /* number of clock ticks since boot time */
03932
03933
      /* Field names for SYS_TRACE, SYS_SVRCTL. */
                                     /* process number of the caller */
/* server control request */
03934
      #define CTL_PROC_NR
                            m2_i1
03935 #define CTL_REQUEST
                            m2_i2
03936
      #define CTL_MM_PRIV
                            m2_i3
                                     /* privilege as seen by PM */
                                     /* pointer to argument */
03937
      #define CTL_ARG_PTR
                            m2_p1
                                     /* address at traced process' space */
03938
      #define CTL_ADDRESS
                            m2_{11}
03939
      #define CTL_DATA
                            m2_{12}
                                     /* data field for tracing */
03940
03941
      /* Field names for SYS KILL, SYS SIGCTL */
      #define SIG_REQUEST
03942
                            m2_{12}
                                     /* PM signal control request */
                                     /* get pending kernel signal */
03943
      #define S_GETSIG
03944 #define S ENDSIG
                                     /* finish a kernel signal */
```

```
book.txt
Feb 25, 11 15:18
                                                               Page 47/393
      File: Page: 684 include/minix/com.h
                          2 /* POSIX style signal handling */
03945 #define S_SENDSIG
03946 #define S_SIGRETURN
                             3
                                 /* return from POSIX handling */
                                /* servers kills process with signal */
03947 #define S_KILL
03948 #define SIG PROC
                         m2_i1
                               /* process number for inform */
                                 /* signal number to send */
03949 #define SIG_NUMBER
                         m2_i2
03950 #define SIG_FLAGS
                         m2_i3
                                /* signal flags field */
03951 #define SIG_MAP
                         m2_11
                                 /* used by kernel to pass signal bit map */
                                 /* pointer to info to restore signal context */
03952 #define SIG_CTXT_PTR m2_p1
03953
03954 /* Field names for SYS_FORK, _EXEC, _EXIT, _NEWMAP. */
03955 #define PR PROC NR
                         m1 i1
                               /* indicates a (child) process */
03956 #define PR PRIORITY
                         m1 i2
                                 /* process priority */
                                 /* indicates a (parent) process */
03957 #define PR_PPROC_NR
                         m1_i2
                                 /* process id at process manager */
03958 #define PR_PID
                          m1_i3
03959 #define PR_STACK_PTR
                                 /* used for stack ptr in sys_exec, sys_getsp */
                         m1_p1
                                 /* flag to indicate tracing is on/ off */
03960 #define PR_TRACING
                         m1_i3
03961 #define PR_NAME_PTR
                         m1_p2
                                 /* tells where program name is for dmp */
                                 /* initial value for ip after exec */
03962 #define PR_IP_PTR
                         m1_p3
03963 #define PR_MEM_PTR
                                 /* tells where memory map is for sys_newmap */
                         m1_p1
03964
03965 /* Field names for SYS_INT86 */
03966 #define INT86_REG86 ml_pl /* pointer to registers */
03967
03968 /* Field names for SELECT (FS). */
03969 #define SEL_NFDS
                         m8 i1
03970 #define SEL READFDS
                         m8 p1
03971 #define SEL WRITEFDS
                         m8 p2
03972 #define SEL_ERRORFDS
                         m8_p3
03973 #define SEL_TIMEOUT
                         m8_p4
03974
03975 /*========*
03976 * Messages for system management server
03978
03979 #define SRV_RQ_BASE
                                 0 \times 700
03980
03981 #define SRV UP
                          (SRV_RQ_BASE + 0)
                                               /* start system service */
                          (SRV_RQ_BASE + 1)
                                               /* stop system service */
03982 #define SRV_DOWN
03983 #define SRV_STATUS
                          (SRV_RQ_BASE + 2)
                                               /* get service status */
03984
03985 # define SRV_PATH_ADDR
                                               /* path of binary */
                                               /* length of binary */
03986 # define SRV PATH LEN
                                 m1 i1
03987 # define SRV_ARGS_ADDR
                                 m1_p2
                                               /* arguments to be passed */
03988 # define SRV_ARGS_LEN
                                 m1_i2
                                               /* length of arguments */
03989 # define SRV DEV MAJOR
                                              /* major device number */
                                 m1 i3
03990 # define SRV PRIV ADDR
                                              /* privileges string */
                                 m1_p3
                                              /* length of privileges */
03991 # define SRV_PRIV_LEN
                                 m1_i3
03993 /*========*
03994 * Miscellaneous messages used by TTY
03995 *==========*/
03996
03997 /* Miscellaneous request types and field names, e.g. used by IS server. */
03998 #define PANIC DUMPS
                            97 /* debug dumps at the TTY on RBT PANIC *
03999 #define FKEY CONTROL
                                        /* control a function key at the TTY */
                                      /* request to perform at TTY */
04000 # define FKEY REQUEST
                               m2_i1
                               10
                                       /* observe function key */
04001 # define FKEY_MAP
                                       /* stop observing function key */
04002 # define
                FKEY_UNMAP
                                 11
04003 # define
                 FKEY EVENTS
                               12
                                       /* request open key presses */
04004 # define FKEY FKEYS
                                      /* F1-F12 keys pressed */
                               m2 11
```

```
Feb 25, 11 15:18
                                  book.txt
                                                              Page 48/393
      File: Page: 685 include/minix/com.h
04005 # define FKEY SFKEYS
                               m2_{12}
                                       /* Shift-F1-F12 keys pressed */
04006 #define DIAGNOSTICS
                               /* output a string without FS in between */
04007 # define DIAG_PRINT_BUF
                               m1_p1
04008 # define DIAG_BUF_COUNT
                               m1_i
04009 # define DIAG_PROC_NR
                               m1_i2
04011 #endif /* _MINIX_COM_H */
include/minix/devio.h
04100 /* This file provides basic types and some constants for the
04101 * SYS_DEVIO and SYS_VDEVIO system calls, which allow user-level
04102 * processes to perform device I/O.
04103
04104 * Created:
04105 * Apr 08, 2004 by Jorrit N. Herder
04106
04107
04108 #ifndef _DEVIO_H
04109 #define _DEVIO_H
04110
04111 #include <minix/sys config.h>
                                  /* needed to include <minix/type.h> */
04112 #include <sys/types.h>
                           /* u8_t, u16_t, u32_t needed */
04113
04114 typedef ul6 t port t;
04115 typedef U16 t Port t;
04116
04117 /* We have different granularities of port I/O: 8, 16, 32 bits.
      * Also see <ibm/portio.h>, which has functions for bytes, words,
04118
      * and longs. Hence, we need different (port, value) - pair types.
04119
04120 */
04121 typedef struct { u16_t port; u8_t value; } pvb_pair_t; 04122 typedef struct { u16_t port; u16_t value; } pvw_pair_t;
04123 typedef struct { u16_t port; u32_t value; } pvl_pair_t;
04124
04125
      /* Macro shorthand to set (port, value) -pair. */
      #define pv_set(pv, p, v) ((pv).port = (p), (pv).value = (v))
      #define pv_ptr_set(pv_ptr, p, v) ((pv_ptr)->port = (p), (pv_ptr)->value = (v))
04127
04128
04129 #endif /* DEVIO H */
include/minix/dmap.h
04200 #ifndef _DMAP_H
04201 #define _DMAP_H
04202
04203 #include <minix/sys config.h>
04204 #include <minix/ipc.h>
04205
```

```
Feb 25, 11 15:18
                                 book.txt
                                                             Page 49/393
      File: Page: 686 include/minix/dmap.h
04206 /*==========*
04207 * Device <-> Driver Table
04208 *========*/
04209
04210 /* Device table. This table is indexed by major device number. It provides
04211 * the link between major device numbers and the routines that process them.
04212
      * The table can be update dynamically. The field 'dmap_flags' describe an
04213
     * entry's current status and determines what control options are possible.
04214
                                0x01 /* mapping can be overtaken */
0x02 /* driver busy with request */
04215 #define DMAP_MUTABLE
04216 #define DMAP_BUSY
04217
04218 enum dev_style { STYLE_DEV, STYLE_NDEV, STYLE_TTY, STYLE_CLONE };
04219
04220 extern struct dmap {
      int _PROTOTYPE ((*dmap_opcl), (int, Dev_t, int, int) );
04221
04222
       void _PROTOTYPE ((*dmap_io), (int, message *));
       int dmap_driver;
04223
04224
       int dmap_flags;
04225 } dmap[];
04226
04227 /*==========*
04228 * Major and minor device numbers
04229 *=========*/
04230
04231 /* Total number of different devices. */
04232 #define NR_DEVICES 32
                                                 /* number of (major) dev
ices */
04233
04234 /* Major and minor device numbers for MEMORY driver. */
04235 #define MEMORY_MAJOR 1 /* major device for memory devices */
                                      /* minor device for /dev/ram */
04236 # define RAM_DEV
04237 # define MEM_DEV
                                 1 /* minor device for /dev/mem */
04238 # define KMEM_DEV
                                2 /* minor device for /dev/kmem */
3 /* minor device for /dev/null */
04239 # define NULL_DEV
                                4 /* minor device for /dev/boot */
5 /* minor device for /dev/zero */
04240 # define BOOT_DEV
04241 # define ZERO_DEV
04242
04243 #define CTRLR(n) ((n) == 0 ? 3 : (8 + 2*((n)-1))) /* magic formula */
04244
04246 \# define DEV_RAM 0x0100 /* device number of /dev/ram */
                              0x0104 /* device number of /dev/boot */
04247 # define DEV_BOOT
04248
                                  2 /* major device for floppy disks */
04249 #define FLOPPY MAJOR
                                  4 /* major device for ttys */
5 /* major device for /dev/tty */
04250 #define TTY MAJOR
04251 #define CTTY_MAJOR
04252
04253 #define INET_MAJOR
                                 7 /* major device for inet */
04254
04255 #define LOG MAJOR
                                15 /* major device for log driver */
04256 # define IS_KLOG_DEV
                                 0 /* minor device for /dev/klog */
04257
04258 #endif /* DMAP H */
```

```
book.txt
 Feb 25, 11 15:18
                                                                          Page 50/393
       File: Page: 687 include/ibm/portio.h
include/ibm/portio.h
04301 ibm/portio.h
04302
04303 Created:
                      Jan 15, 1992 by Philip Homburg
04304 */
04305
04306 #ifndef _PORTIO_H_
04307 #define _PORTIO_H_
04308
04309 #ifndef TYPES H
04310 #include <sys/types.h>
04311 #endif
04312
04313 unsigned inb(U16_t _port);
04314 unsigned inw(U16_t _port);
04315 unsigned inl(U32_t _port);
04318 void outl(U16_t _port, U32_t _value);
04318 Void Out!(U16_t _port, void *_buf, size_t _count);
04310 void insw(U16_t _port, void *_buf, size_t _count);
04320 void insw(U16_t _port, void *_buf, size_t _count);
04321 void insl(U16_t _port, void *_buf, size_t _count);
04322 void outsb(U16_t _port, void *_buf, size_t _count);
04323 void outsw(U16_t _port, void *_buf, size_t _count);
04324 void outsl(U16_t _port, void *_buf, size_t _count);
04325 void intr_disable(void);
04326 void intr_enable(void);
04327
04328 #endif /* _PORTIO_H_ */
include/ibm/interrupt.h
04400 /* Interrupt numbers and hardware vectors. */
04401
04402 #ifndef _INTERRUPT_H
04403 #define _INTERRUPT_H
04404
04405 #if (CHIP == INTEL)
04406
04407 /* 8259A interrupt controller ports. */
04408 #define INT_CTL 0x20 /* I/O port for interrupt controller */
                                       /* setting bits in this port disables ints */
04409 #define INT_CTLMASK
                               0x21
04410 #define INT2_CTL 0xA0 /* I/O port for second interrupt controller */
04411 #define INT2_CTLMASK 0xAl /* setting bits in this port disables ints */
04412
04413 /* Magic numbers for interrupt controller. */
04414 #define END_OF_INT 0x20 /* code used to re-enable after an interrupt */
04415
04416 /* Interrupt vectors defined/reserved by processor. */
04417 #define DIVIDE_VECTOR 0 /* divide error */
04418 #define DEBUG_VECTOR 1 /* single step (trace) */
04419 #define NMI VECTOR
                                2 /* non-maskable interrupt */
```

```
Feb 25, 11 15:18
                                    book.txt
                                                                  Page 51/393
      File: Page: 688 include/ibm/interrupt.h
04420 #define BREAKPOINT_VECTOR 3 /* software breakpoint */
04421 #define OVERFLOW_VECTOR 4
                                   /* from INTO */
04422
04423 /* Fixed system call vector. */
04424 #define SYS_VECTOR 32 /* system calls are made with int SYSVEC */
04425 #define SYS386_VECTOR
                            33  /* except 386 system calls use this */
04426 #define LEVELO_VECTOR
                             34 /* for execution of a function at level 0 */
04427
04428 /* Suitable irg bases for hardware interrupts. Reprogram the 8259(s) from
04429 * the PC BIOS defaults since the BIOS doesn't respect all the processor's
      * reserved vectors (0 to 31).
04430
04431 */
                                   /* base of IRQ0-7 vectors used by BIOS */
04432 #define BIOS_IRQ0_VEC
                            0 \times 0.8
04433 #define BIOS_IRQ8_VEC
                                   /* base of IRQ8-15 vectors used by BIOS */
                            0x70
04434 #define IROO VECTOR
                                  /* nice vectors to relocate IRO0-7 to */
                            0 \times 50
04435 #define IRQ8_VECTOR
                            0x70
                                   /* no need to move IRO8-15 */
04436
04437 /* Hardware interrupt numbers. */
04438 #define NR_IRQ_VECTORS 16
04439 #define CLOCK_IRQ
                              Ω
04440 #define KEYBOARD_IRQ
04441 #define CASCADE_IRQ
                                   /* cascade enable for 2nd AT controller */
                              3 /* default ethernet interrupt vector */
04442 #define ETHER_IRQ
                            3 /* RS232 interrupt vector for port 2 */
04443 #define SECONDARY_IRQ
                              4 /* RS232 interrupt vector for port 1 */
5 /* xt winchester */
04444 #define RS232_IRQ
04445 #define XT_WINI_IRQ
                                 /* floppy disk */
04446 #define FLOPPY IRO
04447 #define PRINTER_IRQ
04448 #define AT_WINI_0_IRQ
                            14 /* at winchester controller 0 */
                           15 /* at winchester controller 1 */
04449 #define AT_WINI_1_IRQ
04450
04451 /* Interrupt number to hardware vector. */
04452 #define BIOS_VECTOR(irg) \
              (((irq) < 8 ? BIOS_IRQO_VEC : BIOS_IRQ8_VEC) + ((irq) & 0x07))
04453
04454 #define VECTOR(irg) \
04455
             (((irq) < 8 ? IRQ0_VECTOR : IRQ8_VECTOR) + ((irq) & 0x07))
04456
04457 #endif /* (CHIP == INTEL) */
04458
04459 #endif /* _INTERRUPT_H */
include/ibm/ports.h
04500 /* Addresses and magic numbers for miscellaneous ports. */
04501
04502 #ifndef _PORTS_H
04503 #define _PORTS_H
04504
04505 #if (CHIP == INTEL)
04506
04507 /* Miscellaneous ports. */
04508 #define PCR
                            0x65
                                  /* Planar Control Register */
04509 #define PORT_B
                            0x61
                                   /* I/O port for 8255 port B (kbd, beeper...) */
                                   /* I/O port for timer channel 0 */
04510 #define TIMER0
                            0x40
                                 /* I/O port for timer channel 2 */
04511 #define TIMER2
                            0x42
04512 #define TIMER_MODE
                                 /* I/O port for timer mode control */
                            0x43
04513
04514 #endif /* (CHIP == INTEL) */
```

```
Feb 25, 11 15:18
                                    book.txt
                                                                  Page 52/393
      File: Page: 689 include/ibm/ports.h
04515
04516 #endif /* _PORTS_H */
kernel/kernel.h
04600 #ifndef KERNEL_H
04601 #define KERNEL H
04602
04603 /* This is the master header for the kernel. It includes some other files
04604 * and defines the principal constants.
04605
04606 #define _POSIX_SOURCE
                              1 /* tell headers to include POSIX stuff */
04600 #define _NINIX 1 /* tell headers to include MINIX 5.001. /* tell headers that this is the kernel */
04609
04610 /* The following are so basic, all the *.c files get them automatically. */
04611 #include <minix/config.h> /* global configuration, MUST be first */
04612 #include <ansi.h> /* C style: ANSI or K&R, MUST be second */
                                 /* general system types */
04613 #include <sys/types.h>
                                 /* MINIX specific constants */
04614 #include <minix/const.h>
                                   /* MINIX specific types, e.g. message */
04615 #include <minix/type.h>
                               /* MINIX run-time system */
04616 #include <minix/ipc.h>
04617 #include <timers.h>
                                   /* watchdog timer management */
                                   /* return codes and error numbers */
04618 #include <errno.h>
                                 /* device I/O and toggle interrupts */
04619 #include <ibm/portio.h>
04620
04621 /* Important kernel header files. */
04622 #include "config.h" /* configuration, MUST be first */
04623 #include "const.h"
                                   /* constants, MUST be second */
04624 #include "type.h"
                                  /* type definitions, MUST be third */
                                  /* function prototypes */
04625 #include "proto.h"
04626 #include "glo.h"
04627 #include "ipc.h"
                                   /* global variables */
                                   /* IPC constants */
04628 /* #include "debug.h" */
                                  /* debugging, MUST be last kernel header */
04629
04630 #endif /* KERNEL H */
kernel/config.h
04700 #ifndef CONFIG_H
04701 #define CONFIG_H
04702
04703 /* This file defines the kernel configuration. It allows to set sizes of some
04704 * kernel buffers and to enable or disable debugging code, timing features,
      * and individual kernel calls.
04705
04706
04707
      * Changes:
04708 * Jul 11, 2005
                            Created. (Jorrit N. Herder)
04709
```

```
book.txt
Feb 25, 11 15:18
                                                                       Page 53/393
      File: Page: 690 kernel/config.h
04710
04711 /* In embedded and sensor applications, not all the kernel calls may be
      * needed. In this section you can specify which kernel calls are needed
       * and which are not. The code for unneeded kernel calls is not included in
04713
      * the system binary, making it smaller. If you are not sure, it is best
04714
04715 * to keep all kernel calls enabled.
04716 */
04717 #define USE_FORK
                                      /* fork a new process */
04718 #define USE_NEWMAP
                                 1
                                    /* set a new memory map */
04719 #define USE_EXEC
                                     /* update process after execute */
                                     /* clean up after process exit */
04720 #define USE EXIT
04721 #define USE TRACE
                                     /* process information and tracing */
                                     /* retrieve pending kernel signals */
04722 #define USE_GETKSIG
                                     /* finish pending kernel signals */
04723 #define USE_ENDKSIG
04724 #define USE KILL
                                     /* send a signal to a process */
04725 #define USE_SIGSEND
                                     /* send POSIX-style signal */
04726 #define USE_SIGRETURN
                                     /* sys_sigreturn(proc_nr, ctxt_ptr, flags) */
                                      /* shut down MINIX */
04727 #define USE_ABORT
04728 #define USE_GETINFO
                                     /* retrieve a copy of kernel data */
04729 #define USE_TIMES
                                      /* get process and system time info */
04730 #define USE_SETALARM
                                      /* schedule a synchronous alarm */
04731 #define USE_DEVIO
                                     /* read or write a single I/O port */
04732 #define USE_VDEVIO
                                      /* process vector with I/O requests */
                                     /* perform I/O request on a buffer */
04733 #define USE SDEVIO
04734 #define USE_IRQCTL
                                     /* set an interrupt policy */
04735 #define USE_SEGCTL
                                      /* set up a remote segment */
04736 #define USE PRIVCTL
                                     /* system privileges control */
04737 #define USE NICE
                                     /* change scheduling priority */
                                     /* map virtual to physical address */
04738 #define USE_UMAP
04739 #define USE VIRCOPY
                                     /* copy using virtual addressing */
04740 #define USE_VIRVCOPY
                                     /* vector with virtual copy requests */
                                 1
04741 #define USE_PHYSCOPY
                                 1
                                     /* copy using physical addressing */
04742 #define USE_PHYSVCOPY
                                     /* vector with physical copy requests */
04743 #define USE_MEMSET
                                1
                                     /* write char to a given memory area */
04744
04745 /* Length of program names stored in the process table. This is only used
04746 * for the debugging dumps that can be generated with the IS server. The PM
04747 * server keeps its own copy of the program name.
04748 */
04749 #define P_NAME_LEN
04750
04751 /* Kernel diagnostics are written to a circular buffer. After each message,
      * a system server is notified and a copy of the buffer can be retrieved to
04752
04753
      * display the message. The buffers size can safely be reduced.
04754 */
04755 #define KMESS BUF SIZE 256
04756
04757 /* Buffer to gather randomness. This is used to generate a random stream by
04758
      * the MEMORY driver when reading from /dev/random.
04759 */
04760 #define RANDOM_ELEMENTS 32
04761
04762 /* This section contains defines for valuable system resources that are used
04763 * by device drivers. The number of elements of the vectors is determined by
04764
       * the maximum needed by any given driver. The number of interrupt hooks may
04765
       * be incremented on systems with many device drivers.
04766
      #define NR_IRQ_HOOKS
04767
                               16
                                             /* number of interrupt hooks */
04768 #define VDEVIO_BUF_SIZE 64
                                             /* max elements per VDEVIO request */
04769 #define VCOPY VEC SIZE 16
                                             /* max elements per VCOPY request */
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 54/393
       File: Page: 691 kernel/config.h
04770
04772 #define K_STACK_BYTES 1024
04773
04774 /* This section allows to enable kernel debugging and timing functionality.
04775
       * For normal operation all options should be disabled.
04776
04777 #define DEBUG_SCHED_CHECK 0
                                    /* sanity check of scheduling queues */
                                  /* kernel lock() sanity check */
04778
      #define DEBUG LOCK CHECK 0
04779
      #define DEBUG_TIME_LOCKS
                                 /* measure time spent in locks */
                              0
04780
04781
      #endif /* CONFIG H */
04782
kernel/const.h
04800 /* General macros and constants used by the kernel. */
04801 #ifndef CONST H
04802 #define CONST_H
04803
04804 #include <ibm/interrupt.h>
                                    /* interrupt numbers and hardware vectors */
04805 #include <ibm/ports.h>
                                    /* port addresses and magic numbers */
                                    /* BIOS addresses, sizes and magic numbers */
04806 #include <ibm/bios.h>
04807 #include <ibm/cpu.h>
                                    /* BIOS addresses, sizes and magic numbers */
04808 #include <minix/config.h>
04809 #include "config.h"
04810
04811 /* To translate an address in kernel space to a physical address. This is
04812 * the same as umap_local(proc_ptr, D, vir, sizeof(*vir)), but less costly.
04813
04814 #define vir2phys(vir) (kinfo.data_base + (vir_bytes) (vir))
04815
04816 /* Map a process number to a privilege structure id. */
04817 #define s_nr_to_id(n) (NR_TASKS + (n) + 1)
04818
04819
      /* Translate a pointer to a field in a structure to a pointer to the structure
       * itself. So it translates '&struct_ptr->field' back to 'struct_ptr'.
04820
04821
04822 #define structof(type, field, ptr) \
04823
              ((type *) (((char *) (ptr)) - offsetof(type, field)))
04824
04825
      /* Constants used in virtual_copy(). Values must be 0 and 1, respectively. */
04826
      #define _SRC_ 0
04827
      #define _DST_ 1
04828
04829 /* Number of random sources */
04830 #define RANDOM_SOURCES 16
04831
04832
      /* Constants and macros for bit map manipulation. */
04833 #define BITCHUNK BITS (sizeof(bitchunk t) * CHAR BIT)
04834
      #define BITMAP_CHUNKS(nr_bits) (((nr_bits)+BITCHUNK_BITS-1)/BITCHUNK_BITS)
04835
      #define MAP_CHUNK(map,bit) (map)[((bit)/BITCHUNK_BITS)]
      #define CHUNK OFFSET(bit) ((bit)%BITCHUNK BITS))
      #define GET_BIT(map,bit) ( MAP_CHUNK(map,bit) & (1 << CHUNK_OFFSET(bit) ) #define SET_BIT(map,bit) ( MAP_CHUNK(map,bit) | = (1 << CHUNK_OFFSET(bit) )
04837
04838
04839 #define UNSET BIT(map,bit) ( MAP CHUNK(map,bit) &= ~(1 << CHUNK OFFSET(bit) )
```

```
book.txt
Feb 25, 11 15:18
                                                                  Page 55/393
      File: Page: 692 kernel/const.h
04840
04841 #define get_sys_bit(map,bit) \
             ( MAP_CHUNK(map.chunk,bit) & (1 << CHUNK_OFFSET(bit) )
04842
04843 #define set_sys_bit(map,bit) \
             ( MAP_CHUNK(map.chunk,bit) |= (1 << CHUNK_OFFSET(bit) )
04844
04845 #define unset_sys_bit(map,bit) \
04846
              ( MAP_CHUNK(map.chunk,bit) &= ~(1 << CHUNK_OFFSET(bit) )
04847 #define NR_SYS_CHUNKS BITMAP_CHUNKS(NR_SYS_PROCS)
04848
04849
      /* Program stack words and masks. */
04850 #define INIT_PSW 0x0200 /* initial psw */
04851 #define INIT_TASK_PSW 0x1200 /* initial psw for tasks (with IOPL 1) */
04852 #define TRACEBIT 0x0100 /* OR this with psw in prcc[] for tracing */
                                   /* permits only certain bits to be set */ \
04853 #define SETPSW(rp, new)
             ((rp)->p_reg.psw = (rp)->p_reg.psw & ~0xCD5 | (new) & 0xCD5)
04855 #define IF MASK 0x00000200
04856 #define IOPL_MASK 0x003000
04858 /* Disable/ enable hardware interrupts. The parameters of lock() and unlock()
04859 * are used when debugging is enabled. See debug.h for more information.
04861 #define lock(c, v)
                            intr_disable();
04862 #define unlock(c)
                            intr enable();
04864 /* Sizes of memory tables. The boot monitor distinguishes three memory areas,
      * namely low mem below 1M, 1M-16M, and mem after 16M. More chunks are needed
04865
      * for DOS MINIX.
04866
04867
04868 #define NR_MEMS
04869
04870 #endif /* CONST H */
04871
04872
04873
04874
04875
kernel/type.h
04900 #ifndef TYPE H
04901 #define TYPE_H
04902
04903 typedef _PROTOTYPE( void task_t, (void) );
04904
04905 /* Process table and system property related types. */
04906 typedef int proc_nr_t;
                                          /* process table entry number */
                                          /* system process index */
04907 typedef short sys_id_t;
                                          /* bitmap for system indexes */
04908 typedef struct {
        bitchunk_t chunk[BITMAP_CHUNKS(NR_SYS_PROCS)];
04909
      } sys map t;
04910
04911
04912 struct boot_image {
04913
        proc_nr_t proc_nr;
                                          /* process number to use */
04914
        task t *initial pc;
                                          /* start function for tasks */
```

```
book.txt
Feb 25, 11 15:18
                                                                        Page 56/393
      File: Page: 693 kernel/type.h
04915
       int flags;
                                              /* process flags */
04916
        unsigned char quantum;
                                              /* quantum (tick count) */
                                              /* scheduling priority */
04917
        int priority;
04918
        int stksize;
                                              /* stack size for tasks */
                                              /* allowed system call traps */
04919
         short trap_mask;
04920
        bitchunk_t ipc_to;
                                              /* send mask protection */
        long call_mask;
04921
                                              /* system call protection */
        char proc_name[P_NAME_LEN];
                                             /* name in process table */
04922
04923 };
04924
04925 struct memory {
04926
       phys clicks base;
                                              /* start address of chunk */
        phys_clicks size;
                                             /* size of memory chunk */
04927
04928 };
04929
04930
      /* The kernel outputs diagnostic messages in a circular buffer. */
04931 struct kmessages {
04932
       int km_next;
                                              /* next index to write */
04933
                                              /* current size in buffer */
        int km_size;
        char km_buf[KMESS_BUF_SIZE];
                                             /* buffer for messages */
04934
04935 };
04936
04937 struct randomness {
04938
       struct {
04939
                                                     /* next index to write */
              int r_next;
                                                     /* number of random elements */
04940
              int r_size;
              unsigned short r buf[RANDOM ELEMENTS]; /* buffer for random info */
04941
        } bin[RANDOM_SOURCES];
04942
04943 };
04944
04945 #if (CHIP == INTEL)
04946 typedef unsigned reg_t;
                                     /* machine register */
04947
04948 /* The stack frame layout is determined by the software, but for efficiency
04949 * it is laid out so the assembly code to use it is as simple as possible.
04950 * 80286 protected mode and all real modes use the same frame, built with
04951
       * 16-bit registers. Real mode lacks an automatic stack switch, so little
       * is lost by using the 286 frame for it. The 386 frame differs only in
04952
04953
       * having 32-bit registers and more segment registers. The same names are
04954
       * used for the larger registers to avoid differences in the code.
04955
04956 struct stackframe s {
                                      /* proc ptr points here */
      #if _WORD_SIZE == 4
04957
04958
       u16_t gs;
                                      /* last item pushed by save */
04959
        ul6 t fs;
04960
      #endif
                                      /* | */
04961
        u16_t es;
                                      /*
04962
        u16_t ds;
04963
        reg_t di;
                                      /* di through cx are not accessed in C */
04964
        reg_t si;
                                      /* order is to match pusha/popa */
                                      /* bp */
04965
        reg_t fp;
        reg_t st;
                                      /* hole for another copy of sp */
04966
                                      /* | */
04967
        reg_t bx;
                                      /*
04968
        reg t dx;
04969
        reg_t cx;
                                      /* ax and above are all pushed by save */
04970
        reg_t retreg;
                                      /* return address for assembly code save() */
04971
        reg t retadr;
04972
        reg_t pc;
                                            last item pushed by interrupt */
04973
        reg_t cs;
04974
        reg t psw;
```

```
book.txt
 Feb 25, 11 15:18
                                                                    Page 57/393
      File: Page: 694 kernel/type.h
04975
       reg_t sp;
04976
        reg_t ss;
                                    /* these are pushed by CPU during interrupt */
04977 };
04978
04979 struct segdesc_s {
                                    /* segment descriptor for protected mode */
04980
      u16_t limit_low;
04981
        u16_t base_low;
04982
        u8_t base_middle;
                                    /* |P|DL|1|X|E|R|A| */
04983
        u8 t access;
04984
        u8_t granularity;
                                    /* |G|X|0|A|LIMT| */
04985
        u8_t base_high;
04986
04987
04988
      typedef unsigned long irq_policy_t;
04989 typedef unsigned long irg id t;
04990
04991 typedef struct irq_hook {
04992
       struct irq_hook *next;
                                           /* next hook in chain */
        int (*handler)(struct irq_hook *);
                                           /* interrupt handler */
04993
                                           /* IRQ vector number */
04994
        int irq;
04995
        int id;
                                           /* id of this hook */
04996
        int proc_nr;
                                           /* NONE if not in use */
        irq_id_t notify_id;
                                           /* id to return on interrupt */
04997
                                           /* bit mask for policy */
04998
        irq_policy_t policy;
04999 } irq_hook_t;
05000
05001 typedef int (*irg handler t)(struct irg hook *);
05002
05003 #endif /* (CHIP == INTEL) */
05004
05005 #if (CHIP == M68000)
05006
      /* M68000 specific types go here. */
05007 #endif /* (CHIP == M68000) */
05008
05009 #endif /* TYPE_H */
kernel/proto.h
05100 /* Function prototypes. */
05101
05102 #ifndef PROTO H
05103 #define PROTO_H
05105 /* Struct declarations. */
05106 struct proc;
05107 struct timer;
05108
05109 /* clock.c */
05110 _PROTOTYPE( void clock_task, (void)
05111 _PROTOTYPE( void clock_stop, (void) 05112 _PROTOTYPE( clock_t get_uptime, (void)
                                                                         );
                                                                         );
05113 _PROTOTYPE( unsigned long read_clock, (void)
05114 _PROTOTYPE( void set_timer, (struct timer *tp, clock_t t, tmr_func_t f) );
05115 _PROTOTYPE( void reset_timer, (struct timer *tp)
05117 /* main.c */
05118 _PROTOTYPE( void main, (void)
05119 PROTOTYPE( void prepare shutdown, (int how)
                                                                         );
```

```
Feb 25, 11 15:18
                                        book.txt
                                                                         Page 58/393
       File: Page: 695 kernel/proto.h
05120
05121 /* utility.c */
05122 _PROTOTYPE( void kprintf, (const char *fmt, ...)
                                                                              );
05123 _PROTOTYPE( void panic, (_CONST char *s, int n)
                                                                              );
05124
05125 /* proc c */
O5126 _PROTOTYPE( int sys_call, (int function, int src_dest, message *m_ptr) );
O5127 _PROTOTYPE( int lock_notify, (int src, int dst) );
05128 _PROTOTYPE( int lock_send, (int dst, message *m_ptr)
                                                                              );
05129 _PROTOTYPE( void lock_enqueue, (struct proc *rp)
                                                                              );
05130 _PROTOTYPE( void lock_dequeue, (struct proc *rp)
                                                                              );
05131
05132 /* start.c */
05133 _PROTOTYPE( void cstart, (U16_t cs, U16_t ds, U16_t mds,
                                     U16 t parmoff, U16 t parmsize)
05134
05135
05136 /* system.c */
05137 _PROTOTYPE( int get_priv, (register struct proc *rc, int proc_type)
                                                                              );
05138 _PROTOTYPE( void send_sig, (int proc_nr, int sig_nr)
                                                                              );
05139 _PROTOTYPE( void cause_sig, (int proc_nr, int sig_nr)
                                                                              );
05140 _PROTOTYPE( void sys_task, (void)
                                                                              );
05141 _PROTOTYPE( void get_randomness, (int source)
                                                                              );
05142 _PROTOTYPE( int virtual_copy, (struct vir_addr *src, struct vir_addr *dst,
05143
                                      vir_bytes bytes)
                                                                              );
05144 #define numap_local(proc_nr, vir_addr, bytes) \
        umap_local(proc_addr(proc_nr), D, (vir_addr), (bytes))
05145
05146 _PROTOTYPE( phys_bytes umap_local, (struct proc *rp, int seg,
                      vir_bytes vir_addr, vir_bytes bytes)
05147
                                                                              );
05148 _PROTOTYPE( phys_bytes umap_remote, (struct proc *rp, int seg,
                      vir bytes vir addr, vir bytes bytes)
05149
05150 _PROTOTYPE( phys_bytes umap_bios, (struct proc *rp, vir_bytes vir_addr,
05151
                      vir_bytes bytes)
05152
05153 /* exception.c */
05154 _PROTOTYPE( void exception, (unsigned vec_nr)
                                                                              );
05155
05156 /* i8259.c */
05157 _PROTOTYPE( void intr_init, (int mine)
                                                                              );
05158 _PROTOTYPE( void intr_handle, (irq_hook_t *hook)
                                                                              );
05159 _PROTOTYPE( void put_irq_handler, (irq_hook_t *hook, int irq,
05160
                                                      irq_handler_t handler) );
05161 _PROTOTYPE( void rm_irq_handler, (irq_hook_t *hook)
05162
05163 /* klib*.s */
05164 PROTOTYPE( void int86, (void)
05165 _PROTOTYPE( void cp_mess, (int src,phys_clicks src_clicks,vir_bytes src_offset,
05166
                      phys_clicks dst_clicks, vir_bytes dst_offset)
                                                                              );
05167 _PROTOTYPE( void enable_irq, (irq_hook_t *hook)
05168 _PROTOTYPE( int disable_irq, (irq_hook_t *hook)
05169 _PROTOTYPE( ul6_t mem_rdw, (Ul6_t segm, vir_bytes offset)
                                                                              );
                                                                              );
05170 _PROTOTYPE( void phys_copy, (phys_bytes source, phys_bytes dest,
                      phys_bytes count)
05171
                                                                              );
05172 _PROTOTYPE( void phys_memset, (phys_bytes source, unsigned long pattern,
05173
                      phys_bytes count)
05174 _PROTOTYPE( void phys_insb, (U16_t port, phys_bytes buf, size_t count) );
05175 _PROTOTYPE( void phys_insw, (U16_t port, phys_bytes buf, size_t count) );
05176 _PROTOTYPE( void phys_outsb, (U16_t port, phys_bytes buf, size_t count) );
05177 _PROTOTYPE( void phys_outsw, (U16_t port, phys_bytes buf, size_t count) );
05178 _PROTOTYPE( void reset, (void)
05179 PROTOTYPE( void level0, (void (*func)(void))
```

```
book.txt
                                                                        Page 59/393
Feb 25, 11 15:18
       File: Page: 696 kernel/proto.h
05180 _PROTOTYPE( void monitor, (void)
05181 _PROTOTYPE( void read_tsc, (unsigned long *high, unsigned long *low)
                                                                              );
05182 _PROTOTYPE( unsigned long read_cpu_flags, (void)
05183
05184 /* mpx*.s */
05185 _PROTOTYPE( void idle_task, (void)
                                                                              );
05186 _PROTOTYPE( void restart, (void)
                                                                              );
05187
05188 /* The following are never called from C (pure asm procs). */
05189
05190 /* Exception handlers (real or protected mode), in numerical order. */
05191 void _PROTOTYPE( int00, (void) ), _PROTOTYPE( divide_error, (void) );
05192 void _PROTOTYPE( int01, (void) ), _PROTOTYPE( single_step_exception, (void) );
05193 void _PROTOTYPE( int02, (void) ), _PROTOTYPE( nmi, (void) );
05194 void PROTOTYPE( int03, (void) ), PROTOTYPE( breakpoint_exception, (void) );
05195 void PROTOTYPE( int04, (void) ), PROTOTYPE( overflow, (void) );
05196 void _PROTOTYPE( int05, (void) ), _PROTOTYPE( bounds_check, (void) );
05197 void _PROTOTYPE( int06, (void) ), _PROTOTYPE( inval_opcode, (void) );
05198 void PROTOTYPE( int07, (void) ), PROTOTYPE( copr_not_available, (void) );
05199 void
                                       _PROTOTYPE( double_fault, (void) );
05200 void
                                       _PROTOTYPE( copr_seg_overrun, (void) );
                                       _PROTOTYPE( inval_tss, (void) );
05201 void
05202 void
                                        _PROTOTYPE( segment_not_present, (void) );
                                       _PROTOTYPE( stack_exception, (void) );
05203 void
                                       _PROTOTYPE( general_protection, (void) );
05204 void
05205 void
                                        _PROTOTYPE( page_fault, (void) );
05206 void
                                        _PROTOTYPE( copr_error, (void) );
05207
05208 /* Hardware interrupt handlers. */
05209 _PROTOTYPE( void hwint00, (void) );
05210 _PROTOTYPE( void hwint01, (void) );
05211 _PROTOTYPE( void hwint02, (void) );
05212 _PROTOTYPE( void hwint03, (void) );
05213 _PROTOTYPE( void hwint04, (void) );
05214 _PROTOTYPE( void hwint05, (void) );
05215 _PROTOTYPE( void hwint06, (void) );
05216 _PROTOTYPE( void hwint07, (void) );
05217 _PROTOTYPE( void hwint08, (void) );
05218 _PROTOTYPE( void hwint09, (void) );
05219 _PROTOTYPE( void hwint10, (void) );
05220 _PROTOTYPE( void hwint11, (void) );
05221 _PROTOTYPE( void hwint12, (void) );
05222 _PROTOTYPE( void hwint13, (void) );
05223 _PROTOTYPE( void hwint14, (void) );
05224 PROTOTYPE( void hwint15, (void) );
05225
05226 /* Software interrupt handlers, in numerical order. */
05227 _PROTOTYPE( void trp, (void) );
05228 _PROTOTYPE( void s_call, (void) ), _PROTOTYPE( p_s_call, (void) );
05229 _PROTOTYPE( void level0_call, (void) );
05230
05231 /* protect.c */
05232 _PROTOTYPE( void prot_init, (void)
05233 _PROTOTYPE( void init_codeseg, (struct segdesc_s *segdp, phys_bytes base,
                      vir_bytes size, int privilege)
05234
05235 _PROTOTYPE( void init_dataseg, (struct segdesc_s *segdp, phys_bytes base,
                     vir_bytes size, int privilege) );
05236
05237 _PROTOTYPE( phys_bytes seg2phys, (U16_t seg)
05238 _PROTOTYPE( void phys2seg, (u16_t *seg, vir_bytes *off, phys_bytes phys));
05239 _PROTOTYPE( void enable_iop, (struct proc *pp)
```

```
book.txt
 Feb 25, 11 15:18
                                                                    Page 60/393
      File: Page: 697 kernel/proto.h
      _PROTOTYPE( void alloc_segments, (struct proc *rp)
                                                                         );
05241
05242 #endif /* PROTO_H */
05243
05244
kernel/glo.h
05300 #ifndef GLO H
05301 #define GLO H
05302
05303 /* Global variables used in the kernel. This file contains the declarations;
05304 * storage space for the variables is allocated in table.c, because EXTERN is
05305
       * defined as extern unless the _TABLE definition is seen. We rely on the
05306
      * compiler's default initialization (0) for several global variables.
05307 */
05308 #ifdef TABLE
05309 #undef EXTERN
05310 #define EXTERN
05311 #endif
05312
05313 #include <minix/config.h>
05314 #include "config.h"
05315
05316 /* Variables relating to shutting down MINIX. */
05317 EXTERN char kernel_exception; /* TRUE after system exceptions */
                                           /* TRUE after shutdowns / reboots */
05318 EXTERN char shutdown_started;
05319
05320 /* Kernel information structures. This groups vital kernel information. */
05321 EXTERN phys_bytes aout; /* address of a.out headers */
05322 EXTERN struct kinfo kinfo;
                                           /* kernel information for users */
05323 EXTERN struct machine machine;
                                          /* machine information for users */
05324 EXTERN struct kmessages kmess;
                                           /* diagnostic messages in kernel */
                                         /* gather kernel random information */
05325 EXTERN struct randomness krandom;
05326
05327 /* Process scheduling information and the kernel reentry count. */
05328 EXTERN struct proc *prev_ptr; /* previously running process */
05329 EXTERN struct proc *proc_ptr;
                                   /* pointer to currently running process */
                                   /* next process to run after restart() */
05330 EXTERN struct proc *next_ptr;
05331 EXTERN struct proc *bill_ptr; /* process to bill for clock ticks */
05332 EXTERN char k_reenter;
                                    /* kernel reentry count (entry count less 1) */
05333 EXTERN unsigned lost_ticks;
                                    /* clock ticks counted outside clock task */
05334
05335 /* Interrupt related variables. */
05336 EXTERN irq_hook_t irq_hooks[NR_IRQ_HOOKS];
                                                   /* hooks for general use */
05337 EXTERN irg_hook_t *irg_handlers[NR_IRQ_VECTORS];/* list of IRQ handlers */
05338 EXTERN int irq_actids[NR_IRQ_VECTORS]; /* IRQ ID bits active */
05339 EXTERN int irq_use;
                                                   /* map of all in-use irq's */
05340
05341 /* Miscellaneous. */
05342 EXTERN reg_t mon_ss, mon_sp;
                                           /* boot monitor stack */
                                           /* true if we can return to monitor */
05343 EXTERN int mon_return;
05344
05345 /* Variables that are initialized elsewhere are just extern here. */
05346 extern struct boot_image image[]; /* system image processes */
                                           /* task stack space */
05347 extern char *t stack[];
05348 extern struct segdesc_s gdt[];
                                         /* global descriptor table */
05349
```

```
book.txt
Feb 25, 11 15:18
                                                              Page 61/393
      File: Page: 698 kernel/glo.h
05350 EXTERN _PROTOTYPE( void (*level0_func), (void) );
05351
05352 #endif /* GLO_H */
05353
05354
05355
05356
05357
kernel/ipc.h
05400 #ifndef IPC H
05401 #define IPC_H
05402
05403 /* This header file defines constants for MINIX inter-process communication.
05404 * These definitions are used in the file proc.c.
05405 */
05406 #include <minix/com.h>
05407
05408 /* Masks and flags for system calls. */
05409 #define SYSCALL_FUNC
                          0x0F /* mask for system call function */
                                /* mask for system call flags */
05410 #define SYSCALL FLAGS
                          0xF0
                         0x10 /* prevent blocking, return error */
05411 #define NON BLOCKING
05412
05413 /* System call numbers that are passed when trapping to the kernel. The
05414 * numbers are carefully defined so that it can easily be seen (based on
05415 * the bits that are on) which checks should be done in sys_call().
05416 */
05417 #define SEND
                                 /* 0 0 0 1 : blocking send */
05418 #define RECEIVE
                            2 /* 0 0 1 0 : blocking receive */
                                /* 0 0 1 1 : SEND + RECEIVE */
05419 #define SENDREC
                            3
05420 #define NOTIFY
                               /* 0 1 0 0 : nonblocking notify */
                            8 /* 1 0 0 0 : echo a message */
05421 #define ECHO
05422
05423 /* The following bit masks determine what checks that should be done. */
05424 #define CHECK_PTR
                          05425 #define CHECK DST
                               /* 0 0 1 0 : validate message source */
05426 #define CHECK SRC
05427
05428 #endif /* IPC_H */
                               kernel/proc.h
05500 #ifndef PROC_H
05501 #define PROC_H
05502
05503 /* Here is the declaration of the process table. It contains all process
05504 * data, including registers, flags, scheduling priority, memory map,
       * accounting, message passing (IPC) information, and so on.
05505
05506
05507
      * Many assembly code routines reference fields in it. The offsets to these
      * fields are defined in the assembler include file sconst.h. When changing
05508
      * struct proc, be sure to change sconst.h to match.
```

```
book.txt
Feb 25, 11 15:18
                                                                       Page 62/393
      File: Page: 699 kernel/proc.h
05510
05511 #include <minix/com.h>
05512 #include "protect.h"
05513 #include "const.h"
05514 #include "priv.h"
05515
05516 struct proc {
05517
                                     /* process' registers saved in stack frame */
        struct stackframe_s p_reg;
        05518
05519
05520
05521
        proc nr t p nr;
                                      /* number of this process (for fast access) */
        struct priv *p_priv;
                                     /* system privileges structure */
05522
05523
        char p_rts_flags;
                                      /* SENDING, RECEIVING, etc. */
05524
05525
        char p priority;
                                      /* current scheduling priority */
05526
        char p_max_priority;
                                      /* maximum scheduling priority */
05527
        char p_ticks_left;
                                      /* number of scheduling ticks left */
05528
                                      /* quantum size in ticks */
        char p_quantum_size;
05529
05530
        struct mem_map p_memmap[NR_LOCAL_SEGS]; /* memory map (T, D, S) */
05531
05532
        clock_t p_user_time;
                                      /* user time in ticks */
05533
        clock_t p_sys_time;
                                      /* sys time in ticks */
05534
05535
        struct proc *p_nextready;
                                      /* pointer to next ready process */
        struct proc *p_caller_q;
                                      /* head of list of procs wishing to send */
05536
        struct proc *p_q_link;
05537
                                      /* link to next proc wishing to send */
                                      /* pointer to passed message buffer */
05538
        message *p_messbuf;
05539
        proc nr t p getfrom;
                                      /* from whom does process want to receive? */
05540
                                      /* to whom does process want to send? */
        proc_nr_t p_sendto;
05541
05542
        sigset_t p_pending;
                                      /* bit map for pending kernel signals */
05543
05544
        char p_name[P_NAME_LEN];
                                     /* name of the process, including \0 */
05545 };
05546
05547 /* Bits for the runtime flags. A process is runnable iff p_rts_flags == 0. */
05548 #define SLOT FREE
                              0x01 /* process slot is free */
      #define NO_MAP
05549
                                     /* keeps unmapped forked child from running */
                              0 \times 0.2
                                     /* process blocked trying to SEND */
05550
      #define SENDING
                              0 \times 04
                                     /* process blocked trying to RECEIVE */
05551
      #define RECEIVING
                              0x08
      #define SIGNALED
                                     /* set when new kernel signal arrives */
05552
                              0 \times 10
05553
      #define SIG_PENDING
                              0x20
                                     /* unready while signal being processed */
05554 #define P_STOP
                                     /* set when process is being traced */
                              0 \times 40
                                     /* keep forked system process from running */
05555 #define NO PRIV
                             0x80
05556
05557 /* Scheduling priorities for p_priority. Values must start at zero (highest
05558
      * priority) and increment. Priorities of the processes in the boot image
05559
      * can be set in table.c. IDLE must have a queue for itself, to prevent low
05560
       * priority user processes to run round-robin with IDLE.
05561
05562 #define NR_SCHED_QUEUES 16
                                     /* MUST equal minimum priority + 1 */
      #define TASK O
                                     /* highest, used for kernel tasks */
05563
                                0
05564
      #define MAX_USER_Q
                                0
                                     /* highest priority for user processes */
                                     /* default (should correspond to nice 0) */
05565
      #define USER_Q
      #define MIN_USER_Q
                                    /* minimum priority for user processes */
05566
                                     /* lowest, only IDLE process goes here */
05567
      #define IDLE_Q
05568
05569 /* Magic process table addresses. */
```

```
book.txt
 Feb 25, 11 15:18
                                                                     Page 63/393
       File: Page: 700 kernel/proc.h
05570 #define BEG PROC ADDR (&proc[0])
05571 #define BEG_USER_ADDR (&proc[NR_TASKS])
05572 #define END_PROC_ADDR (&proc[NR_TASKS + NR_PROCS])
05573
05574 #define NIL_PROC
                               ((struct proc *) 0)
05575 #define NIL_SYS_PROC
                               ((struct proc *) 1)
05576 #define cproc_addr(n)
                               (&(proc + NR_TASKS)[(n)])
                                (pproc_addr + NR_TASKS)[(n)]
05577 #define proc_addr(n)
05578 #define proc nr(p)
                               ((p)->p nr)
05579
05580 #define isokprocn(n)
                                ((unsigned) ((n) + NR_TASKS) < NR_PROCS + NR_TASKS)
05581 #define isemptyn(n)
                               isemptyp(proc addr(n))
                               ((p)->p_rts_flags == SLOT_FREE)
05582 #define isemptyp(p)
05583 #define iskernelp(p)
                                iskerneln((p)->p_nr)
05584 #define iskerneln(n)
                               ((n) < 0)
05585 #define isuserp(p)
                               isusern((p)->p_nr)
05586 #define isusern(n)
                               ((n) >= 0)
05587
05588 /* The process table and pointers to process table slots. The pointers allow
05589 * faster access because now a process entry can be found by indexing the
05590 * pproc_addr array, while accessing an element i requires a multiplication
05591
       * with sizeof(struct proc) to determine the address.
05592 */
05593 EXTERN struct proc proc[NR_TASKS + NR_PROCS]; /* process table */
05594 EXTERN struct proc *pproc_addr[NR_TASKS + NR_PROCS];
05595 EXTERN struct proc *rdy_head[NR_SCHED_QUEUES]; /* ptrs to ready list headers */
05596 EXTERN struct proc *rdy_tail[NR_SCHED_QUEUES]; /* ptrs to ready list tails */
05597
05598 #endif /* PROC_H */
kernel/sconst.h
05600 ! Miscellaneous constants used in assembler code.
                            _WORD_SIZE
05601 W
                                          ! Machine word size
                    =
05602
05603 ! Offsets in struct proc. They MUST match proc.h.
05604 P_STACKBASE
                   =
                             Ω
05605 GSREG
                             P STACKBASE
05606 FSREG
                             GSREG + 2
                                            ! 386 introduces FS and GS segments
05607 ESREG
                             FSREG + 2
05608 DSREG
                             ESREG + 2
05609 DIREG
                             DSREG + 2
05610 SIREG
                             DIREG + W
05611 BPREG
                             STREG + W
05612 STREG
                             BPREG + W
                                            I hole for another SP
05613 BXREG
                             STREG + W
05614 DXREG
                             BXREG + W
05615 CXREG
                             DXREG + W
05616 AXREG
                             CXREG + W
05617 RETADR
                                            ! return address for save() call
                             AXREG + W
05618 PCREG
                             RETADR + W
05619 CSREG
                             PCREG + W
05620 PSWREG
                             CSREG + W
05621 SPREG
                             PSWREG + W
05622 SSREG
                             SPREG + W
05623 P_STACKTOP
                             SSREG + W
05624 P LDT SEL
                             P STACKTOP
```

```
book.txt
 Feb 25, 11 15:18
                                                                     Page 64/393
       File: Page: 701 kernel/sconst.h
05625 P LDT
                             P_LDT_SEL + W
05626
05627 Msize
                                            ! size of a message in 32-bit words
kernel/priv.h
05700 #ifndef PRIV H
05701 #define PRIV H
05702
05703 /* Declaration of the system privileges structure. It defines flags, system
       * call masks, an synchronous alarm timer, I/O privileges, pending hardware
05705
       * interrupts and notifications, and so on.
05706
       * System processes each get their own structure with properties, whereas all
       * user processes share one structure. This setup provides a clear separation
05708
       * between common and privileged process fields and is very space efficient.
05709
05710
05711
       * Jul 01, 2005
                             Created. (Jorrit N. Herder)
05712
05713 #include <minix/com.h>
05714 #include "protect.h"
05715 #include "const.h"
      #include "type.h"
05716
05717
05718
       struct priv {
05719
                                     /* number of associated process */
        proc nr t s proc nr;
05720
                                    /* index of this system structure */
        sys_id_t s_id;
05721
         short s_flags;
                                    /* PREEMTIBLE, BILLABLE, etc. */
05722
05723
        short s trap mask;
                                     /* allowed system call traps */
                                     /* allowed callers to receive from */
05724
         sys_map_t s_ipc_from;
05725
         sys_map_t s_ipc_to;
                                     /* allowed destination processes */
        long s_call_mask;
05726
                                     /* allowed kernel calls */
05727
05728
        sys_map_t s_notify_pending;
                                    /* bit map with pending notifications */
05729
                                     /* pending hardware interrupts */
         irq_id_t s_int_pending;
                                    /* pending signals */
05730
        sigset_t s_sig_pending;
05731
05732
        05733
05734
                                    /* stack quard word for kernel tasks */
        reg_t *s_stack_guard;
05735
05736
05737
       /* Guard word for task stacks. */
05738
       #define STACK_GUARD ((reg_t) (sizeof(reg_t) == 2 ? 0xBEEF : 0xDEADBEEF))
05739
05740
       /* Bits for the system property flags. */
       #define PREEMPTIBLE
05741
                             0x01 /* kernel tasks are not preemptible */
                                    /* some processes are not billable */
05742 #define BILLABLE
                             0 \times 04
                                    /* system processes are privileged */
05743 #define SYS PROC
                             0x10
05744
       #define SENDREC_BUSY
                           0 \times 20
                                    /* sendrec() in progress */
05745
05746
       /* Magic system structure table addresses. */
       #define BEG_PRIV_ADDR (&priv[0])
05747
05748
       #define END_PRIV_ADDR (&priv[NR_SYS_PROCS])
05749
```

```
book.txt
 Feb 25, 11 15:18
                                                                     Page 65/393
       File: Page: 702 kernel/priv.h
                               (ppriv_addr)[(i)]
05750 #define priv addr(i)
05751 #define priv_id(rp)
                               ((rp)->p_priv->s_id)
05752 #define priv(rp)
                               ((rp)->p_priv)
05753
05754 #define id_to_nr(id)
                             priv_addr(id)->s_proc_nr
05755 #define nr_to_id(nr) priv(proc_addr(nr))->s_id
05756
05757 /* The system structures table and pointers to individual table slots. The
05758 * pointers allow faster access because now a process entry can be found by
05759
       * indexing the psys_addr array, while accessing an element i requires a
05760
       * multiplication with sizeof(struct sys) to determine the address.
05762 EXTERN struct priv priv[NR_SYS_PROCS];
                                                   /* system properties table */
05763 EXTERN struct priv *ppriv_addr[NR_SYS_PROCS]; /* direct slot pointers */
05764
05765 /* Unprivileged user processes all share the same privilege structure.
05766 * This id must be fixed because it is used to check send mask entries.
05767 */
05768 #define USER_PRIV_ID
05769
05770 /* Make sure the system can boot. The following sanity check verifies that
05771 * the system privileges table is large enough for the number of processes
      * in the boot image.
05772
05774 #if (NR_BOOT_PROCS > NR_SYS_PROCS)
05775 #error NR_SYS_PROCS must be larger than NR_BOOT_PROCS
05776 #endif
05777
05778 #endif /* PRIV_H */
                                  kernel/protect.h
05800 /* Constants for protected mode. */
05801
05802 /* Table sizes. */
05803 #define GDT_SIZE (FIRST_LDT_INDEX + NR_TASKS + NR_PROCS)
                                           /* spec. and LDT's */
05804
                                            /* only up to the highest vector */
05805 #define IDT_SIZE (IRQ8_VECTOR + 8)
05806 #define LDT_SIZE (2 + NR_REMOTE_SEGS) /* CS, DS and remote segments */
05807
05808 /* Fixed global descriptors. 1 to 7 are prescribed by the BIOS. */
05809 #define GDT_INDEX 1 /* GDT descriptor */
                                  2 /* IDT descriptor */
05810 #define IDT INDEX
05811 #define DS_INDEX
                                 3 /* kernel DS */
05812 #define ES_INDEX
                                 4 /* kernel ES (386: flag 4 Gb at startup) */
05813 #define SS_INDEX
                                 5 /* kernel SS (386: monitor SS at startup) */
                                  6 /* kernel CS */
05814 #define CS_INDEX
05815 #define MON_CS_INDEX
                                7 /* temp for BIOS (386: monitor CS at startup) *
05816 #define TSS_INDEX
                                 8 /* kernel TSS */
                                  9 /* scratch 16-bit source segment */
05817 #define DS 286 INDEX
                                 10 /* scratch 16-bit destination segment */
05818 #define ES_286_INDEX
                                 11 /* 64K memory segment at A0000 */
05819 #define A_INDEX
                                 12 /* 64K memory segment at B0000 */
05820 #define B INDEX
                                 13 /* 64K memory segment at C0000 */
05821 #define C_INDEX
                                 14 /* 64K memory segment at D0000 */
05822 #define D_INDEX
05823 #define FIRST LDT INDEX
                               15 /* rest of descriptors are LDT's */
05824
```

```
book.txt
Feb 25, 11 15:18
                                                                       Page 66/393
      File: Page: 703 kernel/protect.h
      #define GDT SELECTOR
                                0x08 /* (GDT INDEX * DESC SIZE) bad for asld */
                                    /* (IDT_INDEX * DESC_SIZE) */
05826
      #define IDT_SELECTOR
                                0x10
05827 #define DS_SELECTOR
                                0x18 /* (DS_INDEX * DESC_SIZE) */
05828 #define ES_SELECTOR
                                0x20 /* (ES_INDEX * DESC_SIZE) */
05829 #define FLAT_DS_SELECTOR 0x21 /* less privileged ES */
05830 #define SS_SELECTOR
                                    /* (SS_INDEX * DESC_SIZE) */
05831 #define CS_SELECTOR
                                0x30
                                    /* (CS_INDEX * DESC_SIZE) */
                                     /* (MON_CS_INDEX * DESC_SIZE) */
05832 #define MON_CS_SELECTOR
                               0x38
                                     /* (TSS INDEX * DESC SIZE) */
05833 #define TSS SELECTOR
                                0x40
      #define DS_286_SELECTOR
                                    /* (DS_286_INDEX*DESC_SIZE+TASK_PRIVILEGE) */
05834
                               0x49
05835
      #define ES_286_SELECTOR
                               0x51
                                     /* (ES_286_INDEX*DESC_SIZE+TASK_PRIVILEGE) */
05836
05837
      /* Fixed local descriptors. */
05838 #define CS_LDT_INDEX
                                  0 /* process CS */
                                  1 /* process DS=ES=FS=GS=SS */
05839 #define DS LDT INDEX
05840 #define EXTRA_LDT_INDEX
                                   2 /* first of the extra LDT entries */
05841
05842 /* Privileges. */
05843 #define INTR PRIVILEGE
                                  0 /* kernel and interrupt handlers */
                                  1 /* kernel tasks */
05844 #define TASK PRIVILEGE
05845 #define USER_PRIVILEGE
                                   3 /* servers and user processes */
05846
05847 /* 286 hardware constants. */
05848
05849
      /* Exception vector numbers. */
                                 5 /* bounds check failed */
05850
      #define BOUNDS_VECTOR
05851 #define INVAL_OP_VECTOR
                                   6 /* invalid opcode */
      #define COPROC_NOT_VECTOR
05852
                                 7 /* coprocessor not available */
05853
      #define DOUBLE_FAULT_VECTOR 8
      #define COPROC SEG VECTOR 9 /* coprocessor segment overrun */
      #define INVAL_TSS_VECTOR
05855
                                 10 /* invalid TSS */
                                 11 /* segment not present */
05856
      #define SEG_NOT_VECTOR
05857 #define STACK_FAULT_VECTOR 12 /* stack exception */
05858 #define PROTECTION_VECTOR 13 /* general protection */
05859
05860 /* Selector bits. */
05861 #define TI
                                0x04 /* table indicator */
05862 #define RPL
                               0x03 /* requester privilege level */
05863
05864
      /* Descriptor structure offsets. */
                                  2 /* to base_low */
05865
      #define DESC BASE
      #define DESC BASE MIDDLE
                                   4 /* to base middle */
      #define DESC_ACCESS
                                  5 /* to access byte */
05867
05868
      #define DESC_SIZE
                                  8 /* sizeof (struct segdesc_s) */
05869
05870
      /* Base and limit sizes and shifts. */
05871
      #define BASE_MIDDLE_SHIFT 16 /* shift for base --> base_middle */
05872
05873
      /* Access-byte and type-byte bits. */
05874
      #define PRESENT
                               0x80 /* set for descriptor present */
05875 #define DPL
                                0x60 /* descriptor privilege level mask */
05876
      #define DPL SHIFT
                                  5
05877 #define SEGMENT
                                0x10 /* set for segment-type descriptors */
05878
05879
      /* Access-byte bits. */
05880
      #define EXECUTABLE
                                0x08 /* set for executable segment */
                                0x04 /* set for conforming segment if executable */
05881 #define CONFORMING
      #define EXPAND DOWN
                                0x04 /* set for expand-down segment if !executable*/
05882
                                    /* set for readable segment if executable */
05883 #define READABLE
                                0 \times 0.2
05884 #define WRITEABLE
                                0x02 /* set for writeable segment if !executable */
```

```
book.txt
 Feb 25, 11 15:18
                                                                   Page 67/393
       File: Page: 704 kernel/protect.h
                              0x02 /* set if TSS descriptor is busy */
05885 #define TSS BUSY
05886 #define ACCESSED
                              0x01 /* set if segment accessed */
05888 /* Special descriptor types. */
                                1 /* available 286 TSS */
05889 #define AVL_286_TSS
05890 #define LDT
                                 2 /* local descriptor table */
05891 #define BUSY_286_TSS
                                 3 /* set transparently to the software */
                                 4 /* not used */
05892 #define CALL_286_GATE
                                 5 /* only used by debugger */
05893 #define TASK GATE
                                 6 /* interrupt gate, used for all vectors */
05894 #define INT_286_GATE
                                 7 /* not used */
05895 #define TRAP_286_GATE
05897 /* Extra 386 hardware constants. */
05898
05899 /* Exception vector numbers. */
05900 #define PAGE_FAULT_VECTOR 14
05901 #define COPROC_ERR_VECTOR 16 /* coprocessor error */
05902
05903 /* Descriptor structure offsets. */
05904 #define DESC_GRANULARITY 6 /* to granularity byte */
                                 7 /* to base_high */
05905 #define DESC_BASE_HIGH
05906
05907 /* Base and limit sizes and shifts. */
05908 #define BASE HIGH SHIFT 24 /* shift for base --> base high */
05909 #define BYTE_GRAN_MAX 0xFFFFFL /* maximum size for byte granular segment */
05910 #define GRANULARITY_SHIFT 16 /* shift for limit --> granularity */
                                16 /* shift for (gate) offset --> offset_high */
05911 #define OFFSET HIGH SHIFT
05912 #define PAGE_GRAN_SHIFT
                                12 /* extra shift for page granular limits */
05913
05914 /* Type-byte bits. */
05915 #define DESC 386 BIT 0x08 /* 386 types are obtained by ORing with this */
05916
                                   /* LDT's and TASK_GATE's don't need it */
05917
05918 /* Granularity byte. */
05919 #define GRANULAR
                              0x80 /* set for 4K granularilty */
05920 #define DEFAULT
                              0x40 /* set for 32-bit defaults (executable seg) */
05921 #define BIG
                              0x40 /* set for "BIG" (expand-down seg) */
                              0x10 /* 0 for available */
05922 #define AVL
05923 #define LIMIT HIGH
                              0x0F /* mask for high bits of limit */
kernel/table.c
06000 /* The object file of "table.c" contains most kernel data. Variables that
06001
      * are declared in the *.h files appear with EXTERN in front of them, as in
06003
            EXTERN int x;
06004
06005
       * Normally EXTERN is defined as extern, so when they are included in another
06006
        * file, no storage is allocated. If EXTERN were not present, but just say,
06007
06008
            int x;
06009
06010
        * then including this file in several source files would cause 'x' to be
       * declared several times. While some linkers accept this, others do not,
         so they are declared extern when included normally. However, it must be
06012
       * declared for real somewhere. That is done here, by redefining EXTERN as
06013
       * the null string, so that inclusion of all *.h files in table.c actually
```

```
Feb 25, 11 15:18
                                       book.txt
                                                                        Page 68/393
      File: Page: 705 kernel/table.c
06015
       * generates storage for them.
06016
       * Various variables could not be declared EXTERN, but are declared PUBLIC
06018
       * or PRIVATE. The reason for this is that extern variables cannot have a
       ^{\star} default initialization. If such variables are shared, they must also be
06019
06020
       * declared in one of the *.h files without the initialization. Examples
06021
        * include 'boot_image' (this file) and 'idt' and 'gdt' (protect.c).
06022
       * Changes:
06023
06024
            Aug 02, 2005
                           set privileges and minimal boot image (Jorrit N. Herder)
06025
            Oct 17, 2004
                           updated above and tasktab comments (Jorrit N. Herder)
06026
            May 01, 2004
                           changed struct for system image (Jorrit N. Herder)
06027
06028 #define _TABLE
06029
06030 #include "kernel.h"
06031 #include "proc.h"
06032 #include "ipc.h"
06033 #include <minix/com.h>
06034 #include <ibm/int86.h>
06035
06036 /* Define stack sizes for the kernel tasks included in the system image. */
06037 #define NO_STACK
                             Ω
06038 #define SMALL_STACK
                              (128 * sizeof(char *))
      #define IDL_S SMALL_STACK
06039
                                      /* 3 intr, 3 temps, 4 db for Intel */
                                      /* dummy task, uses kernel stack */
06040
      #define HRD_S
                      NO_STACK
06041 #define TSK_S SMALL_STACK
                                      /* system and clock task */
06042
06043
      /* Stack space for all the task stacks. Declared as (char *) to align it. */
06044 #define TOT STACK SPACE (IDL S + HRD S + (2 * TSK S))
06045 PUBLIC char *t_stack[TOT_STACK_SPACE / sizeof(char *)];
06046
06047 /* Define flags for the various process types. */
06048 #define IDL_F (SYS_PROC | PREEMPTIBLE | BILLABLE)
                                                              /* idle task */
                                                              /* kernel tasks */
06049 #define TSK_F
                      (SYS_PROC)
06050 #define SRV_F
                      (SYS_PROC | PREEMPTIBLE)
                                                              /* system services */
06051 #define USR F
                      (BILLABLE PREEMPTIBLE)
                                                              /* user processes */
06052
06053 /* Define system call traps for the various process types. These call masks
06054
       * determine what system call traps a process is allowed to make.
06055
06056 #define TSK T (1 << RECEIVE)
                                                      /* clock and system */
06057 #define SRV_T (~0)
                                                      /* system services */
06058 #define USR_T
                      ((1 << SENDREC) | (1 << ECHO)) /* user processes */
06059
06060 /* Send masks determine to whom processes can send messages or notifications.
06061
       * The values here are used for the processes in the boot image. We rely on
      * the initialization code in main() to match the s_nr_to_id() mapping for the
06063
       * processes in the boot image, so that the send mask that is defined here
06064
       * can be directly copied onto map[0] of the actual send mask. Privilege
06065
       * structure 0 is shared by user processes.
06066
       * /
      #define s(n)
06067
                              (1 << s_nr_to_id(n))
06068 #define SRV M (~0)
06069
      #define SYS_M (~0)
      #define USR_M (s(PM_PROC_NR) | s(FS_PROC_NR) | s(RS_PROC_NR))
06070
06071 #define DRV_M (USR_M | s(SYSTEM) | s(CLOCK) | s(LOG_PROC_NR) | s(TTY_PROC_NR))
06072
06073 /* Define kernel calls that processes are allowed to make. This is not looking
06074 * very nice, but we need to define the access rights on a per call basis.
```

```
book.txt
 Feb 25, 11 15:18
                                                                     Page 69/393
       File: Page: 706 kernel/table.c
       * Note that the reincarnation server has all bits on, because it should
06076
       * be allowed to distribute rights to services that it starts.
06077
06078 #define c(n)
                     (1 << ((n)-KERNEL_CALL))
06079 #define RS_C
06080 #define PM_C
                    ~(c(SYS_DEVIO) | c(SYS_SDEVIO) | c(SYS_VDEVIO) \
06081
            c(SYS_IRQCTL) | c(SYS_INT86))
                    (c(SYS_KILL) | c(SYS_VIRCOPY) | c(SYS_VIRVCOPY) | c(SYS_UMAP) \
06082
      #define FS_C
            c(SYS_GETINFO) | c(SYS_EXIT) | c(SYS_TIMES) | c(SYS_SETALARM))
06083
      06084
06085
06086
      #define MEM_C (DRV_C | c(SYS_PHYSCOPY) | c(SYS_PHYSVCOPY))
06087
06088 /* The system image table lists all programs that are part of the boot image.
       * The order of the entries here MUST agree with the order of the programs
        * in the boot image and all kernel tasks must come first.
06090
06091
        * Each entry provides the process number, flags, quantum size (qs), scheduling
06092
        * queue, allowed traps, ipc mask, and a name for the process table. The
06093
        * initial program counter and stack size is also provided for kernel tasks.
06094
06095 PUBLIC struct boot_image image[] = {
06096
         process nr, pc, flags, qs, queue, stack, traps, ipcto, call, name */
IDLE, idle_task, IDL_F, 8, IDLE_Q, IDL_S, 0, 0, 0, "IDLE"
06097
                                                                  0, "IDLE" },
          CLOCK, clock_task, TSK_F, 64, TASK_Q, TSK_S, TSK_T,
                                                                   0, "CLOCK" }
06098
                                                             0,
                                                                   0, "SYSTEM"
06099
          SYSTEM, sys_task, TSK_F, 64, TASK_Q, TSK_S, TSK_T,
                                                          0,
06100
          HARDWARE,
                       0, TSK_F, 64, TASK_Q, HRD_S,
                                                             0,
                                                                   0, "KERNEL"
                       0, SRV_F, 32,
                                                   SRV_T, SRV_M, PM_C, "pm"
06101
          PM PROC NR,
                                         3, 0,
                                                  SRV_T, SRV_M, FS_C, "fs"
SRV_T, SYS_M, RS_C, "rs"
                      0, SRV_F, 32,
06102
          FS_PROC_NR,
                                         4, 0,
06103
          RS_PROC_NR,
                       0, SRV_F, 4,
                                         3, 0,
          TTY PROC NR,
                       0, SRV F, 4,
                                                   SRV_T, SYS_M, DRV_C, "tty"
06104
                                         1,0,
                      0, SRV_F, 4,
          MEM PROC NR,
                                                   SRV_T, DRV_M, MEM_C, "memory"
06105
                                         2, 0,
06106
          LOG_PROC_NR,
                       0, SRV_F, 4,
                                         2, 0,
                                                   SRV_T, SYS_M, DRV_C, "log"
                                                   SRV_T, SYS_M, DRV_C, "driver"},
06107
          DRVR_PROC_NR, 0, SRV_F, 4,
                                         2, 0,
06108
          INIT_PROC_NR, 0, USR_F, 8, USER_Q, 0,
                                                                   0, "init" },
                                                  USR_T, USR_M,
06109
06110
06111 /* Verify the size of the system image table at compile time. Also verify that
       * the first chunk of the ipc mask has enough bits to accommodate the processes
06112
06113
       * in the image.
        * If a problem is detected, the size of the 'dummy' array will be negative,
06114
06115
        * causing a compile time error. Note that no space is actually allocated
       * because 'dummy' is declared extern.
06116
06117
06118 extern int dummy[(NR_BOOT_PROCS==sizeof(image)/
              sizeof(struct boot image))?1: -1];
06119
      extern int dummy[(BITCHUNK BITS > NR BOOT PROCS - 1) ? 1 : -1];
06120
06121
kernel/mpx.s
06201 ! Chooses between the 8086 and 386 versions of the Minix startup code.
06202
06203 #include <minix/config.h>
06204 #if WORD SIZE == 2
```

```
book.txt
 Feb 25, 11 15:18
                                                                     Page 70/393
       File: Page: 707 kernel/mpx.s
06205 #include "mpx88.s"
06206 #else
06207 #include "mpx386.s"
06208 #endif
kernel/mpx386.s
06301 ! This file, mpx386.s, is included by mpx.s when Minix is compiled for
06302 ! 32-bit Intel CPUs. The alternative mpx88.s is compiled for 16-bit CPUs.
06303
06304 ! This file is part of the lowest layer of the MINIX kernel. (The other part
06305 ! is "proc.c".) The lowest layer does process switching and message handling.
06306 ! Furthermore it contains the assembler startup code for Minix and the 32-bit
06307 ! interrupt handlers. It cooperates with the code in "start.c" to set up a
06308 ! good environment for main().
06309
06310 ! Every transition to the kernel goes through this file. Transitions to the
06311 ! kernel may be nested. The initial entry may be with a system call (i.e.,
06312 ! send or receive a message), an exception or a hardware interrupt; kernel
06313 ! reentries may only be made by hardware interrupts. The count of reentries
06314 ! is kept in "k_reenter". It is important for deciding whether to switch to
06315 ! the kernel stack and for protecting the message passing code in "proc.c".
06316
06317
       ! For the message passing trap, most of the machine state is saved in the
06318
       ! proc table. (Some of the registers need not be saved.) Then the stack is
        switched to "k stack", and interrupts are reenabled. Finally, the system
        call handler (in C) is called. When it returns, interrupts are disabled
06320
06321
       ! again and the code falls into the restart routine, to finish off held-up
06322 ! interrupts and run the process or task whose pointer is in "proc_ptr".
06323
06324 ! Hardware interrupt handlers do the same, except (1) The entire state must
06325 ! be saved. (2) There are too many handlers to do this inline, so the save
06326
       ! routine is called. A few cycles are saved by pushing the address of the
06327
       ! appropriate restart routine for a return later. (3) A stack switch is
06328
        avoided when the stack is already switched. (4) The (master) 8259 interrupt
06329
        controller is reenabled centrally in save(). (5) Each interrupt handler
06330
        masks its interrupt line using the 8259 before enabling (other unmasked)
        interrupts, and unmasks it after servicing the interrupt. This limits the
06332
       ! nest level to the number of lines and protects the handler from itself.
06333
06334
       ! For communication with the boot monitor at startup time some constant
06335
        data are compiled into the beginning of the text segment. This facilitates
06336
       ! reading the data at the start of the boot process, since only the first
       ! sector of the file needs to be read.
06338
06339 ! Some data storage is also allocated at the end of this file. This data
06340 ! will be at the start of the data segment of the kernel and will be read
06341
      ! and modified by the boot monitor before the kernel starts.
06342
06343 ! sections
06344
06345
      .sect .text
06346 begtext:
       .sect .rom
06347
06348 begrom:
06349 .sect .data
```

Feb 2	5, 11 15:18	book.txt	Page 71/393
	File: Page: 708 kernel	/mpx386.s	
06350	begdata:		
06351	.sect .bss		
06352 06353	begbss:		
06353	#include <minix config<="" th=""><th>, h></th><th></th></minix>	, h>	
06355	#include <minix const.<="" th=""><th></th><th></th></minix>		
06356	#include <minix com.h=""></minix>		
06357	#include <ibm interrup<="" th=""><th>ot.h></th><th></th></ibm>	ot.h>	
06358	#include "const.h"		
06359	#include "protect.h"		
06360 06361	#include "sconst.h"		
06362	/* Selected 386 tss of	fsets */	
06363	#define TSS3_S_SP0	4	
06364			
06365	! Exported functions		
06366	! Note: in assembly]	anguage the .define statement applied to	o a function name
06367		at to a prototype in C code it makes	
06368 06369	! the entity.	clared in the assembly code but does no	t create
06370	: the entrey:		
06371	.define _restart		
06372	.define save		
06373			
06374	.define _divide_error		
06375 06376	.define _single_step_e .define _nmi	exception	
06377	.define _breakpoint_ex	ception	
06378	.define _overflow	100p01011	
06379	.define _bounds_check		
06380	.define _inval_opcode		
06381	.define _copr_not_avai	.lable	
06382 06383	.define _double_fault .define copr seg over	run.	
06384	.define _copr_seg_over	Luii	
06385	.define _segment_not_p	present	
06386	.define _stack_excepti	on	
06387	.define _general_prote	ection	
06388	.define _page_fault		
06389 06390	.define _copr_error		
06391	.define _hwint00	! handlers for hardware interrupts	
06392	.define _hwint01		
06393	.define _hwint02		
06394	.define _hwint03		
06395	.define _hwint04		
06396 06397	.define _hwint05 .define _hwint06		
06397	.define _nwint06		
06399	.define _hwint08		
06400	.define _hwint09 .define _hwint10		
06401	.define _hwint10		
06402	.define _hwint11		
06403 06404	.define _hwint12 .define _hwint13		
06405	.define hwint14		
06406	.define _hwint14 .define _hwint15		
06407			
06408	.define _s_call		
06409	.define _p_s_call		
1			

```
book.txt
Feb 25, 11 15:18
                                                                    Page 72/393
      File: Page: 709 kernel/mpx386.s
06410 .define _level0_call
06411
06412 ! Exported variables.
06413 .define begbss
06414 .define begdata
06415
06416 .sect .text
06417 !*=======*
06418 !*
                                  MINIX
06419 !*========*
06420 MINIX:
                                     ! this is the entry point for the MINIX kernel
06421
                 over flags
                                    ! skip over the next few bytes
              .data2 CLICK_SHIFT
                                   ! for the monitor: memory granularity
06422
06423 flags:
06424
              .data2 0x01FD
                                    ! boot monitor flags:
06425
                                           call in 386 mode, make bss, make stack,
06426
                                           load high, don't patch, will return,
06427
                                           uses generic INT, memory vector,
06428
                                           new boot code return
06429
                                    ! extra byte to sync up disassembler
06430 over_flags:
06431
06432
     ! Set up a C stack frame on the monitor stack. (The monitor sets cs and ds
06433 ! right. The ss descriptor still references the monitor data segment.)
                                   ! monitor stack is a 16 bit stack
06434
             movzx esp, sp
06435
             push
                     ebp
06436
             mov
                     ebp, esp
06437
             push
                    esi
06438
             push
                     edi
06439
                                   ! monitor return vector is
             cmp
                     4(ebp), 0
06440
                                   ! nonzero if return possible
             jz
                    noret
06441
             inc
                     (_mon_return)
06442 noret: mov
                     (_mon_sp), esp ! save stack pointer for later return
06443
06444 ! Copy the monitor global descriptor table to the address space of kernel and
06445 ! switch over to it. Prot_init() can then update it with immediate effect.
06446
06447
                     (_gdt+GDT_SELECTOR)
             sgdt
                                                  ! get the monitor gdtr
06448
             mov
                     esi, (_gdt+GDT_SELECTOR+2)
                                                  ! absolute address of GDT
06449
                                                    address of kernel GDT
             mov
                     ebx, _gdt
06450
             mov
                     ecx, 8*8
                                                  ! copying eight descriptors
06451 copygdt:
06452
             movb
                     al. (esi)
       eseg
06453
             movb
                     (ebx), al
06454
             inc
06455
             inc
                     ebx
06456
             loop
                     copygdt
                     eax, (_gdt+DS_SELECTOR+2)
06457
             mov
                                                  ! base of kernel data
06458
                     eax, 0x00FFFFFF
                                                  ! only 24 bits
             and
06459
             add
                     eax, _gdt
                                                  ! eax = vir2phys(gdt)
06460
             mov
                     (_gdt+GDT_SELECTOR+2), eax
                                                  ! set base of GDT
06461
             lgdt
                     (_gdt+GDT_SELECTOR)
                                                  ! switch over to kernel GDT
06462
06463 ! Locate boot parameters, set up kernel segment registers and stack.
                     ebx, 8(ebp)
06464
                                   ! boot parameters offset
             mov
06465
             mov
                     edx, 12(ebp)
                                    ! boot parameters length
                                   ! address of a.out headers
06466
             mov
                     eax, 16(ebp)
                     (_aout), eax
06467
             mov
                                    ! kernel data
06468
             mov
                     ax, ds
06469
                     es, ax
```

```
book.txt
Feb 25, 11 15:18
                                                                  Page 73/393
      File: Page: 710 kernel/mpx386.s
06470
             mov
                    fs. ax
06471
             mov
                    qs, ax
06472
             mov
                    ss, ax
06473
                    esp, k_stktop ! set sp to point to the top of kernel stack
             mov
06474
06475
      ! Call C startup code to set up a proper environment to run main().
06476
             push
06477
             push
                    ehx
06478
             push
                    SS SELECTOR
06479
             push
                    DS_SELECTOR
06480
                    CS SELECTOR
             push
06481
             call
                     cstart
                                   ! cstart(cs, ds, mds, parmoff, parmlen)
06482
             add
                    esp, 5*4
06483
      ! Reload gdtr, idtr and the segment registers to global descriptor table set
06484
06485
      ! up by prot init().
06486
06487
              lgdt
                     (_gdt+GDT_SELECTOR)
06488
             lidt
                     ( gdt+IDT_SELECTOR)
06489
06490
             jmpf
                    CS_SELECTOR: csinit
06491
      csinit:
06492
         ol6 mov
                    ax, DS_SELECTOR
06493
             mov
                    ds, ax
06494
             mov
                    es, ax
06495
             mov
                    fs, ax
06496
             mov
                    qs, ax
06497
             mov
                    ss. ax
                    ax, TSS_SELECTOR
                                          ! no other TSS is used
06498
          ol6 mov
06499
             1tr
                    ax
06500
                    0
                                          ! set flags to known good state
             push
06501
                                          ! esp, clear nested task and int enable
             popf
06502
06503
             amir
                     main
                                          | main()
06504
06505
06506
      I * ______ *
      1 *
06507
                                   interrupt handlers
06508
                    interrupt handlers for 386 32-bit protected mode
06509
      !*-----
06510
06511
      06512
                                  hwint.00 - 07
06513
      !*==================================
      ! Note this is a macro, it just looks like a subroutine.
06514
      #define hwint_master(irq)
06515
06516
             call
                                           /* save interrupted process state */;\
                                          /* irq_handlers[irq]
06517
             push
                    (_irq_handlers+4*irq)
06518
             call
                     _intr_handle
                                          /* intr_handle(irq_handlers[irq]) */;\
06519
             gog
06520
             cmp
                     (_irg_actids+4*irg), 0 /* interrupt still active?
06521
             jz
                    Ωf
                                                                           ;\
                    INT_CTLMASK
06522
             inb
                                          /* get current mask */
                                                                           ;\
06523
             orb
                    al, [1<<irq]
                                          /* mask irq */
                                          /* disable the irq
06524
                    INT_CTLMASK
             outb
06525
      0:
              movb
                     al, END_OF_INT
06526
             outb
                    INT CTL
                                          /* reenable master 8259
                                          /* restart (another) process
06527
             ret.
06528
06529
     ! Each of these entry points is an expansion of the hwint master macro
```

```
book.txt
 Feb 25, 11 15:18
                                                                                                                                                    Page 74/393
              File: Page: 711 kernel/mpx386.s
06530
                               .align 16
06531
               _hwint00:
                                                                 ! Interrupt routine for irq 0 (the clock).
06532
                             hwint_master(0)
06533
06534
                               .align 16
06535
              hwint01:
                                                                ! Interrupt routine for irq 1 (keyboard)
06536
                             hwint master(1)
06537
06538
                               .align 16
              _hwint02:
06539
                                                                 ! Interrupt routine for irq 2 (cascade!)
06540
                             hwint master(2)
06541
06542
                               .align 16
              _hwint03:
06543
                                                                 ! Interrupt routine for irq 3 (second serial)
06544
                              hwint master(3)
06545
06546
                               .align 16
06547
              _hwint04:
                                                                ! Interrupt routine for irg 4 (first serial)
06548
                             hwint master(4)
06549
06550
                               .align 16
              _hwint05:
06551
                                                                 ! Interrupt routine for irg 5 (XT winchester)
06552
                             hwint_master(5)
06553
06554
                               .align 16
06555
              hwint06:
                                                                 ! Interrupt routine for irq 6 (floppy)
                             hwint master(6)
06556
06557
06558
                               .align 16
              hwint07:
06559
                                                                ! Interrupt routine for irg 7 (printer)
                             hwint master(7)
06560
06561
06562
              I * ______ * * ___ * * ___ * * ___ * * ___ * * ___ * * ___ * * ___ * * ___ * * ___ * * ___ * * ___ * * ___ * * ___ * * ___ * * ___ * * ___ * * ___ * * ___ * * ___ * * ___ * * ___ * * ___ * ___ * * ___ * * ___ * * ___ * * ___ * * ___ * ___ * ___ * * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ___ * ____ * ____ * ___ * ___ * ___ * ____ * ____ * ___ * ___ * ____ * ____ * ____ * ___ * ___ * __
06563
                                                                              hwint08 - 15
              06564
06565
              ! Note this is a macro, it just looks like a subroutine.
              #define hwint_slave(irg)
06566
                                                                                               /* save interrupted process state */;\
06567
                             call
                                             save
06568
                             push
                                              ( irg handlers+4*irg)
                                                                                              /* irq_handlers[irq]
                                                                                              /* intr_handle(irq_handlers[irq])
                                                                                                                                                                  */;\
06569
                              call.
                                               _intr_handle
06570
                              gog
                                               (_irq_actids+4*irq), 0 /* interrupt still active?
06571
                              cmp
06572
                                                                                                                                                                      ;\
                               iz
                                              0f
06573
                              inb
                                              INT2_CTLMASK
                                                                                                                                                                       ;\
06574
                              orb
                                              al, [1<<[irq-8]]
                                                                                               /* disable the irg
06575
                              out.b
                                               INT2 CTLMASK
06576
                               movb
                                                al, END_OF_INT
06577
                              outb
                                               INT_CTL
                                                                                               /* reenable master 8259
06578
                                                                                               /* reenable slave 8259
                                                                                                                                                                   */;\
                              outh
                                               INT2 CTL
06579
                             ret
                                                                                              /* restart (another) process
06580
06581
              ! Each of these entry points is an expansion of the hwint_slave macro
06582
                               .align 16
06583
              hwint08:
                                                                ! Interrupt routine for irg 8 (realtime clock)
06584
                             hwint slave(8)
06585
06586
                               .aliqn 16
              _hwint09:
06587
                                                                 ! Interrupt routine for irg 9 (irg 2 redirected)
06588
                             hwint_slave(9)
06589
```

```
book.txt
Feb 25, 11 15:18
                                                                Page 75/393
      File: Page: 712 kernel/mpx386.s
06590
             .align 16
06591
      _hwint10:
                           ! Interrupt routine for irq 10
             hwint_slave(10)
06592
06593
06594
             .align 16
06595
     _hwint11:
                           ! Interrupt routine for irg 11
06596
            hwint slave(11)
06597
06598
             .align 16
      _hwint12:
06599
                            ! Interrupt routine for irq 12
06600
             hwint slave(12)
06601
06602
             .align 16
06603
      _hwint13:
                            ! Interrupt routine for irq 13 (FPU exception)
             hwint slave(13)
06604
06605
06606
             .align 16
06607
     _hwint14:
                           ! Interrupt routine for irq 14 (AT winchester)
            hwint_slave(14)
06608
06609
06610
             .align 16
06611
      _hwint15:
                           ! Interrupt routine for irg 15
06612
             hwint_slave(15)
06613
06614
      06615
06616
     06617
      ! Save for protected mode.
06618
      ! This is much simpler than for 8086 mode, because the stack already points
     ! into the process table, or has already been switched to the kernel stack.
06620
06621
             .align 16
06622 save:
06623
             cld
                                 ! set direction flag to a known value
06624
             pushad
                                 ! save "general" registers
         ol6 push ds
06625
                                 ! save ds
         ol6 push
06626
                                 I save es
                    es
06627
         ol6 push
                   fs
                                 ! save fs
06628
         ol6 push
                   as
                                 ! save qs
06629
                                 ! ss is kernel data segment
            mov
                    dx, ss
06630
             mov
                    ds, dx
                                 ! load rest of kernel segments
06631
             mov
                    es, dx
                                 ! kernel does not use fs, qs
06632
             mov
                    eax, esp
                                 ! prepare to return
06633
             incb
                    (_k_reenter)
                                 ! from -1 if not reentering
                                 ! stack is already kernel stack
06634
             jnz
                    set restart1
06635
                    esp, k_stktop
             mov
06636
             push
                    _restart
                                  ! build return address for int handler
06637
                    ebp, ebp
                                 ! for stacktrace
             xor
06638
             jmp
                    RETADR-P_STACKBASE(eax)
06639
06640
             .align
06641 set_restart1:
06642
             push
                    restart1
06643
             jmp
                    RETADR-P STACKBASE(eax)
06644
06645
06646
                               s call
06647 !*============*
06648
             .align 16
06649 s call:
```

```
book.txt
Feb 25, 11 15:18
                                                                Page 76/393
      File: Page: 713 kernel/mpx386.s
06650 _p_s_call:
06651
            cld
                                  ! set direction flag to a known value
                    esp, 6*4
06652
             sub
                                  ! skip RETADR, eax, ecx, edx, ebx, est
06653
                                  ! stack already points into proc table
             push
                   ebp
06654
             push
                   esi
06655
             push
                    edi
         ol6 push
06656
                   ds
06657
         ol6 push
                   es
06658
         ol6 push
                   fs
06659
         ol6 push
                    as
06660
             mov
                    dx, ss
06661
             mov
                    ds, dx
                    es, dx
06662
             mov
06663
             incb
                    (_k_reenter)
                                  ! assumes P STACKBASE == 0
06664
             mov
                    esi, esp
06665
                    esp, k stktop
             mov
06666
                    ebp, ebp
                                  ! for stacktrace
             xor
06667
                                  ! end of inline save
06668
                                  ! now set up parameters for sys_call()
06669
             push
                    ebx
                                 ! pointer to user message
06670
             push
                   eax
                                  ! src/dest
06671
             push
                                 ! SEND/RECEIVE/BOTH
                    ecx
06672
             call
                   _sys_call
                                 ! sys_call(function, src_dest, m_ptr)
06673
                                 ! caller is now explicitly in proc ptr
                   AXREG(esi), eax ! sys_call MUST PRESERVE si
06674
             mov
06675
06676
     ! Fall into code to restart proc/task running.
06677
06678
      |*-----*
06679
                                restart
06680 !*===========*
06681
06682
06683 ! Restart the current process or the next process if it is set.
06684
06685
                    (_next_ptr), 0
                                        ! see if another process is scheduled
06686
                    Ωf
             iz
06687
             mov
                    eax, (_next_ptr)
06688
             mov
                    (_proc_ptr), eax
                                        ! schedule new process
06689
                    (_next_ptr), 0
             mov
06690 0:
                    esp, (_proc_ptr)
                                         ! will assume P_STACKBASE == 0
             mov
                    P LDT SEL(esp)
                                         ! enable process' segment descriptors
06691
06692
             lea
                    eax, P_STACKTOP(esp)
                                        ! arrange for next interrupt
06693
             mov
                    (_tss+TSS3_S_SP0), eax ! to save state in process table
06694 restart1:
06695
            decb
                    ( k reenter)
06696
         ol6 pop
                    gs
06697
         ol6 pop
                    fs
06698
         ol6 pop
                    es
06699
         ol6 pop
                    ds
06700
            popad
06701
             add
                                 ! skip return adr
                    esp, 4
06702
             iretd
                                 ! continue process
06703
06704
      !*-----*
06705
                                 exception handlers
06706 !*===========*
     _divide_error:
06707
06708
            push
                   DIVIDE_VECTOR
06709
             qmp
                   exception
```

Feb 2	5, 11 15:18	bo	ok.txt	Page 77/393
	File: Page: 714	kernel/mpx386.s		
06710	-41-			
06711 06712	_single_step_ex push	ception: DEBUG VECTOR		
06712	pusn qmj	exception		
06714	Juip	CACCPCION		
06715	_nmi:			
6716	_ push	NMI_VECTOR		
6717	jmp	exception		
5718				
719 720	_breakpoint_exc			
721	jmp	BREAKPOINT_VECTOR exception		
722	Juip	exception		
723	_overflow:			
724	_ push	OVERFLOW_VECTOR		
725	jmp	exception		
726				
27	_bounds_check:	DOINING THEMON		
28 29	push	BOUNDS_VECTOR		
730	jmp	exception		
731	_inval_opcode:			
32	push	INVAL_OP_VECTOR		
33	jmp	exception		
34				
35	_copr_not_avail	able:		
36		COPROC_NOT_VECTOR		
37 38	jmp	exception		
39	_double_fault:			
40	push	DOUBLE_FAULT_VECTOR		
41	jmp	errexception		
42				
43	_copr_seg_overr	run:		
44	push	COPROC_SEG_VECTOR		
45 46	jmp	exception		
747	_inval_tss:			
748	push	INVAL_TSS_VECTOR		
749	jmp	errexception		
750				
751	_segment_not_pr			
52	push	SEG_NOT_VECTOR		
53 54	jmp	errexception		
55	_stack_exceptio	on:		
56	push	STACK_FAULT_VECTOR		
57	jmp	errexception		
58				
59	_general_protec			
60	push	PROTECTION_VECTOR		
61 62	jmp	errexception		
762 763	_page_fault:			
64	_page_raurc. push	PAGE_FAULT_VECTOR		
65	jmp	errexception		
66	J 1	-		
67	_copr_error:			
68	push	COPROC_ERR_VECTOR		
69	jmp	exception		

```
book.txt
Feb 25, 11 15:18
                                                   Page 78/393
    File: Page: 715 kernel/mpx386.s
06770
06771 !*=======*
06772 !*
                        exception
06774 ! This is called for all exceptions which do not push an error code.
06775
06776
          .align 16
06777 exception:
06778
                (trap_errno), 0
                               ! clear trap errno
     sseg mov
                (ex_number)
06779
     sseg pop
06780
          jmp
                exception1
06781
06782
    06783
             errexception
06784 !*========*
06785 ! This is called for all exceptions which push an error code.
06786
06787
          .align 16
06788 errexception:
                (ex_number)
06789
     sseg pop
06790
     sseg
                (trap_errno)
         pop
06791
    exception1:
                                 ! Common for all exceptions.
06792
          push
                                ! eax is scratch register
06793
                eax, 0+4(esp)
                                ! old eip
          mov
06794
     sseg
                (old_eip), eax
          mov
                                ! old cs
06795
          movzx
                eax, 4+4(esp)
06796
                (old_cs), eax
     sseg
          mov
                eax, 8+4(esp)
06797
          mov
                                ! old eflags
06798
     sseg
          mov
                (old_eflags), eax
06799
                eax
          gog
06800
          call
                save
                (old_eflags)
06801
          push
06802
          push
                (old_cs)
06803
          push
                (old_eip)
06804
          push
                (trap_errno)
06805
          push
               (ex_number)
06806
          call
               _exception
                                ! (ex_number, trap_errno, old_eip,
06807
                                     old_cs, old_eflags)
06808
          add
                esp, 5*4
06809
          ret.
06810
06811 !*==========*
06812 !*
                       level0 call
06813 !*===========*
06814 _level0_call:
06815
          call
               save
06816
          jmp (_level0_func)
06817
06818 !*========*
06819 !*
                         data
06820 !*========*
06821
06822
    .sect .rom ! Before the string table please
06823
                      ! this must be the first data entry (magic #)
         .data2 0x526F
06824
06825
    .sect .bss
06826 k_stack:
          .space K_STACK_BYTES
                          ! kernel stack
06827
06828 k_stktop:
                            ! top of kernel stack
06829
          .comm ex number, 4
```

```
book.txt
Feb 25, 11 15:18
                                                                 Page 79/393
      File: Page: 716 kernel/mpx386.s
06830
             .comm trap errno, 4
06831
             .comm
                    old_eip, 4
06832
             .comm old_cs, 4
06833
             .comm old_eflags, 4
kernel/start.c
06900 /* This file contains the C startup code for Minix on Intel processors.
06901 * It cooperates with mpx.s to set up a good environment for main().
06902
06903 * This code runs in real mode for a 16 bit kernel and may have to switch
06904 * to protected mode for a 286.
06905 * For a 32 bit kernel this already runs in protected mode, but the selectors
06906 * are still those given by the BIOS with interrupts disabled, so the
06907 * descriptors need to be reloaded and interrupt descriptors made.
06908 */
06909
06910 #include "kernel.h"
06911 #include "protect.h"
06912 #include "proc.h"
06913 #include <stdlib.h>
06914 #include <string.h>
06915
06916 FORWARD PROTOTYPE( char *get value, ( CONST char *params, CONST char *key));
06917 /*=========*
06918 *
                                 cstart
06919 *-----*/
06920 PUBLIC void cstart(cs, ds, mds, parmoff, parmsize)
06921 U16_t cs, ds; /* kernel code and data segment */
06922 U16_t mds;
                                  /* monitor data segment */
06923 U16_t parmoff, parmsize;
                              /* boot parameters offset and length */
06924
06925 /* Perform system initializations prior to calling main(). Most settings are
06926
       * determined with help of the environment strings passed by MINIX' loader.
06927
06928
        char params[128*sizeof(char *)];
                                                /* boot monitor parameters */
06929
        register char *value;
                                                 /* value in key=value pair */
06930
        extern int etext, end;
06931
        /* Decide if mode is protected; 386 or higher implies protected mode.
06932
06933
         * This must be done first, because it is needed for, e.g., seg2phys().
         * For 286 machines we cannot decide on protected mode, yet. This is
06934
06935
         * done below.
06936
06937 #if _WORD_SIZE != 2
06938
        machine.protected = 1;
06939 #endif
06940
        /* Record where the kernel and the monitor are. */
06941
06942
        kinfo.code_base = seg2phys(cs);
06943
        kinfo.code_size = (phys_bytes) &etext;
                                                /* size of code segment */
06944
        kinfo.data_base = seg2phys(ds);
06945
        kinfo.data_size = (phys_bytes) &end;
                                                /* size of data segment */
06946
06947
        /* Initialize protected mode descriptors. */
06948
        prot_init();
06949
```

```
book.txt
Feb 25, 11 15:18
                                                                     Page 80/393
      File: Page: 717 kernel/start.c
06950
        /* Copy the boot parameters to the local buffer. */
06951
        kinfo.params_base = seg2phys(mds) + parmoff;
        kinfo.params_size = MIN(parmsize, sizeof(params)-2);
06952
06953
        phys_copy(kinfo.params_base, vir2phys(params), kinfo.params_size);
06954
06955
        /* Record miscellaneous information for user-space servers. */
06956
        kinfo.nr_procs = NR_PROCS;
06957
        kinfo.nr_tasks = NR_TASKS;
06958
        strncpy(kinfo.release, OS_RELEASE, sizeof(kinfo.release));
06959
        kinfo.release[sizeof(kinfo.release)-1] = '\0';
06960
        strncpy(kinfo.version, OS_VERSION, sizeof(kinfo.version));
06961
        kinfo.version[sizeof(kinfo.version)-1] = '\0';
06962
        kinfo.proc_addr = (vir_bytes) proc;
06963
        kinfo.kmem_base = vir2phys(0);
06964
        kinfo.kmem_size = (phys_bytes) &end;
06965
06966
        /* Processor? 86, 186, 286, 386, ...
06967
         * Decide if mode is protected for older machines.
06968
06969
        machine.processor=atoi(get_value(params, "processor"));
      #if _WORD_SIZE == 2
06970
06971
       machine.protected = machine.processor >= 286;
06972
      #endif
06973
       if (! machine.protected) mon return = 0;
06974
06975
        /* XT, AT or MCA bus? */
        value = get value(params, "bus");
06976
06977
        if (value == NIL_PTR || strcmp(value, "at") == 0) {
                                                   /* PC-AT compatible hardware */
06978
            machine.pc_at = TRUE;
06979
        } else if (strcmp(value, "mca") == 0) {
06980
            machine.pc_at = machine.ps_mca = TRUE;
                                                  /* PS/2 with micro channel */
06981
06982
06983
        /* Type of VDU: */
        value = get_value(params, "video");
06984
                                                  /* EGA or VGA video unit */
        if (strcmp(value, "ega") == 0) machine.vdu_ega = TRUE;
06985
        if (strcmp(value, "vga") == 0) machine.vdu_vga = machine.vdu_ega = TRUE;
06986
06987
06988
        /* Return to assembler code to switch to protected mode (if 286),
06989
         \star reload selectors and call main().
06990
06991
06993
      /*-----*
06994
                                get value
06995
       06996
06997 PRIVATE char *get_value(params, name)
06998
      _CONST char *params;
                                                   /* boot monitor parameters */
06999
       _CONST char *name;
                                                   /* key to look up */
07000
07001
      /* Get environment value - kernel version of getenv to avoid setting up the
       * usual environment array.
07002
07003
07004
       register _CONST char *namep;
07005
        register char *envp;
07006
07007
        for (envp = (char *) params; *envp != 0;) {
07008
             for (namep = name; *namep != 0 && *namep == *envp; namep++, envp++)
07009
```

```
Feb 25, 11 15:18
                                  book.txt
                                                              Page 81/393
      File: Page: 718 kernel/start.c
07010
             if (*namep == '\0' && *envp == '=') return(envp + 1);
07011
             while (*envp++ != 0)
07012
07013
07014
        return(NIL_PTR);
07015 }
kernel/main.c
07100 /* This file contains the main program of MINIX as well as its shutdown code.
07101
      * The routine main() initializes the system and starts the ball rolling by
      * setting up the process table, interrupt vectors, and scheduling each task
07103
       * to run to initialize itself.
07104
       * The routine shutdown() does the opposite and brings down MINIX.
07105
07106
       * The entries into this file are:
       * main:
07107
                          MINIX main program
       * prepare_shutdown: prepare to take MINIX down
07108
07109
07110
      * Changes:
      * Nov 24, 2004 simplified main() with system image (Jorrit N. Herder)
07111
07112
       * Aug 20, 2004 new prepare_shutdown() and shutdown() (Jorrit N. Herder)
07113
07114 #include "kernel.h"
07115 #include <signal.h>
07116 #include <string.h>
07117 #include <unistd.h>
07118 #include <a.out.h>
07119 #include <minix/callnr.h>
07120 #include <minix/com.h>
07121 #include "proc.h"
07122
07123 /* Prototype declarations for PRIVATE functions. */
07124 FORWARD _PROTOTYPE( void announce, (void));
07125
      FORWARD _PROTOTYPE( void shutdown, (timer_t *tp));
07126
07127
     07128
                                main
07129
      PUBLIC void main()
07130
07131
07132 /* Start the ball rolling. */
       struct boot_image *ip;
07133
                                 /* boot image pointer */
07134
        register struct proc *rp;
                                 /* process pointer */
07135
        register struct priv *sp;
                                 /* privilege structure pointer */
07136
        register int i, s;
07137
        int hdrindex;
                                 /* index to array of a.out headers */
07138
        phys clicks text base;
07139
        vir_clicks text_clicks, data_clicks;
07140
        req t ktsb;
                                 /* kernel task stack base */
07141
        struct exec e hdr;
                                 /* for a copy of an a.out header */
07142
        /* Initialize the interrupt controller. */
07143
07144
        intr init(1);
```

```
book.txt
Feb 25, 11 15:18
                                                                           Page 82/393
       File: Page: 719 kernel/main.c
07145
07146
         /* Clear the process table. Anounce each slot as empty and set up mappings
07147
          * for proc_addr() and proc_nr() macros. Do the same for the table with
07148
          * privilege structures for the system processes.
07149
07150
         for (rp = BEG_PROC_ADDR, i = -NR_TASKS; rp < END_PROC_ADDR; ++rp, ++i) {
07151
               rp->p_rts_flags = SLOT_FREE;
                                                       /* initialize free slot */
                                                        /* proc number from ptr */
07152
               rp->p_nr = i;
07153
               (pproc_addr + NR_TASKS)[i] = rp;
                                                        /* proc ptr from number */
07154
07155
         for (sp = BEG_PRIV_ADDR, i = 0; sp < END_PRIV_ADDR; ++sp, ++i) {
07156
               sp->s_proc_nr = NONE;
                                                        /* initialize as free */
               sp->s_id = i;
                                                        /* priv structure index */
07157
                                                        /* priv ptr from number */
07158
               ppriv_addr[i] = sp;
07159
07160
07161
         /st Set up proc table entries for tasks and servers. The stacks of the
07162
          * kernel tasks are initialized to an array in data space. The stacks
07163
          * of the servers have been added to the data segment by the monitor, so
07164
          * the stack pointer is set to the end of the data segment. All the
07165
          * processes are in low memory on the 8086. On the 386 only the kernel
07166
          * is in low memory, the rest is loaded in extended memory.
07167
07168
07169
         /* Task stacks. */
07170
         ktsb = (reg_t) t_stack;
07171
07172
         for (i=0; i < NR_BOOT_PROCS; ++i) {
07173
               ip = &image[i];
                                                        /* process' attributes */
07174
               rp = proc addr(ip->proc nr);
                                                        /* get process pointer */
07175
               rp->p_max_priority = ip->priority;
                                                        /* max scheduling priority */
07176
               rp->p_priority = ip->priority;
                                                        /* current priority */
07177
               rp->p_quantum_size = ip->quantum;
                                                       /* quantum size in ticks */
07178
               rp->p_ticks_left = ip->quantum;
                                                        /* current credit */
               strncpy(rp->p_name, ip->proc_name, P_NAME_LEN); /* set process name */
07179
               (void) get_priv(rp, (ip->flags & SYS_PROC)); /* assign structure */
07180
               priv(rp)->s_flags = ip->flags;
07181
                                                                /* process flags */
07182
                                                                /* allowed traps */
               priv(rp)->s_trap_mask = ip->trap_mask;
07183
               priv(rp)->s_call_mask = ip->call_mask;
                                                              /* kernel call mask */
               priv(rp)->s_ipc_to.chunk[0] = ip->ipc_to;
                                                               /* restrict targets */
07184
               if (iskerneln(proc_nr(rp))) {
    if (ip->stksize > 0) {
                                                       /* part of the kernel? */
07185
                                                        /* HARDWARE stack size is 0 */
07186
                               rp->p_priv->s_stack_guard = (reg_t *) ktsb;
07187
07188
                                *rp->p_priv->s_stack_guard = STACK_GUARD;
07189
07190
                       ktsb += ip->stksize;    /* point to high end of stack */
rp->p_reg.sp = ktsb;    /* this task's initial stack ptr */
07191
                       text_base = kinfo.code_base >> CLICK_SHIFT;
07192
07193
                                                /* processes that are in the kernel */
07194
                       hdrindex = 0;
                                                /* all use the first a.out header */
07195
               } else
07196
                       hdrindex = 1 + i-NR_TASKS;
                                                       /* servers, drivers, INIT */
07197
07198
07199
               /* The bootstrap loader created an array of the a.out headers at
07200
                * absolute address 'aout'. Get one element to e_hdr.
07201
07202
               phys_copy(aout + hdrindex * A_MINHDR, vir2phys(&e_hdr),
                                                         (phys_bytes) A_MINHDR);
07203
07204
               /* Convert addresses to clicks and build process memory map */
```

```
book.txt
Feb 25, 11 15:18
                                                                     Page 83/393
      File: Page: 720 kernel/main.c
07205
              text_base = e_hdr.a_syms >> CLICK_SHIFT;
07206
              text_clicks = (e_hdr.a_text + CLICK_SIZE-1) >> CLICK_SHIFT;
              if (!(e_hdr.a_flags & A_SEP)) text_clicks = 0; /* common I&D */
07207
07208
              data_clicks = (e_hdr.a_total + CLICK_SIZE-1) >> CLICK_SHIFT;
07209
              rp->p_memmap[T].mem_phys = text_base;
07210
              rp->p_memmap[T].mem_len = text_clicks;
07211
              rp->p_memmap[D].mem_phys = text_base + text_clicks;
              rp->p_memmap[D].mem_len = data_clicks;
07212
              rp->p_memmap[S].mem_phys = text_base + text_clicks + data_clicks;
07213
07214
              rp->p_memmap[S].mem_vir = data_clicks; /* empty - stack is in data */
07215
07216
              /* Set initial register values. The processor status word for tasks
               * is different from that of other processes because tasks can
07217
               * access I/O; this is not allowed to less-privileged processes
07218
07219
07220
              rp->p_reg.pc = (reg_t) ip->initial_pc;
07221
              rp->p_reg.psw = (iskernelp(rp)) ? INIT_TASK_PSW : INIT_PSW;
07222
07223
              /* Initialize the server stack pointer. Take it down one word
07224
               * to give crtso.s something to use as "argc".
07225
07226
              if (isusern(proc_nr(rp))) {
                                                    /* user-space process? */
                     rp->p_reg.sp = (rp->p_memmap[S].mem_vir +
07227
07228
                                    rp->p_memmap[S].mem_len) << CLICK_SHIFT;
07229
                     rp->p_reg.sp -= sizeof(reg_t);
07230
07231
07232
              /* Set ready. The HARDWARE task is never ready. */
07233
              if (rp->p_nr != HARDWARE) {
                     rp->p rts flags = 0;
                                                    /* runnable if no flags */
07234
07235
                                                   /* add to scheduling queues */
                     lock_enqueue(rp);
07236
              } else {
07237
                     rp->p_rts_flags = NO_MAP;
                                                   /* prevent from running */
07238
07239
07240
              /* Code and data segments must be allocated in protected mode. */
07241
              alloc_segments(rp);
07242
07243
07244
        /* We're definitely not shutting down. */
07245
        shutdown started = 0;
07246
07247
        /* MINIX is now ready. All boot image processes are on the ready queue.
07248
         * Return to the assembly code to start running the current process.
07249
07250
        bill_ptr = proc_addr(IDLE);
                                            /* it has to point somewhere */
07251
        announce();
                                            /* print MINIX startup banner */
07252
        restart();
07253
07255
      07256
                                    announce
       *----*
07257
07258
      PRIVATE void announce(void)
07259
07260
         /* Display the MINIX startup banner. */
        kprintf("MINIX %s.%s."
07261
            "Copyright 2006, Vrije Universiteit, Amsterdam, The Netherlands\n",
07262
07263
            OS_RELEASE, OS_VERSION);
07264
```

```
book.txt
 Feb 25, 11 15:18
                                                                                                                              Page 84/393
            File: Page: 721 kernel/main.c
07265
               /* Real mode, or 16/32-bit protected mode? */
07266
               kprintf("Executing in %s mode.\n\n",
07267
                      machine.protected ? "32-bit protected" : "real");
07268
07270 /*=========*
                                                              prepare_shutdown
07271
07272
            *========*/
07273 PUBLIC void prepare_shutdown(how)
07274
            int how;
07275
07276
            /* This function prepares to shutdown MINIX. */
               static timer_t shutdown_timer;
07277
07278
               register struct proc *rp;
07279
               message m;
07280
07281
               /st Show debugging dumps on panics. Make sure that the TTY task is still
07282
                 * available to handle them. This is done with help of a non-blocking send.
07283
                 * We rely on TTY to call sys_abort() when it is done with the dumps.
07284
07285
               if (how == RBT_PANIC) {
07286
                      m.m_type = PANIC_DUMPS;
                      if (nb_send(TTY_PROC_NR,&m)==OK) /* don't block if TTY isn't ready */
07287
07288
                                                                                /* await sys abort() from TTY */
07289
07290
07291
               /* Send a signal to all system processes that are still alive to inform
                 * them that the MINIX kernel is shutting down. A proper shutdown sequence
07292
                 * should be implemented by a user-space server. This mechanism is useful
07293
07294
                 * as a backup in case of system panics, so that system processes can still
07295
                 * run their shutdown code, e.g, to synchronize the FS or to let the TTY
07296
                 * switch to the first console.
07297
                \begin{tabular}{ll} \be
07298
07299
               for (rp=BEG_PROC_ADDR; rp<END_PROC_ADDR; rp++) {
07300
                      if (!isemptyp(rp) && (priv(rp)->s_flags & SYS_PROC) && !iskernelp(rp))
07301
                             send_sig(proc_nr(rp), SIGKSTOP);
07302
07303
07304
               /* We're shutting down. Diagnostics may behave differently now. */
07305
               shutdown started = 1;
07306
07307
               /* Notify system processes of the upcoming shutdown and allow them to be
07308
                 * scheduled by setting a watchog timer that calls shutdown(). The timer
07309
                 * argument passes the shutdown status.
07310
07311
               kprintf("MINIX will now be shut down ...\n");
07312
               tmr_arg(&shutdown_timer)->ta_int = how;
07313
07314
               /* Continue after 1 second, to give processes a chance to get
07315
                 * scheduled to do shutdown work.
07316
07317
               set_timer(&shutdown_timer, get_uptime() + HZ, shutdown);
07318
07320
07321
                                                                shutdown
07322
             07323 PRIVATE void shutdown(tp)
07324 timer t *tp;
```

```
book.txt
 Feb 25, 11 15:18
                                                                     Page 85/393
       File: Page: 722 kernel/main.c
07325
07326
       /* This function is called from prepare_shutdown or stop_sequence to bring
07327
       * down MINIX. How to shutdown is in the argument: RBT_HALT (return to the
07328
        * monitor), RBT_MONITOR (execute given code), RBT_RESET (hard reset).
07329
07330
        int how = tmr_arg(tp)->ta_int;
        ul6_t magic;
07331
07332
07333
         /* Now mask all interrupts, including the clock, and stop the clock. */
07334
        outb(INT_CTLMASK, ~0);
07335
        clock stop();
07336
07337
        if (mon_return && how != RBT_RESET) {
07338
              /* Reinitialize the interrupt controllers to the BIOS defaults. */
07339
              intr init(0);
07340
              outb(INT CTLMASK, 0);
07341
              outb(INT2_CTLMASK, 0);
07342
07343
              /* Return to the boot monitor. Set the program if not already done. */
07344
              if (how != RBT_MONITOR) phys_copy(vir2phys(""), kinfo.params_base, 1);
07345
07346
07347
07348
         /* Reset the system by jumping to the reset address (real mode), or by
         * forcing a processor shutdown (protected mode). First stop the BIOS
07349
07350
          * memory test by setting a soft reset flag.
07351
07352
         magic = STOP_MEM_CHECK;
         phys_copy(vir2phys(&magic), SOFT_RESET_FLAG_ADDR, SOFT_RESET_FLAG_SIZE);
07353
07354
         level0(reset);
07355
kernel/proc.c
07400 /* This file contains essentially all of the process and message handling.
       * Together with "mpx.s" it forms the lowest layer of the MINIX kernel.
        * There is one entry point from the outside:
07402
07403
07404
                            a system call, i.e., the kernel is trapped with an INT
07405
07406
        * As well as several entry points used from the interrupt and task level:
07407
07408
           lock notify:
                            notify a process of a system event
07409
           lock_send:
                            send a message to a process
07410
           lock_enqueue:
                            put a process on one of the scheduling queues
07411
           lock_dequeue:
                            remove a process from the scheduling queues
07412
07413
         Changes:
07414
           Aug 19, 2005
                           rewrote scheduling code (Jorrit N. Herder)
07415
           Jul 25, 2005
                           rewrote system call handling (Jorrit N. Herder)
07416
           May 26, 2005
                           rewrote message passing functions (Jorrit N. Herder)
                           new notification system call (Jorrit N. Herder)
07417
           May 24, 2005
07418
           Oct 28, 2004
                           nonblocking send and receive calls (Jorrit N. Herder)
07419
```

```
book.txt
Feb 25, 11 15:18
                                                                          Page 86/393
       File: Page: 723 kernel/proc.c
07420
         The code here is critical to make everything work and is important for the
07421
         overall performance of the system. A large fraction of the code deals with
        * list manipulation. To make this both easy to understand and fast to execute
07422
07423
         pointer pointers are used throughout the code. Pointer pointers prevent
07424
          exceptions for the head or tail of a linked list.
07425
07426
          node_t *queue, *new_node;
node_t **xpp = &queue;
                                       // assume these as global variables
07427
                                       // get pointer pointer to head of queue
          while (*xpp != NULL)
                                       // find last pointer of the linked list
07428
07429
              xpp = &(*xpp)->next;
                                       // get pointer to next pointer
07430
           *xpp = new node;
                                       // now replace the end (the NULL pointer)
07431
          new node->next = NULL;
                                       // and mark the new end of the list
07432
       * For example, when adding a new node to the end of the list, one normally
07433
       * makes an exception for an empty list and looks up the end of the list for
07434
07435
        * nonempty lists. As shown above, this is not required with pointer pointers.
07436
07437
07438 #include <minix/com.h>
07439 #include <minix/callnr.h>
07440 #include "kernel.h"
07441 #include "proc.h"
07442
07443 /* Scheduling and message passing functions. The functions are available to
07444
       * other parts of the kernel through lock_...(). The lock temporarily disables
       * interrupts to prevent race conditions.
07445
07446
07447 FORWARD _PROTOTYPE( int mini_send, (struct proc *caller_ptr, int dst,
07448
                       message *m_ptr, unsigned flags) );
      FORWARD PROTOTYPE( int mini receive, (struct proc *caller ptr, int src,
07449
07450
                      message *m_ptr, unsigned flags) );
07451 FORWARD _PROTOTYPE( int mini_notify, (struct proc *caller_ptr, int dst) );
07452
07453 FORWARD _PROTOTYPE( void enqueue, (struct proc *rp) );
07454
      FORWARD _PROTOTYPE( void dequeue, (struct proc *rp) );
07455 FORWARD _PROTOTYPE( void sched, (struct proc *rp, int *queue, int *front) );
07456 FORWARD _PROTOTYPE( void pick_proc, (void) );
07457
07458
       #define BuildMess(m_ptr, src, dst_ptr) \
07459
               (m_ptr)->m_source = (src);
07460
               (m_ptr)->m_type = NOTIFY_FROM(src);
               (m_ptr)->NOTIFY_TIMESTAMP = get_uptime();
07461
07462
               switch (src)
07463
               case HARDWARE:
                       (m ptr)->NOTIFY ARG = priv(dst ptr)->s int pending;
07464
07465
                       priv(dst_ptr)->s_int_pending = 0;
07466
                       break;
07467
07468
                       (m_ptr)->NOTIFY_ARG = priv(dst_ptr)->s_sig_pending;
07469
                       priv(dst_ptr)->s_sig_pending = 0;
07470
07471
07472
       #define CopyMess(s,sp,sm,dp,dm) \
07473
07474
               cp_mess(s, (sp)->p_memmap[D].mem_phys,
07475
                        (vir_bytes)sm, (dp)->p_memmap[D].mem_phys, (vir_bytes)dm)
07476
```

```
book.txt
Feb 25, 11 15:18
                                                                        Page 87/393
       File: Page: 724 kernel/proc.c
      /*========*
07478
                                     sys_call
07479
      07480 PUBLIC int sys_call(call_nr, src_dst, m_ptr)
07481 int call_nr;
                                      /* system call number and flags */
07482 int src dst;
                                      /* src to receive from or dst to send to */
                                      /* pointer to message in the caller's space */
07483 message *m ptr;
07484
07485 /* System calls are done by trapping to the kernel with an INT instruction.
07486
       * The trap is caught and sys_call() is called to send or receive a message
        * (or both). The caller is always given by 'proc_ptr'.
07487
07488
07489
        register struct proc *caller_ptr = proc_ptr; /* get pointer to caller */
int function = call_nr & SYSCALL_FUNC; /* get system call function
                                                      /* get system call function */
07490
                                                      /* get flags */
07491
         unsigned flags = call nr & SYSCALL FLAGS;
07492
         int mask entry;
                                                      /* bit to check in send mask */
07493
         int result;
                                                      /* the system call's result */
07494
         vir_clicks vlo, vhi;
                                    /* virtual clicks containing message to send */
07495
07496
         /* Check if the process has privileges for the requested call. Calls to the
07497
          * kernel may only be SENDREC, because tasks always reply and may not block
07498
          * if the caller doesn't do receive().
07499
07500
         if (! (priv(caller_ptr)->s_trap_mask & (1 << function)) ||
                 (iskerneln(src_dst) && function != SENDREC
07501
07502
                  && function != RECEIVE)) {
07503
             kprintf("sys call: trap %d not allowed, caller %d, src dst %d\n",
07504
                 function, proc_nr(caller_ptr), src_dst);
07505
                                              /* trap denied by mask or kernel */
             return(ECALLDENIED);
07506
07507
07508
         /* Require a valid source and/ or destination process, unless echoing. */
07509
         if (! (isokprocn(src_dst) | | src_dst == ANY | | function == ECHO)) {
             kprintf("sys_call: invalid src_dst, src_dst %d, caller %d\n",
07510
07511
                 src_dst, proc_nr(caller_ptr));
07512
             return(EBADSRCDST);
                                              /* invalid process number */
07513
07514
07515
         /* If the call involves a message buffer, i.e., for SEND, RECEIVE, SENDREC,
07516
           or ECHO, check the message pointer. This check allows a message to be
07517
           anywhere in data or stack or gap. It will have to be made more elaborate
07518
          * for machines which don't have the gap mapped.
07519
07520
         if (function & CHECK_PTR) {
07521
             vlo = (vir bytes) m ptr >> CLICK SHIFT;
             vhi = ((vir_bytes) m_ptr + MESS_SIZE - 1) >> CLICK_SHIFT;
07522
07523
             if (vlo < caller_ptr->p_memmap[D].mem_vir || vlo > vhi ||
07524
                     vhi >= caller_ptr->p_memmap[S].mem_vir +
                 caller_ptr->p_memmap[S].mem_len) {
kprintf("sys_call: invalid message pointer, trap %d, caller %d\n",
07525
07526
07527
                      function, proc_nr(caller_ptr));
07528
                 return(EFAULT);
                                              /* invalid message pointer */
07529
07530
07531
         /* If the call is to send to a process, i.e., for SEND, SENDREC or NOTIFY,
07532
07533
          * verify that the caller is allowed to send to the given destination and
07534
          * that the destination is still alive.
07535
07536
         if (function & CHECK DST) {
```

```
book.txt
Feb 25, 11 15:18
                                                                       Page 88/393
      File: Page: 725 kernel/proc.c
07537
            if (! get_sys_bit(priv(caller_ptr)->s_ipc_to, nr_to_id(src_dst))) {
07538
                kprintf("sys\_call: ipc mask denied %d sending to %d\n",
                      proc_nr(caller_ptr), src_dst);
07539
07540
                return(ECALLDENIED);
                                             /* call denied by ipc mask */
07541
07542
            if (isemptyn(src_dst) && !shutdown_started) {
   kprintf("sys_call: dead dest; %d, %d, %d\n",
07543
07544
                    function, proc_nr(caller_ptr), src_dst);
07545
                return(EDEADDST);
07546
                                             /* cannot send to the dead */
07547
07548
07549
        /* Now check if the call is known and try to perform the request. The only
07550
07551
         * system calls that exist in MINIX are sending and receiving messages.
07552
            - SENDREC: combines SEND and RECEIVE in a single system call
           - SEND:
07553
                         sender blocks until its message has been delivered
         * - RECEIVE: receiver blocks until an acceptable message has arrived
07554
07555
             - NOTIFY: nonblocking call; deliver notification or mark pending
           - ECHO:
07556
                         nonblocking call; directly echo back the message
07557
07558
        switch(function) {
07559
        case SENDREC:
07560
            /* A flag is set so that notifications cannot interrupt SENDREC. */
07561
            priv(caller_ptr)->s_flags |= SENDREC_BUSY;
07562
            /* fall through */
07563
07564
            result = mini_send(caller_ptr, src_dst, m_ptr, flags);
if (function == SEND || result != OK) {
07565
07566
                                                      /* done, or SEND failed */
                break;
07567
                                                     /* fall through for SENDREC */
07568
        case RECEIVE:
07569
            if (function == RECEIVE)
07570
                priv(caller_ptr)->s_flags &= ~SENDREC_BUSY;
07571
            result = mini_receive(caller_ptr, src_dst, m_ptr, flags);
07572
07573
        case NOTIFY:
07574
            result = mini_notify(caller_ptr, src_dst);
07575
07576
        case ECHO:
07577
            CopyMess(caller_ptr->p_nr, caller_ptr, m_ptr, caller_ptr, m_ptr);
07578
            result = OK;
07579
            break;
07580
        default:
07581
            result = EBADCALL;
                                                     /* illegal system call */
07582
07583
07584
        /* Now, return the result of the system call to the caller. */
07585
        return(result);
07586
07588
      07589
                                    mini send
       *===========*/
07591 PRIVATE int mini_send(caller_ptr, dst, m_ptr, flags)
07592
      register struct proc *caller_ptr; /* who is trying to send a message? */
                                             /* to whom is message being sent? */
07593 int dst;
07594
      message *m ptr;
                                             /* pointer to message buffer */
      unsigned flags;
                                             /* system call flags */
07595
07596
```

```
book.txt
Feb 25, 11 15:18
                                                                   Page 89/393
      File: Page: 726 kernel/proc.c
      /* Send a message from 'caller ptr' to 'dst'. If 'dst' is blocked waiting
07598
      * for this message, copy the message to it and unblock 'dst'. If 'dst' is
       * not waiting at all, or is waiting for another source, queue 'caller_ptr'.
07600
07601
        register struct proc *dst_ptr = proc_addr(dst);
07602
        register struct proc **xpp;
07603
        register struct proc *xp;
07604
        /* Check for deadlock by 'caller ptr' and 'dst' sending to each other. */
07605
07606
        xp = dst_ptr;
07607
        while (xp->p_rts_flags & SENDING) {
                                                  /* check while sending */
07608
             xp = proc addr(xp->p sendto);
                                                  /* get xp's destination */
07609
              if (xp == caller_ptr) return(ELOCKED); /* deadlock if cyclic */
07610
07611
07612
        /* Check if 'dst' is blocked waiting for this message. The destination's
07613
         * SENDING flag may be set when its SENDREC call blocked while sending.
07614
07615
        07616
07617
              /* Destination is indeed waiting for this message. */
07618
              CopyMess(caller_ptr->p_nr, caller_ptr, m_ptr, dst_ptr,
07619
                      dst_ptr->p_messbuf);
              if ((dst ptr->p rts flags &= ~RECEIVING) == 0) enqueue(dst ptr);
07620
07621
        } else if ( ! (flags & NON_BLOCKING)) {
07622
              /* Destination is not waiting. Block and dequeue caller. */
              caller ptr->p messbuf = m ptr;
07623
07624
              if (caller_ptr->p_rts_flags == 0) dequeue(caller_ptr);
              caller_ptr->p_rts_flags |= SENDING;
07625
07626
              caller ptr->p sendto = dst;
07627
07628
              /* Process is now blocked. Put in on the destination's queue. */
07629
              xpp = &dst_ptr->p_caller_q;
                                             /* find end of list */
07630
              while (*xpp != NIL_PROC) xpp = &(*xpp)->p_q_link;
07631
              *xpp = caller_ptr;
                                                  /* add caller to end */
                                                  /* mark new end of list */
07632
              caller_ptr->p_q_link = NIL_PROC;
        } else {
07633
07634
             return(ENOTREADY);
07635
07636
        return(OK);
07637
07639
      /*=======*
07640
                                  mini_receive
      07642 PRIVATE int mini receive(caller ptr, src, m ptr, flags)
07643 register struct proc *caller_ptr;
                                           /* process trying to get message */
                                           /* which message source is wanted */
07644 int src;
07645 message *m_ptr;
                                           /* pointer to message buffer */
07646 unsigned flags;
                                           /* system call flags */
07647
07648 /* A process or task wants to get a message. If a message is already queued,
      * acquire it and deblock the sender. If no message from the desired source
07649
       * is available block the caller, unless the flags don't allow blocking.
07650
07651
07652
        register struct proc **xpp;
07653
        register struct notification **ntf q pp;
07654
        message m;
07655
        int bit_nr;
07656
        sys_map_t *map;
```

```
book.txt
Feb 25, 11 15:18
                                                                          Page 90/393
       File: Page: 727 kernel/proc.c
07657
         bitchunk t *chunk;
07658
         int i, src_id, src_proc_nr;
07659
07660
         /* Check to see if a message from desired source is already available.
          * The caller's SENDING flag may be set if SENDREC couldn't send. If it is
07661
07662
          * set, the process should be blocked.
07663
07664
         if (!(caller_ptr->p_rts_flags & SENDING)) {
07665
07666
           /* Check if there are pending notifications, except for SENDREC. */
07667
           if (! (priv(caller_ptr)->s_flags & SENDREC_BUSY)) {
07668
07669
               map = &priv(caller_ptr)->s_notify_pending;
07670
               for (chunk=&map->chunk[0]; chunk<&map->chunk[NR_SYS_CHUNKS]; chunk++) {
07671
07672
                   /* Find a pending notification from the requested source. */
07673
                   if (! *chunk) continue;
                                                               /* no bits in chunk */
                                                               /* look up the bit */
07674
                   for (i=0; ! (*chunk & (1<<i)); ++i) {}
07675
                   src_id = (chunk - &map->chunk[0]) * BITCHUNK_BITS + i;
07676
                   if (src_id >= NR_SYS_PROCS) break;
                                                               /* out of range */
                                                                /* get source proc */
07677
                   src_proc_nr = id_to_nr(src_id);
07678
                   if (src!=ANY && src!=src_proc_nr) continue; /* source not ok */
                                                               /* no longer pending */
07679
                   *chunk &= ~(1 << i);
07680
07681
                   /* Found a suitable source, deliver the notification message. */
07682
                   BuildMess(&m, src_proc_nr, caller_ptr);  /* assemble message */
                   CopyMess(src_proc_nr, proc_addr(HARDWARE), &m, caller_ptr, m_ptr);
07683
07684
                   return(OK);
                                                               /* report success */
07685
07686
07687
07688
           /* Check caller queue. Use pointer pointers to keep code simple. */
07689
           xpp = &caller_ptr->p_caller_q;
           while (*xpp != NIL_PROC) {
07690
               if (src == ANY || src == proc_nr(*xpp)) {
07691
07692
                   /* Found acceptable message. Copy it and update status. */
07693
                   CopyMess((*xpp)->p_nr, *xpp, (*xpp)->p_messbuf, caller_ptr, m_ptr);
07694
                   if (((*xpp)->p_rts_flags &= ~SENDING) == 0) enqueue(*xpp);
07695
                   *xpp = (*xpp)->p_q_link;
                                                       /* remove from queue */
07696
                   return(OK);
                                                       /* report success */
07697
07698
               xpp = &(*xpp) -> p q link;
                                                       /* proceed to next */
07699
07700
07701
07702
         /* No suitable message is available or the caller couldn't send in SENDREC.
07703
          * Block the process trying to receive, unless the flags tell otherwise.
07704
07705
         if ( ! (flags & NON_BLOCKING))
07706
             caller_ptr->p_getfrom = src;
07707
             caller_ptr->p_messbuf = m_ptr;
             if (caller_ptr->p_rts_flags == 0) dequeue(caller_ptr);
07708
07709
             caller_ptr->p_rts_flags |= RECEIVING;
07710
             return(OK);
07711
         } else {
07712
             return(ENOTREADY);
07713
07714 }
```

```
book.txt
Feb 25, 11 15:18
                                                                 Page 91/393
      File: Page: 728 kernel/proc.c
07716 /*==========*
07717
                                mini_notify
07718
     07719 PRIVATE int mini_notify(caller_ptr, dst)
07720 register struct proc *caller_ptr;
                                         /* sender of the notification */
07721 int dst;
                                         /* which process to notify */
07722 {
07723
        register struct proc *dst_ptr = proc_addr(dst);
07724
                                        /* source id for late delivery */
07725
                                         /* the notification message */
        message m;
07726
07727
        /* Check to see if target is blocked waiting for this message. A process
07728
        * can be both sending and receiving during a SENDREC system call.
07729
07730
        if ((dst ptr->p rts flags & (RECEIVING|SENDING)) == RECEIVING &&
07731
           ! (priv(dst_ptr)->s_flags & SENDREC_BUSY) &&
            (dst_ptr->p_getfrom == ANY || dst_ptr->p_getfrom == caller_ptr->p_nr)) {
07732
07733
07734
           /* Destination is indeed waiting for a message. Assemble a notification
07735
            * message and deliver it. Copy from pseudo-source HARDWARE, since the
07736
            * message is in the kernel's address space.
07737
07738
           BuildMess(&m, proc_nr(caller_ptr), dst_ptr);
07739
           CopyMess(proc_nr(caller_ptr), proc_addr(HARDWARE), &m,
07740
               dst_ptr, dst_ptr->p_messbuf);
07741
            dst_ptr->p_rts_flags &= ~RECEIVING;
                                                /* deblock destination */
07742
           if (dst_ptr->p_rts_flags == 0) enqueue(dst_ptr);
07743
           return(OK);
07744
07745
07746
        /* Destination is not ready to receive the notification. Add it to the
07747
        * bit map with pending notifications. Note the indirectness: the system id
07748
         * instead of the process number is used in the pending bit map.
07749
07750
        src_id = priv(caller_ptr)->s_id;
07751
        set_sys_bit(priv(dst_ptr)->s_notify_pending, src_id);
07752
        return(OK);
07753 }
07755 /*==========*
07756
                                 lock notify
07758 PUBLIC int lock_notify(src, dst)
                                  /* sender of the notification */
07759 int src;
07760 int dst;
                                  /* who is to be notified */
07761
07763 * is explicitly given to prevent confusion where the call comes from. MINIX
07764
       * kernel is not reentrant, which means to interrupts are disabled after
07765
       * the first kernel entry (hardware interrupt, trap, or exception). Locking
07766
       * is done by temporarily disabling interrupts.
07767
07768
       int result;
07769
07770
        /* Exception or interrupt occurred, thus already locked. */
07771
        if (k reenter >= 0) {
07772
           result = mini notify(proc addr(src), dst);
07773
07774
07775
       /* Call from task level, locking is required. */
```

```
book.txt
Feb 25, 11 15:18
                                                                Page 92/393
      File: Page: 729 kernel/proc.c
07776
       else {
07777
           lock(0, "notify");
           result = mini_notify(proc_addr(src), dst);
07778
07779
           unlock(0);
07780
07781
       return(result);
07782 }
07784 /*========*
07785
                               enqueue
07786
      *-----*/
07787 PRIVATE void enqueue(rp)
07788 register struct proc *rp;
                                /* this process is now runnable */
07789
07790
     /* Add 'rp' to one of the queues of runnable processes. This function is
07791
      * responsible for inserting a process into one of the scheduling queues.
07792
       * The mechanism is implemented here. The actual scheduling policy is
07793
      * defined in sched() and pick_proc().
07794
07795
                                               /* scheduling queue to use */
       int q;
07796
       int front;
                                                /* add to front or back */
07797
07798
        /* Determine where to insert to process. */
07799
        sched(rp, &q, &front);
07800
07801
        /* Now add the process to the queue. */
       if (rdy_head[q] == NIL_PROC) {
                                               /* add to empty gueue */
07802
           rdy_head[q] = rdy_tail[q] = rp;
07803
                                               /* create a new queue */
                                               /* mark new end */
07804
           rp->p_nextready = NIL_PROC;
07805
07806
       else if (front) {
                                               /* add to head of queue */
07807
           rp->p_nextready = rdy_head[q];
                                               /* chain head of queue */
07808
           rdy_head[q] = rp;
                                               /* set new queue head */
07809
07810
                                               /* add to tail of queue */
           rdy_tail[q]->p_nextready = rp;
                                               /* chain tail of queue */
07811
           rdy_tail[q] = rp;
07812
                                               /* set new queue tail */
07813
           rp->p_nextready = NIL_PROC;
                                               /* mark new end */
07814
07815
07816
        /* Now select the next process to run. */
07817
       pick proc();
07818
07820 /*========*
07821
                                 dequeue
07822
      *-----*/
07823 PRIVATE void dequeue(rp)
07824 register struct proc *rp;
                             /* this process is no longer runnable */
07825
07826
     /* A process must be removed from the scheduling queues, for example, because
07827
      * it has blocked. If the currently active process is removed, a new process
      * is picked to run by calling pick_proc().
07828
07829
07830
       register int q = rp->p_priority;
                                               /* queue to use */
                                               /* iterate over queue */
07831
        register struct proc **xpp;
       register struct proc *prev xp;
07832
07833
        /* Side-effect for kernel: check if the task's stack still is ok? */
07834
07835
       if (iskernelp(rp)) {
```

```
book.txt
Feb 25, 11 15:18
                                                                      Page 93/393
      File: Page: 730 kernel/proc.c
07836
              if (*priv(rp)->s stack quard != STACK GUARD)
07837
                     panic("stack overrun by task", proc_nr(rp));
07838
07839
07840
        /* Now make sure that the process is not in its ready queue. Remove the
07841
         * process if it is found. A process can be made unready even if it is not
07842
         * running by being sent a signal that kills it.
07843
07844
        prev xp = NIL PROC;
07845
        for (xpp = &rdy_head[q]; *xpp != NIL_PROC; xpp = &(*xpp)->p_nextready) {
07846
07847
            if (*xpp == rp) {
                                                    /* found process to remove */
07848
                *xpp = (*xpp)->p_nextready;
                                                   /* replace with next chain */
                                                    /* queue tail removed */
07849
                if (rp == rdy_tail[q])
07850
                    rdy tail[q] = prev xp;
                                                    /* set new tail */
07851
                if (rp == proc_ptr || rp == next_ptr) /* active process removed */
07852
                    pick_proc();
                                                    /* pick new process to run */
07853
                break;
07854
07855
            prev_xp = *xpp;
                                                    /* save previous in chain */
07856
07857 }
07859 /*=========*
07860
                                  sched
07861
       *========*/
07862 PRIVATE void sched(rp, queue, front)
07863
      register struct proc *rp;
                                                    /* process to be scheduled */
                                                   /* return: queue to use */
07864
      int *queue;
07865 int *front;
                                                    /* return: front or back */
07866
07867 /* This function determines the scheduling policy. It is called whenever a
      * process must be added to one of the scheduling queues to decide where to
07869
       * insert it. As a side-effect the process' priority may be updated.
07870
07871
        static struct proc *prev_ptr = NIL_PROC;
                                                    /* previous without time */
07872
        int time_left = (rp->p_ticks_left > 0);
                                                    /* quantum fully consumed */
07873
        int penalty = 0;
                                                    /* change in priority */
07874
07875
        / \, ^{\star} Check whether the process has time left. Otherwise give a new quantum
         * and possibly raise the priority. Processes using multiple quantums
07876
07877
         * in a row get a lower priority to catch infinite loops in high priority
07878
         * processes (system servers and drivers).
07879
07880
        if (! time left) {
                                                    /* quantum consumed ? */
07881
            rp->p_ticks_left = rp->p_quantum_size;
                                                    /* give new quantum */
                                                    /* catch infinite loops */
07882
            if (prev_ptr == rp) penalty ++;
            else penalty --;
07883
                                                    /* give slow way back */
07884
            prev_ptr = rp;
                                                    /* store ptr for next */
07885
07886
07887
        /* Determine the new priority of this process. The bounds are determined
07888
         * by IDLE's queue and the maximum priority of this process. Kernel tasks
07889
         * and the idle process are never changed in priority.
07890
        if (penalty != 0 && ! iskernelp(rp)) {
07891
07892
            rp->p priority += penalty;
                                                    /* update with penalty */
07893
            if (rp->p_priority < rp->p_max_priority) /* check upper bound */
07894
                rp->p_priority=rp->p_max_priority;
07895
            else if (rp->p priority > IDLE 0-1)
                                                    /* check lower bound */
```

```
book.txt
Feb 25, 11 15:18
                                                           Page 94/393
     File: Page: 731 kernel/proc.c
07896
             rp->p_priority = IDLE_Q-1;
07897
07898
07899
       /* If there is time left, the process is added to the front of its queue,
07900
        * so that it can immediately run. The queue to use simply is always the
07901
       * process' current priority.
07902
07903
       *queue = rp->p_priority;
       *front = time left;
07904
07905
     /*-----*
07908
                             pick proc
07909
      *=======*,
07910 PRIVATE void pick proc()
07911
07912
     /* Decide who to run now. A new process is selected by setting 'next_ptr'.
07913
      * When a billable process is selected, record it in 'bill_ptr', so that the
07914
      * clock task can tell who to bill for system time.
07915
07916
       register struct proc *rp;
                                            /* process to run */
07917
       int q;
                                            /* iterate over queues */
07918
07919
       /* Check each of the scheduling queues for ready processes. The number of
07920
       * queues is defined in proc.h, and priorities are set in the image table.
        * The lowest queue contains IDLE, which is always ready.
07921
07922
07923
       for (q=0; q < NR\_SCHED\_QUEUES; q++) {
          if ((rp = rdy_head[q]) != NIL_PROC) {
07924
07925
             next ptr = rp;
                                            /* run process 'rp' next */
             if (priv(rp)->s_flags & BILLABLE)
07926
07927
                bill_ptr = rp;
                                            /* bill for system time */
07928
             return;
07929
07930
07931 }
0.7933 /*===========*
07934
                              lock send
07935
      *-----*
07936 PUBLIC int lock_send(dst, m_ptr)
                               /* to whom is message being sent? */
07937 int dst;
     message *m ptr;
                               /* pointer to message buffer */
07938
07939
07940
     /* Safe gateway to mini send() for tasks. */
07941
       int result;
07942
       lock(2, "send");
07943
       result = mini_send(proc_ptr, dst, m_ptr, NON_BLOCKING);
07944
       unlock(2);
07945
       return(result);
07946 }
0.7948 /*============*
07949
                             lock enqueue
07950
      07951 PUBLIC void lock_enqueue(rp)
07952 struct proc *rp;
                               /* this process is now runnable */
07953
     /* Safe gateway to enqueue() for tasks. */
07954
07955
     lock(3, "enqueue");
```

```
book.txt
Feb 25, 11 15:18
                                                            Page 95/393
      File: Page: 732 kernel/proc.c
07956
       enqueue(rp);
07957
       unlock(3);
07958
07960 /*==========*
07961 *
                               lock_dequeue
07963 PUBLIC void lock_dequeue(rp)
07964 struct proc *rp;
                               /* this process is no longer runnable */
07965
      /* Safe gateway to dequeue() for tasks. */
07966
07967
       lock(4, "dequeue");
07968
       dequeue(rp);
07969
       unlock(4);
07970 }
kernel/exception.c
08000 /* This file contains a simple exception handler. Exceptions in user
08001 * processes are converted to signals. Exceptions in a kernel task cause
08002
     * a panic.
08003
08004
08005 #include "kernel.h"
08006 #include <signal.h>
08007 #include "proc.h"
08008
08009 /*=========*
08010 *
                              exception
08011 *============*/
08012 PUBLIC void exception(vec_nr)
08013 unsigned vec nr;
08014
      /* An exception or unexpected interrupt has occurred. */
08015
08016
       struct ex_s {
08017
08018
            char *msg;
08019
            int signum;
08020
            int minprocessor;
08021
08022
       static struct ex_s ex_data[] = {
08023
              "Divide error", SIGFPE, 86 },
08024
              "Debug exception", SIGTRAP, 86 },
08025
              "Nonmaskable interrupt", SIGBUS, 86 },
              "Breakpoint", SIGEMT, 86 },
"Overflow", SIGFPE, 86 },
08026
08027
              "Bounds check", SIGFPE, 186 },
"Invalid opcode", SIGILL, 186 },
08028
08029
08030
              "Coprocessor not available", SIGFPE, 186 },
              "Double fault", SIGBUS, 286 },
"Copressor segment overrun", SIGSEGV, 286 },
"Invalid TSS", SIGSEGV, 286 },
08031
08032
08033
08034
              "Segment not present", SIGSEGV, 286 },
```

```
book.txt
 Feb 25, 11 15:18
                                                                      Page 96/393
       File: Page: 733 kernel/exception.c
08035
                 "Stack exception", SIGSEGV, 286 },
                                                    /* STACK FAULT already used */
08036
                 "General protection", SIGSEGV, 286 },
                 "Page fault", SIGSEGV, 386 },
08037
                                                    /* not close */
                NIL_PTR, SIGILL, 0 },
08038
                                                    /* probably software trap */
                "Coprocessor error", SIGFPE, 386 },
08039
08040
08041
         register struct ex_s *ep;
         struct proc *saved_proc;
08042
08043
08044
         /* Save proc_ptr, because it may be changed by debug statements. */
08045
         saved proc = proc ptr;
08046
08047
         ep = &ex data[vec nr];
08048
08049
                                     /* spurious NMI on some machines */
         if (vec nr == 2) {
08050
              kprintf("got spurious NMI\n");
08051
              return;
08052
08053
08054
         /* If an exception occurs while running a process, the k_reenter variable
08055
          * will be zero. Exceptions in interrupt handlers or system traps will make
08056
          * k_reenter larger than zero.
08057
08058
         if (k reenter == 0 && ! iskernelp(saved proc)) {
08059
              cause_sig(proc_nr(saved_proc), ep->signum);
08060
              return;
08061
08062
         /* Exception in system code. This is not supposed to happen. */
08063
         if (ep->msq == NIL PTR || machine.processor < ep->minprocessor)
08064
08065
              kprintf("\nIntel-reserved exception %d\n", vec_nr);
08066
08067
              kprintf("\n%s\n", ep->msg);
         kprintf("k_reenter = %d ", k_reenter);
kprintf("process %d (%s), ", proc_nr(saved_proc), saved_proc->p_name);
08068
08069
08070
         kprintf("pc = %u: 0x%x", (unsigned) saved_proc->p_reg.cs,
         (unsigned) saved_proc->p_reg.pc);
08071
08072
08073
         panic("exception in a kernel task", NO_NUM);
08074
kernel/i8259.c
08100 /* This file contains routines for initializing the 8259 interrupt controller:
              put_irq_handler: register an interrupt handler
08101 *
              rm_irq_handler: deregister an interrupt handler
08102
08103
              intr handle:
                              handle a hardware interrupt
08104
              intr_init:
                              initialize the interrupt controller(s)
08105
08106
08107
      #include "kernel.h"
08108 #include "proc.h"
08109 #include <minix/com.h>
```

```
book.txt
Feb 25, 11 15:18
                                                                 Page 97/393
      File: Page: 734 kernel/i8259.c
08110
08111 #define ICW1_AT
                           0x11
                                  /* edge triggered, cascade, need ICW4 */
08112 #define ICW1_PC
                           0x13
                                  /* edge triggered, no cascade, need ICW4 */
08113 #define ICW1 PS
                                  /* level triggered, cascade, need ICW4 */
                           0 \times 19
                                  /* not SFNM, not buffered, normal EOI, 8086 */
08114 #define ICW4_AT_SLAVE
                           0 \times 01
08115 #define ICW4_AT_MASTER 0x05
                                  /* not SFNM, not buffered, normal EOI, 8086 */
08116 #define ICW4_PC_SLAVE
                           0x09
                                  /* not SFNM, buffered, normal EOI, 8086 */
08117 #define ICW4_PC_MASTER 0x0D
                                  /* not SFNM, buffered, normal EOI, 8086 */
08118
08119 #define set_vec(nr, addr)
                                  ((void)0)
08120
08121 /*=========*
08122
                                  intr init
08124 PUBLIC void intr init(mine)
08125
      int mine;
08126
08127 /* Initialize the 8259s, finishing with all interrupts disabled. This is
      * only done in protected mode, in real mode we don't touch the 8259s, but
08128
       * use the BIOS locations instead. The flag "mine" is set if the 8259s are
08129
08130
       * to be programmed for MINIX, or to be reset to what the BIOS expects.
08131
08132
       int i;
08133
       intr_disable();
08134
08135
08136
           /* The AT and newer PS/2 have two interrupt controllers, one master,
08137
            * one slaved at IRQ 2. (We don't have to deal with the PC that
08138
            * has just one controller, because it must run in real mode.)
08139
08140
           outb(INT_CTL, machine.ps_mca ? ICW1_PS : ICW1_AT);
08141
           outb(INT_CTLMASK, mine ? IRQ0_VECTOR : BIOS_IRQ0_VEC);
08142
                                                       /* ICW2 for master */
08143
                                                        /* ICW3 tells slaves */
           outb(INT_CTLMASK, (1 << CASCADE_IRQ));
           outb(INT_CTLMASK, ICW4_AT_MASTER);
08144
08145
           outb(INT_CTLMASK, ~(1 << CASCADE_IRQ));
                                                        /* IRQ 0-7 mask */
08146
           outb(INT2_CTL, machine.ps_mca ? ICW1_PS : ICW1_AT);
08147
           outb(INT2_CTLMASK, mine ? IRQ8_VECTOR : BIOS_IRQ8_VEC);
08148
                                                       /* ICW2 for slave */
                                                /* ICW3 is slave nr */
08149
           outb(INT2_CTLMASK, CASCADE_IRQ);
08150
           outb(INT2_CTLMASK, ICW4_AT_SLAVE);
08151
           outb(INT2 CTLMASK, ~0);
                                                       /* IRO 8-15 mask */
08152
08153
           /* Copy the BIOS vectors from the BIOS to the Minix location, so we
            * can still make BIOS calls without reprogramming the i8259s.
08154
08155
08156
           phys_copy(BIOS_VECTOR(0) * 4L, VECTOR(0) * 4L, 8 * 4L);
08157 }
put_irq_handler
08161 *===========*/
08162 PUBLIC void put_irg_handler(hook, irg, handler)
08163 irg hook t *hook;
08164 int irq;
08165
     irq_handler_t handler;
08166
      /* Register an interrupt handler. */
08167
08168
       int id;
08169
       irg hook t **line;
```

```
Feb 25, 11 15:18
                                  book.txt
                                                               Page 98/393
      File: Page: 735 kernel/i8259.c
08170
08171
       if (irq < 0 | | irq >= NR_IRQ_VECTORS)
           panic("invalid call to put_irq_handler", irq);
08172
08173
08174
       line = &irq_handlers[irq];
08175
08176
       while (*line != NULL) {
           if (hook == *line) return;
08177
                                        /* extra initialization */
           line = &(*line)->next;
08178
08179
           id <<= 1;
08180
08181
       if (id == 0) panic("Too many handlers for irg", irg);
08182
08183
       hook->next = NULL;
       hook->handler = handler;
08184
08185
       hook->irq = irq;
08186
       hook->id = id;
08187
       *line = hook;
08188
08189
       irq_use |= 1 << irq;
08190 }
08192 /*=======*
08193
                               rm irg handler
      *-----*
08194
08195
     PUBLIC void rm_irq_handler(hook)
08196
     irg hook t *hook;
08197
      /* Unregister an interrupt handler. */
08198
       int irg = hook->irg;
08199
08200
       int id = hook->id;
08201
       irq_hook_t **line;
08202
08203
       if (irq < 0 || irq >= NR_IRQ_VECTORS)
08204
           panic("invalid call to rm_irq_handler", irq);
08205
08206
       line = &irq_handlers[irq];
       while (*line != NULL) {
08207
08208
           if ((*line)->id == id) {
08209
              (*line) = (*line)->next;
08210
              if (! irq_handlers[irq]) irq_use &= ~(1 << irq);
08211
              return;
08212
08213
           line = &(*line)->next;
08214
       /* When the handler is not found, normally return here. */
08215
08216
08218
     /*-----*
08219
                                intr_handle
08220
      *----*
08221
     PUBLIC void intr handle(hook)
08222
     irq_hook_t *hook;
08223
08224 /* Call the interrupt handlers for an interrupt with the given hook list.
      * The assembly part of the handler has already masked the IRQ, reenabled the
08225
      * controller(s) and enabled interrupts.
08226
08227
08228
08229
       /* Call list of handlers for an IRO. */
```

```
book.txt
Feb 25, 11 15:18
                                                                  Page 99/393
      File: Page: 736 kernel/i8259.c
08230
        while (hook != NULL)
08231
            /* For each handler in the list, mark it active by setting its ID bit,
08232
             * call the function, and unmark it if the function returns true.
08233
08234
            irq_actids[hook->irq] |= hook->id;
08235
            if ((*hook->handler)(hook)) irg_actids[hook->irg] &= ~hook->id;
08236
            hook = hook->next;
08237
08238
        /* The assembly code will now disable interrupts, unmask the IRQ if and only
08239
         * if all active ID bits are cleared, and restart a process.
08240
08241
08242 }
kernel/protect.c
08300 /* This file contains code for initialization of protected mode, to initialize
08301 * code and data segment descriptors, and to initialize global descriptors
      * for local descriptors in the process table.
08302
08304
08305 #include "kernel.h"
08306 #include "proc.h"
08307 #include "protect.h"
08308
08309 #define INT GATE TYPE (INT 286 GATE | DESC 386 BIT)
08310 #define TSS TYPE
                            (AVL 286 TSS DESC 386 BIT)
08311
08312 struct desctableptr_s {
08313
        char limit[sizeof(u16_t)];
                                        /* really u24_t + pad for 286 */
08314
        char base[sizeof(u32_t)];
08315 };
08316
08317 struct gatedesc_s {
08318
      ul6 t offset low;
08319
        u16_t selector;
                                   /* |000|XXXXX| ig & trpg, |XXXXXXXX| task g */
08320
        u8_t pad;
                                  /* |P|DL|0|TYPE| */
08321
        u8_t p_dpl_type;
08322
        u16_t offset_high;
08323 };
08324
08325 struct tss_s {
08326
       reg_t backlink;
08327
        reg_t sp0;
                                   /* stack pointer to use during interrupt */
08328
        reg_t ss0;
                                   /* " segment " " "
08329
        reg_t sp1;
08330
        reg_t ss1;
        reg_t sp2;
08331
08332
        reg_t ss2;
08333
        reg t cr3;
08334
        reg_t ip;
08335
        reg_t flags;
08336
        req t ax;
08337
        reg_t cx;
08338
        reg_t dx;
08339
        reg t bx;
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                     Page 100/393
      File: Page: 737 kernel/protect.c
08340
       req t sp;
08341
        reg_t bp;
08342
        reg_t si;
08343
        reg_t di;
08344
        reg_t es;
08345
        reg_t cs;
08346
        reg_t ss;
08347
        reg_t ds;
08348
        req t fs;
08349
        reg_t gs;
08350
        reg t ldt;
08351
        ul6 t trap;
        u16_t iobase;
08352
       /* u8_t iomap[0]; */
08353
08354 };
08355
08356 PUBLIC struct segdesc_s gdt[GDT_SIZE];
                                                    /* used in klib.s and mpx.s */
      PRIVATE struct gatedesc_s idt[IDT_SIZE];
                                                    /* zero-init so none present */
08357
                                                    /* zero init */
08358 PUBLIC struct tss s tss;
08359
08360 FORWARD _PROTOTYPE( void int_gate, (unsigned vec_nr, vir_bytes offset,
08361
                     unsigned dpl_type) );
08362 FORWARD _PROTOTYPE( void sdesc, (struct segdesc_s *segdp, phys_bytes base,
08363
                     vir_bytes size) );
08364
08365
      /*----*
08366
                                prot init
08367
       08368
      PUBLIC void prot_init()
08369
08370
      /* Set up tables for protected mode.
08371
       * All GDT slots are allocated at compile time.
08372
08373
        struct gate_table_s *gtp;
08374
        struct desctableptr_s *dtp;
08375
        unsigned ldt_index;
08376
        register struct proc *rp;
08377
08378
        static struct gate table s {
08379
              _PROTOTYPE( void (*gate), (void) );
08380
              unsigned char vec_nr;
08381
              unsigned char privilege;
08382
08383
        gate_table[] = {
                divide error, DIVIDE VECTOR, INTR PRIVILEGE },
08384
08385
                single_step_exception, DEBUG_VECTOR, INTR_PRIVILEGE },
08386
                nmi, NMI_VECTOR, INTR_PRIVILEGE },
08387
                breakpoint_exception, BREAKPOINT_VECTOR, USER_PRIVILEGE },
08388
                overflow, OVERFLOW_VECTOR, USER_PRIVILEGE },
08389
                bounds_check, BOUNDS_VECTOR, INTR_PRIVILEGE }
                inval_opcode, INVAL_OP_VECTOR, INTR_PRIVILEGE },
copr_not_available, COPROC_NOT_VECTOR, INTR_PRIVILEGE },
08390
08391
08392
                double_fault, DOUBLE_FAULT_VECTOR, INTR_PRIVILEGE },
                copr_seg_overrun, COPROC_SEG_VECTOR, INTR_PRIVILEGE },
08393
08394
                inval_tss, INVAL_TSS_VECTOR, INTR_PRIVILEGE },
08395
                segment_not_present, SEG_NOT_VECTOR, INTR_PRIVILEGE
                stack_exception, STACK_FAULT_VECTOR, INTR_PRIVILEGE
08396
                general_protection, PROTECTION_VECTOR, INTR_PRIVILEGE },
08397
                page_fault, PAGE_FAULT_VECTOR, INTR_PRIVILEGE },
08398
08399
                copr error, COPROC ERR VECTOR, INTR PRIVILEGE },
```

```
book.txt
Feb 25, 11 15:18
                                                                            Page 101/393
       File: Page: 738 kernel/protect.c
08400
                  hwint00, VECTOR( 0), INTR_PRIVILEGE
                  hwint01, VECTOR( 1), INTR_PRIVILEGE
08401
08402
                  hwint02, VECTOR( 2), INTR_PRIVILEGE
08403
                  hwint03, VECTOR( 3), INTR_PRIVILEGE
08404
                  hwint04, VECTOR(4), INTR_PRIVILEGE
08405
                  hwint05, VECTOR(5), INTR_PRIVILEGE
                 hwint06, VECTOR( 6), INTR_PRIVILEGE
hwint07, VECTOR( 7), INTR_PRIVILEGE
08406
08407
                  hwint08, VECTOR( 8), INTR_PRIVILEGE
08408
08409
                  hwint09, VECTOR( 9), INTR_PRIVILEGE
08410
                  hwint10, VECTOR(10), INTR_PRIVILEGE
08411
                  hwint11, VECTOR(11), INTR_PRIVILEGE
                  hwint12, VECTOR(12), INTR_PRIVILEGE
hwint13, VECTOR(13), INTR_PRIVILEGE
08412
08413
                  hwint14, VECTOR(14), INTR_PRIVILEGE
08414
08415
                  hwint15, VECTOR(15), INTR_PRIVILEGE
08416
                  s_call, SYS386_VECTOR, USER_PRIVILEGE },
                                                                   /* 386 system call */
08417
                 level0_call, LEVEL0_VECTOR, TASK_PRIVILEGE },
         };
08418
08419
08420
         /* Build gdt and idt pointers in GDT where the BIOS expects them. */
08421
         dtp= (struct desctableptr_s *) &gdt[GDT_INDEX];
08422
         * (u16_t *) dtp->limit = (sizeof gdt) - 1;
         * (u32_t *) dtp->base = vir2phys(gdt);
08423
08424
08425
         dtp= (struct desctableptr_s *) &gdt[IDT_INDEX];
         * (u16 t *) dtp->limit = (sizeof idt) - 1;
08426
         * (u32_t *) dtp->base = vir2phys(idt);
08427
08428
08429
          /* Build segment descriptors for tasks and interrupt handlers. */
08430
         init codeseg(&qdt[CS INDEX],
08431
                kinfo.code_base, kinfo.code_size, INTR_PRIVILEGE);
08432
         init_dataseg(&gdt[DS_INDEX],
08433
                kinfo.data_base, kinfo.data_size, INTR_PRIVILEGE);
08434
         init_dataseg(&gdt[ES_INDEX], OL, O, TASK_PRIVILEGE);
08435
08436
         /* Build scratch descriptors for functions in klib88. */
init_dataseg(&gdt[DS_286_INDEX], OL, O, TASK_PRIVILEGE);
08437
08438
         init_dataseg(&gdt[ES_286_INDEX], OL, O, TASK_PRIVILEGE);
08439
08440
         /* Build local descriptors in GDT for LDT's in process table.
          * The LDT's are allocated at compile time in the process table, and
08441
          * initialized whenever a process map is initialized or changed.
08442
08443
08444
         for (rp = BEG PROC ADDR, ldt index = FIRST LDT INDEX;
08445
               rp < END_PROC_ADDR; ++rp, ldt_index++)
08446
               init_dataseg(&gdt[ldt_index], vir2phys(rp->p_ldt),
08447
                                              sizeof(rp->p_ldt), INTR_PRIVILEGE);
08448
                gdt[ldt_index].access = PRESENT | LDT;
08449
               rp->p_ldt_sel = ldt_index * DESC_SIZE;
08450
08451
         /* Build main TSS.
08452
08453
          * This is used only to record the stack pointer to be used after an
08454
          * interrupt.
08455
          * The pointer is set up so that an interrupt automatically saves the
08456
          * current process's registers ip: cs: f: sp: ss in the correct slots in the
08457
          * process table.
08458
08459
         tss.ss0 = DS SELECTOR;
```

```
book.txt
Feb 25, 11 15:18
                                                            Page 102/393
      File: Page: 739 kernel/protect.c
       init_dataseg(&gdt[TSS_INDEX], vir2phys(&tss), sizeof(tss), INTR_PRIVILEGE);
gdt[TSS_INDEX].access = PRESENT | (INTR_PRIVILEGE << DPL_SHIFT) | TSS_TYPE;</pre>
08460
08461
08462
08463
       /* Build descriptors for interrupt gates in IDT. */
08464
       for (gtp = &gate_table[0];
08465
           gtp < &gate_table[sizeof gate_table / sizeof gate_table[0]]; ++gtp) {</pre>
            08466
08467
08468
08469
08470
       /* Complete building of main TSS. */
08471
       tss.iobase = sizeof tss; /* empty i/o permissions map */
08472 }
     /*----*
08475
                                init_codeseg
08476 *=======*/
08477 PUBLIC void init_codeseg(segdp, base, size, privilege)
08478 register struct segdesc_s *segdp;
08479 phys_bytes base;
08480 vir_bytes size;
08481 int privilege;
08482
08483 /* Build descriptor for a code segment. */
08484
       sdesc(segdp, base, size);
08485
       segdp->access = (privilege << DPL_SHIFT)</pre>
                    (PRESENT | SEGMENT | EXECUTABLE | READABLE);
08486
                   /* CONFORMING = 0, ACCESSED = 0 */
08487
08488
08490 /*=============*
08491 *
                               init_dataseg
08492 *========*/
08493 PUBLIC void init_dataseg(segdp, base, size, privilege)
08494 register struct segdesc_s *segdp;
08495 phys_bytes base;
08496 vir_bytes size;
08497 int privilege;
08498
08499
      * Build descriptor for a data segment. */
08500
       sdesc(segdp, base, size);
       seqdp->access = (privilege << DPL SHIFT) | (PRESENT | SEGMENT | WRITEABLE);</pre>
08501
                   /* EXECUTABLE = 0, EXPAND_DOWN = 0, ACCESSED = 0 */
08502
08503
08505 /*=========*
08506
     *-----*/
08508 PRIVATE void sdesc(segdp, base, size)
08509 register struct segdesc_s *segdp;
08510 phys_bytes base;
08511 vir_bytes size;
08512
08513 /* Fill in the size fields (base, limit and granularity) of a descriptor. */
08514
       segdp->base_low = base;
08515
       seqdp->base middle = base >> BASE MIDDLE SHIFT;
08516
       segdp->base high = base >> BASE HIGH SHIFT;
08517
                                /* convert to a limit, 0 size means 4G */
08518
       --size;
08519
       if (size > BYTE GRAN MAX) {
```

```
book.txt
Feb 25, 11 15:18
                                                          Page 103/393
     File: Page: 740 kernel/protect.c
08520
            segdp->limit low = size >> PAGE GRAN SHIFT;
08521
            segdp->granularity = GRANULAR | (size >>
08522
                                   (PAGE_GRAN_SHIFT + GRANULARITY_SHIFT));
08523
       } else {
08524
            segdp->limit_low = size;
08525
            segdp->granularity = size >> GRANULARITY_SHIFT;
08526
       segdp->granularity |= DEFAULT;
08527
                                      /* means BIG for data seg */
08528
08530
08531
                             seq2phys
08532
      08533
     PUBLIC phys_bytes seg2phys(seg)
08534
     U16 t seq;
08535
08536
      ^{\prime *} Return the base address of a segment, with seg being either a 8086 segment
08537
      * register, or a 286/386 segment selector.
08538
08539
       phys_bytes base;
08540
       struct segdesc_s *segdp;
08541
08542
       if (! machine.protected) {
            base = hclick_to_physb(seg);
08543
       } else {
08544
08545
            segdp = &gdt[seg >> 3];
                    ((u32_t) segdp->base_low << 0)
08546
            base =
08547
                    ((u32_t) segdp->base_middle << 16)
08548
                    ((u32_t) segdp->base_high << 24);
08549
08550
       return base;
08551
08553
     /*_____*
08554
                               phys2seg
     *=======*/
08555
08556 PUBLIC void phys2seg(seg, off, phys)
08557 u16_t *seg;
08558 vir bytes *off;
08559 phys_bytes phys;
08560
     /* Return a segment selector and offset that can be used to reach a physical
08561
      * address, for use by a driver doing memory I/O in the A0000 - DFFFF range.
08562
08563
08564
       *seg = FLAT DS SELECTOR;
08565
       *off = phys;
08566
08569
                               int_gate
08570
     08571 PRIVATE void int_gate(vec_nr, offset, dpl_type)
08572 unsigned vec_nr;
08573 vir bytes offset;
08574 unsigned dpl_type;
08575
08576
      /* Build descriptor for an interrupt gate. */
08577
       register struct gatedesc_s *idp;
08578
08579
       idp = &idt[vec nr];
```

```
Feb 25, 11 15:18
                                   book.txt
                                                                 Page 104/393
      File: Page: 741 kernel/protect.c
08580
        idp->offset low = offset;
08581
        idp->selector = CS_SELECTOR;
        idp->p_dpl_type = dpl_type;
08582
08583
        idp->offset_high = offset >> OFFSET_HIGH_SHIFT;
08584
08586 /*=========*
08587
                                  enable_iop
08588
      *============*/
08589
     PUBLIC void enable_iop(pp)
08590
      struct proc *pp;
08591
08592
      /* Allow a user process to use I/O instructions. Change the I/O Permission
      * Level bits in the psw. These specify least-privileged Current Permission
08593
      * Level allowed to execute I/O instructions. Users and servers have CPL 3.
08594
08595
       * You can't have less privilege than that. Kernel has CPL 0, tasks CPL 1.
08596
08597
        pp->p_reg.psw |= 0x3000;
08598 }
     08601
                                  alloc segments
08602
      *----*
08603 PUBLIC void alloc segments(rp)
     register struct proc *rp;
08604
08605
08606
      /* This is called at system initialization from main() and by do newmap().
08607
       * The code has a separate function because of all hardware-dependencies.
       * Note that IDLE is part of the kernel and gets TASK_PRIVILEGE here.
08608
08609
08610
        phys_bytes code_bytes;
08611
        phys_bytes data_bytes;
08612
        int privilege;
08613
08614
        if (machine.protected) {
08615
           data_bytes = (phys_bytes) (rp->p_memmap[S].mem_vir +
08616
               rp->p_memmap[S].mem_len) << CLICK_SHIFT;
08617
           if (rp->p_memmap[T].mem_len == 0)
08618
               code_bytes = data_bytes;
                                         /* common I&D, poor protect */
08619
           else
08620
               code_bytes = (phys_bytes) rp->p_memmap[T].mem_len << CLICK_SHIFT;</pre>
           privilege = (iskernelp(rp)) ? TASK PRIVILEGE : USER PRIVILEGE;
08621
08622
           init_codeseg(&rp->p_ldt[CS_LDT_INDEX],
08623
               (phys_bytes) rp->p_memmap[T].mem_phys << CLICK_SHIFT,
08624
               code bytes, privilege);
08625
           init_dataseg(&rp->p_ldt[DS_LDT_INDEX],
08626
               (phys_bytes) rp->p_memmap[D].mem_phys << CLICK_SHIFT,
08627
               data_bytes, privilege);
08628
           rp->p_reg.cs = (CS_LDT_INDEX * DESC_SIZE) | TI | privilege;
08629
           rp->p_reg.gs =
08630
           rp->p_reg.fs =
08631
           rp->p_reg.ss =
08632
           rp->p_reg.es =
08633
           rp->p_reg.ds = (DS_LDT_INDEX*DESC_SIZE) | TI | privilege;
08634
        } else {
08635
           rp->p_reg.cs = click_to_hclick(rp->p_memmap[T].mem_phys);
08636
           rp->p req.ss =
08637
           rp->p req.es =
08638
           rp->p_reg.ds = click_to_hclick(rp->p_memmap[D].mem_phys);
08639
```

```
book.txt
 Feb 25, 11 15:18
                                                               Page 105/393
      File: Page: 742 kernel/protect.c
08640
kernel/klib.s
08701 ! Chooses between the 8086 and 386 versions of the low level kernel code.
08702
08703 #include <minix/config.h>
08704 #if WORD SIZE == 2
08705 #include "klib88.s"
08706 #else
08707 #include "klib386.s"
08708 #endif
kernel/klib386 s
08800 #
08801 ! sections
08802
08803 .sect .text; .sect .rom; .sect .data; .sect .bss
08804
08805 #include <minix/config.h>
08806 #include <minix/const.h>
08807 #include "const.h"
08808 #include "sconst.h"
08809 #include "protect.h"
08810
08811 ! This file contains a number of assembly code utility routines needed by the
08812 ! kernel. They are:
08813
08814 .define _monitor
                           ! exit Minix and return to the monitor
08815 .define _int86
                           ! let the monitor make an 8086 interrupt call
                           ! copies messages from source to destination
08816 .define cp mess
                           ! dummy for library routines
08817 .define _exit
08818 .define __exit
                           ! dummy for library routines
08819 .define ___exit
                           ! dummy for library routines
08820 .define ___main
                           ! dummy for GCC
08821 .define _phys_insw
                           ! transfer data from (disk controller) port to memory
08822 .define _phys_insb
                           ! likewise byte by byte
08823 .define _phys_outsw
                          ! transfer data from memory to (disk controller) port
08824 .define _phys_outsb
                          ! likewise byte by byte
08825 .define _enable_irq
                          ! enable an irg at the 8259 controller
08826 .define _disable_irq
08827 .define _phys_copy
                          ! disable an irq
                           ! copy data from anywhere to anywhere in memory
08828 .define _phys_memset
                          ! write pattern anywhere in memory
08829 .define _mem_rdw
                             copy one word from [segment: offset]
08830 .define _reset
                             reset the system
08831 .define _idle_task
                           ! task executed when there is no work
                             call a function at level 0
08832 .define _level0
08833 .define _read_tsc
                           ! read the cycle counter (Pentium and up)
08834 .define read cpu flags ! read the cpu flags
```

```
book.txt
Feb 25, 11 15:18
                                                               Page 106/393
      File: Page: 743 kernel/klib386.s
08835
08836
      ! The routines only guarantee to preserve the registers the C compiler
08837
     ! expects to be preserved (ebx, esi, edi, ebp, esp, segment registers, and
     ! direction bit in the flags).
08838
08839
08840 .sect .text
08841 !*=========*
08842 !*
                                monitor
08843 !*=========*
     ! PUBLIC void monitor();
08844
08845
     ! Return to the monitor.
08846
08847 _monitor:
08848
            mov
                    esp, (_mon_sp)
                                        ! restore monitor stack pointer
08849
         ol6 mov
                    dx, SS SELECTOR
                                        ! monitor data segment
08850
                   ds, dx
            mov
08851
                    es, dx
            mov
08852
            mov
                    fs, dx
08853
                    gs, dx
            mov
08854
            mov
                    ss. dx
08855
            pop
08856
                    esi
            pop
08857
            pop
                    ebp
08858
         ol6 retf
                                        ! return to the monitor
08859
08860
08861
      !*============
08862
                               int.86
08863 !*===========*
08864 ! PUBLIC void int86();
08865 _int86:
08866
                    (_mon_return), 0
                                        ! is the monitor there?
            cmpb
08867
            inz
08868
                    ah, 0x01
            movb
                                        ! an int 13 error seems appropriate
                    (_reg86+ 0), ah
08869
            movb
                                        ! reg86.w.f = 1 (set carry flag)
08870
            movb
                    (_reg86+13), ah
                                        ! reg86.b.ah = 0x01 = "invalid command"
08871
            ret
08872 0:
             push
                    ebp
                                         ! save C registers
08873
            push
                   esi
08874
                    edi
            push
08875
                    ebx
            push
08876
            pushf
                                        ! save flags
08877
            cli
                                        ! no interruptions
08878
08879
             inb
                    INT2 CTLMASK
08880
            movb
                    ah, al
08881
            inb
                    INT_CTLMASK
08882
            push
                                        ! save interrupt masks
                    eax
08883
                                        ! map of in-use IRQ's
            mov
                    eax, (_irq_use)
08884
            and
                    eax, ~[1<<CLOCK_IRQ]
                                        ! keep the clock ticking
08885
            outb
                    INT_CTLMASK
                                        ! enable all unused IRQ's and vv.
                    al, ah
08886
            movb
                    INT2_CTLMASK
08887
            outb
08888
08889
                    eax, SS_SELECTOR
                                        ! monitor data segment
            mov
08890
            mov
                    ss, ax
08891
            xchq
                    esp, (mon sp)
                                        ! switch stacks
08892
                    (_reg86+36)
            push
                                        ! parameters used in INT call
08893
            push
                    (_reg86+32)
08894
            push
                    (reg86+28)
```

Feb 2	5, 11 15:	18	book	.txt	Page 107/393
	File: Pa	age: 744	kernel/klib386.s		
08895		push	(_reg86+24)		
08896		push	(_reg86+20)		
08897		push	(_reg86+16)		
08898		push	(_reg86+12)		
08899		push	(_reg86+ 8)		
08900		push	(_reg86+ 4)		
08901		push	(_reg86+ 0)		
08902		mov	ds, ax	! remaining data select	ors
08903		mov	es, ax		
08904		mov	fs, ax		
08905 08906		mov	gs, ax		
08907		push push	cs return	! kernel return address	and gologton
08908	016	jmpf	20+2*4+10*4+2*4(esp)		and selector
08909	return:	Juipt	20+2-4+10-4+2-4(esp)	: make the tall	
08910	recurn.	pop	(_reg86+ 0)		
08911		pop	(_reg86+ 4)		
08912		pop	(_reg86+ 8)		
08913		pop	(_reg86+12)		
08914		pop	(_reg86+16)		
08915		pop	(_reg86+20)		
08916		pop	(_reg86+24)		
08917		pop	(_reg86+28)		
08918		pop	(_reg86+32)		
08919		pop	(_reg86+36)		
08920		lgdt	(_gdt+GDT_SELECTOR)	! reload global descrip	tor table
08921		jmpf	CS_SELECTOR: csinit	! restore everything	
	csinit:	mov	eax, DS_SELECTOR		
08923		mov	ds, ax		
08924		mov	es, ax		
08925		mov	fs, ax		
08926		mov	gs, ax		
08927		mov	ss, ax		
08928		xchg	esp, (_mon_sp)	! unswitch stacks ! reload interrupt desc	
08929 08930		lidt andb		LACCESS), ~0x02 ! clear	
08931		mov	eax, TSS_SELECTOR	_ACCESS), ~UXUZ : Clear	iss busy bit
08932		ltr	ax	! set TSS register	
08933		101	an	. Dec 100 regibeer	
08934		pop	eax		
08935		outb	INT_CTLMASK	! restore interrupt mas	ks
08936		movb	al, ah		
08937		outb	INT2_CTLMASK		
08938					
08939		add	(_lost_ticks), ecx	! record lost clock tic	ks
08940					
08941		popf		! restore flags	
08942		pop	ebx	! restore C registers	
08943		pop	edi		
08944		pop	esi		
08945		pop	ebp		
08946 08947		ret			
08947					
08949	1*===			.===========	*
08950	! *		cp_mess		*
08951	•			, :====================================	=======*
08952				.cks src_clicks, vir_byte	
08953	!			licks, vir_bytes dst_off	
	! This :	routine		nessage from anywhere in	
1					

```
book.txt
Feb 25, 11 15:18
                                                                     Page 108/393
      File: Page: 745 kernel/klib386.s
08955 ! space to anywhere else. It also copies the source address provided as a
08956
      ! parameter to the call into the first word of the destination message.
08958 ! Note that the message size, "Msize" is in DWORDS (not bytes) and must be set
08959 ! correctly. Changing the definition of message in the type file and not
08960 ! changing it here will lead to total disaster.
08961
                     4 + 4 + 4 + 4 + 4
                                            ! 4 + 4 + 4 + 4 + 4
08962 CM_ARGS =
08963 !
                     es ds edi esi eip
                                            proc scl sof dcl dof
08964
08965
              .align 16
08966 _cp_mess:
08967
              cld
08968
              push
                      esi
08969
              push
08970
              push
                     ds
08971
              push
                     es
08972
08973
                      eax, FLAT_DS_SELECTOR
              mov
08974
              mov
                      ds, ax
08975
                     es, ax
              mov
08976
08977
              mov
                      esi, CM_ARGS+4(esp)
                                                    ! src clicks
                     esi, CLICK_SHIFT
08978
              shl
08979
                      esi, CM_ARGS+4+4(esp)
                                                    ! src offset
              add
08980
              mov
                      edi, CM_ARGS+4+4+4(esp)
                                                    ! dst clicks
08981
                      edi, CLICK SHIFT
              shl
                      edi, CM_ARGS+4+4+4+(esp)
08982
              add
                                                    ! dst offset
08983
08984
                      eax, CM ARGS(esp)
                                            ! process number of sender
              mov
                                            ! copy number of sender to dest message
08985
              stos
08986
              add
                      esi, 4
                                            ! do not copy first word
08987
              mov
                     ecx, Msize - 1
                                            ! remember, first word does not count
08988
              rep
                                            ! copy the message
08989
              movs
08990
08991
              pop
                      65
08992
              pop
                      ds
08993
              pop
                     edi
08994
              pop
                      esi
                                            ! that is all folks!
08995
              ret
08996
08997
08998
08999 !*
                                    exit
09000 !*=========*
09001 ! PUBLIC void exit();
09002 ! Some library routines use exit, so provide a dummy version.
09003 ! Actual calls to exit cannot occur in the kernel.
09004 ! GNU CC likes to call ____main from main() for nonobvious reasons.
09005
09006 _exit:
09007
      __exit:
09008
      ___exit:
09009
              sti
09010
              jmp
                      ___exit
09011
      ___main:
09012
09013
              ret
09014
```

```
Feb 25, 11 15:18
                              book.txt
                                                        Page 109/393
     File: Page: 746 kernel/klib386.s
09015
09016
    !*_____*
09017
                            phys_insw
09018 !*=========*
    ! PUBLIC void phys_insw(Port_t port, phys_bytes buf, size_t count);
09019
09020 ! Input an array from an I/O port. Absolute address version of insw().
09021
09022
     _phys_insw:
09023
           push
                 ebp
09024
                 ebp, esp
           mov
09025
           cld
09026
           push
                 edi
09027
           push
                 es
                 ecx, FLAT_DS_SELECTOR
09028
           mov
09029
           mov
                 es, cx
09030
                 edx, 8(ebp)
                                    ! port to read from
           mov
09031
           mov
                 edi, 12(ebp)
                                    ! destination addr
09032
           mov
                 ecx, 16(ebp)
                                    ! byte count
09033
                                    ! word count
           shr
                 ecx, 1
09034 rep ol6 ins
                                    ! input many words
09035
           gog
09036
                 edi
           pop
09037
           pop
                 ebp
09038
           ret.
09039
09040
09041
     09042
                             phys_insb
     !*-----
09043
     ! PUBLIC void phys insb(Port t port, phys bytes buf, size t count);
     ! Input an array from an I/O port. Absolute address version of insb().
09045
09046
09047
     _phys_insb:
09048
           push
                 ebp
09049
           mov
                 ebp, esp
09050
09051
           push
                 edi
09052
           push
                 es
09053
           mov
                 ecx, FLAT_DS_SELECTOR
09054
           mov
                 es, cx
09055
           mov
                 edx, 8(ebp)
                                    ! port to read from
                                    ! destination addr
09056
           mov
                 edi, 12(ebp)
                                    ! byte count
09057
           mov
                 ecx, 16(ebp)
09058
           shr
                 ecx, 1
                                    ! word count
                                    ! input many bytes
09059
       rep insb
09060
           gog
                 es
09061
                 edi
           pop
09062
                 ebp
           gog
09063
           ret
09064
09065
09066
    !*_____*
09067 !*
                             phys_outsw
    ! PUBLIC void phys_outsw(Port_t port, phys_bytes buf, size_t count);
09069
09070
     ! Output an array to an I/O port. Absolute address version of outsw().
09072
            .align 16
09073
     _phys_outsw:
09074
           push
```

```
book.txt
Feb 25, 11 15:18
                                                            Page 110/393
      File: Page: 747 kernel/klib386.s
09075
            mov
                   ebp, esp
09076
            cld
09077
            push
09078
            push
                   ds
09079
                   ecx, FLAT_DS_SELECTOR
            mov
09080
            mov
                   ds, cx
                   edx, 8(ebp)
09081
            mov
                                       ! port to write to
09082
            mov
                   esi, 12(ebp)
                                       ! source addr
                   ecx, 16(ebp)
09083
            mov
                                       ! byte count
09084
                                       ! word count
            shr
                   ecx, 1
09085
     rep ol6 outs
                                       ! output many words
09086
            qoq
09087
            gog
                   esi
09088
            pop
                   ebp
09089
            ret
09090
09091
09092
     09093 !*
                              phys_outsb
09094 !*==========*
     ! PUBLIC void phys_outsb(Port_t port, phys_bytes buf, size_t count);
09096
     ! Output an array to an I/O port. Absolute address version of outsb().
09097
09098
            .align 16
09099
     _phys_outsb:
09100
            push
                   ebp
09101
            mov
                   ebp, esp
09102
            cld
09103
            push
                   esi
09104
            push
                   ds
09105
                   ecx, FLAT DS SELECTOR
            mov
09106
            mov
                   ds, cx
09107
                   edx, 8(ebp)
                                       ! port to write to
            mov
09108
                   esi, 12(ebp)
            mov
                                       ! source addr
09109
            mov
                   ecx, 16(ebp)
                                       ! byte count
09110
        rep outsb
                                       ! output many bytes
09111
            pop
                   ds
09112
            pop
                   esi
09113
                   ebp
            gog
09114
            ret.
09115
09116
09117
      !*-----
09118
                                enable_irq
09119
     ! PUBLIC void enable_irq(irq_hook_t *hook)
09120
09121
      ! Enable an interrupt request line by clearing an 8259 bit.
     ! Equivalent C code for hook->irg < 8:
09122
        if ((irq_actids[hook->irq] &= ~hook->id) == 0)
09123
09124
            outb(INT_CTLMASK, inb(INT_CTLMASK) & ~(1 << irq));
09125
09126
            .align 16
09127
     _enable_irq:
09128
            push
                   ebp
09129
            mov
                   ebp, esp
09130
            pushf
09131
            cli
09132
            mov
                   eax, 8(ebp)
                                       ! hook
09133
            mov
                   ecx, 8(eax)
                                       ! irq
09134
                   eax, 12(eax)
                                       ! id bit
```

```
book.txt
Feb 25, 11 15:18
                                                                  Page 111/393
      File: Page: 748 kernel/klib386.s
09135
             not.
                     eax
09136
              and
                     _irq_actids(ecx*4), eax ! clear this id bit
09137
                     en_done
                                          ! still masked by other handlers?
              inz
09138
             movb
                     ah, ~1
09139
             rolb
                     ah, cl
                                           ! ah = \sim (1 << (irq % 8))
09140
             mov
                     edx, INT_CTLMASK
                                           ! enable irq < 8 at the master 8259
09141
             cmpb
                     cl, 8
09142
              jb
                     Ωf
09143
             mov
                     edx, INT2 CTLMASK
                                           ! enable irg >= 8 at the slave 8259
09144 0:
              inb
                      dx
09145
              andb
                     al, ah
09146
             outb
                     dx
                                           ! clear bit at the 8259
09147
      en_done: popf
09148
              leave
09149
             ret
09150
09151
09152
     09153 1*
                                  disable_irq
! PUBLIC int disable_irg(irg_hook_t *hook)
09156
      ! Disable an interrupt request line by setting an 8259 bit.
09157
      ! Equivalent C code for irq < 8:
      ! irq_actids[hook->irq] |= hook->id;
09158
         outb(INT_CTLMASK, inb(INT_CTLMASK) | (1 << irq));
09159
09160
      ! Returns true iff the interrupt was not already disabled.
09161
09162
              .align 16
      _disable_irq:
09163
09164
             push
                     ebp
09165
                     ebp, esp
             mov
09166
             pushf
09167
             cli
09168
                     eax, 8(ebp)
             mov
                                           1 hook
09169
             mov
                     ecx, 8(eax)
                                           ! irq
09170
             mov
                     eax, 12(eax)
                                          ! id bit
09171
                     _irq_actids(ecx*4), eax ! set this id bit
             or
09172
             movb
                     ah, 1
09173
             rolb
                     ah, cl
                                           ! ah = (1 << (irg % 8))
                     edx, INT_CTLMASK
09174
             mov
                                           ! disable irq < 8 at the master 8259
09175
              cmpb
                     cl, 8
09176
              jb
                                           ! disable irq >= 8 at the slave 8259
09177
                     edx, INT2_CTLMASK
              mov
09178 0:
              inb
                      dx
09179
              testb
                     al, ah
                                           ! already disabled?
09180
                     dis_already
              inz
09181
              orb
                     al, ah
09182
             outb
                                           ! set bit at the 8259
09183
                     eax, 1
                                           ! disabled by this function
             mov
09184
              popf
09185
              leave
09186
             ret
09187 dis_already:
09188
             xor
                     eax, eax
                                          ! already disabled
09189
              lgog
09190
             leave
09191
             ret
09192
09193
```

```
book.txt
Feb 25, 11 15:18
                                                            Page 112/393
      File: Page: 749 kernel/klib386.s
09194
     09195
                                phys_copy
     1*_____*
09197
     ! PUBLIC void phys_copy(phys_bytes source, phys_bytes destination,
09198
                         phys_bytes bytecount);
09199
     ! Copy a block of physical memory.
09200
                   4 + 4 + 4 + 4 ! 4 + 4 + 4
09201 PC_ARGS =
09202 !
                   es edi esi eip src dst len
09203
09204
            .align 16
09205
     _phys_copy:
09206
            cld
09207
            push
                   esi
09208
            push
                   edi
09209
            push
                   es
09210
09211
            mov
                   eax, FLAT_DS_SELECTOR
09212
            mov
                   es, ax
09213
09214
            mov
                   esi, PC_ARGS(esp)
09215
                   edi, PC_ARGS+4(esp)
            mov
09216
            mov
                   eax, PC_ARGS+4+4(esp)
09217
                                       ! avoid align overhead for small counts
09218
            cmp
                   eax, 10
09219
            jb
                   pc_small
09220
            mov
                   ecx, esi
                                       ! align source, hope target is too
09221
            nea
                   ecx
09222
            and
                   ecx, 3
                                       ! count for alignment
09223
            sub
                   eax, ecx
09224
            rep
09225
        eseg movsb
09226
            mov
                   ecx, eax
09227
                                       ! count of dwords
            shr
                   ecx, 2
09228
            rep
09229
        eseg movs
09230
            and
                   eax. 3
     pc_small:
09231
09232
            xchq
                   ecx. eax
                                       ! remainder
09233
            rep
09234
        eseg movsb
09235
09236
            ana
                   es
09237
            pop
                   edi
09238
            gog
                   esi
09239
            ret.
09240
09241 !*=======*
09242 !*
                                phys_memset
09243 !*========*
     ! PUBLIC void phys_memset(phys_bytes source, unsigned long pattern,
09244
            phys_bytes bytecount);
09245
09246
     ! Fill a block of physical memory with pattern.
09247
09248
            .align 16
09249
     _phys_memset:
09250
            push
                   ebp
09251
            mov
                   ebp, esp
09252
            push
                   esi
09253
            push
                   ebx
```

```
book.txt
Feb 25, 11 15:18
                                                          Page 113/393
     File: Page: 750 kernel/klib386.s
09254
           push
                  ds
09255
            mov
                  esi, 8(ebp)
09256
            mov
                  eax, 16(ebp)
                  ebx, FLAT_DS_SELECTOR
09257
            mov
09258
            mov
                  ds, bx
09259
            mov
                  ebx, 12(ebp)
09260
            shr
                  eax, 2
09261 fill_start:
09262
            mov
                  (esi), ebx
09263
            add
                  esi, 4
09264
            dec
                  eax
09265
            jnz
                  fill start
            ! Any remaining bytes?
09266
09267
            mov
                  eax, 16(ebp)
09268
                  eax, 3
            and
09269 remain fill:
09270
            cmp
09271
            jz
                  fill_done
09272
                  bl. 12(ebp)
            movb
09273
            movb
                  (esi), bl
09274
            add
                  esi, 1
09275
            inc
                  ebp
09276
            dec
                  eax
                  remain fill
09277
            qmj
09278 fill_done:
09279
            gog
09280
            gog
09281
                  esi
            gog
09282
            pop
                  ebp
09283
            ret
09284
09285
     I * ______*
                             mem_rdw
09287 !*========*
09288 ! PUBLIC u16_t mem_rdw(U16_t segment, u16_t *offset);
09289 ! Load and return word at far pointer segment: offset.
09290
09291
            .align 16
    _mem_rdw:
09292
09293
                  cx, ds
           mov
09294
            mov
                  ds, 4(esp)
                                      ! segment
                  eax, 4+4(esp)
                                      ! offset
09295
           mov
           movzx eax, (eax)
                                      ! word to return
09296
09297
           mov
                  ds, cx
09298
09299
09300
09301 !*===========*
09302 !*
                              reset
09304 ! PUBLIC void reset();
09305 ! Reset the system by loading IDT with offset 0 and interrupting.
09306
09307 _reset:
09308
           lidt
                  (idt_zero)
                               ! anything goes, the 386 will not like it
09309
            int
09310
     .sect .data
09311 idt zero:
                   .data4 0, 0
09312
     .sect .text
09313
```

```
book.txt
Feb 25, 11 15:18
                                                   Page 114/393
     File: Page: 751 kernel/klib386.s
09314
09315 !*=======*
09316 1*
                          idle_task
idle task:
09318
09319 ! This task is called when the system has nothing else to do. The HLT
09320 ! instruction puts the processor in a state where it draws minimum power.
09321
          push
               halt
09322
          call
                level0
                           ! level0(halt)
09323
          pop
                eax
09324
          qmj
                idle task
09325 halt:
09326
          sti
09327
          h1t.
09328
          cli
09329
          ret.
09330
09331 !*========*
09332 !*
                        level0
09334 ! PUBLIC void level0(void (*func)(void))
09335
    ! Call a function at permission level 0. This allows kernel tasks to do
09336
    ! things that are only possible at the most privileged CPU level.
09337 !
09338 _level0:
09339
          mov
                eax, 4(esp)
09340
                ( level0 func), eax
          mov
09341
          int.
                LEVELO_VECTOR
09342
          ret.
09343
09344
09345 !*=======*
09346 !*
                        read_tsc
09347 !*=========*
09348 ! PUBLIC void read_tsc(unsigned long *high, unsigned long *low);
09349 ! Read the cycle counter of the CPU. Pentium and up.
09350 .align 16
09351 _read_tsc:
09352 .data1 0x0f
                      ! this is the RDTSC instruction
09353
     .data1 0x31
                     ! it places the TSC in EDX: EAX
09354
          push ebp
09355
          mov ebp, 8(esp)
          mov (ebp), edx
09356
09357
          mov ebp, 12(esp)
09358
          mov (ebp), eax
09359
          pop ebp
09360
          ret
09361
09362 !*========*
09363 !*
                         read_flags
09364 !*=========*
09365 ! PUBLIC unsigned long read_cpu_flags(void);
09366 ! Read CPU status flags from C.
09367 .align 16
    _read_cpu_flags:
09368
09369
          pushf
09370
          mov eax, (esp)
09371
          popf
09372
09373
```

```
book.txt
Feb 25, 11 15:18
                                                           Page 115/393
      File: Page: 752 kernel/utility.c
kernel/utility.c
09400 /* This file contains a collection of miscellaneous procedures:
09401 * panic:
                      abort MINIX due to a fatal error
      * kprintf:
09402
                      diagnostic output for the kernel
09403
      * Changes:
09404
      * Dec 10, 2004 kernel printing to circular buffer (Jorrit N. Herder)
09405
09406
      * This file contains the routines that take care of kernel messages, i.e., * diagnostic output within the kernel. Kernel messages are not directly
09407
09408
      * displayed on the console, because this must be done by the output driver.
09409
09410
       * Instead, the kernel accumulates characters in a buffer and notifies the
09411
      * output driver when a new message is ready.
09412
09413
09414 #include <minix/com.h>
09415 #include "kernel.h"
09416 #include <stdarg.h>
09417 #include <unistd.h>
09418 #include <stddef.h>
09419 #include <stdlib.h>
09420 #include <signal.h>
09421 #include "proc.h"
09422
09423 #define END_OF_KMESS -1
09424 FORWARD PROTOTYPE(void kputc, (int c));
09425
09426 /*=======*
09427 *
             panic
09428 *===========*/
09429 PUBLIC void panic(mess,nr)
09430 _CONST char *mess;
09431 int nr;
09432
09433
     /* The system has run aground of a fatal kernel error. Terminate execution. */
09434
       static int panicking = 0;
09435
       if (panicking ++) return;
                                      /* prevent recursive panics */
09436
09437
       if (mess != NULL) {
09438
            kprintf("\nKernel panic: %s", mess);
09439
            if (nr != NO NUM) kprintf(" %d", nr);
09440
            kprintf("\n",NO_NUM);
09441
09442
09443
       /* Abort MINIX. */
09444
       prepare_shutdown(RBT_PANIC);
09445
09447 /*============*
09448
                              kprintf
09449
       *========*/
09450
      PUBLIC void kprintf(const char *fmt, ...) /* format to be printed */
09451
09452
       int c:
                                            /* next character in fmt */
09453
       int d;
09454
       unsigned long u;
                                            /* hold number argument */
```

```
book.txt
Feb 25, 11 15:18
                                                                      Page 116/393
       File: Page: 753 kernel/utility.c
09455
        int base;
                                                     /* base of number arg */
09456
        int negative = 0;
                                                     /* print minus sign */
                                                     /* nr conversion table */
09457
        static char x2c[] = "0123456789ABCDEF";
        char ascii[8 * sizeof(long) / 3 + 2];
09458
                                                     /* string for ascii number */
                                                     /* string to be printed */
09459
        char *s = NULL;
09460
        va_list argp;
                                                     /* optional arguments */
09461
09462
                                                     /* init variable arguments */
        va_start(argp, fmt);
09463
09464
        while((c=*fmt++) != 0) {
09465
09466
            if (c == '%') {
                                                     /* expect format '%key' */
                switch(c = *fmt++) {
09467
                                                     /* determine what to do */
09468
09469
                /* Known keys are %d, %u, %x, %s, and %%. This is easily extended
09470
                 * with number types like %b and %o by providing a different base.
09471
                 * Number type keys don't set a string to 's', but use the general
09472
                 * conversion after the switch statement.
09473
                case 'd':
09474
                                                       /* output decimal */
09475
                    d = va_arg(argp, signed int);
09476
                    if (d < 0) { negative = 1; u = -d; } else { u = d; }
09477
                    base = 10;
09478
                    break;
09479
                case 'u':
                                                       /* output unsigned long */
09480
                    u = va_arg(argp, unsigned long);
09481
                    base = 10;
09482
                    break;
09483
                case 'x':
                                                       /* output hexadecimal */
                    u = va arg(argp, unsigned long);
09484
09485
                    base = 0x10;
09486
                    break;
09487
                case 's':
                                                      /* output string */
09488
                    s = va_arg(argp, char *);
                    if (s == NULL) s = "(null)";
09489
09490
                    break;
09491
                case '%':
                                                      /* output percent */
09492
                    s = "%":
09493
                    break;
09494
09495
                /* Unrecognized key. */
09496
                default:
                                                      /* echo back %key */
09497
                    s = "%?";
09498
                    s[1] = c;
                                                     /* set unknown key */
09499
09500
09501
                /* Assume a number if no string is set. Convert to ascii. */
09502
                if (s == NULL) {
09503
                    s = ascii + sizeof(ascii)-1;
09504
                    *s = 0;
09505
                    do { *--s = x2c[(u % base)]; } /* work backwards */
09506
                    while ((u /= base) > 0);
09507
09508
09509
                /* This is where the actual output for format "%key" is done. */
                09510
                                                     /* print string/ number */
09511
                                                     /* reset for next round */
09512
                s = NULL;
09513
09514
            élse {
```

```
book.txt
Feb 25, 11 15:18
                                                            Page 117/393
      File: Page: 754 kernel/utility.c
09515
              kputc(c);
                                              /* print and continue */
09516
09517
09518
       kputc(END_OF_KMESS);
                                              /* terminate output */
09519
                                              /* end variable arguments */
       va_end(argp);
09520 }
09522 /*==========*
09523 * kputc
       09524
09525 PRIVATE void kputc(c)
                                       /* character to append */
09527
09528 \not * Accumulate a single character for a kernel message. Send a notification
      * to the output driver if an END_OF_KMESS is encountered.
09529
09530
09531
       if (c != END_OF_KMESS) {
           kmess.km_buf[kmess.km_next] = c; /* put normal char in buffer */
09532
09533
           if (kmess.km_size < KMESS_BUF_SIZE)
09534
              kmess.km_size += 1;
09535
           kmess.km_next = (kmess.km_next + 1) % KMESS_BUF_SIZE;
09536
       } else {
09537
           send_sig(OUTPUT_PROC_NR, SIGKMESS);
09538
09539 }
kernel/system.h
09600 /* Function prototypes for the system library.
09601 * The implementation is contained in src/kernel/system/.
09602
09603 * The system library allows access to system services by doing a kernel call.
09604
       * Kernel calls are transformed into request messages to the SYS task that is
09605
      * responsible for handling the call. By convention, sys_call() is transformed
      * into a message with type SYS_CALL that is handled in a function do_call().
09607
09608
09609 #ifndef SYSTEM H
09610 #define SYSTEM H
09611
09612 /* Common includes for the system library. */
09613 #include "kernel.h"
09614 #include "proto.h"
09615 #include "proc.h"
09616
09617 /* Default handler for unused kernel calls. */
09618 _PROTOTYPE( int do_unused, (message *m_ptr) );
09619 _PROTOTYPE( int do_exec, (message *m_ptr) );
09620 _PROTOTYPE( int do_fork, (message *m_ptr) );
09621 _PROTOTYPE( int do_newmap, (message *m_ptr) );
09622 _PROTOTYPE( int do_exit, (message *m_ptr) );
09623 _PROTOTYPE( int do_trace, (message *m_ptr) );
09624 PROTOTYPE( int do nice, (message *m ptr) );
```

```
Feb 25, 11 15:18
                                                                  book.txt
                                                                                                                        Page 118/393
            File: Page: 755 kernel/system.h
 09625 _PROTOTYPE( int do_copy, (message *m_ptr) );
09626 #define do_vircopy do_copy
09627 #define do_physcopy do_copy
 09627 #define do_physcopy
09628 _PROTOTYPE( int do_vcopy, (message *m_ptr) );
09629 #define do_virvcopy do_vcopy
09630 #define do_physvcopy do_vcopy
09631 _PROTOTYPE( int do_umap, (message *m_ptr) );
09632 _PROTOTYPE( int do_memset, (message *m_ptr) );
09633 _PROTOTYPE( int do_abort, (message *m_ptr) );
09634 _PROTOTYPE( int do_getinfo, (message *m_ptr) );
09635 _PROTOTYPE( int do_privctl, (message *m_ptr) );
 09636 _PROTOTYPE( int do_segctl, (message *m_ptr) );
 09637 _PROTOTYPE( int do_irqctl, (message *m_ptr) );
09638 _PROTOTYPE( int do_devio, (message *m_ptr) );
 09639 _PROTOTYPE( int do_vdevio, (message *m_ptr) );
09640 _PROTOTYPE( int do_int86, (message *m_ptr) );
09641 _PROTOTYPE( int do_sdevio, (message *m_ptr) );
 09642 _PROTOTYPE( int do_kill, (message *m_ptr) );
09643 _PROTOTYPE( int do_getksig, (message *m_ptr) );
09644 _PROTOTYPE( int do_endksig, (message *m_ptr) );
 09645 _PROTOTYPE( int do_sigsend, (message *m_ptr) );
09648 _PROTOTYPE( int do_setalarm, (message *m_ptr) );
09649
09650 #endif /* SYSTEM H */
09651
09652
09653
kernel/system.c
09700 /* This task provides an interface between the kernel and user-space system
09701 * processes. System services can be accessed by doing a kernel call. Kernel
09702
             * calls are transformed into request messages, which are handled by this
            * task. By convention, a sys_call() is transformed in a SYS_CALL request
             * message that is handled in a function named do_call().
 09704
09705
 09706
             * A private call vector is used to map all kernel calls to the functions that
 09707
              * handle them. The actual handler functions are contained in separate files
09708
              * to keep this file clean. The call vector is used in the system task's main
             * loop to handle all incoming requests.
 09710
09711
             * In addition to the main sys_task() entry point, which starts the main loop,
             * there are several other minor entry points:
 09712
09713
             * get_priv: assign privilege structure to user or system process
send_sig: send a signal directly to a system process

09715 * cause_sig: take action to cause a signal to occur via PM

09716 * umap_local: map virtual address in LOCAL_SEG to physical

09717 * umap_remote: map virtual address in REMOTE CEC to the series of the series
           * umap_bios:
                                                     map virtual address in BIOS_SEG to physical
09718
09719
             * virtual_copy:
                                                     copy bytes from one virtual address to another
             * get_randomness:
09720
                                                     accumulate randomness in a buffer
09721
             * Changes:
09722
09723 * Aug 04, 2005 check if kernel call is allowed (Jorrit N. Herder)
09724 * Jul 20, 2005 send signal to services with message (Jorrit N. Herder)
```

```
book.txt
Feb 25, 11 15:18
                                                                    Page 119/393
      File: Page: 756 kernel/system.c
           Jan 15, 2005 new, generalized virtual copy function (Jorrit N. Herder)
09726
           Oct 10, 2004
                         dispatch system calls from call vector (Jorrit N. Herder)
09727
          Sep 30, 2004 source code documentation updated (Jorrit N. Herder)
09728 */
09729
09730 #include "kernel.h"
09731 #include "system.h"
09732 #include <stdlib.h>
09733 #include <signal.h>
09734 #include <unistd.h>
09735 #include <sys/sigcontext.h>
09736 #include <ibm/memory.h>
09737 #include "protect.h
09738
09739 /* Declaration of the call vector that defines the mapping of kernel calls
09740
      * to handler functions. The vector is initialized in sys_init() with map(),
09741
      * which makes sure the kernel call numbers are ok. No space is allocated,
      * because the dummy is declared extern. If an illegal call is given, the
09742
09743
       * array size will be negative and this won't compile.
09744 */
09745 PUBLIC int (*call_vec[NR_SYS_CALLS])(message *m_ptr);
09746
09747
      #define map(call_nr, handler) \
          {extern int dummy[NR_SYS_CALLS>(unsigned)(call_nr-KERNEL_CALL) ? 1: -1];} \
call_vec[(call_nr-KERNEL_CALL)] = (handler)
09748
09749
09750
09751 FORWARD PROTOTYPE( void initialize, (void));
09752
09753
      09754
                                  sys task
09755
       09756
      PUBLIC void sys_task()
09757
09758
      /* Main entry point of sys_task. Get the message and dispatch on type. */
09759
        static message m;
09760
        register int result;
        register struct proc *caller_ptr;
09761
09762
        unsigned int call_nr;
09763
        int s;
09764
09765
        /* Initialize the system task. */
09766
        initialize();
09767
09768
        while (TRUE) {
09769
            /* Get work. Block and wait until a request message arrives. */
09770
            receive(ANY, &m);
09771
            call_nr = (unsigned) m.m_type - KERNEL_CALL;
09772
            caller_ptr = proc_addr(m.m_source);
09773
09774
            /* See if the caller made a valid request and try to handle it. */
09775
            if (! (priv(caller_ptr)->s_call_mask & (1<<call_nr))) {</pre>
                kprintf("SYSTEM: request %d from %d denied.\n", call_nr,m.m_source);
09776
09777
                result = ECALLDENIED;
                                                   /* illegal message type */
            } else if (call_nr >= NR_SYS_CALLS) {
                                                          /* check call number */
09778
                kprintf("SYSTEM: illegal request %d from %d.\n", call_nr,m.m_source);
09779
09780
                result = EBADREQUEST;
                                                   /* illegal message type */
09781
09782
            else {
09783
                result = (*call_vec[call_nr])(&m); /* handle the kernel call */
09784
```

```
book.txt
Feb 25, 11 15:18
                                                                       Page 120/393
      File: Page: 757 kernel/system.c
09785
09786
             /* Send a reply, unless inhibited by a handler function. Use the kernel
              * function lock_send() to prevent a system call trap. The destination
09787
09788
              * is known to be blocked waiting for a message.
09789
            if (result != EDONTREPLY) {
09790
                                                      /* report status of call */
09791
                m.m_type = result;
09792
                if (OK != (s=lock_send(m.m_source, &m))) {
09793
                    kprintf("SYSTEM, reply to %d failed: %d\n", m.m_source, s);
09794
09795
09796
09797 }
09800
                                    initialize
09801
       *_____*/
09802
      PRIVATE void initialize(void)
09803
09804
        register struct priv *sp;
09805
        int i;
09806
09807
         /* Initialize IRQ handler hooks. Mark all hooks available. */
        for (i=0; i<NR IRO HOOKS; i++) {
09808
09809
            irq_hooks[i].proc_nr = NONE;
09810
09811
09812
         /* Initialize all alarm timers for all processes. */
09813
         for (sp=BEG_PRIV_ADDR; sp < END_PRIV_ADDR; sp++) {</pre>
09814
          tmr inittimer(&(sp->s alarm timer));
09815
09816
09817
         /* Initialize the call vector to a safe default handler. Some kernel calls
09818
          * may be disabled or nonexistant. Then explicitly map known calls to their
          * handler functions. This is done with a macro that gives a compile error
09819
09820
          * if an illegal call number is used. The ordering is not important here.
09821
09822
        for (i=0; i<NR_SYS_CALLS; i++) {
09823
            call vec[i] = do unused;
09824
09825
09826
         /* Process management. */
        map(SYS_FORK, do_fork);
09827
                                              /* a process forked a new process */
09828
        map(SYS_EXEC, do_exec);
                                              /* update process after execute */
09829
         map(SYS_EXIT, do_exit);
                                              /* clean up after process exit */
09830
         map(SYS_NICE, do_nice);
                                              /* set scheduling priority */
09831
         map(SYS_PRIVCTL, do_privctl);
                                              /* system privileges control */
09832
         map(SYS_TRACE, do_trace);
                                              /* request a trace operation */
09833
09834
        /* Signal handling. */
        map(SYS_KILL, do_kill);
map(SYS_GETKSIG, do_getksig);
09835
                                              /* cause a process to be signaled */
                                              /* PM checks for pending signals */
09836
                                              /* PM finished processing signal */
09837
         map(SYS_ENDKSIG, do_endksig);
         map(SYS SIGSEND, do sigsend);
                                              /* start POSIX-style signal */
09838
        map(SYS_SIGRETURN, do_sigreturn);
09839
                                              /* return from POSIX-style signal */
09840
09841
        /* Device I/O. */
                                              /* interrupt control operations */
09842
         map(SYS_IRQCTL, do_irqctl);
                                              /* inb, inw, inl, outb, outw, outl */
09843
        map(SYS_DEVIO, do_devio);
09844
         map(SYS SDEVIO, do sdevio);
                                              /* phys_insb, _insw, _outsb, _outsw */
```

```
book.txt
Feb 25, 11 15:18
                                                                  Page 121/393
      File: Page: 758 kernel/system.c
        map(SYS VDEVIO, do vdevio);
09845
                                           /* vector with devio requests */
09846
        map(SYS_INT86, do_int86);
                                           /* real-mode BIOS calls */
09847
09848
        /* Memory management. */
09849
        map(SYS_NEWMAP, do_newmap);
                                           /* set up a process memory map */
09850
        map(SYS_SEGCTL, do_segctl);
                                           /* add segment and get selector */
09851
        map(SYS_MEMSET, do_memset);
                                           /* write char to memory area */
09852
09853
        /* Copying. */
        map(SYS_UMAP, do_umap);
09854
                                           /* map virtual to physical address */
                                           /* use pure virtual addressing */
09855
        map(SYS_VIRCOPY, do_vircopy);
09856
        map(SYS_PHYSCOPY, do_physcopy);
                                           /* use physical addressing */
        map(SYS_VIRVCOPY, do_virvcopy);
                                           /* vector with copy requests */
09857
                                           /* vector with copy requests */
09858
        map(SYS_PHYSVCOPY, do_physvcopy);
09859
09860
        /* Clock functionality. */
09861
        map(SYS_TIMES, do_times);
                                           /* get uptime and process times */
09862
        map(SYS_SETALARM, do_setalarm);
                                           /* schedule a synchronous alarm */
09863
09864
        /* System control. */
09865
        map(SYS_ABORT, do_abort);
                                           /* abort MINIX */
09866
        map(SYS_GETINFO, do_getinfo);
                                           /* request system information */
09867
09869
     /*==================================
09870
                         get priv
09872 PUBLIC int get_priv(rc, proc_type)
09873 register struct proc *rc;
                                           /* new (child) process pointer */
                                          /* system or user process flag */
09874 int proc type;
09875
09876
      /* Get a privilege structure. All user processes share the same privilege
09877
      * structure. System processes get their own privilege structure.
09878
09879
        register struct priv *sp;
                                                  /* privilege structure */
09880
09881
        if (proc_type == SYS_PROC) {
                                                  /* find a new slot */
09882
            for (sp = BEG_PRIV_ADDR; sp < END_PRIV_ADDR; ++sp)
               if (sp->s_proc_nr == NONE && sp->s_id != USER_PRIV_ID) break;
09883
09884
            if (sp->s_proc_nr != NONE) return(ENOSPC);
09885
            rc->p priv = sp;
                                                  /* assign new slot */
            rc->p_priv->s_proc_nr = proc_nr(rc);
                                                  /* set association */
09886
09887
            rc->p_priv->s_flags = SYS_PROC;
                                                  /* mark as privileged */
09888
        } else {
           rc->p priv = &priv[USER PRIV ID];
                                                  /* use shared slot */
09889
09890
            rc->p_priv->s_proc_nr = INIT_PROC_NR;
                                                  /* set association */
09891
            rc->p_priv->s_flags = 0;
                                                  /* no initial flags */
09892
09893
        return(OK);
09894
09896
     /*_____*
09897
                        get_randomness
      09899 PUBLIC void get_randomness(source)
09900
      int source;
09901
09902
     /* On machines with the RDTSC (cycle counter read instruction - pentium
      * and up), use that for high-resolution raw entropy gathering. Otherwise,
09903
09904 * use the realtime clock (tick resolution).
```

```
book.txt
Feb 25, 11 15:18
                                                               Page 122/393
      File: Page: 759 kernel/system.c
09905
09906
      * Unfortunately this test is run-time - we don't want to bother with
09907
      * compiling different kernels for different machines.
09908
       * On machines without RDTSC, we use read_clock().
09909
09910
09911
       int r next;
09912
       unsigned long tsc_high, tsc_low;
09913
09914
       source %= RANDOM_SOURCES;
09915
       r next= krandom.bin[source].r next;
09916
        if (machine.processor > 486)
09917
           read_tsc(&tsc_high, &tsc_low);
09918
           krandom.bin[source].r_buf[r_next] = tsc_low;
09919
09920
           krandom.bin[source].r buf[r next] = read clock();
09921
09922
        if (krandom.bin[source].r_size < RANDOM_ELEMENTS) {
09923
             krandom.bin[source].r size ++;
09924
09925
       krandom.bin[source].r_next = (r_next + 1 ) % RANDOM_ELEMENTS;
09926
09928 /*-----*
09929
                                send_sig
09930
      *-----*/
09931 PUBLIC void send_sig(proc_nr, sig_nr)
      int proc_nr;
09932
                                  /* system process to be signalled */
                                 /* signal to be sent, 1 to _NSIG */
09933
     int sig_nr;
09934
09935 /* Notify a system process about a signal. This is straightforward. Simply
09936
      * set the signal that is to be delivered in the pending signals map and
09937
      * send a notification with source SYSTEM.
09938
09939
       register struct proc *rp;
09940
09941
       rp = proc_addr(proc_nr);
09942
       sigaddset(&priv(rp)->s_sig_pending, sig_nr);
09943
       lock notify(SYSTEM, proc nr);
09944
09946 /*==========*
09947
                               cause_sig
09949 PUBLIC void cause_sig(proc_nr, sig_nr)
09950 int proc_nr;
                                 /* process to be signalled */
09951 int sig_nr;
                                 /* signal to be sent, 1 to _NSIG */
09952
09953 /* A system process wants to send a signal to a process. Examples are:
09954 * - HARDWARE wanting to cause a SIGSEGV after a CPU exception
      * - TTY wanting to cause SIGINT upon getting a DEL
09955
      * - FS wanting to cause SIGPIPE for a broken pipe
09956
      * Signals are handled by sending a message to PM. This function handles the
09957
      * signals and makes sure the PM gets them by sending a notification. The
09959
       * process being signaled is blocked while PM has not finished all signals
09960
       * for it.
      * Race conditions between calls to this function and the system calls that
09961
09962
       * process pending kernel signals cannot exist. Signal related functions are
      * only called when a user process causes a CPU exception and from the kernel
09963
      * process level, which runs to completion.
```

```
book.txt
Feb 25, 11 15:18
                                                                   Page 123/393
      File: Page: 760 kernel/system.c
09965
09966
        register struct proc *rp;
09967
09968
        /* Check if the signal is already pending. Process it otherwise. */
09969
        rp = proc_addr(proc_nr);
09970
        if (! sigismember(&rp->p_pending, sig_nr)) {
09971
            sigaddset(&rp->p_pending, sig_nr);
09972
            if (! (rp->p_rts_flags & SIGNALED)) {
                                                          /* other pending */
09973
                if (rp->p_rts_flags == 0) lock_dequeue(rp); /* make not ready */
               rp->p_rts_flags |= SIGNALED | SIG_PENDING;
09974
                                                        /* update flags */
               send_sig(PM_PROC_NR, SIGKSIG);
09975
09976
09977
09978 }
09980 /*==========*
09981 *
                               umap_local
09983 PUBLIC phys_bytes umap_local(rp, seg, vir_addr, bytes)
09984 register struct proc *rp; /* pointer to proc table entry for process */
09985 int seg;
                                   /* T, D, or S segment */
09986 vir_bytes vir_addr;
                                  /* virtual address in bytes within the seg */
                                   /* # of bytes to be copied */
09987
      vir_bytes bytes;
09988
09989
      /* Calculate the physical memory address for a given virtual address. */
                        /* the virtual address in clicks */
09990
       vir clicks vc;
                                   /* intermediate variables as phys_bytes */
09991
        phys bytes pa;
09992
        phys_bytes seg_base;
09993
09994
        /* If 'seg' is D it could really be S and vice versa. T really means T.
         * If the virtual address falls in the gap, it causes a problem. On the
09995
09996
         * 8088 it is probably a legal stack reference, since "stackfaults" are
09997
         * not detected by the hardware. On 8088s, the gap is called S and
09998
         * accepted, but on other machines it is called D and rejected.
09999
         * The Atari ST behaves like the 8088 in this respect.
10000
10001
10002
        if (bytes <= 0) return( (phys_bytes) 0);
        if (vir_addr + bytes <= vir_addr) return 0; /* overflow */</pre>
10003
10004
        vc = (vir_addr + bytes - 1) >> CLICK_SHIFT; /* last click of data */
10005
10006
        if (seq != T)
10007
              seg = (vc < rp->p_memmap[D].mem_vir + rp->p_memmap[D].mem_len ? D : S);
10008
10009
        if ((vir addr>>CLICK SHIFT) >= rp->p memmap[seq].mem vir +
10010
              rp->p_memmap[seg].mem_len) return( (phys_bytes) 0 );
10011
10012
        if (vc >= rp->p_memmap[seg].mem_vir +
10013
             rp->p_memmap[seg].mem_len) return((phys_bytes) 0);
10014
10015
        seg_base = (phys_bytes) rp->p_memmap[seg].mem_phys;
        seg_base = seg_base << CLICK_SHIFT; /* segment origin in bytes */</pre>
10016
10017
        pa = (phys_bytes) vir_addr;
        pa -= rp->p_memmap[seg].mem_vir << CLICK_SHIFT;
10018
10019
        return(seg_base + pa);
10020 }
```

```
book.txt
Feb 25, 11 15:18
                                                             Page 124/393
      File: Page: 761 kernel/system.c
10023 *
                               umap_remote
10025 PUBLIC phys_bytes umap_remote(rp, seg, vir_addr, bytes)
10026 register struct proc *rp; /* pointer to proc table entry for process */
10027 int seg; /* index of remote segment */
10028 vir_bytes vir_addr;
                                 /* virtual address in bytes within the seg */
                                /* # of bytes to be copied */
10029 vir_bytes bytes;
10030
10031
      /* Calculate the physical memory address for a given virtual address. */
10032
       struct far mem *fm;
10033
       if (bytes <= 0) return( (phys_bytes) 0);
if (seg < 0 || seg >= NR_REMOTE_SEGS) return( (phys_bytes) 0);
10034
10035
10036
10037
       fm = &rp->p_priv->s_farmem[seg];
10038
       if (! fm->in_use) return( (phys_bytes) 0);
       if (vir_addr + bytes > fm->mem_len) return( (phys_bytes) 0);
10039
10040
10041
       return(fm->mem_phys + (phys_bytes) vir_addr);
10042 }
10044 /*=======*
10045 *
                              umap bios
10046
      10047 PUBLIC phys_bytes umap_bios(rp, vir_addr, bytes)
10048 register struct proc *rp; /* pointer to proc table entry for process */
10049 vir_bytes vir_addr;
                                 /* virtual address in BIOS segment */
                                /* # of bytes to be copied */
10050 vir_bytes bytes;
10051
10052 \not * Calculate the physical memory address at the BIOS. Note: currently, BIOS
     * address zero (the first BIOS interrupt vector) is not considered as an
10053
      * error here, but since the physical address will be zero as well, the
10055
      * calling function will think an error occurred. This is not a problem,
      * since no one uses the first BIOS interrupt vector.
10056
10057
10058
10059
       /* Check all acceptable ranges. */
10060
       if (vir_addr >= BIOS_MEM_BEGIN && vir_addr + bytes <= BIOS_MEM_END)
10061
            return (phys_bytes) vir_addr;
10062
       else if (vir_addr >= BASE_MEM_TOP && vir_addr + bytes <= UPPER_MEM_END)
            return (phys bytes) vir addr;
10063
10064
       kprintf("Warning, error in umap_bios, virtual address 0x%x\n", vir_addr);
10065
       return 0;
10066
virtual_copy
10070 *============*/
10071 PUBLIC int virtual_copy(src_addr, dst_addr, bytes)
10072 struct vir_addr *src_addr; /* source virtual address */
10073 struct vir_addr *dst_addr;
                                /* destination virtual address */
                                /* # of bytes to copy */
10074 vir_bytes bytes;
10075
10076
      /* Copy bytes from virtual address src_addr to virtual address dst_addr.
      * Virtual addresses can be in ABS, LOCAL_SEG, REMOTE_SEG, or BIOS_SEG.
10077
10078
       struct vir_addr *vir_addr[2]; /* virtual source and destination address */
10079
                                /* absolute source and destination */
10080
       phys_bytes phys_addr[2];
10081
       int seg index;
```

```
book.txt
 Feb 25, 11 15:18
                                                                   Page 125/393
       File: Page: 762 kernel/system.c
10082
        int i;
10083
10084
         /* Check copy count. */
10085
        if (bytes <= 0) return(EDOM);
10086
10087
         /* Do some more checks and map virtual addresses to physical addresses. */
        vir_addr[_SRC_] = src_addr;
vir_addr[_DST_] = dst_addr;
10088
10089
        for (i=_SRC_; i<=_DST_; i++) {
10090
10091
10092
            /* Get physical address. */
10093
            switch((vir addr[i]->segment & SEGMENT TYPE)) {
10094
            case LOCAL_SEG:
10095
                seg_index = vir_addr[i]->segment & SEGMENT_INDEX;
10096
                phys addr[i] = umap local( proc addr(vir addr[i]->proc nr),
10097
                    seg_index, vir_addr[i]->offset, bytes );
10098
10099
            case REMOTE SEG:
10100
                seg_index = vir_addr[i]->segment & SEGMENT_INDEX;
10101
                phys_addr[i] = umap_remote( proc_addr(vir_addr[i]->proc_nr),
                   seg_index, vir_addr[i]->offset, bytes );
10102
10103
                break;
10104
            case BIOS SEG:
10105
                phys addr[i] = umap bios( proc addr(vir addr[i]->proc nr),
                    vir_addr[i]->offset, bytes );
10106
10107
                break;
10108
            case PHYS SEG:
10109
                phys_addr[i] = vir_addr[i]->offset;
10110
                break;
            default:
10111
10112
                return(EINVAL);
10113
10114
10115
            /* Check if mapping succeeded. */
            if (phys_addr[i] <= 0 && vir_addr[i]->segment != PHYS_SEG)
10116
10117
                return(EFAULT);
10118
10119
10120
         /* Now copy bytes between physical addresseses. */
10121
        phys_copy(phys_addr[_SRC_], phys_addr[_DST_], (phys_bytes) bytes);
10122
        return(OK);
10123 }
kernel/system/do_setalarm.c
10200 /* The kernel call implemented in this file:
10201 * m_type: SYS_SETALARM
10202
10203
       * The parameters for this kernel call are:
            m2_11:
10204
                      ALRM_EXP_TIME
                                             (alarm's expiration time)
10205
            m2 i2:
                      ALRM ABS TIME
                                             (expiration time is absolute?)
10206
            m2 11:
                      ALRM TIME LEFT
                                             (return seconds left of previous)
10207
10208
10209 #include "../system.h"
```

```
Feb 25, 11 15:18
                                   book.txt
                                                                Page 126/393
      File: Page: 763 kernel/system/do setalarm.c
10210
10211
      #if USE_SETALARM
10212
10213 FORWARD _PROTOTYPE( void cause_alarm, (timer_t *tp) );
10214
10215
      10216
                                  do setalarm
       *----*/
10217
10218 PUBLIC int do setalarm(m ptr)
      message *m_ptr;
                                  /* pointer to request message */
10219
10220
10221
      /* A process requests a synchronous alarm, or wants to cancel its alarm. */
                                  /* pointer to requesting process */
10222
        register struct proc *rp;
                                  /* which process wants the alarm */
10223
        int proc_nr;
                                  /* expiration time for this alarm */
10224
        long exp time;
10225
                                  /* use absolute or relative time */
        int use_abs_time;
10226
        timer_t *tp;
                                  /* the process' timer structure */
10227
        clock_t uptime;
                                  /* placeholder for current uptime */
10228
10229
        /* Extract shared parameters from the request message. */
10230
        exp_time = m_ptr->ALRM_EXP_TIME; /* alarm's expiration time */
        use_abs_time = m_ptr->ALRM_ABS_TIME; /* flag for absolute time */
10231
10232
        proc_nr = m_ptr->m_source;
                                         /* process to interrupt later */
10233
        rp = proc addr(proc nr);
10234
        if (! (priv(rp)->s_flags & SYS_PROC)) return(EPERM);
10235
10236
        /* Get the timer structure and set the parameters for this alarm. */
10237
        tp = &(priv(rp)->s_alarm_timer);
10238
        tmr_arg(tp)->ta_int = proc_nr;
10239
        tp->tmr func = cause alarm;
10240
10241
        /* Return the ticks left on the previous alarm. */
10242
        uptime = get_uptime();
10243
        if ((tp->tmr_exp_time != TMR_NEVER) && (uptime < tp->tmr_exp_time) ) {
10244
           m_ptr->ALRM_TIME_LEFT = (tp->tmr_exp_time - uptime);
10245
           m_ptr->ALRM_TIME_LEFT = 0;
10246
10247
10248
        /* Finally, (re)set the timer depending on the expiration time. */
10249
10250
        if (exp time == 0) {
10251
           reset timer(tp);
10252
        } else {
10253
           tp->tmr_exp_time = (use_abs_time) ? exp_time : exp_time + get_uptime();
10254
           set_timer(tp, tp->tmr_exp_time, tp->tmr_func);
10255
10256
        return(OK);
10257
10259
     /*========*
                                 cause_alarm
10261
       10262 PRIVATE void cause_alarm(tp)
10263 timer t *tp;
10264
10265
      /* Routine called if a timer goes off and the process requested a synchronous
       * alarm. The process number is stored in timer argument 'ta_int'. Notify that
10266
       * process with a notification message from CLOCK.
10267
10268
10269
       int proc nr = tmr arg(tp)->ta int;
                                                /* get process number */
```

```
Feb 25, 11 15:18
                                  book.txt
                                                               Page 127/393
      File: Page: 764 kernel/system/do setalarm.c
        lock_notify(CLOCK, proc_nr);
10270
                                                /* notify process */
10271
10273 #endif /* USE SETALARM */
kernel/svstem/do exec.c
10300 /* The kernel call implemented in this file:
10301 * m_type: SYS_EXEC
10302
      * The parameters for this kernel call are:
10303
      * ml_i1: PR_PROC_NR
* ml_p1: PR_STACK_PTR
                                  (process that did exec call)
10304
10305
                     PR STACK PTR
                                          (new stack pointer)
           m1_p1:
10306
           m1_p2:
                     PR_NAME_PTR
                                          (pointer to program name)
      * m1_p3:
10307
                    PR_IP_PTR
                                         (new instruction pointer)
10308
      * /
10309 #include "../system.h"
10310 #include <string.h>
10311 #include <signal.h>
10312
10313 #if USE EXEC
10314
10315
10316
                                do exec
10317
      10318 PUBLIC int do_exec(m_ptr)
10319 register message *m ptr;
                                /* pointer to request message */
10320
10321
      /* Handle sys_exec(). A process has done a successful EXEC. Patch it up. */
10322
       register struct proc *rp;
10323
        reg_t sp;
                                  /* new sp */
10324
        phys_bytes phys_name;
10325
        char *np;
10326
10327
        rp = proc_addr(m_ptr->PR_PROC_NR);
10328
        sp = (reg_t) m_ptr->PR_STACK_PTR;
10329
        rp->p_reg.sp = sp;
                          /* set the stack pointer */
        phys_memset(vir2phys(&rp->p_ldt[EXTRA_LDT_INDEX]), 0,
10330
             (LDT_SIZE - EXTRA_LDT_INDEX) * sizeof(rp->p_ldt[0]));
10331
        10332
10333
10334
        if (rp->p_rts_flags == 0) lock_enqueue(rp);
10335
10336
        /* Save command name for debugging, ps(1) output, etc. */
10337
        phys_name = numap_local(m_ptr->m_source, (vir_bytes) m_ptr->PR_NAME_PTR,
10338
                                        (vir_bytes) P_NAME_LEN - 1);
10339
        if (phys_name != 0) {
             phys_copy(phys_name, vir2phys(rp->p_name), (phys_bytes) P_NAME_LEN - 1);
10340
10341
             for (np = rp->p_name; (*np & BYTE) >= ' '; np++) {}
10342
             *np = 0;
                                                       /* mark end */
10343
        } else {
10344
             strncpy(rp->p_name, "<unset>", P_NAME_LEN);
10345
10346
        return(OK);
10347
      #endif /* USE_EXEC */
10348
```

```
book.txt
 Feb 25, 11 15:18
                                                                    Page 128/393
       File: Page: 765 kernel/clock.c
kernel/clock c
10400 /* This file contains the clock task, which handles time related functions.
10401 * Important events that are handled by the CLOCK include setting and
       * monitoring alarm timers and deciding when to (re)schedule processes.
10402
       * The CLOCK offers a direct interface to kernel processes. System services
10404
       * can access its services through system calls, such as sys_setalarm(). The
        * CLOCK task thus is hidden from the outside world.
10405
10406
       * Changes:
10407
       * Oct 08, 2005 reordering and comment editing (A. S. Woodhull)
10408
10409
           Mar 18, 2004 clock interface moved to SYSTEM task (Jorrit N. Herder)
10410
           Sep 30, 2004
                        source code documentation updated (Jorrit N. Herder)
10411
        * Sep 24, 2004 redesigned alarm timers (Jorrit N. Herder)
10412
10413
       * The function do_clocktick() is triggered by the clock's interrupt
       * handler when a watchdog timer has expired or a process must be scheduled.
10414
10415
10416
       * In addition to the main clock_task() entry point, which starts the main
        * loop, there are several other minor entry points:
10417
       * clock stop: called just before MINIX shutdown
10418
10419
           get_uptime:
                              get realtime since boot in clock ticks
10420
           set timer:
                              set a watchdog timer (+)
       * reset_timer:
10421
                              reset a watchdog timer (+)
       * read_clock:
10422
                              read the counter of channel 0 of the 8253A timer
10423
       * (+) The CLOCK task keeps tracks of watchdog timers for the entire kernel.
10424
       * The watchdog functions of expired timers are executed in do clocktick().
10425
10426
       * It is crucial that watchdog functions not block, or the CLOCK task may
10427
       * be blocked. Do not send() a message when the receiver is not expecting it.
10428
       * Instead, notify(), which always returns, should be used.
10429
10430
10431 #include "kernel.h"
10432 #include "proc.h"
10433 #include <signal.h>
10434 #include <minix/com.h>
10435
10436 /* Function prototype for PRIVATE functions. */
10437 FORWARD _PROTOTYPE( void init_clock, (void) );
10438 FORWARD _PROTOTYPE( int clock_handler, (irg_hook_t *hook) );
10439 FORWARD _PROTOTYPE( int do_clocktick, (message *m_ptr) );
10440
10441
       /* Clock parameters. */
10442 #define COUNTER_FREQ (2*TIMER_FREQ) /* counter frequency using square wave */
10443
       #define LATCH_COUNT 0x00 /* cc00xxxx, c = channel, x = any */
                                     /* ccaammmb, a = access, m = mode, b = BCD */
10444
      #define SQUARE_WAVE
                             0x36
                                     /* 11x11, 11 = LSB then MSB, x11 = sq wave */
10445
10446
       #define TIMER_COUNT ((unsigned) (TIMER_FREQ/HZ)) /* initial value for counter*/
10447
       #define TIMER_FREQ 1193182L /* clock frequency for timer in PC and AT */
10448
10449
      #define CLOCK_ACK_BIT 0x80
                                   /* PS/2 clock interrupt acknowledge bit */
10450
10451 /* The CLOCK's timers queue. The functions in <timers.h> operate on this.
       * Each system process possesses a single synchronous alarm timer. If other
10452
      * kernel parts want to use additional timers, they must declare their own
10453
10454 * persistent (static) timer structure, which can be passed to the clock
```

```
book.txt
Feb 25, 11 15:18
                                                                 Page 129/393
      File: Page: 766 kernel/clock.c
10455
       * via (re)set timer().
10456
      * When a timer expires its watchdog function is run by the CLOCK task.
10457
10458 PRIVATE timer_t *clock_timers;
                                          /* queue of CLOCK timers */
10459 PRIVATE clock_t next_timeout;
                                          /* realtime that next timer expires */
10460
10461 /* The time is incremented by the interrupt handler on each clock tick. */
10462 PRIVATE clock_t realtime;
                                         /* real time clock */
10463 PRIVATE irg hook t clock hook;
                                          /* interrupt handler hook */
10464
10465
10466 *
                                 clock task
       *----*/
10467
      PUBLIC void clock_task()
10468
10469
10470
      /* Main program of clock task. If the call is not HARD INT it is an error.
10471
10472
        message m;
                                   /* message buffer for both input and output */
10473
        int result;
                                   /* result returned by the handler */
10474
10475
        init clock();
                                   /* initialize clock task */
10476
10477
        /* Main loop of the clock task. Get work, process it. Never reply. */
10478
        while (TRUE) {
10479
10480
            /* Go get a message. */
           receive(ANY, &m);
10481
10482
            /* Handle the request. Only clock ticks are expected. */
10483
10484
           switch (m.m type) {
           case HARD_INT:
10485
10486
               result = do_clocktick(&m);    /* handle clock tick */
10487
10488
           default:
                                           /* illegal request type */
               kprintf("CLOCK: illegal request %d from %d.\n", m.m_type,m.m_source);
10489
10490
10491
10492 }
10494 /*=========*
10495
                                  do clocktick
10497 PRIVATE int do_clocktick(m_ptr)
10498
      message *m_ptr;
                                          /* pointer to request message */
10499
      /* Despite its name, this routine is not called on every clock tick. It
10500
10501
       * is called on those clock ticks when a lot of work needs to be done.
10502
10503
10504
        /* A process used up a full quantum. The interrupt handler stored this
10505
         * process in 'prev_ptr'. First make sure that the process is not on the
10506
         * scheduling queues. Then announce the process ready again. Since it has
10507
         * no more time left, it gets a new quantum and is inserted at the right
10508
         * place in the queues. As a side-effect a new process will be scheduled.
10509
10510
        if (prev_ptr->p_ticks_left <= 0 && priv(prev_ptr)->s_flags & PREEMPTIBLE) {
           10511
                                          /* and reinsert it again */
10512
            lock_enqueue(prev_ptr);
10513
10514
```

```
Feb 25, 11 15:18
                                 book.txt
                                                             Page 130/393
      File: Page: 767 kernel/clock.c
10515
       /* Check if a clock timer expired and run its watchdog function. */
10516
       if (next_timeout <= realtime) {
10517
            tmrs_exptimers(&clock_timers, realtime, NULL);
10518
            next_timeout = clock_timers == NULL ?
10519
                   TMR_NEVER : clock_timers->tmr_exp_time;
10520
10521
       /* Inhibit sending a reply. */
10522
       return(EDONTREPLY);
10523
10524
     10527
                               init clock
10528
       *_____*
     PRIVATE void init clock()
10529
10530
10531
       /* Initialize the CLOCK's interrupt hook. */
10532
       clock_hook.proc_nr = CLOCK;
10533
10534
       /* Initialize channel 0 of the 8253A timer to, e.g., 60 Hz. */
10535
       outb(TIMER_MODE, SQUARE_WAVE); /* set timer to run continuously */
       outb(TIMERO, TIMER_COUNT);
10536
                                       /* load timer low byte */
10537
       outb(TIMER0, TIMER_COUNT >> 8);
                                      /* load timer high byte */
       put_irg_handler(&clock_hook, CLOCK_IRQ, clock_handler);/* register handler */
10538
10539
       enable_irq(&clock_hook);
                                       /* ready for clock interrupts */
10540 }
10543 *
                               clock_stop
10545 PUBLIC void clock stop()
10546
10547 /* Reset the clock to the BIOS rate. (For rebooting) */
10548
      outb(TIMER_MODE, 0x36);
10549
       outb(TIMER0, 0);
10550
       outb(TIMER0, 0);
10551 }
                              clock handler
10554
10555
      *-----*/
10556 PRIVATE int clock handler(hook)
     irq_hook_t *hook;
10557
10558
10559
     /* This executes on each clock tick (i.e., every time the timer chip generates
10560
      * an interrupt). It does a little bit of work so the clock task does not have
10561
      * to be called on every tick. The clock task is called when:
10562
10563
             (1) the scheduling quantum of the running process has expired, or
10564
            (2) a timer has expired and the watchdog function should be run.
10565
10566
      * Many global global and static variables are accessed here. The safety of
       * this must be justified. All scheduling and message passing code acquires a
10567
       * lock by temporarily disabling interrupts, so no conflicts with calls from
10568
10569
       * the task level can occur. Furthermore, interrupts are not reentrant, the
       * interrupt handler cannot be bothered by other interrupts.
10570
10571
      * Variables that are updated in the clock's interrupt handler:
10572
10573
            lost_ticks:
10574
                   Clock ticks counted outside the clock task. This for example
```

```
book.txt
Feb 25, 11 15:18
                                                                Page 131/393
      File: Page: 768 kernel/clock.c
10575
                    is used when the boot monitor processes a real mode interrupt.
10576
             realtime:
10577
                   The current uptime is incremented with all outstanding ticks.
10578
             proc_ptr, bill_ptr:
10579
                    These are used for accounting. It does not matter if proc.c
10580
                    is changing them, provided they are always valid pointers,
10581
                    since at worst the previous process would be billed.
10582
10583
       register unsigned ticks;
10584
10585
        /* Acknowledge the PS/2 clock interrupt. */
10586
        if (machine.ps mca) outb(PORT B, inb(PORT B) | CLOCK ACK BIT);
10587
        /* Get number of ticks and update realtime. */
10588
10589
        ticks = lost ticks + 1;
10590
        lost ticks = 0;
10591
        realtime += ticks;
10592
10593
        /* Update user and system accounting times. Charge the current process for
10594
         * user time. If the current process is not billable, that is, if a non-user
10595
         * process is running, charge the billable process for system time as well.
10596
         * Thus the unbillable process' user time is the billable user's system time.
10597
10598
        proc ptr->p user time += ticks;
        if (priv(proc_ptr)->s_flags & PREEMPTIBLE) {
10599
10600
           proc_ptr->p_ticks_left -= ticks;
10601
10602
        if (! (priv(proc_ptr)->s_flags & BILLABLE)) {
10603
           bill_ptr->p_sys_time += ticks;
           bill ptr->p ticks left -= ticks;
10604
10605
10606
10607
        /* Check if do_clocktick() must be called. Done for alarms and scheduling.
10608
        * Some processes, such as the kernel tasks, cannot be preempted.
10609
10610
        if ((next_timeout <= realtime) || (proc_ptr->p_ticks_left <= 0)) {</pre>
           prev_ptr = proc_ptr;
10611
                                                /* store running process */
           lock_notify(HARDWARE, CLOCK);
                                                /* send notification */
10612
10613
10614
       return(1);
                                                /* reenable interrupts */
10615
10618
                                get_uptime
10619
10620 PUBLIC clock_t get_uptime()
10621
10622 /* Get and return the current clock uptime in ticks. */
10623
       return(realtime);
10624 }
10626 /*==========*
10627 *
                       set timer
10629 PUBLIC void set_timer(tp, exp_time, watchdog)
10630 struct timer *tp; /* pointer to timer structure */
10631 clock_t exp_time;
                                 /* expiration realtime */
10632 tmr_func_t watchdog;
                                /* watchdog to be called */
10633
10634 /* Insert the new timer in the active timers list. Always update the
```

```
Feb 25, 11 15:18
                                   book.txt
                                                                Page 132/393
      File: Page: 769 kernel/clock.c
10635
       * next timeout time by setting it to the front of the active list.
10636
10637
        tmrs_settimer(&clock_timers, tp, exp_time, watchdog, NULL);
10638
        next timeout = clock timers->tmr exp time;
10639 }
10641 /*=========*
10642 *
                                reset timer
10643
10644 PUBLIC void reset_timer(tp)
10645 struct timer *tp;
                                  /* pointer to timer structure */
10646
10647 /* The timer pointed to by 'tp' is no longer needed. Remove it from both the
      * active and expired lists. Always update the next timeout time by setting
10648
      * it to the front of the active list.
10649
10650
10651
       tmrs_clrtimer(&clock_timers, tp, NULL);
       next_timeout = (clock_timers == NULL) ?
10652
10653
             TMR_NEVER : clock_timers->tmr_exp_time;
10654 }
10656 /*==========*
10657 *
                        read_clock
10658
      10659 PUBLIC unsigned long read_clock()
10660
10661 /* Read the counter of channel 0 of the 8253A timer. This counter counts
10662
       * down at a rate of TIMER_FREQ and restarts at TIMER_COUNT-1 when it
       * reaches zero. A hardware interrupt (clock tick) occurs when the counter
10663
       * gets to zero and restarts its cycle.
10664
10665
10666
       unsigned count;
10667
10668
        outb(TIMER_MODE, LATCH_COUNT);
10669
       count = inb(TIMER0);
10670
       count |= (inb(TIMER0) << 8);
10671
10672
       return count;
10673 }
                               drivers/drivers.h
10700 /* This is the master header for all device drivers. It includes some other
10701 * files and defines the principal constants.
10702 */
10703 #define _POSIX_SOURCE
                                 /* tell headers to include POSIX stuff */
                             1 /* tell headers to include MINIX stuff */
1 /* tell headers to include MINIX stuff */
1 /* get negative error number in <errno.h> */
10704 #define _MINIX
10705 #define _SYSTEM
10706
10707 /* The following are so basic, all the *.c files get them automatically. */
10708 #include <minix/config.h> /* MUST be first */
10709 #include <ansi.h>
                                  /* MUST be second */
10710 #include <minix/type.h>
10711 #include <minix/com.h>
10712 #include <minix/dmap.h>
10713 #include <minix/callnr.h>
10714 #include <sys/types.h>
```

```
book.txt
 Feb 25, 11 15:18
                                                                   Page 133/393
       File: Page: 770 drivers/drivers.h
10715 #include <minix/const.h>
10716 #include <minix/devio.h>
10717 #include <minix/syslib.h>
10718 #include <minix/sysutil.h>
10719 #include <minix/bitmap.h>
10720
10721 #include <ibm/interrupt.h>
                                    /* IRQ vectors and miscellaneous ports */
10722 #include <ibm/bios.h>
                                    /* BIOS index numbers */
10723 #include <ibm/ports.h>
                                    /* Well-known ports */
10724
10725 #include <string.h>
10726 #include <signal.h>
10727 #include <stdlib.h>
10728 #include <limits.h>
10729 #include <stddef.h>
10730 #include <errno.h>
10731 #include <unistd.h>
10732
drivers/libdriver/driver.h
10800 /* Types and constants shared between the generic and device dependent
10801 * device driver code.
10802 */
10803
10804 #define POSIX SOURCE
                               1 /* tell headers to include POSIX stuff */
                              1  /* tell headers to include MINIX stuff */
1  /* get negative error number in <errno.h> */
10805 #define _MINIX
10806 #define _SYSTEM
10808 /* The following are so basic, all the *.c files get them automatically. */
10809 #include <minix/config.h> /* MUST be first */
10810 #include <ansi.h>
                                   /* MUST be second */
10811 #include <minix/type.h>
10812 #include <minix/ipc.h>
10813 #include <minix/com.h>
10814 #include <minix/callnr.h>
10815 #include <sys/types.h>
10816 #include <minix/const.h>
10817 #include <minix/syslib.h>
10818 #include <minix/sysutil.h>
10820 #include <string.h>
10821 #include <limits.h>
10822 #include <stddef.h>
10823 #include <errno.h>
10824
10825 #include <minix/partition.h>
10826 #include <minix/u64.h>
10827
10828 /* Info about and entry points into the device dependent code. */
10829 struct driver
       _PROTOTYPE( char *(*dr_name), (void) );
10830
        _PROTOTYPE( int (*dr_open), (struct driver *dp, message *m_ptr) );
10831
        _PROTOTYPE( int (*dr_close), (struct driver *dp, message *m_ptr) );
10832
        _PROTOTYPE( int (*dr_ioctl), (struct driver *dp, message *m_ptr) );
10833
        PROTOTYPE( struct device *(*dr prepare), (int device) );
```

```
Feb 25, 11 15:18
                                       book.txt
                                                                        Page 134/393
       File: Page: 771 drivers/libdriver/driver.h
10835
         _PROTOTYPE( int (*dr_transfer), (int proc_nr, int opcode, off_t position,
10836
                                              iovec_t *iov, unsigned nr_req) );
10837
         _PROTOTYPE( void (*dr_cleanup), (void) );
10838
         _PROTOTYPE( void (*dr_geometry), (struct partition *entry) );
         _PROTOTYPE( void (*dr_signal), (struct driver *dp, message *m_ptr) );
10839
10840
         _PROTOTYPE( void (*dr_alarm), (struct driver *dp, message *m_ptr) );
10841
         _PROTOTYPE( int (*dr_cancel), (struct driver *dp, message *m_ptr) );
10842
         _PROTOTYPE( int (*dr_select), (struct driver *dp, message *m_ptr) );
      _PROTOTYPE( int (*dr_other), (struct driver *dp, message *m_ptr) );
10843
10844
10845
10846
10847 #if (CHIP == INTEL)
10848
10849
       /* Number of bytes you can DMA before hitting a 64K boundary: */
       #define dma_bytes_left(phys) \
10850
10851
          ((unsigned) (sizeof(int) == 2 ? 0 : 0x10000) - (unsigned) ((phys) & 0xFFFF))
10852
10853 #endif /* CHIP == INTEL */
10854
10855 /* Base and size of a partition in bytes. */
10856 struct device {
10857
       u64_t dv_base;
10858
        u64_t dv_size;
10859 };
10860
10861 #define NIL DEV
                              ((struct device *) 0)
10862
10863 /* Functions defined by driver.c: */
10864 PROTOTYPE( void driver task, (struct driver *dr) );
10865 _PROTOTYPE( char *no_name, (void) );
10866 _PROTOTYPE( int do_nop, (struct driver *dp, message *m_ptr) );
10867 _PROTOTYPE( struct device *nop_prepare, (int device) );
10868 _PROTOTYPE( void nop_cleanup, (void) );
10869 _PROTOTYPE( void nop_task, (void) );
10870 _PROTOTYPE( void nop_signal, (struct driver *dp, message *m_ptr) ); 10871 _PROTOTYPE( void nop_alarm, (struct driver *dp, message *m_ptr) );
10872 _PROTOTYPE( int nop_cancel, (struct driver *dp, message *m_ptr) );
10873 _PROTOTYPE( int nop_select, (struct driver *dp, message *m_ptr) );
10874 _PROTOTYPE( int do_diocntl, (struct driver *dp, message *m_ptr) );
10875
10876
       /* Parameters for the disk drive. */
      #define SECTOR_SIZE 512 /* physical sector size in bytes */
#define SECTOR_SHIFT 9 /* for division */
10877
10878 #define SECTOR_SHIFT
                               511 /* and remainder */
10879 #define SECTOR MASK
10880
10881
       /* Size of the DMA buffer buffer in bytes. */
10882 #define USE_EXTRA_DMA_BUF 0 /* usually not needed */
10883 #define DMA_BUF_SIZE (DMA_SECTORS * SECTOR_SIZE)
10884
10885 #if (CHIP == INTEL)
10886 extern u8_t *tmp_buf;
                                              /* the DMA buffer */
10887 #else
10888 extern u8_t tmp_buf[];
                                             /* the DMA buffer */
10889 #endif
10890 extern phys_bytes tmp_phys;
                                             /* phys address of DMA buffer */
```

```
Feb 25, 11 15:18
                                book.txt
                                                            Page 135/393
      File: Page: 772 drivers/libdriver/drvlib.h
drivers/libdriver/drvlib.h
10900 /* IBM device driver definitions
                                                    Author: Kees J. Bot
10901 *
                                                          7 Dec 1995
10902
10903
10904 #include <ibm/partition.h>
10905
10906 _PROTOTYPE( void partition, (struct driver *dr, int device, int style, int atapi
));
10907
10908 /* BIOS parameter table layout. */
10909 #define bp_cylinders(t) (* (u16_t *) (&(t)[0]))
                               (* (u8_t *) (&(t)[2]))
(* (u16_t *) (&(t)[3]))
10910 #define bp_heads(t)
10911 #define bp_reduced_wr(t)
                               (* (u16_t *) (&(t)[5]))
10912 #define bp_precomp(t)
                                (* (u8_t *) (&(t)[7]))
10913 #define bp_max_ecc(t)
10914 #define bp_ctlbyte(t)
10915 #define bp_landingzone(t)
                              (* (u8_t *) (&(t)[8]))
                                (* (u16_t *) (&(t)[12]))
                                (* (u8_t *) (&(t)[14]))
10916 #define bp_sectors(t)
10917
10918 /* Miscellaneous. */
                         (1 + NR_PARTITIONS)
10919 #define DEV_PER_DRIVE
10920 #define MINOR tO
10921 #define MINOR_r0
                         120
10922 #define MINOR_d0p0s0
                         128
10923 #define MINOR_fd0p0
                         (28 << 2)
10924 #define P FLOPPY
                         0
10925 #define P_PRIMARY
                         1
10926 #define P_SUB
drivers/libdriver/driver.c
11000 /* This file contains device independent device driver interface.
11001
11002
      * Changes:
      * Jul 25, 2005 added SYS_SIG type for signals (Jorrit N. Herder)
11003
      * Sep 15, 2004 added SYN_ALARM type for timeouts (Jorrit N. Herder)
11004
11005
         Jul 23, 2004
                     removed kernel dependencies (Jorrit N. Herder)
11006
      * Apr 02, 1992 constructed from AT wini and floppy driver (Kees J. Bot)
11007
11008
11009
      * The drivers support the following operations (using message format m2):
11010
11011
           m_type
                     DEVICE PROC_NR
                                     COUNT POSITION ADRRESS
11012
11013
          DEV_OPEN | device | proc nr |
11014
11015
          DEV CLOSE | device | proc nr |
11016
11017
           DEV_READ
                   | device | proc nr | bytes
                                            | offset | buf ptr
11018
          DEV_WRITE | device | proc nr | bytes | offset | buf ptr
11019
```

25, 1°	1 15:18		boo	ok.txt		l l	Page 136/39
	e: Page: 773 d						İ
20 * 21 *	DEV_GATHER	device	proc nr	iov len	offset	iov ptr	-
22 * 23 *	DEV_SCATTER						-
	DEV_IOCTL	·	+	++		+	-
	CANCEL					+	-
3 *		+	+	±/w ++		 +	-
0 *	HARD_STOP			 		 	
1 *	The file conta	ains one e	ntrv point	:			
3 *	driver_task				enendent	tagk entry	7
5 */	diivei_edbh		arrea by c	ac acvice a	ependene	cash chery	•
6 7 #in	clude "/driv	ers.h"					
	clude <sys io<br="">clude "driver</sys>						
0	fine BUF_EXTRA						
2			. 4.				
14 PRI	Claim space fo VATE u8_t bufi	[er[(unsig	ned) 2 * Di	MA_BUF_SIZE	+ BUF_EX	TRA];	
15 u8_ 16 phy	t *tmp_buf; s_bytes tmp_pl	ıvs;	/* ti /* pi	he DMA buff hvs address	er eventua of DMA b	ally */ uffer */	
.7	WARD _PROTOTY					,	
19 FOR	WARD _PROTOTY!	PE(int do	_rdwt, (st	ruct driver	*dr, mes		
1	WARD _PROTOTYI		_vrdwt, (s	truct drive	r *dr, me:	ssage *mp)));
2 int 3	device_calle	c i					
			driv		=======		
56 *=							
	LIC void drive uct driver *dp			pendent ent	ry points	. */	
	Main program (of any dev	ice driver	task. */			
	nt r, proc_nr	;					
	essage mess;						
5 / 6 i	* Get a DMA bunit_buffer();	uffer. */					
7	* Here is the		of the di	als to als T	t waita f		
9	* it out, and			sk task. I	.c waits i	or a messa	ige, carrie
1 w	*/ hile (TRUE) {						
'2 '3	/* Wait i	or a requ	est to rea	d or write	a disk blo	ock. */	
'4 '5) continue;			
6 7		aller = me = mess.PRO	ss.m_sourc	e;			
'8 '9	/* Now ca	arry out t	he work. *	/			
		1					

```
Feb 25, 11 15:18
                                      book.txt
                                                                     Page 137/393
      File: Page: 774 drivers/libdriver/driver.c
11080
              switch(mess.m_type) {
11081
              case DEV_OPEN:
                                      r = (*dp->dr_open)(dp, &mess); break;
11082
              case DEV_CLOSE:
                                      r = (*dp->dr_close)(dp, &mess); break;
11083
              case DEV IOCTL:
                                      r = (*dp->dr_ioctl)(dp, &mess); break;
11084
              case CANCEL:
                                      r = (*dp->dr_cancel)(dp, &mess);break;
11085
              case DEV_SELECT:
                                      r = (*dp->dr_select)(dp, &mess);break;
11086
11087
              case DEV_READ:
11088
              case DEV WRITE:
                                r = do rdwt(dp, &mess);
                                                              break;
              case DEV GATHER:
11089
11090
              case DEV_SCATTER: r = do_vrdwt(dp, &mess);
                                                             break;
11091
11092
              case HARD INT:
                                      /* leftover interrupt or expired timer. */
11093
                                     if(dp->dr_hw_int) {
11094
                                             (*dp->dr hw int)(dp, &mess);
11095
11096
                                     continue;
11097
              case SYS_SIG:
                                      (*dp->dr_signal)(dp, &mess);
11098
                                                    /* don't reply */
                                     continue;
11099
              case SYN_ALARM:
                                      (*dp->dr_alarm)(dp, &mess);
11100
                                     continue;
                                                 /* don't reply */
11101
              default:
11102
                      if(dp->dr_other)
11103
                             r = (*dp->dr_other)(dp, \&mess);
11104
                      else
11105
                             r = EINVAL;
11106
                      break;
11107
11108
               /* Clean up leftover state. */
11109
               (*dp->dr_cleanup)();
11110
11111
11112
               /* Finally, prepare and send the reply message. */
              if (r != EDONTREPLY) {
11113
                      mess.m_type = TASK_REPLY;
11114
11115
                      mess.REP_PROC_NR = proc_nr;
                      /* Status is # of bytes transferred or error code. */
11116
11117
                      mess.REP STATUS = r;
11118
                      send(device caller, &mess);
11119
11120
11121 }
11124
                                    init buffer
11125
       11126 PRIVATE void init_buffer()
11127
11128 /* Select a buffer that can safely be used for DMA transfers. It may also
      * be used to read partition tables and such. Its absolute address is
11129
11130
      * 'tmp_phys', the normal address is 'tmp_buf'.
11131
11132
11133
        unsigned left;
11134
11135
         tmp buf = buffer;
11136
        sys_umap(SELF, D, (vir_bytes)buffer, (phys_bytes)sizeof(buffer), &tmp_phys);
11137
11138
        if ((left = dma_bytes_left(tmp_phys)) < DMA_BUF_SIZE) {</pre>
11139
               /* First half of buffer crosses a 64K boundary, can't DMA into that */
```

```
Feb 25, 11 15:18
                                   book.txt
                                                                Page 138/393
      File: Page: 775 drivers/libdriver/driver.c
11140
             tmp buf += left;
11141
             tmp_phys += left;
11142
11143 }
11145 /*===========*
11146
                                  do_rdwt
11147
      *-----*
11148 PRIVATE int do_rdwt(dp, mp)
     struct driver *dp;
11149
                                  /* device dependent entry points */
11150
     message *mp;
                                  /* pointer to read or write message */
11151
11152
       * Carry out a single read or write request. */
11153
        iovec_t iovec1;
11154
        int r, opcode;
11155
        phys_bytes phys_addr;
11156
11157
        /* Disk address? Address and length of the user buffer? */
11158
        if (mp->COUNT < 0) return(EINVAL);
11159
11160
        /* Check the user buffer. */
11161
        sys_umap(mp->PROC_NR, D, (vir_bytes) mp->ADDRESS, mp->COUNT, &phys_addr);
11162
        if (phys_addr == 0) return(EFAULT);
11163
11164
        /* Prepare for I/O. */
11165
        if ((*dp->dr_prepare)(mp->DEVICE) == NIL_DEV) return(ENXIO);
11166
11167
        /* Create a one element scatter/gather vector for the buffer. */
11168
        opcode = mp->m_type == DEV_READ ? DEV_GATHER : DEV_SCATTER;
        iovec1.iov_addr = (vir_bytes) mp->ADDRESS;
11169
        iovec1.iov_size = mp->COUNT;
11170
11171
11172
        /* Transfer bytes from/to the device. */
11173
        r = (*dp->dr_transfer)(mp->PROC_NR, opcode, mp->POSITION, &iovec1, 1);
11174
11175
        /* Return the number of bytes transferred or an error code. */
11176
        return(r == OK ? (mp->COUNT - iovec1.iov_size) : r);
11177
11179
      /*-----*
11180
                                  do vrdwt
11181
       *-----*/
11182 PRIVATE int do_vrdwt(dp, mp)
11183 struct driver *dp;
                           /* device dependent entry points */
                           /* pointer to read or write message */
11184 message *mp;
11185
11186
      /* Carry out an device read or write to/from a vector of user addresses.
11187
       * The "user addresses" are assumed to be safe, i.e. FS transferring to/from
11188
       * its own buffers, so they are not checked.
11189
11190
        static iovec_t iovec[NR_IOREQS];
11191
        iovec_t *iov;
11192
        phys_bytes iovec_size;
11193
        unsigned nr_req;
11194
        int r;
11195
11196
        nr reg = mp->COUNT; /* Length of I/O vector */
11197
11198
        if (mp->m_source < 0) {
11199
         /* Called by a task, no need to copy vector. */
```

```
Feb 25, 11 15:18
                                 book.txt
                                                             Page 139/393
      File: Page: 776 drivers/libdriver/driver.c
11200
         iov = (iovec t *) mp->ADDRESS;
11201
         else {
11202
         /* Copy the vector from the caller to kernel space. */
11203
         if (nr_req > NR_IOREQS) nr_req = NR_IOREQS;
11204
         iovec_size = (phys_bytes) (nr_req * sizeof(iovec[0]));
11205
11206
         if (OK != sys_datacopy(mp->m_source, (vir_bytes) mp->ADDRESS,
11207
                   SELF, (vir_bytes) iovec, iovec_size))
            panic((*dp->dr_name)(), "bad I/O vector by", mp->m_source);
11208
11209
         iov = iovec;
11210
11211
11212
       /* Prepare for I/O. */
       if ((*dp->dr_prepare)(mp->DEVICE) == NIL_DEV) return(ENXIO);
11213
11214
11215
       /* Transfer bytes from/to the device. */
11216
       r = (*dp->dr_transfer)(mp->PROC_NR, mp->m_type, mp->POSITION, iov, nr_req);
11217
11218
       /* Copy the I/O vector back to the caller. */
11219
       if (mp->m_source >= 0) {
11220
         sys_datacopy(SELF, (vir_bytes) iovec,
11221
            mp->m_source, (vir_bytes) mp->ADDRESS, iovec_size);
11222
11223
       return(r);
11224 }
     11227
                              no name
11228
      11229 PUBLIC char *no_name()
11230
11231 /* Use this default name if there is no specific name for the device. This was
11232 * originally done by fetching the name from the task table for this process:
      * "return(tasktab[proc_number(proc_ptr) + NR_TASKS].name);", but currently a
11233
      * real "noname" is returned. Perhaps, some system information service can be
11234
11235
     * queried for a name at a later time.
11236
       static char name[] = "noname";
11237
11238
       return name;
11239 }
11241 /*----*
11242
                               do nop
11243 *-----*/
11244 PUBLIC int do nop(dp, mp)
11245 struct driver *dp;
11246 message *mp;
11247
11248 /* Nothing there, or nothing to do. */
11249
       switch (mp->m_type) {
11250
11251
       case DEV_OPEN:
                          return(ENODEV);
       case DEV_CLOSE:
11252
                          return(OK);
11253
       case DEV IOCTL:
                          return(ENOTTY);
11254
       default:
                           return(EIO);
11255
11256
```

```
book.txt
Feb 25, 11 15:18
                                     Page 140/393
   File: Page: 777 drivers/libdriver/driver.c
11259 * nop_signal
11261 PUBLIC void nop_signal(dp, mp)
11262 struct driver *dp;
11263 message *mp;
11264
   /* Default action for signal is to ignore. */
11265
11266 }
11268 /*----*
11269
                 nop alarm
11270
    *----*
11271 PUBLIC void nop_alarm(dp, mp)
11272 struct driver *dp;
11273 message *mp;
11274
   /* Ignore the leftover alarm. */
11275
11276 }
11278 /*==========*
11279
                  nop_prepare
11281 PUBLIC struct device *nop prepare(device)
11282
11283 /* Nothing to prepare for. */
   return(NIL DEV);
11284
11285
11288
                  nop cleanup
11289
   *_____*
11290 PUBLIC void nop_cleanup()
11291
   /* Nothing to clean up. */
11292
11293 }
11295 /*===================================
11296
                  nop_cancel
    *-----*
11297
11298 PUBLIC int nop_cancel(struct driver *dr, message *m)
11299
11300 /* Nothing to do for cancel. */
11301
    return(OK);
11302 }
11304 /*============*
                 nop_select
11307 PUBLIC int nop_select(struct driver *dr, message *m)
11308 {
11309 /* Nothing to do for select. */
    return(OK);
11310
11311 }
do diocntl
11316 PUBLIC int do_diocntl(dp, mp)
11317 struct driver *dp;
```

```
Feb 25, 11 15:18
                                    book.txt
                                                                  Page 141/393
       File: Page: 778 drivers/libdriver/driver.c
11318 message *mp;
                                    /* pointer to ioctl request */
11319
11320
      /* Carry out a partition setting/getting request. */
11321
        struct device *dv;
11322
        struct partition entry;
11323
        int s;
11324
11325
        if (mp->REQUEST != DIOCSETP && mp->REQUEST != DIOCGETP) {
             if(dp->dr_other) {
11326
                     return dp->dr_other(dp, mp);
11327
11328
              } else return(ENOTTY);
11329
11330
11331
         /* Decode the message parameters. */
        if ((dv = (*dp->dr prepare)(mp->DEVICE)) == NIL DEV) return(ENXIO);
11332
11333
11334
        if (mp->REQUEST == DIOCSETP) {
              /* Copy just this one partition table entry. */
11335
11336
              if (OK != (s=sys_datacopy(mp->PROC_NR, (vir_bytes) mp->ADDRESS,
11337
                     SELF, (vir_bytes) &entry, sizeof(entry))))
11338
                  return s;
11339
              dv->dv_base = entry.base;
11340
              dv->dv_size = entry.size;
11341
              /lpha Return a partition table entry and the geometry of the drive. */
11342
11343
              entry.base = dv->dv_base;
              entry.size = dv->dv size;
11344
11345
              (*dp->dr_geometry)(&entry);
              if (OK != (s=sys_datacopy(SELF, (vir_bytes) &entry,
11346
                     mp->PROC_NR, (vir_bytes) mp->ADDRESS, sizeof(entry))))
11347
11348
11349
11350
        return(OK);
11351 }
drivers/libdriver/drvlib.c
11400 /* IBM device driver utility functions.
                                                         Author: Kees J. Bot
11401 *
                                                                 7 Dec 1995
11402 * Entry point:
11403 * partition: partition a disk to the partition table(s) on it.
11405
11406 #include "driver.h"
11407 #include "drvlib.h"
11408 #include <unistd.h>
11409
11410 /* Extended partition? */
11411 #define ext_part(s)
                           ((s) == 0x05 | | (s) == 0x0F)
11412
11413 FORWARD _PROTOTYPE( void extpartition, (struct driver *dp, int extdev,
11414
                                                  unsigned long extbase) );
11415 FORWARD _PROTOTYPE( int get_part_table, (struct driver *dp, int device,
                            unsigned long offset, struct part_entry *table));
11416
11417 FORWARD _PROTOTYPE( void sort, (struct part_entry *table) );
11418
11419 #ifndef CD SECTOR SIZE
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                     Page 142/393
       File: Page: 779 drivers/libdriver/drvlib.c
11420
      #define CD SECTOR SIZE 2048
11421 #endif
11422
11423 /*===========*
11424 *
                                     partition
11426 PUBLIC void partition(dp, device, style, atapi)
11427 struct driver *dp; /* device dependent entry points */
                            /* device to partition */
11428 int device;
                            /* partitioning style: floppy, primary, sub. */
11429 int style;
                             /* atapi device */
11430 int atapi;
11431
11432 /* This routine is called on first open to initialize the partition tables
      * of a device. It makes sure that each partition falls safely within the
11433
       * device's limits. Depending on the partition style we are either making
11434
       * floppy partitions, primary partitions or subpartitions. Only primary
11435
11436
        * partitions are sorted, because they are shared with other operating
       * systems that expect this.
11437
11438
       */
11439
        struct part_entry table[NR_PARTITIONS], *pe;
11440
        int disk, par;
11441
         struct device *dv;
11442
        unsigned long base, limit, part_limit;
11443
11444
         /* Get the geometry of the device to partition */
11445
         if ((dv = (*dp->dr_prepare)(device)) == NIL_DEV
                                     || cmp64u(dv->dv_size, 0) == 0) return;
11446
11447
         base = div64u(dv->dv_base, SECTOR_SIZE);
         limit = base + div64u(dv->dv_size, SECTOR_SIZE);
11448
11449
11450
         /* Read the partition table for the device. */
11451
        if(!get_part_table(dp, device, OL, table)) {
11452
                return;
11453
11454
11455
         /* Compute the device number of the first partition. */
11456
        switch (style) {
11457
        case P_FLOPPY:
11458
              device += MINOR fd0p0;
11459
              break;
11460
         case P PRIMARY:
11461
              sort(table);
                                     /* sort a primary partition table */
11462
              device += 1;
11463
              break;
11464
        case P SUB:
              disk = device / DEV PER DRIVE;
11465
11466
              par = device % DEV_PER_DRIVE - 1;
              device = MINOR_d0p0s0 + (disk * NR_PARTITIONS + par) * NR_PARTITIONS;
11467
11468
11469
11470
         /* Find an array of devices. */
11471
         if ((dv = (*dp->dr_prepare)(device)) == NIL_DEV) return;
11472
11473
         /* Set the geometry of the partitions from the partition table. */
11474
         for (par = 0; par < NR_PARTITIONS; par++, dv++)
11475
              /* Shrink the partition to fit within the device. */
11476
              pe = &table[par];
11477
              part_limit = pe->lowsec + pe->size;
11478
              if (part_limit < pe->lowsec) part_limit = limit;
11479
              if (part limit > limit) part limit = limit;
```

```
Feb 25, 11 15:18
                                    book.txt
                                                                   Page 143/393
      File: Page: 780 drivers/libdriver/drvlib.c
11480
              if (pe->lowsec < base) pe->lowsec = base;
11481
              if (part_limit < pe->lowsec) part_limit = pe->lowsec;
11482
11483
              dv->dv_base = mul64u(pe->lowsec, SECTOR_SIZE);
              dv->dv_size = mul64u(part_limit - pe->lowsec, SECTOR_SIZE);
11484
11485
11486
              if (style == P_PRIMARY)
                     /* Each Minix primary partition can be subpartitioned. */
11487
11488
                     if (pe->sysind == MINIX PART)
11489
                            partition(dp, device + par, P_SUB, atapi);
11490
                     /* An extended partition has logical partitions. */
11491
11492
                     if (ext_part(pe->sysind))
11493
                            extpartition(dp, device + par, pe->lowsec);
11494
11495
11496
11499
                                   extpartition
11500
      11501 PRIVATE void extpartition(dp, extdev, extbase)
11502 struct driver *dp;
                            /* device dependent entry points */
                            /* extended partition to scan */
11503 int extdev;
11504 unsigned long extbase; /* sector offset of the base extended partition */
11505
11506
     /* Extended partitions cannot be ignored alas, because people like to move
       * files to and from DOS partitions. Avoid reading this code, it's no fun.
11507
11508
11509
        struct part_entry table[NR_PARTITIONS], *pe;
        int subdev, disk, par;
11510
11511
        struct device *dv;
11512
        unsigned long offset, nextoffset;
11513
11514
        disk = extdev / DEV_PER_DRIVE;
11515
        par = extdev % DEV_PER_DRIVE - 1;
11516
        subdev = MINOR_d0p0s0 + (disk * NR_PARTITIONS + par) * NR_PARTITIONS;
11517
11518
        offset = 0;
11519
        do {
11520
              if (!get_part_table(dp, extdev, offset, table)) return;
11521
              sort(table);
11522
11523
              /* The table should contain one logical partition and optionally
              * another extended partition. (It's a linked list.)
11524
11525
11526
              nextoffset = 0;
11527
              for (par = 0; par < NR_PARTITIONS; par++) {</pre>
11528
                     pe = &table[par];
11529
                     if (ext_part(pe->sysind)) {
11530
                            nextoffset = pe->lowsec;
11531
                     } else
11532
                     if (pe->sysind != NO_PART) {
11533
                            if ((dv = (*dp->dr prepare)(subdev)) == NIL DEV) return;
11534
11535
                            dv->dv base = mul64u(extbase + offset + pe->lowsec,
11536
                                                                  SECTOR SIZE);
11537
                            dv->dv_size = mul64u(pe->size, SECTOR_SIZE);
11538
11539
                            /* Out of devices? */
```

```
Feb 25, 11 15:18
                                 book.txt
                                                             Page 144/393
      File: Page: 781 drivers/libdriver/drvlib.c
11540
                          if (++subdev % NR PARTITIONS == 0) return;
11541
11542
       } while ((offset = nextoffset) != 0);
11543
11544
11547
                                get_part_table
11548
      *-----
11549 PRIVATE int get_part_table(dp, device, offset, table)
11550 struct driver *dp;
11551 int device;
11552 unsigned long offset;
                                /* sector offset to the table */
11553 struct part_entry *table;
                                /* four entries */
11554
11555
      /* Read the partition table for the device, return true iff there were no
11556
      * errors.
11557
11558
       iovec_t iovec1;
11559
       off_t position;
11560
       static unsigned char partbuf[CD_SECTOR_SIZE];
11561
11562
       position = offset << SECTOR_SHIFT;
11563
       iovec1.iov_addr = (vir_bytes) partbuf;
11564
       iovec1.iov_size = CD_SECTOR_SIZE;
11565
       if ((*dp->dr_prepare)(device) != NIL_DEV) {
11566
            (void) (*dp->dr_transfer)(SELF, DEV_GATHER, position, &iovec1, 1);
11567
11568
       if (iovec1.iov_size != 0) {
11569
            return 0;
11570
11571
       if (partbuf[510] != 0x55 || partbuf[511] != 0xAA) {
11572
            /* Invalid partition table. */
11573
            return 0;
11574
11575
       memcpy(table, (partbuf + PART_TABLE_OFF), NR_PARTITIONS * sizeof(table[0]));
11576
       return 1;
11577
11579
      11580
11581
      11582 PRIVATE void sort(table)
11583
     struct part_entry *table;
11584
11585
      /* Sort a partition table. */
11586
       struct part_entry *pe, tmp;
11587
       int n = NR_PARTITIONS;
11588
11589
11590
            for (pe = table; pe < table + NR_PARTITIONS-1; pe++) {
11591
                   if (pe[0].sysind == NO_PART
11592
                          | (pe[0].lowsec > pe[1].lowsec
11593
                                       && pe[1].sysind != NO_PART)) {
                          tmp = pe[0]; pe[0] = pe[1]; pe[1] = tmp;
11594
11595
11596
       } while (--n > 0);
11597
11598 }
```

```
book.txt
 Feb 25, 11 15:18
                                                                        Page 145/393
       File: Page: 782 drivers/memory/memory.c
drivers/memory/memory.c
11600 /* This file contains the device dependent part of the drivers for the
11601 * following special files:
                              - RAM disk
11602
             /dev/ram
11603
              /dev/mem
                               - absolute memory
11604
              /dev/kmem
                              - kernel virtual memory
11605
              /dev/null
                              - null device (data sink)
11606
             /dev/boot
                             - boot device loaded from boot image
11607
             /dev/zero
                              - null byte stream generator
11608
       * Changes:
11609
11610
               Apr 29, 2005
                               added null byte generator (Jorrit N. Herder)
11611
               Apr 09, 2005
                               added support for boot device (Jorrit N. Herder)
11612
               Jul 26, 2004
                               moved RAM driver to user-space (Jorrit N. Herder)
11613 *
               Apr 20, 1992
                               device dependent/independent split (Kees J. Bot)
11614 */
11615
11616 #include "../drivers.h"
11617 #include "../libdriver/driver.h"
11618 #include <sys/ioc memory.h>
11619 #include "../../kernel/const.h"
11620 #include "../../kernel/config.h"
11621 #include "../../kernel/type.h"
11622
11623 #include "assert.h"
11624
11625 #define NR DEVS
                                  6
                                               /* number of minor devices */
11626
11627 PRIVATE struct device m_geom[NR_DEVS]; /* base and size of each device */
11628 PRIVATE int m_seg[NR_DEVS];
                                               /* segment index of each device */
                                               /* current device */
11629 PRIVATE int m_device;
11630 PRIVATE struct kinfo kinfo;
                                               /* kernel information */
11631 PRIVATE struct machine machine;
                                               /* machine information */
11632
11633 extern int errno;
                                               /* error number for PM calls */
11634
11635 FORWARD _PROTOTYPE( char *m_name, (void)
11636 FORWARD _PROTOTYPE( struct device *m_prepare, (int device) );
11637 FORWARD _PROTOTYPE( int m_transfer, (int proc_nr, int opcode, off_t position,
11638 iovec_t *iov, unsigned nr_req) );
11639 FORWARD _PROTOTYPE( int m_do_open, (struct driver *dp, message *m_ptr) );
11640 FORWARD _PROTOTYPE( void m_init, (void) );
11641 FORWARD _PROTOTYPE( int m_ioctl, (struct driver *dp, message *m_ptr)
                                                                               );
11642 FORWARD PROTOTYPE( void m_geometry, (struct partition *entry)
11643
11644 /* Entry points to this driver. */
11645 PRIVATE struct driver m_dtab = {
        m_name, /* current device's name */
m_do_open, /* open or mount */
11646
11647
                    /* nothing on a close */
11648
         do_nop,
                     /* specify ram disk geometry */
/* prepare for I/O on a given minor device */
11649
         m_ioctl,
11650
         m prepare,
         m_transfer, /* do the I/O */
11651
         nop_cleanup, /* no need to clean up */
11652
         m_geometry, /* memory device "geometry" */
nop_signal, /* system signals */
11653
11654
```

```
Feb 25, 11 15:18
                           book.txt
                                                  Page 146/393
    File: Page: 783 drivers/memory/memory.c
     nop_alarm,
11655
11656
      nop_cancel,
11657
      nop_select,
11658
      NITIT.T.
11659
      NIII.I.
11660 };
11661
11662
    /* Buffer for the /dev/zero null byte feed. */
11663 #define ZERO_BUF_SIZE
11664 PRIVATE char dev_zero[ZERO_BUF_SIZE];
11665
11666
    #define click to round k(n) \
          ((unsigned) ((((unsigned long) (n) << CLICK_SHIFT) + 512) / 1024))
11667
11668
11669 /*========*
11670
                            main
11672 PUBLIC int main(void)
11673
11674 /* Main program. Initialize the memory driver and start the main loop. */
11675
     m_init();
11676
      driver task(&m dtab);
11677
     return(OK);
11678 }
11680 /*-----*
11681
                       m name
11682
     *-----*
11683 PRIVATE char *m_name()
11684
11685 /* Return a name for the current device. */
11686
     static char name[] = "memory";
11687
     return name;
11688 }
11690 /*=========*
11691
                  m prepare
11693 PRIVATE struct device *m prepare(device)
11694 int device;
11695
11696 /* Prepare for I/O on a device: check if the minor device number is ok. */
11697
     if (device < 0 | | device >= NR_DEVS) return(NIL_DEV);
11698
      m_device = device;
11699
11700
     return(&m geom[device]);
11701 }
11703 /*========**
11704 *
         m_transfer
11706 PRIVATE int m_transfer(proc_nr, opcode, position, iov, nr_req)
11707 int proc_nr; /* process doing the request */
                          /* DEV GATHER or DEV SCATTER */
11708 int opcode;
                         /* offset on device to read or write */
11709 off_t position;
                          /* pointer to read or write request vector */
11710 iovec_t *iov;
11711 unsigned nr reg;
                          /* length of request vector */
11712
11713 /* Read or write one the driver's minor devices. */
11714 phys bytes mem phys;
```

```
Feb 25, 11 15:18
                                        book.txt
                                                                         Page 147/393
       File: Page: 784 drivers/memory/memory.c
11715
         int seq;
11716
         unsigned count, left, chunk;
11717
         vir_bytes user_vir;
11718
         struct device *dv;
11719
         unsigned long dv_size;
11720
11721
11722
         /* Get minor device number and check for /dev/null. */
11723
         dv = &m geom[m device];
         dv_size = cv64ul(dv->dv_size);
11724
11725
11726
         while (nr reg > 0) {
11727
11728
               /* How much to transfer and where to / from. */
11729
               count = iov->iov size;
               user vir = iov->iov addr;
11730
11731
11732
               switch (m_device) {
11733
11734
               /* No copying; ignore request. */
11735
               case NULL_DEV:
11736
                   if (opcode == DEV_GATHER) return(OK);
                                                               /* always at EOF */
11737
                   break;
11738
               /\!\!\!\!\!\!^* Virtual copying. For RAM disk, kernel memory and boot device. ^*/\!\!\!\!\!
11739
11740
               case RAM DEV:
11741
               case KMEM DEV:
11742
               case BOOT DEV:
                                                                /* check for EOF */
11743
                   if (position >= dv_size) return(OK);
                   if (position + count > dv_size) count = dv_size - position;
11744
11745
                   seg = m_seg[m_device];
11746
11747
                   if (opcode == DEV_GATHER) {
                                                                /* copy actual data */
11748
                       sys_vircopy(SELF,seg,position, proc_nr,D,user_vir, count);
11749
                   } else {
11750
                       sys_vircopy(proc_nr,D,user_vir, SELF,seg,position, count);
11751
11752
                   break;
11753
               /* Physical copying. Only used to access entire memory. */
11754
11755
               case MEM DEV:
11756
                   if (position >= dv size) return(OK);
                                                                /* check for EOF */
                   if (position + count > dv_size) count = dv_size - position;
11757
11758
                   mem_phys = cv64ul(dv->dv_base) + position;
11759
11760
                   if (opcode == DEV GATHER) {
                                                                /* copy data */
                       sys_physcopy(NONE, PHYS_SEG, mem_phys,
11761
11762
                               proc_nr, D, user_vir, count);
11763
                   } else {
11764
                       sys_physcopy(proc_nr, D, user_vir,
11765
                               NONE, PHYS_SEG, mem_phys, count);
11766
11767
                   break;
11768
11769
               /* Null byte stream generator. */
11770
               case ZERO_DEV:
11771
                   if (opcode == DEV GATHER) {
11772
                       left = count;
11773
                       while (left > 0) {
11774
                           chunk = (left > ZERO BUF SIZE) ? ZERO BUF SIZE : left;
```

```
Feb 25, 11 15:18
                                  book.txt
                                                               Page 148/393
      File: Page: 785 drivers/memory/memory.c
                       if (OK != (s=sys_vircopy(SELF, D, (vir_bytes) dev_zero,
11775
11776
                             proc_nr, D, user_vir, chunk)))
11777
                           report("MEM", "sys_vircopy failed", s);
11778
                       left -= chunk;
11779
                       user_vir += chunk;
11780
11781
11782
                break;
11783
             /* Unknown (illegal) minor device. */
11784
11785
             default:
11786
                return(EINVAL);
11787
11788
             /* Book the number of bytes transferred. */
11789
11790
             position += count;
11791
             iov->iov_addr += count;
11792
             if ((iov->iov_size -= count) == 0) { iov++; nr_req--; }
11793
11794
11795
       return(OK);
11796 }
11798 /*-----*
11799
                                m do open
11800
      11801 PRIVATE int m do open(dp, m ptr)
11802 struct driver *dp;
11803
     message *m_ptr;
11804
11805 /* Check device number on open. (This used to give I/O privileges to a
11806
      * process opening /dev/mem or /dev/kmem. This may be needed in case of
11807
      * memory mapped I/O. With system calls to do I/O this is no longer needed.)
11808
11809
       if (m_prepare(m_ptr->DEVICE) == NIL_DEV) return(ENXIO);
11810
11811
       return(OK);
11812
11814
      /*-----*
11815
                                 m init
11816
      11817 PRIVATE void m_init()
11818
        /* Initialize this task. All minor devices are initialized one by one. */
11819
11820
       int i, s;
11821
11822
       if (OK != (s=sys_getkinfo(&kinfo))) {
11823
           panic("MEM", "Couldn't get kernel information.",s);
11824
11825
11826
       /* Install remote segment for /dev/kmem memory. */
11827
        m_geom[KMEM_DEV].dv_base = cvul64(kinfo.kmem_base);
        m geom[KMEM DEV].dv size = cvul64(kinfo.kmem size);
11828
11829
        if (OK != (s=sys_segctl(&m_seg[KMEM_DEV], (ul6_t *) &s, (vir_bytes *) &s,
11830
                   kinfo.kmem_base, kinfo.kmem_size))) {
           panic("MEM", "Couldn't install remote segment.", s);
11831
11832
11833
11834
       /* Install remote segment for /dev/boot memory, if enabled. */
```

```
Feb 25, 11 15:18
                                   book.txt
                                                                 Page 149/393
      File: Page: 786 drivers/memory/memory.c
11835
        m_geom[BOOT_DEV].dv_base = cvul64(kinfo.bootdev_base);
11836
        m_geom[BOOT_DEV].dv_size = cvul64(kinfo.bootdev_size);
11837
        if (kinfo.bootdev_base > 0) {
11838
           11839
11840
               panic("MEM", "Couldn't install remote segment.", s);
11841
11842
11843
11844
        /* Initialize /\text{dev}/\text{zero}. Simply write zeros into the buffer. */
11845
        for (i=0; i<ZERO_BUF_SIZE; i++) {
11846
            dev zero[i] = '\0';
11847
11848
11849
        /* Set up memory ranges for /dev/mem. */
11850
        if (OK != (s=sys getmachine(&machine))) {
11851
            panic("MEM", "Couldn't get machine information.",s);
11852
11853
        if (! machine.protected) {
             m_geom[MEM_DEV].dv_size = cvul64(0x100000); /* 1M for 8086 systems */
11854
11855
11856
             m_geom[MEM_DEV].dv_size = cvul64(0xFFFFFFFF); /* 4G-1 for 386 systems */
11857
11858 }
11860 /*----*
11861 *
                                 m ioctl
11862
      11863 PRIVATE int m_ioctl(dp, m_ptr)
11864 struct driver *dp;
                                          /* pointer to driver structure */
11865 message *m ptr;
                                          /* pointer to control message */
11866
11867 /* I/O controls for the memory driver. Currently there is one I/O control:
11868
      * - MIOCRAMSIZE: to set the size of the RAM disk.
11869
11870
       struct device *dv;
11871
        if ((dv = m_prepare(m_ptr->DEVICE)) == NIL_DEV) return(ENXIO);
11872
11873
        switch (m ptr->REQUEST) {
11874
         case MIOCRAMSIZE:
11875
              /* FS wants to create a new RAM disk with the given size. */
11876
             phys bytes ramdev size;
11877
             phys_bytes ramdev_base;
11878
             int s;
11879
11880
             if (m ptr->PROC NR != FS PROC NR) {
11881
                 report("MEM", "warning, MIOCRAMSIZE called by", m_ptr->PROC_NR);
                 return(EPERM);
11882
11883
11884
11885
             /* Try to allocate a piece of memory for the RAM disk. */
11886
             ramdev_size = m_ptr->POSITION;
11887
             if (allocmem(ramdev_size, &ramdev_base) < 0) {</pre>
                 report("MEM", "warning, allocmem failed", errno);
11888
                 return(ENOMEM);
11889
11890
11891
             dv->dv base = cvul64(ramdev base);
11892
             dv->dv_size = cvul64(ramdev_size);
11893
11894
             if (OK != (s=sys seqctl(&m seq[RAM DEV], (ul6 t *) &s, (vir bytes *) &s,
```

```
book.txt
 Feb 25, 11 15:18
                                                         Page 150/393
     File: Page: 787 drivers/memory/memory.c
11895
                  ramdev_base, ramdev_size)))
11896
                  panic("MEM", "Couldn't install remote segment.", s);
11897
11898
           break;
11899
11900
11901
        default:
11902
           return(do_diocntl(&m_dtab, m_ptr));
11903
       return(OK);
11904
11905
11908
                            m_geometry
11909 *-----*/
11910 PRIVATE void m geometry(entry)
11911 struct partition *entry;
11912 {
11913
       /* Memory devices don't have a geometry, but the outside world insists. */
       entry->cylinders = div64u(m_geom[m_device].dv_size, SECTOR_SIZE) / (64 * 32);
11914
11915
       entry->heads = 64;
11916
       entry->sectors = 32;
11917 }
drivers/at wini/at wini.h
12000 #include "../drivers.h"
12001 #include "../libdriver/driver.h"
12002 #include "../libdriver/drvlib.h"
12003
12004 _PROTOTYPE(int main, (void));
12005
                          0 /* display identify messages during boot */
12006 #define VERBOSE
12007 #define ENABLE_ATAPI 0
                              /* add ATAPI cd-rom support to driver */
                            drivers/at wini/at wini.c
12100 /* This file contains the device dependent part of a driver for the IBM-AT
12101 * winchester controller. Written by Adri Koppes.
12102
12103
      * The file contains one entry point:
12104
12105
     * at_winchester_task:
                               main entry when system is brought up
12106
12107 * Changes:
     * Aug 19, 2005 ata pci support, supports SATA (Ben Gras)
12108
12109
         Nov 18, 2004
                     moved AT disk driver to user-space (Jorrit N. Herder)
12110
         Aug 20, 2004
                     watchdogs replaced by sync alarms (Jorrit N. Herder)
         Mar 23, 2000
                     added ATAPI CDROM support (Michael Temari)
12111
         May 14, 2000
                     d-d/i rewrite (Kees J. Bot)
12112
     * Apr 13, 1992
12113
                     device dependent/independent split (Kees J. Bot)
12114 */
```

```
Feb 25, 11 15:18
                                       book.txt
                                                                        Page 151/393
       File: Page: 788 drivers/at wini/at wini.c
12115
12116 #include "at_wini.h"
12117 #include "../libpci/pci.h"
12118
12119 #include <minix/sysutil.h>
12120 #include <minix/keymap.h>
12121 #include <sys/ioc_disk.h>
12122
12123 #define ATAPI DEBUG
                                  0 /* To debug ATAPI code. */
12124
12125 /* I/O Ports used by winchester disk controllers. */
12126
12127 /* Read and write registers */
12128 #define REG_CMD_BASE0
                                      /* command base register of controller 0 */
                              0x1F0
12129 #define REG CMD BASE1
                                      /* command base register of controller 1 */
                              0 \times 170
12130 #define REG CTL BASE0
                              0x3F6
                                      /* control base register of controller 0 */
12131 #define REG_CTL_BASE1
                              0x376
                                      /* control base register of controller 1 */
12132
12133 #define REG_DATA
                                      /* data register (offset from the base reg.) */
                                      /* start of write precompensation */
12134 #define REG_PRECOMP
12135 #define REG_COUNT
                                      /* sectors to transfer */
12136 #define REG_SECTOR
                                      /* sector number */
                                      /* low byte of cylinder number */
12137 #define REG_CYL_LO
                                  4
                                     /* high byte of cylinder number */
12138 #define REG CYL HI
12139 #define REG_LDH
                                     /* lba, drive and head */
                                      0xA0 /* ECC enable, 512 bytes per sector */
12140 #define
                LDH DEFAULT
                                              /* Use LBA addressing */
12141 #define
                LDH LBA
12142 #define ldh_init(drive)
                                       (LDH_DEFAULT | ((drive) << 4))
12143
12144 /* Read only registers */
12145 #define REG_STATUS
                                      /* status */
                                             /* controller busy */
12146 #define
                STATUS_BSY
                                      0x80
12147 #define
                STATUS_RDY
                                       0 \times 40
                                              /* drive ready */
12148 #define
                STATUS_WF
                                              /* write fault */
                                       0 \times 20
                                              /* seek complete (obsolete) */
12149 #define
                STATUS_SC
                                      0x10
                                              /* data transfer request */
12150 #define
                 STATUS_DRQ
                                       0x08
12151 #define
                 STATUS_CRD
                                      0 \times 04
                                              /* corrected data */
                                              /* index pulse */
                                      0x02
12152 #define
                STATUS_IDX
12153 #define
                STATUS ERR
                                      0 \times 01
                                              /* error */
      #define
                 STATUS_ADMBSY
                                     0x100
                                              /* administratively busy (software) */
12154
12155 #define REG ERROR
                                  1 /* error code */
                                            /* bad block */
12156 #define
                 ERROR BB
                                       0x80
                                              /* bad ecc bytes */
12157
      #define
                 ERROR_ECC
                                       0x40
                                              /* id not found */
12158 #define
                 ERROR_ID
                                       0x10
12159 #define
                 ERROR AC
                                              /* aborted command */
                                       0 \times 0.4
12160 #define
                                      0x02
                                              /* track zero error */
                 ERROR TK
12161 #define
                ERROR_DM
                                      0 \times 01
                                              /* no data address mark */
12162
12163 /* Write only registers */
                                       /* command */
12164 #define REG_COMMAND
12165 #define CMD_IDLE
                                       0x00
                                            /* for w_command: drive idle */
12166 #define
                 CMD RECALIBRATE
                                       0x10
                                              /* recalibrate drive */
                                              /* read data */
12167 #define
                 CMD READ
                                       0x20
                                              /* read data (LBA48 addressed) */
12168 #define
                 CMD_READ_EXT
                                       0x24
12169 #define
                CMD_WRITE
                                       0x30
                                              /* write data */
                                              /* write data (LBA48 addressed) */
12170 #define
                 CMD WRITE EXT
                                       0x34
12171 #define
                                              /* read verify */
                 CMD READVERIFY
                                      0x40
                CMD_FORMAT
                                              /* format track */
12172 #define
                                      0 \times 50
                                              /* seek cylinder */
12173 #define
                 CMD_SEEK
                                       0x70
12174 #define
                 CMD DIAG
                                              /* execute device diagnostics */
```

```
book.txt
Feb 25, 11 15:18
                                                                          Page 152/393
       File: Page: 789 drivers/at wini/at wini.c
12175
       #define CMD_SPECIFY
                                        0x91
                                               /* specify parameters */
                                               /* identify drive */
12176 #define ATA_IDENTIFY
                                        0xEC
                                        0x206 */ /* control register */
       /* #define REG_CTL
12178
       #define REG_CTL
                              0
                                        /* control register */
12179
       #define
                 CTL_NORETRY
                                        0x80
                                               /* disable access retry */
12180
       #define
                 CTL_NOECC
                                        0x40
                                               /* disable ecc retry */
                 CTL_EIGHTHEADS
12181
       #define
                                        0x08
                                               /* more than eight heads */
                                               /* reset controller */
12182 #define
                 CTL_RESET
                                       0 \times 04
                                               /* disable interrupts */
12183
       #define
                 CTL INTDISABLE
                                       0x02
12184
                                       /* status */
12185
       #define REG_STATUS
12186
       #define
                 STATUS BSY
                                        0x80
                                             /* controller busy */
                                               /* drive ready */
12187
       #define
                 STATUS_DRDY
                                        0x40
                                                /* dma ready/drive fault */
12188
       #define
                 STATUS_DMADF
                                        0x20
       #define
                 STATUS SRVCDSC
                                                /* service or dsc */
12189
                                        0 \times 10
12190
       #define
                                                /* data transfer request */
                 STATUS DRO
                                       0 \times 0 8
12191
       #define
                 STATUS_CORR
                                       0 \times 0.4
                                                /* correctable error occurred */
                                               /* check error */
12192
       #define
                 STATUS_CHECK
12193
12194
       /* Interrupt request lines. */
12195
       #define NO_IRQ
                                       /* no IRQ set yet */
12196
12197
       #define ATAPI_PACKETSIZE
                                       12
12198
       #define SENSE PACKETSIZE
                                       18
12199
12200
       /* Common command block */
12201
       struct command {
12202
         u8 t precomp;
                                /* REG PRECOMP, etc. */
12203
         u8_t count;
12204
         u8 t sector;
12205
         u8_t cyl_lo;
12206
         u8_t cyl_hi;
12207
         u8_t ldh;
12208
         u8_t command;
12209
12210
12211
       /* Error codes */
12212
       #define ERR
                                 (-1)
                                     /* general error */
12213
       #define ERR BAD SECTOR
                               (-2) /* block marked bad detected */
12214
12215
       /* Some controllers don't interrupt, the clock will wake us up. */
                               (32*HZ) /* drive may be out for 31 seconds max */
12216
       #define WAKEUP
12217
12218
       /* Miscellaneous. */
       #define MAX DRIVES
12219
       #define COMPAT DRIVES
12220
                                  4
12221
       #define MAX_SECS
                                       /* controller can transfer this many sectors */
                                       /* how often to try rd/wt before quitting */
12222
       #define MAX_ERRORS
                                (MAX DRIVES * DEV_PER_DRIVE)
12223
       #define NR_MINORS
                               (NR_PARTITIONS * NR_PARTITIONS)
12224
       #define SUB_PER_DRIVE
12225
       #define NR_SUBDEVS
                                (MAX_DRIVES * SUB_PER_DRIVE)
12226
       #define DELAY USECS
                               1000
                                       /* controller timeout in microseconds */
                                       /* controller timeout in ticks */
12227
       #define DELAY_TICKS
       #define DEF_TIMEOUT_TICKS
                                             /* controller timeout in ticks */
12228
       #define RECOVERY_USECS 500000
                                       /* controller recovery time in microseconds */
/* controller recovery time in ticks */
12229
12230
       #define RECOVERY TICKS
                                 30
       #define INITIALIZED
                                        /* drive is initialized */
12231
       #define DEAF
                                       /* controller must be reset */
12232
                               0 \times 0.2
                                       /* drive supports ATA commands */
12233
       #define SMART
                               0 \times 0.4
12234 #define ATAPI
                                       /* don't bother with ATAPI; optimise out */
```

```
book.txt
Feb 25, 11 15:18
                                                                      Page 153/393
       File: Page: 790 drivers/at wini/at wini.c
12235 #define IDENTIFIED 0x10 /* w_identify done successfully */
12236 #define IGNORING
                              0x20
                                    /* w_identify failed once */
12237
12238 /* Timeouts and max retries. */
12239 int timeout_ticks = DEF_TIMEOUT_TICKS, max_errors = MAX_ERRORS;
12240 int wakeup_ticks = WAKEUP;
12241 long w_standard_timeouts = 0, w_pci_debug = 0, w_instance = 0,
12242 w_lba48 = 0, atapi_debug = 0;
12243
12244 int w_testing = 0, w_silent = 0;
12245
12246 int w next drive = 0;
12247
12248 /* Variables. */
12249
12250 /* wini is indexed by controller first, then drive (0-3).
12251 * controller 0 is always the 'compatability' ide controller, at
12252 * the fixed locations, whether present or not.
12253 */
12254 PRIVATE struct wini {
                                     /* main drive struct, one entry per drive */
12255
       unsigned state;
                                  /* drive state: deaf, initialized, dead */
                                   /* device status register */
/* command base register */
12256
         unsigned w_status;
        unsigned base_cmd;
12257
                                   /* control base register */
        unsigned base_ctl;
12258
        unsigned irq;
unsigned irq_mask;
                                   /* interrupt request line */
12259
                                     /* 1 << irq */
12260
         unsigned irq_need_ack;
                                   /* irq needs to be acknowledged */
12261
        int irq_hook_id;
                                    /* id of irq hook at the kernel */
/* supports lba48 */
12262
12263
        int 1ba48;
                                 /* logical number of cylinders (BIOS) */
/* logical number of heads */
12264
         unsigned lcylinders;
        unsigned lheads;
12265
12266
        unsigned lsectors;
                                     /* logical number of sectors per track */
                                  /* physical number of cylinders (translated) */
12267
         unsigned pcylinders;
12268
        unsigned pheads;
unsigned psectors;
                                     /* physical number of heads */
                                     /* physical number of sectors per track */
12269
        unsigned ldhpref;
                                    /* top four bytes of the LDH (head) register */
12270
                                     /* write precompensation cylinder / 4 */
12271
         unsigned precomp;
        unsigned max_count;
12272
                                     /* max request for this drive */
12273
         unsigned open ct;
                                     /* in-use count */
        struct device part[DEV_PER_DRIVE]; /* disks and partitions */
struct device subpart[SUB_PER_DRIVE]; /* subpartitions */
12274
12275
12276 } wini[MAX DRIVES], *w wn;
12277
12278 PRIVATE int w_device = -1;
12279 PRIVATE int w controller = -1;
12280 PRIVATE int w major = -1;
12281 PRIVATE char w_id_string[40];
12283 PRIVATE int win_tasknr;
                                             /* my task number */
                                             /* current command in execution */
12284 PRIVATE int w_command;
                                             /* used for SYS_IRQCTL */
12285 PRIVATE u8_t w_byteval;
12286 PRIVATE int w_drive;
                                             /* selected drive */
12287 PRIVATE int w_controller;
                                             /* selected controller */
                                           /* device's base and size */
12288 PRIVATE struct device *w dv;
12289
12290 FORWARD _PROTOTYPE( void init_params, (void)
t.));
12292 FORWARD _PROTOTYPE( void init_params_pci, (int)
12293 FORWARD PROTOTYPE( int w do open, (struct driver *dp, message *m ptr) );
12294 FORWARD PROTOTYPE( struct device *w_prepare, (int dev)
```

```
book.txt
Feb 25, 11 15:18
                                                                 Page 154/393
      File: Page: 791 drivers/at wini/at wini.c
12295 FORWARD _PROTOTYPE( int w_identify, (void)
                                                                       );
12296 FORWARD _PROTOTYPE( char *w_name, (void)
                                                                       );
12297 FORWARD _PROTOTYPE( int w_specify, (void)
                                                                       );
12298 FORWARD _PROTOTYPE( int w_io_test, (void)
                                                                       );
12299 FORWARD PROTOTYPE( int w_transfer, (int proc_nr, int opcode, off_t position,
12300
                                          iovec_t *iov, unsigned nr_req) );
12301 FORWARD _PROTOTYPE( int com_out, (struct command *cmd)
12302 FORWARD _PROTOTYPE( void w_need_reset, (void)
                                                                       );
                                                                       );
12303 FORWARD _PROTOTYPE( void ack_irqs, (unsigned int)
                                                                       );
12304 FORWARD PROTOTYPE( int w_do_close, (struct driver *dp, message *m_ptr) );
12305 FORWARD PROTOTYPE( int w_other, (struct driver *dp, message *m_ptr)
12306 FORWARD PROTOTYPE( int w_hw_int, (struct driver *dp, message *m_ptr)
                                                                       );
12307 FORWARD _PROTOTYPE( int com_simple, (struct command *cmd) 12308 FORWARD _PROTOTYPE( void w_timeout, (void)
                                                                       );
                                                                        );
12309 FORWARD _PROTOTYPE( int w_reset, (void)
12310 FORWARD _PROTOTYPE( void w_intr_wait, (void)
                                                                       );
12311 FORWARD _PROTOTYPE( int at_intr_wait, (void)
                                                                       );
12312 FORWARD _PROTOTYPE( int w_waitfor, (int mask, int value)
                                                                       );
12313 FORWARD PROTOTYPE (void w_geometry, (struct partition *entry)
12314
12315 /* Entry points to this driver. */
12316 PRIVATE struct driver w_dtab = {
12317
       w_name,
w_do_open,
                          /* current device's name */
                          /* open or mount request, initialize device */
12318
                         /* release device */
/* get or set a partition's geometry */
/* prepare for I/O on a given minor device */
        w_do_close,
12319
        do_diocntl,
12320
        w_prepare,
12321
                         /* do the I/O */
/* nothing to clean up */
/* tell the geometry of the disk */
12322
        w transfer,
12323
       nop_cleanup,
       w_geometry,
12324
                           /* no cleanup needed on shutdown */
12325
       nop_signal,
                           /* ignore leftover alarms */
12326
       nop_alarm,
12327
        nop_cancel,
                           /* ignore CANCELs */
                           /* ignore selects */
12328
        nop_select,
                           /* catch-all for unrecognized commands and ioctls */
12329
        w_other,
w_hw_int
                          /* leftover hardware interrupts */
12330
12331 };
12332
12333 /*----*
12334
       * at_winchester_task
      12335
12336 PUBLIC int main()
12337
12338
      /* Set special disk parameters then call the generic main loop. */
12339
       init params();
12340
        driver task(&w dtab);
12341
        return(OK);
12342 }
12344 /*========*
12345 * init_params
12346
       12347 PRIVATE void init_params()
12348
12349 /* This routine is called at startup to initialize the drive parameters. */
12350
12351
        ul6 t parv[2];
        unsigned int vector, size;
12352
12353
        int drive, nr_drives;
12354
        struct wini *wn;
```

```
Feb 25, 11 15:18
                                        book.txt
                                                                         Page 155/393
       File: Page: 792 drivers/at wini/at wini.c
12355
         u8 t params[16];
12356
         int s;
12357
12358
         /* Boot variables */
         env_parse("ata_std_timeout", "d", 0, &w_standard_timeouts, 0, 1);
12359
         12360
12361
12362
         env parse("atapi debug", "d", 0, &atapi debug, 0, 1);
12363
12364
12365
         if (w instance == 0) {
12366
                 /* Get the number of drives from the BIOS data area */
                 if ((s=sys_vircopy(SELF, BIOS_SEG, NR_HD_DRIVES_ADDR,
12367
12368
                               SELF, D, (vir_bytes) params, NR_HD_DRIVES_SIZE)) != OK)
                       panic(w name(), "Couldn't read BIOS", s);
12369
12370
                 if ((nr_drives = params[0]) > 2) nr_drives = 2;
12371
12372
                 for (drive = 0, wn = wini; drive < COMPAT_DRIVES; drive++, wn++) {
12373
                       if (drive < nr_drives) {
12374
                            /* Copy the BIOS parameter vector */
12375
                           vector = (drive == 0) ? BIOS_HD0_PARAMS_ADDR: BIOS_HD1_PARAM
S ADDR;
12376
                           size = (drive == 0) ? BIOS_HD0_PARAMS_SIZE: BIOS_HD1_PARAMS_
SIZE;
12377
                           if ((s=sys_vircopy(SELF, BIOS_SEG, vector,
                                       SELF, D, (vir_bytes) parv, size)) != OK)
panic(w name(), "Couldn't read BIOS", s);
12378
12379
12380
12381
                               /* Calculate the address of the parameters and copy them
12382
                               if ((s=sys vircopy(
12383
                                       SELF, BIOS_SEG, hclick_to_physb(parv[1]) + parv[
0],
12384
                                       SELF, D, (phys_bytes) params, 16L))!=OK)
12385
                                   panic(w_name(), "Couldn't copy parameters", s);
12386
12387
                                /* Copy the parameters to the structures of the drive */
12388
                               wn->lcylinders = bp_cylinders(params);
12389
                               wn->lheads = bp_heads(params);
12390
                               wn->lsectors = bp_sectors(params);
12391
                               wn->precomp = bp_precomp(params) >> 2;
12392
12393
12394
                        /* Fill in non-BIOS parameters. */
12395
                       init drive(wn,
12396
                               drive < 2 ? REG CMD BASE0 : REG CMD BASE1,
12397
                               drive < 2 ? REG_CTL_BASE0 : REG_CTL_BASE1,
12398
                               NO_IRQ, 0, 0, drive);
12399
                       w next drive++;
12400
12401
12402
12403
         /* Look for controllers on the pci bus. Skip none the first instance,
12404
          * skip one and then 2 for every instance, for every next instance.
12405
12406
         if (w instance == 0)
12407
               init params pci(0);
12408
12409
                init_params_pci(w_instance*2-1);
12410
12411
12413 #define ATA_IF_NOTCOMPAT1 (1L << 0)
12414 #define ATA_IF_NOTCOMPAT2 (1L << 2)
```

```
Feb 25, 11 15:18
                                   book.txt
                                                                 Page 156/393
       File: Page: 793 drivers/at wini/at wini.c
12415
12416
      /*-----*
12417
                                  init_drive
       *=======*/
12418
12419 PRIVATE void init_drive(struct wini *w, int base_cmd, int base_ctl, int irq, int
ack, int hook, int drive)
12420
1.2421
              w->state = 0;
12422
              w->w status = 0;
12423
              w->base_cmd = base_cmd;
12424
              w->base ctl = base ctl;
12425
              w->irg = irg;
              w->irq_mask = 1 << irq;
12426
12427
              w->irq_need_ack = ack;
              w->irg hook id = hook;
12428
12429
              w->ldhpref = ldh init(drive);
12430
             w->max_count = MAX_SECS << SECTOR_SHIFT;
12431
              w - > 1 ba 48 = 0;
12432
12434
      /*----*
12435
                                   init_params_pci
12436
       *-----*/
12437
      PRIVATE void init params pci(int skip)
12438
12439
        int r, devind, drive;
        ul6 t vid, did;
12440
12441
        pci init();
        for(drive = w_next_drive; drive < MAX_DRIVES; drive++)
12442
              wini[drive].state = IGNORING;
12443
        for(r = pci_first_dev(&devind, &vid, &did);
12444
12445
             r != 0 && w_next_drive < MAX_DRIVES; r = pci_next_dev(&devind, &vid, &di
d)) {
12446
              int interface, irq, irq_hook;
12447
              /* Base class must be 01h (mass storage), subclass must
12448
              * be 01h (ATA).
12449
              if (pci_attr_r8(devind, PCI_BCR) != 0x01 ||
12450
12451
                pci_attr_r8(devind, PCI_SCR) != 0x01)
12452
                continue;
12453
              /* Found a controller.
12454
               * Programming interface register tells us more.
12455
12456
12457
              interface = pci attr r8(devind, PCI PIFR);
             irq = pci_attr_r8(devind, PCI_ILR);
12458
12459
12460
              /* Any non-compat drives? */
12461
              if (interface & (ATA_IF_NOTCOMPAT1 | ATA_IF_NOTCOMPAT2)) {
12462
                     int s;
12463
                     irq_hook = irq;
12464
                     if (skip > 0) {
                            if (w_pci_debug) printf("atapci skipping controller (rem
12465
ain %d)\n", skip);
12466
                            skip--;
12467
                            continue;
12468
12469
                     if ((s=sys_irqsetpolicy(irq, 0, &irq_hook)) != OK) {
                            printf("atapci: couldn't set IRQ policy %d\n", irq);
12470
12471
                            continue;
12472
12473
                     if ((s=sys_irgenable(&irg_hook)) != OK) {
12474
                            printf("atapci: couldn't enable IRQ line %d\n", irg);
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 157/393
       File: Page: 794 drivers/at wini/at wini.c
12475
                             continue;
12476
12477
              } else {
12478
                      /* If not.. this is not the ata-pci controller we're
                      * looking for.
12479
12480
12481
                      if (w_pci_debug) printf("atapci skipping compatability controlle
r\n");
12482
                      continue;
12483
12484
12485
               /* Primary channel not in compatability mode? */
              if (interface & ATA_IF_NOTCOMPAT1) {
12486
12487
                      u32_t base_cmd, base_ctl;
                      base cmd = pci attr r32(devind, PCI BAR) & 0xffffffe0;
12488
                      base_ctl = pci_attr_r32(devind, PCI_BAR_2) & 0xffffffe0;
12489
12490
                      if (base_cmd != REG_CMD_BASE0 && base_cmd != REG_CMD_BASE1) {
12491
                             init_drive(&wini[w_next_drive],
12492
                                    base_cmd, base_ctl, irq, 1, irq_hook, 0);
12493
                             init_drive(&wini[w_next_drive+1],
12494
                                    base_cmd, base_ctl, irq, 1, irq_hook, 1);
12495
                             if (w_pci_debug)
12496
                                    printf("atapci %d: 0x%x 0x%x irg %d\n", devind,
base_cmd, base_ctl, irq);
                       else printf("atapci: ignored drives on primary channel, base
12497
%x\n", base cmd);
12498
12499
12500
               /* Secondary channel not in compatability mode? */
              if (interface & ATA_IF_NOTCOMPAT2) {
12501
12502
                      u32_t base_cmd, base_ctl;
12503
                      base_cmd = pci_attr_r32(devind, PCI_BAR_3) & 0xffffffe0;
12504
                      base_ctl = pci_attr_r32(devind, PCI_BAR_4) & 0xffffffe0;
12505
                      if (base_cmd != REG_CMD_BASE0 && base_cmd != REG_CMD_BASE1) {
12506
                             init_drive(&wini[w_next_drive+2],
12507
                                    base_cmd, base_ctl, irq, 1, irq_hook, 2);
                             init_drive(&wini[w_next_drive+3],
12508
12509
                                    base_cmd, base_ctl, irq, 1, irq_hook, 3);
12510
                             if (w pci debug)
                                    printf("atapci %d: 0x%x 0x%x irq %d\n", devind,
12511
base_cmd, base_ctl, irq);
12512
                        else printf("atapci: ignored drives on secondary channel, bas
e %x\n", base_cmd);
12513
               w next drive += 4;
12514
12515
12516
12519
                                    w_do_open
      *-----*/
12521 PRIVATE int w_do_open(dp, m_ptr)
12522 struct driver *dp;
12523
      message *m ptr;
12524
       /* Device open: Initialize the controller and read the partition table. */
12525
12526
12527
         struct wini *wn;
12528
12529
        if (w prepare(m ptr->DEVICE) == NIL DEV) return(ENXIO);
12530
12531
12532
12533
         /* If we've probed it before and it failed, don't probe it again. */
12534
         if (wn->state & IGNORING) return ENXIO;
```

```
Feb 25, 11 15:18
                                      book.txt
                                                                       Page 158/393
       File: Page: 795 drivers/at wini/at wini.c
12535
12536
         /* If we haven't identified it yet, or it's gone deaf,
12537
          * (re-)identify it.
12538
         if (!(wn->state & IDENTIFIED) || (wn->state & DEAF)) {
12539
12540
              /* Try to identify the device. */
12541
              if (w_identify() != OK) {
12542
                      if (wn->state & DEAF) w_reset();
12543
                      wn->state = IGNORING;
                      return(ENXIO);
12544
12545
12546
                /* Do a test transaction unless it's a CD drive (then
                 * we can believe the controller, and a test may fail
12547
                  * due to no CD being in the drive). If it fails, ignore
12548
                 * the device forever.
12549
12550
12551
                if (!(wn->state & ATAPI) && w_io_test() != OK) {
12552
                      wn->state |= IGNORING;
                      return(ENXIO);
12553
12554
12555
12556
12557
          /* If it's not an ATAPI device, then don't open with RO_BIT. */
12558
         if (!(wn->state & ATAPI) && (m ptr->COUNT & RO BIT)) return EACCES;
12559
12560
         /* Partition the drive if it's being opened for the first time,
12561
         * or being opened after being closed.
12562
12563
         if (wn->open_ct == 0) {
12564
12565
              /* Partition the disk. */
12566
              memset(wn->part, sizeof(wn->part), 0);
12567
              memset(wn->subpart, sizeof(wn->subpart), 0);
              partition(&w_dtab, w_drive * DEV_PER_DRIVE, P_PRIMARY, wn->state & ATAPI
12568
12569
12570
         wn->open_ct++;
12571
         return(OK);
12572
12574
12575
                                    w prepare
12576
       12577
       PRIVATE struct device *w_prepare(int device)
12578
12579
       /* Prepare for I/O on a device. */
12580
      struct wini *prev_wn;
12581 prev_wn = w_wn;
12582
         w_device = device;
12583
12584
         if (device < NR_MINORS) {</pre>
                                                      /* d0, d0p[0-3], d1, ... */
12585
              w_drive = device / DEV_PER_DRIVE;
                                                      /* save drive number */
12586
              w_wn = &wini[w_drive];
12587
              w_dv = &w_wn->part[device % DEV_PER_DRIVE];
12588
         } else
12589
         if ((unsigned) (device -= MINOR_d0p0s0) < NR_SUBDEVS) {/*d[0-7]p[0-3]s[0-3]*/
              w_drive = device / SUB_PER_DRIVE;
12590
              w wn = &wini[w drive];
12591
12592
              w_dv = &w_wn->subpart[device % SUB_PER_DRIVE];
12593
         } else {
12594
              w_{device} = -1;
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                     Page 159/393
      File: Page: 796 drivers/at wini/at wini.c
12595
              return(NIL DEV);
12596
12597
        return(w_dv);
12598
      /*=================================
12601
                                    w_identify
12602
      *-----*
12603 PRIVATE int w identify()
12604
      /* Find out if a device exists, if it is an old AT disk, or a newer ATA
12605
12606
      * drive, a removable media device, etc.
12607
12608
12609
        struct wini *wn = w wn;
12610
        struct command cmd;
12611
        int i, s;
12612
        unsigned long size;
12613 #define id_byte(n)
                             (&tmp_buf[2 * (n)])
                              (((u16_t) id_byte(n)[0] << 0) \
12614 #define id_word(n)
12615
                              ((u16_t) id_byte(n)[1] << 8))
12616
      #define id_longword(n)
                              (((u32_t) id_byte(n)[0] << 0) \
12617
                              ((u32_t) id_byte(n)[1] << 8) \
                              ((u32_t) id_byte(n)[2] << 16) \
12618
12619
                              ((u32_t) id_byte(n)[3] << 24))
12620
12621
        /* Try to identify the device. */
12622
        cmd.ldh
                  = wn->ldhpref;
        cmd.command = ATA_IDENTIFY;
12623
        if (com simple(&cmd) == OK) {
12624
12625
              /* This is an ATA device. */
12626
              wn->state |= SMART;
12627
12628
              /* Device information. */
12629
              if ((s=sys_insw(wn->base_cmd + REG_DATA, SELF, tmp_buf, SECTOR_SIZE)) !=
OK)
12630
                      panic(w_name(), "Call to sys_insw() failed", s);
12631
12632
              /* Why are the strings byte swapped??? */
              for (i = 0; i < 40; i++) w_id_string[i] = id_byte(27)[i^1];
12633
12634
12635
              /* Preferred CHS translation mode. */
              wn->pcylinders = id word(1);
12636
12637
              wn->pheads = id_word(3);
12638
              wn->psectors = id word(6);
12639
              size = (u32_t) wn->pcylinders * wn->pheads * wn->psectors;
12640
12641
              if ((id_byte(49)[1] & 0x02) && size > 512L*1024*2) {
12642
                      /* Drive is LBA capable and is big enough to trust it to
12643
                       * not make a mess of it.
12644
12645
                      wn->ldhpref |= LDH_LBA;
12646
                      size = id_longword(60);
12647
                      if (w_lba48 && ((id_word(83)) & (1L << 10)))</pre>
12648
                             /* Drive is LBA48 capable (and LBA48 is turned on). */
12649
                             if (id_word(102) || id_word(103)) {
12650
                                     /* If no. of sectors doesn't fit in 32 bits,
12651
                                      * trunacte to this. So it's LBA32 for now.
12652
12653
                                      * This can still address devices up to 2TB
12654
                                      * though.
```

```
Feb 25, 11 15:18
                                      book.txt
                                                                      Page 160/393
       File: Page: 797 drivers/at wini/at wini.c
12655
12656
                                      size = ULONG_MAX;
12657
                              } else {
12658
                                      /* Actual number of sectors fits in 32 bits. */
12659
                                      size = id_longword(100);
12660
12661
                              wn - > 1ba48 = 1;
12662
12663
12664
12665
12666
              if (wn->lcylinders == 0) {
12667
                      /* No BIOS parameters? Then make some up. */
12668
                      wn->lcylinders = wn->pcylinders;
                      wn->lheads = wn->pheads;
12669
12670
                      wn->lsectors = wn->psectors;
12671
                      while (wn->lcylinders > 1024) {
12672
                              wn->lheads *= 2;
12673
                              wn->lcylinders /= 2;
12674
12675
12676
        } else´{
12677
              /{}^{\star} Not an ATA device; no translations, no special features. Don't
               * touch it unless the BIOS knows about it.
12678
12679
12680
              if (wn->lcylinders == 0) { return(ERR); }
                                                             /* no BIOS parameters */
              wn->pcylinders = wn->lcylinders;
12681
12682
              wn->pheads = wn->lheads;
12683
              wn->psectors = wn->lsectors;
              size = (u32 t) wn->pcylinders * wn->pheads * wn->psectors;
12684
12685
12686
12687
         /* Size of the whole drive */
12688
         wn->part[0].dv_size = mul64u(size, SECTOR_SIZE);
12689
12690
         /* Reset/calibrate (where necessary) */
12691
         if (w_specify() != OK && w_specify() != OK) {
12692
              return(ERR);
12693
12694
12695
         if (wn->irq == NO_IRQ) {
                 /* Everything looks OK; register IRO so we can stop polling. */
12696
                wn->irq = w_drive < 2 ? AT_WINI_0_IRQ : AT_WINI_1_IRQ;
12697
12698
                wn->irq_hook_id = wn->irq; /* id to be returned if interrupt occurs
12699
                if ((s=sys irgsetpolicy(wn->irg, IRO REENABLE, &wn->irg hook id)) != 0
12700
                      panic(w_name(), "couldn't set IRQ policy", s);
12701
                if ((s=sys_irqenable(&wn->irq_hook_id)) != OK)
12702
                      panic(w_name(), "couldn't enable IRQ line", s);
12703
12704
        wn->state |= IDENTIFIED;
12705
        return(OK);
12706
12708
12709
                                     w name
12710
       12711
      PRIVATE char *w_name()
12712
12713 /* Return a name for the current device. */
12714
       static char name[] = "AT-D0";
```

```
Feb 25, 11 15:18
                                    book.txt
                                                                   Page 161/393
      File: Page: 798 drivers/at wini/at wini.c
12715
12716
        name[4] = '0' + w_drive;
12717
        return name;
12718
12720 /*============*
12721
                                  w io test
12722
      *----*
12723 PRIVATE int w io test(void)
12724
12725
              int r, save_dev;
12726
              int save timeout, save errors, save wakeup;
12727
              iovec_t iov;
              static char buf[SECTOR_SIZE];
12728
              iov.iov addr = (vir bytes) buf;
12729
              iov.iov size = sizeof(buf);
12730
12731
              save_dev = w_device;
12732
12733
              /* Reduce timeout values for this test transaction. */
12734
              save_timeout = timeout_ticks;
12735
              save_errors = max_errors;
12736
              save_wakeup = wakeup_ticks;
12737
12738
              if (!w_standard_timeouts) {
                     timeout_ticks = HZ * 4;
12739
                     wakeup_ticks = HZ * 6;
12740
12741
                     \max \text{ errors} = 3;
12742
12743
12744
              w testing = 1;
12745
12746
              /* Try I/O on the actual drive (not any (sub)partition). */
12747
              if (w_prepare(w_drive * DEV_PER_DRIVE) == NIL_DEV)
12748
                     panic(w_name(), "Couldn't switch devices", NO_NUM);
12749
12750
              r = w_transfer(SELF, DEV_GATHER, 0, &iov, 1);
12751
12752
              /* Switch back. */
12753
              if (w_prepare(save_dev) == NIL_DEV)
                     panic(w_name(), "Couldn't switch back devices", NO_NUM);
12754
12755
12756
              /* Restore parameters. */
12757
              timeout ticks = save timeout;
12758
              max_errors = save_errors;
12759
              wakeup ticks = save wakeup;
12760
              w_testing = 0;
12761
12762
              /* Test if everything worked. */
12763
              if (r != OK || iov.iov_size != 0) {
12764
                     return ERR;
12765
12766
12767
              /* Everything worked. */
12768
12769
              return OK;
12770 }
```

```
Feb 25, 11 15:18
                                  book.txt
                                                               Page 162/393
      File: Page: 799 drivers/at wini/at wini.c
12772
     /*-----*
12773
                                w_specify
12774
      *_____*
12775
     PRIVATE int w_specify()
12776
12777
      /* Routine to initialize the drive after boot or when a reset is needed. */
12778
12779
       struct wini *wn = w wn;
12780
       struct command cmd;
12781
12782
        if ((wn->state & DEAF) && w_reset() != OK) {
12783
             return(ERR);
12784
12785
12786
        if (!(wn->state & ATAPI)) {
             /* Specify parameters: precompensation, number of heads and sectors. */
12787
12788
             cmd.precomp = wn->precomp;
            cmd.count = wm->psectors;
cmd.ldh = w_wn->ldhpref | (wn->pheads - 1);
12789
12790
12791
             cmd.command = CMD_SPECIFY;
                                               /* Specify some parameters */
12792
12793
             /* Output command block and see if controller accepts the parameters. */
12794
             if (com_simple(&cmd) != OK) return(ERR);
12795
12796
             if (!(wn->state & SMART))
12797
                    /* Calibrate an old disk. */
12798
                    cmd.sector = 0;
12799
                    cmd.cyl_lo = 0;
12800
                   cmd.cyl_hi = 0;
                    cmd.ldh = w wn->ldhpref;
12801
                    cmd.command = CMD RECALIBRATE;
12802
12803
12804
                    if (com_simple(&cmd) != OK) return(ERR);
12805
12806
12807
       wn->state |= INITIALIZED;
12808
       return(OK);
12809
12811
      /*-----*
12812
                                 do transfer
      12814 PRIVATE int do_transfer(struct wini *wn, unsigned int precomp, unsigned int coun
12815
             unsigned int sector, unsigned int opcode)
12816 {
12817
             struct command cmd;
12818
             unsigned secspcyl = wn->pheads * wn->psectors;
12819
12820
             cmd.precomp = precomp;
12821
             cmd.count = count;
12822
             cmd.command = opcode == DEV_SCATTER ? CMD_WRITE : CMD_READ;
12823
12824
             if (w_lba48 && wn->lba48) {
12825
             }else */
12826
             if (wn->ldhpref & LDH_LBA) {
12827
                   cmd.sector = (sector >> 0) & 0xFF;
12828
                    cmd.cyl_lo = (sector >> 8) & 0xFF;
12829
                   cmd.cyl_hi = (sector >> 16) & 0xFF;
12830
                    cmd.ldh = wn->ldhpref | ((sector >> 24) & 0xF);
12831
             } else {
```

```
Feb 25, 11 15:18
                                    book.txt
                                                                   Page 163/393
      File: Page: 800 drivers/at wini/at wini.c
                     int cylinder, head, sec;
12832
12833
                     cylinder = sector / secspcyl;
12834
                     head = (sector % secspcyl) / wn->psectors;
12835
                     sec = sector % wn->psectors;
12836
                     cmd.sector = sec + 1;
12837
                     cmd.cyl_lo = cylinder & BYTE;
12838
                     cmd.cyl_hi = (cylinder >> 8) & BYTE;
                              = wn->ldhpref | head;
                     cmd.ldh
12839
12840
12841
12842
              return com out(&cmd);
12843
12845
      w transfer
12847
      12848 PRIVATE int w_transfer(proc_nr, opcode, position, iov, nr_req)
12849 int proc_nr;
                                 /* process doing the request */
12850 int opcode;
                                   /* DEV_GATHER or DEV_SCATTER */
                                   /* offset on device to read or write */
12851 off_t position;
12852 iovec_t *iov;
                                   /* pointer to read or write request vector */
12853
      unsigned nr_req;
                                   /* length of request vector */
12854
12855
        struct wini *wn = w wn;
12856
        iovec_t *iop, *iov_end = iov + nr_req;
12857
        int r, s, errors;
        unsigned long block;
12858
        unsigned long dv_size = cv64ul(w_dv->dv_size);
12859
12860
        unsigned cylinder, head, sector, nbytes;
12861
12862
        /* Check disk address. */
12863
        if ((position & SECTOR_MASK) != 0) return(EINVAL);
12864
12865
        errors = 0;
12866
12867
        while (nr_req > 0) {
              /* How many bytes to transfer? */
12868
12869
              nbvtes = 0;
12870
              for (iop = iov; iop < iov end; iop++) nbytes += iop->iov size;
12871
              if ((nbytes & SECTOR_MASK) != 0) return(EINVAL);
12872
              /* Which block on disk and how close to EOF? */
12873
12874
              if (position >= dv_size) return(OK);
                                                          /* At EOF */
12875
              if (position + nbytes > dv_size) nbytes = dv_size - position;
12876
              block = div64u(add64ul(w_dv->dv_base, position), SECTOR_SIZE);
12877
12878
              if (nbytes >= wn->max_count) {
12879
                     /* The drive can't do more then max_count at once. */
12880
                     nbvtes = wn->max count;
12881
12882
12883
              /* First check to see if a reinitialization is needed. */
12884
              if (!(wn->state & INITIALIZED) && w_specify() != OK) return(EIO);
12885
12886
              /* Tell the controller to transfer nbytes bytes. */
12887
              r = do_transfer(wn, wn->precomp, ((nbytes >> SECTOR_SHIFT) & BYTE),
12888
                     block, opcode);
12889
12890
              while (r == OK && nbytes > 0) {
12891
                     /* For each sector, wait for an interrupt and fetch the data
```

```
Feb 25, 11 15:18
                                      book.txt
                                                                       Page 164/393
       File: Page: 801 drivers/at wini/at wini.c
12892
                       * (read), or supply data to the controller and wait for an
12893
                        * interrupt (write).
12894
12895
12896
                       if (opcode == DEV_GATHER) {
12897
                              /* First an interrupt, then data. */
12898
                              if ((r = at_intr_wait()) != OK) {
12899
                                      /* An error, send data to the bit bucket. */
12900
                                      if (w_wn->w_status & STATUS_DRQ) {
12901
               if ((s=sys_insw(wn->base_cmd + REG_DATA, SELF, tmp_buf, SECTOR_SIZE)) !=
OK)
12902
                       panic(w name(), "Call to sys insw() failed", s);
12903
12904
                                      break;
12905
12906
12907
12908
                       /* Wait for data transfer requested. */
12909
                      if (!w_waitfor(STATUS_DRQ, STATUS_DRQ)) { r = ERR; break; }
12910
12911
                       /* Copy bytes to or from the device's buffer. */
12912
                       if (opcode == DEV_GATHER) {
12913
               if ((s=sys_insw(wn->base_cmd + REG_DATA, proc_nr, (void *) iov->iov_addr
 SECTOR_SIZE)) != OK)
12914
                      panic(w_name(), "Call to sys_insw() failed", s);
12915
                       } else {
12916
               if ((s=sys outsw(wn->base cmd + REG DATA, proc nr, (void *) iov->iov add
r, SECTOR_SIZE)) != OK)
12917
                      panic(w_name(), "Call to sys_insw() failed", s);
12918
12919
                              /* Data sent, wait for an interrupt. */
12920
                              if ((r = at_intr_wait()) != OK) break;
12921
12922
                       /* Book the bytes successfully transferred. */
12923
12924
                      nbytes -= SECTOR_SIZE;
                      position += SECTOR SIZE;
12925
12926
                      iov->iov_addr += SECTOR_SIZE;
12927
                      if ((iov->iov size -= SECTOR SIZE) == 0) { iov++; nr req--; }
12928
12929
               /* Any errors? */
12930
12931
               if (r != OK) {
12932
                       /* Don't retry if sector marked bad or too many errors. */
12933
                       if (r == ERR BAD SECTOR | | ++errors == max errors) {
12934
                              w command = CMD IDLE;
12935
                              return(ETO);
12936
12937
12938
12939
12940
         w command = CMD IDLE;
12941
         return(OK);
12942
12944
12945
                                     com out
12946
        12947 PRIVATE int com_out(cmd)
12948 struct command *cmd;
                                      /* Command block */
12949
12950 /* Output the command block to the winchester controller and return status */
12951
```

```
Feb 25, 11 15:18
                                    book.txt
                                                                   Page 165/393
      File: Page: 802 drivers/at wini/at wini.c
12952
        struct wini *wn = w wn;
12953
        unsigned base_cmd = wn->base_cmd;
12954
        unsigned base_ctl = wn->base_ctl;
12955
        pvb_pair_t outbyte[7];
                                            /* vector for sys_voutb() */
12956
                                            /* status for sys_(v)outb() */
        int s;
12957
12958
        if (w_wn->state & IGNORING) return ERR;
12959
12960
        if (!w waitfor(STATUS BSY, 0)) {
12961
              printf("%s: controller not ready\n", w_name());
12962
              return(ERR);
12963
12964
        /* Select drive. */
12965
        if ((s=sys outb(base cmd + REG LDH, cmd->ldh)) != OK)
12966
12967
              panic(w_name(), "Couldn't write register to select drive",s);
12968
12969
        if (!w_waitfor(STATUS_BSY, 0)) {
12970
              printf("%s: com_out: drive not ready\n", w_name());
12971
              return(ERR);
12972
12973
12974
        /* Schedule a wakeup call, some controllers are flaky. This is done with
         * a synchronous alarm. If a timeout occurs a SYN ALARM message is sent
12975
12976
         * from HARDWARE, so that w_intr_wait() can call w_timeout() in case the
12977
         * controller was not able to execute the command. Leftover timeouts are
12978
         * simply ignored by the main loop.
12979
12980
        sys_setalarm(wakeup_ticks, 0);
12981
12982
        wn->w status = STATUS ADMBSY;
12983
        w_command = cmd->command;
12984
        pv_set(outbyte[0], base_ctl + REG_CTL, wn->pheads >= 8 ? CTL_EIGHTHEADS : 0);
        pv_set(outbyte[1], base_cmd + REG_PRECOMP, cmd->precomp);
12985
12986
        pv_set(outbyte[2], base_cmd + REG_COUNT, cmd->count);
12987
        pv_set(outbyte[3], base_cmd + REG_SECTOR, cmd->sector);
12988
        pv_set(outbyte[4], base_cmd + REG_CYL_LO, cmd->cyl_lo);
12989
        pv_set(outbyte[5], base_cmd + REG_CYL_HI, cmd->cyl_hi);
12990
        pv_set(outbyte[6], base_cmd + REG_COMMAND, cmd->command);
        if ((s=sys_voutb(outbyte,7)) != OK)
12991
12992
              panic(w_name(), "Couldn't write registers with sys_voutb()",s);
12993
        return(OK);
12994 }
      12997
                                    w need reset
12998
      *_____*/
12999 PRIVATE void w_need_reset()
13000
13001 /* The controller needs to be reset. */
13002
       struct wini *wn;
13003
        int dr = 0;
13004
        for (wn = wini; wn < &wini[MAX DRIVES]; wn++, dr++) {
13005
13006
             if (wn->base_cmd == w_wn->base_cmd) {
13007
                     wn->state |= DEAF;
                     wn->state &= ~INITIALIZED;
13008
13009
13010
13011 }
```

```
Feb 25, 11 15:18
                              book.txt
                                                        Page 166/393
     File: Page: 803 drivers/at wini/at wini.c
13013 /*=============*
13014 *
                             w_do_close
13015
     13016 PRIVATE int w_do_close(dp, m_ptr)
13017 struct driver *dp;
13018 message *m_ptr;
13019
13020 /* Device close: Release a device. */
      if (w_prepare(m_ptr->DEVICE) == NIL_DEV)
13021
13022
           return(ENXIO);
13023
       w wn->open ct--;
      return(OK);
13024
13025 }
13028 *
                             com_simple
13029 *=======*
13030 PRIVATE int com simple(cmd)
13031 struct command *cmd;
                              /* Command block */
13032
13033
     /* A simple controller command, only one interrupt and no data-out phase. */
13034
      int r;
13035
13036
       if (w_wn->state & IGNORING) return ERR;
13037
13038
       if ((r = com out(cmd)) == OK) r = at intr wait();
       w_command = CMD_IDLE;
13039
13040
       return(r);
13041
13043
     /*_____*
13044
                            w_timeout
13045
      13046
     PRIVATE void w_timeout(void)
13047
13048
       struct wini *wn = w_wn;
13049
13050
       switch (w_command) {
       case CMD_IDLE:
13051
                        /* fine */
13052
           break;
13053
       case CMD READ:
13054
       case CMD WRITE:
13055
           /* Impossible, but not on PC's: The controller does not respond. */
13056
13057
           /* Limiting multisector I/O seems to help. */
13058
           if (wn->max_count > 8 * SECTOR_SIZE) {
13059
                 wn->max_count = 8 * SECTOR_SIZE;
13060
            } else {
13061
                  wn->max_count = SECTOR_SIZE;
13062
13063
            /*FALL THROUGH*/
13064
       default:
13065
           /* Some other command. */
           if (w_testing) wn->state |= IGNORING; /* Kick out this drive. */
13066
           else if (!w_silent) printf("%s: timeout on command %02x\n", w_name(), w
13067
command);
13068
           w need reset();
13069
           wn->w_status = 0;
13070
13071 }
```

```
Feb 25, 11 15:18
                                 book.txt
                                                             Page 167/393
      File: Page: 804 drivers/at wini/at wini.c
w_reset
13075
      13076
     PRIVATE int w_reset()
13077
13078
     /* Issue a reset to the controller. This is done after any catastrophe,
      * like the controller refusing to respond.
13079
13080
13081
       int s;
       struct wini *wn = w wn;
13082
13083
13084
       /* Don't bother if this drive is forgotten. */
13085
       if (w_wn->state & IGNORING) return ERR;
13086
13087
       /* Wait for any internal drive recovery. */
13088
       tickdelay(RECOVERY_TICKS);
13089
13090
        /* Strobe reset bit */
13091
       if ((s=sys_outb(wn->base_ctl + REG_CTL, CTL_RESET)) != OK)
13092
             panic(w_name(), "Couldn't strobe reset bit", s);
13093
       tickdelay(DELAY_TICKS);
13094
       if ((s=sys_outb(wn->base_ctl + REG_CTL, 0)) != OK)
13095
            panic(w name(), "Couldn't strobe reset bit", s);
13096
       tickdelay(DELAY_TICKS);
13097
13098
        /* Wait for controller ready */
13099
       if (!w_waitfor(STATUS_BSY, 0)) {
            printf("%s: reset failed, drive busy\n", w_name());
13100
            return(ERR);
13101
13102
13103
13104
       /* The error register should be checked now, but some drives mess it up. */
13105
       for (wn = wini; wn < &wini[MAX_DRIVES]; wn++) {
13106
13107
            if (wn->base_cmd == w_wn->base_cmd) {
13108
                   wn->state &= ~DEAF;
13109
                   if (w_wn->irq_need_ack) {
13110
                          /* Make sure irq is actually enabled.. */
13111
                          sys_irqenable(&w_wn->irq_hook_id);
13112
13113
13114
13115
13116
13117
       return(OK);
13118
13120
     /*----*
13121
                                w_intr_wait
13122
      13123
      PRIVATE void w_intr_wait()
13124
13125 /* Wait for a task completion interrupt. */
13126
13127
       message m;
13128
       if (w_wn->irq != NO_IRQ) {
13129
13130
             /* Wait for an interrupt that sets w_status to "not busy". */
13131
             while (w wn->w status & (STATUS ADMBSY STATUS BSY)) {
```

```
Feb 25, 11 15:18
                                  book.txt
                                                               Page 168/393
      File: Page: 805 drivers/at wini/at wini.c
13132
                    receive(ANY, &m);
                                                /* expect HARD_INT message */
13133
                    if (m.m_type == SYN_ALARM) {
                                                /* but check for timeout */
                                                /* a.o. set w_status */
13134
                       w_timeout();
13135
                    } else if (m.m_type == HARD_INT) {
13136
                       sys_inb(w_wn->base_cmd + REG_STATUS, &w_wn->w_status);
13137
                       ack_irgs(m.NOTIFY_ARG);
13138
                    } else {
13139
                           printf("AT_WINI got unexpected message %d from %d\n",
                                  m.m_type, m.m_source);
13140
13141
13142
13143
        } else {
             /* Interrupt not yet allocated; use polling. */
13144
13145
             (void) w_waitfor(STATUS_BSY, 0);
13146
13147 }
     /*_____*
13150
                                at_intr_wait
13151
      *========*/
     PRIVATE int at_intr_wait()
13153
      /* Wait for an interrupt, study the status bits and return error/success. */
13154
13155
       int r;
       int s, inbval;
13156
                           /* read value with sys_inb */
13157
13158
        w intr wait();
13159
        if ((w_wn->w_status & (STATUS_BSY | STATUS_WF | STATUS_ERR)) == 0) {
13160
             r = OK;
13161
        } else {
13162
             if ((s=sys_inb(w_wn->base_cmd + REG_ERROR, &inbval)) != OK)
13163
                   panic(w_name(), "Couldn't read register",s);
13164
             if ((w_wn->w_status & STATUS_ERR) && (inbval & ERROR_BB)) {
                   r = ERR_BAD_SECTOR;
                                       /* sector marked bad, retries won't help
13165
* /
13166
             } else {
13167
                    r = ERR;
                                        /* any other error */
13168
13169
13170
        w_wn->w_status |= STATUS_ADMBSY;
                                        /* assume still busy with I/O */
13171
        return(r);
13172
13174
     13175
                                w waitfor
13176
      13177 PRIVATE int w_waitfor(mask, value)
13178 int mask;
                                 /* status mask */
13179 int value;
                                  /* required status */
13180
13181 /* Wait until controller is in the required state. Return zero on timeout.
13182
       * An alarm that set a timeout flag is used. TIMEOUT is in micros, we need
       * ticks. Disabling the alarm is not needed, because a static flag is used
13183
13184
       * and a leftover timeout cannot do any harm.
13185
13186
        clock_t t0, t1;
13187
        int s;
       getuptime(&t0);
13188
13189
        do {
13190
             if ((s=sys inb(w wn->base cmd + REG STATUS, &w wn->w status)) != OK)
13191
                    panic(w name(), "Couldn't read register",s);
```

```
Feb 25, 11 15:18
                                  book.txt
                                                               Page 169/393
      File: Page: 806 drivers/at wini/at wini.c
13192
             if ((w_wn->w_status & mask) == value) {
13193
                   return 1;
13194
13195
        while ((s=getuptime(&t1)) == OK && (t1-t0) < timeout ticks );</pre>
        if (OK != s) printf("AT_WINI: warning, get_uptime failed: %d\n",s);
13196
13197
13198
        w need reset();
                                         /* controller gone deaf */
13199
        return(0);
13200
13202
13203
                                w geometry
13204
       *=======*/
      PRIVATE void w_geometry(entry)
13205
      struct partition *entry;
13206
13207
13208
        struct wini *wn = w_wn;
13209
13210
       if (wn->state & ATAPI) {
                                        /* Make up some numbers. */
13211
             entry->cylinders = div64u(wn->part[0].dv_size, SECTOR_SIZE) / (64*32);
13212
             entry->heads = 64;
             entry->sectors = 32;
13213
13214
       } else {
                                         /* Return logical geometry. */
            entry->cylinders = wn->lcylinders;
13215
             entry->heads = wn->lheads;
13216
13217
             entry->sectors = wn->lsectors;
13218
13219 }
13221 /*-----*
                                 w_other
13222
13224 PRIVATE int w_other(dr, m)
13225 struct driver *dr;
13226 message *m;
13227 {
13228
             int r, timeout, prev;
13229
13230
             if (m->m type != DEV IOCTL ) {
                    return EINVAL;
13231
13232
13233
             if (m->REQUEST == DIOCTIMEOUT) {
13234
13235
                    if ((r=sys_datacopy(m->PROC_NR, (vir_bytes)m->ADDRESS,
                           SELF, (vir_bytes)&timeout, sizeof(timeout))) != OK)
13236
13237
                           return r;
13238
                    if (timeout == 0) {
13239
                           /* Restore defaults. */
13240
13241
                           timeout_ticks = DEF_TIMEOUT_TICKS;
13242
                           max_errors = MAX_ERRORS;
13243
                           wakeup_ticks = WAKEUP;
13244
                           w_silent = 0;
                    } else if (timeout < 0) {
13245
13246
                           return EINVAL;
13247
                    } else
                           prev = wakeup ticks;
13248
13249
13250
                           if (!w_standard_timeouts) {
13251
                                  /* Set (lower) timeout, lower error
```

```
Feb 25, 11 15:18
                                   book.txt
                                                                Page 170/393
      File: Page: 807 drivers/at wini/at wini.c
13252
                                    * tolerance and set silent mode.
13253
13254
                                  wakeup_ticks = timeout;
13255
                                  max errors = 3;
13256
                                  w silent = 1;
13257
13258
                                  if (timeout ticks > timeout)
13259
                                         timeout_ticks = timeout;
13260
13261
13262
                           if ((r=sys_datacopy(SELF, (vir_bytes)&prev,
13263
                                  m->PROC NR, (vir bytes)m->ADDRESS, sizeof(prev))
) != OK)
13264
                                  return r;
13265
13266
13267
                    return OK;
13268
             } else if (m->REQUEST == DIOCOPENCT) {
13269
                    int count;
                    if (w_prepare(m->DEVICE) == NIL_DEV) return ENXIO;
13270
13271
                    count = w_wn->open_ct;
13272
                    if ((r=sys_datacopy(SELF, (vir_bytes)&count,
13273
                           m->PROC_NR, (vir_bytes)m->ADDRESS, sizeof(count))) != OK
13274
                           return r;
13275
                    return OK;
13276
13277
             return EINVAL;
13278
13281
                                  w_hw_int
13282
13283 PRIVATE int w hw int(dr. m)
13284 struct driver *dr;
13285 message *m;
13286 {
        /* Leftover interrupt(s) received; ack it/them. */
13287
13288
        ack irgs(m->NOTIFY ARG);
13289
13290
        return OK;
13291 }
13294 /*-----*
13295
                                  ack irgs
13296
       *----*
13297 PRIVATE void ack_irqs(unsigned int irqs)
13298 {
13299
        unsigned int drive;
13300
        for (drive = 0; drive < MAX_DRIVES && irgs; drive++) {
13301
             if (!(wini[drive].state & IGNORING) && wini[drive].irq_need_ack &&
13302
                    (wini[drive].irq_mask & irqs)) {
13303
                    if (sys_inb((wini[drive].base_cmd + REG_STATUS), &wini[drive].w_
status) != OK)
13304
                           printf("couldn't ack irq on drive %d\n", drive);
                    if (sys_irqenable(&wini[drive].irq_hook_id) != OK)
13305
                           printf("couldn't re-enable drive %d\n", drive);
13306
                    irqs &= ~wini[drive].irq_mask;
13307
13308
13309
13310 }
```

```
Feb 25, 11 15:18
                                   book.txt
                                                                 Page 171/393
      File: Page: 808 drivers/at wini/at wini.c
13313 #define STSTR(a) if (status & STATUS_ ## a) { strcat(str, #a); strcat(str, " ");
13314 #define ERRSTR(a) if (e & ERROR_ ## a) { strcat(str, #a); strcat(str, " "); }
13315 char *strstatus(int status)
13316 {
13317
              static char str[200];
13318
              str[0] = ' \setminus 0';
13319
13320
              STSTR(BSY);
13321
              STSTR(DRDY);
13322
              STSTR (DMADF);
              STSTR(SRVCDSC);
13323
13324
              STSTR(DRQ);
              STSTR(CORR);
13325
13326
              STSTR (CHECK);
13327
             return str;
13328 }
13330 char *strerr(int e)
13331 {
13332
              static char str[200];
             str[0] = '\0';
13333
13334
13335
              ERRSTR(BB);
13336
              ERRSTR(ECC);
13337
              ERRSTR(ID);
13338
              ERRSTR(AC);
13339
              ERRSTR (TK);
              ERRSTR(DM);
13340
13341
13342
              return str;
13343 }
drivers/tty/tty.h
13400 /*
              tty.h - Terminals
13401
13402 #include <timers.h>
13403
13404 /* First minor numbers for the various classes of TTY devices. */
13405 #define CONS_MINOR
                               Ω
13406 #define LOG_MINOR
                              15
13407 #define RS232 MINOR
                              16
13408 #define TTYPX_MINOR
                             128
13409 #define PTYPX_MINOR
13410
13411 #define LINEWRAP
                             1
                                   /* console.c - wrap lines at column 80 */
13412
13413 #define TTY_IN_BYTES
                             256
                                   /* tty input queue size */
                                   /* distance between tab stops */
13414 #define TAB SIZE
                              8
13415 #define TAB MASK
                                   /* mask to compute a tab stop position */
13416
                            '\33'
13417 #define ESC
                                   /* escape */
13418
13419 #define O NOCTTY
                           00400
                                   /* from <fcntl.h>, or cc will choke */
```

```
Feb 25, 11 15:18
                                        book.txt
                                                                         Page 172/393
       File: Page: 809 drivers/tty/tty.h
13420
       #define O NONBLOCK
13421
13422
13423
       typedef _PROTOTYPE( int (*devfun_t), (struct tty *tp, int try_only) );
       typedef _PROTOTYPE( void (*devfunarg_t), (struct tty *tp, int c) );
13424
13425
13426
       typedef struct tty {
                                       /* set when TTY should inspect this line */
13427
         int tty_events;
                                       /* index into TTY table */
13428
         int tty index;
         int tty_minor;
                                       /* device minor number */
13429
13430
13431
         /* Input queue. Typed characters are stored here until read by a program. */
         u16_t *tty_inhead;
u16_t *tty_intail;
                                       /* pointer to place where next char goes */
13432
                                       /* pointer to next char to be given to prog */
13433
13434
         int tty incount;
                                       /* # chars in the input queue */
13435
         int tty eotct;
                                       /* number of "line breaks" in input queue */
13436
         devfun_t tty_devread;
                                       /* routine to read from low level buffers */
         devfun_t tty_icancel;
                                       /* cancel any device input */
13437
13438
                                       /* minimum requested #chars in input queue */
         int tty_min;
         timer_t tty_tmr;
13439
                                       /* the timer for this tty */
13440
13441
         /* Output section. */
13442
         devfun_t tty_devwrite;
                                       /* routine to start actual device output */
                                       /* routine to echo characters input */
13443
         devfunarg t tty echo;
                                       /* cancel any ongoing device output */
13444
         devfun_t tty_ocancel;
13445
         devfun t tty break;
                                       /* let the device send a break */
13446
13447
         /* Terminal parameters and status. */
                                       /* current position on the screen for echoing */
13448
         int tty_position;
13449
                                       /* 1 when echoed input messed up, else 0 */
         char tty reprint;
13450
                                       /* 1 when LNEXT (^V) just seen, else 0 */
         char tty_escaped;
13451
         char tty_inhibited;
                                       /* 1 when STOP (^S) just seen (stops output) */
13452
         char tty_pgrp;
                                       /* slot number of controlling process */
13453
                                       /* count of number of opens of this tty */
         char tty_openct;
13454
13455
         /* Information about incomplete I/O requests is stored here. */
13456
         char tty_inrepcode;
                                       /* reply code, TASK_REPLY or REVIVE */
                                       /* set to 1 if revive callback is pending */
13457
         char tty_inrevived;
13458
         char tty incaller;
                                       /* process that made the call (usually FS) */
13459
         char tty_inproc;
                                       /* process that wants to read from tty */
13460
         vir_bytes tty_in_vir;
                                       /* virtual address where data is to go */
         int tty inleft;
                                       /* how many chars are still needed */
13461
                                       /* # chars input so far */
13462
         int tty_incum;
13463
         char tty_outrepcode;
                                       /* reply code, TASK_REPLY or REVIVE */
                                       /* set to 1 if revive callback is pending */
13464
         char tty outrevived;
13465
         char tty_outcaller;
                                       /* process that made the call (usually FS) */
13466
         char tty_outproc;
                                       /* process that wants to write to tty */
                                       /* virtual address where data comes from */
13467
         vir_bytes tty_out_vir;
         int tty_outleft;
13468
                                       /* # chars vet to be output */
13469
         int tty_outcum;
                                       /* # chars output so far */
13470
         char tty_iocaller;
                                       /* process that made the call (usually FS) */
13471
         char tty_ioproc;
                                       /* process that wants to do an ioctl */
                                       /* ioctl request code */
13472
         int tty_ioreq;
                                       /* virtual address of ioctl buffer */
13473
         vir_bytes tty_iovir;
13474
13475
         /* select() data */
         int tty select ops;
13476
                                       /* which operations are interesting */
13477
                                       /* which process wants notification */
         int tty_select_proc;
13478
13479
         /* Miscellaneous. */
```

```
book.txt
Feb 25, 11 15:18
                                                                        Page 173/393
       File: Page: 810 drivers/tty/tty.h
         devfun_t tty_ioctl;
13480
                                       /* set line speed, etc. at the device level */
                                       /* tell the device that the tty is closed */
13481
         devfun_t tty_close;
                                       /* pointer to per device private data */
13482
         void *tty_priv;
13483
         struct termios tty_termios; /* terminal attributes */
         struct winsize tty_winsize; /* window size (#lines and #columns) */
13484
13485
13486
         ul6_t tty_inbuf[TTY_IN_BYTES];/* tty input buffer */
13487
13488 } tty_t;
13489
13490
      /* Memory allocated in tty.c, so extern here. */
13491 extern tty_t tty_table[NR_CONS+NR_RS_LINES+NR_PTYS];
                                   /* currently visible console */
13492 extern int ccurrent;
13493 extern int irq_hook_id;
                                       /* hook id for keyboard irq */
13494
13495 extern unsigned long kbd_irq_set;
13496 extern unsigned long rs_irq_set;
13497
13498 /* Values for the fields. */
13499 #define NOT_ESCAPED
                                       /* previous character is not LNEXT (^V) */
13500 #define ESCAPED
                                      /* previous character was LNEXT (^V) */
13501 #define RUNNING
                                  0
                                      /* no STOP (^S) has been typed to stop output */
13502 #define STOPPED
                                 1
                                      /* STOP (^S) has been typed to stop output */
13504 \mbox{ /* Fields} and flags on characters in the input queue. */ 13505 \mbox{ \#define IN\_CHAR} \mbox{ 0x00FF} \mbox{ /* low 8 bits are the character itself */ }
                                       /* length of char if it has been echoed */
13506 #define IN LEN
                             0x0F00
13507 #define IN LSHIFT
                                8
                                      /* length = (c & IN_LEN) >> IN_LSHIFT */
                             0x1000
                                      /* char is a line break (^D, LF) */
13508 #define IN_EOT
13509 #define IN EOF
                             0x2000
                                      /* char is EOF (^D), do not return to user */
13510 #define IN ESC
                             0x4000
                                      /* escaped by LNEXT (^V), no interpretation */
13511
13512 /* Times and timeouts. */
13513 #define force_timeout() ((void) (0))
13514
13515 /* Memory allocated in tty.c, so extern here. */
13516 extern timer_t *tty_timers; /* queue of TTY timers */
13517 extern clock_t tty_next_timeout;
                                               /* next TTY timeout */
13518
13519 /* Number of elements and limit of a buffer. */
                            (sizeof(buf) / sizeof((buf)[0]))
13520 #define buflen(buf)
13521 #define bufend(buf)
                              ((buf) + buflen(buf))
13522
13523 /* Memory allocated in tty.c, so extern here. */
13524 extern struct machine machine; /* machine information (a.o.: pc at, eqa) */
13525
13526 /* Function prototypes for TTY driver. */
13527 /* tty.c */
13528 _PROTOTYPE( void handle_events, (struct tty *tp)
                                                                               );
13529 _PROTOTYPE( void sigchar, (struct tty *tp, int sig)
                                                                               );
13530 _PROTOTYPE( void tty_task, (void)
                                                                               );
13531 _PROTOTYPE( int in_process, (struct tty *tp, char *buf, int count)
13532 _PROTOTYPE( void out_process, (struct tty *tp, char *bstart, char *bpos,
                                       char *bend, int *icount, int *ocount)
13533
13534 _PROTOTYPE( void tty_wakeup, (clock_t now)
                                                                               );
13535 _PROTOTYPE( void tty_reply, (int code, int replyee, int proc_nr,
13536
                                                              int status)
13537 _PROTOTYPE( int tty_devnop, (struct tty *tp, int try)
                                                                               );
13538
      _PROTOTYPE( int select_try, (struct tty *tp, int ops)
                                                                               );
13539 PROTOTYPE( int select retry, (struct tty *tp)
```

```
Feb 25, 11 15:18
                                      book.txt
                                                                     Page 174/393
       File: Page: 811 drivers/tty/tty.h
13540
13541 /* console.c */
13542 _PROTOTYPE( void kputc, (int c)
13543 _PROTOTYPE( void cons_stop, (void)
                                                                           );
13544 _PROTOTYPE( void do_new_kmess, (message *m)
                                                                            );
13545 _PROTOTYPE( void do_diagnostics, (message *m)
                                                                           );
13546 _PROTOTYPE( void scr_init, (struct tty *tp) 13547 _PROTOTYPE( void toggle_scroll, (void)
                                                                            );
                                                                           );
13548 PROTOTYPE( int con loadfont, (message *m)
                                                                           );
13549 _PROTOTYPE( void select_console, (int cons_line)
                                                                           );
13550
13551 /* keyboard.c */
13552 _PROTOTYPE( void kb_init, (struct tty *tp)
                                                                           );
13553 _PROTOTYPE( void kb_init_once, (void)
                                                                            );
13554 PROTOTYPE( int kbd loadmap, (message *m)
                                                                            );
13555
      _PROTOTYPE( void do_panic_dumps, (message *m)
                                                                           );
13556 _PROTOTYPE( void do_fkey_ctl, (message *m)
                                                                           );
13557 _PROTOTYPE( void kbd_interrupt, (message *m)
                                                                           );
13558
13559 /* vidcopy.s */
13560 _PROTOTYPE( void vid_vid_copy, (unsigned src, unsigned dst, unsigned count));
13561 _PROTOTYPE( void mem_vid_copy, (ul6_t *src, unsigned dst, unsigned count));
drivers/ttv/ttv.c
13600 /* This file contains the terminal driver, both for the IBM console and regular
13601 * ASCII terminals. It handles only the device-independent part of a TTY, the
       * device dependent parts are in console.c, rs232.c, etc. This file contains
        * two main entry points, tty_task() and tty_wakeup(), and several minor entry
13603
        * points for use by the device-dependent code.
13604
13605
13606
        * The device-independent part accepts "keyboard" input from the device-
        * dependent part, performs input processing (special key interpretation),
13607
        * and sends the input to a process reading from the TTY. Output to a TTY
13608
        * is sent to the device-dependent code for output processing and "screen"
13609
        * display. Input processing is done by the device by calling 'in_process'
13610
        * on the input characters, output processing may be done by the device itself
13611
        * or by calling 'out_process'. The TTY takes care of input queuing, the
13612
13613
        * device does the output queuing. If a device receives an external signal,
        * like an interrupt, then it causes tty_wakeup() to be run by the CLOCK task
13614
13615
        * to, you guessed it, wake up the TTY to check if input or output can
13616
        * continue
13617
13618
        * The valid messages and their parameters are:
13619
13620
                            output has been completed or input has arrived
                          e.g., MINIX wants to shutdown; run code to cleanly stop
13621
           SYS_SIG:
13622
           DEV_READ:
                           a process wants to read from a terminal
13623
           DEV WRITE:
                            a process wants to write on a terminal
           DEV_IOCTL:
13624
                            a process wants to change a terminal's parameters
13625
           DEV OPEN:
                            a tty line has been opened
           DEV CLOSE:
                            a tty line has been closed
13626
           DEV_SELECT:
13627
                            start select notification request
13628
           DEV_STATUS:
                            FS wants to know status for SELECT or REVIVE
13629
           CANCEL:
                            terminate a previous incomplete system call immediately
```

Feb 2	5, 11	15:18	book.txt				Page 175/393	
File: Page: 812 drivers/tty/tty.c 13630 *								
13631	* *	m_type	TTY_LINE	PROC_NR	COUNT	TTY_SPEK	TTY_FLAGS	ADDRESS
	* *	HARD_INT	 +			 +		
13635 13636	*	SYS_SIG	sig set	<u> </u>	<u>į</u>	<u>į</u>	<u> </u>	
13637		DEV_READ	minor dev	proc nr	count	(O_NONBLOCK	buf ptr
13639	*	DEV_WRITE	minor dev	proc nr	count			buf ptr
13640 13641 13642	*	DEV_IOCTL	minor dev	proc nr	func code	erase etc	flags	
13643	*	DEV_OPEN	minor dev	proc nr	O_NOCTTY	İ		
13644 13645	*	DEV_CLOSE	minor dev	proc nr				
13646 13647		DEV_STATUS						
13648 13649 13650		CANCEL		proc nr	†	†	+ 	
13653 13654 13655 13656 13657 13658 13661 13662 13663 13664 13665 13667 13667 13672 13673 13674 13675 13676 13676 13676 13676 13676 13676 13676	* C * * * * * * / #inc #inc #inc #inc #inc #inc #inc #inc	Changes: Jan 20, 2004 moved TTY driver to user-space (Jorrit N. Herder) Sep 20, 2004 local timer management/ sync alarms (Jorrit N. Herder) Jul 13, 2004 support for function key observers (Jorrit N. Herder)						
13686 13687 13688	<pre>/* A device exists if at least its 'devread' function is defined. */ #define tty_active(tp) ((tp)->tty_devread != NULL) /* RS232 lines or pseudo terminals can be completely configured out. */</pre>							
13689	/* F	x5232 lines or	pseudo te	rulnals ca	n be compl	ecely confi	igured out.	~/

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 176/393
       File: Page: 813 drivers/tty/tty.c
13690 #if NR RS LINES == 0
13691 #define rs_init(tp)
                             ((void) 0)
13692 #endif
13693 #if NR_PTYS == 0
13694 #define pty_init(tp) ((void) 0)
13695 #define do_pty(tp, mp) ((void) 0)
13696 #endif
13697
13698 FORWARD _PROTOTYPE( void tty_timed_out, (timer_t *tp)
13699 FORWARD _PROTOTYPE( void expire_timers, (void)
                                                                          );
13700 FORWARD _PROTOTYPE( void settimer, (tty_t *tty_ptr, int enable)
                                                                          );
13701 FORWARD _PROTOTYPE( void do_cancel, (tty_t *tp, message *m_ptr)
                                                                          );
13702 FORWARD _PROTOTYPE( void do_ioctl, (tty_t *tp, message *m_ptr)
                                                                          );
13703 FORWARD _PROTOTYPE( void do_open, (tty_t *tp, message *m_ptr)
                                                                          );
13704 FORWARD _PROTOTYPE( void do_close, (tty_t *tp, message *m_ptr)
                                                                          );
13705 FORWARD _PROTOTYPE( void do_read, (tty_t *tp, message *m_ptr)
                                                                          );
13706 FORWARD _PROTOTYPE( void do_write, (tty_t *tp, message *m_ptr)
                                                                          );
13707 FORWARD PROTOTYPE( void do_select, (tty_t *tp, message *m_ptr)
                                                                          );
13708 FORWARD _PROTOTYPE( void do_status, (message *m_ptr)
                                                                          );
13709 FORWARD _PROTOTYPE( void in_transfer, (tty_t *tp)
                                                                          );
13710 FORWARD _PROTOTYPE( int tty_echo, (tty_t *tp, int ch)
                                                                          );
13711 FORWARD _PROTOTYPE( void rawecho, (tty_t *tp, int ch)
                                                                          );
13712 FORWARD _PROTOTYPE( int back_over, (tty_t *tp)
                                                                          );
13713 FORWARD _PROTOTYPE( void reprint, (tty_t *tp)
                                                                          );
13714 FORWARD _PROTOTYPE( void dev_ioctl, (tty_t *tp)
                                                                          );
13715 FORWARD _PROTOTYPE( void setattr, (tty_t *tp)
                                                                          );
13716 FORWARD _PROTOTYPE( void tty_icancel, (tty_t *tp)
                                                                          );
13717 FORWARD _PROTOTYPE( void tty_init, (void)
                                                                          );
13718
13719 /* Default attributes. */
13720 PRIVATE struct termios termios_defaults = {
13721
        TINPUT_DEF, TOUTPUT_DEF, TCTRL_DEF, TLOCAL_DEF, TSPEED_DEF, TSPEED_DEF,
13722
13723
              TEOF_DEF, TEOL_DEF, TERASE_DEF, TINTR_DEF, TKILL_DEF, TMIN_DEF,
13724
              TQUIT_DEF, TTIME_DEF, TSUSP_DEF, TSTART_DEF, TSTOP_DEF,
13725
              TREPRINT_DEF, TLNEXT_DEF, TDISCARD_DEF,
_3,26 },
13727 };
13728 PRIVATE struct winsize winsize defaults;
                                                   /* = all zeroes */
13729
13730
       /* Global variables for the TTY task (declared extern in tty.h). */
13731 PUBLIC tty_t tty_table[NR_CONS+NR_RS_LINES+NR_PTYS];
13732 PUBLIC int ccurrent;
                                            /* currently active console */
13733 PUBLIC timer_t *tty_timers;
                                            /* queue of TTY timers */
                                          /* time that the next alarm is due */
13734 PUBLIC clock t tty next timeout;
                                            /* kernel environment variables */
13735 PUBLIC struct machine machine;
13736
13737 /*===========*
13738
                                   tty_task
13739
       *-----*/
13740 PUBLIC void main(void)
13741
       /* Main routine of the terminal task. */
13742
13743
13744
                                    /* buffer for all incoming messages */
        message tty_mess;
13745
         unsigned line;
13746
         int s;
        char *types[] = {"task", "driver", "server", "user"};
13747
13748
         register struct proc *rp;
13749
        register tty t *tp;
```

```
Feb 25, 11 15:18
                                       book.txt
                                                                         Page 177/393
       File: Page: 814 drivers/tty/tty.c
13750
13751
         /* Initialize the TTY driver. */
13752
         tty_init();
13753
13754
         /* Get kernel environment (protected_mode, pc_at and ega are needed). */
13755
         if (OK != (s=sys_getmachine(&machine))) {
13756
           panic("TTY", "Couldn't obtain kernel environment.", s);
13757
13758
13759
         /* Final one-time keyboard initialization. */
13760
         kb init once();
13761
13762
         printf("\n");
13763
         while (TRUE) {
13764
13765
13766
               /* Check for and handle any events on any of the ttys. */
               for (tp = FIRST_TTY; tp < END_TTY; tp++) {
13767
13768
                       if (tp->tty_events) handle_events(tp);
13769
13770
13771
               /* Get a request message. */
13772
               receive(ANY, &tty_mess);
13773
13774
               /* First handle all kernel notification types that the TTY supports.
13775
                * - An alarm went off, expire all timers and handle the events.
                * - A hardware interrupt also is an invitation to check for events.
13776
                * - A new kernel message is available for printing.
13777
                * - Reset the console on system shutdown.
13778
                * Then see if this message is different from a normal device driver
13779
13780
                * request and should be handled separately. These extra functions
13781
                * do not operate on a device, in constrast to the driver requests.
13782
13783
               switch (tty_mess.m_type) {
                                                /* fall through */
13784
               case SYN_ALARM:
13785
                       expire_timers();
                                               /* run watchdogs of expired timers */
13786
                       continue;
                                               /* contine to check for events */
                                                /* hardware interrupt notification */
13787
               case HARD INT: {
13788
                       if (tty_mess.NOTIFY_ARG & kbd_irq_set)
                               kbd_interrupt(&tty_mess);/* fetch chars from keyboard */
13789
13790
       #if NR RS LINES > 0
                       if (tty mess.NOTIFY ARG & rs irg set)
13791
13792
                               rs_interrupt(&tty_mess);/* serial I/O */
13793 #endif
13794
                       expire timers();
                                               /* run watchdogs of expired timers */
13795
                       continue;
                                               /* contine to check for events */
13796
13797
               case SYS_SIG: {
                                                /* system signal */
13798
                       sigset_t sigset = (sigset_t) tty_mess.NOTIFY_ARG;
13799
13800
                       if (sigismember(&sigset, SIGKSTOP)) {
                                                       /* switch to primary console */
13801
                               cons_stop();
                               if (irq_hook_id != -1) {
13802
                                       sys_irqdisable(&irq_hook_id);
13803
13804
                                       sys_irqrmpolicy(KEYBOARD_IRQ, &irq_hook_id);
13805
13806
13807
                       if (sigismember(&sigset, SIGTERM)) cons_stop();
13808
                       if (sigismember(&sigset, SIGKMESS)) do_new_kmess(&tty_mess);
13809
                       continue;
```

```
Feb 25, 11 15:18
                                         book.txt
                                                                            Page 178/393
       File: Page: 815 drivers/tty/tty.c
13810
13811
                case PANIC_DUMPS:
                                                  /* allow panic dumps */
13812
                        cons_stop();
                                                 /* switch to primary console */
13813
                        do_panic_dumps(&tty_mess);
13814
                        continue;
13815
                case DIAGNOSTICS:
                                                   /* a server wants to print some */
                        do _diagnostics(&tty_mess);
13816
13817
                        continue;
13818
                case FKEY CONTROL:
                                                  /* (un)register a fkey observer */
13819
                        do_fkey_ctl(&tty_mess);
13820
                        continue;
13821
                default:
                                                   /* should be a driver request */
                                                 /* do nothing; end switch */
13822
13823
13824
13825
                /* Only device requests should get to this point. All requests,
13826
                 * except DEV_STATUS, have a minor device number. Check this
13827
                 * exception and get the minor device number otherwise.
13828
13829
                if (tty_mess.m_type == DEV_STATUS) {
13830
                        do_status(&tty_mess);
13831
                        continue;
1.3832
13833
                line = tty_mess.TTY_LINE;
                if ((line - CONS_MINOR) < NR_CONS)
13834
13835
                        tp = tty_addr(line - CONS_MINOR);
                 else if (line == LOG_MINOR) {
13836
                 tp = tty_addr(0);
else if ((line - RS232_MINOR) < NR_RS_LINES) {</pre>
13837
13838
                        tp = tty_addr(line - RS232_MINOR + NR_CONS);
13839
13840
                } else if ((line - TTYPX_MINOR) < NR_PTYS) {
13841
                        tp = tty_addr(line - TTYPX_MINOR + NR_CONS + NR_RS_LINES);
13842
                } else if ((line - PTYPX_MINOR) < NR_PTYS) {</pre>
13843
                        tp = tty_addr(line - PTYPX_MINOR + NR_CONS + NR_RS_LINES);
13844
                        if (tty_mess.m_type != DEV_IOCTL) {
13845
                                do_pty(tp, &tty_mess);
13846
                                continue;
13847
13848
                } else +
13849
                        tp = NULL;
13850
13851
               /* If the device doesn't exist or is not configured return ENXIO. */
if (tp == NULL |  ! tty_active(tp)) {
13852
13853
13854
                        printf("Warning, TTY got illegal request %d from %d\n",
13855
                                tty_mess.m_type, tty_mess.m_source);
13856
                        tty_reply(TASK_REPLY, tty_mess.m_source,
                                                          tty_mess.PROC_NR, ENXIO);
13857
13858
                        continue;
13859
13860
13861
                /* Execute the requested device driver function. */
13862
                switch (tty_mess.m_type) {
13863
                    case DEV READ:
                                           do_read(tp, &tty_mess);
                                                                              break;
13864
                    case DEV_WRITE:
                                           do_write(tp, &tty_mess);
                                                                              break;
13865
                    case DEV IOCTL:
                                           do_ioctl(tp, &tty_mess);
                                                                              break;
13866
                    case DEV OPEN:
                                           do_open(tp, &tty_mess);
                                                                              break;
13867
                    case DEV CLOSE:
                                           do_close(tp, &tty_mess);
                                                                              break;
13868
                    case DEV_SELECT:
                                           do_select(tp, &tty_mess);
                                                                              break;
13869
                    case CANCEL:
                                           do cancel(tp, &tty mess);
                                                                              break;
```

```
book.txt
Feb 25, 11 15:18
                                                                    Page 179/393
      File: Page: 816 drivers/tty/tty.c
13870
                  default:
13871
                     printf("Warning, TTY got unexpected request %d from %d\n",
13872
                             tty_mess.m_type, tty_mess.m_source);
13873
                  tty_reply(TASK_REPLY, tty_mess.m_source,
                                                   tty_mess.PROC_NR, EINVAL);
13874
13875
13876
13877 }
13879
      /*-----*
13880
                                    do status
13881
       *-----*/
      PRIVATE void do_status(m_ptr)
13882
13883
      message *m_ptr;
13884
13885
        register struct tty *tp;
13886
        int event_found;
13887
        int status;
13888
        int ops;
13889
13890
        /* Check for select or revive events on any of the ttys. If we found an,
13891
         * event return a single status message for it. The FS will make another
13892
         * call to see if there is more.
13893
13894
        event_found = 0;
13895
        for (tp = FIRST_TTY; tp < END_TTY; tp++) {
13896
              if ((ops = select_try(tp, tp->tty_select_ops)) &&
13897
                             tp->tty_select_proc == m_ptr->m_source) {
13898
13899
                      /* I/O for a selected minor device is ready. */
13900
                     m_ptr->m_type = DEV_IO_READY;
13901
                     m_ptr->DEV_MINOR = tp->tty_index;
13902
                     m_ptr->DEV_SEL_OPS = ops;
13903
13904
                      tp->tty_select_ops &= ~ops;
                                                    /* unmark select event */
                     event_found = 1;
13905
13906
                     break;
13907
13908
              else if (tp->tty_inrevived && tp->tty_incaller == m_ptr->m_source) {
13909
13910
                      /* Suspended request finished. Send a REVIVE. */
                     m_ptr->m_type = DEV_REVIVE;
13911
                     m_ptr->REP_PROC_NR = tp->tty_inproc;
13912
13913
                     m_ptr->REP_STATUS = tp->tty_incum;
13914
13915
                     tp->tty_inleft = tp->tty_incum = 0;
13916
                     tp->tty_inrevived = 0;
                                                   /* unmark revive event */
13917
                     event_found = 1;
13918
                     break;
13919
13920
              else if (tp->tty_outrevived && tp->tty_outcaller == m_ptr->m_source) {
13921
                      /* Suspended request finished. Send a REVIVE. */
13922
                     m_ptr->m_type = DEV_REVIVE;
13923
                     m_ptr->REP_PROC_NR = tp->tty_outproc;
13924
13925
                     m_ptr->REP_STATUS = tp->tty_outcum;
13926
13927
                     tp->tty_outcum = 0;
13928
                     tp->tty_outrevived = 0;
                                                    /* unmark revive event */
13929
                     event found = 1;
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 180/393
      File: Page: 817 drivers/tty/tty.c
13930
                     break;
13931
13932
13933
13934
      #if NR_PTYS > 0
13935
        if (!event_found)
              event_found = pty_status(m_ptr);
13936
      #endif
13937
13938
13939
        if (! event_found) {
              /* No events of interest were found. Return an empty message. */
13940
13941
              m_ptr->m_type = DEV_NO_STATUS;
13942
13943
13944
        /* Almost done. Send back the reply message to the caller. */
13945
        if ((status = send(m_ptr->m_source, m_ptr)) != OK)
13946
              panic("TTY", "send in do_status failed, status\n", status);
13947
13948
13950
      13951
                                    do read
13952
       *-----*/
13953 PRIVATE void do_read(tp, m_ptr)
13954 register tty_t *tp;
                                    /* pointer to tty struct */
13955
      register message *m ptr;
                                    /* pointer to message sent to the task */
13956
13957
        * A process wants to read from a terminal. */
13958
        int r, status;
13959
        phys bytes phys addr;
13960
13961
        /* Check if there is already a process hanging in a read, check if the
13962
         * parameters are correct, do I/O.
13963
13964
        if (tp->tty_inleft > 0) {
13965
             r = EIO;
13966
         } else
        if (m_ptr->COUNT <= 0) {
13967
13968
              r = EINVAL;
13969
         } else
13970
        if (sys_umap(m_ptr->PROC_NR, D, (vir_bytes) m_ptr->ADDRESS, m_ptr->COUNT,
13971
                     &phys_addr) != OK) {
              r = EFAULT;
13972
13973
        } else {
13974
              /* Copy information from the message to the tty struct. */
13975
              tp->tty_inrepcode = TASK_REPLY;
13976
              tp->tty_incaller = m_ptr->m_source;
13977
              tp->tty_inproc = m_ptr->PROC_NR;
13978
              tp->tty_in_vir = (vir_bytes) m_ptr->ADDRESS;
13979
              tp->tty_inleft = m_ptr->COUNT;
13980
13981
              if (!(tp->tty_termios.c_lflag & ICANON)
13982
                                            && tp->tty_termios.c_cc[VTIME] > 0) {
13983
                     if (tp->tty_termios.c_cc[VMIN] == 0) {
13984
                             /* MIN & TIME specify a read timer that finishes the
                              * read in TIME/10 seconds if no bytes are available.
13985
13986
13987
                             settimer(tp, TRUE);
13988
                             tp->tty_min = 1;
13989
                     } else
```

```
book.txt
Feb 25, 11 15:18
                                                                     Page 181/393
       File: Page: 818 drivers/tty/tty.c
13990
                              /* MIN & TIME specify an inter-byte timer that may
13991
                              * have to be cancelled if there are no bytes yet.
13992
13993
                             if (tp->tty_eotct == 0) {
13004
                                     settimer(tp, FALSE);
13995
                                     tp->tty_min = tp->tty_termios.c_cc[VMIN];
13996
13997
13998
13999
14000
               /* Anything waiting in the input buffer? Clear it out... */
14001
               in transfer(tp);
14002
               /* ...then go back for more. */
14003
              handle_events(tp);
14004
              if (tp->tty inleft == 0) {
14005
                      if (tp->tty_select_ops)
14006
                             select_retry(tp);
                                             /* already done */
14007
14008
14009
14010
               /* There were no bytes in the input queue available, so either suspend
14011
               * the caller or break off the read if nonblocking.
14012
14013
              if (m_ptr->TTY_FLAGS & O_NONBLOCK) {
14014
                      r = EAGAIN;
                                                            /* cancel the read */
14015
                      tp->tty_inleft = tp->tty_incum = 0;
14016
              } else {
14017
                      r = SUSPEND;
                                                            /* suspend the caller */
14018
                      tp->tty_inrepcode = REVIVE;
14019
14020
14021
         tty_reply(TASK_REPLY, m_ptr->m_source, m_ptr->PROC_NR, r);
14022
        if (tp->tty_select_ops)
14023
              select_retry(tp);
14024
14026
      /*_____*
14027
                                    do_write
14029 PRIVATE void do_write(tp, m_ptr)
14030 register tty_t *tp;
      register message *m ptr;
                                     /* pointer to message sent to the task */
14032
14033
      /* A process wants to write on a terminal. */
14034
       int r;
14035
        phys_bytes phys_addr;
14036
14037
         /* Check if there is already a process hanging in a write, check if the
14038
         * parameters are correct, do I/O.
14039
14040
        if (tp->tty_outleft > 0) {
14041
             r = ETO;
        } else
14042
14043
        if (m_ptr->COUNT <= 0) {
14044
             r = EINVAL;
14045
          else
14046
         if (sys_umap(m_ptr->PROC_NR, D, (vir_bytes) m_ptr->ADDRESS, m_ptr->COUNT,
                      &phys_addr) != OK) {
14047
              r = EFAULT;
14048
14049
        } else {
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 182/393
      File: Page: 819 drivers/tty/tty.c
14050
              /* Copy message parameters to the tty structure. */
14051
              tp->tty_outrepcode = TASK_REPLY;
14052
              tp->tty_outcaller = m_ptr->m_source;
14053
              tp->tty_outproc = m_ptr->PROC_NR;
14054
              tp->tty_out_vir = (vir_bytes) m_ptr->ADDRESS;
14055
              tp->tty_outleft = m_ptr->COUNT;
14056
14057
              /* Try to write. */
14058
              handle events(tp);
14059
              if (tp->tty_outleft == 0)
14060
                     return; /* already done */
14061
14062
              /* None or not all the bytes could be written, so either suspend the
               * caller or break off the write if nonblocking.
14063
14064
14065
                                                           /* cancel the write */
              if (m_ptr->TTY_FLAGS & O_NONBLOCK) {
14066
                     r = tp->tty_outcum > 0 ? tp->tty_outcum : EAGAIN;
14067
                      tp->tty_outleft = tp->tty_outcum = 0;
14068
              } else {
14069
                      r = SUSPEND;
                                                           /* suspend the caller */
14070
                      tp->tty_outrepcode = REVIVE;
14071
14072
14073
        tty_reply(TASK_REPLY, m_ptr->m_source, m_ptr->PROC_NR, r);
14074
      /*----*
14077
                                    do_ioctl
14078
       *-----*
14079 PRIVATE void do ioctl(tp, m ptr)
14080 register tty_t *tp;
14081 message *m_ptr;
                                    /* pointer to message sent to task */
14082
14083
      /* Perform an IOCTL on this terminal. Posix termios calls are handled
       * by the IOCTL system call
14084
14085
14086
14087
        int r;
14088
        union
14089
              int i;
14090
        } param;
14091
        size t size;
14092
14093
        /* Size of the ioctl parameter. */
14094
        switch (m ptr->TTY REQUEST) {
14095
          case TCGETS:
                              /* Posix togetattr function */
14096
          case TCSETS:
                              /* Posix tcsetattr function, TCSANOW option */
14097
          case TCSETSW:
                              /* Posix tosetattr function, TCSADRAIN option */
14098
          case TCSETSF:
                              /* Posix tosetattr function, TCSAFLUSH option */
14099
              size = sizeof(struct termios);
14100
14101
                              /* Posix tcsendbreak function */
14102
          case TCSBRK:
                              /* Posix tcflow function */
14103
          case TCFLOW:
14104
          case TCFLSH:
                              /* Posix tcflush function */
                              /* Posix tcgetpgrp function */
14105
          case TIOCGPGRP:
          case TIOCSPGRP:
                              /* Posix tcsetpgrp function */
14106
14107
              size = sizeof(int);
14108
              break;
14109
```

```
book.txt
 Feb 25, 11 15:18
                                                                          Page 183/393
       File: Page: 820 drivers/tty/tty.c
14110
           case TIOCGWINSZ:
                                /* get window size (not Posix) */
                                 /* set window size (not Posix) */
14111
            case TIOCSWINSZ:
14112
               size = sizeof(struct winsize);
14113
                break;
14114
14115
           case KIOCSMAP:
                                 /* load keymap (Minix extension) */
                size = sizeof(keymap_t);
14116
14117
                break;
14118
           case TIOCSFON:
                                 /* load font (Minix extension) */
14119
                size = sizeof(u8 t [8192]);
14120
14121
                break;
14122
14123
            case TCDRAIN:
                                 /* Posix tcdrain function -- no parameter */
14124
           default:
14125
14126
14127
14128
         switch (m_ptr->TTY_REQUEST) {
14129
           case TCGETS:
14130
                /* Get the termios attributes. */
14131
                r = sys_vircopy(SELF, D, (vir_bytes) &tp->tty_termios,
14132
                        m_ptr->PROC_NR, D, (vir_bytes) m_ptr->ADDRESS,
14133
                        (vir bytes) size);
14134
               break;
14135
14136
           case TCSETSW:
14137
           case TCSETSF:
14138
           case TCDRAIN:
14139
                if (tp->tty outleft > 0) {
14140
                        /* Wait for all ongoing output processing to finish. */
14141
                        tp->tty_iocaller = m_ptr->m_source;
14142
                        tp->tty_ioproc = m_ptr->PROC_NR;
14143
                        tp->tty_ioreq = m_ptr->REQUEST;
14144
                        tp->tty_iovir = (vir_bytes) m_ptr->ADDRESS;
14145
                        r = SUSPEND;
14146
                        break;
14147
14148
                if (m_ptr->TTY_REQUEST == TCDRAIN) break;
                if (m_ptr->TTY_REQUEST == TCSETSF) tty_icancel(tp);
14149
14150
                /*FALL THROUGH*/
14151
            case TCSETS:
14152
                /* Set the termios attributes. */
14153
                r = sys_vircopy( m_ptr->PROC_NR, D, (vir_bytes) m_ptr->ADDRESS,
                        SELF, D, (vir_bytes) &tp->tty_termios, (vir_bytes) size);
14154
14155
                if (r != OK) break;
14156
                setattr(tp);
14157
               break;
14158
14159
            case TCFLSH:
14160
               r = sys_vircopy( m_ptr->PROC_NR, D, (vir_bytes) m_ptr->ADDRESS,
14161
                        SELF, D, (vir_bytes) &param.i, (vir_bytes) size);
14162
                if (r != OK) break;
14163
                switch (param.i) {
                    case TCIFLUSH:
14164
                                         tty_icancel(tp);
                                                                                     bre
ak;
                    case TCOFLUSH:
14165
                                         (*tp->tty ocancel)(tp, 0);
                                                                                      bre
ak;
14166
                    case TCIOFLUSH:
                                         tty_icancel(tp); (*tp->tty_ocancel)(tp, 0); bre
ak;
14167
                    default:
                                         r = EINVAL;
14168
14169
                hreak;
```

```
Feb 25, 11 15:18
                                        book.txt
                                                                          Page 184/393
       File: Page: 821 drivers/tty/tty.c
14170
14171
           case TCFLOW:
14172
               r = sys_vircopy( m_ptr->PROC_NR, D, (vir_bytes) m_ptr->ADDRESS,
14173
                       SELF, D, (vir_bytes) &param.i, (vir_bytes) size);
14174
               if (r != OK) break;
14175
               switch (param.i) {
14176
                   case TCOOFF:
14177
                   case TCOON:
14178
                       tp->tty_inhibited = (param.i == TCOOFF);
14179
                       tp->tty_events = 1;
14180
                       break;
14181
                   case TCIOFF:
14182
                        (*tp->tty_echo)(tp, tp->tty_termios.c_cc[VSTOP]);
14183
                       break;
14184
                   case TCTON:
14185
                        (*tp->tty_echo)(tp, tp->tty_termios.c_cc[VSTART]);
14186
                       break;
14187
                   default:
14188
                       r = EINVAL;
14189
14190
               break;
14191
14192
           case TCSBRK:
14193
               if (tp->tty_break != NULL) (*tp->tty_break)(tp,0);
14194
               break;
14195
14196
           case TIOCGWINSZ:
14197
               r = sys_vircopy(SELF, D, (vir_bytes) &tp->tty_winsize,
14198
                        m_ptr->PROC_NR, D, (vir_bytes) m_ptr->ADDRESS,
14199
                        (vir bytes) size);
14200
               break;
14201
14202
           case TIOCSWINSZ:
14203
               r = sys_vircopy( m_ptr->PROC_NR, D, (vir_bytes) m_ptr->ADDRESS,
14204
                       SELF, D, (vir_bytes) &tp->tty_winsize, (vir_bytes) size);
14205
               /* SIGWINCH... */
14206
               break;
14207
14208
           case KIOCSMAP:
14209
               /* Load a new keymap (only /dev/console). */
               if (isconsole(tp)) r = kbd_loadmap(m_ptr);
14210
14211
               break;
14212
14213
           case TIOCSFON:
14214
               /* Load a font into an EGA or VGA card (hs@hck.hr) */
14215
               if (isconsole(tp)) r = con_loadfont(m_ptr);
14216
               break;
14217
14218
       /* These Posix functions are allowed to fail if _POSIX_JOB_CONTROL is
14219
       * not defined.
14220
14221
           case TIOCGPGRP:
           case TIOCSPGRP:
14222
14223
           default:
14224
               r = ENOTTY;
14225
14226
14227
         /* Send the reply. */
14228
         tty_reply(TASK_REPLY, m_ptr->m_source, m_ptr->PROC_NR, r);
14229
```

```
book.txt
Feb 25, 11 15:18
                                                         Page 185/393
     File: Page: 822 drivers/tty/tty.c
14232 *
                              do_open
14234 PRIVATE void do_open(tp, m_ptr)
14235 register tty_t *tp;
14236 message *m_ptr;
                               /* pointer to message sent to task */
14237
14238 /* A tty line has been opened. Make it the callers controlling tty if
14239
      * O_NOCTTY is *not* set and it is not the log device. 1 is returned if
      * the tty is made the controlling tty, otherwise OK or an error code.
14240
14241
14242
      int r = OK;
14243
       if (m ptr->TTY LINE == LOG MINOR) {
14244
14245
            /* The log device is a write-only diagnostics device. */
14246
            if (m_ptr->COUNT & R_BIT) r = EACCES;
14247
       } else {
14248
            if (!(m_ptr->COUNT & O_NOCTTY))
14249
                  tp->tty_pgrp = m_ptr->PROC_NR;
14250
14251
14252
            tp->tty_openct++;
14253
14254
       tty_reply(TASK_REPLY, m_ptr->m_source, m_ptr->PROC_NR, r);
14255
14258
                              do_close
14259
14260 PRIVATE void do close(tp, m ptr)
14261 register tty_t *tp;
14262 message *m_ptr;
                               /* pointer to message sent to task */
14263
     /* A tty line has been closed. Clean up the line if it is the last close. */
14264
14265
       if (m_ptr->TTY_LINE != LOG_MINOR && --tp->tty_openct == 0) {
14266
14267
            tp->tty_pgrp = 0;
14268
            tty icancel(tp);
14269
            (*tp->tty_ocancel)(tp, 0);
14270
            (*tp->tty_close)(tp, 0);
14271
            tp->tty termios = termios defaults;
14272
            tp->tty_winsize = winsize_defaults;
14273
            setattr(tp);
14274
14275
       tty_reply(TASK_REPLY, m_ptr->m_source, m_ptr->PROC_NR, OK);
14276
14279
                              do_cancel
     14281 PRIVATE void do_cancel(tp, m_ptr)
14282 register tty_t *tp;
14283 message *m_ptr;
                              /* pointer to message sent to task */
14284
     /* A signal has been sent to a process that is hanging trying to read or write.
14285
     * The pending read or write must be finished off immediately.
14286
14287
14288
14289
       int proc nr;
```

```
Feb 25, 11 15:18
                                        book.txt
                                                                         Page 186/393
       File: Page: 823 drivers/tty/tty.c
14290
         int mode;
14291
14292
         /* Check the parameters carefully, to avoid cancelling twice. */
14293
         proc_nr = m_ptr->PROC_NR;
14294
         mode = m_ptr->COUNT;
14295
         if ((mode & R_BIT) && tp->tty_inleft != 0 && proc_nr == tp->tty_inproc) {
14296
               /* Process was reading when killed. Clean up input. */
14297
               tty_icancel(tp);
14298
               tp->tty_inleft = tp->tty_incum = 0;
14299
14300
         if ((mode & W_BIT) && tp->tty_outleft != 0 && proc_nr == tp->tty_outproc) {
14301
               /* Process was writing when killed. Clean up output. */
14302
               (*tp->tty_ocancel)(tp, 0);
14303
               tp->tty_outleft = tp->tty_outcum = 0;
14304
14305
         if (tp->tty_ioreq != 0 && proc_nr == tp->tty_ioproc) {
14306
               /* Process was waiting for output to drain. */
14307
               tp->tty_ioreq = 0;
14308
14309
         tp->tty_events = 1;
14310
         tty_reply(TASK_REPLY, m_ptr->m_source, proc_nr, EINTR);
14311
14313 PUBLIC int select_try(struct tty *tp, int ops)
14314 {
14315
               int ready ops = 0;
14316
14317
               /* Special case. If line is hung up, no operations will block.
                * (and it can be seen as an exceptional condition.)
14318
14319
14320
               if (tp->tty_termios.c_ospeed == B0) {
14321
                       ready_ops |= ops;
14322
14323
               if (ops & SEL_RD) {
14324
14325
                       /* will i/o not block on read? */
14326
                       if (tp->tty_inleft > 0) {
                                                       /* EIO - no blocking */
14327
                               ready_ops |= SEL_RD;
14328
                       } else if (tp->tty_incount > 0) {
                               /* Is a regular read possible? tty_incount
14329
                                * says there is data. But a read will only succeed
14330
                                * in canonical mode if a newline has been seen.
14331
14332
14333
                               if (!(tp->tty_termios.c_lflag & ICANON) ||
14334
                                       tp->tty eotct > 0) {
14335
                                       ready_ops |= SEL_RD;
14336
14337
14338
14339
14340
               if (ops & SEL_WR) {
14341
                       if (tp->tty_outleft > 0) ready_ops |= SEL_WR;
                       else if ((*tp->tty_devwrite)(tp, 1)) ready_ops |= SEL_WR;
14342
14343
14344
14345
               return ready_ops;
14346
14348 PUBLIC int select_retry(struct tty *tp)
14349
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 187/393
      File: Page: 824 drivers/tty/tty.c
14350
              if (select_try(tp, tp->tty_select_ops))
14351
                     notify(tp->tty_select_proc);
14352
14353
14355 /*============*
14356
                                    handle events
14357
       14358 PUBLIC void handle events(tp)
                                    /* TTY to check for events. */
14359
      tty_t *tp;
14360
14361
      /* Handle any events pending on a TTY. These events are usually device
       * interrupts.
14362
14363
14364
       * Two kinds of events are prominent:
14365
              - a character has been received from the console or an RS232 line.
14366
              - an RS232 line has completed a write request (on behalf of a user).
14367
       * The interrupt handler may delay the interrupt message at its discretion
         to avoid swamping the TTY task. Messages may be overwritten when the
14368
14369
       * lines are fast or when there are races between different lines, input
14370
       * and output, because MINIX only provides single buffering for interrupt
14371
       * messages (in proc.c). This is handled by explicitly checking each line
       * for fresh input and completed output on each interrupt.
14372
14373
14374
        char *buf;
14375
        unsigned count;
14376
        int status;
14377
14378
14379
              tp->tty events = 0;
14380
14381
              /* Read input and perform input processing. */
14382
              (*tp->tty_devread)(tp, 0);
14383
14384
              /* Perform output processing and write output. */
14385
              (*tp->tty_devwrite)(tp, 0);
14386
14387
              /* Ioctl waiting for some event? */
14388
              if (tp->tty_ioreq != 0) dev_ioctl(tp);
14389
        } while (tp->tty_events);
14390
14391
         /* Transfer characters from the input queue to a waiting process. */
14392
        in_transfer(tp);
14393
14394
         /* Reply if enough bytes are available. */
14395
        if (tp->tty_incum >= tp->tty_min && tp->tty_inleft > 0) {
14396
              if (tp->tty_inrepcode == REVIVE) {
14397
                     notify(tp->tty_incaller);
14398
                      tp->tty_inrevived = 1;
14399
              } else {
14400
                     tty_reply(tp->tty_inrepcode, tp->tty_incaller,
14401
                             tp->tty_inproc, tp->tty_incum);
14402
                     tp->tty_inleft = tp->tty_incum = 0;
14403
14404
14405
        if (tp->tty_select_ops)
14406
              select retry(tp);
      \#if\ NR\ PTYS > 0
14407
14408
        if (ispty(tp))
14409
              select retry pty(tp);
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 188/393
      File: Page: 825 drivers/tty/tty.c
14410 #endif
14411
14413 /*==========*
14414
                                    in_transfer
14415
       *----*/
14416 PRIVATE void in transfer(tp)
14417 register tty_t *tp;
                                     /* pointer to terminal to read from */
14418
       ^{*} Transfer bytes from the input queue to a process reading from a terminal. */
14419
14420
14421
14422
        int count;
14423
        char buf[64], *bp;
14424
14425
        /* Force read to succeed if the line is hung up, looks like EOF to reader. */
14426
        if (tp->tty_termios.c_ospeed == B0) tp->tty_min = 0;
14427
14428
         /* Anything to do? */
14429
        if (tp->tty_inleft == 0 || tp->tty_eotct < tp->tty_min) return;
14430
14431
14432
        while (tp->tty_inleft > 0 && tp->tty_eotct > 0) {
14433
              ch = *tp->tty intail;
14434
14435
              if (!(ch & IN EOF)) {
14436
                      /* One character to be delivered to the user. */
14437
                      *bp = ch & IN_CHAR;
14438
                      tp->tty_inleft--;
14439
                      if (++bp == bufend(buf))
                             /* Temp buffer full, copy to user space. */
14440
14441
                             sys_vircopy(SELF, D, (vir_bytes) buf,
14442
                                    tp->tty_inproc, D, tp->tty_in_vir,
14443
                                     (vir_bytes) buflen(buf));
14444
                             tp->tty_in_vir += buflen(buf);
14445
                             tp->tty_incum += buflen(buf);
14446
                             bp = buf;
14447
14448
14449
14450
              /* Remove the character from the input queue. */
              if (++tp->tty intail == bufend(tp->tty inbuf))
14451
14452
                      tp->tty_intail = tp->tty_inbuf;
14453
              tp->tty_incount--;
14454
              if (ch & IN EOT) {
14455
                      tp->tty_eotct--;
14456
                      /* Don't read past a line break in canonical mode. */
14457
                      if (tp->tty_termios.c_lflag & ICANON) tp->tty_inleft = 0;
14458
14459
14460
14461
        if (bp > buf) {
              /* Leftover characters in the buffer. */
14462
14463
              count = bp - buf;
14464
              sys_vircopy(SELF, D, (vir_bytes) buf,
14465
                     tp->tty_inproc, D, tp->tty_in_vir, (vir_bytes) count);
14466
              tp->tty in vir += count;
14467
              tp->tty_incum += count;
14468
14469
```

```
Feb 25, 11 15:18
                                    book.txt
                                                                   Page 189/393
      File: Page: 826 drivers/tty/tty.c
14470
        /* Usually reply to the reader, possibly even if incum == 0 (EOF). */
14471
        if (tp->tty_inleft == 0) {
              if (tp->tty_inrepcode == REVIVE) {
14472
14473
                     notify(tp->tty_incaller);
14474
                     tp->tty_inrevived = 1;
14475
14476
                     tty_reply(tp->tty_inrepcode, tp->tty_incaller,
14477
                            tp->tty_inproc, tp->tty_incum);
14478
                     tp->tty_inleft = tp->tty_incum = 0;
14479
14480
14481
14483
      /*----*
14484
                                  in process
14485
      14486 PUBLIC int in_process(tp, buf, count)
14487 register tty_t *tp;
                                   /* terminal on which character has arrived */
14488 char *buf;
                                    /* buffer with input characters */
                                   /* number of input characters */
14489 int count;
14490
14491
      /* Characters have just been typed in. Process, save, and echo them. Return
      * the number of characters processed.
14492
14493
14494
14495
        int ch, sig, ct;
14496
        int timeset = FALSE;
14497
        static unsigned char csize_mask[] = { 0x1F, 0x3F, 0x7F, 0xFF };
14498
        for (ct = 0; ct < count; ct++) {
14499
              /* Take one character. */
14500
14501
              ch = *buf++ & BYTE;
14502
14503
              /* Strip to seven bits? */
14504
              if (tp->tty_termios.c_iflag & ISTRIP) ch &= 0x7F;
14505
14506
              /* Input extensions? */
14507
              if (tp->tty_termios.c_lflag & IEXTEN) {
14508
14509
                     /* Previous character was a character escape? */
14510
                     if (tp->tty escaped) {
                            tp->tty escaped = NOT ESCAPED;
14511
                            ch |= IN_ESC; /* protect character */
14512
14513
14514
14515
                     /* LNEXT (^V) to escape the next character? */
14516
                     if (ch == tp->tty_termios.c_cc[VLNEXT]) {
14517
                            tp->tty_escaped = ESCAPED;
14518
                            rawecho(tp, '^');
                            rawecho(tp, '\b');
14519
14520
                            continue;
                                          /* do not store the escape */
14521
14522
14523
                      /* REPRINT (^R) to reprint echoed characters? */
14524
                     if (ch == tp->tty_termios.c_cc[VREPRINT]) {
14525
                            reprint(tp);
14526
                            continue;
14527
14528
14529
```

```
Feb 25, 11 15:18
                                        book.txt
                                                                          Page 190/393
       File: Page: 827 drivers/tty/tty.c
14530
               /* _POSIX_VDISABLE is a normal character value, so better escape it. */
14531
               if (ch == _POSIX_VDISABLE) ch |= IN_ESC;
14532
14533
               /* Map CR to LF, ignore CR, or map LF to CR. */
14534
               if (ch == '\r')
14535
                       if (tp->tty_termios.c_iflag & IGNCR) continue;
14536
                        if (tp->tty_termios.c_iflag & ICRNL) ch = '\n';
14537
               } else
14538
               if (ch == '\n') {
14539
                       if (tp->tty_termios.c_iflag & INLCR) ch = '\r';
14540
14541
               /* Canonical mode? */
14542
14543
               if (tp->tty_termios.c_lflag & ICANON) {
14544
14545
                        /* Erase processing (rub out of last character). */
14546
                       if (ch == tp->tty_termios.c_cc[VERASE]) {
14547
                               (void) back_over(tp);
14548
                               if (!(tp->tty_termios.c_lflag & ECHOE)) {
                                        (void) tty_echo(tp, ch);
14549
14550
14551
                               continue;
14552
14553
14554
                       /* Kill processing (remove current line). */
14555
                       if (ch == tp->tty_termios.c_cc[VKILL]) {
14556
                               while (back_over(tp)) {}
14557
                               if (!(tp->tty_termios.c_lflag & ECHOE)) {
                                        (void) tty_echo(tp, ch);
14558
14559
                                       if (tp->tty termios.c lflag & ECHOK)
14560
                                               rawecho(tp, '√n');
14561
14562
                               continue;
14563
14564
14565
                        /* EOF (^D) means end-of-file, an invisible "line break". */
14566
                       if (ch == tp->tty_termios.c_cc[VEOF]) ch |= IN_EOT | IN_EOF;
14567
14568
                        /* The line may be returned to the user after an LF. */
14569
                       if (ch == '\n') ch |= IN_EOT;
14570
14571
                        /* Same thing with EOL, whatever it may be. */
                       if (ch == tp->tty_termios.c_cc[VEOL]) ch |= IN_EOT;
14572
14573
14574
14575
               /* Start/stop input control? */
14576
               if (tp->tty_termios.c_iflag & IXON) {
14577
14578
                        /* Output stops on STOP (^S). */
                       if (ch == tp->tty_termios.c_cc[VSTOP]) {
14579
14580
                               tp->tty_inhibited = STOPPED;
14581
                               tp->tty_events = 1;
14582
                               continue;
14583
14584
14585
                        /* Output restarts on START (^Q) or any character if IXANY. */
14586
                       if (tp->tty inhibited) {
                               if (ch == tp->tty_termios.c_cc[VSTART]
14587
                                                 (tp->tty_termios.c_iflag & IXANY)) {
14588
14589
                                        tp->tty inhibited = RUNNING;
```

```
book.txt
Feb 25, 11 15:18
                                                                   Page 191/393
      File: Page: 828 drivers/tty/tty.c
14590
                                    tp->tty events = 1;
14591
                                    if (ch == tp->tty_termios.c_cc[VSTART])
14592
                                           continue;
14593
14594
14595
14596
14597
              if (tp->tty_termios.c_lflag & ISIG) {
                     /* Check for INTR (^?) and QUIT (^\) characters. */
14598
14599
                     if (ch == tp->tty_termios.c_cc[VINTR]
14600
                                            | ch == tp->tty_termios.c_cc[VQUIT]) {
14601
                             sig = SIGINT;
                             if (ch == tp->tty_termios.c_cc[VQUIT]) sig = SIGQUIT;
14602
14603
                             sigchar(tp, sig);
14604
                             (void) tty_echo(tp, ch);
14605
                             continue;
14606
14607
14608
14609
              /* Is there space in the input buffer? */
14610
              if (tp->tty_incount == buflen(tp->tty_inbuf)) {
14611
                     /* No space; discard in canonical mode, keep in raw mode. */
14612
                     if (tp->tty_termios.c_lflag & ICANON) continue;
14613
                     break;
14614
14615
14616
              if (!(tp->tty termios.c lflag & ICANON)) {
14617
                     /* In raw mode all characters are "line breaks". */
14618
                     ch |= IN_EOT;
14619
                     /* Start an inter-byte timer? */
14620
14621
                     if (!timeset && tp->tty_termios.c_cc[VMIN] > 0
14622
                                   && tp->tty_termios.c_cc[VTIME] > 0) {
14623
                             settimer(tp, TRUE);
14624
                            timeset = TRUE;
14625
14626
14627
14628
              /* Perform the intricate function of echoing. */
14629
              if (tp->tty_termios.c_lflag & (ECHO|ECHONL)) ch = tty_echo(tp, ch);
14630
14631
              /* Save the character in the input queue. */
              *tp->tty_inhead++ = ch;
14632
14633
              if (tp->tty_inhead == bufend(tp->tty_inbuf))
                     tp->tty_inhead = tp->tty_inbuf;
14634
14635
              tp->tty_incount++;
14636
              if (ch & IN_EOT) tp->tty_eotct++;
14637
14638
              /* Try to finish input if the queue threatens to overflow. */
14639
              if (tp->tty_incount == buflen(tp->tty_inbuf)) in_transfer(tp);
14640
14641
        return ct;
14642
14644
      /*-----*
14645
                                    echo
14646
       14647 PRIVATE int tty_echo(tp, ch)
14648 register tty_t *tp;
                                    /* terminal on which to echo */
14649 register int ch;
                                    /* pointer to character to echo */
```

```
Feb 25, 11 15:18
                                      book.txt
                                                                      Page 192/393
       File: Page: 829 drivers/tty/tty.c
14650
14651
      /* Echo the character if echoing is on. Some control characters are echoed
       * with their normal effect, other control characters are echoed as "^X",
14652
        * normal characters are echoed normally. EOF (^D) is echoed, but immediately
14653
        * backspaced over. Return the character with the echoed length added to its
14654
14655
       * attributes.
14656
14657
        int len, rp;
14658
        ch &= ~IN_LEN;
14659
14660
         if (!(tp->tty_termios.c_lflag & ECHO)) {
14661
              if (ch == ('\n' | IN_EOT) && (tp->tty_termios.c_lflag
14662
                                             & (ICANON | ECHONL)) == (ICANON | ECHONL))
14663
                       (*tp->tty_echo)(tp,
14664
              return(ch);
14665
14666
14667
         /* "Reprint" tells if the echo output has been messed up by other output. */
14668
         rp = tp->tty_incount == 0 ? FALSE : tp->tty_reprint;
14669
14670
        if ((ch & IN_CHAR) < ' ')
14671
              switch (ch & (IN_ESC IN_EOF IN_EOT IN_CHAR)) {
                  case '\t':
14672
14673
                      len = 0;
14674
                      do {
14675
                              (*tp->tty_echo)(tp, '');
14676
14677
                       } while (len < TAB_SIZE && (tp->tty_position & TAB_MASK) != 0);
14678
                      break;
14679
                  case '\r'
                  case '\n' IN EOT:
14680
14681
                      (*tp->tty_echo)(tp, ch & IN_CHAR);
14682
                      len = 0;
14683
                      break;
14684
                  default:
14685
                      (*tp->tty_echo)(tp, '^');
14686
                       (*tp->tty_echo)(tp, '@' + (ch & IN_CHAR));
14687
                      len = 2;
14688
14689
         } else
14690
         if ((ch & IN_CHAR) == '\177') {
              /* A DEL prints as "^?".
14691
               (*tp->tty_echo)(tp, '^');
14692
14693
               (*tp->tty_echo)(tp, '?');
14694
              len = 2;
14695
        } else {
14696
                tp->tty_echo)(tp, ch & IN_CHAR);
14697
14698
14699
         if (ch & IN_EOF) while (len > 0) { (*tp->tty_echo)(tp, '\b'); len--; }
14700
14701
         tp->tty_reprint = rp;
        return(ch | (len << IN_LSHIFT));
14702
14703
14705
14706
                                    rawecho
14707
       14708 PRIVATE void rawecho(tp, ch)
14709 register tty t *tp;
```

```
book.txt
Feb 25, 11 15:18
                                                              Page 193/393
      File: Page: 830 drivers/tty/tty.c
14710 int ch;
14711
14712
     /* Echo without interpretation if ECHO is set. */
       int rp = tp->tty_reprint;
14713
14714
       if (tp->tty_termios.c_lflag & ECHO) (*tp->tty_echo)(tp, ch);
14715
       tp->tty_reprint = rp;
14716
14718 /*=============*
14719
                               back_over
14720
      *-----*
14721 PRIVATE int back over(tp)
14722 register tty_t *tp;
14723
14724 /* Backspace to previous character on screen and erase it. */
14725
       ul6 t *head;
14726
       int len;
14727
14728
       if (tp->tty_incount == 0) return(0); /* queue empty */
14729
       head = tp->tty_inhead;
14730
       if (head == tp->tty_inbuf) head = bufend(tp->tty_inbuf);
                                      /* can't erase "line breaks" */
14731
       if (*--head & IN_EOT) return(0);
                                              /* reprint if messed up */
14732
       if (tp->tty_reprint) reprint(tp);
       tp->tty inhead = head;
14733
       tp->tty_incount--;
14734
14735
       if (tp->tty_termios.c_lflag & ECHOE) {
             len = (*head & IN LEN) >> IN LSHIFT;
14736
14737
             while (len > 0) {
                   rawecho(tp, '\b');
14738
                   rawecho(tp, '');
14739
                   rawecho(tp, '\b');
14740
14741
                   len--;
14742
14743
14744
       return(1);
                                        /* one character erased */
14745
14747
     /*----*
14748
                               reprint
14749
       *=======*/
14750 PRIVATE void reprint(tp)
14751
     register tty t *tp;
                               /* pointer to tty struct */
14752
14753

angle * Restore what has been echoed to screen before if the user input has been
      * messed up by output, or if REPRINT (^R) is typed.
14754
14755
14756
       int count;
14757
       u16_t *head;
14758
14759
       tp->tty_reprint = FALSE;
14760
14761
        /* Find the last line break in the input. */
14762
       head = tp->tty_inhead;
14763
       count = tp->tty incount;
14764
        while (count > 0) {
             if (head == tp->tty_inbuf) head = bufend(tp->tty_inbuf);
14765
             if (head[-1] & IN EOT) break;
14766
14767
            head--;
14768
            count -- ;
14769
```

```
Feb 25, 11 15:18
                                      book.txt
                                                                      Page 194/393
      File: Page: 831 drivers/tty/tty.c
14770
        if (count == tp->tty incount) return;
                                                     /* no reason to reprint */
14771
14772
         /* Show REPRINT (^R) and move to a new line. */
14773
         (void) tty_echo(tp, tp->tty_termios.c_cc[VREPRINT] | IN_ESC);
14774
         rawecho(tp, '\r');
14775
        rawecho(tp, '\n');
14776
14777
         /* Reprint from the last break onwards. */
14778
14779
              if (head == bufend(tp->tty_inbuf)) head = tp->tty_inbuf;
14780
               *head = tty_echo(tp, *head);
14781
              head++;
14782
              count++;
14783
         } while (count < tp->tty_incount);
14784 }
14786 /*=======*
14787
                                    out_process
14788
       *-----*/
14789 PUBLIC void out_process(tp, bstart, bpos, bend, icount, ocount)
14790 tty_t *tp;
14791 char *bstart, *bpos, *bend;
                                     /* start/pos/end of circular buffer */
14792 int *icount;
                                     /* # input chars / input chars used */
14793 int *ocount;
                                     /* max output chars / output chars used */
14794
14795 \not Perform output processing on a circular buffer. *icount is the number of
       * bytes to process, and the number of bytes actually processed on return.
14796
       * *ocount is the space available on input and the space used on output. * (Naturally *icount < *ocount.) The column position is updated modulo
14797
14798
       * the TAB size, because we really only need it for tabs.
14799
14800
14801
14802
        int tablen;
14803
        int ict = *icount;
        int oct = *ocount;
14804
14805
        int pos = tp->tty_position;
14806
14807
         while (ict > 0) {
              switch (*bpos) {
14808
14809
              case '\7':
14810
                      break;
              case '\b':
14811
14812
                      pos--;
14813
                      break;
              case '\r':
14814
14815
                      pos = 0;
14816
                      break;
              case '\n':
14817
14818
                      if ((tp->tty_termios.c_oflag & (OPOST|ONLCR))
14819
                                                             == (OPOST | ONLCR)) {
14820
                              /* Map LF to CR+LF if there is space. Note that the
14821
                               * next character in the buffer is overwritten, so
                               * we stop at this point.
14822
14823
14824
                              if (oct >= 2) {
 *bpos = '\r';
14825
                                      if (++bpos == bend) bpos = bstart;
14826
                                      *bpos = '\n';
14827
                                     pos = 0;
14828
14829
                                      ict--;
```

```
Feb 25, 11 15:18
                                    book.txt
                                                                  Page 195/393
      File: Page: 832 drivers/tty/tty.c
14830
                                    oct. -= 2;
14831
14832
                            goto out_done; /* no space or buffer got changed */
14833
14834
                     break;
14835
              case '\t':
                     /* Best guess for the tab length. */
14836
14837
                     tablen = TAB_SIZE - (pos & TAB_MASK);
14838
                     if ((tp->tty_termios.c_oflag & (OPOST|XTABS))
14839
                                                          == (OPOST | XTABS)) {
14840
14841
                             /* Tabs must be expanded. */
14842
                            if (oct >= tablen) {
14843
                                   pos += tablen;
14844
                                    ict--;
14845
                                    oct -= tablen;
14846
                                    do {
14847
                                           *bpos = ' ';
14848
                                           if (++bpos == bend) bpos = bstart;
                                    } while (--tablen != 0);
14849
14850
14851
                            goto out_done;
14852
14853
                     /* Tabs are output directly. */
14854
                     pos += tablen;
14855
                     break;
14856
              default:
14857
                     /* Assume any other character prints as one character. */
14858
                     pos++;
14859
14860
              if (++bpos == bend) bpos = bstart;
14861
              ict--;
14862
             oct--;
14863
14864
      out_done:
14865
        tp->tty_position = pos & TAB_MASK;
14866
14867
        *icount -= ict;
                            /* [io]ct are the number of chars not used */
14868
        *ocount -= oct;
                            /* *[io]count are the number of chars that are used */
14869
      14872
                                   dev ioctl
14873
       14874 PRIVATE void dev ioctl(tp)
14875
      tty t *tp;
14876
14877 /* The ioctl's TCSETSW, TCSETSF and TCDRAIN wait for output to finish to make
14878
       * sure that an attribute change doesn't affect the processing of current
14879
       * output. Once output finishes the ioctl is executed as in do_ioctl().
14880
14881
        int result;
14882
14883
        if (tp->tty_outleft > 0) return;
                                                  /* output not finished */
14884
14885
        if (tp->tty_ioreq != TCDRAIN) {
              if (tp->tty_ioreq == TCSETSF) tty_icancel(tp);
14886
14887
              result = sys_vircopy(tp->tty_ioproc, D, tp->tty_iovir,
14888
                            SELF, D, (vir_bytes) &tp->tty_termios,
14889
                            (vir bytes) sizeof(tp->tty termios));
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                     Page 196/393
       File: Page: 833 drivers/tty/tty.c
14890
              setattr(tp);
14891
14892
        tp->tty_ioreq = 0;
14893
        tty_reply(REVIVE, tp->tty_iocaller, tp->tty_ioproc, result);
14894
14896
      /*_____*
14897
                                     setattr
14898
       *-----*
      PRIVATE void setattr(tp)
14899
14900
       tty t *tp;
14901
14902
        * Apply the new line attributes (raw/canonical, line speed, etc.) */
14903
        u16_t *inp;
14904
        int count;
14905
14906
        if (!(tp->tty_termios.c_lflag & ICANON)) {
              /* Raw mode; put a "line break" on all characters in the input queue.
14907
14908
               ^{\star} It is undefined what happens to the input queue when ICANON is
14909
               * switched off, a process should use TCSAFLUSH to flush the queue.
14910
               * Keeping the queue to preserve typeahead is the Right Thing, however
14911
               * when a process does use TCSANOW to switch to raw mode.
14912
14913
              count = tp->tty_eotct = tp->tty_incount;
              inp = tp->tty_intail;
14914
14915
              while (count > 0) {
                      *inp |= IN EOT;
14916
14917
                      if (++inp == bufend(tp->tty_inbuf)) inp = tp->tty_inbuf;
14918
                      --count;
14919
14920
14921
14922
        /* Inspect MIN and TIME. */
14923
        settimer(tp, FALSE);
14924
        if (tp->tty_termios.c_lflag & ICANON)
14925
              /* No MIN & TIME in canonical mode. */
14926
              tp->tty_min = 1;
14927
        } else
14928
              /* In raw mode MIN is the number of chars wanted, and TIME how long
               {}^{\star} to wait for them. With interesting exceptions if either is zero.
14929
14930
14931
              tp->tty min = tp->tty termios.c cc[VMIN];
14932
              if (tp->tty_min == 0 && tp->tty_termios.c_cc[VTIME] > 0)
14933
                     tp->tty_min = 1;
14934
14935
14936
        if (!(tp->tty_termios.c_iflag & IXON)) {
14937
              /* No start/stop output control, so don't leave output inhibited. */
14938
              tp->tty_inhibited = RUNNING;
14939
              tp->tty_events = 1;
14940
14941
14942
        /* Setting the output speed to zero hangs up the phone. */
14943
        if (tp->tty termios.c ospeed == B0) sigchar(tp, SIGHUP);
14944
14945
         /* Set new line speed, character size, etc at the device level. */
        (*tp->tty_ioctl)(tp, 0);
14946
14947
```

```
book.txt
Feb 25, 11 15:18
                                                         Page 197/393
     File: Page: 834 drivers/tty/tty.c
14949
     14950 *
                       tty_reply
     *-----*/
14952 PUBLIC void tty_reply(code, replyee, proc_nr, status)
                              /* TASK_REPLY or REVIVE */
14953 int code;
14954 int replyee;
                              /* destination address for the reply */
14955 int proc_nr;
                              /* to whom should the reply go? */
14956 int status;
                              /* reply code */
14957
14958
     /* Send a reply to a process that wanted to read or write data. */
14959
       message tty mess;
14960
14961
       tty_mess.m_type = code;
tty_mess.REP_PROC_NR = proc_nr;
14962
14963
       tty mess.REP STATUS = status;
14964
14965
       if ((status = send(replyee, &tty_mess)) != OK) {
14966
           panic("TTY", "tty_reply failed, status\n", status);
14967
14968
14971 *
                              sigchar
     14973 PUBLIC void sigchar(tp, sig)
14974 register tty_t *tp;
                              /* SIGINT, SIGOUIT, SIGKILL or SIGHUP */
14975 int sig;
14976
14977 /* Process a SIGINT, SIGQUIT or SIGKILL char from the keyboard or SIGHUP from
     * a tty close, "stty 0", or a real RS-232 hangup. MM will send the signal to
14979
      * the process group (INT, QUIT), all processes (KILL), or the session leader
14980
      * (HUP).
14981
      * /
14982
      int status;
14983
14984
       if (tp->tty_pgrp != 0)
          if (OK != (status = sys_kill(tp->tty_pgrp, sig)))
14985
14986
            panic("TTY", "Error, call to sys_kill failed", status);
14987
14988
       if (!(tp->tty_termios.c_lflag & NOFLSH)) {
            tp->tty_incount = tp->tty_eotct = 0;
tp->tty_intail = tp->tty_inhead;
                                           /* kill earlier input */
14989
14990
14991
            (*tp->tty_ocancel)(tp, 0);
                                                  /* kill all output */
14992
            tp->tty_inhibited = RUNNING;
14993
            tp->tty events = 1;
14994
14995
14998
                            tty_icancel
     15000 PRIVATE void tty_icancel(tp)
15001
     register tty_t *tp;
15002
15003
     /* Discard all pending input, tty buffer or device. */
15004
15005
       tp->tty incount = tp->tty eotct = 0;
15006
       tp->tty_intail = tp->tty_inhead;
15007
       (*tp->tty_icancel)(tp, 0);
15008 }
```

```
book.txt
Feb 25, 11 15:18
                                                        Page 198/393
     File: Page: 835 drivers/tty/tty.c
15011 *
                             tty_init
15012
      *-----*/
     PRIVATE void tty_init()
15013
15014
     /* Initialize tty structure and call device initialization routines. */
15015
15016
15017
       register tty_t *tp;
15018
       int s;
15019
       struct sigaction sigact;
15020
15021
       /* Initialize the terminal lines. */
       for (tp = FIRST_TTY, s=0; tp < END_TTY; tp++,s++) {
15022
15023
15024
           tp->tty index = s;
15025
15026
           tmr_inittimer(&tp->tty_tmr);
15027
15028
           tp->tty_intail = tp->tty_inhead = tp->tty_inbuf;
15029
           tp->tty_min = 1;
15030
           tp->tty_termios = termios_defaults;
15031
           tp->tty_icancel = tp->tty_ocancel = tp->tty_ioctl = tp->tty_close =
15032
                                                       tty devnop;
15033
           if (tp < tty_addr(NR_CONS)) {
15034
                 scr init(tp);
15035
                  tp->tty_minor = CONS_MINOR + s;
15036
            } else
15037
           if (tp < tty_addr(NR_CONS+NR_RS_LINES)) {
15038
                  rs init(tp);
                  tp->tty_minor = RS232_MINOR + s-NR_CONS;
15039
15040
           } else {
15041
                  pty_init(tp);
15042
                  tp->tty_minor = s - (NR_CONS+NR_RS_LINES) + TTYPX_MINOR;
15043
15044
15045 }
15047 /*----*
15048
                            tty_timed_out
15049
      15050 PRIVATE void tty timed out(timer t *tp)
15051
15052
     /* This timer has expired. Set the events flag, to force processing. */
15053
      tty t *tty ptr;
15054
       tty_ptr = &tty_table[tmr_arg(tp)->ta_int];
15055
       tty_ptr->tty_min = 0;
                                   /* force read to succeed */
       tty_ptr->tty_events = 1;
15056
15057 }
     15060
                             expire timers
     *-----*
15061
15062 PRIVATE void expire timers(void)
15063
15064
     /* A synchronous alarm message was received. Check if there are any expired
      * timers. Possibly set the event flag and reschedule another alarm.
15065
15066
                                    /* current time */
15067
      clock_t now;
15068
      int s;
```

```
book.txt
Feb 25, 11 15:18
                                                                 Page 199/393
      File: Page: 836 drivers/tty/tty.c
15069
15070
        /* Get the current time to compare the timers against. */
15071
        if ((s=getuptime(&now)) != OK)
15072
             panic("TTY", "Couldn't get uptime from clock.", s);
15073
15074
        /* Scan the queue of timers for expired timers. This dispatch the watchdog
15075
         * functions of expired timers. Possibly a new alarm call must be scheduled.
15076
15077
        tmrs exptimers(&tty timers, now, NULL);
15078
        if (tty_timers == NULL) tty_next_timeout = TMR_NEVER;
15079
                                                   /* set new sync alarm */
             tty_next_timeout = tty_timers->tmr_exp_time;
15080
             if ((s=sys_setalarm(tty_next_timeout, 1)) != OK)
15081
                    panic("TTY", "Couldn't set synchronous alarm.", s);
15082
15083
15084 }
15087
                                 settimer
15088
     *-----*/
15089 PRIVATE void settimer(tty_ptr, enable)
15090 tty_t *tty_ptr;
                           /* line to set or unset a timer on */
15091 int enable;
                                  /* set timer if true, otherwise unset */
15092 {
15093
        clock t. now;
                                          /* current time */
15094
        clock_t exp_time;
15095
15096
        /* Get the current time to calculate the timeout time. */
15097
        if ((s=getuptime(&now)) != OK)
15098
15099
             panic("TTY", "Couldn't get uptime from clock.", s);
15100
        if (enable) {
15101
             exp_time = now + tty_ptr->tty_termios.c_cc[VTIME] * (HZ/10);
             /* Set a new timer for enabling the TTY events flags. */
15102
15103
             tmrs_settimer(&tty_timers, &tty_ptr->tty_tmr,
15104
                    exp_time, tty_timed_out, NULL);
15105
        } else {
             / Remove the timer from the active and expired lists. */
15106
15107
             tmrs_clrtimer(&tty_timers, &tty_ptr->tty_tmr, NULL);
15108
15109
        /* Now check if a new alarm must be scheduled. This happens when the front
15110
         * of the timers queue was disabled or reinserted at another position, or
15111
15112
         * when a new timer was added to the front.
15113
15114
        if (tty_timers == NULL) tty_next_timeout = TMR_NEVER;
15115
        else if (tty_timers->tmr_exp_time != tty_next_timeout) {
             tty_next_timeout = tty_timers->tmr_exp_time;
15116
15117
             if ((s=sys_setalarm(tty_next_timeout, 1)) != OK)
15118
                    panic("TTY", "Couldn't set synchronous alarm.", s);
15119
15120 }
15122 /*----*
15123 *
                                 tty_devnop
15124
15125 PUBLIC int tty_devnop(tp, try)
15126 tty_t *tp;
15127 int try;
15128
```

```
Feb 25, 11 15:18
                                  book.txt
                                                              Page 200/393
      File: Page: 837 drivers/tty/tty.c
15129
        /* Some functions need not be implemented at the device level. */
15130
15132 /*========*
15133 *
                                 do_select
15135 PRIVATE void do_select(tp, m_ptr)
                                 /* pointer to tty struct */
15136 register tty_t *tp;
15137 register message *m ptr;
                                 /* pointer to message sent to the task */
15138
15139
             int ops, ready ops = 0, watch;
15140
15141
             ops = m_ptr->PROC_NR & (SEL_RD|SEL_WR|SEL_ERR);
             watch = (m_ptr->PROC_NR & SEL_NOTIFY) ? 1 : 0;
15142
15143
15144
             ready ops = select try(tp, ops);
15145
15146
             if (!ready_ops && ops && watch) {
15147
                   tp->tty_select_ops |= ops;
15148
                   tp->tty_select_proc = m_ptr->m_source;
15149
15150
15151
             tty_reply(TASK_REPLY, m_ptr->m_source, m_ptr->PROC_NR, ready_ops);
15152
15153
             return;
15154 }
                               drivers/tty/keyboard.c
15200 /* Keyboard driver for PC's and AT's.
15201
     * Changes:
15202
15203
      * Jul 13, 2004 processes can observe function keys (Jorrit N. Herder)
15204
          Jun 15, 2004 removed wreboot(), except panic dumps (Jorrit N. Herder)
      * Feb 04, 1994 loadable keymaps (Marcus Hampel)
15205
15206
15207
15208 #include "../drivers.h"
15209 #include <sys/time.h>
15210 #include <sys/select.h>
15211 #include <termios.h>
15212 #include <signal.h>
15213 #include <unistd.h>
15214 #include <minix/callnr.h>
15215 #include <minix/com.h>
15216 #include <minix/keymap.h>
15217 #include "tty.h"
15218 #include "keymaps/us-std.src"
15219 #include "../../kernel/const.h"
15220 #include "../../kernel/config.h"
15221 #include "../../kernel/type.h"
15222 #include "../../kernel/proc.h"
15223
15224 int irg hook id = -1;
```

```
Feb 25, 11 15:18
                                       book.txt
                                                                        Page 201/393
       File: Page: 838 drivers/tty/keyboard.c
15225
15226
      /* Standard and AT keyboard. (PS/2 MCA implies AT throughout.) */
15227 #define KEYBD
                              0x60 /* I/O port for keyboard data */
15228
15229 /* AT keyboard. */
15230 #define KB_COMMAND
                                    /* I/O port for commands on AT */
                              0x0-
0x64
15231 #define KB_STATUS
                                     /* I/O port for status on AT */
                                      /* keyboard ack response */
15232 #define KB_ACK
15233 #define KB OUT FULL
                                    /* status bit set when keypress char pending */
                              0 \times 01
15234 #define KB_IN_FULL
                                    /* status bit set when not ready to receive */
/* command to keyboard to set LEDs */
                              0 \times 02
15235 #define LED CODE
                              0xED
15236 #define MAX_KB_ACK_RETRIES 0x1000
                                            /* max #times to wait for kb ack */
                                              /* max #times to loop while kb busy */
15237 #define MAX_KB_BUSY_RETRIES 0x1000
15238 #define KBIT
                              0x80 /* bit used to ack characters to keyboard */
15239
15240 /* Miscellaneous. */
15241 #define ESC_SCAN
                              0 \times 01
                                      /* reboot key when panicking */
                                      /* to recognize numeric slash */
15242 #define SLASH_SCAN
                               0x35
15243 #define RSHIFT_SCAN
                                      /* to distinguish left and right shift */
                               0 \times 36
                                      /* first key on the numeric keypad */
15244 #define HOME_SCAN
                               0x47
15245 #define INS_SCAN
                               0x52
                                      /* INS for use in CTRL-ALT-INS reboot */
15246 #define DEL_SCAN
                              0x53
                                      /* DEL for use in CTRL-ALT-DEL reboot */
15247
15248 #define CONSOLE
                                      /* line number for console */
15249 #define KB_IN_BYTES
                                32
                                      /* size of keyboard input buffer */
15250 PRIVATE char ibuf[KB IN BYTES]; /* input buffer */
15251 PRIVATE char *ihead = ibuf; /* next free spot in input buffer */
15252 PRIVATE char *itail = ibuf;
                                      /* scan code to return to TTY */
                                      /* # codes in buffer */
15253 PRIVATE int icount;
15254
15255 PRIVATE int esc;
                                      /* escape scan code detected? */
15256 PRIVATE int alt_1;
                                      /* left alt key state */
15257 PRIVATE int alt_r;
                                      /* right alt key state */
15258 PRIVATE int alt;
                                      /* either alt key */
                                      /* left control key state */
15259 PRIVATE int ctrl_l;
15260 PRIVATE int ctrl_r;
                                      /* right control key state */
                                      /* either control key */
15261 PRIVATE int ctrl;
15262 PRIVATE int shift_1;
                                      /* left shift key state */
                                      /* right shift key state */
15263 PRIVATE int shift r;
15264 PRIVATE int shift;
                                      /* either shift key */
                                      /* num lock key depressed */
15265 PRIVATE int num down;
                                      /* caps lock key depressed */
15266 PRIVATE int caps down;
15267 PRIVATE int scroll_down;
                                      /* scroll lock key depressed */
15268 PRIVATE int locks[NR_CONS];
                                      /* per console lock keys state */
15269
15270 /* Lock key active bits. Chosen to be equal to the keyboard LED bits. */
15271 #define SCROLL_LOCK
                              0 \times 01
15272 #define NUM_LOCK
                               0 \times 0.2
15273 #define CAPS_LOCK
                               0 \times 0.4
15274
15275 PRIVATE char numpad_map[] =
15276
                       {'H', 'Y', 'A', 'B', 'D', 'C', 'V', 'U', 'G', 'S', 'T', '@'};
15277
15278 /* Variables and definition for observed function keys. */
15279 typedef struct observer { int proc_nr; int events; } obs_t;
15280 PRIVATE obs_t fkey_obs[12]; /* observers for F1-F12 */
15281 PRIVATE obs_t sfkey_obs[12]; /* observers for SHIFT F1-F12 */
15282
      FORWARD _PROTOTYPE( int kb_ack, (void)
15283
15284 FORWARD PROTOTYPE( int kb wait, (void)
```

```
book.txt
Feb 25, 11 15:18
                                                          Page 202/393
     File: Page: 839 drivers/tty/keyboard.c
15285 FORWARD _PROTOTYPE( int func_key, (int scode)
15286 FORWARD _PROTOTYPE( int scan_keyboard, (void)
                                                               );
15287 FORWARD PROTOTYPE (unsigned make_break, (int scode)
                                                               );
15288 FORWARD _PROTOTYPE( void set_leds, (void)
                                                               );
15289 FORWARD _PROTOTYPE( void show_key_mappings, (void)
                                                               );
15290 FORWARD PROTOTYPE( int kb_read, (struct tty *tp, int try)
                                                               );
15291 FORWARD _PROTOTYPE( unsigned map_key, (int scode)
                                                               );
15292
15293 /*-----*
15294
                             map_key0
     *-----*/
15295
15296 /* Map a scan code to an ASCII code ignoring modifiers. */
     #define map_key0(scode) \
15297
15298
           ((unsigned) keymap[(scode) * MAP_COLS])
15299
15300 /*========*
15301 *
                              map kev
     *-----*/
15302
15303 PRIVATE unsigned map_key(scode)
15304
     int scode;
15305
15306
     /* Map a scan code to an ASCII code. */
15307
15308
       int caps, column, lk;
15309
       u16_t *keyrow;
15310
15311
       if (scode == SLASH SCAN && esc) return '/'; /* don't map numeric slash */
15312
15313
       keyrow = &keymap[scode * MAP_COLS];
15314
15315
       caps = shift;
15316
       lk = locks[ccurrent];
15317
       if ((1k & NUM_LOCK) && HOME_SCAN <= scode && scode <= DEL_SCAN) caps = !caps;
15318
       if ((lk & CAPS_LOCK) && (keyrow[0] & HASCAPS)) caps = !caps;
15319
15320
15321
            column = 2;
15322
            if (ctrl | | alt_r) column = 3; /* Ctrl + Alt == AltGr */
15323
            if (caps) column = 4;
15324
       } else {
15325
            column = 0;
            if (caps) column = 1;
15326
            if (ctrl) column = 5;
15327
15328
       return keyrow[column] & ~HASCAPS;
15329
15330
15332 /*----*
15333
                             kbd_interrupt
15334
     *========*/
15335 PUBLIC void kbd_interrupt(m_ptr)
15336
     message *m_ptr;
15337
15338 /* A keyboard interrupt has occurred. Process it. */
15339
       int scode;
15340
       static timer t timer;
                               /* timer must be static! */
15341
15342
       /* Fetch the character from the keyboard hardware and acknowledge it. */
15343
       scode = scan_keyboard();
15344
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                     Page 203/393
      File: Page: 840 drivers/tty/keyboard.c
15345
        /* Store the scancode in memory so the task can get at it later. */
15346
        if (icount < KB_IN_BYTES) {</pre>
              *ihead++ = scode;
15347
15348
              if (ihead == ibuf + KB_IN_BYTES) ihead = ibuf;
15349
              icount++;
15350
              tty_table[ccurrent].tty_events = 1;
              if (tty_table[ccurrent].tty_select_ops & SEL_RD) {
15351
15352
                      select_retry(&tty_table[ccurrent]);
15353
15354
15355
15357
      15358
                                    kb_read
15359
15360 PRIVATE int kb_read(tp, try)
15361 tty_t *tp;
15362 int try;
15363
15364 /* Process characters from the circular keyboard buffer. */
15365
15366
        int scode;
15367
        unsigned ch;
15368
15369
        tp = &tty_table[ccurrent];
                                          /* always use the current console */
15370
15371
        if (try)
15372
              if (icount > 0) return 1;
15373
              return 0;
15374
15375
15376
        while (icount > 0) {
15377
              scode = *itail++;
                                                    /* take one key scan code */
15378
              if (itail == ibuf + KB IN BYTES) itail = ibuf;
15379
              icount --;
15380
15381
              /* Function keys are being used for debug dumps. */
15382
              if (func_key(scode)) continue;
15383
15384
              /* Perform make/break processing. */
15385
              ch = make break(scode);
15386
15387
              if (ch <= 0xFF)
15388
                      /* A normal character. */
15389
                      buf[0] = ch;
15390
                      (void) in_process(tp, buf, 1);
15391
              } else
15392
              if (HOME <= ch && ch <= INSRT) {
15393
                      /* An ASCII escape sequence generated by the numeric pad. */
15394
                      buf[0] = ESC;
15395
                      buf[1] = '[';
15396
                      buf[2] = numpad_map[ch - HOME];
15397
                      (void) in_process(tp, buf, 3);
15398
               } else
15399
              if (ch == ALEFT) {
                      /* Choose lower numbered console as current console. */
15400
15401
                      select console(ccurrent - 1);
15402
                      set_leds();
15403
               } else
15404
              if (ch == ARIGHT) {
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 204/393
      File: Page: 841 drivers/tty/keyboard.c
15405
                     /* Choose higher numbered console as current console. */
15406
                     select_console(ccurrent + 1);
15407
                     set_leds();
15408
              } else
15409
              if (AF1 <= ch && ch <= AF12) {
15410
                     /* Alt-F1 is console, Alt-F2 is ttyc1, etc. */
15411
                     select_console(ch - AF1);
15412
                     set_leds();
15413
              } else
              if (CF1 <= ch && ch <= CF12) {
15414
15415
                  switch(ch) {
15416
                     case CF1: show key mappings(); break;
                     case CF3: toggle_scroll(); break; /* hardware <-> software */
15417
                     case CF7: sigchar(&tty_table[CONSOLE], SIGQUIT); break;
15418
15419
                     case CF8: sigchar(&tty_table[CONSOLE], SIGINT); break;
15420
                     case CF9: sigchar(&tty_table[CONSOLE], SIGKILL); break;
15421
15422
15423
15424
15425
        return 1;
15426
15428
      /*-----*
15429
                                   make break
15430
       *============*/
15431 PRIVATE unsigned make_break(scode)
15432
      int scode;
                                    /* scan code of key just struck or released */
15433
15434 /* This routine can handle keyboards that interrupt only on key depression,
15435
      * as well as keyboards that interrupt on key depression and key release.
15436
       * For efficiency, the interrupt routine filters out most key releases.
15437
15438
        int ch, make, escape;
15439
        static int CAD_count = 0;
15440
15441
        /* Check for CTRL-ALT-DEL, and if found, halt the computer. This would
         * be better done in keyboard() in case TTY is hung, except control and
15442
15443
         * alt are set in the high level code.
15444
15445
        if (ctrl && alt && (scode == DEL SCAN | | scode == INS SCAN))
15446
15447
              if (++CAD_count == 3) sys_abort(RBT_HALT);
15448
              sys_kill(INIT_PROC_NR, SIGABRT);
15449
              return -1;
15450
15451
15452
        /* High-order bit set on key release. */
15453
        make = (scode & KEY_RELEASE) == 0;
                                                   /* true if pressed */
15454
15455
        ch = map_key(scode &= ASCII_MASK);
                                                   /* map to ASCII */
15456
15457
        escape = esc;
                             /* Key is escaped? (true if added since the XT) */
15458
        esc = 0;
15459
        switch (ch) {
15460
15461
              case CTRL:
                                     /* Left or right control key */
                      *(escape ? &ctrl_r : &ctrl_l) = make;
15462
15463
                     ctrl = ctrl l | ctrl r;
15464
                     break;
```

```
book.txt
Feb 25, 11 15:18
                                                                     Page 205/393
      File: Page: 842 drivers/tty/keyboard.c
15465
              case SHIFT:
                                     /* Left or right shift key */
15466
                      *(scode == RSHIFT_SCAN ? &shift_r : &shift_l) = make;
15467
                      shift = shift_l | shift_r;
15468
                     break;
                                     /* Left or right alt key */
15469
              case ALT:
15470
                      *(escape ? &alt_r : &alt_l) = make;
15471
                      alt = alt_l | alt_r;
15472
                     break;
15473
              case CALOCK:
                                      /* Caps lock - toggle on 0 -> 1 transition */
                      if (caps_down < make) {
    locks[ccurrent] ^= CAPS LOCK;
15474
15475
15476
                             set leds();
15477
15478
                      caps_down = make;
15479
                      break;
15480
              case NLOCK:
                                     /* Num lock */
15481
                      if (num_down < make) {
                             locks[ccurrent] ^= NUM_LOCK;
15482
15483
                             set_leds();
15484
15485
                     num down = make;
15486
                     break;
                                     /* Scroll lock */
15487
              case SLOCK:
                     if (scroll_down < make) {
     locks[ccurrent] ^= SCROLL_LOCK;</pre>
15488
15489
15490
                             set leds();
15491
15492
                      scroll down = make;
15493
                      break;
              case EXTKEY:
                                      /* Escape keycode */
15494
                                          /* Next key is escaped */
15495
                      esc = 1;
15496
                      return(-1);
15497
                                     /* A normal key */
15498
                     if (make) return(ch);
15499
15500
15501
        /* Key release, or a shift type key. */
15502
        return(-1);
15503
15505
15506
15507
       *======*/
15508
      PRIVATE void set_leds()
15509
15510
       /* Set the LEDs on the caps, num, and scroll lock keys */
15511
        if (! machine.pc_at) return; /* PC/XT doesn't have LEDs */
15512
15513
15514
                                     /* wait for buffer empty */
15515
        if ((s=sys_outb(KEYBD, LED_CODE)) != OK)
15516
            printf("Warning, sys_outb couldn't prepare for LED values: %d\n", s);
15517
                                     /* prepare keyboard to accept LED values */
                                     /* wait for ack response */
15518
        kb ack();
15519
15520
                                     /* wait for buffer empty */
15521
        if ((s=sys outb(KEYBD, locks[ccurrent])) != OK)
            printf("Warning, sys_outb couldn't give LED values: %d\n", s);
15522
                                     /* give keyboard LED values */
15523
15524
                                     /* wait for ack response */
```

```
book.txt
Feb 25, 11 15:18
                                                Page 206/393
    File: Page: 843 drivers/tty/keyboard.c
15525 }
    /*_____*
15528
                         kb wait
    15529
15530 PRIVATE int kb wait()
15531
    /* Wait until the controller is ready; return zero if this times out. */
15532
15533
15534
      int retries, status, temp;
15535
      int s;
15536
      15537
15538
      do {
15539
        s = sys inb(KB STATUS, &status);
15540
        if (status & KB_OUT_FULL) {
15541
           s = sys_inb(KEYBD, &temp); /* discard value */
15542
15543
        if (! (status & (KB_IN_FULL | KB_OUT_FULL)) )
                        /* wait until ready */
15544
          break;
      } while (--retries != 0);
15545
                               /* continue unless timeout */
      return(retries);
15546
                        /* zero on timeout, positive if ready */
15547
15550
                        kb ack
15551
     15552
    PRIVATE int kb ack()
15553
15554
    /* Wait until kbd acknowledges last command; return zero if this times out. */
15555
15556
      int retries, s;
15557
      u8_t u8val;
15558
15559
      retries = MAX_KB_ACK_RETRIES + 1;
15560
      do {
        s = sys_inb(KEYBD, &u8val);
15561
15562
        if (u8val == KB_ACK)
15563
          break;
                          /* wait for ack */
      } while(--retries != 0);
15564
                         /* continue unless timeout */
15565
                          /* nonzero if ack received */
15566
      return(retries);
15567 }
15570
                        kb init
15571 *-----*/
15572 PUBLIC void kb_init(tp)
15573 tty_t *tp;
15574 {
15575 /* Initialize the keyboard driver. */
15576
15577
      tp->tty_devread = kb_read; /* input function */
15578 }
kb init once
     *-----*/
15582
15583 PUBLIC void kb_init_once(void)
15584
```

```
Feb 25, 11 15:18
                                  book.txt
                                                                Page 207/393
      File: Page: 844 drivers/tty/keyboard.c
15585
        int i;
15586
15587
                                  /* turn off numlock led */
15588
        scan_keyboard();
                                  /* discard leftover keystroke */
15589
15590
            /* Clear the function key observers array. Also see func_key(). */
15591
           for (i=0; i<12; i++) {
               fkey_obs[i].proc_nr = NONE; /* F1-F12 observers */
15592
               fkey obs[i].events = 0;
                                        /* F1-F12 observers */
15593
               sfkey_obs[i].proc_nr = NONE; /* Shift F1-F12 observers */
15594
                                        /* Shift F1-F12 observers */
15595
               sfkey obs[i].events = 0;
15596
15597
           /* Set interrupt handler and enable keyboard IRQ. */
15598
15599
           irg hook id = KEYBOARD IRO; /* id to be returned on interrupt */
15600
           if ((i=sys_irqsetpolicy(KEYBOARD_IRQ, IRQ_REENABLE, &irq_hook_id)) != OK)
15601
               panic("TTY", "Couldn't set keyboard IRQ policy", i);
            if ((i=sys_irgenable(&irg_hook_id)) != OK)
15602
15603
           panic("TTY", "Couldn't enable keyboard IRQs", i);
kbd_irq_set |= (1 << KEYBOARD_IRQ);</pre>
15604
15605
15608
                                 kbd loadmap
15609
       15610
      PUBLIC int kbd_loadmap(m)
15611 message *m;
15612
      /* Load a new keymap. */
15613
15614
       int result;
15615
       result = sys_vircopy(m->PROC_NR, D, (vir_bytes) m->ADDRESS,
15616
             SELF, D, (vir_bytes) keymap,
15617
             (vir_bytes) sizeof(keymap));
15618
       return(result);
15619
15621
     /*_____*
15622
                                 do_fkey_ctl
15623
      PUBLIC void do_fkey_ctl(m_ptr)
15624
                                  /* pointer to the request message */
15625
      message *m ptr;
15626
15627
      /* This procedure allows processes to register a function key to receive
15628
      * notifications if it is pressed. At most one binding per key can exist.
15629
15630
       int i;
15631
        int result;
15632
15633
        switch (m_ptr->FKEY_REQUEST) {
                                         /* see what we must do */
                                          /* request for new mapping */
15634
        case FKEY_MAP:
15635
           result = OK;
                                         /* assume everything will be ok*/
                                         /* check F1-F12 keys */
15636
           for (i=0; i < 12; i++) {
               if (bit_isset(m_ptr->FKEY_FKEYS, i+1) ) {
15637
                  if (fkey_obs[i].proc_nr == NONE) {
15638
15639
                      fkey_obs[i].proc_nr = m_ptr->m_source;
                      fkey_obs[i].events = 0;
15640
                      bit_unset(m_ptr->FKEY_FKEYS, i+1);
15641
15642
                  } else {
                      printf("WARNING, fkey_map failed F%d\n", i+1);
15643
15644
                      result = EBUSY;
                                         /* report failure, but try rest */
```

```
Feb 25, 11 15:18
                                       book.txt
                                                                        Page 208/393
       File: Page: 845 drivers/tty/keyboard.c
15645
15646
15647
15648
             /* check Shift+F1-F12 keys */
15649
15650
                     if (sfkey_obs[i].proc_nr == NONE) {
15651
                         sfkey_obs[i].proc_nr = m_ptr->m_source;
15652
                         sfkey_obs[i].events = 0;
                         bit_unset(m_ptr->FKEY_SFKEYS, i+1);
15653
15654
                     } else {
                         printf("WARNING, fkey_map failed Shift F%d\n", i+1);
15655
15656
                         result = EBUSY;
                                              /* report failure but try rest */
15657
15658
15659
15660
             break;
15661
         case FKEY_UNMAP:
15662
             result = OK;
                                              /* assume everything will be ok*/
15663
             for (i=0; i < 12; i++) {
                                              /* check F1-F12 kevs */
                if (bit_isset(m_ptr->FKEY_FKEYS, i+1) ) {
15664
15665
                     if (fkey_obs[i].proc_nr == m_ptr->m_source)
15666
                         fkey_obs[i].proc_nr = NONE;
15667
                         fkey_obs[i].events = 0;
15668
                         bit_unset(m_ptr->FKEY_FKEYS, i+1);
15669
                     } else
15670
                         result = EPERM;
                                              /* report failure, but try rest */
15671
15672
15673
15674
             for (i=0; i < 12; i++) {
                                              /* check Shift+F1-F12 keys */
                 if (bit_isset(m_ptr->FKEY_SFKEYS, i+1) ) {
15675
15676
                     if (sfkey_obs[i].proc_nr == m_ptr->m_source) {
15677
                         sfkey_obs[i].proc_nr = NONE;
15678
                         sfkey_obs[i].events = 0;
15679
                         bit_unset(m_ptr->FKEY_SFKEYS, i+1);
15680
                     } else {
15681
                         result = EPERM;
                                              /* report failure, but try rest */
15682
15683
15684
15685
             break;
         case FKEY EVENTS:
15686
15687
             m_ptr->FKEY_FKEYS = m_ptr->FKEY_SFKEYS = 0;
15688
             for (i=0; i < 12; i++) {
                                             /* check (Shift+) F1-F12 keys */
15689
                 if (fkey obs[i].proc nr == m ptr->m source) {
15690
                     if (fkey_obs[i].events) {
                         bit_set(m_ptr->FKEY_FKEYS, i+1);
15691
15692
                         fkey_obs[i].events = 0;
15693
15694
15695
                 if (sfkey_obs[i].proc_nr == m_ptr->m_source) {
                     if (sfkey_obs[i].events)
15696
                         bit_set(m_ptr->FKEY_SFKEYS, i+1);
15697
15698
                         sfkey obs[i].events = 0;
15699
15700
15701
15702
             break;
15703
         default:
15704
                result = EINVAL;
                                              /* key cannot be observed */
```

```
Feb 25, 11 15:18
                                  book.txt
                                                               Page 209/393
      File: Page: 846 drivers/tty/keyboard.c
15705
15706
15707
        /* Almost done, return result to caller. */
15708
        m_ptr->m_type = result;
15709
       send(m_ptr->m_source, m_ptr);
15710 }
15712 /*=============*
                               func key
15714
       *----*/
15715 PRIVATE int func_key(scode)
15716 int scode;
                                 /* scan code for a function key */
15717
15718 /* This procedure traps function keys for debugging purposes. Observers of
     * function keys are kept in a global array. If a subject (a key) is pressed
15719
15720
       * the observer is notified of the event. Initialization of the arrays is done
15721
       * in kb_init, where NONE is set to indicate there is no interest in the key.
15722
      * Returns FALSE on a key release or if the key is not observable.
15723
15724
15725
        int key;
15726
        int proc_nr;
15727
        int i.s.
15728
       15729
15730
15731
15732
        /* Key pressed, now see if there is an observer for the pressed key.
15733
15734
                 F1-F12 observers are in fkey obs array.
           SHIFT F1-F12 observers are in sfkey_req array.
CTRL F1-F12 reserved (see kb_read)
15735
15736
15737
        * ALT F1-F12 reserved (see kb_read)
15738
         * Other combinations are not in use. Note that Alt+Shift+F1-F12 is yet
15739
         * defined in <minix/keymap.h>, and thus is easy for future extensions.
15740
       if (F1 <= key && key <= F12) {
    proc_nr = fkey_obs[key - F1].proc_nr;</pre>
15741
                                                /* F1-F12 */
15742
15743
           fkey_obs[key - F1].events ++ ;
15744
        } else if (SF1 <= key && key <= SF12) {
                                                /* Shift F2-F12 */
           proc_nr = sfkey_obs[key - SF1].proc_nr;
15745
15746
           sfkey obs[key - SF1].events ++;
15747
15748
        else {
15749
           return(FALSE);
                                                /* not observable */
15750
15751
15752
        /* See if an observer is registered and send it a message. */
15753
        if (proc_nr != NONE) {
15754
           m.NOTIFY_TYPE = FKEY_PRESSED;
15755
           notify(proc_nr);
15756
        return(TRUE);
15757
15758
                     show key mappings
       *----*/
15762
15763 PRIVATE void show_key_mappings()
15764
```

```
Feb 25, 11 15:18
                                 book.txt
                                                             Page 210/393
      File: Page: 847 drivers/tty/keyboard.c
15765
         int i.s;
15766
         struct proc proc;
15767
15768
         printf("\n");
15769
         printf("System information. Known function key mappings to request debug d
umps: \n");
15770
----\n");
15771
         for (i=0; i<12; i++) {
15772
           printf(" %sF%d: ", i+1<10? " ": "", i+1);
15773
15774
           if (fkey obs[i].proc nr != NONE) {
              if ((s=sys_getproc(&proc, fkey_obs[i].proc_nr))!=OK)
    printf("sys_getproc: %d\n", s);
15775
15776
15777
              printf("%-14.14s", proc.p_name);
15778
           } else {
15779
              printf("%-14.14s", "<none>");
15780
15781
           printf(" %sShift-F%d: ", i+1<10? " ": "", i+1);
15782
15783
           if (sfkey_obs[i].proc_nr != NONE) {
15784
              if ((s=sys_getproc(&proc, sfkey_obs[i].proc_nr))!=OK)
    printf("sys_getproc: %d\n", s);
15785
15786
              printf("%-14.14s", proc.p_name);
15787
           } else {
              printf("%-14.14s", "<none>");
15788
15789
           printf("\n");
15790
15791
15792
15793
         printf("Press one of the registered function keys to trigger a debug dump.\n
');
15794
         printf("\n");
15795 }
15797
      15798
                               scan kevboard
15799
      *=======*/
15800 PRIVATE int scan keyboard()
15801
      /* Fetch the character from the keyboard hardware and acknowledge it. */
15802
15803
        pvb pair t byte in[2], byte out[2];
15804
15805
        byte_in[0].port = KEYBD;
                                 /* get the scan code for the key struck */
15806
        byte in[1].port = PORT B;
                                 /* strobe the keyboard to ack the char */
15807
        sys_vinb(byte_in, 2);
                                 /* request actual input */
15808
15809
        pv_set(byte_out[0], PORT_B, byte_in[1].value | KBIT); /* strobe bit high */
15810
        15811
        sys_voutb(byte_out, 2);
                                /* request actual output */
15812
15813
        return(byte_in[0].value);
                                        /* return scan code */
15814 }
15817
                               do panic dumps
15819 PUBLIC void do_panic_dumps(m)
15820
      message *m;
                                 /* request message to TTY */
15821
15822 /* Wait for keystrokes for printing debugging info and reboot. */
15823
       int quiet, code;
15824
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 211/393
       File: Page: 848 drivers/tty/keyboard.c
15825
         /* A panic! Allow debug dumps until user wants to shutdown. */
15826
         printf("\nHit ESC to reboot, DEL to shutdown, F-keys for debug dumps\n");
15827
15828
         (void) scan_keyboard();
                                    /* ack any old input */
         quiet = scan_keyboard();/* quiescent value (0 on PC, last code on AT)*/
15829
15830
        for (;;) {
15831
              tickdelav(10);
15832
              /* See if there are pending request for output, but don't block.
15833
               * Diagnostics can span multiple printf()s, so do it in a loop.
15834
15835
              while (nb_receive(ANY, m) == OK) {
15836
                      switch(m->m_type) {
                      case FKEY_CONTROL: do_fkey_ctl(m);
15837
                                                            break;
15838
                      case SYS_SIG:
                                        do_new_kmess(m);
                                                            break;
                      case DIAGNOSTICS:
15839
                                       do diagnostics(m);
                                                           break;
15840
                      default:
                                             /* do nothing */
                                    ;
15841
15842
                      tickdelay(1);
                                            /* allow more */
15843
15844
              code = scan_keyboard();
15845
              if (code != quiet) {
15846
                      /* A key has been pressed. */
15847
                      switch (code) {
                                                    /* possibly abort MINIX */
                      case ESC SCAN: sys abort(RBT REBOOT); return;
15848
                      case DEL_SCAN: sys_abort(RBT_HALT);
15849
                                                           return;
15850
15851
                      (void) func key(code);
                                                   /* check for function key */
15852
                      quiet = scan_keyboard();
15853
15854
15855 }
drivers/tty/console.c
15900 /* Code and data for the IBM console driver.
15901 *
       * The 6845 video controller used by the IBM PC shares its video memory with
15902
15903
         the CPU somewhere in the 0xB0000 memory bank. To the 6845 this memory
         consists of 16-bit words. Each word has a character code in the low byte
15905
         and a so-called attribute byte in the high byte. The CPU directly modifies
15906
        * video memory to display characters, and sets two registers on the 6845 that
15907
         specify the video origin and the cursor position. The video origin is the
15908
        * place in video memory where the first character (upper left corner) can
15909
        * be found. Moving the origin is a fast way to scroll the screen. Some
15910
        * video adapters wrap around the top of video memory, so the origin can
15911
        * move without bounds. For other adapters screen memory must sometimes be
15912
        * moved to reset the origin. All computations on video memory use character
        * (word) addresses for simplicity and assume there is no wrapping. The
15914
        ^{\star} assembly support functions translate the word addresses to byte addresses
15915
        * and the scrolling function worries about wrapping.
15916
15917
15918 #include "../drivers.h"
15919 #include <termios.h>
```

```
Feb 25, 11 15:18
                                        book.txt
                                                                          Page 212/393
       File: Page: 849 drivers/tty/console.c
       #include <minix/callnr.h>
15921
       #include <minix/com.h>
15922 #include "tty.h"
15923
15924 #include "../../kernel/const.h"
15925 #include "../../kernel/config.h"
15926 #include "../../kernel/type.h"
15927
15928
       /* Definitions used by the console driver. */
                            0xB0000L /* base of mono video memory */
0xB8000L /* base of color video memory */
15929
       #define MONO_BASE
15930
       #define COLOR BASE
15931
       #define MONO SIZE
                              0x1000
                                        /* 4K mono video memory */
       #define COLOR_SIZE
                              0x4000
                                        /* 16K color video memory */
15932
                                       /* EGA & VGA have at least 32K */
15933
       #define EGA_SIZE
                              0x8000
       #define BLANK COLOR
                              0 \times 0700
                                        /* determines cursor color on blank screen */
15934
15935
       #define SCROLL UP
                                        /* scroll forward */
                                  Ω
15936
       #define SCROLL_DOWN
                                  1
                                        /* scroll backward */
       #define BLANK_MEM ((u16_t *) 0) /* tells mem_vid_copy() to blank the screen */
15937
15938
       #define CONS_RAM_WORDS
                               80 /* video ram buffer size */
4 /* number of escape sequence params allowed */
15939 #define MAX_ESC_PARMS
15940
15941
       /* Constants relating to the controller chips. */
15942 #define M_6845
                               0x3B4
                                        /* port for 6845 mono */
                                        /* port for 6845 color */
15943
       #define C 6845
                               0x3D4
15944
       #define INDEX
                                        /* 6845's index register */
                                  0
                                        /* 6845's data register */
15945
       #define DATA
                                        /* 6845's status register */
15946
       #define STATUS
                                       /* 6845's origin register */
15947
       #define VID ORG
                                  12
                                        /* 6845's cursor register */
15948
       #define CURSOR
                                  14
15949
15950
       /* Beeper. */
15951 #define BEEP_FREQ
                              0 \times 0533
                                        /* value to put into timer to set beep freq */
15952 #define B_TIME
                                        /* length of CTRL-G beep is ticks */
15953
15954
       /* definitions used for font management */
15955 #define GA_SEQUENCER_INDEX
                                        0x3C4
15956
       #define GA_SEQUENCER_DATA
                                        0x3C5
                                        0 \times 3 CE
15957
       #define GA_GRAPHICS_INDEX
15958
       #define GA GRAPHICS DATA
                                        0x3CF
       #define GA_VIDEO_ADDRESS
15959
                                        0×A0000T
15960
       #define GA_FONT_SIZE
                                        8192
15961
       /\!\!\!\!\!^{\star} Global variables used by the console driver and assembly support. ^{\star}/\!\!\!\!
15962
15963 PUBLIC int vid_index;
                                        /* index of video segment in remote mem map */
15964 PUBLIC ul6 t vid seq;
15965 PUBLIC vir_bytes vid_off;
                                        /* video ram is found at vid seq: vid off */
15966 PUBLIC unsigned vid_size;
                                        /* 0x2000 for color or 0x0800 for mono */
15967 PUBLIC unsigned vid_mask;
                                        /* 0x1FFF for color or 0x07FF for mono */
15968 PUBLIC unsigned blank_color = BLANK_COLOR; /* display code for blank */
15969
15970
      /* Private variables used by the console driver. */
15971 PRIVATE int vid_port;
                                        /* I/O port for accessing 6845 */
                                        /* hardware can wrap? */
15972 PRIVATE int wrap;
15973 PRIVATE int softscroll;
                                        /* 1 = software scrolling, 0 = hardware */
15974 PRIVATE int beeping;
                                        /* speaker is beeping? */
                                        /* font lines per character */
15975 PRIVATE unsigned font_lines;
15976 PRIVATE unsigned scr_width;
                                        /* # characters on a line */
15977 PRIVATE unsigned scr_lines;
                                        /* # lines on the screen */
                                        /* # characters on the screen */
15978 PRIVATE unsigned scr_size;
15979
```

```
book.txt
Feb 25, 11 15:18
                                                                    Page 213/393
      File: Page: 850 drivers/tty/console.c
15980 /* Per console data. */
15981 typedef struct console {
        tty_t *c_tty;
                                    /* associated TTY struct */
15983
        int c_column;
                                    /* current column number (0-origin) */
15984
                                    /* current row (0 at top of screen) */
        int c_row;
15985
        int c_rwords;
                                    /* number of WORDS (not bytes) in outqueue */
15986
        unsigned c_start;
                                    /* start of video memory of this console */
                                    /* limit of this console's video memory */
15987
        unsigned c_limit;
                                    /* location in RAM where 6845 base points */
15988
        unsigned c org;
15989
        unsigned c_cur;
                                    /* current position of cursor in video RAM */
                                    /* character attribute */
15990
        unsigned c attr;
15991
        unsigned c blank;
                                    /* blank attribute */
        char c reverse;
                                    /* reverse video */
15992
                                    /* 0=normal, 1=ESC, 2=ESC[ */
15993
        char c_esc_state;
15994
        char c esc intro;
                                    /* Distinguishing character following ESC */
15995
        int *c_esc_parmp;
                                    /* pointer to current escape parameter */
15996
        int c_esc_parmv[MAX_ESC_PARMS];
                                            /* list of escape parameters */
                                            /* buffer for video RAM */
15997
        u16_t c_ramqueue[CONS_RAM_WORDS];
15998
       } console_t;
15999
16000 PRIVATE int nr_cons= 1;
                                     /* actual number of consoles */
16001 PRIVATE console_t cons_table[NR_CONS];
16002 PRIVATE console_t *curcons;
                                    /* currently visible */
16003
16004 /* Color if using a color controller. */
16005 #define color (vid port == C 6845)
16006
16007 /* Map from ANSI colors to the attributes used by the PC */
16008 PRIVATE int ansi_colors[8] = {0, 4, 2, 6, 1, 5, 3, 7};
16010 /* Structure used for font management */
16011 struct sequence {
16012
             unsigned short index;
16013
              unsigned char port;
16014
              unsigned char value;
16015 };
16016
16017 FORWARD _PROTOTYPE( int cons_write, (struct tty *tp, int try)
                                                                          );
16018 FORWARD _PROTOTYPE( void cons_echo, (tty_t *tp, int c)
16019 FORWARD _PROTOTYPE( void out_char, (console_t *cons, int c)
                                                                          );
16020 FORWARD _PROTOTYPE( void putk, (int c)
                                                                          );
16021 FORWARD _PROTOTYPE( void beep, (void)
                                                                          );
16022 FORWARD _PROTOTYPE( void do_escape, (console_t *cons, int c)
                                                                          );
16023 FORWARD _PROTOTYPE( void flush, (console_t *cons)
                                                                          );
16024 FORWARD PROTOTYPE( void parse escape, (console t *cons, int c)
                                                                          );
16025 FORWARD _PROTOTYPE( void scroll_screen, (console_t *cons, int dir)
                                                                          );
16026 FORWARD _PROTOTYPE( void set_6845, (int reg, unsigned val)
                                                                          );
16027 FORWARD _PROTOTYPE( void get_6845, (int reg, unsigned *val)
                                                                          );
16028 FORWARD _PROTOTYPE( void stop_beep, (timer_t *tmrp)
                                                                          );
16029 FORWARD _PROTOTYPE( void cons_org0, (void)
                                                                          );
16030 FORWARD _PROTOTYPE( int ga_program, (struct sequence *seq)
                                                                          );
16031 FORWARD _PROTOTYPE( int cons_ioctl, (tty_t *tp, int)
16032
16033 /*-----*
16034 *
                                  cons_write
16035
      *-----*/
16036 PRIVATE int cons_write(tp, try)
                                    /* tells which terminal is to be used */
16037
      register struct tty *tp;
16038
      int try;
16039
```

```
book.txt
Feb 25, 11 15:18
                                                                         Page 214/393
       File: Page: 851 drivers/tty/console.c
16040 /* Copy as much data as possible to the output queue, then start I/O. On
16041
       * memory-mapped terminals, such as the IBM console, the I/O will also be
       * finished, and the counts updated. Keep repeating until all I/O done.
16043
16044
16045
         int count;
16046
         int result;
         register char *tbuf;
16047
16048
         char buf[64];
16049
         console_t *cons = tp->tty_priv;
16050
16051
         if (try) return 1; /* we can always write to console */
16052
16053
         /* Check quickly for nothing to do, so this can be called often without
16054
          * unmodular tests elsewhere.
16055
16056
         if ((count = tp->tty_outleft) == 0 || tp->tty_inhibited) return;
16057
16058
         /* Copy the user bytes to buf[] for decent addressing. Loop over the
16059
          * copies, since the user buffer may be much larger than buf[].
16060
16061
         do {
16062
               if (count > sizeof(buf)) count = sizeof(buf);
16063
               if ((result = sys vircopy(tp->tty outproc, D, tp->tty out vir,
16064
                               SELF, D, (vir_bytes) buf, (vir_bytes) count)) != OK)
16065
                       break;
               tbuf = buf;
16066
16067
16068
               /* Update terminal data structure. */
               tp->tty out vir += count;
16069
16070
               tp->tty_outcum += count;
16071
               tp->tty_outleft -= count;
16072
16073
               /* Output each byte of the copy to the screen. Avoid calling
16074
                * out_char() for the "easy" characters, put them into the buffer
16075
                * directly.
16076
16077
               do {
16078
                       if ((unsigned) *tbuf < ' ' | | cons->c_esc_state > 0
                                  cons->c_column >= scr_width
16079
16080
                                  cons->c_rwords >= buflen(cons->c_ramqueue))
16081
16082
                               out_char(cons, *tbuf++);
16083
                       } else {
16084
                               cons->c ramqueue[cons->c rwords++] =
16085
                                               cons->c_attr | (*tbuf++ & BYTE);
16086
                               cons->c_column++;
16087
16088
               } while (--count != 0);
16089
         } while ((count = tp->tty_outleft) != 0 && !tp->tty_inhibited);
16090
16091
         flush(cons);
                                       /* transfer anything buffered to the screen */
16092
16093
         /* Reply to the writer if all output is finished or if an error occured. */
16094
         if (tp->tty_outleft == 0 || result != OK) {
16095
               /* REVIVE is not possible. I/O on memory mapped consoles finishes. */
16096
               tty_reply(tp->tty_outrepcode, tp->tty_outcaller, tp->tty_outproc,
16097
                                                               tp->tty_outcum);
16098
               tp->tty_outcum = 0;
16099
```

```
Feb 25, 11 15:18
                               book.txt
                                                          Page 215/393
     File: Page: 852 drivers/tty/console.c
16100 }
16103 *
                               cons echo
16105 PRIVATE void cons_echo(tp, c)
                               /* pointer to tty struct */
16106 register tty_t *tp;
                               /* character to be echoed */
16107 int c;
16108
16109
     /* Echo keyboard input (print & flush). */
16110
       console_t *cons = tp->tty_priv;
16111
16112
       out char(cons. c);
16113
       flush(cons);
16114 }
16117
                              out_char
16118
     16119 PRIVATE void out_char(cons, c)
16120 register console_t *cons;
                               /* pointer to console struct */
16121 int c;
                               /* character to be output */
16122
16123 /* Output a character on the console. Check for escape sequences first. */
      if (cons->c_esc_state > 0) {
16124
16125
            parse_escape(cons, c);
16126
            return;
16127
16128
       switch(c) {
16129
16130
            case 000:
                                /* null is typically used for padding */
16131
                  return;
                               /* better not do anything */
16132
16133
            case 007:
                                /* ring the bell */
                               /* print any chars queued for output */
16134
                  flush(cons);
16135
                  beep();
16136
                  return;
16137
16138
            case '\b':
                                /* backspace */
                  if (--cons->c_column < 0) {
16139
16140
                        if (--cons->c row >= 0) cons->c column += scr width;
16141
16142
                  flush(cons);
16143
                  return;
16144
            case '\n':
                                /* line feed */
16145
16146
                  if ((cons->c_tty->tty_termios.c_oflag & (OPOST|ONLCR))
16147
                                            == (OPOST|ONLCR)) {
16148
                         cons->c_column = 0;
16149
16150
                   /*FALL THROUGH*/
16151
            case 013:
                               /* CTRL-K */
                                /* CTRL-L */
16152
            case 014:
                  if (cons->c row == scr lines-1) {
16153
16154
                        scroll_screen(cons, SCROLL_UP);
16155
                   } else {
16156
                         cons->c row++;
16157
16158
                  flush(cons);
16159
                  return;
```

```
Feb 25, 11 15:18
                                    book.txt
                                                                   Page 216/393
      File: Page: 853 drivers/tty/console.c
16160
16161
              case '\r':
                                     /* carriage return */
16162
                     cons->c_column = 0;
16163
                     flush(cons);
16164
                     return;
16165
16166
              case '\t':
                                    /* tab */
16167
                     cons->c_column = (cons->c_column + TAB_SIZE) & ~TAB_MASK;
                     if (cons->c column > scr width) {
16168
16169
                            cons->c_column -= scr_width;
16170
                             if (cons->c_row == scr_lines-1) {
16171
                                    scroll screen(cons, SCROLL UP);
16172
                             } else {
16173
                                    cons->c_row++;
16174
16175
16176
                     flush(cons);
16177
                     return;
16178
16179
              case 033:
                                     /* ESC - start of an escape sequence */
16180
                     flush(cons); /* print any chars queued for output */
16181
                     cons->c_esc_state = 1; /* mark ESC as seen */
16182
                     return;
16183
16184
                                    /* printable chars are stored in ramqueue */
              default:
16185
                     if (cons->c column >= scr width) {
                            if (!LINEWRAP) return;
16186
16187
                             if (cons->c_row == scr_lines-1) {
                                    scroll_screen(cons, SCROLL_UP);
16188
16189
16190
                                    cons->c row++;
16191
16192
                            cons->c_column = 0;
16193
                            flush(cons);
16194
16195
                     if (cons->c_rwords == buflen(cons->c_ramqueue)) flush(cons);
16196
                     cons->c_ramqueue[cons->c_rwords++] = cons->c_attr | (c & BYTE);
16197
                                                          /* next column */
                     cons->c column++;
16198
                     return;
16199
16200
16203
                                    scroll_screen
16204
      16205 PRIVATE void scroll screen(cons, dir)
16206 register console_t *cons;
                                    /* pointer to console struct */
                                    /* SCROLL_UP or SCROLL_DOWN */
16207
      int dir;
16208
16209
        unsigned new_line, new_org, chars;
16210
16211
        flush(cons);
16212
        chars = scr_size - scr_width;
                                           /* one screen minus one line */
16213
16214
        /* Scrolling the screen is a real nuisance due to the various incompatible
16215
         * video cards. This driver supports software scrolling (Hercules?),
         * hardware scrolling (mono and CGA cards) and hardware scrolling without
16216
         * wrapping (EGA cards). In the latter case we must make sure that
16217
16218
                     c_start <= c_org && c_org + scr_size <= c_limit</pre>
16219
         * holds, because EGA doesn't wrap around the end of video memory.
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 217/393
      File: Page: 854 drivers/tty/console.c
16220
16221
        if (dir == SCROLL_UP) {
              /* Scroll one line up in 3 ways: soft, avoid wrap, use origin. */
16222
16223
              if (softscroll) {
16224
                     vid_vid_copy(cons->c_start + scr_width, cons->c_start, chars);
16225
              if (!wrap && cons->c_org + scr_size + scr_width >= cons->c_limit)
16226
                     vid_vid_copy(cons->c_org + scr_width, cons->c_start, chars);
16227
16228
                     cons->c_org = cons->c_start;
16229
              } else {
16230
                     cons->c_org = (cons->c_org + scr_width) & vid_mask;
16231
16232
              new_line = (cons->c_org + chars) & vid_mask;
16233
        } else {
              /* Scroll one line down in 3 ways: soft, avoid wrap, use origin. */
16234
              if (softscroll) {
16235
16236
                     vid_vid_copy(cons->c_start, cons->c_start + scr_width, chars);
16237
16238
              if (!wrap && cons->c_org < cons->c_start + scr_width) {
16239
                     new_org = cons->c_limit - scr_size;
16240
                     vid_vid_copy(cons->c_org, new_org + scr_width, chars);
16241
                     cons->c_org = new_org;
16242
              } else {
16243
                     cons->c_org = (cons->c_org - scr_width) & vid_mask;
16244
16245
              new line = cons->c org;
16246
16247
        /* Blank the new line at top or bottom. */
16248
        blank_color = cons->c_blank;
        mem vid copy(BLANK MEM, new line, scr width);
16249
16250
16251
         /* Set the new video origin. */
16252
        if (cons == curcons) set_6845(VID_ORG, cons->c_org);
16253
        flush(cons);
16254
16256
      /*_____*
16257
                                    flush
16258
       PRIVATE void flush(cons)
16259
16260
      register console t *cons;
                                    /* pointer to console struct */
16261
16262
      /* Send characters buffered in 'ramqueue' to screen memory, check the new
16263
       * cursor position, compute the new hardware cursor position and set it.
16264
16265
        unsigned cur;
16266
        tty_t *tp = cons->c_tty;
16267
16268
        /* Have the characters in 'ramqueue' transferred to the screen. */
16269
        if (cons->c_rwords > 0) {
16270
              mem_vid_copy(cons->c_ramqueue, cons->c_cur, cons->c_rwords);
16271
              cons->c_rwords = 0;
16272
16273
              /* TTY likes to know the current column and if echoing messed up. */
16274
              tp->tty_position = cons->c_column;
16275
              tp->tty_reprint = TRUE;
16276
16277
16278
         /* Check and update the cursor position. */
16279
        if (cons->c column < 0) cons->c column = 0;
```

```
book.txt
Feb 25, 11 15:18
                                                                      Page 218/393
       File: Page: 855 drivers/tty/console.c
16280
        if (cons->c_column > scr_width) cons->c_column = scr_width;
16281
        if (cons->c_row < 0) cons->c_row = 0;
        if (cons->c_row >= scr_lines) cons->c_row = scr_lines - 1;
16282
16283
        cur = cons->c_org + cons->c_row * scr_width + cons->c_column;
16284
        if (cur != cons->c_cur) {
16285
              if (cons == curcons) set_6845(CURSOR, cur);
16286
              cons->c_cur = cur;
16287
16288 }
16290
16291
                                   parse escape
16292
       *-----*
16293 PRIVATE void parse_escape(cons, c)
16294 register console_t *cons;
                                 /* pointer to console struct */
16295 char c;
                                     /* next character in escape sequence */
16296
16297 /* The following ANSI escape sequences are currently supported.
       * If n and/or m are omitted, they default to 1.
16298
       * ESC [nA moves up n lines
16299
16300
           ESC [nB moves down n lines
16301
           ESC [nC moves right n spaces
16302
           ESC [nD moves left n spaces
16303
           ESC [m;nH" moves cursor to (m,n)
16304
           ESC [J clears screen from cursor
16305
           ESC [K clears line from cursor
16306
           ESC [nL inserts n lines ar cursor
16307
           ESC [nM deletes n lines at cursor
16308
           ESC [nP deletes n chars at cursor
16309
           ESC [n@ inserts n chars at cursor
16310
           ESC [nm enables rendition n (0=normal, 4=bold, 5=blinking, 7=reverse)
16311
           ESC M scrolls the screen backwards if the cursor is on the top line
16312
16313
16314
         switch (cons->c_esc_state) {
16315
          case 1:
                                      /* ESC seen */
              cons->c_esc_intro = '\0';
16316
16317
              cons->c_esc_parmp = bufend(cons->c_esc_parmv);
16318
16319
                      *--cons->c_esc_parmp = 0;
16320
              } while (cons->c_esc_parmp > cons->c_esc_parmv);
16321
              switch (c) {
16322
                  case '[':
                              /* Control Sequence Introducer */
16323
                      cons->c_esc_intro = c;
16324
                      cons->c esc state = 2;
16325
                      break;
16326
                  case 'M':
                               /* Reverse Index */
16327
                      do_escape(cons, c);
16328
                      break;
                  default:
16329
16330
                      cons->c_esc_state = 0;
16331
16332
              break;
16333
16334
                                      /* ESC [ seen */
          case 2:
              if (c >= '0' && c <= '9') {
16335
                     if (cons->c esc parmp < bufend(cons->c esc parmv))
16336
16337
                              *cons->c_esc_parmp = *cons->c_esc_parmp * 10 + (c-'0');
16338
               } else
16339
              if (c == ';') {
```

```
Feb 25, 11 15:18
                                  book.txt
                                                              Page 219/393
      File: Page: 856 drivers/tty/console.c
16340
                   if (cons->c esc parmp < bufend(cons->c esc parmv))
16341
                          cons->c_esc_parmp++;
16342
             } else {
16343
                   do_escape(cons, c);
16344
16345
             break;
16346
16347 }
16350 *
                                 do escape
      *----*/
16352 PRIVATE void do_escape(cons, c)
                                /* pointer to console struct */
16353 register console_t *cons;
16354 char c;
                                 /* next character in escape sequence */
16355
16356
       int value, n;
16357
       unsigned src, dst, count;
16358
       int *parmp;
16359
16360
        /* Some of these things hack on screen RAM, so it had better be up to date */
16361
       flush(cons);
16362
16363
       if (cons->c_esc_intro == '\0') {
             /* Handle a sequence beginning with just ESC */
16364
             switch (c) {
16365
                case 'M':
                                 /* Reverse Index */
16366
                   if (cons->c_row == 0) {
16367
16368
                          scroll_screen(cons, SCROLL_DOWN);
16369
                    } else {
16370
                          cons->c row--;
16371
16372
                   flush(cons);
16373
                   break;
16374
16375
                default: break;
16376
16377
       } else
16378
       if (cons->c esc intro == '[') {
             /* Handle a sequence beginning with ESC [ and parameters */
16379
16380
             value = cons->c_esc_parmv[0];
             switch (c) {
16381
                case 'A':
16382
                                  /* ESC [nA moves up n lines */
16383
                   n = (value == 0 ? 1 : value);
                   cons->c row -= n;
16384
16385
                   flush(cons);
16386
                   break;
16387
16388
                case 'B':
                                 /* ESC [nB moves down n lines */
16389
                   n = (value == 0 ? 1 : value);
16390
                   cons->c_row += n;
16391
                   flush(cons);
16392
                   break;
16393
                   16394
                case 'C':
16395
                   cons->c column += n;
16396
                   flush(cons);
16397
16398
                   break;
16399
```

```
book.txt
Feb 25, 11 15:18
                                                                         Page 220/393
       File: Page: 857 drivers/tty/console.c
16400
                   case 'D':
                                       /* ESC [nD moves left n spaces */
16401
                      n = (value == 0 ? 1 : value);
16402
                       cons->c_column -= n;
16403
                       flush(cons);
16404
                      break;
16405
16406
                   case 'H':
                                       /* ESC [m;nH" moves cursor to (m,n) */
16407
                      cons->c_row = cons->c_esc_parmv[0] - 1;
16408
                       cons->c column = cons->c esc parmv[1] - 1;
                       flush(cons);
16409
16410
                      break;
16411
                                        /* ESC [sJ clears in display */
                   case 'J':
16412
16413
                      switch (value) {
                                        /\!\!\!\!\!\!^{\star} Clear from cursor to end of screen ^{\star}/\!\!\!\!
16414
                          case 0:
16415
                               count = scr_size - (cons->c_cur - cons->c_org);
16416
                               dst = cons->c_cur;
16417
                               break;
16418
                           case 1:
                                        /* Clear from start of screen to cursor */
16419
                              count = cons->c_cur - cons->c_org;
16420
                               dst = cons->c_org;
16421
                              break;
16422
                           case 2:
                                        /* Clear entire screen */
16423
                               count = scr size;
16424
                               dst = cons->c_org;
16425
                               break;
                                        /* Do nothing */
16426
                           default:
16427
                               count = 0;
16428
                               dst = cons->c_org;
16429
16430
                       blank color = cons->c blank;
16431
                       mem_vid_copy(BLANK_MEM, dst, count);
16432
16433
                   case 'K':
                                        /* ESC [sK clears line from cursor */
16434
16435
                      switch (value) {
                                        /* Clear from cursor to end of line */
16436
                          case 0:
16437
                             count = scr_width - cons->c_column;
16438
                               dst = cons->c cur;
16439
                              break;
16440
                           case 1:
                                        /* Clear from beginning of line to cursor */
                               count = cons->c column;
16441
                               dst = cons->c_cur - cons->c_column;
16442
16443
                               break;
16444
                                        /* Clear entire line */
                           case 2:
16445
                               count = scr width;
16446
                               dst = cons->c_cur - cons->c_column;
16447
                               break;
16448
                           default:
                                        /* Do nothing */
16449
                              count = 0;
16450
                               dst = cons->c_cur;
16451
16452
                       blank_color = cons->c_blank;
                       mem_vid_copy(BLANK_MEM, dst, count);
16453
16454
                       break;
16455
                   case 'L':
                                        /* ESC [nL inserts n lines at cursor */
16456
                      n = value;
16457
16458
                       if (n < 1) n = 1;
16459
                       if (n > (scr lines - cons->c row))
```

```
Feb 25, 11 15:18
                                       book.txt
                                                                         Page 221/393
       File: Page: 858 drivers/tty/console.c
16460
                               n = scr_lines - cons->c_row;
16461
16462
                       src = cons->c_org + cons->c_row * scr_width;
16463
                       dst = src + n * scr_width;
16464
                       count = (scr_lines - cons->c_row - n) * scr_width;
16465
                       vid_vid_copy(src, dst, count);
16466
                       blank_color = cons->c_blank;
16467
                       mem_vid_copy(BLANK_MEM, src, n * scr_width);
16468
16469
16470
                   case 'M':
                                        /* ESC [nM deletes n lines at cursor */
16471
                       n = value;
16472
                       if (n < 1) n = 1;
16473
                       if (n > (scr_lines - cons->c_row))
                               n = scr lines - cons->c row;
16474
16475
16476
                       dst = cons->c_org + cons->c_row * scr_width;
16477
                       src = dst + n * scr_width;
16478
                       count = (scr_lines - cons->c_row - n) * scr_width;
16479
                       vid_vid_copy(src, dst, count);
16480
                       blank_color = cons->c_blank;
16481
                       mem_vid_copy(BLANK_MEM, dst + count, n * scr_width);
16482
                       break;
16483
16484
                   case '@':
                                        /* ESC [n@ inserts n chars at cursor */
16485
                       n = value;
16486
                       if (n < 1) n = 1;
                       if (n > (scr_width - cons->c_column))
16487
16488
                               n = scr_width - cons->c_column;
16489
16490
                       src = cons->c_cur;
16491
                       dst = src + n;
16492
                       count = scr_width - cons->c_column - n;
16493
                       vid_vid_copy(src, dst, count);
16494
                       blank_color = cons->c_blank;
                       mem_vid_copy(BLANK_MEM, src, n);
16495
16496
                       break;
16497
16498
                   case 'P':
                                        /* ESC [nP deletes n chars at cursor */
16499
                       n = value;
16500
                       if (n < 1) n = 1;
                       if (n > (scr width - cons->c column))
16501
                              n = scr_width - cons->c_column;
16502
16503
16504
                       dst = cons->c cur;
16505
                       src = dst + n;
16506
                       count = scr_width - cons->c_column - n;
16507
                       vid_vid_copy(src, dst, count);
16508
                       blank_color = cons->c_blank;
16509
                       mem_vid_copy(BLANK_MEM, dst + count, n);
16510
                       break;
16511
                   case 'm':
16512
                                        /* ESC [nm enables rendition n */
16513
                       for (parmp = cons->c_esc_parmv; parmp <= cons->c_esc_parmp
16514
                                       && parmp < bufend(cons->c_esc_parmv); parmp++) {
16515
                               if (cons->c reverse)
                                       /* Unswap fg and bg colors */
16516
                                       cons->c_attr = ((cons->c_attr & 0x7000) >> 4)
16517
16518
                                                        ((cons->c_attr & 0x0700) << 4)
16519
                                                       ((cons->c attr & 0x8800));
```

```
Feb 25, 11 15:18
                                        book.txt
                                                                         Page 222/393
       File: Page: 859 drivers/tty/console.c
16520
16521
                               switch (n = *parmp) {
16522
                                   case 0: /* NORMAL */
16523
                                       cons->c_attr = cons->c_blank = BLANK_COLOR;
16524
                                       cons->c_reverse = FALSE;
16525
                                       break;
16526
                                                /* BOLD */
16527
                                   case 1:
16528
                                       /* Set intensity bit */
16529
                                       cons->c_attr |= 0x0800;
16530
                                       break;
16531
                                                /* UNDERLINE */
16532
                                   case 4:
16533
                                       if (color) {
16534
                                                /* Change white to cyan, i.e. lose red
16535
16536
                                                cons->c_attr = (cons->c_attr & 0xBBFF);
16537
                                        } else {
16538
                                                /* Set underline attribute */
16539
                                                cons->c_attr = (cons->c_attr & 0x99FF);
16540
16541
                                       hreak;
16542
                                                /* BLINKING */
16543
                                   case 5:
                                       /* Set the blink bit */
16544
16545
                                       cons->c_attr |= 0x8000;
16546
                                       break;
16547
                                                /* REVERSE */
16548
                                   case 7:
16549
                                       cons->c reverse = TRUE;
16550
                                       break;
16551
16552
                                   default:
                                                /* COLOR */
16553
                                       if (n == 39) n = 37;
                                                                /* set default color */
16554
                                       if (n == 49) n = 40;
16555
16556
                                       if (!color)
16557
                                               /* Don't mess up a monochrome screen */
16558
                                         else
16559
                                       if (30 <= n && n <= 37)
16560
                                                /* Foreground color */
16561
                                               cons->c_attr =
                                                        (cons->c_attr & 0xF8FF) |
16562
16563
                                                        (ansi_colors[(n - 30)] << 8);
16564
                                                cons->c blank =
16565
                                                        (cons->c blank & 0xF8FF)
16566
                                                        (ansi_colors[(n - 30)] << 8);
16567
16568
                                       if (40 <= n && n <= 47)
16569
                                                /* Background color */
16570
                                                cons->c_attr =
                                                        (cons->c_attr & 0x8FFF) |
16571
                                                        (ansi_colors[(n - 40)] << 12);
16572
16573
                                               cons->c blank =
16574
                                                        (cons->c_blank & 0x8FFF)
16575
                                                        (ansi colors[(n - 40)] << 12);
16576
16577
                               if (cons->c_reverse) {
16578
16579
                                       /* Swap fg and bg colors */
```

```
book.txt
Feb 25, 11 15:18
                                                      Page 223/393
     File: Page: 860 drivers/tty/console.c
16580
                             cons->c_attr = ((cons->c_attr & 0x7000) >> 4)
16581
                                         ((cons->c_attr & 0x0700) << 4)
                                         ((cons->c_attr & 0x8800));
16582
16583
16584
16585
                 break;
16586
16587
16588
      cons->c_esc_state = 0;
16589
    /*----*
16592
                           set 6845
16593
      16594 PRIVATE void set_6845(reg, val)
16595 int reg;
                             /* which register pair to set */
16596
     unsigned val;
                            /* 16-bit value to set it to */
16597
16598 /* Set a register pair inside the 6845.
     * Registers 12-13 tell the 6845 where in video ram to start
16599
      * Registers 14-15 tell the 6845 where to put the cursor
16601
16602
      pvb_pair_t char_out[4];
      pv_set(char_out[0], vid_port + INDEX, reg); /* set index register */
16603
      16604
16605
      pv_set(char_out[3], vid_port + DATA, val&BYTE);
                                                  /* low byte */
16606
16607
      sys_voutb(char_out, 4);
                                         /* do actual output */
16608
16611 *
                           get_6845
    16613 PRIVATE void get_6845(reg, val)
                             /* which register pair to set */
16614 int req;
16615 unsigned *val;
                            /* 16-bit value to set it to */
16616 {
16617
      char v1, v2;
16618 /* Get a register pair inside the 6845. */
     sys_outb(vid_port + INDEX, reg);
16619
      sys_inb(vid_port + DATA, &v1);
16620
      sys_outb(vid_port + INDEX, reg+1);
16621
      sys_inb(vid_port + DATA, &v2);

*val = (v1 << 8) | v2;
16622
16623
16624 }
16626 /*========*
                           beep
16628 *==========*/
16629 PRIVATE void beep()
16630
16631 /* Making a beeping sound on the speaker (output for CRTL-G).
     * This routine works by turning on the bits 0 and 1 in port B of the 8255
16632
     * chip that drive the speaker.
16633
16634
16635
      static timer_t tmr_stop_beep;
      pvb_pair_t char_out[3];
16636
16637
       clock t now;
16638
      int port_b_val, s;
16639
```

```
Feb 25, 11 15:18
                                   book.txt
                                                                Page 224/393
      File: Page: 861 drivers/tty/console.c
16640
        /* Fetch current time in advance to prevent beeping delay. */
16641
        if ((s=getuptime(&now)) != OK)
             panic("TTY", "Console couldn't get clock's uptime.", s);
16642
        if (!beeping) {
16643
16644
             /* Set timer channel 2, square wave, with given frequency. */
16645
             pv_set(char_out[0], TIMER_MODE, 0xB6);
             pv_set(char_out[1], TIMER2, (BEEP_FREQ >> 0) & BYTE);
pv_set(char_out[2], TIMER2, (BEEP_FREQ >> 8) & BYTE);
16646
16647
             if (sys_voutb(char_out, 3)==OK) {
16648
                    if (sys_inb(PORT_B, &port_b_val)==OK &&
16649
16650
                        sys_outb(PORT_B, (port_b_val | 3)) == OK)
16651
                           beeping = TRUE;
16652
16653
16654
        /* Add a timer to the timers list. Possibly reschedule the alarm. */
        tmrs_settimer(&tty_timers, &tmr_stop_beep, now+B_TIME, stop_beep, NULL);
16655
16656
        if (tty_timers->tmr_exp_time != tty_next_timeout) {
16657
             tty_next_timeout = tty_timers->tmr_exp_time;
16658
             if ((s=sys_setalarm(tty_next_timeout, 1)) != OK)
                    panic("TTY", "Console couldn't set alarm.", s);
16659
16660
16661 }
16663 /*==========*
16664
                               stop_beep
16665
      *_____*
16666 PRIVATE void stop beep(tmrp)
16667
      timer t *tmrp;
16668
16669 /* Turn off the beeper by turning off bits 0 and 1 in PORT B. */
16670
       int port b val;
16671
       if (sys_inb(PORT_B, &port_b_val) == OK &&
16672
             sys_outb(PORT_B, (port_b_val & ~3)) == OK)
16673
                    beeping = FALSE;
16674 }
16676 /*============*
      * scr_init
16677
16678
      16679 PUBLIC void scr_init(tp)
16680
      tty t *tp;
16681
16682 /* Initialize the screen driver. */
16683
       console_t *cons;
        phys bytes vid base;
16684
16685
        ul6 t bios columns, bios crtbase, bios fontlines;
16686
        u8_t bios_rows;
        int line;
16687
16688
        int s;
16689
        static int vdu_initialized = 0;
16690
        unsigned page_size;
16691
16692
        /* Associate console and TTY. */
        line = tp - &tty table[0];
16693
16694
        if (line >= nr_cons) return;
16695
        cons = &cons table[line];
16696
        cons->c tty = tp;
16697
        tp->tty_priv = cons;
16698
16699
        /* Initialize the keyboard driver. */
```

```
Feb 25, 11 15:18
                                       book.txt
                                                                        Page 225/393
       File: Page: 862 drivers/tty/console.c
16700
         kb_init(tp);
16701
16702
         /* Fill in TTY function hooks. */
         tp->tty_devwrite = cons_write;
16703
16704
         tp->tty_echo = cons_echo;
16705
         tp->tty_ioctl = cons_ioctl;
16706
16707
         /* Get the BIOS parameters that describe the VDU. */
16708
         if (! vdu initialized++) {
16709
16710
               /* How about error checking? What to do on failure??? */
16711
               s=sys_vircopy(SELF, BIOS_SEG, (vir_bytes) VDU_SCREEN_COLS_ADDR,
                       SELF, D, (vir_bytes) &bios_columns, VDU_SCREEN_COLS_SIZE);
16712
16713
               s=sys_vircopy(SELF, BIOS_SEG, (vir_bytes) VDU_CRT_BASE_ADDR,
                       SELF, D, (vir_bytes) &bios_crtbase, VDU_CRT_BASE_SIZE);
16714
16715
               s=sys_vircopy(SELF, BIOS_SEG, (vir_bytes) VDU_SCREEN_ROWS_ADDR,
16716
                       SELF, D, (vir_bytes) &bios_rows, VDU_SCREEN_ROWS_SIZE);
               s=sys_vircopy(SELF, BIOS_SEG, (vir_bytes) VDU_FONTLINES_ADDR,
16717
16718
                       SELF, D, (vir_bytes) &bios_fontlines, VDU_FONTLINES_SIZE);
16710
16720
               vid_port = bios_crtbase;
16721
               scr_width = bios_columns;
16722
               font_lines = bios_fontlines;
16723
               scr lines = machine.vdu ega ? bios rows+1 : 25;
16724
16725
               if (color) {
                       vid base = COLOR BASE;
16726
                       vid_size = COLOR_SIZE;
16727
16728
               } else {
                       vid base = MONO BASE;
16729
16730
                       vid size = MONO SIZE;
16731
16732
               if (machine.vdu_ega) vid_size = EGA_SIZE;
16733
               wrap = ! machine.vdu_ega;
16734
16735
               s = sys_segctl(&vid_index, &vid_seg, &vid_off, vid_base, vid_size);
16736
16737
                                     /* word count */
               vid size >>= 1;
16738
               vid mask = vid size - 1;
16739
16740
               /* Size of the screen (number of displayed characters.) */
               scr size = scr lines * scr width;
16741
16742
16743
               /* There can be as many consoles as video memory allows. */
16744
               nr cons = vid size / scr size;
16745
               if (nr cons > NR CONS) nr cons = NR CONS;
16746
               if (nr_cons > 1) wrap = 0;
16747
              page_size = vid_size / nr_cons;
16748
16749
16750
         cons->c_start = line * page_size;
16751
         cons->c_limit = cons->c_start + page_size;
16752
         cons->c_cur = cons->c_org = cons->c_start;
         cons->c_attr = cons->c_blank = BLANK_COLOR;
16753
16754
16755
         if (line != 0) {
               /* Clear the non-console vtys. */
16756
               blank color = BLANK COLOR;
16757
16758
               mem_vid_copy(BLANK_MEM, cons->c_start, scr_size);
16759
        } else {
```

```
Feb 25, 11 15:18
                                 book.txt
                                                            Page 226/393
      File: Page: 863 drivers/tty/console.c
16760
            int i. n;
16761
            /* Set the cursor of the console vty at the bottom. c_cur
16762
             * is updated automatically later.
16763
16764
            scroll_screen(cons, SCROLL_UP);
16765
            cons->c_row = scr_lines - 1;
16766
            cons->c column = 0;
16767
16768
       select console(0);
16769
       cons_ioctl(tp, 0);
16770
16773 *
                              kputc
16775 PUBLIC void kputc(c)
16776 int c;
16777 {
16778
            putk(c);
16779
16781 /*=========*
16782 *
                       do_new_kmess
16783
     16784 PUBLIC void do_new_kmess(m)
16785 message *m;
16786
16787
       * Notification for a new kernel message. */
                                              /* kmessages structure */
16788
       struct kmessages kmess;
                                              /* previous next seen */
16789
       static int prev next = 0;
16790
       int size, next;
16791
       int bytes;
16792
       int r;
16793
       /* Try to get a fresh copy of the buffer with kernel messages. */
16794
16795
       sys_getkmessages(&kmess);
16796
16797
       /* Print only the new part. Determine how many new bytes there are with
16798
        * help of the current and previous 'next' index. Note that the kernel
16799
        * buffer is circular. This works fine if less then KMESS_BUF_SIZE bytes
16800
        * is new data; else we miss % KMESS BUF SIZE here.
        * Check for size being positive, the buffer might as well be emptied!
16801
16802
16803
       if (kmess.km_size > 0) {
16804
           bytes = ((kmess.km next + KMESS BUF SIZE) - prev next) % KMESS BUF SIZE;
16805
                                              /* start at previous old */
           r=prev next;
16806
           while (bytes > 0) {
              putk( kmess.km_buf[(r%KMESS_BUF_SIZE)] );
16807
16808
              bytes --:
16809
              r ++;
16810
          putk(0);
16811
                                /* terminate to flush output */
16812
16813
16814
       /* Almost done, store 'next' so that we can determine what part of the
16815
        * kernel messages buffer to print next time a notification arrives.
16816
16817
       prev_next = kmess.km_next;
16818 }
```

```
Feb 25, 11 15:18
                             book.txt
                                                      Page 227/393
     File: Page: 864 drivers/tty/console.c
16821
                     do_diagnostics
     16823 PUBLIC void do_diagnostics(m_ptr)
16824 message *m_ptr;
                            /* pointer to request message */
16825
16826 /* Print a string for a server. */
16827
      char c;
16828
      vir bytes src;
16829
      int count;
16830
      int result = OK;
16831
      int proc_nr = m_ptr->DIAG_PROC_NR;
      if (proc_nr == SELF) proc_nr = m_ptr->m_source;
16832
16833
16834
       src = (vir bytes) m ptr->DIAG PRINT BUF;
16835
      for (count = m_ptr->DIAG_BUF_COUNT; count > 0; count--) {
16836
           if (sys_vircopy(proc_nr, D, src++, SELF, D, (vir_bytes) &c, 1) != OK) {
16837
                 result = EFAULT;
16838
                 break;
16839
16840
           putk(c);
16841
16842
      putk(0);
                             /* always terminate, even with EFAULT */
16843
      m_ptr->m_type = result;
16844
      send(m_ptr->m_source, m_ptr);
16845
16848
     16850 PRIVATE void putk(c)
16851 int c;
                            /* character to print */
16852
16853 \dot{} This procedure is used by the version of printf() that is linked with
     * the TTY driver. The one in the library sends a message to FS, which is
16854
     * not what is needed for printing within the TTY. This version just queues
16856
      * the character and starts the output.
16857
16858
      if (c != 0) {
16859
           if (c == '\n') putk('\r');
16860
           out_char(&cons_table[0], (int) c);
16861
      } else {
           flush(&cons_table[0]);
16862
16863
16864 }
16866
     /*____*
                           toggle_scroll
16868
     *-----*/
16869 PUBLIC void toggle_scroll()
16870
16871 /* Toggle between hardware and software scroll. */
16872
16873
      cons orq0();
16874
      softscroll = !softscroll;
16875
      printf("%sware scrolling enabled.\n", softscroll ? "Soft" : "Hard");
16876
```

```
book.txt
Feb 25, 11 15:18
                                                       Page 228/393
     File: Page: 865 drivers/tty/console.c
16878 /*=============*
16879
                    cons stop
16880
     *_____*
16881 PUBLIC void cons stop()
16882
16883 /* Prepare for halt or reboot. */
16884
      cons_org0();
16885
      softscroll = 1;
16886
      select console(0);
16887
      cons_table[0].c_attr = cons_table[0].c_blank = BLANK_COLOR;
16888
16890
     /*============*
16891
                            cons_org0
16892
16893
     PRIVATE void cons org0()
16894
16895 /* Scroll video memory back to put the origin at 0. */
16896
      int cons_line;
      console_t *cons;
16897
      unsigned n;
16898
16899
16900
      for (cons_line = 0; cons_line < nr_cons; cons_line++) {</pre>
           cons = &cons table[cons line];
16901
16902
           while (cons->c_org > cons->c_start) {
                                         /* amount of unused memory */
16903
                 n = vid_size - scr_size;
16904
                 if (n > cons->c_org - cons->c_start)
16905
                       n = cons->c_org - cons->c_start;
16906
                 vid_vid_copy(cons->c_org, cons->c_org - n, scr_size);
16907
                 cons->c org -= n;
16908
16909
           flush(cons);
16910
16911
      select_console(ccurrent);
16912
16914
     /*_____*
16915
                   select_console
16916
     *===========*/
     PUBLIC void select_console(int cons_line)
16917
16918
16919 /* Set the current console to console number 'cons line'. */
16920
16921
      if (cons_line < 0 || cons_line >= nr_cons) return;
      ccurrent = cons line;
16922
16923
      curcons = &cons_table[cons_line];
16924
      set_6845(VID_ORG, curcons->c_org);
16925
      set_6845(CURSOR, curcons->c_cur);
16926 }
16928
     16929
                            con loadfont
16930 *-----*/
16931 PUBLIC int con loadfont(m)
16932 message *m;
16933
16934 /* Load a font into the EGA or VGA adapter. */
     int result;
16935
16936
      static struct sequence seq1[7] = {
16937
           { GA SEQUENCER INDEX, 0x00, 0x01 },
```

```
Feb 25, 11 15:18
                                 book.txt
                                                              Page 229/393
      File: Page: 866 drivers/tty/console.c
16938
              GA_SEQUENCER_INDEX, 0x02, 0x04 }
16939
              GA_SEQUENCER_INDEX, 0x04, 0x07
              GA_SEQUENCER_INDEX, 0x00, 0x03 }, GA_GRAPHICS_INDEX, 0x04, 0x02 },
16940
16941
16942
              GA_GRAPHICS_INDEX, 0x05, 0x00
16943
              GA_GRAPHICS_INDEX, 0x06, 0x00 },
16944
16945
       static struct sequence seq2[7] = {
              GA_SEQUENCER_INDEX, 0x00, 0x01 }
16946
              GA_SEQUENCER_INDEX, 0x02, 0x03
16947
16948
              GA_SEQUENCER_INDEX, 0x04, 0x03
16949
              GA_SEQUENCER_INDEX, 0x00, 0x03 },
              GA_GRAPHICS_INDEX, 0x04, 0x00 },
16950
              GA_GRAPHICS_INDEX, 0x05, 0x10
16951
              GA GRAPHICS INDEX, 0x06,
16952
       };
16953
16954
16955
       seq2[6].value= color ? 0x0E : 0x0A;
16956
16957
        if (!machine.vdu_ega) return(ENOTTY);
16958
       result = ga_program(seq1); /* bring font memory into view */
16959
       result = sys_physcopy(m->PROC_NR, D, (vir_bytes) m->ADDRESS,
16960
16961
            NONE, PHYS_SEG, (phys_bytes) GA_VIDEO_ADDRESS, (phys_bytes)GA_FONT_SIZE)
16962
16963
       result = qa program(seq2); /* restore */
16964
16965
       return(result);
16966
16968
     /*_____*
16969
                              ga_program
16970
     16971 PRIVATE int ga_program(seq)
16972 struct sequence *seq;
16973 {
16974
       pvb_pair_t char_out[14];
16975
       int i;
16976
       for (i=0; i<7; i++) {
           pv_set(char_out[2*i], seq->index, seq->port);
16977
16978
           pv_set(char_out[2*i+1], seq->index+1, seq->value);
16979
           seq++;
16980
16981
       return sys voutb(char out, 14);
16982
16985
                               cons_ioctl
16986
     *----*/
16987 PRIVATE int cons_ioctl(tp, try)
16988 tty_t *tp;
16989 int try;
16990
16991 /* Set the screen dimensions. */
16992
16993
       tp->tty winsize.ws row= scr lines;
16994
       tp->tty_winsize.ws_col= scr_width;
       tp->tty_winsize.ws_xpixel= scr_width * 8;
16995
16996
       tp->tty_winsize.ws_ypixel= scr_lines * font_lines;
16997 }
```

```
book.txt
 Feb 25, 11 15:18
                                                           Page 230/393
      File: Page: 867 servers/pm/pm.h
servers/pm/pm.h
17000 /* This is the master header for PM. It includes some other files
17001
      * and defines the principal constants.
17002
17003 #define _POSIX_SOURCE
                           1 /* tell headers to include POSIX stuff */
                           1 /* tell headers to include MINIX stuff */
1 /* tell headers that this is the kernel */
17004 #define _MINIX
17005 #define SYSTEM
17006
17007
      /* The following are so basic, all the *.c files get them automatically. */
17008 #include <minix/config.h> /* MUST be first */
17009 #include <ansi.h>
                                /* MUST be second */
17010 #include <sys/types.h>
17011 #include <minix/const.h>
17012 #include <minix/type.h>
17013
17014 #include <fcntl.h>
17015 #include <unistd.h>
17016 #include <minix/syslib.h>
17017 #include <minix/sysutil.h>
17018
17019 #include <limits.h>
17020 #include <errno.h>
17021
17022 #include "const.h"
17023 #include "type.h"
17024 #include "proto.h"
17025 #include "glo.h"
servers/pm/const.h
17100 /* Constants used by the Process Manager. */
17101
17102 #define NO_MEM ((phys_clicks) 0) /* returned by alloc_mem() with mem is up */
17103
17104 #define NR PIDS
                                /* process ids range from 0 to NR PIDS-1.
                                 * (magic constant: some old applications use
17105
17106
                                 * a 'short' instead of pid_t.)
17107
17108
17109 #define PM_PID
                              /* PM's process id number */
17110 #define INIT_PID
                             /* INIT's process id number */
17111
```

```
book.txt
Feb 25, 11 15:18
                                                            Page 231/393
      File: Page: 868 servers/pm/type.h
servers/pm/type.h
17200 /* If there were any type definitions local to the Process Manager, they would
17201 * be here. This file is included only for symmetry with the kernel and File
17202 * System, which do have some local type definitions.
17203 */
17204
servers/pm/proto.h
17300 /* Function prototypes. */
17301
17302 struct mproc;
17303 struct stat;
17304 struct mem_map;
17305 struct memory;
17306
17307 #include <timers.h>
17308
17309 /* alloc.c */
17310 _PROTOTYPE( phys_clicks alloc_mem, (phys_clicks clicks)
17311 _PROTOTYPE( void free_mem, (phys_clicks base, phys_clicks clicks)
17312 _PROTOTYPE( void mem_init, (struct memory *chunks, phys_clicks *free) );
17313 #define swap_in() ((void)0)
                            ((void)0)
((void)0)
17314 #define swap inqueue(rmp)
17315
17316 /* break.c */
17317 _PROTOTYPE( int adjust, (struct mproc *rmp,
                     vir_clicks data_clicks, vir_bytes sp)
17318
17319 _PROTOTYPE( int do_brk, (void)
17320 PROTOTYPE( int size_ok, (int file_type, vir_clicks tc, vir_clicks dc,
17321
                        vir_clicks sc, vir_clicks dvir, vir_clicks s_vir) );
17322
17323 /* devio.c */
17324 _PROTOTYPE( int do_dev_io, (void) );
17325 _PROTOTYPE( int do_dev_io, (void) );
17326
17327 /* dmp.c */
17328 _PROTOTYPE( int do_fkey_pressed, (void)
17329
17330 /* exec.c */
17331 _PROTOTYPE( int do_exec, (void)
17332 _PROTOTYPE( void rw_seg, (int rw, int fd, int proc, int seg,
17333
                                            phys_bytes seg_bytes) );
17334 _PROTOTYPE( struct mproc *find_share, (struct mproc *mp_ign, Ino_t ino,
17335
                       Dev_t dev, time_t ctime)
17336
17337 /* forkexit.c */
17338 _PROTOTYPE( int do_fork, (void)
                                                                  );
17339 _PROTOTYPE( int do_pm_exit, (void)
                                                                  );
17340 _PROTOTYPE( int do_waitpid, (void)
                                                                  );
17341 _PROTOTYPE( void pm_exit, (struct mproc *rmp, int exit_status)
17342
17343 /* getset.c */
17344 PROTOTYPE( int do getset, (void)
                                                                  );
```

```
book.txt
 Feb 25, 11 15:18
                                                                                   Page 232/393
        File: Page: 869 servers/pm/proto.h
17345
17346 /* main.c */
17347 _PROTOTYPE( int main, (void)
                                                                                           );
17348
17349 /* misc.c */
17350 _PROTOTYPE( int do_reboot, (void)
                                                                                           );
17351 _PROTOTYPE( int do_getsysinfo, (void) 17352 _PROTOTYPE( int do_getprocnr, (void)
                                                                                           );
                                                                                           );
17353 _PROTOTYPE( int do_svrctl, (void) 17354 _PROTOTYPE( int do_allocmem, (void)
                                                                                           );
                                                                                           );
17355 _PROTOTYPE( int do_freemem, (void)
                                                                                           );
17356 _PROTOTYPE( int do_getsetpriority, (void)
17357
17358 PROTOTYPE( void setreply, (int proc nr, int result)
17359
17360 /* signal.c */
17361 _PROTOTYPE( int do_alarm, (void)
                                                                                           );
17362 _PROTOTYPE( int do_kill, (void)
17363 _PROTOTYPE( int ksig_pending, (void)
                                                                                           );
                                                                                           );
17364 _PROTOTYPE( int do_pause, (void)
17365 _PROTOTYPE( int set_alarm, (int proc_nr, int sec)
17366 _PROTOTYPE( int check_sig, (pid_t proc_id, int signo)
                                                                                           );
                                                                                           );
17367 _PROTOTYPE( void sig_proc, (struct mproc *rmp, int sig_nr)
17368 _PROTOTYPE( int do_sigaction, (void)
                                                                                           );
17369 _PROTOTYPE( int do_sigpending, (void)
                                                                                           );
17370 _PROTOTYPE( int do_sigprocmask, (void)
                                                                                           );
17371 _PROTOTYPE( int do_sigreturn, (void)
                                                                                           );
17372 _PROTOTYPE( int do_sigsuspend, (void)
                                                                                           );
17373 PROTOTYPE( void check pending, (struct mproc *rmp)
                                                                                           );
17374
17375 /* time.c */
17376 _PROTOTYPE( int do_stime, (void)
                                                                                           );
17377 _PROTOTYPE( int do_time, (void) 17378 _PROTOTYPE( int do_times, (void)
                                                                                           );
                                                                                           );
17379 _PROTOTYPE( int do_gettimeofday, (void)
17380
17381 /* timers.c */
17382 _PROTOTYPE( void pm_set_timer, (timer_t *tp, int delta,
                tmr_func_t watchdog, int arg));
17383
17384 _PROTOTYPE( void pm_expire_timers, (clock_t now));
17385 _PROTOTYPE( void pm_cancel_timer, (timer_t *tp));
17386
17387 /* trace.c */
17388 _PROTOTYPE( int do_trace, (void)
                                                                                           );
17389 _PROTOTYPE( void stop_proc, (struct mproc *rmp, int sig_nr)
                                                                                           );
17390
17391 /* utility.c */
| 17392 | __PROTOTYPE( pid_t get_free_pid, (void) | ); | 17393 | __PROTOTYPE( int allowed, (char *name_buf, struct stat *s_buf, int mask) ); |
17394 _PROTOTYPE( int no_sys, (void)
                                                                                           );
17395 _PROTOTYPE( void panic, (char *who, char *mess, int num)
17396 _PROTOTYPE( void tell_fs, (int what, int p1, int p2, int p3)
                                                                                           );
                                                                                           );
17397 _PROTOTYPE( int get_stack_ptr, (int proc_nr, vir_bytes *sp)
                                                                                           );
17398 _PROTOTYPE( int get_mem_map, (int proc_nr, struct mem_map *mem_map)
17399 _PROTOTYPE( char *find_param, (const char *key));
17400 _PROTOTYPE( int proc_from_pid, (pid_t p));
```

```
book.txt
Feb 25, 11 15:18
                                                             Page 233/393
      File: Page: 870 servers/pm/glo.h
servers/pm/glo.h
17500 /* EXTERN should be extern except in table.c */
17501 #ifdef _TABLE
17502 #undef EXTERN
17503 #define EXTERN
17504 #endif
17505
17506 /* Global variables. */
17507 EXTERN struct mproc *mp;
                                /* ptr to 'mproc' slot of current process */
                                /* how many processes are marked as IN_USE */
17508 EXTERN int procs_in_use;
17509 EXTERN char monitor params[128*sizeof(char *)]; /* boot monitor parameters */
17510 EXTERN struct kinfo kinfo;
                                              /* kernel information */
17511
17512 /* The parameters of the call are kept here. */
                             /* the incoming message itself is kept here. */
17513 EXTERN message m_in;
                                /* caller's proc number */
17514 EXTERN int who;
17515 EXTERN int call_nr;
                                /* system call number */
17516
17517 extern _PROTOTYPE (int (*call_vec[]), (void) ); /* system call handlers */
17518 extern char core name[];
                               /* file name where core images are produced */
17519 EXTERN sigset_t core_sset;
                                 /* which signals cause core images */
17520 EXTERN sigset t ign sset;
                                 /* which signals are by default ignored */
servers/pm/mproc.h
17600 /* This table has one slot per process. It contains all the process management
17601 * information for each process. Among other things, it defines the text, data
17602
      * and stack segments, uids and gids, and various flags. The kernel and file
      * systems have tables that are also indexed by process, with the contents
17604
      * of corresponding slots referring to the same process in all three.
17605 */
17606 #include <timers.h>
17607
17608 EXTERN struct mproc {
       struct mem map mp seq[NR LOCAL SEGS]; /* points to text, data, stack */
17609
                             /* storage for status when process exits */
17610
        char mp exitstatus;
                                 /* storage for signal # for killed procs */
17611
        char mp_sigstatus;
       pid_t mp_pid;
17612
                                /* process id */
17613
       pid_t mp_procgrp;
                                /* pid of process group (used for signals) */
17614
        pid_t mp_wpid;
                                 /* pid this process is waiting for */
17615
        int mp_parent;
                                 /* index of parent process */
17616
17617
        /* Child user and system times. Accounting done on child exit. */
        17618
17619
        clock_t mp_child_stime;
                                 /* cumulative sys time of children */
17620
        /* Real and effective uids and gids. */
17621
                        /* process' real uid */
/* process' effective uid */
17622
        uid_t mp_realuid;
17623
        uid_t mp_effuid;
17624
        gid t mp realgid;
                               /* process' real gid */
```

```
book.txt
 Feb 25, 11 15:18
                                                                  Page 234/393
       File: Page: 871 servers/pm/mproc.h
17625
        qid t mp effqid;
                                   /* process' effective gid */
17626
17627
        /* File identification for sharing. */
        ino_t mp_ino;
17628
                                   /* inode number of file */
                                   /* device number of file system */
17629
        dev_t mp_dev;
17630
        time_t mp_ctime;
                                   /* inode changed time */
17631
17632
        /* Signal handling information. */
        17633
        sigset_t mp_catch;
                                   /* 1 means catch the signal, 0 means don't */
17634
                                   /* 1 means transform into notify message */
17635
        sigset_t mp_sig2mess;
17636
        sigset t mp sigmask;
                                   /* signals to be blocked */
17637
                                   /* saved copy of mp_sigmask */
        sigset_t mp_sigmask2;
                                   /* pending signals to be handled */
17638
        sigset_t mp_sigpending;
17639
        struct sigaction mp sigact[ NSIG + 1]; /* as in sigaction(2) */
17640
        vir bytes mp sigreturn;
                                   /* address of C library __sigreturn function */
                                   /* watchdog timer for alarm(2) */
17641
        struct timer mp_timer;
17642
17643
        /* Backwards compatibility for signals. */
17644
        sighandler_t mp_func;
                                   /* all sigs vectored to a single user fcn */
17645
17646
        unsigned mp_flags;
                                   /* flag bits */
17647
        vir_bytes mp_procargs;
                                   /* ptr to proc's initial stack arguments */
        struct mproc *mp_swapq;
                                   /* queue of procs waiting to be swapped in */
17648
17649
        message mp_reply;
                                   /* reply message to be sent to one */
17650
17651
        /* Scheduling priority. */
17652
        signed int mp_nice;
                                   /* nice is PRIO MIN..PRIO MAX, standard 0. */
17653
17654
        char mp name[PROC NAME LEN]; /* process name */
17655
      } mproc[NR PROCS];
17656
17657
      /* Flag values */
                            0x001 /* set when 'mproc' slot in use */
17658
      #define IN USE
                                   /* set by WAIT system call */
17659
      #define WAITING
                            0 \times 002
17660
      #define ZOMBIE
                            0x004 /* set by EXIT, cleared by WAIT */
17661 #define PAUSED
                            0x008 /* set by PAUSE system call */
17662 #define ALARM_ON
                            0x010 /* set when SIGALRM timer started */
                            0x020 /* set if file is separate I & D space */
17663 #define SEPARATE
17664
      #define TRACED
                            0 \times 040
                                   /* set if process is to be traced */
                                   /* set if process stopped for tracing */
17665
      #define STOPPED
                            0 \times 0 \times 0
      #define SIGSUSPENDED
                                   /* set by SIGSUSPEND system call */
17666
                            0x100
17667
      #define REPLY
                            0x200
                                   /* set if a reply message is pending */
                                   /* set if data segment is swapped out */
17668
      #define ONSWAP
                            0x400
17669
      #define SWAPIN
                                   /* set if on the "swap this in" queue */
                            0x800
17670
      #define DONT SWAP
                           0x1000
                                   /* never swap out this process */
                                   /* system process, special privileges */
17671 #define PRIV_PROC
                           0x2000
17672
17673 #define NIL_MPROC ((struct mproc *) 0)
17674
servers/pm/param.h
17700 /* The following names are synonyms for the variables in the input message. */
17701 #define addr
                            m1 p1
17702 #define exec name
                            m1_p1
17703 #define exec_len
                            m1_i1
17704 #define func
```

Feb 2	5, 11 15:18	book.txt	Page 235/393		
File: Page: 872 servers/pm/param.h					
17705	#define grp_id	m1_i1			
17706	#define namelen	m1_i2			
17707	#define pid	m1_i1			
17708	#define procnr	m1_i1			
17709	#define seconds	m1_i1			
17710	#define sig	m6_i1			
17711	#define stack_bytes	m1_i2			
17712	#define stack_ptr	m1_p2			
17713	#define status	m1_i1			
17714	#define usr_id	m1_i1			
17715	#define request	m2_i2			
17716	#define taddr	m2_11			
17717	#define data	m2_12			
17718 17719	#define sig_nr	m1_i2			
17720	#define sig_nsa #define sig_osa	m1_p1 m1_p2			
17721	#define sig_ret	m1_p3			
17722	#define sig_set	m2 11			
17723	#define sig_how	m2_i1			
17724	#define sig_flags	m2_i2			
17725	#define sig_context	m2 p1			
17726	#define info_what	m1 i1			
17727	#define info_where	m1_p1			
17728	#define reboot_flag	m1_i1			
17729	#define reboot_code	m1_p1			
17730	#define reboot_strlen	m1_i2			
17731	#define svrctl_req	m2_i1			
17732	#define svrctl_argp	m2_p1			
17733	#define stime	m2_11			
17734	#define memsize	m4_11			
17735	#define membase	m4_12			
17736 17737	/* The fellowing names	and armonyma for the remichles in a	ronly moggage */		
17738	#define reply_res	are synonyms for the variables in a m_type	repry message. "/		
17739	#define reply_res2	m2 i1			
17740	#define reply_ptr	m2_p1			
17741	#define reply_mask	m2_11			
17742	#define reply_trace	m2 12			
17743	#define reply_time	m2 11			
17744	#define reply_utime	m2 12			
17745	#define reply_t1	m4_11			
17746	#define reply_t2	m4_12			
17747	#define reply_t3	m4_13			
17748	#define reply_t4	m4_14			
17749	#define reply_t5	m4_15			
17750					
17751		are used to inform the FS about certa	ain events. */		
17752	#define tell_fs_arg1				
17753	#define tell_fs_arg2	m1_i2			
17754	#define tell_fs_arg3	m1_i3			
17755					

```
book.txt
Feb 25, 11 15:18
                                                                Page 236/393
      File: Page: 873 servers/pm/table.c
servers/pm/table.c
17800 /* This file contains the table used to map system call numbers onto the
17801 * routines that perform them.
17802
17803
17804
      #define _TABLE
17805
17806 #include "pm.h"
17807 #include <minix/callnr.h>
17808 #include <signal.h>
17809 #include "mproc.h"
17810 #include "param.h"
17811
17812 /* Miscellaneous */
17813 char core_name[] = "core";
                                  /* file name where core images are produced */
17814
17815 _PROTOTYPE (int (*call_vec[NCALLS]), (void) ) = {
17816
                           /* 0 = unused */
             no_sys,
                           /* 1 = exit
17817
             do_pm_exit,
                           /* 2 = fork
17818
             do_fork,
                           /* 3 = read
17819
             no_sys,
                           /* 4 = write
17820
             no_sys,
17821
                           /* 5 = open
             no_sys,
                           /* 6 = close
17822
             no_sys,
                           /* 7 = wait
             do_waitpid,
17823
                           /* 8 = creat
17824
             no sys,
                           /* 9 = link
17825
             no_sys,
                           /* 10 = unlink */
17826
             no_sys,
17827
             do_waitpid,
                           /* 11 = waitpid */
                           /* 12 = chdir
17828
             no_sys,
                           /* 13 = time
17829
             do_time,
17830
             no_sys,
                           /* 14 = mknod
17831
                           /* 15 = chmod
             no_sys,
                           /* 16 = chown
17832
             no_sys,
17833
             do_brk,
                           /* 17 = break */
                           /* 18 = stat
17834
             no_sys,
                           /* 19 = lseek
17835
             no_sys,
17836
                           /* 20 = getpid */
             do getset,
                           /* 21 = mount */
17837
             no_sys,
                           /* 22 = umount
17838
             no_sys,
17839
                           /* 23 = setuid */
             do getset,
                           /* 24 = getuid */
17840
             do_getset,
                           /* 25 = stime */
17841
             do_stime,
17842
             do_trace,
                           /* 26 = ptrace */
17843
             do_alarm,
                           /* 27 = alarm */
                           /* 28 = fstat
17844
             no_sys,
17845
             do_pause,
                           /* 29 = pause
                           /* 30 = utime
17846
             no_sys,
                           /* 31 = (stty) */
17847
             no_sys,
17848
                           /* 32 = (gtty) */
             no_sys,
                           /* 33 = access */
17849
             no_sys,
                           /* 34 = (nice) */
17850
             no_sys,
17851
                           /* 35 = (ftime) */
             no_sys,
                           /* 35 = \-- 
/* 36 = sync */
17852
             no_sys,
                           /* 37 = kill
17853
             do_kill,
17854
             no sys,
                           /* 38 = rename */
```

```
book.txt
Feb 25, 11 15:18
                                                                    Page 237/393
      File: Page: 874 servers/pm/table.c
                             /* 39 = mkdir
17855
              no_sys,
                             /* 40 = rmdir
17856
              no_sys,
17857
              no_sys,
                             /* 41 = dup
                             /* 42 = pipe
17858
              no_sys,
                             /* 43 = times */
17859
              do_times,
17860
              no_sys,
                             /* 44 = (prof) */
17861
              no_sys,
                             /* 45 = unused */
                             /* 46 = setgid */
17862
              do_getset,
              do_getset,
                             /* 47 = getgid */
17863
17864
                             /* 48 = (signal)*/
              no_sys,
                             /* 49 = unused */
17865
              no_sys,
17866
              no sys,
                             /* 50 = unused */
17867
                             /* 51 = (acct) */
              no_sys,
                             /* 52 = (phys) */
17868
              no_sys,
                             /* 53 = (lock) */
17869
              no sys,
17870
                             /* 54 = ioctl */
              no_sys,
17871
              no_sys,
                             /* 55 = fcntl */
              no_sys,
                             /* 56 = (mpx) */
17872
17873
                             /* 57 = unused */
              no_sys,
                             /* 58 = unused */
17874
              no_sys,
17875
              do_exec,
                             /* 59 = execve */
17876
              no_sys,
                             /* 60 = umask */
                             /* 61 = chroot */
17877
              no_sys,
                             /* 62 = setsid */
17878
              do getset,
17879
                             /* 63 = getpgrp */
              do_getset,
17880
17881
              no sys,
                             /* 64 = unused */
17882
                             /* 65 = UNPAUSE */
              no_sys,
                             /* 66 = unused */
17883
              no_sys,
                             /* 67 = REVIVE */
17884
              no sys,
17885
                             /* 68 = TASK REPLY */
              no_sys,
                             /* 69 = unused */
17886
              no_sys,
17887
              no_sys,
                             /* 70 = unused */
17888
              do_sigaction,
                            /* 71 = sigaction
              do_sigsuspend, /* 72 = sigsuspend */
17889
              do_sigpending, /* 73 = sigpending */
17890
              do_sigprocmask, /* 74 = sigprocmask */
17891
17892
              do_sigreturn, /* 75 = sigreturn */
17893
              do reboot,
                             /* 76 = reboot */
17894
              do_svrctl,
                             /* 77 = svrctl */
17895
17896
              no sys,
                             /* 78 = unused */
              do_getsysinfo, /* 79 = getsysinfo */
17897
              do_getprocnr, /* 80 = getprocnr */
17898
17899
                             /* 81 = unused */
              no sys,
17900
              no_sys,
                             /* 82 = fstatfs */
              do_allocmem, /* 83 = memalloc */
17901
17902
              do_freemem,
                             /* 84 = memfree */
17903
                             /* 85 = select */
              no_sys,
                             /* 86 = fchdir */
17904
              no_sys,
17905
              no_sys,
                             /* 87 = fsync */
              17906
17907
              do_getsetpriority,
17908
                             /* 90 = gettimeofday */
              do_time,
17909
      /* This should not fail with "array size is negative": */
17910
17911 extern int dummy[sizeof(call vec) == NCALLS * sizeof(call vec[0]) ? 1 : -1];
```

```
book.txt
 Feb 25, 11 15:18
                                                               Page 238/393
      File: Page: 875 servers/pm/main.c
servers/pm/main.c
18000 /* This file contains the main program of the process manager and some related
18001 * procedures. When MINIX starts up, the kernel runs for a little while,
      * initializing itself and its tasks, and then it runs PM and FS. Both PM
18002
       * and FS initialize themselves as far as they can. PM asks the kernel for
       * all free memory and starts serving requests.
18004
18005
18006
      * The entry points into this file are:
       * main:
                     starts PM running
18007
18008
          setreply: set the reply to be sent to process making an PM system call
18009 */
18010
18011 #include "pm.h"
18012 #include <minix/keymap.h>
18013 #include <minix/callnr.h>
18014 #include <minix/com.h>
18015 #include <signal.h>
18016 #include <stdlib.h>
18017 #include <fcntl.h>
18018 #include <sys/resource.h>
18019 #include <string.h>
18020 #include "mproc.h"
18021 #include "param.h"
18022
18023 #include "../../kernel/const.h"
18024 #include "../../kernel/config.h"
18025 #include "../../kernel/type.h"
18026 #include "../../kernel/proc.h"
18027
18028 FORWARD _PROTOTYPE( void get_work, (void)
                                                                     );
18029 FORWARD _PROTOTYPE( void pm_init, (void)
                                                                     );
18030 FORWARD _PROTOTYPE( int get_nice_value, (int queue)
                                                                     );
18031 FORWARD PROTOTYPE( void get_mem_chunks, (struct memory *mem_chunks)
                                                                    );
18032 FORWARD _PROTOTYPE( void patch_mem_chunks, (struct memory *mem_chunks,
18033
             struct mem_map *map_ptr)
18034
18035
      #define click_to_round_k(n) \
             ((unsigned) ((((unsigned long) (n) << CLICK SHIFT) + 512) / 1024))
18036
18037
18038
       * main
18039
18040
       18041
      PUBLIC int main()
18042
18043 /* Main routine of the process manager. */
18044
       int result, s, proc_nr;
18045
        struct mproc *rmp;
18046
        sigset_t sigset;
18047
18048
        pm_init();
                                  /* initialize process manager tables */
18049
        /* This is PM's main loop- get work and do it, forever and forever. */
18050
        while (TRUE) {
18051
18052
             get work();
                                  /* wait for an PM system call */
18053
18054
             /* Check for system notifications first. Special cases. */
```

```
book.txt
Feb 25, 11 15:18
                                                                    Page 239/393
      File: Page: 876 servers/pm/main.c
18055
              if (call_nr == SYN_ALARM) {
18056
                     pm_expire_timers(m_in.NOTIFY_TIMESTAMP);
18057
                     result = SUSPEND;
                                                    /* don't reply */
18058
              } else if (call_nr == SYS_SIG)
                                                    /* signals pending */
18059
                      sigset = m_in.NOTIFY_ARG;
18060
                      if (sigismember(&sigset, SIGKSIG)) (void) ksig_pending();
                                                    /* don't reply */
18061
                      result = SUSPEND;
18062
18063
              /* Else, if the system call number is valid, perform the call. */
18064
              else if ((unsigned) call_nr >= NCALLS) {
18065
                      result = ENOSYS;
18066
              } else
18067
                      result = (*call_vec[call_nr])();
18068
18069
18070
              /* Send the results back to the user to indicate completion. */
18071
              if (result != SUSPEND) setreply(who, result);
18072
18073
                                    /* maybe a process can be swapped in? */
              swap_in();
18074
18075
              /* Send out all pending reply messages, including the answer to
18076
               * the call just made above. The processes must not be swapped out.
18077
18078
              for (proc_nr=0, rmp=mproc; proc_nr < NR_PROCS; proc_nr++, rmp++) {
18079
                      /* In the meantime, the process may have been killed by a
                       * signal (e.g. if a lethal pending signal was unblocked)
18080
                      * without the PM realizing it. If the slot is no longer in
18081
18082
                       * use or just a zombie, don't try to reply.
18083
                      if ((rmp->mp_flags & (REPLY | ONSWAP | IN_USE | ZOMBIE)) ==
18084
18085
                         (REPLY | IN_USE)) {
18086
                             if ((s=send(proc_nr, &rmp->mp_reply)) != OK) {
18087
                                    panic(__FILE__, "PM can't reply to", proc_nr);
18088
18089
                             rmp->mp_flags &= ~REPLY;
18090
18091
18092
18093
        return(OK);
18094
      18097
                                   get_work
18098
       *-----*/
18099
      PRIVATE void get work()
18100
18101
      /* Wait for the next message and extract useful information from it. */
        if (receive(ANY, &m_in) != OK) panic(__FILE__, "PM receive error", NO_NUM);
18102
18103
                                    /* who sent the message */
        who = m in.m source;
18104
        call_nr = m_in.m_type;
                                    /* system call number */
18105
18106
        /* Process slot of caller. Misuse PM's own process slot if the kernel is
18107
         * calling. This can happen in case of synchronous alarms (CLOCK) or or
         * event like pending kernel signals (SYSTEM).
18108
18109
18110
        mp = &mproc[who < 0 ? PM_PROC_NR : who];</pre>
18111 }
```

```
book.txt
Feb 25, 11 15:18
                                                                  Page 240/393
      File: Page: 877 servers/pm/main.c
18113
      18114
                                   setreply
      *-----*
18116 PUBLIC void setreply(proc_nr, result)
18117 int proc_nr;
                                   /* process to reply to */
18118 int result;
                                   /* result of call (usually OK or error #) */
18119
18120 /* Fill in a reply message to be sent later to a user process. System calls
       * may occasionally fill in other fields, this is only for the main return
18121
       * value, and for setting the "must send reply" flag.
18122
18123
18124
        register struct mproc *rmp = &mproc[proc nr];
18125
18126
        rmp->mp_reply.reply_res = result;
18127
        rmp->mp_flags |= REPLY;
                                   /* reply pending */
18128
18129
        if (rmp->mp_flags & ONSWAP)
18130
             swap_inqueue(rmp);
                                   /* must swap this process back in */
18131
18133
      18134
                                   pm init
18135
       18136 PRIVATE void pm init()
18137
18138 /* Initialize the process manager.
      * Memory use info is collected from the boot monitor, the kernel, and
18139
18140
       * all processes compiled into the system image. Initially this information
       * is put into an array mem_chunks. Elements of mem_chunks are struct memory,
18141
       * and hold base, size pairs in units of clicks. This array is small, there
       * should be no more than 8 chunks. After the array of chunks has been built
18143
18144
       * the contents are used to initialize the hole list. Space for the hole list
18145
       * is reserved as an array with twice as many elements as the maximum number
       * of processes allowed. It is managed as a linked list, and elements of the
18146
18147
       * array are struct hole, which, in addition to storage for a base and size in
18148
       * click units also contain space for a link, a pointer to another element.
18149 */
18150
        int s;
18151
        static struct boot_image image[NR_BOOT_PROCS];
        register struct boot_image *ip;
static char core_sigs[] = { SIGQUIT, SIGILL, SIGTRAP, SIGABRT,
18152
18153
                            SIGEMT, SIGFPE, SIGUSR1, SIGSEGV, SIGUSR2 };
18154
18155
        static char ign_sigs[] = { SIGCHLD };
18156
        register struct mproc *rmp;
        register char *sig ptr;
18157
18158
        phys_clicks total_clicks, minix_clicks, free_clicks;
18159
        message mess;
18160
        struct mem_map mem_map[NR_LOCAL_SEGS];
18161
        struct memory mem_chunks[NR_MEMS];
18162
18163
        /* Initialize process table, including timers. */
        for (rmp=&mproc[0]; rmp<&mproc[NR_PROCS]; rmp++) {</pre>
18164
18165
              tmr_inittimer(&rmp->mp_timer);
18166
18167
18168
        /* Build the set of signals which cause core dumps, and the set of signals
18169
         * that are by default ignored.
18170
18171
        sigemptyset(&core_sset);
18172
        for (sig ptr = core sigs; sig ptr < core sigs+sizeof(core sigs); sig ptr++)
```

```
book.txt
Feb 25, 11 15:18
                                                                          Page 241/393
       File: Page: 878 servers/pm/main.c
18173
               sigaddset(&core_sset, *sig_ptr);
18174
         sigemptyset(&ign_sset);
18175
         for (sig_ptr = ign_sigs; sig_ptr < ign_sigs+sizeof(ign_sigs); sig_ptr++)</pre>
18176
               sigaddset(&ign_sset, *sig_ptr);
18177
18178
         /* Obtain a copy of the boot monitor parameters and the kernel info struct.
          * Parse the list of free memory chunks. This list is what the boot monitor
18179
18180
          * reported, but it must be corrected for the kernel and system processes.
18181
18182
         if ((s=sys_getmonparams(monitor_params, sizeof(monitor_params))) != OK)
18183
             panic(__FILE__, "get monitor params failed",s);
18184
         get mem chunks(mem chunks);
18185
         if ((s=sys_getkinfo(&kinfo)) != OK)
18186
             panic(__FILE__, "get kernel info failed",s);
18187
18188
         ^{\prime *} Get the memory map of the kernel to see how much memory it uses. ^{*}/
18189
         if ((s=get_mem_map(SYSTASK, mem_map)) != OK)
18190
               panic(__FILE__, "couldn't get memory map of SYSTASK",s);
18191
         minix_clicks = (mem_map[S].mem_phys+mem_map[S].mem_len)-mem_map[T].mem_phys;
18192
         patch_mem_chunks(mem_chunks, mem_map);
18193
18194
         /* Initialize PM's process table. Request a copy of the system image table
18195
          * that is defined at the kernel level to see which slots to fill in.
18196
18197
         if (OK != (s=sys_getimage(image)))
18198
               panic(__FILE__, "couldn't get image table: %d\n", s);
         procs in use = 0;
                                                       /* start populating table */
18199
18200
         printf("Building process table: ");
                                                         /* show what's happening */
         for (ip = &image[0]; ip < &image[NR_BOOT_PROCS]; ip++) {
18201
18202
               if (ip->proc nr >= 0) {
                                                        /* task have negative nrs */
18203
                       procs in use += 1;
                                                        /* found user process */
18204
18205
                        /* Set process details found in the image table. */
18206
                       rmp = &mproc[ip->proc_nr];
18207
                       strncpy(rmp->mp_name, ip->proc_name, PROC_NAME_LEN);
18208
                       rmp->mp_parent = RS_PROC_NR;
                       rmp->mp_nice = get_nice_value(ip->priority);
if (ip->proc_nr == INIT_PROC_NR) {    /* us
18209
18210
                                                             /* user process */
                               rmp->mp_pid = INIT_PID;
18211
18212
                                rmp->mp_flags |= IN_USE;
18213
                                sigemptyset(&rmp->mp_ignore);
18214
18215
                       else {
                                                                 /* system process */
18216
                                rmp->mp_pid = get_free_pid();
                               rmp->mp flags |= IN USE | DONT SWAP | PRIV PROC;
18217
18218
                                sigfillset(&rmp->mp_ignore);
18219
18220
                       sigemptyset(&rmp->mp_sigmask);
18221
                       sigemptyset(&rmp->mp_catch);
18222
                       sigemptyset(&rmp->mp_sig2mess);
18223
18224
                        /* Get memory map for this process from the kernel. */
                       if ((s=get_mem_map(ip->proc_nr, rmp->mp_seg)) != OK)
18225
                               panic(__FILE__,"couldn't get process entry",s);
18226
18227
                       if (rmp->mp_seg[T].mem_len != 0) rmp->mp_flags |= SEPARATE;
18228
                       minix_clicks += rmp->mp_seg[S].mem_phys +
                               rmp->mp_seg[S].mem_len - rmp->mp_seg[T].mem_phys;
18229
18230
                       patch_mem_chunks(mem_chunks, rmp->mp_seg);
18231
18232
                       /* Tell FS about this system process. */
```

```
book.txt
Feb 25, 11 15:18
                                                                  Page 242/393
      File: Page: 879 servers/pm/main.c
18233
                     mess.PR_PROC_NR = ip->proc_nr;
18234
                     mess.PR_PID = rmp->mp_pid;
                     if (OK != (s=send(FS_PROC_NR, &mess)))
18235
18236
                            panic(__FILE__, "can't sync up with FS", s);
18237
                     printf(" %s", ip->proc_name); /* display process name */
18238
18239
        printf(".\n");
                                                  /* last process done */
18240
18241
18242
        /* Override some details. PM is somewhat special. */
        mproc[PM_PROC_NR].mp_pid = PM_PID;
                                                  /* magically override pid */
18243
18244
        mproc[PM_PROC_NR].mp_parent = PM_PROC_NR;
                                                  /* PM doesn't have parent */
18245
18246
        /* Tell FS that no more system processes follow and synchronize. */
18247
        mess.PR PROC NR = NONE;
18248
        if (sendrec(FS_PROC_NR, &mess) != OK | mess.m_type != OK)
18249
             panic(__FILE__, "can't sync up with FS", NO_NUM);
18250
18251
        /* Initialize tables to all physical memory and print memory information. */
18252
        printf("Physical memory: ");
18253
        mem_init(mem_chunks, &free_clicks);
        total_clicks = minix_clicks + free_clicks;
18254
18255
        printf(" total %u KB,", click_to_round_k(total_clicks));
        printf(" system %u KB,", click_to_round_k(minix_clicks));
18256
18257
        printf(" free %u KB.\n", click_to_round_k(free_clicks));
18258
18261
                                   get_nice_value
18262
18263 PRIVATE int get_nice_value(queue)
18264
     int queue;
                                           /* store mem chunks here */
18265
18266
       * Processes in the boot image have a priority assigned. The PM doesn't know
       * about priorities, but uses 'nice' values instead. The priority is between
18267
18268
       * MIN_USER_Q and MAX_USER_Q. We have to scale between PRIO_MIN and PRIO_MAX.
18269
18270
        int nice_val = (queue - USER_Q) * (PRIO_MAX-PRIO_MIN+1) /
18271
            (MIN_USER_Q-MAX_USER_Q+1);
        if (nice_val > PRIO_MAX) nice_val = PRIO_MAX; /* shouldn't happen */
18272
        if (nice_val < PRIO_MIN) nice_val = PRIO_MIN; /* shouldn't happen */
18273
18274
        return nice val;
18275
18277 /*=========*
18278
                                   get_mem_chunks
18279
      *_____*/
18280 PRIVATE void get_mem_chunks(mem_chunks)
18281 struct memory *mem_chunks;
                                                  /* store mem chunks here */
18282
18283 /* Initialize the free memory list from the 'memory' boot variable. Translate
18284
       * the byte offsets and sizes in this list to clicks, properly truncated. Also
       * make sure that we don't exceed the maximum address space of the 286 or the
18285
18286
       * 8086, i.e. when running in 16-bit protected mode or real mode.
18287
18288
        long base, size, limit;
        char *s, *end;
18289
                                          /* use to parse boot variable */
        int i, done = 0;
18290
18291
        struct memory *memp;
18292
```

```
Feb 25, 11 15:18
                                  book.txt
                                                                Page 243/393
      File: Page: 880 servers/pm/main.c
18293
        /* Initialize everything to zero. */
18294
        for (i = 0; i < NR_MEMS; i++) {
18295
             memp = &mem_chunks[i];
                                         /* next mem chunk is stored here */
18296
             memp->base = memp->size = 0;
18297
18298
        18299
18300
         * in boot.s. The format is "b0: s0,b1: s1,b2: s2", where b0: s0 is low mem,
18301
         * b1: s1 is mem between 1M and 16M, b2: s2 is mem above 16M. Pairs b1: s1
18302
18303
         * and b2: s2 are combined if the memory is adjacent.
18304
18305
                                         /* get memory boot variable */
        s = find param("memory");
18306
        for (i = 0; i < NR_MEMS && !done; i++) {
18307
             18308
             base = size = 0;
                                         /* initialize next base: size pair */
18309
             if (*s != 0) {
                                         /* get fresh data, unless at end */
18310
18311
                 /* Read fresh base and expect colon as next char. */
18312
                 base = strtoul(s, &end, 0x10);
                                                      /* get number */
18313
                 if (end != s && *end == ': ') s = ++end;
                                                        /* skip ': ' */
18314
                 else *s=0;
                                         /* terminate, should not happen */
18315
18316
                 /* Read fresh size and expect comma or assume end. */
18317
                 size = strtoul(s, &end, 0x10);
                                                       /* get number */
                 if (end != s && *end == ',') s = ++end;
18318
                                                       /* skip ',' */
18319
                 else done = 1;
18320
             limit = base + size;
18321
             base = (base + CLICK SIZE-1) & ~(long)(CLICK SIZE-1);
18322
18323
             limit &= ~(long)(CLICK SIZE-1);
18324
             if (limit <= base) continue;
18325
             memp->base = base >> CLICK_SHIFT;
18326
             memp->size = (limit - base) >> CLICK_SHIFT;
18327
18328 }
18330 /*============*
18331 *
                                patch mem chunks
      *----*
18332
18333 PRIVATE void patch_mem_chunks(mem_chunks, map_ptr)
18334 struct memory *mem chunks;
                                                /* store mem chunks here */
18335 struct mem_map *map_ptr;
                                                /* memory to remove */
18336
18337 /* Remove server memory from the free memory list. The boot monitor
18338
      * promises to put processes at the start of memory chunks. The
18339
       * tasks all use same base address, so only the first task changes
18340
       * the memory lists. The servers and init have their own memory
18341
       * spaces and their memory will be removed from the list.
18342
18343
       struct memory *memp;
18344
        for (memp = mem_chunks; memp < &mem_chunks[NR_MEMS]; memp++) {</pre>
             if (memp->base == map_ptr[T].mem_phys) {
18345
                    memp->base += map_ptr[T].mem_len + map_ptr[D].mem_len;
18346
                    memp->size -= map_ptr[T].mem_len + map_ptr[D].mem_len;
18347
18348
18349
18350 }
```

```
Feb 25, 11 15:18
                                    book.txt
                                                                   Page 244/393
      File: Page: 881 servers/pm/forkexit.c
servers/pm/forkexit.c
18400 /* This file deals with creating processes (via FORK) and deleting them (via
18401 * EXIT/WAIT). When a process forks, a new slot in the 'mproc' table is
       * allocated for it, and a copy of the parent's core image is made for the
18402
       * child. Then the kernel and file system are informed. A process is removed * from the 'mproc' table when two events have occurred: (1) it has exited or
18403
18404
       * been killed by a signal, and (2) the parent has done a WAIT. If the process
18405
18406
       * exits first, it continues to occupy a slot until the parent does a WAIT.
18407
       * The entry points into this file are:
18408
18409
       * do_fork: perform the FORK system call
18410
           do_pm_exit: perform the EXIT system call (by calling pm_exit())
18411
          pm_exit:
                       actually do the exiting
18412 *
           do_wait:
                      perform the WAITPID or WAIT system call
18413 */
18414
18415 #include "pm.h"
18416 #include <svs/wait.h>
18417 #include <minix/callnr.h>
18418 #include <minix/com.h>
18419 #include <signal.h>
18420 #include "mproc.h"
18421 #include "param.h"
18422
      #define LAST_FEW
                                2 /* last few slots reserved for superuser */
18423
18424
18425 FORWARD _PROTOTYPE (void cleanup, (register struct mproc *child) );
18426
18427 /*=========*
18428
                                   do_fork
       *----*
18429
18430 PUBLIC int do_fork()
18431
18432
      ^{\prime *} The process pointed to by 'mp' has forked. Create a child process. */
        register struct mproc *rmp; /* pointer to parent */
register struct mproc *rmc; /* pointer to child */
18433
18434
18435
        int child nr, s;
        phys clicks prog clicks, child base;
18436
18437
        phys_bytes prog_bytes, parent_abs, child_abs; /* Intel only */
18438
        pid_t new_pid;
18439
18440
       /* If tables might fill up during FORK, don't even start since recovery half
18441
        * way through is such a nuisance.
18442
18443
        rmp = mp;
18444
        if ((procs_in_use == NR_PROCS) |
18445
                     (procs_in_use >= NR_PROCS-LAST_FEW && rmp->mp_effuid != 0))
18446
              printf("PM: warning, process table is full!\n");
18447
18448
              return(EAGAIN);
18449
18450
18451
        /* Determine how much memory to allocate. Only the data and stack need to
18452
         * be copied, because the text segment is either shared or of zero length.
18453
18454
        prog clicks = (phys clicks) rmp->mp seg[S].mem len;
```

```
book.txt
Feb 25, 11 15:18
                                                                      Page 245/393
      File: Page: 882 servers/pm/forkexit.c
18455
        prog_clicks += (rmp->mp_seg[S].mem_vir - rmp->mp_seg[D].mem_vir);
        prog_bytes = (phys_bytes) prog_clicks << CLICK_SHIFT;</pre>
18456
18457
         if ( (child_base = alloc_mem(prog_clicks)) == NO_MEM) return(ENOMEM);
18458
         /* Create a copy of the parent's core image for the child. */
18459
18460
         child_abs = (phys_bytes) child_base << CLICK_SHIFT;</pre>
18461
        parent_abs = (phys_bytes) rmp->mp_seg[D].mem_phys << CLICK_SHIFT;
        s = sys_abscopy(parent_abs, child_abs, prog_bytes);
18462
        if (s < 0) panic( FILE , "do fork can't copy", s);
18463
18464
         /\!\!\!\!\!\!^{\star} Find a slot in 'mproc' for the child process. A slot must exist. \!\!\!\!^{\star}/\!\!\!\!
18465
18466
        for (rmc = &mproc[0]; rmc < &mproc[NR PROCS]; rmc++)
              if ((rmc->mp_flags & IN_USE) == 0) break;
18467
18468
         /* Set up the child and its memory map; copy its 'mproc' slot from parent. */
18469
18470
         child nr = (int)(rmc - mproc);
                                            /* slot number of the child */
18471
        procs_in_use++;
18472
         *rmc = *rmp;
                                     /* copy parent's process slot to child's */
                                             /* record child's parent */
18473
        rmc->mp_parent = who;
        /* inherit only these flags */
18474
18475
        rmc->mp_flags &= (IN_USE | SEPARATE | PRIV_PROC | DONT_SWAP);
18476
        rmc->mp_child_utime = 0;
                                             /* reset administration */
18477
                                             /* reset administration */
        rmc->mp_child_stime = 0;
18478
18479
        /\ast A separate I&D child keeps the parents text segment. The data and stack
18480
         * segments must refer to the new copy.
18481
18482
        if (!(rmc->mp_flags & SEPARATE)) rmc->mp_seg[T].mem_phys = child_base;
        rmc->mp_seg[D].mem_phys = child_base;
18483
        rmc->mp_seg[S].mem_phys = rmc->mp_seg[D].mem_phys +
18484
18485
                             (rmp->mp_seg[S].mem_vir - rmp->mp_seg[D].mem_vir);
18486
         rmc->mp_exitstatus = 0;
18487
        rmc->mp_sigstatus = 0;
18488
18489
         /* Find a free pid for the child and put it in the table. */
18490
        new_pid = get_free_pid();
18491
        rmc->mp_pid = new_pid;
                                     /* assign pid to child */
18492
18493
         /* Tell kernel and file system about the (now successful) FORK. */
18494
         sys_fork(who, child_nr);
18495
         tell fs(FORK, who, child nr, rmc->mp pid);
18496
18497
         /* Report child's memory map to kernel. */
18498
         sys_newmap(child_nr, rmc->mp_seg);
18499
18500
        /* Reply to child to wake it up. */
18501
        setreply(child_nr, 0);
                                             /* only parent gets details */
18502
        rmp->mp_reply.procnr = child_nr;
                                             /* child's process number */
18503
        return(new_pid);
                                             /* child's pid */
18504
18506 /*===========*
18507
                                    do_pm_exit
18508
      18509 PUBLIC int do_pm_exit()
18510
18511 /* Perform the exit(status) system call. The real work is done by pm exit(),
       * which is also called when a process is killed by a signal.
18512
18513
18514
       pm exit(mp, m in.status);
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 246/393
      File: Page: 883 servers/pm/forkexit.c
18515
        return(SUSPEND);
                                     /* can't communicate from beyond the grave */
18516
18518 /*========*
18519 *
18521 PUBLIC void pm_exit(rmp, exit_status)
18522 register struct mproc *rmp; /* pointer to the process to be terminated */
18523 int exit status;
                                    /* the process' exit status (for parent) */
18524

angle * A process is done. Release most of the process' possessions. If its
18525
18526
       * parent is waiting, release the rest, else keep the process slot and
       * become a zombie.
18527
18528
18529
        register int proc nr;
18530
        int parent waiting, right child;
18531
        pid_t pidarg, procgrp;
18532
        struct mproc *p_mp;
18533
        clock_t t[5];
18534
18535
        proc_nr = (int) (rmp - mproc);
                                           /* get process slot number */
18536
18537
        /* Remember a session leader's process group. */
18538
        procgrp = (rmp->mp_pid == mp->mp_procgrp) ? mp->mp_procgrp : 0;
18539
         /* If the exited process has a timer pending, kill it. */
18540
18541
        if (rmp->mp flags & ALARM ON) set alarm(proc nr, (unsigned) 0);
18542
        /* Do accounting: fetch usage times and accumulate at parent. */
18543
18544
        sys times(proc nr, t);
        p_mp = &mproc[rmp->mp_parent];
18545
                                                           /* process' parent */
        p_mp->mp_child_utime += t[0] + rmp->mp_child_utime; /* add user time */
18546
18547
        p_mp->mp_child_stime += t[1] + rmp->mp_child_stime; /* add system time */
18548
18549
        /* Tell the kernel and FS that the process is no longer runnable. */
18550
        tell_fs(EXIT, proc_nr, 0, 0); /* file system can free the proc slot */
        sys_exit(proc_nr);
18551
18552
18553
        /* Pending reply messages for the dead process cannot be delivered. */
        rmp->mp_flags &= ~REPLY;
18554
18555
18556
         /* Release the memory occupied by the child. */
18557
        if (find_share(rmp, rmp->mp_ino, rmp->mp_dev, rmp->mp_ctime) == NULL) {
18558
              /* No other process shares the text segment, so free it. */
18559
              free mem(rmp->mp seq[T].mem phys, rmp->mp seq[T].mem len);
18560
18561
         /* Free the data and stack segments. */
18562
        free_mem(rmp->mp_seg[D].mem_phys,
            rmp->mp_seg[S].mem_vir
18563
18564
              + rmp->mp_seg[S].mem_len - rmp->mp_seg[D].mem_vir);
18565
        /st The process slot can only be freed if the parent has done a WAIT. st/
18566
18567
        rmp->mp_exitstatus = (char) exit_status;
18568
18569
        pidarg = p_mp->mp_wpid;
                                            /* who's being waited for? */
18570
        parent_waiting = p_mp->mp_flags & WAITING;
                                           /* child meets one of the 3 tests? */
18571
        right child =
              (pidarg == -1 || pidarg == rmp->mp_pid || -pidarg == rmp->mp_procgrp);
18572
18573
18574
        if (parent waiting && right child) {
```

```
book.txt
Feb 25, 11 15:18
                                                                  Page 247/393
      File: Page: 884 servers/pm/forkexit.c
18575
             cleanup(rmp);
                                           /* tell parent and release child slot */
18576
         else {
18577
             rmp->mp_flags = IN_USE ZOMBIE; /* parent not waiting, zombify child */
18578
             sig_proc(p_mp, SIGCHLD);
                                          /* send parent a "child died" signal */
18579
18580
18581
        /* If the process has children, disinherit them. INIT is the new parent. */
18582
        for (rmp = &mproc[0]; rmp < &mproc[NR_PROCS]; rmp++) {
             if (rmp->mp_flags & IN_USE && rmp->mp_parent == proc_nr) {
18583
                     /* 'rmp' now points to a child to be disinherited. */
18584
18585
                     rmp->mp parent = INIT PROC NR;
18586
                     parent waiting = mproc[INIT PROC NR].mp flags & WAITING;
                     if (parent_waiting && (rmp->mp_flags & ZOMBIE)) cleanup(rmp);
18587
18588
18589
18590
18591
        /* Send a hangup to the process' process group if it was a session leader. */
        if (procgrp != 0) check_sig(-procgrp, SIGHUP);
18592
18593
18595
      18596
                                  do waitpid
18597
      *----*
18598 PUBLIC int do waitpid()
18599
18600 /* A process wants to wait for a child to terminate. If a child is already
      * waiting, go clean it up and let this WAIT call terminate. Otherwise,
18602
       * really wait.
       * A process calling WAIT never gets a reply in the usual way at the end
18603
       * of the main loop (unless WNOHANG is set or no qualifying child exists).
18605
       * If a child has already exited, the routine cleanup() sends the reply
18606
       * to awaken the caller.
18607
       * Both WAIT and WAITPID are handled by this code.
18608
18609
        register struct mproc *rp;
18610
        int pidarg, options, children;
18611
18612
        /* Set internal variables, depending on whether this is WAIT or WAITPID. */
        18613
18614
18615
        if (pidarg == 0) pidarg = -mp->mp_procgrp; /* pidarg < 0 ==> proc grp */
18616
18617
        /* Is there a child waiting to be collected? At this point, pidarg != 0:
18618
             pidarg > 0 means pidarg is pid of a specific process to wait for
             pidarg == -1 means wait for any child
18619
18620
             pidarg < -1 means wait for any child whose process group = -pidarg
18621
18622
18623
        for (rp = &mproc[0]; rp < &mproc[NR_PROCS]; rp++) {</pre>
18624
             if ((rp->mp_flags & IN_USE) && rp->mp_parent == who) {
18625
                     /* The value of pidarg determines which children qualify. */
18626
                     if (pidarg > 0 && pidarg != rp->mp_pid) continue;
                     if (pidarg < -1 && -pidarg != rp->mp_procgrp) continue;
18627
18628
18629
                     children++;
                                           /* this child is acceptable */
                     if (rp->mp_flags & ZOMBIE) {
18630
                            /* This child meets the pid test and has exited. */
18631
                                          /* this child has already exited */
18632
                            cleanup(rp);
18633
                            return(SUSPEND);
18634
```

```
book.txt
 Feb 25, 11 15:18
                                                               Page 248/393
      File: Page: 885 servers/pm/forkexit.c
                    if ((rp->mp_flags & STOPPED) && rp->mp_sigstatus)
18635
18636
                           /* This child meets the pid test and is being traced.*/
18637
                           mp->mp_reply.reply_res2 = 0177 | (rp->mp_sigstatus << 8);
18638
                           rp->mp_sigstatus = 0;
18639
                           return(rp->mp_pid);
18640
18641
18642
18643
18644
        /* No qualifying child has exited. Wait for one, unless none exists. */
18645
        if (children > 0)
18646
             /* At least 1 child meets the pid test exists, but has not exited. */
18647
             if (options & WNOHANG) return(0); /* parent does not want to wait */
                                             /* parent wants to wait */
18648
             mp->mp_flags |= WAITING;
18649
             mp->mp_wpid = (pid_t) pidarg;
                                             /* save pid for later */
18650
             return(SUSPEND);
                                             /* do not reply, let it wait */
18651
18652
             /* No child even meets the pid test. Return error immediately. */
18653
             return(ECHILD);
                                             /* no - parent has no children */
18654
18655 }
18657 /*=======*
18658
                                 cleanup
18659
       18660 PRIVATE void cleanup(child)
18661 register struct mproc *child; /* tells which process is exiting */
18662
      ^{\prime *} Finish off the exit of a process. The process has exited or been killed
18663
       * by a signal, and its parent is waiting.
18664
18665
18666
        struct mproc *parent = &mproc[child->mp_parent];
18667
        int exitstatus;
18668
18669
        /* Wake up the parent by sending the reply message. */
18670
        exitstatus = (child->mp_exitstatus << 8) | (child->mp_sigstatus & 0377);
18671
        parent->mp_reply.reply_res2 = exitstatus;
18672
        setreply(child->mp_parent, child->mp_pid);
18673
        parent->mp flags &= ~WAITING;
                                         /* parent no longer waiting */
18674
        /* Release the process table entry and reinitialize some field. */
18675
        child->mp pid = 0;
18676
18677
        child->mp_flags = 0;
18678
        child->mp_child_utime = 0;
18679
        child->mp child stime = 0;
18680
        procs in use--;
18681
servers/pm/exec.c
18700 /* This file handles the EXEC system call. It performs the work as follows:
18701 * - see if the permissions allow the file to be executed
18702
           - read the header and extract the sizes
          - fetch the initial args and environment from the user space
18703
18704 * - allocate the memory for the new process
```

```
Feb 25, 11 15:18
                                    book.txt
                                                                   Page 249/393
      File: Page: 886 servers/pm/exec.c
18705
           - copy the initial stack from PM to the process
18706
            - read in the text and data segments and copy to the process
18707
            - take care of setuid and setgid bits
18708
            - fix up 'mproc' table
18709
           - tell kernel about EXEC
18710
           - save offset to initial argc (for ps)
18711
18712
       * The entry points into this file are:
       * do_exec: perform the EXEC system call
18713
       * rw_seg:
18714
                       read or write a segment from or to a file
       * find_share: find a process whose text segment can be shared
18715
18716
18717
18718 #include "pm.h"
18719 #include <sys/stat.h>
18720 #include <minix/callnr.h>
18721 #include <minix/com.h>
18722 #include <a.out.h>
18723 #include <signal.h>
18724 #include <string.h>
18725 #include "mproc.h"
18726 #include "param.h"
18727
18728 FORWARD _PROTOTYPE( int new_mem, (struct mproc *sh_mp, vir_bytes text_bytes,
18729
                     vir_bytes data_bytes, vir_bytes bss_bytes,
18730
                     vir_bytes stk_bytes, phys_bytes tot_bytes)
18731 FORWARD _PROTOTYPE( void patch_ptr, (char stack[ARG_MAX], vir_bytes base) );
18732 FORWARD _PROTOTYPE( int insert_arg, (char stack[ARG_MAX],
18733
                     vir_bytes *stk_bytes, char *arg, int replace)
18734 FORWARD _PROTOTYPE( char *patch_stack, (int fd, char stack[ARG_MAX],
                     vir_bytes *stk_bytes, char *script)
18735
                                                                         );
18736 FORWARD _PROTOTYPE( int read_header, (int fd, int *ft, vir_bytes *text_bytes,
18737
                     vir_bytes *data_bytes, vir_bytes *bss_bytes,
18738
                     phys_bytes *tot_bytes, long *sym_bytes, vir_clicks sc,
18739
                     vir_bytes *pc)
18740
18741 #define ESCRIPT (-2000) /* Returned by read_header for a #! script. */
18742 #define PTRSIZE sizeof(char *) /* Size of pointers in argv[] and envp[]. */
18743
18744 /*============*
18745 *
                                    do_exec
18746
      18747 PUBLIC int do_exec()
18748
18749
      /* Perform the execve(name, argv, envp) call. The user library builds a
18750
       * complete stack image, including pointers, args, environ, etc. The stack
18751
       * is copied to a buffer inside PM, and then to the new core image.
18752
18753
        register struct mproc *rmp;
18754
        struct mproc *sh_mp;
18755
        int m, r, fd, ft, sn;
18756
        static char mbuf[ARG_MAX];
                                   /* buffer for stack and zeroes */
        static char name_buf[PATH_MAX]; /* the name of the file to exec */
18757
18758
        char *new sp, *name, *basename;
18759
        vir_bytes src, dst, text_bytes, data_bytes, bss_bytes, stk_bytes, vsp;
18760
        phys_bytes tot_bytes;
                                 /* total space for program, including gap */
18761
        long sym bytes;
18762
        vir clicks sc;
        struct stat s_buf[2], *s_p;
18763
18764
        vir bytes pc;
```

```
Feb 25, 11 15:18
                                        book.txt
                                                                         Page 250/393
       File: Page: 887 servers/pm/exec.c
18765
18766
         /* Do some validity checks. */
18767
         rmp = mp;
18768
         stk bytes = (vir_bytes) m_in.stack_bytes;
18769
                                                       /* stack too big */
         if (stk_bytes > ARG_MAX) return(ENOMEM);
18770
         if (m_in.exec_len <= 0 | m_in.exec_len > PATH_MAX) return(EINVAL);
18771
18772
         /* Get the exec file name and see if the file is executable. */
18773
         src = (vir bytes) m in.exec name;
18774
         dst = (vir_bytes) name_buf;
18775
         r = sys_datacopy(who, (vir_bytes) src,
18776
                       PM_PROC_NR, (vir_bytes) dst, (phys_bytes) m_in.exec_len);
18777
         if (r != OK) return(r);
                                       /* file name not in user data segment */
18778
18779
         /* Fetch the stack from the user before destroying the old core image. */
18780
         src = (vir_bytes) m_in.stack_ptr;
18781
         dst = (vir_bytes) mbuf;
18782
         r = sys_datacopy(who, (vir_bytes) src,
18783
                               PM_PROC_NR, (vir_bytes) dst, (phys_bytes)stk_bytes);
18784
         /* can't fetch stack (e.g. bad virtual addr) */
18785
         if (r != OK) return(EACCES);
18786
18787
         r = 0;
                      /* r = 0 (first attempt), or 1 (interpreted script) */
                               /* name of file to exec. */
18788
         name = name buf;
18789
         do {
18790
               sp = &sbuf[r];
               tell fs(CHDIR, who, FALSE, 0); /* switch to the user's FS environ */
18791
               fd = allowed(name, s_p, X_BIT); /* is file executable? */
18792
                                                       /* file was not executable */
18793
               if (fd < 0) return(fd);</pre>
18794
18795
               /* Read the file header and extract the segment sizes. */
18796
               sc = (stk_bytes + CLICK_SIZE - 1) >> CLICK_SHIFT;
18797
18798
               m = read_header(fd, &ft, &text_bytes, &data_bytes, &bss_bytes,
18799
                                               &tot_bytes, &sym_bytes, sc, &pc);
18800
               if (m != ESCRIPT || ++r > 1) break;
         } while ((name = patch_stack(fd, mbuf, &stk_bytes, name_buf)) != NULL);
18801
18802
18803
         if (m < 0)
18804
               close(fd);
                                       /* something wrong with header */
18805
               return(stk_bytes > ARG_MAX ? ENOMEM : ENOEXEC);
18806
18807
18808
         /* Can the process' text be shared with that of one already running? */
         sh_mp = find_share(rmp, s_p->st_ino, s_p->st_dev, s_p->st_ctime);
18809
18810
18811
         /* Allocate new memory and release old memory. Fix map and tell kernel. */
18812
         r = new_mem(sh_mp, text_bytes, data_bytes, bss_bytes, stk_bytes, tot_bytes);
18813
         if (r != OK) {
18814
               close(fd);
                                       /* insufficient core or program too big */
18815
               return(r);
18816
18817
18818
         /* Save file identification to allow it to be shared. */
18819
         rmp->mp_ino = s_p->st_ino;
18820
         rmp->mp_dev = s_p->st_dev;
18821
         rmp->mp ctime = s p->st ctime;
18822
18823
         /* Patch up stack and copy it from PM to new core image. */
18824
         vsp = (vir bytes) rmp->mp seq[S].mem vir << CLICK SHIFT;</pre>
```

```
book.txt
Feb 25, 11 15:18
                                                                           Page 251/393
       File: Page: 888 servers/pm/exec.c
18825
         vsp += (vir_bytes) rmp->mp_seg[S].mem_len << CLICK_SHIFT;</pre>
18826
         vsp -= stk_bytes;
18827
         patch_ptr(mbuf, vsp);
18828
         src = (vir_bytes) mbuf;
         r = sys_datacopy(PM_PROC_NR, (vir_bytes) src,
18829
18830
                                who, (vir_bytes) vsp, (phys_bytes)stk_bytes);
18831
         if (r != OK) panic(__FILE__, "do_exec stack copy err on", who);
18832
18833
         /* Read in text and data segments. */
18834
         if (sh_mp != NULL) {
                lseek(fd, (off_t) text_bytes, SEEK_CUR); /* shared: skip text */
18835
18836
18837
               rw_seg(0, fd, who, T, text_bytes);
18838
18839
         rw seg(0, fd, who, D, data bytes);
18840
18841
         close(fd);
                                        /* don't need exec file any more */
18842
18843
         /* Take care of setuid/setgid bits. */ if ((rmp->mp_flags & TRACED) == 0) { /* suppress if tracing */
18844
18845
                if (s_buf[0].st_mode & I_SET_UID_BIT) {
18846
                        rmp->mp_effuid = s_buf[0].st_uid;
18847
                        tell_fs(SETUID,who, (int)rmp->mp_realuid, (int)rmp->mp_effuid);
18848
18849
                if (s_buf[0].st_mode & I_SET_GID_BIT)
                        rmp->mp_effgid = s_buf[0].st_gid;
18850
                        tell fs(SETGID, who, (int)rmp->mp realgid, (int)rmp->mp effgid);
18851
18852
18853
18854
18855
         /* Save offset to initial argc (for ps) */
18856
         rmp->mp_procargs = vsp;
18857
18858
         /* Fix 'mproc' fields, tell kernel that exec is done, reset caught sigs. */
18859
         for (sn = 1; sn <= _NSIG; sn++) {
18860
                if (sigismember(&rmp->mp_catch, sn)) {
18861
                        sigdelset(&rmp->mp_catch, sn);
18862
                        rmp->mp_sigact[sn].sa_handler = SIG_DFL;
18863
                        sigemptyset(&rmp->mp_sigact[sn].sa_mask);
18864
18865
18866
18867
         rmp->mp_flags &= ~SEPARATE; /* turn off SEPARATE bit */
18868
         rmp->mp_flags |= ft;
                                        /* turn it on for separate I & D files */
18869
         new sp = (char *) vsp;
18870
18871
         tell_fs(EXEC, who, 0, 0); /* allow FS to handle FD_CLOEXEC files */
18872
18873
         /* System will save command line for debugging, ps(1) output, etc. */
18874
         basename = strrchr(name, '/');
18875
         if (basename == NULL) basename = name; else basename++;
         strncpy(rmp->mp_name, basename, PROC_NAME_LEN-1);
rmp->mp_name[PROC_NAME_LEN] = '\0';
18876
18877
18878
         sys exec(who, new sp, basename, pc);
18879
18880
           * Cause a signal if this process is traced. */
18881
         if (rmp->mp_flags & TRACED) check_sig(rmp->mp_pid, SIGTRAP);
18882
18883
         return(SUSPEND);
                                        /* no reply, new program just runs */
18884 }
```

```
book.txt
Feb 25, 11 15:18
                                                                    Page 252/393
      File: Page: 889 servers/pm/exec.c
read_header
18888
       18889 PRIVATE int read_header(fd, ft, text_bytes, data_bytes, bss_bytes,
18890
                                                   tot_bytes, sym_bytes, sc, pc)
                                    /* file descriptor for reading exec file */
18891 int fd;
18892 int *ft;
                                    /* place to return ft number */
18893 vir bytes *text bytes;
                                    /* place to return text size */
18894 vir_bytes *data_bytes;
                                    /* place to return initialized data size */
18895 vir_bytes *bss_bytes;
                                    /* place to return bss size */
18896 phys_bytes *tot_bytes;
                                    /* place to return total size */
18897 long *sym_bytes;
                                    /* place to return symbol table size */
18898 vir_clicks sc;
                                    /* stack size in clicks */
                                    /* program entry point (initial PC) */
18899 vir bytes *pc;
18900
18901
      /* Read the header and extract the text, data, bss and total sizes from it. */
18902
18903
        int m. ct;
        vir_clicks tc, dc, s_vir, dvir;
18904
18905
        phys_clicks totc;
18906
        struct exec hdr;
                                    /* a.out header is read in here */
18907
18908
        /* Read the header and check the magic number. The standard MINIX header
         * is defined in <a.out.h>. It consists of 8 chars followed by 6 longs.
18909
         * Then come 4 more longs that are not used here.
18910
              Byte 0: magic number 0x01
18911
18912
              Byte 1: magic number 0x03
              Byte 2: normal = 0x10 (not checked, 0 is OK), separate I/D = 0x20
18913
18914
              Byte 3: CPU type, Intel 16 bit = 0x04, Intel 32 bit = 0x10,
18915
                    Motorola = 0x0B, Sun SPARC = 0x17
18916
              Byte 4: Header length = 0x20
18917
              Bytes 5-7 are not used.
18918
18919
              Now come the 6 longs
18920
              Bytes 8-11: size of text segments in bytes
18921
              Bytes 12-15: size of initialized data segment in bytes
18922
              Bytes 16-19: size of bss in bytes
              Bytes 20-23: program entry point
18923
18924
              Bytes 24-27: total memory allocated to program (text, data + stack)
              Bytes 28-31: size of symbol table in bytes
18925
         * The longs are represented in a machine dependent order,
18926
         * little-endian on the 8088, big-endian on the 68000.
18927
18928
         * The header is followed directly by the text and data segments, and the
18929
         * symbol table (if any). The sizes are given in the header. Only the
18930
         * text and data segments are copied into memory by exec. The header is
18931
         * used here only. The symbol table is for the benefit of a debugger and
         * is ignored here.
18932
18933
18934
18935
        if ((m= read(fd, &hdr, A_MINHDR)) < 2) return(ENOEXEC);</pre>
18936
18937
        /* Interpreted script? */
        if (((char *) &hdr)[0] == '#' && ((char *) &hdr)[1] == '!') return(ESCRIPT);
18938
18939
18940
        if (m != A MINHDR) return(ENOEXEC);
18941
        /* Check magic number, cpu type, and flags. */
18942
        if (BADMAG(hdr)) return(ENOEXEC);
18943
18944
        if (hdr.a cpu != A I80386) return(ENOEXEC);
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                     Page 253/393
       File: Page: 890 servers/pm/exec.c
18945
        if ((hdr.a_flags & ~(A_NSYM | A_EXEC | A_SEP)) != 0) return(ENOEXEC);
18946
18947
         *ft = ( (hdr.a_flags & A_SEP) ? SEPARATE : 0); /* separate I & D or not */
18948
18949
        /* Get text and data sizes. */
18950
        *text_bytes = (vir_bytes) hdr.a_text; /* text size in bytes */
         *data_bytes = (vir_bytes) hdr.a_data; /* data size in bytes */
18951
        *bss_bytes = (vir_bytes) hdr.a_bss; /* bss size in bytes */
18952
                                           /* total bytes to allocate for prog */
18953
        *tot_bytes = hdr.a_total;
        *sym_bytes = hdr.a_syms;
18954
                                            /* symbol table size in bytes */
        if (*tot bytes == 0) return(ENOEXEC);
18955
18956
18957
        if (*ft. != SEPARATE)
              /* If I & D space is not separated, it is all considered data. Text=0*/
18958
18959
              *data bytes += *text bytes;
18960
              *text bytes = 0;
18961
18962
        *pc = hdr.a_entry; /* initial address to start execution */
18963
18964
        /* Check to see if segment sizes are feasible. */
18965
        tc = ((unsigned long) *text_bytes + CLICK_SIZE - 1) >> CLICK_SHIFT;
        dc = (*data_bytes + *bss_bytes + CLICK_SIZE - 1) >> CLICK_SHIFT;
totc = (*tot_bytes + CLICK_SIZE - 1) >> CLICK_SHIFT;
18966
18967
18968
        if (dc >= totc) return(ENOEXEC);
                                           /* stack must be at least 1 click */
18969
        dvir = (*ft == SEPARATE ? 0 : tc);
        s_vir = dvir + (totc - sc);
18970
        m = (dvir + dc > s_vir) ? ENOMEM : OK;
18971
        ct = hdr.a_hdrlen & BYTE;
                                            /* header length */
18972
18973
        if (ct > A_MINHDR) lseek(fd, (off_t) ct, SEEK_SET); /* skip unused hdr */
18974
        return(m);
18975 }
18977 /*========**
18978 *
                                    new mem
18979 *=============*/
18980 PRIVATE int new_mem(sh_mp, text_bytes, data_bytes,
18981
            bss_bytes,stk_bytes,tot_bytes)
18982 struct mproc *sh_mp;
                                /* text can be shared with this process */
18983 vir bytes text bytes;
                                    /* text segment size in bytes */
18984 vir_bytes data_bytes;
                                     /* size of initialized data in bytes */
18985 vir_bytes bss_bytes;
                                     /* size of bss in bytes */
                                     /* size of initial stack segment in bytes */
18986 vir bytes stk bytes;
                                     /* total memory to allocate, including gap */
18987 phys_bytes tot_bytes;
18988
18989 /* Allocate new memory and release the old memory. Change the map and report
18990
       * the new map to the kernel. Zero the new core image's bss, gap and stack.
18991
18992
18993
        register struct mproc *rmp = mp;
18994
        vir_clicks text_clicks, data_clicks, gap_clicks, stack_clicks, tot_clicks;
18995
        phys_clicks new_base;
18996
        phys_bytes bytes, base, bss_offset;
18997
        int s;
18998
18999
        /* No need to allocate text if it can be shared. */
19000
        if (sh_mp != NULL) text_bytes = 0;
19001
19002
        /* Allow the old data to be swapped out to make room. (Which is really a
19003
          * waste of time, because we are going to throw it away anyway.)
19004
```

```
Feb 25, 11 15:18
                                        book.txt
                                                                         Page 254/393
       File: Page: 891 servers/pm/exec.c
19005
         rmp->mp_flags |= WAITING;
19006
19007
         /* Acquire the new memory. Each of the 4 parts: text, (data+bss), gap,
19008
          * and stack occupies an integral number of clicks, starting at click
          * boundary. The data and bss parts are run together with no space.
19009
19010
19011
         text_clicks = ((unsigned long) text_bytes + CLICK_SIZE - 1) >> CLICK_SHIFT;
19012
         data_clicks = (data_bytes + bss_bytes + CLICK_SIZE - 1) >> CLICK_SHIFT;
         stack clicks = (stk bytes + CLICK SIZE - 1) >> CLICK SHIFT;
19013
19014
         tot_clicks = (tot_bytes + CLICK_SIZE - 1) >> CLICK_SHIFT;
         gap clicks = tot clicks - data clicks - stack clicks;
19015
         if ( (int) gap_clicks < 0) return(ENOMEM);</pre>
19016
19017
19018
         /* Try to allocate memory for the new process. */
19019
         new base = alloc mem(text clicks + tot clicks);
19020
         if (new base == NO MEM) return(ENOMEM);
19021
19022
         /* We've got memory for the new core image. Release the old one. */
19023
         rmp = mp;
19024
19025
         if (find_share(rmp, rmp->mp_ino, rmp->mp_dev, rmp->mp_ctime) == NULL) {
19026
               /* No other process shares the text segment, so free it. */
19027
               free_mem(rmp->mp_seg[T].mem_phys, rmp->mp_seg[T].mem_len);
19028
19029
         /* Free the data and stack segments. */
19030
         free_mem(rmp->mp_seg[D].mem_phys,
19031
          rmp->mp seq[S].mem vir + rmp->mp seq[S].mem len - rmp->mp seq[D].mem vir);
19032
19033
         /* We have now passed the point of no return. The old core image has been
19034
          * forever lost, memory for a new core image has been allocated. Set up
19035
          * and report new map.
19036
19037
         if (sh_mp != NULL) {
19038
               /* Share the text segment. */
19039
               rmp->mp_seg[T] = sh_mp->mp_seg[T];
19040
19041
              rmp->mp_seg[T].mem_phys = new_base;
19042
               rmp->mp_seg[T].mem_vir = 0;
19043
               rmp->mp seq[T].mem len = text clicks;
19044
19045
         rmp->mp_seg[D].mem_phys = new_base + text_clicks;
         rmp->mp seg[D].mem vir = 0;
19046
19047
         rmp->mp_seg[D].mem_len = data_clicks;
19048
         rmp->mp_seg[S].mem_phys = rmp->mp_seg[D].mem_phys + data_clicks + gap_clicks;
19049
         rmp->mp_seg[S].mem_vir = rmp->mp_seg[D].mem_vir + data_clicks + gap_clicks;
19050
         rmp->mp_seg[S].mem_len = stack_clicks;
19051
19052
         sys_newmap(who, rmp->mp_seg); /* report new map to the kernel */
19053
19054
         /* The old memory may have been swapped out, but the new memory is real. */
19055
         rmp->mp_flags &= ~(WAITING|ONSWAP|SWAPIN);
19056
19057
         /* Zero the bss, gap, and stack segment. */
         bytes = (phys_bytes)(data_clicks + gap_clicks + stack_clicks) << CLICK_SHIFT;
19058
19059
         base = (phys_bytes) rmp->mp_seg[D].mem_phys << CLICK_SHIFT;</pre>
19060
         bss_offset = (data_bytes >> CLICK_SHIFT) << CLICK_SHIFT;</pre>
         base += bss offset;
19061
19062
         bytes -= bss_offset;
19063
19064
         if ((s=sys memset(0, base, bytes)) != OK) {
```

```
Feb 25, 11 15:18
                                  book.txt
                                                              Page 255/393
      File: Page: 892 servers/pm/exec.c
19065
            panic(__FILE__, "new_mem can't zero", s);
19066
19067
19068
       return(OK);
19069
19071 /*===========*
19072
                                 patch_ptr
19073
      19074 PRIVATE void patch_ptr(stack, base)
19075 char stack[ARG_MAX];
                                /* pointer to stack image within PM */
     vir bytes base;
                                 /* virtual address of stack base inside user */
19077
19078 /* When doing an exec(name, argv, envp) call, the user builds up a stack
19079
      * image with arg and env pointers relative to the start of the stack. Now
19080
      * these pointers must be relocated, since the stack is not positioned at
19081
      * address 0 in the user's address space.
19082
19083
       char **ap, flag;
19084
19085
       vir_bytes v;
19086
19087
       flaq = 0;
                                 /* counts number of 0-pointers seen */
       ap = (char **) stack;
                                 /* points initially to 'nargs' */
19088
19089
                                 /* now points to argv[0] */
       ap++;
19090
       while (flag < 2) {
            if (ap >= (char **) &stack[ARG MAX]) return; /* too bad */
19091
19092
             if (*ap != NULL) {
19093
                   v = (vir_bytes) *ap; /* v is relative pointer */
                                        /* relocate it */
19094
                   v += base;
19095
                    *ap = (char *) v;
                                        /* put it back */
19096
             } else {
19097
                    flag++;
19098
             ap++;
19099
19100
19101 }
19103 /*----*
19104
                                insert_arg
      *-----*/
19105
19106 PRIVATE int insert_arg(stack, stk_bytes, arg, replace)
                          /* pointer to stack image within PM */
19107 char stack[ARG_MAX];
19108 vir_bytes *stk_bytes;
                                 /* size of initial stack */
                                /* argument to prepend/replace as new argv[0] */
19109 char *arg;
19110 int replace;
19111
19112 /* Patch the stack so that arg will become argv[0]. Be careful, the stack may
19113
      * be filled with garbage, although it normally looks like this:
19114
            nargs argv[0] ... argv[nargs-1] NULL envp[0] ... NULL
19115
      * followed by the strings "pointed" to by the argv[i] and the envp[i]. The
19116
       * pointers are really offsets from the start of stack.
       * Return true iff the operation succeeded.
19117
19118
19119
       int offset, a0, a1, old_bytes = *stk_bytes;
19120
19121
        /* Prepending arg adds at least one string and a zero byte. */
19122
       offset = strlen(arg) + 1;
19123
19124
        a0 = (int) ((char **) stack)[1];
                                        /* argv[0] */
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 256/393
      File: Page: 893 servers/pm/exec.c
19125
        if (a0 < 4 * PTRSIZE | a0 >= old bytes) return(FALSE);
19126
19127
                                    /* al will point to the strings to be moved */
19128
        if (replace) {
              /* Move al to the end of argv[0][] (argv[1] if nargs > 1). */
19129
19130
19131
                     if (a1 == old_bytes) return(FALSE);
19132
                     --offset;
19133
              } while (stack[a1++] != 0);
19134
        } else {
19135
              offset += PTRSIZE;
                                     /* new argv[0] needs new pointer in argv[] */
19136
              a0 += PTRSIZE;
                                    /* location of new argv[0][]. */
19137
19138
19139
        /* stack will grow by offset bytes (or shrink by -offset bytes) */
19140
        if ((*stk_bytes += offset) > ARG_MAX) return(FALSE);
19141
19142
        /* Reposition the strings by offset bytes */
19143
        memmove(stack + a1 + offset, stack + a1, old_bytes - a1);
19144
19145
        strcpy(stack + a0, arg); /* Put arg in the new space. */
19146
19147
        if (!replace) {
19148
              /* Make space for a new argv[0]. */
19149
              memmove(stack + 2 * PTRSIZE, stack + 1 * PTRSIZE, a0 - 2 * PTRSIZE);
19150
19151
              ((char **) stack)[0]++; /* nargs++; */
19152
        /* Now patch up argv[] and envp[] by offset. */
19153
        patch ptr(stack, (vir bytes) offset);
19154
19155
        ((char **) stack)[1] = (char *) a0; /* set argv[0] correctly */
19156
        return(TRUE);
19157
19160
                                  patch_stack
19161
       *-----*/
19162 PRIVATE char *patch_stack(fd, stack, stk_bytes, script)
19163 int fd;
                                  /* file descriptor to open script file */
19164 char stack[ARG_MAX];
                                    /* pointer to stack image within PM */
                                    /* size of initial stack */
19165
      vir_bytes *stk_bytes;
                                    /* name of script to interpret */
19166
      char *script;
19167
19168

angle^* Patch the argument vector to include the path name of the script to be
       * interpreted, and all strings on the #! line. Returns the path name of
19169
19170
       * the interpreter.
19171
19172
        char *sp, *interp = NULL;
19173
        int n;
19174
        enum { INSERT=FALSE, REPLACE=TRUE };
19175
19176
        /* Make script[] the new argv[0]. */
19177
        if (!insert_arg(stack, stk_bytes, script, REPLACE)) return(NULL);
19178
19179
        if (lseek(fd, 2L, 0) == -1)
                                                   /* just behind the #! */
                                                   /* read line one */
19180
             (n= read(fd, script, PATH_MAX)) < 0</pre>
             (sp= memchr(script, '\n', n)) == NULL) /* must be a proper line */
19181
19182
              return(NULL);
19183
19184
        /* Move sp backwards through script[], prepending each string to stack. */
```

```
book.txt
Feb 25, 11 15:18
                                                                     Page 257/393
      File: Page: 894 servers/pm/exec.c
19185
        for (;;) {
19186
              /* skip spaces behind argument. */
              while (sp > script && (*--sp == ' ' || *sp == '\t')) {}
19187
19188
              if (sp == script) break;
19189
19190
19191
               /* Move to the start of the argument. */
              while (sp > script && sp[-1] != ' ' && sp[-1] != '\t') --sp;
19192
19193
19194
19195
              if (!insert_arg(stack, stk_bytes, sp, INSERT)) return(NULL);
19196
19197
19198
         /* Round *stk_bytes up to the size of a pointer for alignment contraints. */
         *stk bytes= ((*stk bytes + PTRSIZE - 1) / PTRSIZE) * PTRSIZE;
19199
19200
19201
         close(fd);
19202
        return(interp);
19203
19205
      /*==================================
19206
                                     rw sea
19208 PUBLIC void rw_seg(rw, fd, proc, seg, seg_bytes0)
19209 int rw;
                                     /* 0 = read, 1 = write */
                                     /* file descriptor to read from / write to */
19210 int fd;
                                     /* process number */
19211 int proc;
19212 int seq;
                                     /* T, D, or S */
                                     /* how much is to be transferred? */
19213
      phys_bytes seg_bytes0;
19214
19215 /* Transfer text or data from/to a file and copy to/from a process segment.
      * This procedure is a little bit tricky. The logical way to transfer a
19216
         segment would be block by block and copying each block to/from the user
19218
         space one at a time. This is too slow, so we do something dirty here,
19219
         namely send the user space and virtual address to the file system in the
19220
         upper 10 bits of the file descriptor, and pass it the user virtual address
19221
         instead of a PM address. The file system extracts these parameters when
19222
         gets a read or write call from the process manager, which is the only
19223
         process that is permitted to use this trick. The file system then copies
19224
         the whole segment directly to/from user space, bypassing PM completely.
19225
19226
         The byte count on read is usually smaller than the segment count, because
        * a segment is padded out to a click multiple, and the data segment is only
19227
19228
        * partially initialized.
19229
19230
19231
        int new_fd, bytes, r;
19232
        char *ubuf_ptr;
19233
        struct mem_map *sp = &mproc[proc].mp_seg[seg];
19234
        phys_bytes seg_bytes = seg_bytes0;
19235
19236
        new_fd = (proc << 7) | (seg << 5) | fd;
ubuf_ptr = (char *) ((vir_bytes) sp->mem_vir << CLICK_SHIFT);</pre>
19237
19238
19239
         while (seg_bytes != 0)
       #define PM CHUNK SIZE 8192
19240
19241
              bytes = MIN((INT_MAX / PM_CHUNK_SIZE) * PM_CHUNK_SIZE, seg_bytes);
19242
              if (rw == 0) {
                      r = read(new_fd, ubuf_ptr, bytes);
19243
19244
              } else {
```

```
Feb 25, 11 15:18
                                  book.txt
                                                               Page 258/393
      File: Page: 895 servers/pm/exec.c
19245
                    r = write(new_fd, ubuf_ptr, bytes);
19246
19247
             if (r != bytes) break;
19248
             ubuf_ptr += bytes;
             seg_bytes -= bytes;
19249
19250
19251 }
19253 /*-----*
19254
                                 find_share
19255
       19256 PUBLIC struct mproc *find share(mp ign, ino, dev, ctime)
19257 struct mproc *mp_ign;
                                  /* process that should not be looked at */
19258 ino_t ino;
                                  /* parameters that uniquely identify a file */
19259 dev t dev;
19260
      time t ctime;
19261
19262 /* Look for a process that is the file <ino, dev, ctime> in execution. Don't
19263
       * accidentally "find" mp_ign, because it is the process on whose behalf this
       * call is made.
19264
19265
       * /
19266
        struct mproc *sh_mp;
        for (sh_mp = &mproc[0]; sh_mp < &mproc[NR_PROCS]; sh_mp++) {</pre>
19267
19268
19269
             if (!(sh_mp->mp_flags & SEPARATE)) continue;
19270
             if (sh_mp == mp_ign) continue;
             if (sh_mp->mp_ino != ino) continue;
19271
             if (sh_mp->mp_dev != dev) continue;
19272
19273
             if (sh_mp->mp_ctime != ctime) continue;
             return sh mp;
19274
19275
19276
        return(NULL);
19277 }
servers/pm/break.c
19300 /* The MINIX model of memory allocation reserves a fixed amount of memory for
19301 * the combined text, data, and stack segments. The amount used for a child
       * process created by FORK is the same as the parent had. If the child does
19302
19303
       * an EXEC later, the new size is taken from the header of the file EXEC'ed.
19304
19305
       * The layout in memory consists of the text segment, followed by the data
19306
        segment, followed by a gap (unused memory), followed by the stack segment.
19307
       * The data segment grows upward and the stack grows downward, so each can
19308
       * take memory from the gap. If they meet, the process must be killed. The
19309
       * procedures in this file deal with the growth of the data and stack segments.
19310
19311
       * The entry points into this file are:
       * do_brk:
19312
                      BRK/SBRK system calls to grow or shrink the data segment
19313
          adjust:
                       see if a proposed segment adjustment is allowed
19314
          size_ok:
                       see if the segment sizes are feasible
19315
19316
19317
      #include "pm.h"
19318 #include <signal.h>
19319 #include "mproc.h"
```

```
book.txt
Feb 25, 11 15:18
                                                               Page 259/393
      File: Page: 896 servers/pm/break.c
19320 #include "param.h"
19321
19322 #define DATA_CHANGED
                             1 /* flag value when data segment size changed */
19323 #define STACK_CHANGED
                             2 /* flag value when stack size changed */
19324
19325 /*==========*
19326 *
                                 do brk
19328 PUBLIC int do brk()
19329
19330 /* Perform the brk(addr) system call.
19331 *
      * The call is complicated by the fact that on some machines (e.g., 8088),
19332
      * the stack pointer can grow beyond the base of the stack segment without
19333
      * anybody noticing it.
19334
19335
       * The parameter, 'addr' is the new virtual address in D space.
19336
19337
19338
       register struct mproc *rmp;
19339
        int r;
19340
        vir_bytes v, new_sp;
19341
       vir_clicks new_clicks;
19342
19343
       rmp = mp;
19344
       v = (vir_bytes) m_in.addr;
        new_clicks = (vir_clicks) ( ((long) v + CLICK_SIZE - 1) >> CLICK_SHIFT);
19345
19346
       if (new_clicks < rmp->mp_seg[D].mem_vir) {
19347
             rmp->mp_reply.reply_ptr = (char *) -1;
19348
             return(ENOMEM);
19349
19350
       new_clicks -= rmp->mp_seg[D].mem_vir;
        if ((r=get_stack_ptr(who, &new_sp)) != OK) /* ask kernel for sp value */
19351
            panic(__FILE__, "couldn't get stack pointer", r);
19352
19353
        r = adjust(rmp, new_clicks, new_sp);
19354
        rmp->mp_reply.reply_ptr = (r == OK ? m_in.addr : (char *) -1);
19355
        return(r);
                                /* return new address or -1 */
19356
19358 /*-----*
19359 *
                                adjust
19360 *========*/
19361 PUBLIC int adjust(rmp, data_clicks, sp)
19362 register struct mproc *rmp; /* whose memory is being adjusted? */
                                 /* how big is data segment to become? */
19363 vir_clicks data_clicks;
                            /* new value of sp */
19364 vir bytes sp;
19365
19366 \not See if data and stack segments can coexist, adjusting them if need be.
19367
      * Memory is never allocated or freed. Instead it is added or removed from the
19368
       * gap between data segment and stack segment. If the gap size becomes
19369
       * negative, the adjustment of data or stack fails and ENOMEM is returned.
19370
19371
19372
        register struct mem_map *mem_sp, *mem_dp;
        vir_clicks sp_click, gap_base, lower, old_clicks;
19373
19374
        int changed, r, ft;
19375
        long base_of_stack, delta;
                                 /* longs avoid certain problems */
19376
19377
                                 /* pointer to data segment map */
        mem_dp = &rmp->mp_seg[D];
                                 /* pointer to stack segment map */
19378
        mem_sp = &rmp->mp_seg[S];
19379
        changed = 0;
                                 /* set when either segment changed */
```

```
Feb 25, 11 15:18
                                         book.txt
                                                                            Page 260/393
       File: Page: 897 servers/pm/break.c
19380
19381
         if (mem_sp->mem_len == 0) return(OK); /* don't bother init */
19382
19383
         /* See if stack size has gone negative (i.e., sp too close to 0xFFFF...) */
         base_of_stack = (long) mem_sp->mem_vir + (long) mem_sp->mem_len;
19384
19385
         sp_click = sp >> CLICK_SHIFT; /* click containing sp */
19386
         if (sp_click >= base_of_stack) return(ENOMEM);
                                                                  /* sp too high */
19387
19388
         /* Compute size of gap between stack and data segments. */
         delta = (long) mem_sp->mem_vir - (long) sp_click;
lower = (delta > 0 ? sp_click : mem_sp->mem_vir);
19389
19390
19391
19392
       /* Add a safety margin for future stack growth. Impossible to do right. */ \#define SAFETY\_BYTES (384 * sizeof(char *))
19393
       #define SAFETY CLICKS ((SAFETY BYTES + CLICK SIZE - 1) / CLICK SIZE)
19394
19395
         gap_base = mem_dp->mem_vir + data_clicks + SAFETY_CLICKS;
19396
         if (lower < gap_base) return(ENOMEM); /* data and stack collided */
19397
19398
         /* Update data length (but not data orgin) on behalf of brk() system call. */
19399
         old_clicks = mem_dp->mem_len;
19400
         if (data_clicks != mem_dp->mem_len) {
19401
               mem_dp->mem_len = data_clicks;
19402
               changed |= DATA_CHANGED;
19403
19404
19405
          /* Update stack length and origin due to change in stack pointer. */
19406
         if (delta > 0) {
19407
               mem_sp->mem_vir -= delta;
19408
               mem_sp->mem_phys -= delta;
19409
               mem sp->mem len += delta;
19410
               changed |= STACK CHANGED;
19411
19412
19413
         /* Do the new data and stack segment sizes fit in the address space? */
19414
         ft = (rmp->mp_flags & SEPARATE);
19415
         r = (rmp->mp_seg[D].mem_vir + rmp->mp_seg[D].mem_len >
                 rmp->mp_seg[S].mem_vir) ? ENOMEM : OK;
19416
19417
         if (r == OK) {
19418
               if (changed) sys_newmap((int)(rmp - mproc), rmp->mp_seg);
19419
               return(OK);
19420
19421
         /* New sizes don't fit or require too many page/segment registers. Restore.*/
19422
         if (changed & DATA_CHANGED) mem_dp->mem_len = old_clicks;
19423
         if (changed & STACK CHANGED) {
19424
19425
               mem_sp->mem_vir += delta;
19426
               mem_sp->mem_phys += delta;
19427
               mem_sp->mem_len -= delta;
19428
19429
         return(ENOMEM);
19430 }
```

```
book.txt
Feb 25, 11 15:18
                                                                 Page 261/393
      File: Page: 898 servers/pm/signal.c
servers/pm/signal.c
19500 /* This file handles signals, which are asynchronous events and are generally
      * a messy and unpleasant business. Signals can be generated by the KILL
       * system call, or from the keyboard (SIGINT) or from the clock (SIGALRM).
19502
         In all cases control eventually passes to check_sig() to see which processes
19504
         can be signaled. The actual signaling is done by sig_proc().
19505
19506
       * The entry points into this file are:
           do_sigaction: perform the SIGACTION system call
19507
19508
           do_sigpending:
                          perform the SIGPENDING system call
19509
           do_sigprocmask: perform the SIGPROCMASK system call
19510
           do_sigreturn: perform the SIGRETURN system call do_sigsuspend: perform the SIGSUSPEND system call
19511
19512
       * do_kill: perform the KILL system call
       * do_alarm: perform the ALARM system call by calling set_alarm()
19513
19514
           set_alarm: tell the clock task to start or stop a timer
19515
           do_pause: perform the PAUSE system call
19516
           ksig_pending: the kernel notified about pending signals
19517
           sig_proc: interrupt or terminate a signaled process
           check sig: check which processes to signal with sig proc()
19518
19519
           check_pending: check if a pending signal can now be delivered
19520
19521
19522 #include "pm.h"
19523 #include <sys/stat.h>
19524 #include <sys/ptrace.h>
19525 #include <minix/callnr.h>
19526 #include <minix/com.h>
19527 #include <signal.h>
19528 #include <svs/sigcontext.h>
19529 #include <string.h>
19530 #include "mproc.h"
19531 #include "param.h"
19532
19533 #define CORE MODE
                                   /* mode to use on core image files */
19534 #define DUMPED
                                   /* bit set in status when core dumped */
                            0200
19535
19536
      FORWARD _PROTOTYPE( void dump_core, (struct mproc *rmp)
      FORWARD _PROTOTYPE( void unpause, (int pro)
19537
                                                                       );
19538
      FORWARD _PROTOTYPE( void handle_sig, (int proc_nr, sigset_t sig_map)
                                                                       );
19539 FORWARD _PROTOTYPE( void cause_sigalrm, (struct timer *tp)
19540
19541
      /*_____*
19542
                                  do_sigaction
19543
       *----*/
19544 PUBLIC int do_sigaction()
19545
19546
        int r;
19547
        struct sigaction svec;
19548
        struct sigaction *svp;
19549
19550
        if (m_in.sig_nr == SIGKILL) return(OK);
        if (m_in.sig_nr < 1 || m_in.sig_nr > _NSIG) return (EINVAL);
svp = &mp->mp_sigact[m_in.sig_nr];
19551
19552
19553
        if ((struct sigaction *) m_in.sig_osa != (struct sigaction *) NULL) {
19554
              r = sys datacopy(PM PROC NR, (vir bytes) svp,
```

```
Feb 25, 11 15:18
                                  book.txt
                                                               Page 262/393
      File: Page: 899 servers/pm/signal.c
19555
                    who, (vir_bytes) m_in.sig_osa, (phys_bytes) sizeof(svec));
19556
             if (r != OK) return(r);
19557
19558
19559
        if ((struct sigaction *) m_in.sig_nsa == (struct sigaction *) NULL)
19560
             return(OK);
19561
19562
        /* Read in the sigaction structure. */
19563
        r = sys_datacopy(who, (vir_bytes) m_in.sig_nsa,
19564
                    PM_PROC_NR, (vir_bytes) &svec, (phys_bytes) sizeof(svec));
19565
        if (r != OK) return(r);
19566
19567
        if (svec.sa_handler == SIG_IGN) {
19568
             sigaddset(&mp->mp_ignore, m_in.sig_nr);
19569
             sigdelset(&mp->mp_sigpending, m_in.sig_nr);
19570
             sigdelset(&mp->mp_catch, m_in.sig_nr);
19571
             sigdelset(&mp->mp_sig2mess, m_in.sig_nr);
        } else if (svec.sa_handler == SIG_DFL) {
19572
             sigdelset(&mp->mp_ignore, m_in.sig_nr);
19573
             sigdelset(&mp->mp_catch, m_in.sig_nr);
19574
19575
             sigdelset(&mp->mp_sig2mess, m_in.sig_nr);
19576
        } else if (svec.sa_handler == SIG_MESS) {
19577
             if (! (mp->mp_flags & PRIV_PROC)) return(EPERM);
19578
             sigdelset(&mp->mp_ignore, m_in.sig_nr);
19579
             sigaddset(&mp->mp_sig2mess, m_in.sig_nr);
19580
             sigdelset(&mp->mp_catch, m_in.sig_nr);
19581
        } else
19582
             sigdelset(&mp->mp_ignore, m_in.sig_nr);
19583
             sigaddset(&mp->mp_catch, m_in.sig_nr);
19584
             sigdelset(&mp->mp sig2mess, m in.sig nr);
19585
19586
        mp->mp_sigact[m_in.sig_nr].sa_handler = svec.sa_handler;
19587
        sigdelset(&svec.sa_mask, SIGKILL);
19588
        mp->mp_sigact[m_in.sig_nr].sa_mask = svec.sa_mask;
19589
        mp->mp_sigact[m_in.sig_nr].sa_flags = svec.sa_flags;
19590
        mp->mp_sigreturn = (vir_bytes) m_in.sig_ret;
19591
        return(OK);
19592
19594
      19595
                                  do sigpending
19596
      19597 PUBLIC int do_sigpending()
19598
19599
        mp->mp_reply.reply_mask = (long) mp->mp_sigpending;
19600
       return OK;
19601
19603
     /*_____*
19604
                                do_sigprocmask
19605
     19606 PUBLIC int do_sigprocmask()
19607
19608 /* Note that the library interface passes the actual mask in sigmask_set,
      * not a pointer to the mask, in order to save a copy. Similarly,
19609
19610
      * the old mask is placed in the return message which the library
      * interface copies (if requested) to the user specified address.
19612
      * The library interface must set SIG_INQUIRE if the 'act' argument
19613
19614 * is NULL.
```

```
Feb 25, 11 15:18
                               book.txt
                                                          Page 263/393
     File: Page: 900 servers/pm/signal.c
19615
19616
19617
19618
       mp->mp_reply.reply_mask = (long) mp->mp_sigmask;
19619
19620
19621
       switch (m_in.sig_how) {
19622
          case SIG_BLOCK:
19623
           sigdelset((sigset_t *)&m_in.sig_set, SIGKILL);
19624
            for (i = 1; i <= _NSIG; i++) {
                  if (sigismember((sigset_t *)&m_in.sig_set, i))
19625
19626
                        sigaddset(&mp->mp sigmask, i);
19627
19628
            break;
19629
19630
          case SIG UNBLOCK:
19631
            for (i = 1; i <= _NSIG; i++) {
                  if (sigismember((sigset_t *)&m_in.sig_set, i))
19632
19633
                        sigdelset(&mp->mp_sigmask, i);
19634
19635
            check_pending(mp);
19636
            break;
19637
19638
          case SIG SETMASK:
19639
            sigdelset((sigset_t *) &m_in.sig_set, SIGKILL);
19640
            mp->mp_sigmask = (sigset_t) m_in.sig_set;
19641
            check pending(mp);
19642
           break;
19643
19644
          case SIG INQUIRE:
19645
           break;
19646
19647
          default:
19648
           return(EINVAL);
19649
           break;
19650
19651
       return OK;
19652
19655
                              do sigsuspend
19656
      PUBLIC int do_sigsuspend()
19657
19658
       mp->mp sigmask2 = mp->mp sigmask; /* save the old mask */
19659
       mp->mp_sigmask = (sigset_t) m_in.sig_set;
19660
19661
       sigdelset(&mp->mp_sigmask, SIGKILL);
19662
       mp->mp_flags |= SIGSUSPENDED;
19663
       check_pending(mp);
19664
       return(SUSPEND);
19665
do sigreturn
19669
      19670
     PUBLIC int do_sigreturn()
19671
     /* A user signal handler is done. Restore context and check for
19672
     * pending unblocked signals.
19673
19674
     * /
```

```
Feb 25, 11 15:18
                               book.txt
                                                         Page 264/393
     File: Page: 901 servers/pm/signal.c
19675
19676
19677
19678
       mp->mp_sigmask = (sigset_t) m_in.sig_set;
19679
       sigdelset(&mp->mp_sigmask, SIGKILL);
19680
19681
       r = sys_sigreturn(who, (struct sigmsg *) m_in.sig_context);
19682
       check_pending(mp);
19683
       return(r);
19684
     /*----*
19687
                             do kill
19688
      PUBLIC int do kill()
19689
19690
19691
     /* Perform the kill(pid, signo) system call. */
19692
19693
       return check_sig(m_in.pid, m_in.sig_nr);
19694 }
19696 /*=========*
19697 *
                             ksig_pending
19698
     19699 PUBLIC int ksig_pending()
19700
19701 /* Certain signals, such as segmentation violations originate in the kernel.
19702
      * When the kernel detects such signals, it notifies the PM to take further
      ^{\star} action. The PM requests the kernel to send messages with the process
19703
19704
      * slot and bit map for all signaled processes. The File System, for example,
19705
      * uses this mechanism to signal writing on broken pipes (SIGPIPE).
19706
19707
      * The kernel has notified the PM about pending signals. Request pending
19708
      * signals until all signals are handled. If there are no more signals,
19709
      * NONE is returned in the process number field.
19710
19711
      int proc_nr;
19712
      sigset_t sig_map;
19713
19714
      while (TRUE) {
19715
        sys_getksig(&proc_nr, &sig_map);
                                     /* get an arbitrary pending signal */
19716
        if (NONE == proc_nr) {
                                    /* stop if no more pending signals */
19717
           break;
19718
        } else {
19719
           handle sig(proc nr, sig map); /* handle the received signal */
                                     /* tell kernel it's done */
19720
           sys_endksig(proc_nr);
19721
19722
19723
      return(SUSPEND);
                                     /* prevents sending reply */
19724
19726 /*==========*
19727 *
                              handle_sig
19728
     19729 PRIVATE void handle_sig(proc_nr, sig_map)
19730 int proc nr;
19731 sigset t sig map;
19732
19733
       register struct mproc *rmp;
19734
       int i;
```

```
book.txt
Feb 25, 11 15:18
                                                             Page 265/393
      File: Page: 902 servers/pm/signal.c
19735
       pid t proc id, id;
19736
19737
       rmp = &mproc[proc_nr];
19738
       if ((rmp->mp_flags & (IN_USE | ZOMBIE)) != IN_USE) return;
19739
       proc_id = rmp->mp_pid;
19740
       mp = &mproc[0];
                                        /* pretend signals are from PM */
19741
       mp->mp_procgrp = rmp->mp_procgrp;
                                        /* get process group right */
19742
19743
       /* Check each bit in turn to see if a signal is to be sent. Unlike
        * kill(), the kernel may collect several unrelated signals for a
19744
19745
         * process and pass them to PM in one blow. Thus loop on the bit
19746
        * map. For SIGINT and SIGOUIT, use proc id 0 to indicate a broadcast
        * to the recipient's process group. For SIGKILL, use proc_id -1 to
19747
19748
        * indicate a systemwide broadcast.
19749
19750
       for (i = 1; i <= _NSIG; i++) {
19751
            if (!sigismember(&sig_map, i)) continue;
19752
            switch (i) {
19753
                case STGTNT:
19754
                case SIGOUIT:
19755
                 id = 0; break; /* broadcast to process group */
19756
                case SIGKILL:
19757
                   id = -1; break; /* broadcast to all except INIT */
19758
                default:
19759
                   id = proc_id;
19760
                   break;
19761
19762
             check sig(id, i);
19763
19764 }
19766
     /*____*
              do_alarm
19768
     19769 PUBLIC int do_alarm()
19770
19771 /* Perform the alarm(seconds) system call. */
19772
      return(set_alarm(who, m_in.seconds));
19773 }
19775 /*============*
19776
                               set alarm
19777
       *=======*/
19778 PUBLIC int set_alarm(proc_nr, sec)
19779 int proc_nr; /* process that wants the alarm */
19780
                               /* how many seconds delay before the signal */
19781
19782 /* This routine is used by do_alarm() to set the alarm timer. It is also used
19783
      * to turn the timer off when a process exits with the timer still on.
19784
19785
                          /* number of ticks for alarm */
       clock_t exptime;
19786
                          /* needed for remaining time on previous alarm */
                          /* current system time */
19787
       clock_t uptime;
                          /* previous time left in seconds */
19788
       int remaining;
19789
19790
19791
        /* First determine remaining time of previous alarm, if set. */
19792
       if (mproc[proc_nr].mp_flags & ALARM_ON) {
19793
             if ( (s=getuptime(&uptime)) != OK)
19794
                   panic( FILE , "set alarm couldn't get uptime", s);
```

```
book.txt
Feb 25, 11 15:18
                                                                Page 266/393
      File: Page: 903 servers/pm/signal.c
19795
             exptime = *tmr exp time(&mproc[proc nr].mp timer);
19796
             remaining = (int) ((exptime - uptime + (HZ-1))/HZ);
19797
             if (remaining < 0) remaining = 0;
19798
        } else {
19799
             remaining = 0;
19800
19801
        /* Tell the clock task to provide a signal message when the time comes.
19802
19803
19804
        * Large delays cause a lot of problems. First, the alarm system call
19805
         * takes an unsigned seconds count and the library has cast it to an int.
19806
         * That probably works, but on return the library will convert "negative"
19807
         * unsigneds to errors. Presumably no one checks for these errors, so
19808
         * force this call through. Second, If unsigned and long have the same
19809
         * size, converting from seconds to ticks can easily overflow. Finally,
19810
         * the kernel has similar overflow bugs adding ticks.
19811
         \mbox{\ensuremath{^{\star}}} Fixing this requires a lot of ugly casts to fit the wrong interface
19812
         * types and to avoid overflow traps. ALRM_EXP_TIME has the right type
19813
19814
         * (clock_t) although it is declared as long. How can variables like
19815
         * this be declared properly without combinatorial explosion of message
19816
         * types?
19817
        ticks = (clock_t) (HZ * (unsigned long) (unsigned) sec);
19818
19819
        if ( (unsigned long) ticks / HZ != (unsigned) sec)
                                 /* eternity (really TMR_NEVER) */
19820
             ticks = LONG MAX;
19821
        if (ticks != 0) {
19822
             pm_set_timer(&mproc[proc_nr].mp_timer, ticks, cause_sigalrm, proc_nr);
19823
19824
             mproc[proc nr].mp flags |= ALARM ON;
19825
        } else if (mproc[proc_nr].mp_flags & ALARM_ON)
19826
             pm_cancel_timer(&mproc[proc_nr].mp_timer);
19827
             mproc[proc_nr].mp_flags &= ~ALARM ON;
19828
19829
        return(remaining);
19830
19832 /*============*
19833
                                cause sigalrm
19834
      *-----*
19835 PRIVATE void cause sigalrm(tp)
19836
     struct timer *tp;
19837
19838
        int proc_nr;
19839
       register struct mproc *rmp;
19840
19841
        proc_nr = tmr_arg(tp)->ta_int;
                                       /* get process from timer */
19842
        rmp = &mproc[proc_nr];
19843
        if ((rmp->mp_flags & (IN_USE | ZOMBIE)) != IN_USE) return;
19844
19845
        if ((rmp->mp_flags & ALARM_ON) == 0) return;
        rmp->mp_flags &= ~ALARM ON;
19846
19847
        check_sig(rmp->mp_pid, SIGALRM);
19848 }
do pause
19852
      19853 PUBLIC int do_pause()
19854
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 267/393
      File: Page: 904 servers/pm/signal.c
19855
      /* Perform the pause() system call. */
19856
19857
        mp->mp_flags |= PAUSED;
19858
        return(SUSPEND);
19859
19861 /*===========*
19862
                                   sig_proc
      19864 PUBLIC void sig_proc(rmp, signo)
19865 register struct mproc *rmp;
                                  /* pointer to the process to be signaled */
      int signo;
                                    /* signal to send to process (1 to NSIG) */
19867
19868 /* Send a signal to a process. Check to see if the signal is to be caught,
      * ignored, tranformed into a message (for system processes) or blocked.
19870
       * - If the signal is to be transformed into a message, request the KERNEL to
19871
       * send the target process a system notification with the pending signal as an
      * argument.
19872
19873
       \star - If the signal is to be caught, request the KERNEL to push a sigcontext
19874
       * structure and a sigframe structure onto the catcher's stack. Also, KERNEL
19875
       * will reset the program counter and stack pointer, so that when the process
       * next runs, it will be executing the signal handler. When the signal handler
19876
19877
       * returns, sigreturn(2) will be called. Then KERNEL will restore the signal
       * context from the sigcontext structure.
19879
       * If there is insufficient stack space, kill the process.
19880
19881
19882
        vir_bytes new_sp;
19883
        int s;
        int slot;
19884
19885
        int sigflags;
19886
        struct sigmsg sm;
19887
19888
        slot = (int) (rmp - mproc);
        if ((rmp->mp_flags & (IN_USE | ZOMBIE)) != IN_USE) {
19889
19890
              printf("PM: signal %d sent to %s process %d\n",
              signo, (rmp->mp_flags & ZOMBIE) ? "zombie" : "dead", slot);
panic(__FILE__,"", NO_NUM);
19891
19892
19893
19894
        if ((rmp->mp_flags & TRACED) && signo != SIGKILL) {
19895
              /* A traced process has special handling. *,
              unpause(slot);
19896
19897
              stop_proc(rmp, signo); /* a signal causes it to stop */
19898
              return;
19899
19900
        /* Some signals are ignored by default. */
19901
        if (sigismember(&rmp->mp_ignore, signo)) {
19902
              return;
19903
19904
        if (sigismember(&rmp->mp_sigmask, signo)) {
19905
              /* Signal should be blocked. */
19906
              sigaddset(&rmp->mp_sigpending, signo);
19907
              return;
19908
19909
        sigflags = rmp->mp_sigact[signo].sa_flags;
19910
        if (sigismember(&rmp->mp_catch, signo)) {
              if (rmp->mp flags & SIGSUSPENDED)
19911
19912
                      sm.sm_mask = rmp->mp_sigmask2;
19913
              else
19914
                      sm.sm mask = rmp->mp sigmask;
```

```
book.txt
Feb 25, 11 15:18
                                                                     Page 268/393
       File: Page: 905 servers/pm/signal.c
19915
              sm.sm signo = signo;
19916
              sm.sm_sighandler = (vir_bytes) rmp->mp_sigact[signo].sa_handler;
              sm.sm_sigreturn = rmp->mp_sigreturn;
19917
19918
              if ((s=get_stack_ptr(slot, &new_sp)) != OK)
19919
                      panic(__FILE__,"couldn't get new stack pointer",s);
19920
              sm.sm_stkptr = new_sp;
19921
              /* Make room for the sigcontext and sigframe struct. */
19922
19923
              new_sp -= sizeof(struct sigcontext)
19924
                                      + 3 * sizeof(char *) + 2 * sizeof(int);
19925
19926
              if (adjust(rmp, rmp->mp_seg[D].mem_len, new_sp) != OK)
19927
                     goto doterminate;
19928
19929
              rmp->mp sigmask |= rmp->mp sigact[signo].sa mask;
19930
              if (sigflags & SA NODEFER)
19931
                      sigdelset(&rmp->mp_sigmask, signo);
19932
19933
                      sigaddset(&rmp->mp_sigmask, signo);
19934
19935
              if (sigflags & SA_RESETHAND) {
19936
                      sigdelset(&rmp->mp_catch, signo);
19937
                      rmp->mp_sigact[signo].sa_handler = SIG_DFL;
19938
19939
19940
              if (OK == (s=sys_sigsend(slot, &sm))) {
19941
19942
                      sigdelset(&rmp->mp_sigpending, signo);
                      /* If process is hanging on PAUSE, WAIT, SIGSUSPEND, tty,
19943
19944
                       * pipe, etc., release it.
19945
19946
                      unpause(slot);
19947
                      return;
19948
              panic(__FILE__, "warning, sys_sigsend failed", s);
19949
19950
        else if (sigismember(&rmp->mp_sig2mess, signo)) {
19951
19952
              if (OK != (s=sys_kill(slot,signo)))
19953
                     panic(__FILE__, "warning, sys_kill failed", s);
19954
              return;
19955
19956
19957
      doterminate:
19958
        /* Signal should not or cannot be caught. Take default action. */
19959
         if (sigismember(&ign_sset, signo)) return;
19960
19961
         rmp->mp_sigstatus = (char) signo;
19962
         if (sigismember(&core_sset, signo)) {
19963
              /* Switch to the user's FS environment and dump core. */
19964
              tell_fs(CHDIR, slot, FALSE, 0);
19965
              dump_core(rmp);
19966
19967
        pm_exit(rmp, 0);
                                     /* terminate process */
19968
19970
19971
                       check sig
19972
       19973 PUBLIC int check_sig(proc_id, signo)
19974 pid t proc id;
                                   /* pid of proc to sig, or 0 or -1, or -pgrp */
```

```
Feb 25, 11 15:18
                                       book.txt
                                                                         Page 269/393
       File: Page: 906 servers/pm/signal.c
19975
                                       /* signal to send to process (0 to NSIG) */
       int signo;
19976
19977
       /* Check to see if it is possible to send a signal. The signal may have to be
19978
       * sent to a group of processes. This routine is invoked by the KILL system
19979
        * call, and also when the kernel catches a DEL or other signal.
19980
19981
19982
         register struct mproc *rmp;
19983
         int count;
                                       /* count # of signals sent */
19984
         int error_code;
19985
19986
         if (signo < 0 | signo > NSIG) return(EINVAL);
19987
19988
         /* Return EINVAL for attempts to send SIGKILL to INIT alone. */
19989
         if (proc id == INIT PID && signo == SIGKILL) return(EINVAL);
19990
19991
         /* Search the proc table for processes to signal. (See forkexit.c about
19992
          * pid magic.)
19993
19994
         count = 0;
         error_code = ESRCH;
19995
19996
         for (rmp = &mproc[0]; rmp < &mproc[NR_PROCS]; rmp++) {</pre>
19997
               if (!(rmp->mp_flags & IN_USE)) continue;
               if ((rmp->mp_flags & ZOMBIE) && signo != 0) continue;
19998
19999
20000
               /* Check for selection. */
               if (proc_id > 0 && proc_id != rmp->mp_pid) continue;
20001
20002
               if (proc_id == 0 && mp->mp_procgrp != rmp->mp_procgrp) continue;
               if (proc_id == -1 && rmp->mp_pid <= INIT_PID) continue;
20003
               if (proc_id < -1 && rmp->mp_procgrp != -proc_id) continue;
20004
20005
20006
               /* Check for permission. */
20007
               if (mp->mp_effuid != SUPER_USER
                   && mp->mp_realuid != rmp->mp_realuid
20008
20009
                   && mp->mp_effuid != rmp->mp_realuid
20010
                   && mp->mp_realuid != rmp->mp_effuid
20011
                   && mp->mp_effuid != rmp->mp_effuid) {
                       error_code = EPERM;
20012
20013
                       continue;
20014
20015
20016
               count++;
               if (signo == 0) continue;
20017
20018
20019
               /* 'sig proc' will handle the disposition of the signal. The
                * signal may be caught, blocked, ignored, or cause process
20020
20021
                * termination, possibly with core dump.
20022
20023
               sig_proc(rmp, signo);
20024
20025
               if (proc_id > 0) break; /* only one process being signaled */
20026
20027
20028
         /* If the calling process has killed itself, don't reply. */
         if ((mp->mp_flags & (IN_USE | ZOMBIE)) != IN_USE) return(SUSPEND);
20029
20030
         return(count > 0 ? OK : error_code);
20031
```

```
Feb 25, 11 15:18
                                  book.txt
                                                               Page 270/393
      File: Page: 907 servers/pm/signal.c
20033
     20034
                                 check_pending
      20036 PUBLIC void check_pending(rmp)
20037
     register struct mproc *rmp;
20038
20039
        /* Check to see if any pending signals have been unblocked. The
        * first such signal found is delivered.
20040
20041
20042
        \mbox{\ensuremath{^{\star}}} If multiple pending unmasked signals are found, they will be
         * delivered sequentially.
20043
20044
20045
        * There are several places in this file where the signal mask is
         * changed. At each such place, check_pending() should be called to
20046
20047
        * check for newly unblocked signals.
20048
20049
20050
       int i;
20051
20052
        for (i = 1; i <= _NSIG; i++) {
            if (sigismember(&rmp->mp_sigpending, i) &&
20053
20054
                    !sigismember(&rmp->mp_sigmask, i)) {
20055
                    sigdelset(&rmp->mp_sigpending, i);
20056
                    sig proc(rmp, i);
20057
                   break;
20058
20059
20060 }
20062 /*========*
20063
                                 unpause
20064
     *-----*
20065 PRIVATE void unpause(pro)
20066 int pro;
                                 /* which process number */
20067
20068 /* A signal is to be sent to a process. If that process is hanging on a
20069
      * system call, the system call must be terminated with EINTR. Possible
20070
      * calls are PAUSE, WAIT, READ and WRITE, the latter two for pipes and ttys.
20071
      * First check if the process is hanging on an PM call. If not, tell FS,
20072
      * so it can check for READs and WRITEs from pipes, ttys and the like.
20073
20074
20075
       register struct mproc *rmp;
20076
20077
       rmp = &mproc[pro];
20078
20079
        /* Check to see if process is hanging on a PAUSE, WAIT or SIGSUSPEND call. */
20080
        if (rmp->mp_flags & (PAUSED | WAITING | SIGSUSPENDED)) {
20081
             rmp->mp_flags &= ~(PAUSED | WAITING | SIGSUSPENDED);
20082
             setreply(pro, EINTR);
20083
             return;
20084
20085
20086
        /* Process is not hanging on an PM call. Ask FS to take a look. */
20087
       tell_fs(UNPAUSE, pro, 0, 0);
20088 }
```

```
book.txt
Feb 25, 11 15:18
                                                                   Page 271/393
      File: Page: 908 servers/pm/signal.c
20090
     20091
                                    dump core
      20092
20093 PRIVATE void dump_core(rmp)
20094
      register struct mproc *rmp;
                                    /* whose core is to be dumped */
20095
20096
      /* Make a core dump on the file "core", if possible. */
20097
20098
        int s, fd, seq, slot;
20099
        vir_bytes current_sp;
20100
        long trace data, trace off;
20101
20102
        slot = (int) (rmp - mproc);
20103
        /* Can core file be written? We are operating in the user's FS environment,
20104
20105
         * so no special permission checks are needed.
20106
20107
        if (rmp->mp_realuid != rmp->mp_effuid) return;
        if ( (fd = open(core_name, O_WRONLY | O_CREAT | O_TRUNC | O_NONBLOCK,
20108
20109
                                                   CORE_MODE)) < 0) return;
20110
        rmp->mp_sigstatus |= DUMPED;
20111
20112
        /* Make sure the stack segment is up to date.
         * We don't want adjust() to fail unless current_sp is preposterous,
20113
20114
         * but it might fail due to safety checking. Also, we don't really want
20115
         * the adjust() for sending a signal to fail due to safety checking.
         * Maybe make SAFETY_BYTES a parameter.
20116
20117
        if ((s=get_stack_ptr(slot, &current_sp)) != OK)
20118
             panic( FILE , "couldn't get new stack pointer", s);
20119
        adjust(rmp, rmp->mp_seg[D].mem_len, current_sp);
20120
20121
20122
        /* Write the memory map of all segments to begin the core file. */
20123
        if (write(fd, (char *) rmp->mp_seg, (unsigned) sizeof rmp->mp_seg)
20124
            != (unsigned) sizeof rmp->mp_seg) {
20125
             close(fd);
20126
             return;
20127
20128
20129
        /* Write out the whole kernel process table entry to get the regs. */
20130
        trace off = 0;
20131
        while (sys trace(T GETUSER, slot, trace off, &trace data) == OK)
              if (write(fd, (char *) &trace_data, (unsigned) sizeof (long))
20132
20133
                 != (unsigned) sizeof (long)) {
                     close(fd);
20134
                     return;
20135
20136
20137
              trace_off += sizeof (long);
20138
20139
20140
        /* Loop through segments and write the segments themselves out. */
20141
        for (seg = 0; seg < NR_LOCAL_SEGS; seg++) {
20142
             rw_seg(1, fd, slot, seg,
20143
                     (phys bytes) rmp->mp seq[seq].mem len << CLICK SHIFT);
20144
20145
        close(fd);
20146
```

```
Feb 25, 11 15:18
                                 book.txt
                                                            Page 272/393
      File: Page: 909 servers/pm/timers.c
servers/pm/timers.c
20200 /* PM watchdog timer management. These functions in this file provide
20201 * a convenient interface to the timers library that manages a list of
      * watchdog timers. All details of scheduling an alarm at the CLOCK task
20202
20203
      * are hidden behind this interface.
      * Only system processes are allowed to set an alarm timer at the kernel.
20204
       * Therefore, the PM maintains a local list of timers for user processes
20205
20206
      * that requested an alarm signal.
20207
      * The entry points into this file are:
20208
      * pm_set_timer: reset and existing or set a new watchdog timer
* pm_expire_timers: check for expired timers and run watchdog functions
20209
20210
         pm_cancel_timer: remove a time from the list of timers
20211
20212 *
20213 */
20214
20215 #include "pm.h"
20216
20217 #include <timers.h>
20218 #include <minix/syslib.h>
20219 #include <minix/com.h>
20220
20221 PRIVATE timer t *pm timers = NULL;
20222
20223 /*----*
20224
                              pm set timer
      *-----*/
20225
20226 PUBLIC void pm_set_timer(timer_t *tp, int ticks, tmr_func_t watchdog, int arg)
20227
20228
             int r;
20229
            clock_t now, prev_time = 0, next_time;
20230
20231
            if ((r = getuptime(&now)) != OK)
                   panic(__FILE__, "PM couldn't get uptime", NO_NUM);
20232
20233
            /* Set timer argument and add timer to the list. */
20234
20235
            tmr arg(tp)->ta int = arg;
            prev time = tmrs settimer(&pm timers,tp,now+ticks,watchdog,&next time);
20236
20237
20238
             /* Reschedule our synchronous alarm if necessary. */
             if (! prev_time | | prev_time > next_time) {
20239
20240
                   if (sys_setalarm(next_time, 1) != OK)
20241
                          panic(__FILE__, "PM set timer couldn't set alarm.", NO_N
TTM);
20242
20243
20244
             return;
20245 }
20247 /*=========*
20248
                              pm_expire_timers
      *-----*
20249
20250 PUBLIC void pm_expire_timers(clock_t now)
20251 {
20252
             clock_t next_time;
20253
20254
            /* Check for expired timers and possibly reschedule an alarm. */
```

```
Feb 25, 11 15:18
                              book.txt
                                                        Page 273/393
     File: Page: 910 servers/pm/timers.c
20255
           tmrs_exptimers(&pm_timers, now, &next_time);
20256
           if (next_time > 0) {
20257
                 if (sys_setalarm(next_time, 1) != OK)
20258
                        panic(__FILE__, "PM expire timer couldn't set alarm.", N
O NUM);
20259
20260
20262
     /*========*
20263
                            pm_cancel_timer
20264
      20265
     PUBLIC void pm_cancel_timer(timer_t *tp)
20266
20267
            clock_t next_time, prev_time;
20268
           prev time = tmrs clrtimer(&pm timers, tp, &next time);
20269
20270
            /* If the earliest timer has been removed, we have to set the alarm to
20271
         * the next timer, or cancel the alarm altogether if the last timer has
20272
         * been cancelled (next_time will be 0 then).
20273
20274
            if (prev_time < next_time | | ! next_time) {</pre>
20275
                 if (sys_setalarm(next_time, 1) != OK)
20276
                        panic(__FILE__, "PM expire timer couldn't set alarm.", N
O NUM);
20277
20278
servers/pm/time.c
20300 /* This file takes care of those system calls that deal with time.
20301
     * The entry points into this file are
20302
     * do_time:
                     perform the TIME system call
20303
                        perform the STIME system call
20304
      * do stime:
     * do_times:
20305
                         perform the TIMES system call
20306
20307
20308 #include "pm.h"
20309 #include <minix/callnr.h>
20310 #include <minix/com.h>
20311 #include <signal.h>
20312 #include "mproc.h"
20313 #include "param.h"
20314
20315 PRIVATE time_t boottime;
20316
20318 *
                            do_time
20320 PUBLIC int do_time()
20321
20322 /* Perform the time(tp) system call. This returns the time in seconds since
     * 1.1.1970. MINIX is an astrophysically naive system that assumes the earth
20323
      * rotates at a constant rate and that such things as leap seconds do not
      * exist.
20325
20326
20327
       clock t uptime;
20328
       int s;
20329
```

```
Feb 25, 11 15:18
                                 book.txt
                                                              Page 274/393
     File: Page: 911 servers/pm/time.c
20330
       if ( (s=getuptime(&uptime)) != OK)
20331
            panic(__FILE__, "do_time couldn't get uptime", s);
20332
20333
       mp->mp reply.reply time = (time t) (boottime + (uptime/HZ));
20334
       mp->mp_reply_reply_utime = (uptime%HZ)*1000000/HZ;
20335
       return(OK);
20336
20338
     /*-----
20339
                                 do_stime
20340
      *-----*
20341 PUBLIC int do stime()
20342
20343 /* Perform the stime(tp) system call. Retrieve the system's uptime (ticks
      * since boot) and store the time in seconds at system boot in the global
20344
20345
      * variable 'boottime'.
20346
20347
       clock_t uptime;
20348
       int s;
20349
20350
       if (mp->mp_effuid != SUPER_USER) {
20351
          return(EPERM);
20352
20353
       if ( (s=getuptime(&uptime)) != OK)
           panic(__FILE__, "do_stime couldn't get uptime", s);
20354
20355
       boottime = (long) m_in.stime - (uptime/HZ);
20356
20357
       /* Also inform FS about the new system time. */
20358
       tell_fs(STIME, boottime, 0, 0);
20359
20360
       return(OK);
20361
20363
     /*----*
20364
                                 do times
20365
      *-----*/
20366
     PUBLIC int do times()
20367
20368
      /* Perform the times(buffer) system call. */
20369
       register struct mproc *rmp = mp;
20370
       clock t t[5];
20371
       int s;
20372
20373
       if (OK != (s=sys_times(who, t)))
        panic(__FILE__, "do_times couldn't get times", s);
20374
20375
       rmp->mp_reply.reply_t1 = t[0];
                                              /* user time */
20376
       rmp->mp_reply.reply_t2 = t[1];
                                               /* system time */
20377
       rmp->mp_reply.reply_t3 = rmp->mp_child_utime; /* child user time */
20378
       rmp->mp_reply.reply_t4 = rmp->mp_child_stime; /* child system time */
20379
       rmp->mp_reply.reply_t5 = t[4];
                                              /* uptime since boot */
20380
20381
       return(OK);
20382 }
```

```
book.txt
Feb 25, 11 15:18
                                                              Page 275/393
      File: Page: 912 servers/pm/getset.c
servers/pm/getset.c
20400 /* This file handles the 4 system calls that get and set uids and gids.
20401 * It also handles getpid(), setsid(), and getpgrp(). The code for each
20402
      * one is so tiny that it hardly seemed worthwhile to make each a separate
20403 * function.
20404 */
20405
20406 #include "pm.h"
20407 #include <minix/callnr.h>
20408 #include <signal.h>
20409 #include "mproc.h"
20410 #include "param.h"
20411
20412 /*----*
20413 *
                                do getset
20414 *=========*/
20415 PUBLIC int do_getset()
20416
20417 /* Handle GETUID, GETGID, GETPID, GETPGRP, SETUID, SETGID, SETSID. The four
      * GETs and SETSID return their primary results in 'r'. GETUID, GETGID, and
20418
20419
       * GETPID also return secondary results (the effective IDs, or the parent
20420
       * process ID) in 'reply_res2', which is returned to the user.
20421
20422
20423
        register struct mproc *rmp = mp;
        register int r;
20424
20425
20426
        switch(call_nr) {
20427
            case GETUID:
20428
                   r = rmp->mp_realuid;
20429
                    rmp->mp_reply.reply_res2 = rmp->mp_effuid;
20430
                    break;
20431
20432
             case GETGID:
20433
                    r = rmp->mp realgid;
20434
                    rmp->mp_reply.reply_res2 = rmp->mp_effgid;
20435
                    break;
20436
20437
             case GETPID:
20438
                    r = mproc[who].mp_pid;
20439
                    rmp->mp_reply.reply_res2 = mproc[rmp->mp_parent].mp_pid;
                    break;
20440
20441
20442
             case SETUID:
20443
                   if (rmp->mp_realuid != (uid_t) m_in.usr_id &&
20444
                                 rmp->mp_effuid != SUPER_USER)
                          return(EPERM);
20445
20446
                    rmp->mp_realuid = (uid_t) m_in.usr_id;
20447
                    rmp->mp_effuid = (uid_t) m_in.usr_id;
20448
                    tell_fs(SETUID, who, rmp->mp_realuid, rmp->mp_effuid);
20449
                    r = OK;
20450
                    break;
20451
             case SETGID:
20452
20453
                    if (rmp->mp_realgid != (gid_t) m_in.grp_id &&
20454
                                 rmp->mp effuid != SUPER USER)
```

```
book.txt
 Feb 25, 11 15:18
                                                             Page 276/393
      File: Page: 913 servers/pm/getset.c
20455
                          return(EPERM);
20456
                   rmp->mp_realgid = (gid_t) m_in.grp_id;
                   rmp->mp_effgid = (gid_t) m_in.grp_id;
20457
20458
                   tell_fs(SETGID, who, rmp->mp_realgid, rmp->mp_effgid);
20459
                   r = OK;
20460
                   break;
20461
             case SETSID:
20462
20463
                   if (rmp->mp_procgrp == rmp->mp_pid) return(EPERM);
20464
                    rmp->mp_procgrp = rmp->mp_pid;
20465
                   tell_fs(SETSID, who, 0, 0);
20466
                   /* fall through */
20467
20468
             case GETPGRP:
20469
                   r = rmp->mp procgrp;
20470
                   break;
20471
20472
             default:
20473
                   r = EINVAL;
20474
                   break;
20475
20476
       return(r);
20477 }
servers/pm/misc.c
20500 /* Miscellaneous system calls.
                                                     Author: Kees J. Bot.
20501 *
                                                            31 Mar 2000
20502
     * The entry points into this file are:
20503
       * do_reboot: kill all processes, then reboot system
* do_syrctl: process manager control
20504
20505
          do_getsysinfo: request copy of PM data structure (Jorrit N. Herder)
20506
          do_getprocnr: lookup process slot number (Jorrit N. Herder)
20507
          do_memalloc: allocate a chunk of memory (Jorrit N. Herder)
20508
          do memfree: deallocate a chunk of memory (Jorrit N. Herder)
20509
      * do_getsetpriority: get/set process priority
20510 */
20511
20512 #include "pm.h"
20513 #include <minix/callnr.h>
20514 #include <signal.h>
20515 #include <sys/svrctl.h>
20516 #include <sys/resource.h>
20517 #include <minix/com.h>
20518 #include <string.h>
20519 #include "mproc.h"
20520 #include "param.h"
20521
20522 /*==========*
20523
                                do allocmem
20524
       *-----*/
20525
      PUBLIC int do_allocmem()
20526
        vir_clicks mem_clicks;
20527
20528
        phys_clicks mem_base;
20529
```

```
Feb 25, 11 15:18
                                 book.txt
                                                            Page 277/393
      File: Page: 914 servers/pm/misc.c
20530
       mem_clicks = (m_in.memsize + CLICK_SIZE -1 ) >> CLICK_SHIFT;
20531
       mem_base = alloc_mem(mem_clicks);
       if (mem_base == NO_MEM) return(ENOMEM);
20532
20533
       mp->mp_reply.membase = (phys_bytes) (mem_base << CLICK_SHIFT);</pre>
20534
       return(OK);
20535
20537
     /*----*
20538
                              do freemem
      20539
20540
      PUBLIC int do freemem()
20541
20542
       vir clicks mem clicks;
20543
       phys_clicks mem_base;
20544
20545
       mem_clicks = (m_in.memsize + CLICK_SIZE -1 ) >> CLICK_SHIFT;
20546
       mem_base = (m_in.membase + CLICK_SIZE -1 ) >> CLICK_SHIFT;
20547
       free_mem(mem_base, mem_clicks);
20548
       return(OK);
20549
20551 /*=========*
20552 *
                      do_getsysinfo
20553
      20554 PUBLIC int do_getsysinfo()
20555
20556
       struct mproc *proc addr;
20557
       vir_bytes src_addr, dst_addr;
20558
       struct kinfo kinfo;
20559
       size t len;
20560
       int s;
20561
20562
       switch(m_in.info_what) {
20563
                                        /* kernel info is obtained via PM */
       case SI_KINFO:
20564
            sys_getkinfo(&kinfo);
20565
            src_addr = (vir_bytes) &kinfo;
20566
            len = sizeof(struct kinfo);
20567
            break;
20568
       case SI PROC ADDR:
                                        /* get address of PM process table */
20569
            proc_addr = &mproc[0];
20570
            src_addr = (vir_bytes) &proc_addr;
20571
            len = sizeof(struct mproc *);
20572
            break;
20573
       case SI_PROC_TAB:
                                        /* copy entire process table */
20574
            src addr = (vir bytes) mproc;
20575
            len = sizeof(struct mproc) * NR PROCS;
20576
            break;
20577
       default:
20578
            return(EINVAL);
20579
20580
20581
       dst_addr = (vir_bytes) m_in.info_where;
20582
       if (OK != (s=sys_datacopy(SELF, src_addr, who, dst_addr, len)))
20583
            return(s);
20584
       return(OK);
20585
```

```
book.txt
Feb 25, 11 15:18
                                                             Page 278/393
      File: Page: 915 servers/pm/misc.c
20587
     20588
                               do_getprocnr
20589
      20590
     PUBLIC int do_getprocnr()
20591
20592
       register struct mproc *rmp;
20593
       static char search_key[PROC_NAME_LEN+1];
20594
       int key_len;
20595
       int s;
20596
20597
       if (m_in.pid >= 0) {
                                               /* lookup process by pid */
20598
            for (rmp = &mproc[0]; rmp < &mproc[NR_PROCS]; rmp++) {
20599
                   if ((rmp->mp_flags & IN_USE) && (rmp->mp_pid==m_in.pid)) {
20600
                          mp->mp_reply.procnr = (int) (rmp - mproc);
20601
                          return(OK);
20602
20603
20604
            return(ESRCH);
20605
       } else if (m_in.namelen > 0) {
                                              /* lookup process by name */
20606
            key_len = MIN(m_in.namelen, PROC_NAME_LEN);
            if (OK != (s=sys_datacopy(who, (vir_bytes) m_in.addr,
20607
20608
                          SELF, (vir_bytes) search_key, key_len)))
20609
                   return(s);
            search key[key len] = '\0';
20610
                                      /* terminate for safety */
            for (rmp = &mproc[0]; rmp < &mproc[NR_PROCS]; rmp++) {
20611
20612
                   if ((rmp->mp_flags & IN_USE) &&
20613
                          strncmp(rmp->mp_name, search_key, key_len)==0) {
20614
                          mp->mp_reply.procnr = (int) (rmp - mproc);
20615
                          return(OK);
20616
20617
20618
            return(ESRCH);
20619
       } else {
                                        /* return own process number */
20620
            mp->mp_reply.procnr = who;
20621
20622
       return(OK);
20623
20625
     do_reboot
20626
20627
      *=======*/
      #define REBOOT CODE "delay; boot"
20628
     PUBLIC int do_reboot()
20629
20630
       char monitor code[32*sizeof(char *)];
20631
20632
       int code len;
20633
       int abort_flag;
20634
20635
       if (mp->mp_effuid != SUPER_USER) return(EPERM);
20636
20637
       switch (m_in.reboot_flag) {
20638
       case RBT HALT:
20639
       case RBT PANIC:
20640
       case RBT RESET:
20641
            abort_flag = m_in.reboot_flag;
20642
            break;
       case RBT REBOOT:
20643
20644
            code len = strlen(REBOOT CODE) + 1;
20645
            strncpy(monitor_code, REBOOT_CODE, code_len);
20646
            abort flag = RBT MONITOR;
```

```
book.txt
Feb 25, 11 15:18
                                                                     Page 279/393
       File: Page: 916 servers/pm/misc.c
20647
              break;
20648
        case RBT_MONITOR:
20649
              code_len = m_in.reboot_strlen + 1;
20650
              if (code_len > sizeof(monitor_code)) return(EINVAL);
              if (sys_datacopy(who, (vir_bytes) m_in.reboot_code,
20651
20652
                      PM_PROC_NR, (vir_bytes) monitor_code,
20653
                      (phys_bytes) (code_len)) != OK) return(EFAULT);
20654
              if (monitor_code[code_len-1] != 0) return(EINVAL);
              abort flag = RBT MONITOR;
20655
20656
              break;
20657
        default:
20658
              return(EINVAL);
20659
20660
                                            /* kill all processes except init */
20661
        check sig(-1, SIGKILL);
20662
        tell_fs(REBOOT,0,0,0);
                                            /* tell FS to prepare for shutdown */
20663
20664
        /* Ask the kernel to abort. All system services, including the PM, will
20665
         * get a HARD_STOP notification. Await the notification in the main loop.
20666
20667
        sys_abort(abort_flag, PM_PROC_NR, monitor_code, code_len);
20668
        return(SUSPEND);
                                            /* don't reply to killed process */
20669
20671
      /*==================================
20672
                                    do getsetpriority
20673
       20674
      PUBLIC int do_getsetpriority()
20675
20676
              int arg_which, arg_who, arg_pri;
20677
              int rmp_nr;
20678
              struct mproc *rmp;
20679
20680
              arg_which = m_in.ml_i1;
20681
              arg_who = m_in.m1_i2;
20682
              arg_pri = m_in.ml_i3; /* for SETPRIORITY */
20683
20684
              /* Code common to GETPRIORITY and SETPRIORITY. */
20685
20686
              /* Only support PRIO_PROCESS for now. */
20687
              if (arg which != PRIO PROCESS)
                      return(EINVAL);
20688
20689
20690
              if (arg_who == 0)
20691
                      rmp_nr = who;
20692
              else
20693
                      if ((rmp_nr = proc_from_pid(arg_who)) < 0)</pre>
20694
                             return(ESRCH);
20695
20696
              rmp = &mproc[rmp_nr];
20697
20698
              if (mp->mp_effuid != SUPER_USER &&
                 mp->mp_effuid != rmp->mp_effuid && mp->mp_effuid != rmp->mp_realuid)
20699
20700
                      return EPERM;
20701
20702
              /* If GET, that's it. */
              if (call nr == GETPRIORITY) {
20703
20704
                      return(rmp->mp_nice - PRIO_MIN);
20705
20706
```

```
book.txt
Feb 25, 11 15:18
                                                                    Page 280/393
      File: Page: 917 servers/pm/misc.c
20707
              /* Only root is allowed to reduce the nice level. */
20708
              if (rmp->mp_nice > arg_pri && mp->mp_effuid != SUPER_USER)
20709
                     return(EACCES);
20710
20711
              /* We're SET, and it's allowed. Do it and tell kernel. */
20712
              rmp->mp_nice = arg_pri;
20713
              return sys_nice(rmp_nr, arg_pri);
20714
20716
      /*-----*
20717
                                    do svrctl
20718
       *-----*
      PUBLIC int do_svrctl()
20719
20720
20721
        int s, req;
20722
        vir_bytes ptr;
20723
      #define MAX_LOCAL_PARAMS 2
20724
        static struct {
20725
              char name[30];
20726
              char value[30];
20727
        } local_param_overrides[MAX_LOCAL_PARAMS];
20728
        static int local_params = 0;
20729
20730
        reg = m in.svrctl reg;
20731
        ptr = (vir_bytes) m_in.svrctl_argp;
20732
20733
          Is the request indeed for the MM? */
20734
        if (((req >> 8) & 0xFF) != 'M') return(EINVAL);
20735
20736
        /* Control operations local to the PM. */
20737
        switch(reg) {
20738
        case MMSETPARAM:
20739
        case MMGETPARAM: {
20740
            struct sysgetenv sysgetenv;
20741
            char search_key[64];
            char *val_start;
20742
20743
            size_t val_len;
20744
            size_t copy_len;
20745
20746
            /* Copy sysgetenv structure to PM. */
20747
            if (sys_datacopy(who, ptr, SELF, (vir_bytes) &sysgetenv,
20748
                    sizeof(sysgetenv)) != OK) return(EFAULT);
20749
20750
            /* Set a param override? */
20751
            if (reg == MMSETPARAM) {
20752
              if (local_params >= MAX_LOCAL_PARAMS) return ENOSPC;
20753
              if (sysgetenv.keylen <= 0
               || sysgetenv.keylen >=
20754
20755
                      sizeof(local_param_overrides[local_params].name)
20756
                 sysgetenv.vallen <= 0
20757
                 sysgetenv.vallen >=
20758
                      sizeof(local_param_overrides[local_params].value))
20759
                     return EINVAL:
20760
20761
                if ((s = sys_datacopy(who, (vir_bytes) sysgetenv.key,
20762
                  SELF, (vir_bytes) local_param_overrides[local_params].name,
20763
                    sysgetenv.keylen)) != OK)
20764
                     return s;
                if ((s = sys_datacopy(who, (vir_bytes) sysgetenv.val,
20765
20766
                  SELF, (vir bytes) local param overrides[local params].value,
```

```
Feb 25, 11 15:18
                                        book.txt
                                                                          Page 281/393
       File: Page: 918 servers/pm/misc.c
20767
                     sysgetenv.keylen)) != OK)
20768
                       return s;
20769
                   local_param_overrides[local_params].name[sysgetenv.keylen] = '\0';
                   local_param_overrides[local_params].value[sysgetenv.vallen] = '\0';
20770
20771
20772
               local_params++;
20773
20774
               return OK;
20775
20776
20777
             if (sysgetenv.keylen == 0) {
                                                /* copy all parameters */
20778
                 val start = monitor params;
                 val_len = sizeof(monitor_params);
20779
20780
                                                /* lookup value for key */
20781
             else {
20782
                 int p;
20783
                 /* Try to get a copy of the requested key. */
20784
                 if (sysgetenv.keylen > sizeof(search_key)) return(EINVAL);
20785
                 if ((s = sys_datacopy(who, (vir_bytes) sysgetenv.key,
20786
                         SELF, (vir_bytes) search_key, sysgetenv.keylen)) != OK)
20787
20788
20789
                 /* Make sure key is null-terminated and lookup value.
                  * First check local overrides.
20790
20791
20792
                 search_key[sysgetenv.keylen-1]= '\0';
                 for(p = 0; p < local_params; p++) {</pre>
20793
20794
                       if (!strcmp(search_key, local_param_overrides[p].name)) {
20795
                               val_start = local_param_overrides[p].value;
20796
20797
20798
20799
                 if (p >= local_params && (val_start = find_param(search_key)) == NULL)
20800
                      return(ESRCH);
20801
                 val_len = strlen(val_start) + 1;
20802
20803
             /* See if it fits in the client's buffer. */
20804
20805
             if (val_len > sysgetenv.vallen)
20806
               return E2BIG;
20807
20808
             /* Value found, make the actual copy (as far as possible). */
             copy_len = MIN(val_len, sysgetenv.vallen);
20809
20810
             if ((s=sys_datacopy(SELF, (vir_bytes) val_start,
20811
                     who, (vir_bytes) sysgetenv.val, copy_len)) != OK)
20812
                 return(s);
20813
20814
             return OK;
20815
20816
         default:
20817
               return(EINVAL);
20818
20819
```

```
Feb 25, 11 15:18
                                book.txt
                                                            Page 282/393
      File: Page: 919 servers/fs/fs.h
servers/fs/fs.h
20900 /* This is the master header for fs. It includes some other files
20901
      * and defines the principal constants.
20902
20903 #define _POSIX_SOURCE
                                /* tell headers to include POSIX stuff */
20904
      #define _MINIX
                                /* tell headers to include MINIX stuff */
                            1
20905
      #define SYSTEM
                            1
                                /* tell headers that this is the kernel */
20906
      #define VERBOSE
20907
                                /* show messages during initialization? */
20908
      /* The following are so basic, all the *.c files get them automatically. */
20909
20910 #include <minix/config.h>
                                /* MUST be first */
20911 #include <ansi.h>
                                /* MUST be second */
20912 #include <sys/types.h>
20913 #include <minix/const.h>
20914 #include <minix/type.h>
20915 #include <minix/dmap.h>
20916
20917
      #include <limits.h>
      #include <errno.h>
20918
20919
20920 #include <minix/syslib.h>
20921 #include <minix/sysutil.h>
20922
20923
      #include "const.h"
20924 #include "type.h"
20925 #include "proto.h"
20926 #include "glo.h"
servers/fs/const.h
21000 /* Tables sizes */
21001 #define V1 NR DZONES
                                /* # direct zone numbers in a V1 inode */
                          9
                                /* total # zone numbers in a V1 inode */
21002 #define V1_NR_TZONES
21003 #define V2_NR_DZONES
                                /* # direct zone numbers in a V2 inode */
21004 #define V2 NR TZONES
                               /* total # zone numbers in a V2 inode */
                           1.0
21005
21006
      #define NR_FILPS
                          128
                                /* # slots in filp table */
                                /* # slots in "in core" inode table */
21007 #define NR_INODES
21008 #define NR_SUPERS
                            8
                                /* # slots in super block table */
21009 #define NR_LOCKS
                            8
                                /* # slots in the file locking table */
21010
* taking the sizes of small objects so that there are no surprises like
21012
      * (small) long constants being passed to routines expecting an int.
21013
21014
21015 #define usizeof(t) ((unsigned) sizeof(t))
21016
      /* File system types. */
21017
21018 #define SUPER_MAGIC 0x137F
                                /* magic number contained in super-block */
21019 #define SUPER REV
                        0 \times 7 F13
                                /* magic # when 68000 disk read on PC or vv */
```

```
book.txt
Feb 25, 11 15:18
                                                                      Page 283/393
       File: Page: 920 servers/fs/const.h
21021 #define SUPER_V2_REV 0x6824
                                     /* V2 magic written on PC, read on 68K or vv */
21022 #define SUPER_V3 0x4d5a
                                     /* magic # for V3 file systems */
21023
21024 #define V1
                                     /* version number of V1 file systems */
21025 #define V2
                                 2 /* version number of V2 file systems */
21026 #define V3
                                     /* version number of V3 file systems */
21027
21028 /* Miscellaneous constants */
21029 #define SU_UID ((uid_t) 0)
                                    /* super_user's uid_t */
21030 #define SYS_UID ((uid_t) 0)
                                     /* uid_t for processes MM and INIT */
21031 #define SYS_GID ((gid_t) 0)
                                    /* gid_t for processes MM and INIT */
                        0 /* forces get_block to do disk read */
1 /* prevents get_block from doing disk read */
21032 #define NORMAL
21033 #define NO_READ
                                2 /* tells get_block not to read or mark dev */
21034 #define PREFETCH
21035
21036 #define XPIPE (-NR_TASKS-1) /* used in fp_task when susp'd on pipe */
21037 #define XLOCK (-NR_TASKS-2) /* used in fp_task when susp'd on lock */
21038 #define XPOPEN (-NR_TASKS-3)
                                     /* used in fp_task when susp'd on pipe open */
                                     /* used in fp_task when susp'd on select */
21039 #define XSELECT (-NR_TASKS-4)
21040
21041 #define NO_BIT ((bit_t) 0) /* returned by alloc_bit() to signal failure */
21042
21043 #define DUP MASK
                              0100 /* mask to distinguish dup2 from dup */
21044
                                 0 /* tells search_dir to lookup string */
21045 #define LOOK UP
21046 #define ENTER
                                1 /* tells search dir to make dir entry */
21047 #define DELETE
                                 2 /* tells search_dir to delete entry */
                                3 /* tells search_dir to ret. OK or ENOTEMPTY */
21048 #define IS_EMPTY
21049
                              0  /* disk and memory copies identical */
1  /* disk and memory copies differ */
21050 #define CLEAN
21051 #define DIRTY
                                    /* disk and memory copies differ */
21052 #define ATIME
                                   /* set if atime field needs updating */
21053 #define CTIME
                               004
                                   /* set if ctime field needs updating */
/* set if mtime field needs updating */
21054 #define MTIME
                              010
21055
21056 #define BYTE_SWAP 0 /* tells conv2/conv4 to swap bytes */
21057
21058 #define END_OF_FILE (-104) /* eof detected */
21059
21060 #define ROOT_INODE
                                             /* inode number for root directory */
                                           /* block number of boot block */
21061 #define BOOT BLOCK ((block t) 0)
21062 #define SUPER_BLOCK_BYTES (1024)
                                             /* bytes offset */
21063 #define START_BLOCK 2
                                             /* first block of FS (not counting SB) *
21064
21065 #define DIR_ENTRY_SIZE
                                   usizeof (struct direct) /* # bytes/dir entry */
21066 #define NR_DIR_ENTRIES(b) ((b)/DIR_ENTRY_SIZE) /* # dir entries/blk */
21067 #define SUPER_SIZE usizeof (struct super_block) /* super_block size */
                              (V1_NR_DZONES*(b)) /* pipe size in bytes */
21068 #define PIPE_SIZE(b)
21069
21070 #define FS_BITMAP_CHUNKS(b) ((b)/usizeof (bitchunk_t))/* # map chunks/blk */
21071 #define FS_BITCHUNK_BITS (usizeof(bitchunk_t) * CHAR_BIT)
21071 #define FS_BITCHUNK_BITS
21072 #define FS_BITS_PER_BLOCK(b) (FS_BITMAP_CHUNKS(b) * FS_BITCHUNK_BITS)
21073
21074 /* Derived sizes pertaining to the V1 file system. */
21075 #define V1_ZONE_NUM_SIZE usizeof (zone1_t) /* # bytes in V1 zone */
21076 #define V1_INODE_SIZE
                                      usizeof (dl_inode) /* bytes in Vl dsk ino */
21077
21078 /* # zones/indir block */
21079 #define V1 INDIRECTS (STATIC BLOCK SIZE/V1 ZONE NUM SIZE)
```

```
Feb 25, 11 15:18
                                 book.txt
                                                             Page 284/393
      File: Page: 921 servers/fs/const.h
21080
21081 /* # V1 dsk inodes/blk */
21082 #define V1_INODES_PER_BLOCK (STATIC_BLOCK_SIZE/V1_INODE_SIZE)
21083
21084 /* Derived sizes pertaining to the V2 file system. */
21085 #define V2_ZONE_NUM_SIZE usizeof (zone_t) /* # bytes in V2 zone */
                                  usizeof (d2_inode) /* bytes in V2 dsk ino */
21086 #define V2_INODE_SIZE
21087 #define V2_INDIRECTS(b) ((b)/V2_ZONE_NUM_SIZE) /* # zones/indir block */
21088 #define V2_INODES_PER_BLOCK(b) ((b)/V2_INODE_SIZE)/* # V2 dsk inodes/blk */
servers/fs/type.h
21100 /* Declaration of the V1 inode as it is on the disk (not in core). */
                       /* V1.x disk inode */
21101 typedef struct {
                                /* file type, protection, etc. */
/* user id of the file's owner */
21102 mode_t d1_mode;
21103
       uid_t d1_uid;
                                /* current file size in bytes */
       off_t d1_size;
21104
21105
       time_t d1_mtime;
                                /* when was file data last changed */
21106
       u8_t d1_gid;
                                /* group number */
       u8_t d1_nlinks;
                                /* how many links to this file */
21107
       ul6_t dl_zone[V1_NR_TZONES]; /* block nums for direct, ind, and dbl ind */
21108
21109 } d1_inode;
21110
21111 /* Declaration of the V2 inode as it is on the disk (not in core). */
21112 typedef struct { /* V2.x disk inode */
                                /* file type, protection, etc. */
       mode_t d2_mode;
21113
                              /* how many links to this file. HACK! */
/* user id of the file's owner. */
/* group works.
       u16_t d2_nlinks;
21114
       uid_t d2_uid;
21115
       u16_t d2_gid;
21116
                                /* group number HACK! */
21117
       off_t d2_size;
                               /* current file size in bytes */
21118
        time_t d2_atime;
                                /* when was file data last accessed */
                                /* when was file data last changed */
21119
        time_t d2_mtime;
       time_t d2_ctime;
21120
                                /* when was inode data last changed */
        zone_t d2_zone[V2_NR_TZONES]; /* block nums for direct, ind, and dbl ind */
21121
21122 } d2_inode;
servers/fs/proto.h
21200 /* Function prototypes. */
21201
21202 #include "timers.h"
21203
21205 struct buf;
21206 struct filp;
21207 struct inode;
21208 struct super block;
21209
21210 /* cache.c */
21211 _PROTOTYPE( zone_t alloc_zone, (Dev_t dev, zone_t z)
21212 _PROTOTYPE( void flushall, (Dev_t dev)
                                                                  );
21213 _PROTOTYPE( void free_zone, (Dev_t dev, zone_t numb)
21214 PROTOTYPE( struct buf *get block, (Dev t dev, block t block,int only search));
```

Feb 25, 11 15:18		book.txt	Page 285/393
		922 servers/fs/proto.h	
21215	_PROTOTYPE(void invalidate, (Dev_t device)) <i>;</i>
21216	_PROTOTYPE(<pre>void put_block, (struct buf *bp, int block_type)</pre>);
21217		void rw_block, (struct buf *bp, int rw_flag));
21218 21219	_PROTOTYPE(void rw_scattered, (Dev_t dev,	lag));
21219		struct buf **bufq, int bufqsize, int rw_f	lag)),
21221	/* device.c	* /	
21222		int dev_open, (Dev_t dev, int proc, int flags));
21223		void dev_close, (Dev_t dev));
21224	_PROTOTYPE(int dev_io, (int op, Dev_t dev, int proc, void *buf,	
21225		off_t pos, int bytes, int flags));
21226	_PROTOTYPE(int gen_opcl, (int op, Dev_t dev, int proc, int flags);
21227 21228	_PROTOTYPE(void gen_io, (int task_nr, message *mess_ptr)););
21220	_PROTOTIPE(int no_dev, (int op, Dev_t dev, int proc, int flags) int tty_opcl, (int op, Dev_t dev, int proc, int flags int tty_opcl, (int op, Dev_t dev, int proc, int flag int clone_opcl, (int op, Dev_t dev, int proc, int flag int clone_opcl, (int op, Dev_t dev, int proc, int flag	;));
21230	PROTOTYPE (int ctty opel, (int op. Dev t dev. int proc. int flag	(s));
21231	PROTOTYPE (int clone opcl, (int op, Dev t dev, int proc, int fla	igs));
21232	_PROTOTYPE(void ctty_io, (int task_nr, message *mess_ptr));
21233	_PROTOTYPE(int do_ioctl, (void));
21234		int_do_setsid, (void));
21235	_PROTOTYPE(<pre>void dev_status, (message *)</pre>);
21236 21237	/* dmp.c */		
21237		<pre>int do_fkey_pressed, (void)</pre>);
21239	_PROTOTIFE(inc do_ikey_pressed, (void)	,,
21240	/* dmap.c *	/	
21241		int do_devctl, (void));
21242	_PROTOTYPE(<pre>void build_dmap, (void)</pre>);
21243	_PROTOTYPE(int map_driver, (int major, int proc_nr, int dev_styl	.e));
21244	/+ E:1-J	- +/	
21245 21246	/* filedes.	c ~/ struct filp *find_filp, (struct inode *rip, mode_t bi	.ts));
21247		int get_fd, (int start, mode_t bits, int *k, struct f	
21248		struct filp *get_filp, (int fild));
21249			
21250	/* inode.c	*/	
21251		struct inode *alloc_inode, (dev_t dev, mode_t bits)););
21252 21253	DDOTOTVDE/	<pre>void dup_inode, (struct inode *ip) void free_inode, (Dev_t dev, Ino_t numb)</pre>	١.
21253	_PROTOTIPE(struct inode *get_inode, (Dev_t dev, int numb));
21255	PROTOTYPE (void put_inode, (struct inode *rip));
21256	PROTOTYPE (void update times, (struct inode *rip));
21257	_PROTOTYPE(<pre>void rw_inode, (struct inode *rip, int rw_flag)</pre>	
21258	_PROTOTYPE(<pre>void wipe_inode, (struct inode *rip)</pre>);
21259	/± 1' 1 ±		
21260 21261	/* link.c *	int do_link, (void));
21261	_PROTOTIPE(int do_unlink, (void));
21263		int do_rename, (void));
21264		void truncate, (struct inode *rip));
21265			
21266	/* lock.c *		V -
21267 21268		<pre>int lock_op, (struct filp *f, int req) void lock_revive, (void)</pre>););
21268	_FROIDIIPE(VOIG IOCK_IEVIVE, (VOIG)) (
21270	/* main.c *	/	
21271	_PROTOTYPE(int main, (void));
21272	_PROTOTYPE(void reply, (int whom, int result));
21273	/* miaa - *		
212/4	/* misc.c *	1	

```
Feb 25, 11 15:18
                                        book.txt
                                                                        Page 286/393
       File: Page: 923 servers/fs/proto.h
21275 _PROTOTYPE( int do_dup, (void)
21276 _PROTOTYPE( int do_exit, (void)
                                                                               );
21277 _PROTOTYPE( int do_fcntl, (void)
                                                                               );
21278 _PROTOTYPE( int do_fork, (void)
                                                                               );
21279 _PROTOTYPE( int do_exec, (void)
                                                                               );
21280 _PROTOTYPE( int do_revive, (void)
                                                                               );
21281 _PROTOTYPE( int do_set, (void)
                                                                               );
21282 _PROTOTYPE( int do_sync, (void)
                                                                               );
21283 _PROTOTYPE( int do_fsync, (void)
                                                                               );
21284 _PROTOTYPE( int do_reboot, (void)
                                                                               );
21285 _PROTOTYPE( int do_svrctl, (void)
                                                                               );
21286 _PROTOTYPE( int do_getsysinfo, (void)
                                                                               );
21287
21288 /* mount.c */
21289 PROTOTYPE( int do mount, (void)
                                                                               );
21290 _PROTOTYPE( int do_umount, (void)
                                                                               );
21291 _PROTOTYPE( int unmount, (Dev_t dev)
                                                                               );
21292
21293 /* open.c */
21294 _PROTOTYPE( int do_close, (void)
                                                                               );
21295 _PROTOTYPE( int do_creat, (void)
                                                                               );
21296 _PROTOTYPE( int do_lseek, (void) 21297 _PROTOTYPE( int do_mknod, (void)
                                                                               );
                                                                               );
21298 _PROTOTYPE( int do_mkdir, (void)
                                                                               );
21299 _PROTOTYPE( int do_open, (void)
                                                                               );
21300
21301 /* path.c */
21302 _PROTOTYPE( struct inode *advance,(struct inode *dirp, char string[NAME_MAX]));
21303 _PROTOTYPE( int search_dir, (struct inode *ldir_ptr,
                               char string [NAME_MAX], ino_t *numb, int flag) );
21305 _PROTOTYPE( struct inode *eat_path, (char *path)
21306 _PROTOTYPE( struct inode *last_dir, (char *path, char string [NAME_MAX]));
21307
21308 /* pipe.c */
                                                                               );
21309 _PROTOTYPE( int do_pipe, (void)
21310 _PROTOTYPE( int do_unpause, (void)
                                                                               );
21311 _PROTOTYPE( int pipe_check, (struct inode *rip, int rw_flag,
21312
                              int oflags, int bytes, off_t position, int *canwrite, in
t notouch));
21313 _PROTOTYPE( void release, (struct inode *ip, int call_nr, int count)
                                                                               );
21314 _PROTOTYPE( void revive, (int proc_nr, int bytes)
                                                                               );
21315 PROTOTYPE( void suspend, (int task)
21316 _PROTOTYPE( int select_request_pipe, (struct filp *f, int *ops, int bl) );
21317 _PROTOTYPE( int select_cancel_pipe, (struct filp *f)
                                                                               );
21318 _PROTOTYPE( int select_match_pipe, (struct filp *f)
                                                                               );
21319
21320 /* protect.c */
21321 _PROTOTYPE( int do_access, (void)
                                                                               );
21322 _PROTOTYPE( int do_chmod, (void)
                                                                               );
21323 _PROTOTYPE( int do_chown, (void)
                                                                               );
21324 _PROTOTYPE( int do_umask, (void)
                                                                               );
21325 _PROTOTYPE( int forbidden, (struct inode *rip, mode_t access_desired)
                                                                               );
21326 _PROTOTYPE( int read_only, (struct inode *ip)
                                                                               );
21327
21328 /* read.c */
21329 _PROTOTYPE( int do_read, (void)
                                                                               );
21330 _PROTOTYPE( struct buf *rahead, (struct inode *rip, block_t baseblock,
21331
                               off_t position, unsigned bytes_ahead)
                                                                               );
21332 _PROTOTYPE( void read_ahead, (void)
                                                                               );
21333 _PROTOTYPE( block_t read_map, (struct inode *rip, off_t position)
                                                                               );
21334 _PROTOTYPE( int read_write, (int rw_flag)
                                                                               );
```

```
book.txt
 Feb 25, 11 15:18
                                                                               Page 287/393
        File: Page: 924 servers/fs/proto.h
21335 _PROTOTYPE( zone_t rd_indir, (struct buf *bp, int index)
21336
21337 /* stadir c */
21338 _PROTOTYPE( int do_chdir, (void) 21339 _PROTOTYPE( int do_fchdir, (void)
                                                                                       );
                                                                                       );
21340 _PROTOTYPE( int do_chroot, (void)
                                                                                       );
21341 _PROTOTYPE( int do_fstat, (void) 21342 _PROTOTYPE( int do_stat, (void)
                                                                                       );
                                                                                       );
21343 PROTOTYPE( int do fstatfs, (void)
                                                                                      );
21344
21345 /* super.c */
21346 _PROTOTYPE( bit_t alloc_bit, (struct super_block *sp, int map, bit_t origin));
21347 _PROTOTYPE( void free_bit, (struct super_block *sp, int map,
21348
                                                          bit_t bit_returned)
21349 _PROTOTYPE( struct super_block *get_super, (Dev_t dev)
                                                                                      );
21350 _PROTOTYPE( int mounted, (struct inode *rip)
                                                                                       );
21351 _PROTOTYPE( int read_super, (struct super_block *sp)
                                                                                       );
21352 _PROTOTYPE( int get_block_size, (dev_t dev)
21353
21354 /* time.c */
21355 _PROTOTYPE( int do_stime, (void)
                                                                                       );
21356 _PROTOTYPE( int do_utime, (void)
21357
21358 /* utility.c */
21359 _PROTOTYPE( time_t clock_time, (void)
                                                                                       );
21360 _PROTOTYPE( unsigned conv2, (int norm, int w)
                                                                                       );
21361 _PROTOTYPE( long conv4, (int norm, long x)
21362 _PROTOTYPE( int fetch_name, (char *path, int len, int flag)
                                                                                       );
21363 _PROTOTYPE( int no_sys, (void)
                                                                                       );
21364 _PROTOTYPE( void panic, (char *who, char *mess, int num)
21365
21366 /* write.c */
21367 _PROTOTYPE( void clear_zone, (struct inode *rip, off_t pos, int flag) );
21368 _PROTOTYPE( int do_write, (void) );
21369 _PROTOTYPE( struct buf *new_block, (struct inode *rip, off_t position) );
21370 _PROTOTYPE( void zero_block, (struct buf *bp)
21371
21372 /* select.c */
21373 _PROTOTYPE( int do_select, (void)
21374 _PROTOTYPE( int select_callback, (struct filp *, int ops)
21375 _PROTOTYPE( void select_forget, (int fproc)
21376 _PROTOTYPE( void select_timeout_check, (timer_t *)
                                                                                       );
21377 _PROTOTYPE( void init_select, (void)
                                                                                       );
21378 _PROTOTYPE( int select_notified, (int major, int minor, int ops)
21379
21380 /* timers.c */
21381 _PROTOTYPE( void fs_set_timer, (timer_t *tp, int delta, tmr_func_t watchdog, int
arg));
21382 _PROTOTYPE( void fs_expire_timers, (clock_t now)
21383 _PROTOTYPE( void fs_cancel_timer, (timer_t *tp)
                                                                                       );
21384 _PROTOTYPE( void fs_init_timer, (timer_t *tp)
21385
21386 /* cdprobe.c */
21387 _PROTOTYPE( int cdprobe, (void)
                                                                                      );
```

```
book.txt
  Feb 25, 11 15:18
                                                                                                                      Page 288/393
            File: Page: 925 servers/fs/glo.h
servers/fs/glo.h
21401 #ifdef TABLE
 21402 #undef EXTERN
 21403 #define EXTERN
 21404 #endif
 21405
 21406 /* File System global variables */
 21407 EXTERN struct fproc *fp; /* pointer to caller's fproc struct */
                                                               /* 1 if caller is super_user, else 0 */
 21408 EXTERN int super_user;
21408 EXIERN int super_user, /* I if carrier is super_user, else v /
21409 EXTERN int susp_count; /* number of procs suspended on pipe */
21410 EXTERN int nr_locks; /* number of locks currently in place */
21411 EXTERN int reviving; /* number of pipe processes to be revived */
21412 EXTERN off_t rdahedpos; /* position to read ahead */
21413 EXTERN int super_user, else v //
21410 EXTERN int super_user, else v //
21410 EXTERN int super_user, else v //
21411 EXTERN int super_user, else v //
21412 EXTERN int super_user, else v //
21413 EXTERN int super_user, else v //
21414 EXTERN int super_user, else v //
21415 EXTERN int super_user, else v //
21416 EXTERN int super_user, else v //
21417 EXTERN int super_user, else v //
21418 EXTERN int super_user, else v //
21419 EXTERN int super_user, else v //
21410 EXTERN int super_user, else v //
21410 EXTERN int super_user, else v //
21411 EXTERN int super_user, else v //
21412 EXTERN int reviving; /* number of procs suspended on pipe */
21412 EXTERN int reviving; /* number of pipe processes to be revived */
21412 EXTERN int reviving; /* position to read ahead */
21413 EXTERN int super_user, else v //
21414 EXTERN int super_user, else v //
21415 EXTERN int super_user, else v //
21416 EXTERN int super_user, else v //
21417 EXTERN int super_user, else v //
21418 EXTERN int super_user, else v //
21419 EXTERN int super_user, else v //
21410 EXTERN int super_user, else v //
21410 EXTERN int super_user, else v //
21411 EXTERN int super_user, else v //
21412 EXTERN int super_user, else v //
21412 EXTERN int super_user, else v //
21412 EXTERN int super_user, else v //
21412 EXTERN int super_user, else v //
21412 EXTERN int super_user, else v //
21412 EXTERN int super_user, else v //
21412 EXTERN int super_user, else v //
21412 EXTERN int super_user, else v //
21412 EXTERN int super_user, else v //
21412 EXTERN int super_user, else v //
21412 EXTERN int super_user, else v //
21412 EXTERN int super_user, else v //
21412 EXTERN int super_user, else v //
21412 EXTERN int super_user, els
 21413 EXTERN struct inode *rdahed_inode; /* pointer to inode to read ahead */
21414 EXTERN Dev_t root_dev; /* device number of the root device */
21415 EXTERN time_t boottime; /* time in seconds at system boot */
 21416
21417 /* The parameters of the call are kept here. */
 21418 EXTERN message m_in; /* the input message itself */
 21419 EXTERN message m_out;
                                                              /* the output message used for reply */
21420 EXTERN int who; /* caller's proc number */
21421 EXTERN int call_nr; /* system call number */
 21422 EXTERN char user_path[PATH_MAX];/* storage for user path name */
 21423
 21424 /* The following variables are used for returning results to the caller. */
21425 EXTERN int err_code; /* temporary storage for error number */
                                                              /* status of last disk i/o request */
 21426 EXTERN int rdwt_err;
 21427
 21428 /* Data initialized elsewhere. */
 21429 extern _PROTOTYPE (int (*call_vec[]), (void) ); /* sys call table */
21430 extern char dot1[2]; /* dot1 (&dot1[0]) and dot2 (&dot2[0]) have a special */
21431 extern char dot2[3]; /* meaning to search_dir: no access permission check. */
servers/fs/fproc.h
21500 /* This is the per-process information. A slot is reserved for each potential
 21502 * possible or even necessary to tell when a slot is free here.
 21503
 21504 EXTERN struct fproc {
 21505
            mode_t fp_umask;
                                                               /* mask set by umask system call */
               struct inode *fp_workdir; /* pointer to working directory's inode */
struct inode *fp_rootdir; /* pointer to current root dir (see chroot) */
 21506
 21507
               struct filp *fp_filp[OPEN_MAX];/* the file descriptor table */
 21508
 21509
               /* effective user id */
               uid_t fp_effuid;
 21510
               gid t fp realgid;
                                                            /* real group id */
 21511
                                                            /* effective group id */
/* major/minor of controlling tty */
               gid_t fp_effgid;
 21512
               dev_t fp_tty;
 21513
 21514
               int fp fd;
                                                            /* place to save fd if rd/wr can't finish */
```

```
book.txt
 Feb 25, 11 15:18
                                                                    Page 289/393
       File: Page: 926 servers/fs/fproc.h
21515
        char *fp buffer;
                                    /* place to save buffer if rd/wr can't finish*/
                                     /* place to save bytes if rd/wr can't finish */
21516
        int fp_nbytes;
                                    /* partial byte count if rd/wr can't finish */
21517
        int fp_cum_io_partial;
21518
        char fp_suspended;
                                    /* set to indicate process hanging */
                                     /* set to indicate process being revived */
21519
        char fp_revived;
21520
        char fp_task;
                                     /* which task is proc suspended on */
21521
        char fp_sesldr;
                                    /* true if proc is a session leader */
                                    /* process id */
21522
        pid_t fp_pid;
        long fp cloexec;
                                    /* bit map for POSIX Table 6-2 FD CLOEXEC */
21523
21524 } fproc[NR_PROCS];
21525
21526 /* Field values. */
21527 #define NOT SUSPENDED
                                0
                                    /* process is not suspended on pipe or task */
                                    /* process is suspended on pipe or task */
21528 #define SUSPENDED
                                1
21529 #define NOT REVIVING
                                   /* process is not being revived */
21530 #define REVIVING
                                    /* process is being revived from suspension */
                               1
21531 #define PID_FREE
                                Ω
                                   /* process slot free */
21532
21533 /* Check is process number is acceptable - includes system processes. */
21534 #define isokprocnr(n) ((unsigned)((n)+NR_TASKS) < NR_PROCS + NR_TASKS)
21535
servers/fs/buf.h
21600 /* Buffer (block) cache. To acquire a block, a routine calls get_block(),
21601 * telling which block it wants. The block is then regarded as "in use"
21602 * and has its 'b_count' field incremented. All the blocks that are not
21603 * in use are chained together in an LRU list, with 'front' pointing
21604 * to the least recently used block, and 'rear' to the most recently used
21605 * block. A reverse chain, using the field b_prev is also maintained.
21606 * Usage for LRU is measured by the time the put_block() is done. The second
21607 * parameter to put_block() can violate the LRU order and put a block on the
21608 * front of the list, if it will probably not be needed soon. If a block
21609
       * is modified, the modifying routine must set b_dirt to DIRTY, so the block
21610 * will eventually be rewritten to the disk.
21611 */
21612
21613 #include <sys/dir.h>
                                          /* need struct direct */
21614 #include <dirent.h>
21615
21616 EXTERN struct buf {
       /* Data portion of the buffer. */
21617
21618
        union {
21619
          char b__data[MAX_BLOCK_SIZE];
                                                        /* ordinary user data */
21620 /*
          directory block */
21621
          struct direct b__dir[NR_DIR_ENTRIES(MAX_BLOCK_SIZE)];
21622 /* V1 indirect block */
          zone1_t b__v1_ind[V1_INDIRECTS];
21623
21624 /* V2 indirect block */
          zone_t b__v2_ind[V2_INDIRECTS(MAX_BLOCK_SIZE)];
21625
      /* V1 inode block */
21626
          d1_inode b__v1_ino[V1_INODES_PER_BLOCK];
21627
21628 /* V2 inode block */
21629
          d2 inode b v2 ino[V2 INODES PER BLOCK(MAX BLOCK SIZE)];
```

```
book.txt
 Feb 25, 11 15:18
                                                                   Page 290/393
       File: Page: 927 servers/fs/buf.h
21630 /* bit map block */
21631
          bitchunk_t b__bitmap[FS_BITMAP_CHUNKS(MAX_BLOCK_SIZE)];
21632
21633
21634
        /* Header portion of the buffer. */
21635
        struct buf *b_next; /* used to link all free bufs in a chain */
        struct buf *b_prev;
                                    /* used to link all free bufs the other way */
21636
        struct buf *b_hash;
                                    /* used to link bufs on hash chains */
21637
        block t b blocknr;
                                  /* block number of its (minor) device */
21638
21639
        dev_t b_dev;
                                    /* major | minor device where block resides */
                                    /* CLEAN or DIRTY */
21640
        char b dirt;
21641
        char b count;
                                    /* number of users of this buffer */
21642 } buf[NR BUFS];
21643
21644 /* A block is free if b dev == NO DEV. */
21645
21646 #define NIL_BUF ((struct buf *) 0)
                                        /* indicates absence of a buffer */
21647
21648 /* These defs make it possible to use to bp->b_data instead of bp->b.b_data */
21649 #define b_data b.b__data
21650 #define b_dir b.b_dir
21651 #define b_v1_ind b.b__v1_ind
21652 #define b_v2_ind b.b__v2_ind
21653 #define b v1 ino b.b v1 ino
21654 #define b_v2_ino b.b__v2_ino
21655 #define b bitmap b.b bitmap
21656
21657 EXTERN struct buf *buf hash[NR BUF HASH]; /* the buffer hash table */
21658
21659 EXTERN struct buf *front;
                                    /* points to least recently used free block */
21660 EXTERN struct buf *rear;
                                    /* points to most recently used free block */
21661 EXTERN int bufs_in_use;
                                    /* # bufs currently in use (not on free list)*/
21662
21663 /* When a block is released, the type of usage is passed to put_block(). */ 21664 #define WRITE_IMMED 0100 /* block should be written to disk now */
21665 #define ONE_SHOT 0200 /* set if block not likely to be needed soon */
21666
21667 #define INODE_BLOCK
                                                            /* inode block */
21668 #define DIRECTORY BLOCK 1
                                                           /* directory block */
21669
       #define INDIRECT_BLOCK
                                                           /* pointer block */
                                                           /* bit map */
21670 #define MAP BLOCK
21671 #define FULL_DATA_BLOCK 5
                                                            /* data, fully used */
21672 #define PARTIAL_DATA_BLOCK 6
                                                            /* data, partly used*/
21673
21674 #define HASH MASK (NR BUF HASH - 1) /* mask for hashing block numbers */
servers/fs/file.h
21700 /* This is the filp table. It is an intermediary between file descriptors and
21701 * inodes. A slot is free if filp_count == 0.
21702 */
21703
21704 EXTERN struct filp {
21705
       mode_t filp_mode;
                                    /* RW bits, telling how file is opened */
        int filp flags;
                                    /* flags from open and fcntl */
21706
21707
         int filp count;
                                    /* how many file descriptors share this slot?*/
        struct inode *filp_ino;
                                   /* pointer to the inode */
21708
21709
        off t filp pos;
                                    /* file position */
```

```
book.txt
Feb 25, 11 15:18
                                                                Page 291/393
      File: Page: 928 servers/fs/file.h
21710
21711
        /* the following fields are for select() and are owned by the generic
21712
         * select() code (i.e., fd-type-specific select() code can't touch these).
21713
21714
        int filp_selectors;
                                  /* select()ing processes blocking on this fd */
21715
        int filp_select_ops;
                                  /* interested in these SEL_* operations */
21716
21717
        /* following are for fd-type-specific select() */
21718
        int filp_pipe_select_ops;
21719
      } filp[NR_FILPS];
21720
21721
      #define FILP CLOSED
                                  /* filp mode: associated device closed */
21722
21723
      #define NIL_FILP (struct filp *) 0
                                       /* indicates absence of a filp slot */
servers/fs/lock.h
21800 /* This is the file locking table. Like the filp table, it points to the
21801 * inode table, however, in this case to achieve advisory locking. 21802 */
21803 EXTERN struct file_lock {
21804
      short lock_type;
                                  /* F_RDLOCK or F_WRLOCK; 0 means unused slot */
21805
        pid_t lock_pid;
                                  /* pid of the process holding the lock */
        struct inode *lock_inode;
                                 /* pointer to the inode locked */
21806
21807
        off_t lock_first;
                                  /* offset of first byte locked */
        off_t lock_last;
                                  /* offset of last byte locked */
21808
21809 } file lock[NR LOCKS];
servers/fs/inode.h
21900 /* Inode table. This table holds inodes that are currently in use. In some
21901 * cases they have been opened by an open() or creat() system call, in other
      * cases the file system itself needs the inode for one reason or another,
21902
21903 * such as to search a directory for a path name.
21904 * The first part of the struct holds fields that are present on the
       * disk; the second part holds fields not present on the disk.
21905
       * The disk inode part is also declared in "type.h" as 'd1_inode' for V1
       * file systems and 'd2_inode' for V2 file systems.
21907
21908
21909
21910 EXTERN struct inode {
21911
        mode_t i_mode;
                                  /* file type, protection, etc. */
                                  /* how many links to this file */
21912
        nlink_t i_nlinks;
21913
        uid_t i_uid;
                                  /* user id of the file's owner */
21914
        gid_t i_gid;
                                  /* group number */
21915
        off_t i_size;
                                  /* current file size in bytes */
        time_t i_atime;
                                  /* time of last access (V2 only) */
21916
                                  /* when was file data last changed */
21917
        time_t i_mtime;
                                  /* when was inode itself changed (V2 only)*/
21918
        time t i ctime;
21919
        zone_t i_zone[V2_NR_TZONES]; /* zone numbers for direct, ind, and dbl ind */
21920
21921
        /* The following items are not present on the disk. */
        dev_t i_dev; /* which device is the inode on */
21922
                                  /* inode number on its (minor) device */
21923
        ino_t i_num;
21924
        int i count;
                                 /* # times inode used; 0 means slot is free */
```

```
book.txt
 Feb 25, 11 15:18
                                                                               Page 292/393
        File: Page: 929 servers/fs/inode.h
21925
          int i ndzones;
                                          /* # direct zones (Vx NR DZONES) */
21926
          int i_nindirs;
                                           /* # indirect zones per indirect block */
          struct super_block *i_sp;
21927
                                          /* pointer to super block for inode's device */
          char i_dirt;
21928
                                          /* CLEAN or DIRTY */
                                          /* set to I_PIPE if pipe */
21929
          char i_pipe;
21930
          char i_mount;
                                          /* this bit is set if file mounted on */
21931
          char i seek;
                                          /* set on LSEEK, cleared on READ/WRITE */
21932
          char i_update;
                                          /* the ATIME, CTIME, and MTIME bits are here */
21933 } inode[NR_INODES];
21934
        #define NIL INODE (struct inode *) 0 /* indicates absence of inode slot */
21935
21936
21936
21937 /* Field values. Note that CLEAN and DIRTY are defined in "const.h" */
21938 #define NO_PIPE 0 /* i_pipe is NO_PIPE if inode is not a pipe */
21939 #define I_PIPE 1 /* i_pipe is I_PIPE if inode is a pipe */
21940 #define NO_MOUNT 0 /* i_mount is NO_MOUNT if file not mounted on*/
21941 #define I_MOUNT 1 /* i_mount is I_MOUNT if file mounted on */
21942 #define NO_SEEK 0 /* i_seek = NO_SEEK if last op was not SEEK */
21943 #define ISEEK 1 /* i_seek = ISEEK if last op was SEEK */
servers/fs/param.h
22000 /* The following names are synonyms for the variables in the input message. */
22001 #define acc time
                                m2 11
22002 #define addr
                                m1 i3
22003 #define buffer
                                m1_p1
22004 #define child
                                m1 i2
22005 #define co_mode
                                m1_i1
22006 #define eff_grp_id
                                m1_i3
22007 #define eff_user_id
                                m1_i3
22008 #define erki
                                m1_p1
22009 #define fd
                                m1_i1
22010 #define fd2
                                m1 i2
22011 #define ioflags
                                m1 i3
22012 #define group
                                m1_i3
22013 #define real_grp_id
                                m1 i2
22014 #define ls_fd
                                m2_i1
22015 #define mk mode
                                m1 i2
22016 #define mk z0
                                m1 i3
22017 #define mode
                                m3 i2
22018 #define c_mode
                                m1_i3
22019 #define c name
                                m1 p1
22020 #define name
                                m3 p1
22021 #define name1
                                m1_p1
22022 #define name2
                                m1_p2
22023 #define name_length
                               m3 i1
22024 #define namel_length ml_i1
22025 #define name2_length m1_i2
22026 #define nbytes
                                m1_i2
22027 #define owner
                                m1_i2
22028 #define parent
                                m1 i1
22029 #define pathname
                                m3 cal
22030 #define pid
                                m1 i3
                                m1 i1
22031 #define pro
        #define ctl_req
22032
                                m4 11
22033 #define driver_nr
                                m4_{12}
22034 #define dev nr
```

```
book.txt
 Feb 25, 11 15:18
                                                                    Page 293/393
       File: Page: 930 servers/fs/param.h
22035 #define dev style
                           m4 14
22036 #define rd_only
                           m1_i3
22037 #define real_user_id m1_i2
22038 #define request
                           m1 i 2
22039 #define sig
                           m1_i2
22040 #define slot1
                           m1 i1
22041 #define tp
                           m2_11
22042 #define utime_actime m2_11
22043 #define utime_modtime m2_12
22044 #define utime_file
                          m2 p1
22045 #define utime length m2 i1
22046 #define utime strlen m2 i2
22047 #define whence
                           m2 i2
22048 #define svrctl_req
                           m2_i1
22049 #define syrctl argp
                           m2 p1
22050 #define pm stime
                           m1 i1
22051 #define info_what
                           m1_i1
22052 #define info_where
                           m1_p1
22053
22054 /* The following names are synonyms for the variables in the output message. */
22055 #define reply_type m_type
22056 #define reply_11
                           m2_11
22057 #define reply_i1
                           m1_i1
22058 #define reply i2
                           m1 i2
22059 #define reply_t1
                           m4 11
22060 #define reply t2
                           m4 12
22061 #define reply t3
                           m4 13
22062 #define reply_t4
                           m4 14
22063 #define reply_t5
                           m4_{15}
servers/fs/super.h
22100 /* Super block table. The root file system and every mounted file system 22101 * has an entry here. The entry holds information about the sizes of the bit
       * maps and inodes. The s_ninodes field gives the number of inodes available
22102
       * for files and directories, including the root directory. Inode 0 is
        * on the disk, but not used. Thus s_ninodes = 4 means that 5 bits will be
22104
        * used in the bit map, bit 0, which is always 1 and not used, and bits 1-4
22105
       * for files and directories. The disk layout is:
22107
22108
            Item
                        # blocks
22109
            boot block
                        1
            super block
                               (offset 1kB)
22110
                           1
22111
            inode map
                         s_imap_blocks
            zone map
22112
                         s_zmap_blocks
22113
            inodes
                         (s_ninodes + 'inodes per block' - 1)/'inodes per block'
22114
            unused
                         whatever is needed to fill out the current zone
22115
            data zones
                       (s_zones - s_firstdatazone) << s_log_zone_size
22116
       * A super_block slot is free if s_dev == NO_DEV.
22117
22118
22119
22120
      EXTERN struct super_block {
22121
        ino_t s_ninodes;
                                     /* # usable inodes on the minor device */
        zonel_t s_nzones;
                                    /* total device size, including bit maps etc */
22122
                                    /* # of blocks used by inode bit map */
22123
         short s_imap_blocks;
22124
        short s zmap blocks;
                                    /* # of blocks used by zone bit map */
```

```
book.txt
 Feb 25, 11 15:18
                                                                     Page 294/393
       File: Page: 931 servers/fs/super.h
22125
         zonel t s firstdatazone;
                                     /* number of first data zone */
22126
         short s_log_zone_size;
                                     /* log2 of blocks/zone */
                                     /* try to avoid compiler-dependent padding */
22127
         short s_pad;
22128
         off t s_max_size;
                                     /* maximum file size on this device */
                                     /* number of zones (replaces s_nzones in V2) */
22129
         zone_t s_zones;
22130
         short s_magic;
                                     /* magic number to recognize super-blocks */
22131
22132
         /* The following items are valid on disk only for V3 and above */
22133
22134
         /* The block size in bytes. Minimum MIN_BLOCK SIZE. SECTOR_SIZE
22135
          * multiple. If V1 or V2 filesystem, this should be
22136
         * initialised to STATIC_BLOCK_SIZE. Maximum MAX_BLOCK_SIZE.
22137
22138
         short s_pad2;
                                     /* try to avoid compiler-dependent padding */
         unsigned short s block size; /* block size in bytes. */
22139
         char's disk version;
                                     /* filesystem format sub-version */
22140
22141
22142
         /* The following items are only used when the super_block is in memory. */
22143
         struct inode *s_isup;
                                     /* inode for root dir of mounted file sys */
                                     /* inode mounted on */
22144
         struct inode *s_imount;
         unsigned s_inodes_per_block; /* precalculated from magic number */
22145
22146
         dev_t s_dev;
                                     /* whose super block is this? */
                                     /* set to 1 iff file sys mounted read only */
22147
         int s_rd_only;
                                     /* set to 1 iff not byte swapped file system */
22148
         int s native;
                                     /* file system version, zero means bad magic */
         int s_version;
22149
                                     /* # direct zones in an inode */
22150
         int s ndzones;
                                     /* # indirect zones per indirect block */
22151
         int s nindirs;
        bit_t s_isearch;
22152
                                     /* inodes below this bit number are in use */
                                     /* all zones below this bit number are in use*/
22153
         bit_t s_zsearch;
22154 } super block[NR SUPERS];
22155
22156
       #define NIL_SUPER (struct super_block *) 0
22157 #define IMAP 0 ^{-}/* operating on the inode bit map */
22158 #define ZMAP
                                     /* operating on the zone bit map */
servers/fs/table.c
22200 /* This file contains the table used to map system call numbers onto the
22201 * routines that perform them.
22202 */
22203
22204 #define TABLE
22205
22206 #include "fs.h"
22207 #include <minix/callnr.h>
22208 #include <minix/com.h>
22209 #include "buf.h"
22210 #include "file.h'
22211 #include "fproc.h"
22212 #include "inode.h"
22213 #include "lock.h"
22214 #include "super.h"
22215
22216 PUBLIC _PROTOTYPE (int (*call_vec[]), (void) ) = {
                         /* 0 = unused */
22217
          no_sys,
                             /* 1 = exit */
22218
              do_exit,
                             /* 2 = fork
22219
              do fork,
```

Feb 25, 11 15:18	book.txt	Page 295/393
File: Page: 932 serv		
22220 do_read,	/* 3 = read */	
22221 do_write, 22222 do open,	/* 4 = write */ /* 5 = open */	
22222 do_open, 22223 do_close,	/* 5 = open */ /* 6 = close */	
22223 do_crose, 22224 no_sys,	/* 7 = wait */	
22225 do_creat,	/* 8 = creat */	
22226 do_link,	/* 9 = link */	
22227 do_unlink,	/* 10 = unlink */	
22228 no_sys,	/* 11 = waitpid */	
22229 do_chdir,	/* 12 = chdir */	
22230 no_sys,	/* 13 = time */	
22231 do_mknod,	/* 14 = mknod */	
22232 do_chmod,	/* 15 = chmod */	
22233 do_chown, 22234 no sys,	/* 16 = chown */ /* 17 = break */	
22234 no_sys, 22235 do_stat,	/* 17 = break "/ /* 18 = stat */	
22236 do_lseek,	/* 19 = lseek */	
22237 no_sys,	/* 20 = getpid */	
22238 do_mount,	/* 21 = mount */	
22239 do_umount,	/* 22 = umount */	
22240 do_set,	/* 23 = setuid */	
22241 no_sys,	/* 24 = getuid */	
22242 do_stime,	/* 25 = stime */	
22243 no_sys,	/* 26 = ptrace */ /* 27 = alarm */	
22244 no_sys, 22245 do fstat.		
22245 do_fstat, 22246 no_sys,	/* 28 = fstat */ /* 29 = pause */	
22247 do utime,	/* 30 = utime */	
22248 no_sys,	/* 31 = (stty) */	
22249 no_sys,	/* 32 = (gtty) */	
22250 do_access,	/* 33 = access */	
22251 no_sys,	/* 34 = (nice) */	
22252 no_sys,	/* 35 = (ftime) */	
22253 do_sync,	/* 36 = sync */ /* 37 = kill */	
22254 no_sys, 22255 do_rename,	/* 37 = KIII "/ /* 38 = rename */	
22256 do_mkdir,	/* 39 = mkdir */	
22257 do_unlink,	/* 40 = rmdir */	
22258 do_dup,	/* 41 = dup */	
22259 do_pipe,	/* 42 = pipe */	
22260 no_sys,	/* 43 = times */	
22261 no_sys,	/* 44 = (prof) */	
22262 no_sys,	/* 45 = unused */ /* 46 = setaid */	
22263 do_set, 22264 no_sys,	/* 46 = setgid */ /* 47 = getgid */	
22265 no_sys,	/* 48 = (signal)*/	
22266 no_sys,	/* 49 = unused */	
22267 no_sys,	/* 50 = unused */	
22268 no_sys,	/* 51 = (acct) */	
22269 no_sys,	/* 52 = (phys) */	
22270 no_sys,	/* 53 = (lock) */	
22271 do_ioctl, 22272 do fcntl,	/* 54 = ioctl */ /* 55 = fcntl */	
22272 do_fcntl, 22273 no_sys,	/* 55 = ICHCI */ /* 56 = (mpx) */	
22274 no_sys,	/* 57 = unused */	
22275 no_sys,	/* 58 = unused */	
22276 do_exec,	/* 59 = execve */	
22277 do_umask,	/* 60 = umask */	
22278 do_chroot,	/* 61 = chroot */	
22279 do_setsid,	/* 62 = setsid */	

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 296/393
       File: Page: 933 servers/fs/table.c
22280
                             /* 63 = getpgrp */
              no_sys,
22281
                             /* 64 = KSIG: signals originating in the kernel */
22282
              no sys,
22283
                             /* 65 = UNPAUSE */
              do_unpause,
                             /* 66 = unused */
22284
              no_sys,
22285
              do_revive,
                             /* 67 = REVIVE */
22286
              no_sys,
                             /* 68 = TASK_REPLY
                                                    * /
                             /* 69 = unused */
22287
              no_sys,
                             /* 70 = unused */
22288
              no_sys,
                             /* 71 = si */
22289
              no_sys,
                             /* 72 = sigsuspend */
22290
              no_sys,
22291
              no sys,
                             /* 73 = sigpending */
22292
                             /* 74 = sigprocmask */
              no_sys,
                             /* 75 = sigreturn */
22293
              no_sys,
                             /* 76 = reboot */
22294
              do reboot,
22295
              do_svrctl,
                             /* 77 = svrctl */
22296
22297
              no sys,
                             /* 78 = unused */
              do_getsysinfo, /* 79 = getsysinfo */
22298
                             /* 80 = unused */
22299
              no_sys,
22300
              do_devctl,
                             /* 81 = devctl */
22301
              do_fstatfs,
                             /* 82 = fstatfs */
                             /* 83 = memalloc */
22302
              no_sys,
                             /* 84 = memfree */
22303
              no_sys,
              do_select,
                             /* 85 = select */
22304
                             /* 86 = fchdir */
22305
              do_fchdir,
                             /* 87 = fsync */
22306
              do fsync,
22307
              no_sys,
                             /* 88 = getpriority */
                             /* 89 = setpriority */
22308
              no_sys,
22309
                             /* 90 = gettimeofday */
              no sys,
22310 };
22311 /* This should not fail with "array size is negative": */
22312 extern int dummy[sizeof(call_vec) == NCALLS * sizeof(call_vec[0]) ? 1 : -1];
22313
servers/fs/cache.c
22400 /* The file system maintains a buffer cache to reduce the number of disk
22401 * accesses needed. Whenever a read or write to the disk is done, a check is
       * first made to see if the block is in the cache. This file manages the
22402
       * cache.
22403
22404
22405
       * The entry points into this file are:
22406
       * get_block:
                       request to fetch a block for reading or writing from cache
           put_block:
22407
                       return a block previously requested with get_block
           alloc_zone: allocate a new zone (to increase the length of a file) free_zone: release a zone (when a file is removed)
22408
22409
22410
           rw_block:
                      read or write a block from the disk itself
22411
           invalidate: remove all the cache blocks on some device
22412
22413
22414 #include "fs.h"
22415 #include <minix/com.h>
22416 #include "buf.h"
22417 #include "file.h"
22418 #include "fproc.h"
22419 #include "super.h"
```

```
book.txt
Feb 25, 11 15:18
                                                                     Page 297/393
      File: Page: 934 servers/fs/cache.c
22420
22421 FORWARD _PROTOTYPE( void rm_lru, (struct buf *bp) );
22422
22423 /*=========**
22424 *
                                     get_block
22426 PUBLIC struct buf *get_block(dev, block, only_search)
22427 register dev_t dev;
                                 /* on which device is the block? */
                                     /* which block is wanted? */
22428 register block t block;
      int only_search;
                                     /* if NO_READ, don't read, else act normal */
22429
22430
22431 /* Check to see if the requested block is in the block cache. If so, return
      * a pointer to it. If not, evict some other block and fetch it (unless * 'only_search' is 1). All the blocks in the cache that are not in use
22432
22433
         are linked together in a chain, with 'front' pointing to the least recently
22434
22435
       * used block and 'rear' to the most recently used block. If 'only_search' is
22436
       * 1, the block being requested will be overwritten in its entirety, so it is
22437
         only necessary to see if it is in the cache; if it is not, any free buffer
22438
       * will do. It is not necessary to actually read the block in from disk.
       * If 'only_search' is PREFETCH, the block need not be read from the disk,
22439
22440
       * and the device is not to be marked on the block, so callers can tell if
22441
       * the block returned is valid.
       * In addition to the LRU chain, there is also a hash chain to link together
22442
       * blocks whose block numbers end with the same bit strings, for fast lookup.
22443
22444
22445
22446
22447
        register struct buf *bp, *prev_ptr;
22448
22449
        /* Search the hash chain for (dev, block). Do read() can use
22450
         * get block(NO DEV ...) to get an unnamed block to fill with zeros when
22451
         * someone wants to read from a hole in a file, in which case this search
22452
         * is skipped
22453
        if (dev != NO_DEV) {
22454
22455
              b = (int) block & HASH_MASK;
22456
              bp = buf_hash[b];
22457
              while (bp != NIL_BUF) {
22458
                      if (bp->b blocknr == block && bp->b dev == dev) {
22459
                              /* Block needed has been found. */
                             if (bp->b_count == 0) rm_lru(bp);
22460
                             bp->b count++; /* record that block is in use */
22461
22462
22463
                             return(bp);
                      } else {
22464
22465
                              /* This block is not the one sought. */
22466
                             bp = bp->b_hash; /* move to next block on hash chain */
22467
22468
22469
22470
22471
        /* Desired block is not on available chain. Take oldest block ('front'). */
22472
        if ((bp = front) == NIL_BUF) panic(__FILE__, "all buffers in use", NR_BUFS);
22473
        rm lru(bp);
22474
22475
         /* Remove the block that was just taken from its hash chain. */
        b = (int) bp->b blocknr & HASH MASK;
22476
22477
        prev ptr = buf hash[b];
22478
        if (prev_ptr == bp) {
22479
              buf hash[b] = bp->b hash;
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 298/393
      File: Page: 935 servers/fs/cache.c
22480
        } else {
22481
              /* The block just taken is not on the front of its hash chain. */
              while (prev_ptr->b_hash != NIL_BUF)
22482
22483
                     if (prev_ptr->b_hash == bp)
                             prev_ptr->b_hash = bp->b_hash; /* found it */
22484
22485
                             break;
22486
                     } else {
22487
                             prev_ptr = prev_ptr->b_hash; /* keep looking */
22488
22489
22490
22491
        /* If the block taken is dirty, make it clean by writing it to the disk.
22492
         * Avoid hysteresis by flushing all other dirty blocks for the same device.
22493
22494
        if (bp->b dev != NO DEV) {
22495
              if (bp->b dirt == DIRTY) flushall(bp->b dev);
22496
22497
22498
        /* Fill in block's parameters and add it to the hash chain where it goes. */
                                    /* fill in device number */
22499
        bp->b_dev = dev;
22500
        bp->b_blocknr = block;
                                     /* fill in block number */
22501
        bp->b_count++;
                                    /* record that block is being used */
22502
        b = (int) bp->b_blocknr & HASH_MASK;
22503
        bp->b hash = buf hash[b];
22504
        buf_hash[b] = bp;
                                    /* add to hash list */
22505
        /* Go get the requested block unless searching or prefetching. */
22506
22507
        if (dev != NO DEV) {
              if (only_search == PREFETCH) bp->b_dev = NO_DEV;
22508
22509
22510
              if (only_search == NORMAL)
22511
                     rw_block(bp, READING);
22512
22513
22514
        return(bp);
                                    /* return the newly acquired block */
22515
22517 /*-----*
22518
                                   put block
22519
       *-----*
22520 PUBLIC void put_block(bp, block_type)
22521 register struct buf *bp; /* pointer to the buffer to be released */
22522 int block_type;
                                    /* INODE_BLOCK, DIRECTORY_BLOCK, or whatever */
22523
22524 /* Return a block to the list of available blocks. Depending on 'block type'
       * it may be put on the front or rear of the LRU chain. Blocks that are
22525
22526
       * expected to be needed again shortly (e.g., partially full data blocks)
22527
       * go on the rear; blocks that are unlikely to be needed again shortly
22528
       * (e.g., full data blocks) go on the front. Blocks whose loss can hurt
       * the integrity of the file system (e.g., inode blocks) are written to
22529
22530
       * disk immediately if they are dirty.
22531
22532
        if (bp == NIL_BUF) return;
                                  /* it is easier to check here than in caller */
22533
22534
        bp->b_count--;
                                    /* there is one use fewer now */
        if (bp->b count != 0) return; /* block is still in use */
22535
22536
22537
        bufs in use--;
                                    /* one fewer block buffers in use */
22538
22539
        /* Put this block back on the LRU chain. If the ONE SHOT bit is set in
```

```
book.txt
Feb 25, 11 15:18
                                                                      Page 299/393
      File: Page: 936 servers/fs/cache.c
22540
           'block type', the block is not likely to be needed again shortly, so put
22541
          * it on the front of the LRU chain where it will be the first one to be
22542
         * taken when a free buffer is needed later.
22543
22544
        if (bp->b_dev == DEV_RAM | | block_type & ONE_SHOT) {
22545
              /* Block probably won't be needed quickly. Put it on front of chain.
22546
               * It will be the next block to be evicted from the cache.
22547
22548
              bp->b prev = NIL BUF;
22549
              bp->b_next = front;
22550
              if (front == NIL BUF)
22551
                     rear = bp;
                                     /* LRU chain was empty */
22552
              else
22553
                      front->b_prev = bp;
22554
              front = bp;
22555
        } else {
22556
              /* Block probably will be needed quickly. Put it on rear of chain.
22557
               * It will not be evicted from the cache for a long time.
22558
22559
              bp->b_prev = rear;
22560
              bp->b_next = NIL_BUF;
22561
              if (rear == NIL_BUF)
22562
                      front = bp;
22563
22564
                      rear->b_next = bp;
22565
              rear = bp;
22566
22567
22568
        /* Some blocks are so important (e.g., inodes, indirect blocks) that they
         * should be written to the disk immediately to avoid messing up the file
22569
22570
         * system in the event of a crash.
22571
22572
        if ((block_type & WRITE_IMMED) && bp->b_dirt==DIRTY && bp->b_dev != NO_DEV) {
22573
                     rw_block(bp, WRITING);
22574
22575 }
22577 /*============*
22578 *
                                    alloc zone
22579
       22580 PUBLIC zone_t alloc_zone(dev, z)
                                     /* device where zone wanted */
22581 dev t dev;
22582 zone_t z;
                                     /* try to allocate new zone near this one */
22583
      /* Allocate a new zone on the indicated device and return its number. */
22584
22585
22586
        int major, minor;
22587
        bit_t b, bit;
22588
        struct super_block *sp;
22589
22590
        /* Note that the routine alloc_bit() returns 1 for the lowest possible
         * zone, which corresponds to sp->s_firstdatazone. To convert a value * between the bit number, 'b', used by alloc_bit() and the zone number, 'z',
22591
22592
22593
         * stored in the inode, use the formula:
22594
              z = b + sp->s_firstdatazone - 1
         * Alloc_bit() never returns 0, since this is used for NO_BIT (failure).
22595
22596
22597
        sp = get_super(dev);
22598
22599
        /* If z is 0, skip initial part of the map known to be fully in use. */
```

```
Feb 25, 11 15:18
                                   book.txt
                                                                Page 300/393
      File: Page: 937 servers/fs/cache.c
22600
       if (z == sp->s firstdatazone) {
22601
             bit = sp->s_zsearch;
22602
        } else {
22603
             bit = (bit_t) z - (sp->s_firstdatazone - 1);
22604
22605
        b = alloc_bit(sp, ZMAP, bit);
        if (b == NO_BIT) {
22606
22607
             err_code = ENOSPC;
             major = (int) (sp->s dev >> MAJOR) & BYTE;
22608
             minor = (int) (sp->s_dev >> MINOR) & BYTE;
22609
22610
             printf("No space on %sdevice %d/%d\n",
22611
                    sp->s dev == root dev ? "root " : "", major, minor);
             return(NO ZONE);
22612
22613
        if (z == sp->s firstdatazone) sp->s zsearch = b;
22614
                                                        /* for next time */
22615
        return(sp->s firstdatazone - 1 + (zone t) b);
22616
22618 /*========*
22619
                                 free zone
22620
     22621 PUBLIC void free_zone(dev, numb)
22622 dev t dev;
                                          /* device where zone located */
                                         /* zone to be returned */
22623 zone t numb;
22624
22625 /* Return a zone. */
22626
22627
        register struct super block *sp;
22628
       bit_t bit;
22629
22630
        /* Locate the appropriate super block and return bit. */
22631
        sp = get_super(dev);
22632
        if (numb < sp->s_firstdatazone || numb >= sp->s_zones) return;
22633
        bit = (bit_t) (numb - (sp->s_firstdatazone - 1));
22634
        free_bit(sp, ZMAP, bit);
22635
        if (bit < sp->s_zsearch) sp->s_zsearch = bit;
22636 }
22638 /*----*
22639
                                 rw block
22640
22641 PUBLIC void rw_block(bp, rw_flag)
22642 register struct buf *bp;
                                  /* buffer pointer */
22643 int rw_flag;
                                  /* READING or WRITING */
22644
22645
      /* Read or write a disk block. This is the only routine in which actual disk
22646
      * I/O is invoked. If an error occurs, a message is printed here, but the error
      * is not reported to the caller. If the error occurred while purging a block
22647
22648
       * from the cache, it is not clear what the caller could do about it anyway.
22649
22650
22651
       int r, op;
        off_t pos;
22652
22653
        dev t dev;
22654
        int block_size;
22655
22656
       block size = get block size(bp->b dev);
22657
22658
        if ( (dev = bp->b_dev) != NO_DEV)
22659
             pos = (off t) bp->b blocknr * block size;
```

```
Feb 25, 11 15:18
                               book.txt
                                                         Page 301/393
     File: Page: 938 servers/fs/cache.c
            op = (rw flag == READING ? DEV READ : DEV WRITE);
22660
22661
            r = dev_io(op, dev, FS_PROC_NR, bp->b_data, pos, block_size, 0);
22662
            if (r != block_size) {
22663
               if (r >= 0) r = END_OF_FILE;
22664
               if (r != END_OF_FILE)
22665
                printf("Unrecoverable disk error on device %d/%d, block %ld\n",
                        22666
                  bp->b_dev = NO_DEV;
22667
22668
22669
                  /* Report read errors to interested parties. */
22670
                  if (rw flag == READING) rdwt err = r;
22671
22672
22673
       bp->b dirt = CLEAN;
22674
22675
     /*_____*
22678
                              invalidate
22679
     *-----*/
22680 PUBLIC void invalidate(device)
22681
     dev t device;
                              /* device whose blocks are to be purged */
22682
22683 /* Remove all the blocks belonging to some device from the cache. */
22684
22685
       register struct buf *bp;
22686
22687
       for (bp = &buf[0]; bp < &buf[NR_BUFS]; bp++)
22688
           if (bp->b_dev == device) bp->b_dev = NO_DEV;
22689
22691
     /*_____*
22692
                              flushall
22693
      *_____*/
22694 PUBLIC void flushall(dev)
22695
                              /* device to flush */
22696
     /* Flush all dirty blocks for one device. */
22697
22698
22699
       register struct buf *bp;
22700
       static struct buf *dirty[NR_BUFS]; /* static so it isn't on stack */
22701
       int ndirty;
22702
22703
       for (bp = &buf[0], ndirty = 0; bp < &buf[NR_BUFS]; bp++)
22704
            if (bp->b dirt == DIRTY && bp->b dev == dev) dirty[ndirty++] = bp;
       rw_scattered(dev, dirty, ndirty, WRITING);
22705
22706
22708 /*============*
22709
                              rw_scattered
22711 PUBLIC void rw_scattered(dev, bufq, bufqsize, rw_flag)
22712 dev t dev;
                              /* major-minor device number */
22713 struct buf **bufq;
                              /* pointer to array of buffers */
22714 int bufqsize;
                              /* number of buffers */
22715
     int rw flag;
                              /* READING or WRITING */
22716
     /* Read or write scattered data from a device. */
22717
22718
22719
       register struct buf *bp;
```

```
Feb 25, 11 15:18
                                        book.txt
                                                                         Page 302/393
       File: Page: 939 servers/fs/cache.c
22720
         int gap;
22721
         register int i;
         register iovec_t *iop;
22722
22723
         static iovec_t iovec[NR_IOREQS]; /* static so it isn't on stack */
22724
         int j, r;
22725
         int block size;
22726
22727
         block_size = get_block_size(dev);
22728
22729
         /* (Shell) sort buffers on b_blocknr. */
22730
         qap = 1;
22731
22732
               gap = 3 * gap + 1;
22733
         while (gap <= bufqsize);
22734
         while (gap != 1)
22735
               qap /= 3;
22736
               for (j = gap; j < bufqsize; j++) {
22737
                       for (i = j - gap;
22738
                            i >= 0 && bufq[i]->b_blocknr > bufq[i + gap]->b_blocknr;
22739
                            i -= gap)
22740
                               bp = bufq[i];
22741
                               bufq[i] = bufq[i + gap];
22742
                               bufq[i + gap] = bp;
22743
22744
22745
22746
22747
         /* Set up I/O vector and do I/O. The result of dev_io is OK if everything
          * went fine, otherwise the error code for the first failed transfer.
22748
22749
22750
         while (bufqsize > 0) {
22751
               for (j = 0, iop = iovec; j < NR_IOREQS && j < bufqsize; j++, iop++) {
22752
                       bp = bufq[j];
22753
                       if (bp->b_blocknr != bufq[0]->b_blocknr + j) break;
22754
                       iop->iov_addr = (vir_bytes) bp->b_data;
22755
                       iop->iov_size = block_size;
22756
22757
               r = dev_io(rw_flag == WRITING ? DEV_SCATTER : DEV_GATHER,
22758
                       dev, FS_PROC_NR, iovec,
22759
                       (off_t) bufq[0]->b_blocknr * block_size, j, 0);
22760
22761
               /* Harvest the results. Dev_io reports the first error it may have
22762
                * encountered, but we only care if it's the first block that failed.
22763
22764
               for (i = 0, iop = iovec; i < j; i++, iop++) {
22765
                       bp = bufq[i];
22766
                       if (iop->iov_size != 0) {
22767
                               /* Transfer failed. An error? Do we care? */
22768
                               if (r != OK && i == 0) {
22769
                                       printf(
22770
                                        fs: I/O error on device %d/%d, block %lu\n",
22771
                                                (dev>>MAJOR)&BYTE, (dev>>MINOR)&BYTE,
22772
                                               bp->b blocknr);
22773
                                       bp->b dev = NO DEV;
                                                               /* invalidate block */
22774
22775
                               break;
22776
22777
                       if (rw_flag == READING) {
                                                       /* validate block */
22778
                               bp->b_dev = dev;
22779
                               put block(bp, PARTIAL DATA BLOCK);
```

```
Feb 25, 11 15:18
                                 book.txt
                                                             Page 303/393
      File: Page: 940 servers/fs/cache.c
22780
                   } else
22781
                          bp->b_dirt = CLEAN;
22782
22783
22784
             bufq += i;
22785
             bufqsize -= i;
22786
             if (rw_flag == READING) {
22787
                   /* Don't bother reading more than the device is willing to
22788
                    * give at this time. Don't forget to release those extras.
22789
22790
                   while (bufqsize > 0) {
22791
                          put block(*bufg++, PARTIAL DATA BLOCK);
22792
                          bufasize--;
22793
22794
22795
             if (rw_flag == WRITING && i == 0) {
22796
                   /* We're not making progress, this means we might keep
22797
                    * looping. Buffers remain dirty if un-written. Buffers are
22798
                    * lost if invalidate()d or LRU-removed while dirty. This
                    * is better than keeping unwritable blocks around forever..
22799
22800
22801
                   break;
22802
22803
22804 }
      22807
                                rm lru
22808
       22809 PRIVATE void rm_lru(bp)
      struct buf *bp;
22810
22811
22812
      /* Remove a block from its LRU chain. */
22813
       struct buf *next_ptr, *prev_ptr;
22814
22815
        bufs_in_use++;
        next_ptr = bp->b_next;
22816
                                 /* successor on LRII chain */
22817
                                 /* predecessor on LRU chain */
        prev_ptr = bp->b_prev;
22818
        if (prev ptr != NIL BUF)
22819
             prev_ptr->b_next = next_ptr;
22820
                                 /* this block was at front of chain */
22821
             front = next ptr;
22822
22823
        if (next_ptr != NIL_BUF)
22824
            next_ptr->b_prev = prev_ptr;
22825
        else
22826
             rear = prev_ptr;
                                 /* this block was at rear of chain */
22827 }
servers/fs/inode.c
/* This file manages the inode table. There are procedures to allocate and
      * deallocate inodes, acquire, erase, and release them, and read and write
      * them from the disk.
22902
22903
22904
      * The entry points into this file are
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 304/393
      File: Page: 941 servers/fs/inode.c
22905
           get_inode:
                         search inode table for a given inode; if not there,
22906
                        read it
22907
           put_inode:
                         indicate that an inode is no longer needed in memory
22908
           alloc_inode:
                         allocate a new, unused inode
                         erase some fields of a newly allocated inode
22909
           wipe_inode:
22910
           free inode:
                         mark an inode as available for a new file
           update_times: update atime, ctime, and mtime
22911
22912
           rw_inode:
                         read a disk block and extract an inode, or corresp. write
                         copy to/from in-core inode struct and disk inode (V1.x)
22913
           old icopy:
22914
                         copy to/from in-core inode struct and disk inode (V2.x)
           new_icopy:
22915
           dup inode:
                         indicate that someone else is using an inode table entry
22916
22917
      #include "fs.h"
22918
22919 #include "buf.h"
22920
      #include "file.h'
22921 #include "fproc.h"
22922 #include "inode.h"
22923 #include "super.h"
22924
22925 FORWARD _PROTOTYPE( void old_icopy, (struct inode *rip, d1_inode *dip,
22926
                                                   int direction, int norm));
22927 FORWARD _PROTOTYPE( void new_icopy, (struct inode *rip, d2_inode *dip,
22928
                                                   int direction, int norm));
22929
      /*----*
22930
22931
                                  get inode
22932
       22933
      PUBLIC struct inode *get_inode(dev, numb)
                                    /* device on which inode resides */
22934
      dev t dev;
22935
      int numb;
                                    /* inode number (ANSI: may not be unshort) */
22936
22937
      /* Find a slot in the inode table, load the specified inode into it, and
22938
       * return a pointer to the slot. If 'dev' == NO_DEV, just return a free slot.
22939
22940
22941
        register struct inode *rip, *xp;
22942
22943
        /* Search the inode table both for (dev, numb) and a free slot. */
22944
        xp = NIL_INODE;
22945
        for (rip = &inode[0]; rip < &inode[NR_INODES]; rip++) {
             if (rip->i_count > 0) { /* only check used slots for (dev, numb) */
22946
22947
                     if (rip->i_dev == dev && rip->i_num == numb)
22948
                             /* This is the inode that we are looking for. */
22949
                             rip->i count++;
22950
                             return(rip); /* (dev, numb) found */
22951
22952
              } else
22953
                     xp = rip;
                                    /* remember this free slot for later */
22954
22955
22956
22957
        /* Inode we want is not currently in use. Did we find a free slot? */
        if (xp == NIL INODE) {
22958
                                    /* inode table completely full */
22959
             err_code = ENFILE;
22960
              return(NIL INODE);
22961
22962
        /* A free inode slot has been located. Load the inode into it. */
22963
22964
        xp->i dev = dev;
```

```
book.txt
Feb 25, 11 15:18
                                                          Page 305/393
     File: Page: 942 servers/fs/inode.c
22965
       xp->i num = numb;
22966
       xp->i_count = 1;
22967
       22968
       xp->i_update = 0;
                               /* all the times are initially up-to-date */
22969
22970
       return(xp);
22971 }
22973 /*----*
22974
                             put_inode
22975
     22976 PUBLIC void put inode(rip)
22977 register struct inode *rip;
                             /* pointer to inode to be released */
22978
22979 /* The caller is no longer using this inode. If no one else is using it either
22980
     * write it back to the disk immediately. If it has no links, truncate it and
22981
     * return it to the pool of available inodes.
22982
22983
22984
       if (rip == NIL_INODE) return; /* checking here is easier than in caller */
      22985
22986
22987
                  /* i_nlinks == 0 means free the inode. */
                  truncate(rip); /* return all the disk blocks */
22988
                  rip->i_mode = I_NOT_ALLOC;
22989
                                         /* clear I_TYPE field */
22990
                  rip->i dirt = DIRTY;
22991
                  free inode(rip->i dev, rip->i num);
22992
            } else {
                  if (rip->i_pipe == I_PIPE) truncate(rip);
22993
22994
22995
            rip->i pipe = NO PIPE; /* should always be cleared */
            if (rip->i_dirt == DIRTY) rw_inode(rip, WRITING);
22996
22997
22998 }
23000 /*=========*
23001
                             alloc inode
     *_____*
23002
23003 PUBLIC struct inode *alloc inode(dev t dev, mode t bits)
23004
     /* Allocate a free inode on 'dev', and return a pointer to it. */
23005
23006
23007
       register struct inode *rip;
23008
       register struct super_block *sp;
       int major, minor, inumb;
23009
23010
       bit t b;
23011
23012
       sp = get_super(dev); /* get pointer to super_block */
23013
       if (sp->s_rd_only) { /* can't allocate an inode on a read only device. */
23014
            err code = EROFS;
23015
            return(NIL_INODE);
23016
23017
23018
       /* Acquire an inode from the bit map. */
23019
       b = alloc_bit(sp, IMAP, sp->s_isearch);
       if (b == NO_BIT) {
23020
           err_code = ENFILE;
23021
            major = (int) (sp->s_dev >> MAJOR) & BYTE;
23022
23023
            minor = (int) (sp->s_dev >> MINOR) & BYTE;
23024
           printf("Out of i-nodes on %sdevice %d/%d\n",
```

```
Feb 25, 11 15:18
                                  book.txt
                                                              Page 306/393
      File: Page: 943 servers/fs/inode.c
23025
                   sp->s dev == root dev ? "root " : "", major, minor);
             return(NIL_INODE);
23026
23027
23028
       sn->s isearch = h;
                                 /* next time start here */
                                 /* be careful not to pass unshort as param */
23029
       inumb = (int) b;
23030
23031
       /* Try to acquire a slot in the inode table. */
23032
       if ((rip = get_inode(NO_DEV, inumb)) == NIL_INODE) {
             /* No inode table slots available. Free the inode just allocated. */
23033
             free_bit(sp, IMAP, b);
23034
23035
       } else {
            /* An inode slot is available. Put the inode just allocated into it. */
23036
                                 /* set up RWX bits */
            rip->i mode = bits;
23037
                                        /* initial no links */
            rip->i_nlinks = 0;
23038
            rip->i_uid = fp->fp_effuid;
23039
                                      /* file's uid is owner's */
23040
            rip->i_gid = fp->fp_effgid;
                                      /* ditto group id */
23041
            rip->i_dev = dev;
                                        /* mark which device it is on */
23042
            rip->i_ndzones = sp->s_ndzones; /* number of direct zones */
23043
            rip->i_nindirs = sp->s_nindirs; /* number of indirect zones per blk*/
                                        /* pointer to super block */
23044
            rip->i_sp = sp;
23045
23046
             /* Fields not cleared already are cleared in wipe_inode(). They have
23047
              * been put there because truncate() needs to clear the same fields if
             * the file happens to be open while being truncated. It saves space
23048
23049
              * not to repeat the code twice.
23050
             wipe inode(rip);
23051
23052
23053
23054
       return(rip);
23055 }
23057 /*=========*
23058
                                wipe inode
23059 *===========*/
23060 PUBLIC void wipe_inode(rip)
23061 register struct inode *rip;
                               /* the inode to be erased */
23062
23063 /* Erase some fields in the inode. This function is called from alloc inode()
23064
      * when a new inode is to be allocated, and from truncate(), when an existing
      * inode is to be truncated.
23065
23066
23067
23068
       register int i;
23069
23070
       rip->i size = 0;
23071
       rip->i_update = ATIME | CTIME | MTIME;
                                               /* update all times later */
23072
       rip->i_dirt = DIRTY;
23073
       for (i = 0; i < V2_NR_TZONES; i++) rip->i_zone[i] = NO_ZONE;
23074 }
23076 /*=========*
23077 *
                                free inode
23078
     23079 PUBLIC void free_inode(dev, inumb)
23080 dev_t dev;
                                /* on which device is the inode */
                                 /* number of inode to be freed */
23081 ino t inumb;
23082
      /* Return an inode to the pool of unallocated inodes. */
23083
23084
```

```
Feb 25, 11 15:18
                                  book.txt
                                                               Page 307/393
      File: Page: 944 servers/fs/inode.c
23085
       register struct super block *sp;
23086
       bit_t b;
23087
23088
       /* Locate the appropriate super_block. */
23089
        sp = get_super(dev);
23090
       if (inumb <= 0 || inumb > sp->s_ninodes) return;
23091
       b = inumb;
23092
       free_bit(sp, IMAP, b);
       if (b < sp->s_isearch) sp->s_isearch = b;
23093
23094 }
23097
                                update times
23098
      23099 PUBLIC void update times(rip)
     register struct inode *rip;
                                 /* pointer to inode to be read/written */
23100
23101
23102 /* Various system calls are required by the standard to update atime, ctime,
23103 * or mtime. Since updating a time requires sending a message to the clock
      * task--an expensive business--the times are marked for update by setting
23104
23105
      * bits in i_update. When a stat, fstat, or sync is done, or an inode is
23106
       * released, update_times() may be called to actually fill in the times.
23107
23108
23109
       time t cur time;
23110
       struct super block *sp;
23111
23112
        sp = rip -> i sp;
                                  /* get pointer to super block. */
       if (sp->s_rd_only) return; /* no updates for read-only file systems */
23113
23114
23115
       cur time = clock time();
23116
       if (rip->i_update & ATIME) rip->i_atime = cur_time;
23117
        if (rip->i_update & CTIME) rip->i_ctime = cur_time;
23118
       if (rip->i_update & MTIME) rip->i_mtime = cur_time;
23119
       rip->i_update = 0;
                                  /* they are all up-to-date now */
23120 }
23122 /*----*
23123 *
                                rw inode
      *-----*/
23124
23125 PUBLIC void rw_inode(rip, rw_flag)
23126 register struct inode *rip; /* pointer to inode to be read/written */
                                  /* READING or WRITING */
23127 int rw_flag;
23128
23129 /* An entry in the inode table is to be copied to or from the disk. */
23130
23131
       register struct buf *bp;
23132
       register struct super_block *sp;
23133
       dl_inode *dip;
23134
       d2_inode *dip2;
23135
       block_t b, offset;
23136
       /* Get the block where the inode resides. */
23137
       sp = get_super(rip->i_dev);    /* get pointer to super block */
23138
                                 /* inode must contain super block pointer */
23139
       rip->i_sp = sp;
23140
        offset = sp->s_imap_blocks + sp->s_zmap_blocks + 2;
       b = (block_t) (rip->i_num - 1)/sp->s_inodes_per_block + offset;
23141
       bp = get_block(rip->i_dev, b, NORMAL);
23142
       dip = bp->b_v1_ino + (rip->i_num - 1) % V1_INODES_PER_BLOCK;
23143
23144
       dip2 = bp \rightarrow b v2 ino + (rip \rightarrow i num - 1) %
```

```
Feb 25, 11 15:18
                                      book.txt
                                                                      Page 308/393
       File: Page: 945 servers/fs/inode.c
23145
               V2 INODES PER BLOCK(sp->s block size);
23146
23147
         /* Do the read or write. */
23148
        if (rw flag == WRITING) {
              if (rip->i_update) update_times(rip); /* times need updating */
23149
23150
              if (sp->s_rd_only == FALSE) bp->b_dirt = DIRTY;
23151
23152
23153
         /* Copy the inode from the disk block to the in-core table or vice versa.
23154
         * If the fourth parameter below is FALSE, the bytes are swapped.
23155
23156
        if (sp->s version == V1)
23157
              old_icopy(rip, dip, rw_flag, sp->s_native);
23158
         else
23159
              new icopy(rip, dip2, rw flag, sp->s native);
23160
23161
        put_block(bp, INODE_BLOCK);
23162
        rip->i_dirt = CLEAN;
23163 }
23165 /*==========*
23166
                                    old_icopy
23167 *========*/
23168 PRIVATE void old_icopy(rip, dip, direction, norm)
23169 register struct inode *rip; /* pointer to the in-core inode struct */
23170 register dl_inode *dip; /* pointer to the dl_inode inode struct */
                                     /* READING (from disk) or WRITING (to disk) */
23171 int direction;
23172 int norm;
                                     /* TRUE = do not swap bytes; FALSE = swap */
23173
23174
23175 /* The V1.x IBM disk, the V1.x 68000 disk, and the V2 disk (same for IBM and
      * 68000) all have different inode layouts. When an inode is read or written
23176
       * this routine handles the conversions so that the information in the inode
23178
        * table is independent of the disk structure from which the inode came.
       * The old_icopy routine copies to and from V1 disks.
23179
23180
23181
23182
        int i;
23183
23184
        if (direction == READING) {
               /* Copy V1.x inode to the in-core table, swapping bytes if need be. */
23185
              rip->i_mode = conv2(norm, (int) dip->d1_mode);
23186
              rip->i_uid = conv2(norm, (int) dip->dl_uid);
rip->i_size = conv4(norm, dip->dl_size);
23187
23188
              rip->i mtime = conv4(norm,
23189
                                                dip->d1 mtime);
23190
              rip->i_atime = rip->i_mtime;
23191
              rip->i_ctime = rip->i_mtime;
23192
              rip->i_nlinks = dip->dl_nlinks;
                                                             /* 1 char */
23193
              rip->i_gid = dip->dl_gid;
                                                             /* 1 char */
23194
              rip->i_ndzones = V1_NR_DZONES;
23195
              rip->i_nindirs = V1_INDIRECTS;
23196
              for (i = 0; i < V1_NR_TZONES; i++)
                      rip->i_zone[i] = conv2(norm, (int) dip->d1_zone[i]);
23197
        } else {
23198
              /* Copying V1.x inode to disk from the in-core table. */
23199
              dip->dl_mode = conv2(norm, (int) rip->i_mode);
23200
              dip->dl uid = conv2(norm, (int) rip->i uid );
23201
              dip->dl_size = conv4(norm,
23202
                                                rip->i size);
              dip->d1_mtime = conv4(norm,
23203
                                                rip->i_mtime);
23204
              dip->d1 nlinks = rip->i nlinks;
                                                             /* 1 char */
```

```
book.txt
Feb 25, 11 15:18
                                                                Page 309/393
      File: Page: 946 servers/fs/inode.c
23205
             dip->dl_gid = rip->i_gid;
                                                        /* 1 char */
23206
             for (i = 0; i < V1_NR_TZONES; i++)
23207
                    dip->d1_zone[i] = conv2(norm, (int) rip->i_zone[i]);
23208
23209 }
23211 /*=========*
23212 *
                                 new_icopy
23214 PRIVATE void new_icopy(rip, dip, direction, norm)
23215 register struct inode *rip;
                                 /* pointer to the in-core inode struct */
23216 register d2_inode *dip; /* pointer to the d2_inode struct */
                                  /* READING (from disk) or WRITING (to disk) */
23217 int direction;
                                  /* TRUE = do not swap bytes; FALSE = swap */
23218 int norm;
23219
23220
23221
      /* Same as old_icopy, but to/from V2 disk layout. */
23222
23223
       int i;
23224
23225
        if (direction == READING) {
23226
             /* Copy V2.x inode to the in-core table, swapping bytes if need be. */
23227
             rip->i_mode = conv2(norm,dip->d2_mode);
23228
             rip->i uid
                         = conv2(norm,dip->d2 uid);
             rip->i_nlinks = conv2(norm,dip->d2_nlinks);
23229
23230
             rip->i_gid = conv2(norm,dip->d2_gid);
                        = conv4(norm,dip->d2_size);
23231
             rip->i size
             rip->i_atime = conv4(norm,dip->d2_atime);
23232
             rip->i_ctime = conv4(norm,dip->d2_ctime);
23233
             rip->i mtime = conv4(norm,dip->d2 mtime);
23234
             rip->i_ndzones = V2_NR_DZONES;
23235
23236
             rip->i_nindirs = V2_INDIRECTS(rip->i_sp->s_block_size);
23237
             for (i = 0; i < V2_NR_TZONES; i++)
23238
                    rip->i_zone[i] = conv4(norm, (long) dip->d2_zone[i]);
       } else {
23239
23240
             /* Copying V2.x inode to disk from the in-core table. */
             dip->d2_mode = conv2(norm,rip->i_mode);
dip->d2_uid = conv2(norm,rip->i_uid);
23241
23242
             dip->d2_nlinks = conv2(norm,rip->i_nlinks);
23243
             dip->d2_gid = conv2(norm,rip->i_gid);
dip->d2 size = conv4(norm,rip->i size);
23244
23245
             dip->d2 atime = conv4(norm,rip->i atime);
23246
             dip->d2_ctime = conv4(norm,rip->i_ctime);
23247
23248
             dip->d2_mtime = conv4(norm,rip->i_mtime);
             for (i = 0; i < V2 NR TZONES; i++)
23249
                    dip->d2_zone[i] = conv4(norm, (long) rip->i_zone[i]);
23250
23251
23252 }
23255
                                  dup_inode
23256
      23257 PUBLIC void dup_inode(ip)
23258 struct inode *ip;
                                /* The inode to be duplicated. */
23259
      /* This routine is a simplified form of get_inode() for the case where
23260
      * the inode pointer is already known.
23261
23262
23263
23264
       ip->i count++;
```

```
Feb 25, 11 15:18
                                   book.txt
                                                                 Page 310/393
      File: Page: 947 servers/fs/inode.c
23265
servers/fs/super.c
23300 /* This file manages the super block table and the related data structures,
23301 * namely, the bit maps that keep track of which zones and which inodes are
       * allocated and which are free. When a new inode or zone is needed, the
23302
       * appropriate bit map is searched for a free entry.
23303
23304
23305
       * The entry points into this file are
23306
       * alloc_bit:
                           somebody wants to allocate a zone or inode; find one
23307
          free_bit:
                           indicate that a zone or inode is available for allocation
23308
                           search the 'superblock' table for a device
          get_super:
                          tells if file inode is on mounted (or ROOT) file system
23309
          mounted:
                          read a superblock
23310
          read_super:
23311
23312
23313 #include "fs.h"
23314 #include <string.h>
23315 #include <minix/com.h>
23316 #include "buf.h"
23317 #include "inode.h'
23318 #include "super.h"
23319 #include "const.h"
23320
23321 /*=======*
23322 *
                                alloc_bit
23323 *============*/
23324 PUBLIC bit_t alloc_bit(sp, map, origin)
23325 struct super_block *sp; /* the filesystem to allocate from */
23326 int map;
                                   /* IMAP (inode map) or ZMAP (zone map) */
                                   /* number of bit to start searching at */
23327 bit_t origin;
23328
      /* Allocate a bit from a bit map and return its bit number. */
23329
23330
23331
        block_t start_block;
                                   /* first bit block */
                                   /* how many bits are there in the bit map? */
23332
        bit_t map_bits;
23333
        unsigned bit_blocks;
                                   /* how many blocks are there in the bit map? */
        unsigned block, word, bcount;
23334
23335
        struct buf *bp;
        bitchunk_t *wptr, *wlim, k;
23336
23337
        bit_t i, b;
23338
23339
        if (sp->s_rd_only)
23340
             panic(__FILE__, "can't allocate bit on read-only filesys.", NO_NUM);
23341
23342
        if (map == IMAP) {
             start block = START BLOCK;
23343
23344
             map_bits = sp->s_ninodes + 1;
23345
             bit_blocks = sp->s_imap_blocks;
23346
        } else {
23347
             start_block = START_BLOCK + sp->s_imap_blocks;
23348
             map_bits = sp->s_zones - (sp->s_firstdatazone - 1);
23349
             bit blocks = sp->s zmap blocks;
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 311/393
      File: Page: 948 servers/fs/super.c
23350
23351
23352
        /* Figure out where to start the bit search (depends on 'origin'). */
23353
        if (origin >= map_bits) origin = 0; /* for robustness */
23354
23355
         /* Locate the starting place. */
23356
        block = origin / FS_BITS_PER_BLOCK(sp->s_block_size);
23357
        word = (origin % FS_BITS_PER_BLOCK(sp->s_block_size)) / FS_BITCHUNK_BITS;
23358
23359
        /* Iterate over all blocks plus one, because we start in the middle. */
23360
        bcount = bit blocks + 1;
23361
        do {
23362
              bp = get_block(sp->s_dev, start_block + block, NORMAL);
23363
              wlim = &bp->b_bitmap[FS_BITMAP_CHUNKS(sp->s_block_size)];
23364
23365
              /* Iterate over the words in block. */
23366
              for (wptr = &bp->b_bitmap[word]; wptr < wlim; wptr++) {</pre>
23367
23368
                      /* Does this word contain a free bit? */
23369
                      if (*wptr == (bitchunk_t) ~0) continue;
23370
23371
                      /* Find and allocate the free bit. */
23372
                     k = conv2(sp->s_native, (int) *wptr);
23373
                     for (i = 0; (k \& (1 << i)) != 0; ++i) {}
23374
23375
                      /* Bit number from the start of the bit map. */
                     b = ((bit t) block * FS BITS PER BLOCK(sp->s block size))
23376
                         + (wptr - &bp->b_bitmap[0]) * FS_BITCHUNK_BITS
23377
23378
                         + i;
23379
                      /* Don't allocate bits beyond the end of the map. */
23380
23381
                     if (b >= map_bits) break;
23382
23383
                      /* Allocate and return bit number. */
23384
                     k = 1 << i;
23385
                      *wptr = conv2(sp->s_native, (int) k);
23386
                      bp->b dirt = DIRTY;
23387
                     put_block(bp, MAP_BLOCK);
23388
                     return(b);
23389
23390
              put_block(bp, MAP_BLOCK);
              if (++block >= bit blocks) block = 0; /* last block, wrap around */
23391
23392
              word = 0;
23393
        } while (--bcount > 0);
        return(NO BIT);
                                    /* no bit could be allocated */
23394
23395
23397 /*=========*
23398
                                    free bit
23399 *============*/
23400 PUBLIC void free_bit(sp, map, bit_returned)
23401 struct super_block *sp;
                                    /\bar{*} the filesystem to operate on */
                                    /* IMAP (inode map) or ZMAP (zone map) */
23402 int map;
23403 bit_t bit_returned;
                                    /* number of bit to insert into the map */
23404
      /* Return a zone or inode by turning off its bitmap bit. */
23405
23406
23407
        unsigned block, word, bit;
23408
        struct buf *bp;
23409
        bitchunk t k, mask;
```

```
Feb 25, 11 15:18
                                  book.txt
                                                              Page 312/393
      File: Page: 949 servers/fs/super.c
23410
       block_t start_block;
23411
23412
       if (sp->s_rd_only)
23413
            panic(__FILE__, "can't free bit on read-only filesys.", NO_NUM);
23414
23415
       if (map == IMAP) {
23416
            start_block = START_BLOCK;
23417
       } else {
23418
            start block = START BLOCK + sp->s imap blocks;
23419
23420
       block = bit_returned / FS_BITS_PER_BLOCK(sp->s_block_size);
23421
       word = (bit_returned % FS_BITS_PER_BLOCK(sp->s_block_size))
23422
             / FS_BITCHUNK_BITS;
23423
23424
       bit = bit returned % FS BITCHUNK BITS;
23425
       mask = 1 << bit;
23426
23427
       bp = get_block(sp->s_dev, start_block + block, NORMAL);
23428
23429
       k = conv2(sp->s_native, (int) bp->b_bitmap[word]);
23430
       if (!(k & mask)) {
            panic(__FILE__,map == IMAP ? "tried to free unused inode" :
23431
23432
                  "tried to free unused block", NO_NUM);
23433
23434
23435
       k &= ~mask;
       bp->b bitmap[word] = conv2(sp->s native, (int) k);
23436
23437
       bp->b_dirt = DIRTY;
23438
23439
       put block(bp, MAP BLOCK);
23440 }
23442 /*============*
23443
                                 get super
23445 PUBLIC struct super_block *get_super(dev)
23446 dev_t dev;
                                 /* device number whose super_block is sought */
23447
23448
      /* Search the superblock table for this device. It is supposed to be there. */
23449
23450
       register struct super block *sp;
23451
23452
       if (dev == NO DEV)
23453
            panic(__FILE__, "request for super_block of NO_DEV", NO_NUM);
23454
23455
       for (sp = &super_block[0]; sp < &super_block[NR_SUPERS]; sp++)</pre>
23456
            if (sp->s_dev == dev) return(sp);
23457
23458
       /* Search failed. Something wrong. */
23459
       panic(__FILE__, "can't find superblock for device (in decimal)", (int) dev);
23460
23461
       return(NIL SUPER);
                                 /* to keep the compiler and lint quiet */
23462
23465
                                 get block size
23466
      23467
     PUBLIC int get_block_size(dev_t dev)
23468
23469 /* Search the superblock table for this device. */
```

```
book.txt
Feb 25, 11 15:18
                                                              Page 313/393
      File: Page: 950 servers/fs/super.c
23470
23471
       register struct super_block *sp;
23472
23473
       if (dev == NO DEV)
23474
             panic(__FILE__, "request for block size of NO_DEV", NO_NUM);
23475
23476
       for (sp = &super_block[0]; sp < &super_block[NR_SUPERS]; sp++) {</pre>
23477
             if (sp->s_dev == dev)
23478
                   return(sp->s block size);
23479
23480
23481
       /* no mounted filesystem? use this block size then. */
23482
23483
       return MIN_BLOCK_SIZE;
23484
23486 /*=======*
23487
                                 mounted
23488
      *----*/
23489 PUBLIC int mounted(rip)
23490 register struct inode *rip;
                                 /* pointer to inode */
23491
      /* Report on whether the given inode is on a mounted (or ROOT) file system. */
23492
23493
23494
       register struct super_block *sp;
23495
       register dev t dev;
23496
23497
       dev = (dev_t) rip->i_zone[0];
       if (dev == root_dev) return(TRUE); /* inode is on root file system */
23498
23499
23500
       for (sp = &super block[0]; sp < &super block[NR SUPERS]; sp++)
23501
             if (sp->s_dev == dev) return(TRUE);
23502
23503
       return(FALSE);
23504
23506 /*===========*
23507
                                 read_super
      23509 PUBLIC int read_super(sp)
23510
      register struct super_block *sp; /* pointer to a superblock */
23511
23512 /* Read a superblock. */
23513
       dev_t dev;
23514
       int magic;
23515
       int version, native, r;
23516
       static char sbbuf[MIN_BLOCK_SIZE];
23517
23518
                                 /* save device (will be overwritten by copy) */
       dev = sp->s_dev;
23519
       if (dev == NO_DEV)
23520
             panic(__FILE__, "request for super_block of NO_DEV", NO_NUM);
       r = dev_io(DEV_READ, dev, FS_PROC_NR,
23521
23522
             sbbuf, SUPER_BLOCK_BYTES, MIN_BLOCK_SIZE, 0);
23523
       if (r != MIN BLOCK SIZE) {
            return EINVAL;
23524
23525
23526
       memcpy(sp, sbbuf, sizeof(*sp));
       sp->s_dev = NO_DEV;
                                 /* restore later */
23527
23528
       magic = sp->s_magic;
                                 /* determines file system type */
23529
```

```
Feb 25, 11 15:18
                                        book.txt
                                                                          Page 314/393
       File: Page: 951 servers/fs/super.c
23530
         /* Get file system version and type. */
23531
         if (magic == SUPER_MAGIC || magic == conv2(BYTE_SWAP, SUPER_MAGIC)) {
23532
               version = V1;
23533
               native = (magic == SUPER MAGIC);
         } else if (magic == SUPER_V2 || magic == conv2(BYTE_SWAP, SUPER_V2)) {
23534
23535
               version = V2;
23536
               native = (magic == SUPER_V2);
         } else if (magic == SUPER_V3) {
23537
23538
               version = V3;
23539
               native = 1;
23540
         } else {
23541
               return(EINVAL);
23542
23543
23544
         /* If the super block has the wrong byte order, swap the fields; the magic
23545
         * number doesn't need conversion. */
23546
         sp->s_ninodes =
                               conv4(native, sp->s_ninodes);
23547
         sp->s_nzones =
                               conv2(native, (int) sp->s_nzones);
23548
         sp->s_imap_blocks = conv2(native, (int) sp->s_imap_blocks);
sp->s_zmap_blocks = conv2(native, (int) sp->s_zmap_blocks);
23549
23550
         sp->s_firstdatazone = conv2(native, (int) sp->s_firstdatazone);
23551
         sp->s_log_zone_size = conv2(native, (int) sp->s_log_zone_size);
23552
         sp->s_max_size = conv4(native, sp->s_max_size);
23553
         sp->s zones =
                               conv4(native, sp->s_zones);
23554
23555
         /* In V1, the device size was kept in a short, s_nzones, which limited
23556
          * devices to 32K zones. For V2, it was decided to keep the size as a
23557
          * long. However, just changing s_nzones to a long would not work, since
          * then the position of s_magic in the super block would not be the same
23558
23559
          * in V1 and V2 file systems, and there would be no way to tell whether
23560
          * a newly mounted file system was V1 or V2. The solution was to introduce
23561
          * a new variable, s_zones, and copy the size there.
23562
23563
          * Calculate some other numbers that depend on the version here too, to
          * hide some of the differences.
23564
23565
23566
         if (version == V1) {
23567
               sp->s_block_size = STATIC_BLOCK_SIZE;
23568
               sp->s_zones = sp->s_nzones;
                                               /* only V1 needs this copy */
23569
               sp->s_inodes_per_block = V1_INODES_PER_BLOCK;
23570
               sp->s_ndzones = V1_NR_DZONES;
               sp->s nindirs = V1 INDIRECTS;
23571
23572
         } else
23573
               if (version == V2)
23574
                       sp->s block size = STATIC BLOCK SIZE;
23575
               if (sp->s_block_size < MIN_BLOCK_SIZE)
23576
                       return EINVAL;
23577
               sp->s_inodes_per_block = V2_INODES_PER_BLOCK(sp->s_block_size);
23578
               sp->s_ndzones = V2_NR_DZONES;
23579
               sp->s_nindirs = V2_INDIRECTS(sp->s_block_size);
23580
23581
         if (sp->s_block_size < MIN_BLOCK_SIZE) {</pre>
23582
23583
               return EINVAL;
23584
23585
         if (sp->s_block_size > MAX_BLOCK_SIZE) {
               printf("Filesystem block size is %d kB; maximum filesystem\n"
23586
                "block size is d kB. This limit can be increased by recompiling.\n",
23587
23588
               sp->s_block_size/1024, MAX_BLOCK_SIZE/1024);
23589
               return EINVAL;
```

```
Feb 25, 11 15:18
                                 book.txt
                                                             Page 315/393
      File: Page: 952 servers/fs/super.c
23590
23591
        if ((sp->s_block_size % 512) != 0) {
23592
             return EINVAL;
23593
23594
        if (SUPER_SIZE > sp->s_block_size) {
23595
             return EINVAL;
23596
        if ((sp->s_block_size % V2_INODE_SIZE) != 0 ||
23597
          (sp->s_block_size % V1_INODE_SIZE) != 0)
23598
23599
             return EINVAL;
23600
23601
23602
        sp->s isearch = 0;
                                 /* inode searches initially start at 0 */
23603
        sp->s_zsearch = 0;
                                 /* zone searches initially start at 0 */
23604
        sp->s_version = version;
23605
        sp->s native = native;
23606
23607
        /* Make a few basic checks to see if super block looks reasonable. */
23608
        if (sp->s_imap_blocks < 1 || sp->s_zmap_blocks < 1
                                   sp->s_ninodes < 1 || sp->s_zones < 1
23609
23610
                                  (unsigned) sp->s_log_zone_size > 4) {
23611
             printf("not enough imap or zone map blocks, \n");
23612
             printf("or not enough inodes, or not enough zones, "
23613
                    "or zone size too large\n");
             return(EINVAL);
23614
23615
23616
        sp->s dev = dev;
                                 /* restore device number */
23617
        return(OK);
23618
servers/fs/filedes.c
23700 /* This file contains the procedures that manipulate file descriptors.
23701
23702
      * The entry points into this file are
23703
      * get_fd: look for free file descriptor and free filp slots
23704
      * get_filp: look up the filp entry for a given file descriptor
      * find_filp: find a filp slot that points to a given inode
23705
      * /
23706
23707
23708 #include "fs.h"
23709 #include "file.h"
23710 #include "fproc.h"
23711 #include "inode.h"
23712
23713 /*===========*
23714 *
                                get_fd
23716 PUBLIC int get_fd(int start, mode_t bits, int *k, struct filp **fpt)
23717
23718 /* Look for a free file descriptor and a free filp slot. Fill in the mode word
23719
      * in the latter, but don't claim either one yet, since the open() or creat()
      * may yet fail.
23720
23721
23722
        register struct filp *f;
23723
23724
       register int i;
```

```
Feb 25, 11 15:18
                                   book.txt
                                                                Page 316/393
      File: Page: 953 servers/fs/filedes.c
23725
23726
                                  /* we need a way to tell if file desc found */
23727
23728
        /* Search the fproc fp_filp table for a free file descriptor. */
23729
        for (i = start; i < OPEN_MAX; i++)
23730
             if (fp->fp_filp[i] == NIL_FILP) {
23731
                    /* A file descriptor has been located. */
                    *k = i;
23732
23733
                    break;
23734
23735
23736
        /* Check to see if a file descriptor has been found. */
23737
        if (*k < 0) return(EMFILE); /* this is why we initialized k to -1 */
23738
23739
23740
        /\!\!\!\!\!^{*} Now that a file descriptor has been found, look for a free filp slot. ^{*}/\!\!\!\!
23741
        for (f = &filp[0]; f < &filp[NR_FILPS]; f++) {
             if (f->filp_count == 0)
23742
23743
                    f->filp mode = bits;
23744
                    f->filp_pos = 0L;
23745
                    f->filp_selectors = 0;
23746
                    f->filp_select_ops = 0;
23747
                    f->filp_pipe_select_ops = 0;
23748
                    f->filp flags = 0;
23749
                    *fpt = f;
23750
                    return(OK);
23751
23752
23753
23754
        /* If control passes here, the filp table must be full. Report that back. */
23755
        return(ENFILE);
23756
23758
      /*_____*
23759
                                  get_filp
23760
      *-----*/
23761 PUBLIC struct filp *get_filp(fild)
23762
     int fild;
                                  /* file descriptor */
23763
      /* See if 'fild' refers to a valid file descr. If so, return its filp ptr. */
23764
23765
23766
        err code = EBADF;
23767
        if (fild < 0 || fild >= OPEN_MAX ) return(NIL_FILP);
23768
        return(fp->fp_filp[fild]); /* may also be NIL_FILP */
23769
23771 /*=========*
23772
                                  find_filp
23773
      *-----*
23774 PUBLIC struct filp *find_filp(register struct inode *rip, mode_t bits)
23775
      /* Find a filp slot that refers to the inode 'rip' in a way as described
23776
      * by the mode bit 'bits'. Used for determining whether somebody is still
23777
      * interested in either end of a pipe. Also used when opening a FIFO to
23778
23779
       * find partners to share a filp field with (to shared the file position).
       * Like 'get_fd' it performs its job by linear search through the filp table.
23780
23781
23782
        register struct filp *f;
23783
23784
```

```
book.txt
Feb 25, 11 15:18
                                                              Page 317/393
      File: Page: 954 servers/fs/filedes.c
       for (f = &filp[0]; f < &filp[NR_FILPS]; f++) {
23785
23786
             if (f->filp_count != 0 && f->filp_ino == rip && (f->filp_mode & bits)){
23787
                   return(f);
23788
23789
23790
23791
        /* If control passes here, the filp wasn't there. Report that back. */
23792
        return(NIL_FILP);
23793
servers/fs/lock.c
23800 /* This file handles advisory file locking as required by POSIX.
23801 3
23802 * The entry points into this file are
23803 *
          lock_op: perform locking operations for FCNTL system call
23804
          lock_revive: revive processes when a lock is released
23805 */
23806
23807 #include "fs.h"
23808 #include <minix/com.h>
23809 #include <fcntl.h>
23810 #include <unistd.h>
23811 #include "file.h"
23812 #include "fproc.h"
23813 #include "inode.h"
23814 #include "lock.h"
23815 #include "param.h"
23816
23817 /*===========*
23818 *
                                 lock op
23819 *-----*/
23820 PUBLIC int lock_op(f, req)
23821 struct filp *f;
                                 /* either F_SETLK or F_SETLKW */
23822 int req;
23823
23824
      /* Perform the advisory locking required by POSIX. */
23825
23826
        int r, ltype, i, conflict = 0, unlocking = 0;
       mode_t mo;
23827
23828
        off_t first, last;
        struct flock flock;
23829
23830
        vir bytes user flock;
23831
        struct file_lock *flp, *flp2, *empty;
23832
23833
        /* Fetch the flock structure from user space. */
23834
        user_flock = (vir_bytes) m_in.namel;
23835
        r = sys_datacopy(who, (vir_bytes) user_flock,
             FS_PROC_NR, (vir_bytes) &flock, (phys_bytes) sizeof(flock));
23836
23837
        if (r != OK) return(EINVAL);
23838
23839
        /* Make some error checks. */
23840
        ltype = flock.l_type;
        mo = f->filp mode;
23841
23842
        if (ltype != F_UNLCK && ltype != F_RDLCK && ltype != F_WRLCK) return(EINVAL);
23843
        if (req == F_GETLK && ltype == F_UNLCK) return(EINVAL);
23844
        if ((f->filp ino->i mode & I TYPE) != I REGULAR) return(EINVAL);
```

```
Feb 25, 11 15:18
                                         book.txt
                                                                           Page 318/393
       File: Page: 955 servers/fs/lock.c
         if (req != F_GETLK && ltype == F_RDLCK && (mo & R_BIT) == 0) return(EBADF);
23845
23846
         if (req != F_GETLK && ltype == F_WRLCK && (mo & W_BIT) == 0) return(EBADF);
23847
23848
         /* Compute the first and last bytes in the lock region. */
23849
         switch (flock.l_whence)
23850
               case SEEK_SET: first = 0; break;
                                first = f->filp_pos; break;
23851
               case SEEK CUR:
23852
                                first = f->filp_ino->i_size; break;
               case SEEK END:
23853
               default:
                                 return(EINVAL);
23854
         /* Check for overflow. */
23855
         if (((long)flock.l_start > 0) && ((first + flock.l_start) < first))</pre>
23856
23857
               return(EINVAL);
         if (((long)flock.l_start < 0) && ((first + flock.l_start) > first))
23858
23859
               return(EINVAL);
23860
         first = first + flock.l start;
23861
         last = first + flock.l_len - 1;
23862
         if (flock.l_len == 0) last = MAX_FILE_POS;
23863
         if (last < first) return(EINVAL);
23864
23865
         /* Check if this region conflicts with any existing lock. */
23866
         empty = (struct file_lock *) 0;
         for (flp = &file_lock[0]; flp < & file_lock[NR_LOCKS]; flp++) {</pre>
23867
23868
               if (flp->lock_type == 0) {
23869
                       if (empty == (struct file_lock *) 0) empty = flp;
23870
                        continue;
                                        /* 0 means unused slot */
23871
23872
               if (flp->lock_inode != f->filp_ino) continue; /* different file */
               if (last < flp->lock_first) continue; /* new one is in front */
if (first > flp->lock_last) continue; /* new one is afterwards */
23873
23874
23875
               if (ltype == F_RDLCK && flp->lock_type == F_RDLCK) continue;
23876
               if (ltype != F_UNLCK && flp->lock_pid == fp->fp_pid) continue;
23877
23878
               /* There might be a conflict. Process it. */
23879
               conflict = 1;
23880
               if (req == F_GETLK) break;
23881
23882
                /* If we are trying to set a lock, it just failed. */
23883
               if (ltype == F_RDLCK | | ltype == F_WRLCK) {
23884
                       if (req == F_SETLK)
23885
                                /* For F_SETLK, just report back failure. */
23886
                                return(EAGAIN);
                       } else {
23887
                                /* For F_SETLKW, suspend the process. */
23888
23889
                                suspend(XLOCK);
23890
                                return(SUSPEND);
23891
23892
23893
23894
               /* We are clearing a lock and we found something that overlaps. */
23895
               unlocking = 1;
23896
               if (first <= flp->lock_first && last >= flp->lock_last)
                                              /* mark slot as unused */
23897
                        flp->lock_type = 0;
                                                 /* number of locks is now 1 less */
23898
                       nr locks--;
23899
                       continue;
23900
23901
23902
               /* Part of a locked region has been unlocked. */
               if (first <= flp->lock_first) {
23903
23904
                        flp->lock first = last + 1;
```

```
Feb 25, 11 15:18
                                        book.txt
                                                                          Page 319/393
       File: Page: 956 servers/fs/lock.c
23905
                       continue;
23906
23907
23908
               if (last >= flp->lock_last) {
                       flp->lock_last = first - 1;
23909
23910
                       continue;
23911
23912
23913
               /* Bad luck. A lock has been split in two by unlocking the middle. */
23914
               if (nr_locks == NR_LOCKS) return(ENOLCK);
23915
               for (i = 0; i < NR\_LOCKS; i++)
23916
                       if (file_lock[i].lock_type == 0) break;
               flp2 = &file_lock[i];
23917
23918
               flp2->lock_type = flp->lock_type;
               flp2->lock pid = flp->lock pid;
23919
23920
               flp2->lock_inode = flp->lock_inode;
23921
               flp2->lock_first = last + 1;
23922
               flp2->lock_last = flp->lock_last;
23923
               flp->lock last = first - 1;
23924
               nr_locks++;
23925
23926
         if (unlocking) lock_revive();
23927
23928
         if (req == F GETLK)
23929
               if (conflict)
23930
                       /* GETLK and conflict. Report on the conflicting lock. */
                       flock.l_type = flp->lock_type;
23931
                       flock.l_whence = SEEK_SET;
flock.l_start = flp->lock_first;
23932
23933
                       flock.l len = flp->lock last - flp->lock first + 1;
23934
23935
                       flock.l_pid = flp->lock_pid;
23936
23937
               } else {
                        /* It is GETLK and there is no conflict. */
23938
23939
                       flock.l_type = F_UNLCK;
23940
23941
               /* Copy the flock structure back to the caller. */
23942
23943
               r = sys_datacopy(FS_PROC_NR, (vir_bytes) &flock,
23944
                       who, (vir_bytes) user_flock, (phys_bytes) sizeof(flock));
23945
               return(r);
23946
23947
23948
         if (ltype == F_UNLCK) return(OK);
                                               /* unlocked a region with no locks */
23949
23950
         /st There is no conflict. If space exists, store new lock in the table. st/
23951
         if (empty == (struct file_lock *) 0) return(ENOLCK); /* table full */
23952
         empty->lock_type = ltype;
23953
         empty->lock_pid = fp->fp_pid;
         empty->lock_inode = f->filp_ino;
23954
23955
         empty->lock_first = first;
23956
         empty->lock_last = last;
23957
         nr locks++;
23958
         return(OK);
23959 }
```

```
Feb 25, 11 15:18
                                 book.txt
                                                             Page 320/393
      File: Page: 957 servers/fs/lock.c
23961
     23962
                                 lock_revive
23963
      23964 PUBLIC void lock_revive()
23965
23966 /* Go find all the processes that are waiting for any kind of lock and
23967
      * revive them all. The ones that are still blocked will block again when
      ^{\star} they run. The others will complete. This strategy is a space-time
23968
      * tradeoff. Figuring out exactly which ones to unblock now would take
23970
       * extra code, and the only thing it would win would be some performance in
23971
       * extremely rare circumstances (namely, that somebody actually used
23972
      * locking).
23973
      * /
23974
23975
        int task;
23976
       struct fproc *fptr;
23977
23978
        for (fptr = &fproc[INIT_PROC_NR + 1]; fptr < &fproc[NR_PROCS]; fptr++){
             task = -fptr->fp_task;
23979
             if (fptr->fp_suspended == SUSPENDED && task == XLOCK) {
23980
23981
                   revive( (int) (fptr - fproc), 0);
23982
23983
23984 }
servers/fs/main.c
24000 /* This file contains the main program of the File System. It consists of
24001 * a loop that gets messages requesting work, carries out the work, and sends
24002
     * replies.
24003
      * The entry points into this file are:
24004
      * main:
24005
                    main program of the File System
      * reply:
24006
                    send a reply to a process after the requested work is done
24007
24008
24009
24010 struct super block;
                                 /* proto.h needs to know this */
24011
24012 #include "fs.h"
24013 #include <fcntl.h>
24014 #include <string.h>
24015 #include <stdio.h>
24016 #include <signal.h>
24017 #include <stdlib.h>
24018 #include <sys/ioc_memory.h>
24019 #include <sys/svrctl.h>
24020 #include <minix/callnr.h>
24021 #include <minix/com.h>
24022 #include <minix/keymap.h>
24023 #include <minix/const.h>
24024 #include "buf.h"
24025 #include "file.h"
24026 #include "fproc.h"
24027 #include "inode.h"
24028 #include "param.h"
24029 #include "super.h"
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 321/393
      File: Page: 958 servers/fs/main.c
24030
24031 FORWARD _PROTOTYPE( void fs_init, (void)
24032 FORWARD _PROTOTYPE( int igetenv, (char *var, int optional)
                                                                          );
24033 FORWARD _PROTOTYPE( void get_work, (void)
                                                                          );
24034 FORWARD _PROTOTYPE( void load_ram, (void)
                                                                          );
24035 FORWARD _PROTOTYPE( void load_super, (Dev_t super_dev)
24036
      /*_____*
24037
24038
                                  main
       24039
24040
      PUBLIC int main()
24041
24042 /* This is the main program of the file system. The main loop consists of
      * three major activities: getting new work, processing the work, and sending
24043
       * the reply. This loop never terminates as long as the file system runs.
24044
24045
24046
        sigset_t sigset;
24047
        int error;
24048
24049
        fs_init();
24050
24051
        /* This is the main loop that gets work, processes it, and sends replies. */
24052
        while (TRUE) {
24053
              get work();
                                    /* sets who and call nr */
24054
24055
              fp = &fproc[who];
                                   /* pointer to proc table struct */
              super_user = (fp->fp_effuid == SU_UID ? TRUE : FALSE); /* su? */
24056
24057
24058
              /* Check for special control messages first. */
              if (call nr == SYS SIG) {
24059
24060
                      sigset = m_in.NOTIFY_ARG;
24061
                      if (sigismember(&sigset, SIGKSTOP)) {
24062
                             do_sync();
24063
                             sys_exit(0);
                                                   /* never returns */
24064
24065
              } else if (call_nr == SYN_ALARM) {
24066
                      /* Not a user request; system has expired one of our timers,
                      * currently only in use for select(). Check it.
24067
24068
24069
                      fs_expire_timers(m_in.NOTIFY_TIMESTAMP);
24070
              } else if ((call_nr & NOTIFY_MESSAGE)) {
                      /* Device notifies us of an event. */
24071
                      dev_status(&m_in);
24072
24073
              } else {
24074
                      /* Call the internal function that does the work. */
24075
                      if (call_nr < 0 || call_nr >= NCALLS) {
24076
                             error = ENOSYS;
                             printf("FS, warning illegal %d system call by %d\n", cal
24077
l_nr, who);
24078
                      } else if (fp->fp_pid == PID_FREE) {
24079
                             error = ENOSYS;
24080
                             printf("FS, bad process, who = %d, call_nr = %d, slot1 =
%d\n",
24081
                                     who, call_nr, m_in.slot1);
24082
                      } else {
24083
                             error = (*call_vec[call_nr])();
24084
24085
24086
                      /* Copy the results back to the user and send reply. */
24087
                      if (error != SUSPEND) { reply(who, error); }
24088
                     if (rdahed_inode != NIL_INODE) {
24089
                             read_ahead(); /* do block read ahead */
```

```
Feb 25, 11 15:18
                                   book.txt
                                                                Page 322/393
      File: Page: 959 servers/fs/main.c
24090
24091
24092
24093
                                          /* shouldn't come here */
       return(OK);
24094
24096
      24097
                                  get_work
24098
      *-----*/
24099
      PRIVATE void get_work()
24100
24101
        /* Normally wait for new input. However, if 'reviving' is
        * nonzero, a suspended process must be awakened.
24102
24103
24104
        register struct fproc *rp;
24105
24106
        if (reviving != 0) {
24107
             /* Revive a suspended process. */
24108
             for (rp = &fproc[0]; rp < &fproc[NR_PROCS]; rp++)
                    if (rp->fp_revived == REVIVING) {
24109
24110
                           \overline{who} = (int)(rp - fproc);
24111
                           call_nr = rp->fp_fd & BYTE;
                           m_in.fd = (rp->fp_fd >>8) & BYTE;
24112
                           m_in.buffer = rp->fp_buffer;
24113
24114
                           m_in.nbytes = rp->fp_nbytes;
                           rp->fp_suspended = NOT_SUSPENDED; /*no longer hanging*/
24115
                           rp->fp revived = NOT REVIVING;
24116
24117
                           reviving--;
24118
                           return;
24119
24120
             panic(__fILE__,"get_work couldn't revive anyone", NO_NUM);
24121
24122
24123
        /* Normal case. No one to revive. */
        if (receive(ANY, &m_in) != OK) panic(__FILE__, "fs receive error", NO_NUM);
24124
24125
        who = m_in.m_source;
24126
        call_nr = m_in.m_type;
24127
24129
      24130
                                  buf pool
24131
24132 PRIVATE void buf_pool(void)
24133
      /* Initialize the buffer pool. */
24134
24135
24136
       register struct buf *bp;
24137
24138
       bufs_in_use = 0;
24139
        front = &buf[0];
24140
       rear = &buf[NR_BUFS - 1];
24141
        for (bp = &buf[0]; bp < &buf[NR_BUFS]; bp++) {
24142
             bp->b blocknr = NO BLOCK;
24143
24144
             bp->b_dev = NO_DEV;
24145
             bp->b_next = bp + 1;
             bp \rightarrow b_p = bp - 1;
24146
24147
        buf[0].b_prev = NIL_BUF;
24148
24149
        buf[NR BUFS - 1].b next = NIL BUF;
```

```
book.txt
Feb 25, 11 15:18
                                                                Page 323/393
      File: Page: 960 servers/fs/main.c
24150
24151
        for (bp = &buf[0]; bp < &buf[NR_BUFS]; bp++) bp->b_hash = bp->b_next;
24152
        buf_hash[0] = front;
24153
24154
24156 /*=============*
24157 *
                                 reply
      24159 PUBLIC void reply(whom, result)
                                 /* process to reply to */
24160 int whom;
24161 int result;
                                 /* result of the call (usually OK or error #) */
24162
24163 /* Send a reply to a user process. It may fail (if the process has just
24164 * been killed by a signal), so don't check the return code. If the send
      * fails, just ignore it.
24165
24166
24167
      int s;
24168
       m_out.reply_type = result;
24169
        s = send(whom, &m_out);
24170
       if (s != OK) printf("FS: couldn't send reply %d: %d\n", result, s);
24171
24173 /*=============*
                                fs_init
24174
24175
      *-----*/
24176 PRIVATE void fs init()
24177
      /* Initialize global variables, tables, etc. */
24178
       register struct inode *rip;
24179
24180
       register struct fproc *rfp;
24181
        message mess;
24182
       int s;
24183
24184
        /* Initialize the process table with help of the process manager messages.
24185
         * Expect one message for each system process with its slot number and pid.
24186
         * When no more processes follow, the magic process number NONE is sent.
24187
         * Then, stop and synchronize with the PM.
24188
24189
       do {
             if (OK != (s=receive(PM_PROC_NR, &mess)))
24190
                   panic( FILE , "FS couldn't receive from PM", s);
24191
             if (NONE == mess.PR_PROC_NR) break;
24192
24193
             rfp = &fproc[mess.PR PROC NR];
24194
24195
             rfp->fp_pid = mess.PR_PID;
24196
             rfp->fp_realuid = (uid_t) SYS_UID;
24197
             rfp->fp_effuid = (uid_t) SYS_UID;
             rfp->fp_realgid = (gid_t) SYS_GID;
24198
24199
             rfp->fp_effgid = (gid_t) SYS_GID;
24200
             rfp \rightarrow fp\_umask = \sim 0;
24201
        } while (TRUE);
24202
                                         /* continue until process NONE */
                                         /* tell PM that we succeeded */
24203
        mess.m type = OK;
24204
        s=send(PM_PROC_NR, &mess);
                                         /* send synchronization message */
24205
24206
        /* All process table entries have been set. Continue with FS initialization.
24207
         * Certain relations must hold for the file system to work at all. Some
         * extra block_size requirements are checked at super-block-read-in time.
24208
24209
```

```
Feb 25, 11 15:18
                                  book.txt
                                                               Page 324/393
      File: Page: 961 servers/fs/main.c
24210
       if (OPEN_MAX > 127) panic(__FILE__, "OPEN_MAX > 127", NO_NUM);
24211
       if (NR_BUFS < 6) panic(__FILE__,"NR_BUFS < 6", NO_NUM);</pre>
24212
        if (V1_INODE_SIZE != 32) panic(__FILE__,"V1 inode size != 32", N0_NUM);
24213
        if (V2_INODE_SIZE != 64) panic(__FILE__,"V2 inode size != 64", NO_NUM);
        if (OPEN_MAX > 8 * sizeof(long))
24214
24215
             panic(__FILE__, "Too few bits in fp_cloexec", NO_NUM);
24216
24217
        /* The following initializations are needed to let dev_opcl succeed .*/
24218
        fp = (struct fproc *) NULL;
24219
        who = FS_PROC_NR;
24220
24221
       buf pool();
                                 /* initialize buffer pool */
        build dmap();
                                 /* build device table and map boot driver */
24222
                                 /* init RAM disk, load if it is root */
24223
        load_ram();
        load super(root dev);
                                 /* load super block for root device */
24224
24225
        init select();
                                 /* init select() structures */
24226
24227
        /* The root device can now be accessed; set process directories. */
24228
        for (rfp=&fproc[0]; rfp < &fproc[NR_PROCS]; rfp++) {
            if (rfp->fp_pid != PID_FREE) {
24229
24230
                   rip = get_inode(root_dev, ROOT_INODE);
24231
                    dup_inode(rip);
24232
                   rfp->fp_rootdir = rip;
24233
                   rfp->fp_workdir = rip;
24234
24235
24236 }
24238 /*============*
24239
             igetenv
24240
      24241 PRIVATE int igetenv(key, optional)
24242 char *key;
24243 int optional;
24244
24245 /* Ask kernel for an integer valued boot environment variable. */
24246
       char value[64];
24247
       int i;
24248
24249
       if ((i = env_get_param(key, value, sizeof(value))) != OK) {
24250
           if (!optional)
            printf("FS: Warning, couldn't get monitor param: %d\n", i);
24251
24252
           return 0;
24253
       return(atoi(value));
24254
24255 }
24257 /*===========*
24258
                                load ram
24260 PRIVATE void load_ram(void)
24261
^{\prime\prime} Allocate a RAM disk with size given in the boot parameters. If a RAM disk
24263 * image is given, the copy the entire image device block-by-block to a RAM
24264
      * disk with the same size as the image.
      * If the root device is not set, the RAM disk will be used as root instead.
24265
24266
24267
       register struct buf *bp, *bpl;
24268
       u32_t lcount, ram_size_kb;
24269
       zone t zones;
```

```
Feb 25, 11 15:18
                                      book.txt
                                                                       Page 325/393
      File: Page: 962 servers/fs/main.c
24270
        struct super_block *sp, *dsp;
24271
        block_t b;
24272
        Dev_t image_dev;
24273
         static char sbbuf[MIN BLOCK SIZE];
24274
        int block_size_image, block_size_ram, ramfs_block_size;
24275
24276
24277
         /* Get some boot environment variables. */
        root dev = igetenv("rootdev", 0);
24278
24279
         image_dev = igetenv("ramimagedev", 0);
24280
        ram_size_kb = igetenv("ramsize", 0);
24281
24282
         /* Open the root device. */
        if (dev_open(root_dev, FS_PROC_NR, R_BIT|W_BIT) != OK)
24283
               panic( FILE , "Cannot open root device", NO NUM);
24284
24285
24286
         /* If we must initialize a ram disk, get details from the image device. */
24287
         if (root_dev == DEV_RAM) {
              u32_t fsmax, probedev;
24288
24289
24290
               /* If we are running from CD, see if we can find it. */
24291
               if (igetenv("cdproberoot", 1) && (probedev=cdprobe()) != NO_DEV) {
24292
                      char devnum[10];
24293
                      struct sysgetenv env;
24294
24295
                      /* If so, this is our new RAM image device. */
24296
                      image dev = probedev;
24297
                      /* Tell PM about it, so userland can find out about it
24298
                       * with sysenv interface.
24299
24300
24301
                      env.key = "cdproberoot";
24302
                      env.keylen = strlen(env.key);
                      sprintf(devnum, "%d", (int) probedev);
24303
24304
                      env.val = devnum;
24305
                      env.vallen = strlen(devnum);
24306
                      svrctl(MMSETPARAM, &env);
24307
24308
               /* Open image device for RAM root. */
24309
24310
               if (dev_open(image_dev, FS_PROC_NR, R_BIT) != OK)
24311
                      panic(__FILE__, "Cannot open RAM image device", NO_NUM);
24312
24313
               /* Get size of RAM disk image from the super block. */
24314
               sp = &super block[0];
24315
               sp->s dev = image dev;
24316
               if (read_super(sp) != OK)
24317
                      panic(__FILE__, "Bad RAM disk image FS", NO_NUM);
24318
24319
              24320
               /* Stretch the RAM disk file system to the boot parameters size, but
24321
               * no further than the last zone bit map block allows.
24322
24323
24324
              if (ram_size_kb*1024 < lcount*sp->s_block_size)
24325
                      ram_size_kb = lcount*sp->s_block_size/1024;
               fsmax = (u32 t) sp->s zmap blocks * CHAR BIT * sp->s block size;
24326
               fsmax = (fsmax + (sp->s_firstdatazone-1)) << sp->s_log_zone_size;
24327
24328
               if (ram_size_kb*1024 > fsmax*sp->s_block_size)
24329
                      ram size kb = fsmax*sp->s block size/1024;
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                     Page 326/393
       File: Page: 963 servers/fs/main.c
24330
24331
24332
        /* Tell RAM driver how big the RAM disk must be. */
24333
        m_out.m_type = DEV_IOCTL;
24334
        m_out.PROC_NR = FS_PROC_NR;
24335
        m_out.DEVICE = RAM_DEV;
24336
        m_out.REQUEST = MIOCRAMSIZE;
                                                    /* T/O control to use */
        m_out.POSITION = (ram_size_kb * 1024);
                                                    /* request in bytes */
24337
        if ((s=sendrec(MEM_PROC_NR, &m_out)) != OK)
24338
              panic("FS", "sendrec from MEM failed", s);
24339
24340
        else if (m out.REP STATUS != OK)
24341
              /* Report and continue, unless RAM disk is required as root FS. */
24342
              if (root_dev != DEV_RAM) {
24343
                      report("FS", "can't set RAM disk size", m_out.REP_STATUS);
24344
                      return;
24345
              } else {
24346
                      panic(__FILE__,"can't set RAM disk size", m_out.REP_STATUS);
24347
24348
24349
24350
         /* See if we must load the RAM disk image, otherwise return. */
24351
        if (root_dev != DEV_RAM)
24352
              return;
24353
24354
        /* Copy the blocks one at a time from the image to the RAM disk. */
                                                                0 KB");
24355
        printf("Loading RAM disk onto /dev/ram: \33[23CLoaded:
24356
        24357
        inode[0].i_size = LONG_MAX;
24358
        inode[0].i dev = image dev;
24359
24360
        inode[0].i_zone[0] = image_dev;
24361
24362
        block_size_ram = get_block_size(DEV_RAM);
24363
        block_size_image = get_block_size(image_dev);
24364
24365
        /* RAM block size has to be a multiple of the root image block
24366
         * size to make copying easier.
24367
24368
        if (block size image % block size ram) {
24369
              printf("\nram block size: %d image block size: %d\n",
24370
                      block_size_ram, block_size_image);
              panic(__FILE__, "ram disk block size must be a multiple of "
24371
24372
                      "the image disk block size", NO_NUM);
24373
24374
24375
        /* Loading blocks from image device. */
24376
        for (b = 0; b < (block_t) lcount; b++) {
24377
              int rb, factor;
24378
              bp = rahead(&inode[0], b, (off_t)block_size_image * b, block_size_image)
24379
              factor = block_size_image/block_size_ram;
24380
              for(rb = 0; rb < factor; rb++) {
                     bp1 = get_block(root_dev, b * factor + rb, NO_READ);
24381
                      memcpy(bp1->b_data, bp->b_data + rb * block_size_ram,
24382
24383
                             (size_t) block_size_ram);
24384
                      bp1->b_dirt = DIRTY;
24385
                     put_block(bp1, FULL_DATA_BLOCK);
24386
24387
              put_block(bp, FULL_DATA_BLOCK);
24388
              if (b % 11 == 0)
24389
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 327/393
      File: Page: 964 servers/fs/main.c
24390
24391
24392
        /* Commit changes to RAM so dev_io will see it. */
24393
        do_sync();
24394
24395
        printf("\rRAM disk of %u KB loaded onto /dev/ram.", (unsigned) ram_size_kb);
24396
        if (root_dev == DEV_RAM) printf(" Using RAM disk as root FS.");
24397
        printf(" \n");
24398
24399
        /* Invalidate and close the image device. */
24400
        invalidate(image dev);
24401
        dev close(image dev);
24402
24403
         /* Resize the RAM disk root file system. */
24404
        if (dev_io(DEV_READ, root_dev, FS_PROC_NR,
24405
              sbbuf, SUPER_BLOCK_BYTES, MIN_BLOCK_SIZE, 0) != MIN_BLOCK_SIZE) {
24406
              printf("WARNING: ramdisk read for resizing failed\n");
24407
24408
        dsp = (struct super_block *) sbbuf;
24409
        if (dsp->s_magic == SUPER_V3)
24410
              ramfs_block_size = dsp->s_block_size;
24411
24412
              ramfs_block_size = STATIC_BLOCK_SIZE;
        zones = (ram_size_kb * 1024 / ramfs_block_size) >> sp->s_log_zone_size;
24413
24414
24415
        dsp->s_nzones = conv2(sp->s_native, (u16_t) zones);
24416
        dsp->s_zones = conv4(sp->s_native, zones);
24417
        if (dev_io(DEV_WRITE, root_dev, FS_PROC_NR,
              sbbuf, SUPER_BLOCK_BYTES, MIN_BLOCK_SIZE, 0) != MIN_BLOCK_SIZE) {
24418
24419
              printf("WARNING: ramdisk write for resizing failed\n");
24420
24421 }
24423 /*========*
24424
                                    load_super
24425
      *----*/
24426 PRIVATE void load_super(super_dev)
24427 dev_t super_dev;
                                            /* place to get superblock from */
24428
24429
        int bad;
24430
        register struct super_block *sp;
24431
        register struct inode *rip;
24432
24433
        /* Initialize the super_block table. */
        for (sp = &super block[0]; sp < &super block[NR SUPERS]; sp++)
24434
24435
              sp->s dev = NO DEV;
24436
24437
        /* Read in super_block for the root file system. */
24438
        sp = &super_block[0];
24439
        sp->s_dev = super_dev;
24440
24441
        /* Check super_block for consistency. */
24442
        bad = (read_super(sp) != OK);
        if (!bad)
24443
              rip = get_inode(super_dev, ROOT_INODE); /* inode for root dir */
24444
              if ((rip->i_mode & I_TYPE) != I_DIRECTORY || rip->i_nlinks < 3) bad++;</pre>
24445
24446
24447
        if (bad) panic(__FILE__, "Invalid root file system", NO_NUM);
24448
24449
        sp->s imount = rip;
```

```
Feb 25, 11 15:18
                                 book.txt
                                                            Page 328/393
      File: Page: 965 servers/fs/main.c
24450
       dup inode(rip);
24451
       sp->s_isup = rip;
24452
       sp->s_rd_only = 0;
24453
       return;
24454
servers/fs/open.c
24500 /* This file contains the procedures for creating, opening, closing, and
24501 * seeking on files.
24502
     * The entry points into this file are
24503
     * do_creat: perform the CREAT system call
24504
                    perform the OPEN system call
24505
          do open:
24506
         do_mknod:
                    perform the MKNOD system call
     * do_mkdir:
                   perform the MKDIR system call
24507
24508
      * do_close: perform the CLOSE system call
24509
         do_lseek: perform the LSEEK system call
24510 */
24511
24512 #include "fs.h"
24513 #include <sys/stat.h>
24514 #include <fcntl.h>
24515 #include <minix/callnr.h>
24516 #include <minix/com.h>
24517 #include "buf.h"
24518 #include "file.h'
24519 #include "fproc.h"
24520 #include "inode.h"
24521 #include "lock.h"
24522 #include "param.h"
24523 #include "super.h"
24524
24525 #define offset m2_11
24526
24527 PRIVATE char mode_map[] = {R_BIT, W_BIT, R_BIT|W_BIT, 0};
24528
24529
     FORWARD _PROTOTYPE( int common_open, (int oflags, mode_t omode)
24530
     FORWARD _PROTOTYPE( int pipe_open, (struct inode *rip,mode_t bits,int oflags));
24531 FORWARD _PROTOTYPE( struct inode *new_node, (char *path, mode_t bits,
24532
                                                    zone t. z0)
24533
24534 /*============*
24535
                                do creat
24536
      *-----*/
24537 PUBLIC int do_creat()
24538
24539
     /* Perform the creat(name, mode) system call. */
24540
24541
24542
        if (fetch_name(m_in.name, m_in.name_length, M3) != OK) return(err_code);
       r = common_open(O_WRONLY | O_CREAT | O_TRUNC, (mode_t) m_in.mode);
24543
24544
       return(r);
24545 }
```

```
book.txt
Feb 25, 11 15:18
                                                               Page 329/393
      File: Page: 966 servers/fs/open.c
24547
     24548
                                 do_open
24549
      *-----*
24550
      PUBLIC int do_open()
24551
24552 /* Perform the open(name, flags,...) system call. */
24553
24554
                                /* is really mode_t but this gives problems */
        int create_mode = 0;
24555
       int r;
24556
24557
        /* If O_CREAT is set, open has three parameters, otherwise two. */
24558
        if (m in.mode & O CREAT) {
24559
             create_mode = m_in.c_mode;
24560
             r = fetch_name(m_in.c_name, m_in.namel_length, M1);
24561
24562
             r'= fetch name(m in.name, m in.name length, M3);
24563
24564
24565
        if (r != OK) return(err_code); /* name was bad */
24566
       r = common_open(m_in.mode, create_mode);
24567
24568
24570 /*============*
24571
                                common_open
24572
      24573 PRIVATE int common open(register int oflags, mode t omode)
24574
      /* Common code from do_creat and do_open. */
24575
24576
24577
       register struct inode *rip;
24578
       int r, b, exist = TRUE;
24579
        dev_t dev;
24580
       mode_t bits;
24581
        off_t pos;
24582
        struct filp *fil_ptr, *filp2;
24583
24584
        /* Remap the bottom two bits of oflags. */
24585
        bits = (mode_t) mode_map[oflags & O_ACCMODE];
24586
24587
        /* See if file descriptor and filp slots are available. */
        if ( (r = get fd(0, bits, &m in.fd, &fil ptr)) != OK) return(r);
24588
24589
24590
        /* If O_CREATE is set, try to make the file. */
24591
        if (oflags & O CREAT) {
24592
             /* Create a new inode by calling new node(). */
             omode = I_REGULAR | (omode & ALL_MODES & fp->fp_umask);
24593
             rip = new_node(user_path, omode, NO_ZONE);
24594
24595
             r = err code;
24596
             if (r == OK) exist = FALSE;
                                         /* we just created the file */
             else if (r != EEXIST) return(r); /* other error */
24597
             else exist = !(oflags & O_EXCL); /* file exists, if the O_EXCL
24598
                                            flag is set this is an error */
24599
       } else {
    /* Scan path name. */
24600
24601
24602
             if ( (rip = eat_path(user_path)) == NIL_INODE) return(err_code);
24603
24604
        /* Claim the file descriptor and filp slot and fill them in. */
24605
24606
        fp->fp filp[m in.fd] = fil ptr;
```

```
Feb 25, 11 15:18
                                        book.txt
                                                                          Page 330/393
       File: Page: 967 servers/fs/open.c
24607
         fil ptr->filp count = 1;
24608
         fil_ptr->filp_ino = rip;
24609
         fil_ptr->filp_flags = oflags;
24610
         /* Only do the normal open code if we didn't just create the file. */
24611
24612
         if (exist) {
               /* Check protections. */
24613
24614
               if ((r = forbidden(rip, bits)) == OK) {
                       /* Opening reg. files directories and special files differ. */
24615
24616
                       switch (rip->i_mode & I_TYPE) {
24617
                          case I REGULAR:
24618
                                /* Truncate regular file if O TRUNC. */
                                if (oflags & O_TRUNC)
24619
                                        if ((r = forbidden(rip, W_BIT)) !=OK) break;
24620
24621
                                        truncate(rip);
24622
                                        wipe inode(rip);
24623
                                        /* Send the inode from the inode cache to the
24624
                                         * block cache, so it gets written on the next
24625
                                         * cache flush.
24626
24627
                                        rw_inode(rip, WRITING);
24628
24629
                                break;
24630
24631
                          case I DIRECTORY:
24632
                                /* Directories may be read but not written. */
                               r = (bits & W BIT ? EISDIR : OK);
24633
24634
24635
24636
                          case I CHAR SPECIAL:
24637
                          case I_BLOCK_SPECIAL:
24638
                                /* Invoke the driver for special processing. */
24639
                                dev = (dev_t) rip->i_zone[0];
24640
                               r = dev_open(dev, who, bits | (oflags & ~O_ACCMODE));
24641
                               break;
24642
24643
                          case I NAMED PIPE:
24644
                               oflags = O_APPEND; /* force append mode */
24645
                                fil_ptr->filp_flags = oflags;
24646
                                r = pipe_open(rip, bits, oflags);
24647
                                if (r != ENXIO)
                                        /* See if someone else is doing a rd or wt on
24648
24649
                                         * the FIFO. If so, use its filp entry so the * file position will be automatically shared.
24650
24651
24652
                                        b = (bits & R_BIT ? R_BIT : W_BIT);
                                        fil_ptr->filp_count = 0; /* don't find self */
24653
                                        if ((filp2 = find_filp(rip, b)) != NIL_FILP)
24654
24655
                                                /* Co-reader or writer found. Use it.*/
24656
                                                fp->fp_filp[m_in.fd] = filp2;
24657
                                                filp2->filp_count++;
24658
                                                filp2->filp_ino = rip;
24659
                                                filp2->filp_flags = oflags;
24660
24661
                                                /* i_count was incremented incorrectly
                                                 * by eatpath above, not knowing that
24662
24663
                                                 * we were going to use an existing
24664
                                                 * filp entry. Correct this error.
24665
24666
                                                rip->i count--;
```

```
book.txt
Feb 25, 11 15:18
                                                                    Page 331/393
      File: Page: 968 servers/fs/open.c
24667
                                      else {
24668
                                            /* Nobody else found. Restore filp. */
24669
                                            fil_ptr->filp_count = 1;
24670
                                            if (b == R_BIT)
24671
                                                pos = rip->i_zone[V2_NR_DZONES+0];
24672
24673
                                                 pos = rip->i_zone[V2_NR_DZONES+1];
24674
                                            fil_ptr->filp_pos = pos;
24675
24676
24677
                             break;
24678
24679
24680
24681
24682
        /* If error, release inode. */
24683
        if (r != OK) {
24684
              if (r == SUSPEND) return(r);
                                                   /* Oops, just suspended */
              fp->fp_filp[m_in.fd] = NIL_FILP;
24685
24686
              fil_ptr->filp_count= 0;
24687
              put_inode(rip);
24688
              return(r);
24689
24690
24691
        return(m_in.fd);
24692
24694
      /*----*
24695
                                    new node
24696
       PRIVATE struct inode *new_node(char *path, mode_t bits, zone_t z0)
24697
24698
24699
      /* New_node() is called by common_open(), do_mknod(), and do_mkdir().
       * In all cases it allocates a new inode, makes a directory entry for it on
24700
         the path 'path', and initializes it. It returns a pointer to the inode if
24701
24702
       * it can do this; otherwise it returns NIL_INODE. It always sets 'err_code'
24703
       * to an appropriate value (OK or an error code).
24704
24705
24706
        register struct inode *rlast_dir_ptr, *rip;
24707
        register int r;
24708
        char string[NAME MAX];
24709
24710
        /* See if the path can be opened down to the last directory. */
        if ((rlast_dir_ptr = last_dir(path, string)) == NIL_INODE) return(NIL_INODE);
24711
24712
24713
        /st The final directory is accessible. Get final component of the path. st/
        rip = advance(rlast_dir_ptr, string);
24714
24715
        if ( rip == NIL_INODE && err_code == ENOENT) {
24716
              /* Last path component does not exist. Make new directory entry. */
24717
              if ( (rip = alloc_inode(rlast_dir_ptr->i_dev, bits)) == NIL_INODE) {
                     /* Can't creat new inode: out of inodes. */
24718
24719
                     put_inode(rlast_dir_ptr);
24720
                     return(NIL_INODE);
24721
24722
24723
              /* Force inode to the disk before making directory entry to make
               * the system more robust in the face of a crash: an inode with
24724
               * no directory entry is much better than the opposite.
24725
24726
```

```
Feb 25, 11 15:18
                                   book.txt
                                                                Page 332/393
      File: Page: 969 servers/fs/open.c
24727
             rip->i nlinks++;
24728
             rip->i_zone[0] = z0;
                                          /* major/minor device numbers */
                                         /* force inode to disk now */
24729
             rw_inode(rip, WRITING);
24730
24731
             /* New inode acquired. Try to make directory entry. */
24732
             if ((r = search_dir(rlast_dir_ptr, string, &rip->i_num,ENTER)) != OK) {
                    put_inode(rlast_dir_ptr);
24733
24734
                                         /* pity, have to free disk inode */
                    rip->i_nlinks--;
                                         /* dirty inodes are written out */
24735
                    rip->i dirt = DIRTY;
24736
                    put_inode(rip); /* this call frees the inode */
24737
                    err code = r;
24738
                    return(NIL INODE);
24739
24740
24741
        } else {
24742
             /* Either last component exists, or there is some problem. */
24743
             if (rip != NIL_INODE)
24744
                    r = EEXIST;
24745
             else
24746
                    r = err_code;
24747
24748
24749
        /* Return the directory inode and exit. */
24750
        put inode(rlast dir ptr);
24751
        err_code = r;
24752
        return(rip);
24753
24755
      /*-----
24756
                                pipe open
24757
       24758 PRIVATE int pipe_open(register struct inode *rip, register mode_t bits,
24759
             register int oflags)
24760
      /* This function is called from common_open. It checks if
24761
24762
      * there is at least one reader/writer pair for the pipe, if not
24763
         it suspends the caller, otherwise it revives all other blocked
24764
       * processes hanging on the pipe.
24765
24766
24767
        rip->i_pipe = I_PIPE;
        if (find_filp(rip, bits & W_BIT ? R_BIT : W_BIT) == NIL_FILP) {
24768
             if (oflags & O_NONBLOCK) {
24769
24770
                    if (bits & W_BIT) return(ENXIO);
24771
                    suspend(XPOPEN);
24772
                                         /* suspend caller */
24773
                    return(SUSPEND);
24774
24775
        } else if (susp_count > 0) {/* revive blocked processes */
24776
             release(rip, OPEN, susp_count);
24777
             release(rip, CREAT, susp_count);
24778
24779
        return(OK);
24780
24782
24783
                                  do mknod
24784
       PUBLIC int do_mknod()
24785
24786
```

```
book.txt
Feb 25, 11 15:18
                                                                    Page 333/393
      File: Page: 970 servers/fs/open.c
24787
      /* Perform the mknod(name, mode, addr) system call. */
24788
24789
        register mode_t bits, mode_bits;
24790
        struct inode *ip;
24791
24792
        /* Only the super_user may make nodes other than fifos. */
        mode_bits = (mode_t) m_in.mk_mode; /* mode of the inode */
24793
        if (!super_user && ((mode_bits & I_TYPE) != I_NAMED_PIPE)) return(EPERM);
24794
        if (fetch_name(m_in.name1, m_in.name1_length, M1) != OK) return(err_code);
24795
24796
        bits = (mode_bits & I_TYPE) | (mode_bits & ALL_MODES & fp->fp_umask);
24797
        ip = new_node(user_path, bits, (zone_t) m_in.mk_z0);
24798
        put inode(ip);
24799
        return(err_code);
24800
24802 /*========*
24803 *
                                    do_mkdir
      *======*/
24804
24805 PUBLIC int do_mkdir()
24806
24807
      /* Perform the mkdir(name, mode) system call. */
24808
24809
        int r1, r2;
                                     /* status codes */
                                    /* inode numbers for . and .. */
24810
        ino t dot, dotdot;
24811
        mode_t bits;
                                    /* mode bits for the new inode */
                                    /* last component of the new dir's path name */
        char string[NAME MAX];
24812
        register struct inode *rip, *ldirp;
24813
24814
         /* Check to see if it is possible to make another link in the parent dir. */
24815
        if (fetch_name(m_in.name1, m_in.name1_length, M1) != OK) return(err_code);
24816
        ldirp = last_dir(user_path, string); /* pointer to new dir's parent */
24817
24818
        if (ldirp == NIL_INODE) return(err_code);
24819
        if (ldirp->i_nlinks >= (ldirp->i_sp->s_version == V1 ?
               CHAR_MAX : SHRT_MAX)) {
24820
                                    /* return parent */
24821
              put_inode(ldirp);
24822
              return(EMLINK);
24823
24824
24825
        /* Next make the inode. If that fails, return error code. */
24826
        bits = I_DIRECTORY | (m_in.mode & RWX_MODES & fp->fp_umask);
24827
        rip = new_node(user_path, bits, (zone_t) 0);
        if (rip == NIL_INODE | | err_code == EEXIST)
24828
                                    /* can't make dir: it already exists */
24829
              put inode(rip);
24830
              put_inode(ldirp);
                                    /* return parent too */
24831
              return(err code);
24832
24833
24834
        /* Get the inode numbers for . and .. to enter in the directory. */
24835
        dotdot = ldirp->i_num;  /* parent's inode number */
24836
        dot = rip->i_num;
                                    /* inode number of the new dir itself */
24837
24838
        /* Now make dir entries for . and .. unless the disk is completely full. */
        /* Use dot1 and dot2, so the mode of the directory isn't important. */
24839
        rip->i mode = bits; /* set mode */
24840
24841
        r1 = search_dir(rip, dot1, &dot, ENTER);
                                                   /* enter . in the new dir */
        r2 = search dir(rip, dot2, &dotdot, ENTER); /* enter .. in the new dir */
24842
24843
24844
        /* If both . and .. were successfully entered, increment the link counts. */
24845
        if (r1 == OK && r2 == OK) {
24846
              /* Normal case. It was possible to enter . and .. in the new dir. */
```

```
book.txt
Feb 25, 11 15:18
                                                                   Page 334/393
      File: Page: 971 servers/fs/open.c
24847
             rip->i nlinks++;
                                    /* this accounts for . */
                                    /* this accounts for .. */
24848
              ldirp->i_nlinks++;
24849
             ldirp->i_dirt = DIRTY; /* mark parent's inode as dirty */
24850
        } else {
              24851
24852
              (void) search_dir(ldirp, string, (ino_t *) 0, DELETE);
24853
             rip->i nlinks--;
                                    /* undo the increment done in new_node() */
24854
                                    /* either way, i nlinks has changed */
24855
        rip->i dirt = DIRTY;
24856
24857
        put_inode(ldirp);
                                    /* return the inode of the parent dir */
24858
        put inode(rip);
                                    /* return the inode of the newly made dir */
24859
                                    /* new_node() always sets 'err_code' */
        return(err_code);
24860
24862 /*========*
24863 *
                                    do_close
24864
      24865 PUBLIC int do_close()
24866
24867
      /* Perform the close(fd) system call. */
24868
24869
        register struct filp *rfilp;
        register struct inode *rip;
24870
24871
        struct file_lock *flp;
24872
        int rw, mode_word, lock_count;
24873
        dev t dev;
24874
        /\!\!\!\!\!^{\star} First locate the inode that belongs to the file descriptor. \!\!\!\!^{\star}/\!\!\!\!
24875
24876
        if ( (rfilp = get_filp(m_in.fd)) == NIL_FILP) return(err_code);
                                   /* 'rip' points to the inode */
24877
        rip = rfilp->filp_ino;
24878
24879
        if (rfilp->filp_count - 1 == 0 && rfilp->filp_mode != FILP_CLOSED) {
              /* Check to see if the file is special. */
24880
24881
             mode_word = rip->i_mode & I_TYPE;
24882
              if (mode_word == I_CHAR_SPECIAL | mode_word == I_BLOCK_SPECIAL) {
24883
                     dev = (dev_t) rip->i_zone[0];
24884
                     if (mode_word == I_BLOCK_SPECIAL) {
24885
                            /* Invalidate cache entries unless special is mounted
24886
                             * or ROOT
24887
                            if (!mounted(rip)) {
24888
24889
                                    (void) do_sync();
                                                          /* purge cache */
24890
                                    invalidate(dev);
24891
24892
24893
                     /* Do any special processing on device close. */
24894
                     dev_close(dev);
24895
24896
24897
24898
        /* If the inode being closed is a pipe, release everyone hanging on it. */
24899
        if (rip->i_pipe == I_PIPE) {
             rw = (rfilp->filp_mode & R_BIT ? WRITE : READ);
24900
24901
             release(rip, rw, NR_PROCS);
24902
24903
24904
        /* If a write has been done, the inode is already marked as DIRTY. */
24905
        if (--rfilp->filp_count == 0) {
24906
             if (rip->i pipe == I PIPE && rip->i count > 1) {
```

```
book.txt
Feb 25, 11 15:18
                                                                    Page 335/393
      File: Page: 972 servers/fs/open.c
24907
                     /* Save the file position in the i-node in case needed later.
24908
                      * The read and write positions are saved separately. The
24909
                      * last 3 zones in the i-node are not used for (named) pipes.
24910
24911
                     if (rfilp->filp_mode == R_BIT)
24912
                             rip->i_zone[V2_NR_DZONES+0] = (zone_t) rfilp->filp_pos;
24913
                     else
24914
                             rip->i_zone[V2_NR_DZONES+1] = (zone_t) rfilp->filp_pos;
24915
24916
              put_inode(rip);
24917
24918
        fp->fp_cloexec &= \sim(1L << m_in.fd); /* turn off close-on-exec bit */
24919
24920
        fp->fp_filp[m_in.fd] = NIL_FILP;
24921
24922
        /* Check to see if the file is locked. If so, release all locks. */
24923
        if (nr_locks == 0) return(OK);
24924
        lock_count = nr_locks;
                                  /* save count of locks *,
24925
        for (flp = &file_lock[0]; flp < &file_lock[NR_LOCKS]; flp++) {</pre>
              if (flp->lock_type == 0) continue;  /* slot not in use */
24926
24927
              if (flp->lock_inode == rip && flp->lock_pid == fp->fp_pid) {
24928
                     flp \rightarrow lock_type = 0;
24929
                     nr_locks--;
24930
24931
24932
        if (nr locks < lock count) lock revive(); /* lock released */
24933
        return(OK);
24934 }
24936 /*----*
24937
                                   do lseek
24938
      *----*/
24939 PUBLIC int do_lseek()
24940
      /* Perform the lseek(ls_fd, offset, whence) system call. */
24941
24942
24943
        register struct filp *rfilp;
24944
        register off_t pos;
24945
24946
        /* Check to see if the file descriptor is valid. */
24947
        if ( (rfilp = get_filp(m_in.ls_fd)) == NIL_FILP) return(err_code);
24948
24949
        /* No lseek on pipes. */
24950
        if (rfilp->filp_ino->i_pipe == I_PIPE) return(ESPIPE);
24951
24952
        /* The value of 'whence' determines the start position to use. */
24953
        switch(m_in.whence) {
24954
             case 0: pos = 0;
                                     break;
24955
              case 1: pos = rfilp->filp_pos; break;
24956
              case 2: pos = rfilp->filp_ino->i_size; break;
24957
              default: return(EINVAL);
24958
24959
24960
        /* Check for overflow. */
24961
        if (((long)m_in.offset > 0) && ((long)(pos + m_in.offset) < (long)pos))</pre>
24962
              return(EINVAL);
24963
        if (((long)m in.offset < 0) && ((long)(pos + m in.offset) > (long)pos))
24964
              return(EINVAL);
24965
        pos = pos + m_in.offset;
24966
```

```
book.txt
 Feb 25, 11 15:18
                                                          Page 336/393
      File: Page: 973 servers/fs/open.c
24967
      if (pos != rfilp->filp_pos)
24968
           rfilp->filp_ino->i_seek = ISEEK;
                                            /* inhibit read ahead */
       rfilp->filp_pos = pos;
24969
24970
       m_out.reply_11 = pos;
                               /* insert the long into the output message */
24971
       return(OK);
24972 }
servers/fs/read.c
25000 /* This file contains the heart of the mechanism used to read (and write)
25001 * files. Read and write requests are split up into chunks that do not cross
25002 * block boundaries. Each chunk is then processed in turn. Reads on special
25003
      * files are also detected and handled.
25004 *
25005 * The entry points into this file are
25006
      * do_read: perform the READ system call by calling read_write
      * read_write: actually do the work of READ and WRITE
25007
     * read map: given an inode and file position, look up its zone number
25008
                    read an entry in an indirect block
25009
      * rd_indir:
25010 * read ahead: manage the block read ahead business
25011 */
25012
25013 #include "fs.h"
25014 #include <fcntl.h>
25015 #include <minix/com.h>
25016 #include "buf.h"
25017 #include "file.h'
25018 #include "fproc.h"
25019 #include "inode.h"
25020 #include "param.h"
25021 #include "super.h"
25022
25023 FORWARD _PROTOTYPE( int rw_chunk, (struct inode *rip, off_t position,
25024
            unsigned off, int chunk, unsigned left, int rw_flag,
25025
            char *buff, int seg, int usr, int block_size, int *completed));
25026
25028
                             do_read
25029
25030 PUBLIC int do_read()
25031
25032
       return(read_write(READING));
25033 }
25035
     25036
                              read write
25037 *========*/
25038 PUBLIC int read_write(rw_flag)
25039
     int rw_flag;
                               /* READING or WRITING */
25040
     /* Perform read(fd, buffer, nbytes) or write(fd, buffer, nbytes) call. */
25041
25042
25043
       register struct inode *rip;
25044
       register struct filp *f;
```

```
Feb 25, 11 15:18
                                       book.txt
                                                                         Page 337/393
       File: Page: 974 servers/fs/read.c
25045
         off_t bytes_left, f_size, position;
25046
         unsigned int off, cum_io;
25047
         int op, oflags, r, chunk, usr, seg, block_spec, char_spec;
25048
         int regular, partial_pipe = 0, partial_cnt = 0;
25049
         mode_t mode_word;
25050
         struct filp *wf;
25051
         int block_size;
25052
         int completed, r2 = OK;
25053
         phys bytes p;
25054
25055
         /* left unfinished rw_chunk()s from previous call! this can't happen.
25056
         * it means something has gone wrong we can't repair now.
25057
25058
         if (bufs_in_use < 0)
               panic(__FILE__, "start - bufs_in_use negative", bufs_in_use);
25059
25060
25061
25062
         /* MM loads segments by putting funny things in upper 10 bits of 'fd'. */
         if (who == PM_PROC_NR && (m_in.fd & (~BYTE)) ) {
25063
25064
               usr = m_in.fd >> 7;
25065
               seg = (m_in.fd >> 5) & 03;
25066
               m in.fd &= 037;
                                       /* get rid of user and segment bits */
25067
         } else {
              usr = who;
25068
                                       /* normal case */
25069
               seg = D;
25070
25071
25072
         /* If the file descriptor is valid, get the inode, size and mode. */
25073
         if (m_in.nbytes < 0) return(EINVAL);</pre>
         if ((f = get_filp(m_in.fd)) == NIL_FILP) return(err_code);
25074
25075
         if (((f->filp_mode) & (rw_flag == READING ? R_BIT : W_BIT)) == 0) {
25076
               return(f->filp_mode == FILP_CLOSED ? EIO : EBADF);
25077
25078
         if (m in.nbvtes == 0)
25079
                               /* so char special files need not check for 0*/
                return(0);
25080
25081
         /^{\,\star} check if user process has the memory it needs.
25082
          * if not, copying will fail later.
25083
          * do this after 0-check above because umap doesn't want to map 0 bytes.
25084
25085
         if ((r = sys_umap(usr, seg, (vir_bytes) m_in.buffer, m_in.nbytes, &p)) != OK)
25086
               return r;
25087
         position = f->filp_pos;
25088
         oflags = f->filp_flags;
         rip = f->filp ino;
25089
25090
         f size = rip->i size;
25091
        r = OK;
25092
         if (rip->i_pipe == I_PIPE)
25093
               /* fp->fp_cum_io_partial is only nonzero when doing partial writes */
25094
               cum_io = fp->fp_cum_io_partial;
25095
         } else {
25096
               cum_io = 0;
25097
25098
         op = (rw flag == READING ? DEV READ : DEV WRITE);
25099
         mode_word = rip->i_mode & I_TYPE;
         regular = mode_word == I_REGULAR || mode_word == I_NAMED_PIPE;
25100
25101
25102
         if ((char_spec = (mode_word == I_CHAR_SPECIAL ? 1 : 0))) {
25103
               if (rip->i_zone[0] == NO_DEV)
25104
                       panic( FILE , "read write tries to read from "
```

```
Feb 25, 11 15:18
                                        book.txt
                                                                         Page 338/393
       File: Page: 975 servers/fs/read.c
25105
                                'character device NO DEV", NO NUM);
25106
               block_size = get_block_size(rip->i_zone[0]);
25107
25108
         if ((block_spec = (mode_word == I_BLOCK_SPECIAL ? 1 : 0))) {
               f_size = ULONG_MAX;
25109
25110
               if (rip->i_zone[0] == NO_DEV)
25111
                       panic(__FILE__, "read_write tries to read from "
                        " block device NO_DEV", NO_NUM);
25112
25113
               block size = get block size(rip->i zone[0]);
25114
25115
25116
         if (!char spec && !block spec)
25117
               block_size = rip->i_sp->s_block_size;
25118
25119
                                       /* set to EIO if disk error occurs */
         rdwt err = OK;
25120
25121
         /* Check for character special files. */
25122
         if (char_spec) {
25123
               dev_t dev;
25124
               dev = (dev_t) rip->i_zone[0];
25125
               r = dev_io(op, dev, usr, m_in.buffer, position, m_in.nbytes, oflags);
25126
               if (r >= 0)
25127
                       cum_io = r;
25128
                      position += r;
25129
                       r = OK;
25130
25131
         } else
25132
               if (rw_flag == WRITING && block_spec == 0) {
                       /* Check in advance to see if file will grow too big. */
25133
                       if (position > rip->i_sp->s_max_size - m_in.nbytes)
25134
25135
                               return(EFBIG);
25136
25137
                       /* Check for O_APPEND flag. */
25138
                       if (oflags & O_APPEND) position = f_size;
25139
25140
                       /* Clear the zone containing present EOF if hole about
25141
                        * to be created. This is necessary because all unwritten
25142
                        * blocks prior to the EOF must read as zeros.
25143
25144
                       if (position > f_size) clear_zone(rip, f_size, 0);
25145
25146
               /* Pipes are a little different. Check. */
25147
25148
               if (rip->i_pipe == I_PIPE) {
25149
                     r = pipe_check(rip, rw_flag, oflags,
25150
                               m_in.nbytes, position, &partial_cnt, 0);
25151
                      if (r <= 0) return(r);
25152
25153
25154
               if (partial_cnt > 0) partial_pipe = 1;
25155
25156
               /* Split the transfer into chunks that don't span two blocks. */
25157
               while (m_in.nbytes != 0) {
25158
25159
                       off = (unsigned int) (position % block_size);/* offset in blk*/
                       if (partial_pipe) { /* pipes only */
25160
                               chunk = MIN(partial cnt, block size - off);
25161
25162
25163
                               chunk = MIN(m_in.nbytes, block_size - off);
25164
                       if (chunk < 0) chunk = block size - off;
```

```
book.txt
Feb 25, 11 15:18
                                                                         Page 339/393
       File: Page: 976 servers/fs/read.c
25165
25166
                       if (rw_flag == READING) {
25167
                               bytes_left = f_size - position;
25168
                               if (position >= f_size) break; /* we are beyond EOF */
25169
                               if (chunk > bytes_left) chunk = (int) bytes_left;
25170
25171
25172
                       /* Read or write 'chunk' bytes. */
                       r = rw_chunk(rip, position, off, chunk, (unsigned) m_in.nbytes,
25173
25174
                                    rw_flag, m_in.buffer, seg, usr, block_size, &comple
ted);
25175
25176
                       if (r != OK) break;
                                              /* EOF reached */
                       if (rdwt_err < 0) break;
25177
25178
25179
                       /* Update counters and pointers. */
25180
                       m_in.buffer += chunk; /* user buffer address */
25181
                       m_in.nbytes -= chunk; /* bytes yet to be read */
25182
                       cum_io += chunk;
                                               /* bytes read so far */
                                               /* position within the file */
25183
                       position += chunk;
25184
25185
                       if (partial_pipe) {
                               partial_cnt -= chunk;
25186
25187
                               if (partial cnt <= 0) break;
25188
25189
25190
25191
         /* On write, update file size and access time. */
25192
         if (rw flag == WRITING) {
25193
25194
               if (regular | | mode_word == I_DIRECTORY) {
25195
                       if (position > f_size) rip->i_size = position;
25196
25197
         } else
               if (rip->i_pipe == I_PIPE) {
25198
25199
                       if ( position >= rip->i_size) {
25200
                               /* Reset pipe pointers. */
25201
                                                      /* no data left */
                               rip->i_size = 0;
25202
                               position = 0;
                                                       /* reset reader(s) */
                               wf = find_filp(rip, W_BIT);
25203
                               if (wf != NIL FILP) wf->filp pos = 0;
25204
25205
25206
25207
         f->filp pos = position;
25208
25209
25210
         /* Check to see if read-ahead is called for, and if so, set it up. */
25211
         if (rw_flag == READING && rip->i_seek == NO_SEEK && position % block_size== 0
25212
                       && (regular | mode_word == I_DIRECTORY)) {
25213
               rdahed_inode = rip;
25214
               rdahedpos = position;
25215
         rip->i_seek = NO_SEEK;
25216
25217
25218
         if (rdwt_err != OK) r = rdwt_err;
                                               /* check for disk error */
25219
         if (rdwt err == END OF FILE) r = OK;
25220
25221
         /* if user-space copying failed, read/write failed. */
         if (r == OK && r2 != OK) {
25222
25223
               r = r2i
25224
```

```
Feb 25, 11 15:18
                                      book.txt
                                                                      Page 340/393
      File: Page: 977 servers/fs/read.c
25225
        if (r == OK)
25226
              if (rw_flag == READING) rip->i_update |= ATIME;
25227
              if (rw_flag == WRITING) rip->i_update |= CTIME | MTIME;
25228
              rip->i dirt = DIRTY;
                                             /* inode is thus now dirty */
25229
              if (partial_pipe) {
25230
                     partial_pipe = 0;
25231
                             /* partial write on pipe with */
                      /* O_NONBLOCK, return write count */
25232
                      if (!(oflags & O NONBLOCK))
25233
25234
                              fp->fp_cum_io_partial = cum_io;
                             suspend(XPIPE);  /* partial write on pipe with */
return(SUSPEND);  /* nbyte > PIPE_SIZE - non-atomic */
25235
25236
25237
25238
25239
              fp->fp cum io partial = 0;
25240
              return(cum io);
25241
25242
        if (bufs_in_use < 0) {
25243
              panic(__FILE__, "end - bufs_in_use negative", bufs_in_use);
25244
25245
        return(r);
25246
25248
      /*========*
25249
                                    rw_chunk
       *-----
25250
25251 PRIVATE int rw_chunk(rip, position, off, chunk, left, rw_flag, buff,
       seg, usr, block_size, completed)
25252
                                     /* pointer to inode for file to be rd/wr */
25253 register struct inode *rip;
25254 off t position;
                                     /* position within file to read or write */
25255 unsigned off;
                                     /* off within the current block */
25256 int chunk;
                                     /* number of bytes to read or write */
25257 unsigned left;
                                     /* max number of bytes wanted after position */
25258 int rw_flag;
                                     /* READING or WRITING */
25259
                                     /* virtual address of the user buffer */
      char *buff;
25260 int seq;
                                     /* T or D segment in user space */
25261 int usr;
                                     /* which user process */
25262
                                     /* block size of FS operating on */
      int block size;
25263 int *completed;
                                     /* number of bytes copied */
25264
      /* Read or write (part of) a block. */
25265
25266
25267
        register struct buf *bp;
25268
        register int r = OK;
25269
        int n, block spec;
25270
        block_t b;
25271
        dev_t dev;
25272
25273
        *completed = 0;
25274
25275
        block_spec = (rip->i_mode & I_TYPE) == I_BLOCK_SPECIAL;
        if (block_spec)
25276
25277
              b = position/block_size;
25278
              dev = (dev_t) rip->i_zone[0];
25279
        } else {
25280
              b = read_map(rip, position);
25281
              dev = rip->i dev;
25282
25283
25284
        if (!block spec && b == NO BLOCK) {
```

```
book.txt
Feb 25, 11 15:18
                                                                   Page 341/393
      File: Page: 978 servers/fs/read.c
25285
             if (rw flag == READING)
25286
                     /* Reading from a nonexistent block. Must read as all zeros.*/
                     25287
25288
                     zero_block(bp);
              } else {
25289
25290
                      /* Writing to a nonexistent block. Create and enter in inode.*/
                     if ((bp= new_block(rip, position)) == NIL_BUF)return(err code);
25291
25292
        } else if (rw_flag == READING) {
25293
              /* Read and read ahead if convenient. */
25294
25295
              bp = rahead(rip, b, position, left);
25296
             /* Normally an existing block to be partially overwritten is first read * in. However, a full block need not be read in. If it is already in
25297
25298
              * the cache, acquire it, otherwise just acquire a free buffer.
25299
25300
25301
              n = (chunk == block_size ? NO_READ : NORMAL);
25302
              if (!block_spec && off == 0 && position >= rip->i_size) n = NO_READ;
25303
              bp = get_block(dev, b, n);
25304
25305
25306
        /* In all cases, bp now points to a valid buffer. */
25307
        if (bp == NIL_BUF) {
25308
              panic( FILE , "bp not valid in rw chunk, this can't happen", NO NUM);
25309
25310
        if (rw_flag == WRITING && chunk != block_size && !block_spec &&
25311
                                           position >= rip->i size && off == 0) {
25312
              zero_block(bp);
25313
25314
25315
        if (rw flag == READING) {
25316
              /* Copy a chunk from the block buffer to user space. */
25317
              r = sys_vircopy(FS_PROC_NR, D, (phys_bytes) (bp->b_data+off),
                            usr, seg, (phys_bytes) buff,
25318
25319
                            (phys_bytes) chunk);
25320
25321
              /* Copy a chunk from user space to the block buffer. */
25322
              r = sys_vircopy(usr, seg, (phys_bytes) buff,
                            FS_PROC_NR, D, (phys_bytes) (bp->b_data+off),
25323
                             (phys_bytes) chunk);
25324
25325
             bp->b dirt = DIRTY;
25326
        n = (off + chunk == block_size ? FULL_DATA_BLOCK : PARTIAL_DATA_BLOCK);
25327
25328
        put_block(bp, n);
25329
25330
        return(r);
25331 }
25335 *
                                   read_map
25337 PUBLIC block_t read_map(rip, position)
25338 register struct inode *rip; /* ptr to inode to map from */
25339 off t position;
                                    /* position in file whose blk wanted */
25340
25341 /* Given an inode and a position within the corresponding file, locate the
      * block (not zone) number in which that position is to be found and return it.
25342
25343
25344
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 342/393
      File: Page: 979 servers/fs/read.c
25345
        register struct buf *bp;
25346
        register zone_t z;
25347
        int scale, boff, dzones, nr_indirects, index, zind, ex;
25348
        block t b;
25349
        long excess, zone, block_pos;
25350
        scale = rip->i_sp->s_log_zone_size;  /* for block-zone conversion */
25351
        block_pos = position/rip->i_sp->s_block_size; /* relative blk # in file */
25352
        zone = block pos >> scale;  /* position's zone */
25353
25354
        boff = (int) (block_pos - (zone << scale) ); /* relative blk # within zone */
25355
        dzones = rip->i ndzones;
25356
        nr indirects = rip->i nindirs;
25357
        /* Is 'position' to be found in the inode itself? */
25358
25359
        if (zone < dzones) {
25360
              zind = (int) zone;
                                    /* index should be an int */
25361
              z = rip->i_zone[zind];
              if (z == NO_ZONE) return(NO_BLOCK);
25362
25363
              b = ((block_t) z << scale) + boff;
25364
              return(b);
25365
25366
25367
        /* It is not in the inode, so it must be single or double indirect. */
                                    /* first Vx NR DZONES don't count */
25368
        excess = zone - dzones;
25369
25370
        if (excess < nr indirects) {
25371
              /* 'position' can be located via the single indirect block. */
25372
              z = rip->i_zone[dzones];
25373
              ^{1}/^{*} 'position' can be located via the double indirect block. */
25374
25375
              if ( (z = rip->i_zone[dzones+1]) == NO_ZONE) return(NO_BLOCK);
25376
              excess -= nr_indirects;
                                                    /* single indir doesn't count*/
25377
              b = (block_t) z << scale;
25378
              bp = get_block(rip->i_dev, b, NORMAL); /* get double indirect block */
25379
              index = (int) (excess/nr_indirects);
              z = rd_indir(bp, index);
25380
                                                    /* z= zone for single*/
25381
              put_block(bp, INDIRECT_BLOCK);
                                                    /* release double ind block */
25382
              excess = excess % nr_indirects;
                                                    /* index into single ind blk */
25383
25384
        /* 'z' is zone num for single indirect block; 'excess' is index into it. */
25385
        if (z == NO ZONE) return(NO BLOCK);
25386
        b = (block_t) z << scale;
25387
                                                    /* b is blk # for single ind */
25388
        bp = get_block(rip->i_dev, b, NORMAL);
                                                    /* get single indirect block */
25389
        ex = (int) excess;
                                                    /* need an integer */
25390
        z = rd_indir(bp, ex);
                                                    /* get block pointed to */
25391
        put_block(bp, INDIRECT_BLOCK);
                                                    /* release single indir blk */
25392
        if (z == NO_ZONE) return(NO_BLOCK);
25393
        b = ((block_t) z << scale) + boff;
25394
        return(b);
25395 }
25397 /*============*
25398
                                    rd indir
25399
       25400 PUBLIC zone_t rd_indir(bp, index)
25401 struct buf *bp;
                                    /* pointer to indirect block */
                                    /* index into *bp */
25402 int index;
25403
\frac{1}{2}5404 /* Given a pointer to an indirect block, read one entry. The reason for
```

```
book.txt
Feb 25, 11 15:18
                                                               Page 343/393
      File: Page: 980 servers/fs/read.c
       * making a separate routine out of this is that there are four cases:
25405
25406
       * V1 (IBM and 68000), and V2 (IBM and 68000).
25407
25408
25409
        struct super_block *sp;
25410
        zone t zone;
                                  /* V2 zones are longs (shorts in V1) */
25411
25412
        sp = get_super(bp->b_dev);  /* need super block to find file sys type */
25413
25414
        /* read a zone from an indirect block */
25415
        if (sp->s version == V1)
25416
             zone = (zone t) conv2(sp->s native, (int) bp->b v1 ind[index]);
25417
25418
             zone = (zone_t) conv4(sp->s_native, (long) bp->b_v2_ind[index]);
25419
25420
       if (zone != NO ZONE &&
25421
                    (zone < (zone_t) sp->s_firstdatazone || zone >= sp->s_zones)) {
25422
             printf("Illegal zone number %ld in indirect block, index %d\n",
25423
                   (long) zone, index);
25424
             panic(__FILE__, "check file system", NO_NUM);
25425
25426
       return(zone);
25427
25429
     25430
                                read ahead
25431
      *=======*/
25432 PUBLIC void read_ahead()
25433
25434 /* Read a block into the cache before it is needed. */
25435
       int block size;
25436
       register struct inode *rip;
25437
        struct buf *bp;
25438
       block_t b;
25439
25440
        rip = rdahed_inode;
                                  /* pointer to inode to read ahead from */
25441
        block_size = get_block_size(rip->i_dev);
25442
       rdahed_inode = NIL_INODE; /* turn off read ahead */
25443
        if ( (b = read_map(rip, rdahedpos)) == NO_BLOCK) return;
                                                              /* at EOF */
25444
        bp = rahead(rip, b, rdahedpos, block_size);
25445
       put_block(bp, PARTIAL_DATA_BLOCK);
25446
25448 /*==============*
25449 *
                                rahead
25450 *==========*/
25451 PUBLIC struct buf *rahead(rip, baseblock, position, bytes_ahead)
25452 register struct inode *rip; /* pointer to inode for file to be read */
25453 block_t baseblock;
                                 /* block at current position */
25454 off_t position;
                                  /* position within file */
25455 unsigned bytes_ahead;
                                /* bytes beyond position for immediate use */
25456
25457 /* Fetch a block from the cache or the device. If a physical read is
25458 * required, prefetch as many more blocks as convenient into the cache.
25459
      * This usually covers bytes_ahead and is at least BLOCKS_MINIMUM.
25460
       * The device driver may decide it knows better and stop reading at a
       * cylinder boundary (or after an error). Rw_scattered() puts an optional
       * flag on all reads to allow this.
25462
25463
25464
       int block size;
```

```
Feb 25, 11 15:18
                                       book.txt
                                                                        Page 344/393
       File: Page: 981 servers/fs/read.c
      /* Minimum number of blocks to prefetch. */
25466 # define BLOCKS_MINIMUM
                                      (NR_BUFS < 50 ? 18 : 32)
25467
        int block_spec, scale, read_q_size;
25468
         unsigned int blocks_ahead, fragment;
25469
         block_t block, blocks_left;
25470
         off_t ind1_pos;
        dev_t dev;
25471
         struct buf *bp;
25472
25473
         static struct buf *read g[NR BUFS];
25474
25475
         block_spec = (rip->i_mode & I_TYPE) == I_BLOCK_SPECIAL;
25476
         if (block spec) {
25477
              dev = (dev_t) rip->i_zone[0];
25478
         } else {
25479
              dev = rip->i dev;
25480
25481
         block_size = get_block_size(dev);
25482
25483
         block = baseblock;
         bp = get_block(dev, block, PREFETCH);
25484
25485
         if (bp->b_dev != NO_DEV) return(bp);
25486
25487
         /* The best guess for the number of blocks to prefetch: A lot.
         * It is impossible to tell what the device looks like, so we don't even
25488
25489
          * try to guess the geometry, but leave it to the driver.
25490
25491
         * The floppy driver can read a full track with no rotational delay, and it
25492
          * avoids reading partial tracks if it can, so handing it enough buffers to
          * read two tracks is perfect. (Two, because some diskette types have
25493
25494
          * an odd number of sectors per track, so a block may span tracks.)
25495
25496
          * The disk drivers don't try to be smart. With todays disks it is
25497
          * impossible to tell what the real geometry looks like, so it is best to
25498
          * read as much as you can. With luck the caching on the drive allows
          * for a little time to start the next read.
25499
25500
          * The current solution below is a bit of a hack, it just reads blocks from
25501
25502
          * the current file position hoping that more of the file can be found. A
          * better solution must look at the already available zone pointers and
25503
25504
          * indirect blocks (but don't call read_map!).
25505
25506
         fragment = position % block size;
25507
25508
         position -= fragment;
25509
         bytes ahead += fragment;
25510
25511
         blocks_ahead = (bytes_ahead + block_size - 1) / block_size;
25512
25513
         if (block spec && rip->i size == 0) {
25514
              blocks_left = NR_IOREQS;
25515
25516
              blocks_left = (rip->i_size - position + block_size - 1) / block_size;
25517
25518
               /* Go for the first indirect block if we are in its neighborhood. */
25519
              if (!block_spec) {
25520
                       scale = rip->i_sp->s_log_zone_size;
                       indl_pos = (off_t) rip->i_ndzones * (block_size << scale);</pre>
25521
                       if (position <= indl_pos && rip->i_size > indl_pos) {
25522
25523
                               blocks_ahead++;
25524
                               blocks left++;
```

```
Page 345/393
Feb 25, 11 15:18
                                   book.txt
      File: Page: 982 servers/fs/read.c
25525
25526
25527
25528
25529
        /* No more than the maximum request. */
25530
        if (blocks_ahead > NR_IOREQS) blocks_ahead = NR_IOREQS;
25531
25532
        /* Read at least the minimum number of blocks, but not after a seek. */
        if (blocks_ahead < BLOCKS_MINIMUM && rip->i_seek == NO_SEEK)
25533
25534
             blocks_ahead = BLOCKS_MINIMUM;
25535
25536
        /* Can't go past end of file. */
25537
        if (blocks_ahead > blocks_left) blocks_ahead = blocks_left;
25538
25539
        read q size = 0;
25540
25541
        /* Acquire block buffers. */
25542
        for (;;) {
25543
             read_q[read_q_size++] = bp;
25544
25545
             if (--blocks_ahead == 0) break;
25546
25547
              /* Don't trash the cache, leave 4 free. */
25548
             if (bufs in use >= NR BUFS - 4) break;
25549
25550
             block++;
25551
25552
             bp = get_block(dev, block, PREFETCH);
25553
             if (bp->b_dev != NO_DEV) {
25554
                     /* Oops, block already in the cache, get out. */
25555
                     put_block(bp, FULL_DATA_BLOCK);
25556
                     break;
25557
25558
        rw_scattered(dev, read_q, read_q_size, READING);
25559
25560
        return(get_block(dev, baseblock, NORMAL));
25561 }
servers/fs/write.c
25600 /* This file is the counterpart of "read.c". It contains the code for writing
25601 * insofar as this is not contained in read_write().
25602 *
25603 * The entry points into this file are
25604
      * do_write: call read_write to perform the WRITE system call
25605 * clear_zone: erase a zone in the middle of a file
25606
       * new_block: acquire a new block
25607 */
25608
25609 #include "fs.h"
25610 #include <string.h>
25611 #include "buf.h"
25612 #include "file.h"
25613 #include "fproc.h"
25614 #include "inode.h"
```

```
Feb 25, 11 15:18
                                 book.txt
                                                            Page 346/393
      File: Page: 983 servers/fs/write.c
25615 #include "super.h"
25616
25617 FORWARD _PROTOTYPE( int write_map, (struct inode *rip, off_t position,
25618
                         zone_t new_zone)
25619
25620 FORWARD _PROTOTYPE( void wr_indir, (struct buf *bp, int index, zone_t zone) );
25621
25622 /*===========*
25623 *
            do_write
25624
      25625 PUBLIC int do write()
25626
25627 /* Perform the write(fd, buffer, nbytes) system call. */
25628
       return(read write(WRITING));
25629
25630 }
25633 *
                              write_map
25634 *============*/
25635 PRIVATE int write_map(rip, position, new_zone)
25636 register struct inode *rip; /* pointer to inode to be changed */
25637 off_t position; /* file address to be mapped */
25637 off_t position;
25638 zone t new zone;
                               /* zone # to be inserted */
25639
25640 /* Write a new zone into an inode. */
     int scale, ind_ex, new_ind, new_dbl, zones, nr_indirects, single, zindex, ex;
25641
25642
       zone t z, z1;
25643
       register block_t b;
25644
      long excess, zone;
25645
      struct buf *bp;
25646
25647
       rip->i_dirt = DIRTY;
                               /* inode will be changed */
25648
      bp = NIL_BUF;
25649
       scale = rip->i_sp->s_log_zone_size;
                                            /* for zone-block conversion */
25650
       /* relative zone # to insert */
25651
       zone = (position/rip->i_sp->s_block_size) >> scale;
25652
       25653
       nr indirects = rip->i nindirs;/* # indirect zones per indirect block */
25654
25655
       /* Is 'position' to be found in the inode itself? */
25656
       if (zone < zones) {
25657
            zindex = (int) zone; /* we need an integer here */
25658
            rip->i_zone[zindex] = new_zone;
25659
            return(OK);
25660
25661
25662
       /* It is not in the inode, so it must be single or double indirect. */
25663
       excess = zone - zones; /* first Vx_NR_DZONES don't count */
25664
       new ind = FALSE;
25665
       new_dbl = FALSE;
25666
25667
       if (excess < nr_indirects) {
            /* 'position' can be located via the single indirect block. */
25668
            z1 = rip->i_zone[zones];  /* single indirect zone */
25669
            single = TRUE;
25670
25671
       } else {
            /* 'position' can be located via the double indirect block. */
25672
            if ( (z = rip->i_zone[zones+1]) == NO_ZONE) {
25673
25674
                  /* Create the double indirect block. */
```

```
book.txt
Feb 25, 11 15:18
                                                                   Page 347/393
      File: Page: 984 servers/fs/write.c
                     if ( (z = alloc_zone(rip->i_dev, rip->i_zone[0])) == NO_ZONE)
25675
25676
                           return(err_code);
                     rip->i_zone[zones+1] = z;
25677
25678
                     new dbl = TRUE; /* set flag for later */
25679
25680
25681
              /* Either way, 'z' is zone number for double indirect block. */
              excess -= nr_indirects; /* single indirect doesn't count */
25682
              ind ex = (int) (excess / nr indirects);
25683
25684
              excess = excess % nr_indirects;
25685
              if (ind ex >= nr indirects) return(EFBIG);
25686
              b = (block t) z << scale;
              bp = get_block(rip->i_dev, b, (new_dbl ? NO_READ : NORMAL));
25687
              if (new_dbl) zero_block(bp);
25688
25689
              z1 = rd indir(bp, ind ex);
25690
              single = FALSE;
25691
25692
25693
        /* z1 is now single indirect zone; 'excess' is index. */
        if (z1 == NO_ZONE) {
25694
25695
             /* Create indirect block and store zone # in inode or dbl indir blk. */
25696
              z1 = alloc_zone(rip->i_dev, rip->i_zone[0]);
25697
             if (single)
25698
                     rip->i zone[zones] = z1;
                                                  /* update inode */
25699
              else
                     wr indir(bp, ind ex, z1);
                                                /* update dbl indir */
25700
25701
25702
             new_ind = TRUE;
              if (bp != NIL_BUF) bp->b_dirt = DIRTY; /* if double ind, it is dirty*/
25703
              if (z1 == NO ZONE) {
25704
25705
                     put block(bp, INDIRECT BLOCK); /* release dbl indirect blk */
25706
                     return(err_code); /* couldn't create single ind */
25707
25708
25709
        put_block(bp, INDIRECT_BLOCK);
                                         /* release double indirect blk */
25710
25711
        /* zl is indirect block's zone number. */
25712
        b = (block_t) z1 << scale;
25713
        bp = get_block(rip->i_dev, b, (new_ind ? NO_READ : NORMAL) );
25714
        if (new_ind) zero_block(bp);
25715
        ex = (int) excess;
                                           /* we need an int here */
25716
        wr_indir(bp, ex, new_zone);
25717
        bp->b_dirt = DIRTY;
25718
        put_block(bp, INDIRECT_BLOCK);
25719
25720
        return(OK);
25721 }
25723 /*===========*
25724 *
                                 wr_indir
25725 *==========*/
25726 PRIVATE void wr_indir(bp, index, zone)
25727 struct buf *bp;
                                 /* pointer to indirect block */
                                   /* index into *bp */
25728 int index;
25729 zone_t zone;
                                   /* zone to write */
25730
      /* Given a pointer to an indirect block, write one entry. */
25731
25732
25733
        struct super_block *sp;
25734
```

```
Feb 25, 11 15:18
                                  book.txt
                                                               Page 348/393
      File: Page: 985 servers/fs/write.c
25735
       sp = get super(bp->b dev);
                                /* need super block to find file sys type */
25736
25737
        /* write a zone into an indirect block */
25738
        if (sp->s version == V1)
25739
             bp->b_v1_ind[index] = (zone1_t) conv2(sp->s_native, (int) zone);
25740
25741
            bp->b_v2_ind[index] = (zone_t) conv4(sp->s_native, (long) zone);
25742 }
25744 /*============*
25745
                                 clear zone
25746
      25747 PUBLIC void clear_zone(rip, pos, flag)
25748 register struct inode *rip; /* inode to clear */
25749 off_t pos;
                                 /* points to block to clear */
25750 int flag;
                                 /* 0 if called by read_write, 1 by new_block */
25751
25752 /* Zero a zone, possibly starting in the middle. The parameter 'pos' gives
      * a byte in the first block to be zeroed. Clearzone() is called from
25753
      * read_write and new_block().
25754
25755
25756
25757
       register struct buf *bp;
25758
       register block t b, blo, bhi;
25759
        register off t next;
25760
       register int scale;
25761
       register zone t zone size;
25762
25763
        /* If the block size and zone size are the same, clear_zone() not needed. */
25764
        scale = rip->i sp->s log zone size;
25765
        if (scale == 0) return;
25766
25767
        zone_size = (zone_t) rip->i_sp->s_block_size << scale;</pre>
25768
        if (flag == 1) pos = (pos/zone_size) * zone_size;
25769
       next = pos + rip->i_sp->s_block_size - 1;
25770
25771
        /* If 'pos' is in the last block of a zone, do not clear the zone. */
25772
        if (next/zone_size != pos/zone_size) return;
       if ((blo = read_map(rip, next)) == NO_BLOCK) return;
25773
25774
       bhi = ( ((blo>>scale)+1) << scale) - 1;
25775
25776
        /* Clear all the blocks between 'blo' and 'bhi'. */
25777
       for (b = blo; b <= bhi; b++) {
25778
             bp = get_block(rip->i_dev, b, NO_READ);
25779
             zero block(bp);
25780
             put_block(bp, FULL_DATA_BLOCK);
25781
25782 }
25784 /*==========*
25785 *
                              new_block
25786
      25787 PUBLIC struct buf *new_block(rip, position)
25788 register struct inode *rip; /* pointer to inode */
                                 /* file pointer */
25789 off_t position;
25790
25791 /* Acquire a new block and return a pointer to it. Doing so may require
25792
      * allocating a complete zone, and then returning the initial block.
      * On the other hand, the current zone may still have some unused blocks.
25793
25794
```

```
book.txt
Feb 25, 11 15:18
                                                                      Page 349/393
       File: Page: 986 servers/fs/write.c
25795
25796
         register struct buf *bp;
25797
         block_t b, base_block;
25798
         zone t z;
25799
         zone_t zone_size;
25800
         int scale, r;
25801
         struct super_block *sp;
25802
25803
          * Is another block available in the current zone? */
25804
         if ( (b = read_map(rip, position)) == NO_BLOCK) {
25805
               /* Choose first zone if possible. */
25806
               /* Lose if the file is nonempty but the first zone number is NO ZONE
25807
                * corresponding to a zone full of zeros. It would be better to
                * search near the last real zone.
25808
25809
25810
              if (rip->i zone[0] == NO ZONE) {
25811
                      sp = rip -> i_sp;
25812
                      z = sp->s_firstdatazone;
25813
               } else {
25814
                      z = rip->i_zone[0]; /* hunt near first zone */
25815
25816
              if ( (z = alloc_zone(rip->i_dev, z)) == NO_ZONE) return(NIL_BUF);
25817
              if ( (r = write_map(rip, position, z)) != OK) {
                      free_zone(rip->i_dev, z);
25818
25819
                      err_code = r;
25820
                      return(NIL BUF);
25821
25822
25823
               /* If we are not writing at EOF, clear the zone, just to be safe. */
               if ( position != rip->i size) clear zone(rip, position, 1);
25824
               scale = rip->i_sp->s_log_zone_size;
25825
25826
              base_block = (block_t) z << scale;</pre>
25827
              zone_size = (zone_t) rip->i_sp->s_block_size << scale;</pre>
25828
              b = base_block + (block_t)((position % zone_size)/rip->i_sp->s_block_siz
e);
25829
25830
25831
         bp = get_block(rip->i_dev, b, NO_READ);
25832
         zero block(bp);
25833
         return(bp);
25834
25836
      25837
                                     zero_block
25838
25839 PUBLIC void zero_block(bp)
25840
      register struct buf *bp;
                                     /* pointer to buffer to zero */
25841
25842 /* Zero a block. */
25843
        memset(bp->b_data, 0, MAX_BLOCK_SIZE);
25844
         bp->b_dirt = DIRTY;
25845
```

```
book.txt
 Feb 25, 11 15:18
                                                               Page 350/393
      File: Page: 987 servers/fs/pipe.c
servers/fs/pipe.c
25900 /* This file deals with the suspension and revival of processes. A process can
25901
      * be suspended because it wants to read or write from a pipe and can't, or
      * because it wants to read or write from a special file and can't. When a
25902
       * process can't continue it is suspended, and revived later when it is able
25904
       * to continue.
25905
25906
       * The entry points into this file are
                      perform the PIPE system call
25907
          do_pipe:
                      check to see that a read or write on a pipe is feasible now
25908
          pipe_check:
25909
                      suspend a process that cannot do a requested read or write
          suspend:
25910
          release:
                      check to see if a suspended process can be released and do
25911
25912
                      mark a suspended process as able to run again
25913
          do_unpause:
                      a signal has been sent to a process; see if it suspended
25914
25915
25916
      #include "fs.h"
25917 #include <fcntl.h>
25918 #include <signal.h>
25919 #include <minix/callnr.h>
25920 #include <minix/com.h>
25921 #include <sys/select.h>
25922 #include <sys/time.h>
25923 #include "file.h"
25924 #include "fproc.h"
25925 #include "inode.h"
25926 #include "param.h"
25927 #include "super.h"
25928
      #include "select.h"
25929
25930
      25931
                                  do pipe
25932
      *==========*/
25933 PUBLIC int do pipe()
25934
      /* Perform the pipe(fil_des) system call. */
25935
25936
25937
        register struct fproc *rfp;
25938
        register struct inode *rip;
25939
        int r;
25940
        struct filp *fil_ptr0, *fil_ptr1;
25941
        int fil_des[2];
                                  /* reply goes here */
25942
25943
        /* Acquire two file descriptors. */
25944
        rfp = fp;
25945
        if ( (r = get_fd(0, R_BIT, &fil_des[0], &fil_ptr0)) != OK) return(r);
25946
        rfp->fp_filp[fil_des[0]] = fil_ptr0;
25947
        fil_ptr0->filp_count = 1;
25948
        if ( (r = get_fd(0, W_BIT, &fil_des[1], &fil_ptr1)) != OK) {
25949
             rfp->fp_filp[fil_des[0]] = NIL_FILP;
25950
             fil_ptr0->filp_count = 0;
25951
             return(r);
25952
        rfp->fp_filp[fil_des[1]] = fil_ptr1;
25953
25954
        fil ptr1->filp count = 1;
```

```
book.txt
Feb 25, 11 15:18
                                                                    Page 351/393
      File: Page: 988 servers/fs/pipe.c
25955
25956
         /* Make the inode on the pipe device. */
25957
        if ( (rip = alloc_inode(root_dev, I_REGULAR) ) == NIL_INODE) {
25958
              rfp->fp_filp[fil_des[0]] = NIL_FILP;
25959
              fil_ptr0->filp_count = 0;
25960
              rfp->fp_filp[fil_des[1]] = NIL_FILP;
25961
              fil_ptr1->filp_count = 0;
25962
              return(err_code);
25963
25964
25965
        if (read only(rip) != OK)
25966
              panic(__FILE__, "pipe device is read only", NO_NUM);
25967
25968
        rip->i_pipe = I_PIPE;
25969
        rip->i mode &= ~I REGULAR;
25970
        rip->i_mode |= I_NAMED_PIPE; /* pipes and FIFOs have this bit set */
25971
        fil_ptr0->filp_ino = rip;
        fil_ptr0->filp_flags = O_RDONLY;
25972
        dup_inode(rip);
25973
                                    /* for double usage */
25974
        fil_ptrl->filp_ino = rip;
25975
        fil_ptrl->filp_flags = O_WRONLY;
25976
        rw_inode(rip, WRITING);
m_out.reply_i1 = fil_des[0];
                                    /* mark inode as allocated */
25977
25978
        m_out.reply_i2 = fil_des[1];
        rip->i_update = ATIME | CTIME | MTIME;
25979
25980
        return(OK);
25981
25983 /*----*
                                  pipe check
25985
      25986 PUBLIC int pipe_check(rip, rw_flag, oflags, bytes, position, canwrite, notouch)
25987 register struct inode *rip; /* the inode of the pipe */
25988 int rw_flag;
                                    /* READING or WRITING */
                                    /* flags set by open or fcntl */
25989 int oflags;
25990 register int bytes;
                                    /* bytes to be read or written (all chunks) */
25991 register off_t position;
                                    /* current file position */
25992 int *canwrite;
                                    /* return: number of bytes we can write */
                                    /* check only */
25993 int notouch;
25994
      /* Pipes are a little different. If a process reads from an empty pipe for
25995
      * which a writer still exists, suspend the reader. If the pipe is empty
       * and there is no writer, return 0 bytes. If a process is writing to a
25997
25998
       * pipe and no one is reading from it, give a broken pipe error.
25999
26000
26001
        /* If reading, check for empty pipe. */
26002
        if (rw_flag == READING) {
              if (position >= rip->i_size) {
26003
26004
                     /* Process is reading from an empty pipe. */
26005
                     if (find_filp(rip, W_BIT) != NIL_FILP) {
26006
26007
                             /* Writer exists */
26008
                             if (oflags & O_NONBLOCK) {
26009
                                    r = EAGAIN;
26010
                              else
26011
                                     if (!notouch)
                                            suspend(XPIPE); /* block reader */
26012
                                    r = SUSPEND;
26013
26014
```

```
book.txt
Feb 25, 11 15:18
                                                                       Page 352/393
       File: Page: 989 servers/fs/pipe.c
26015
                              /* If need be, activate sleeping writers. */
26016
                              if (susp_count > 0 && !notouch)
26017
                                      release(rip, WRITE, susp_count);
26018
26019
                      return(r);
26020
26021
         } else'
               /* Process is writing to a pipe. */
26022
              if (find_filp(rip, R_BIT) == NIL_FILP) {
26023
                      /* Tell kernel to generate a SIGPIPE signal. */
26024
                      if (!notouch)
26025
26026
                              sys kill((int)(fp - fproc), SIGPIPE);
                      return(EPIPE);
26027
26028
26029
26030
              if (position + bytes > PIPE_SIZE(rip->i_sp->s_block_size)) {
26031
                      if ((oflags & O_NONBLOCK)
                       && bytes < PIPE_SIZE(rip->i_sp->s_block_size))
26032
26033
                             return(EAGAIN);
                      else if ((oflags & O_NONBLOCK)
26034
26035
                      && bytes > PIPE_SIZE(rip->i_sp->s_block_size)) {
26036
                      if ( (*canwrite = (PIPE_SIZE(rip->i_sp->s_block_size)
26037
                              - position)) > 0)
26038
                                      /* Do a partial write. Need to wakeup reader */
26039
                                      if (!notouch)
26040
                                             release(rip, READ, susp_count);
26041
                                      return(1);
26042
                              } else
                                      return(EAGAIN);
26043
26044
26045
                      if (bytes > PIPE_SIZE(rip->i_sp->s_block_size)) {
26046
26047
                              if ((*canwrite = PIPE_SIZE(rip->i_sp->s_block_size)
26048
                                      - position) > 0) {
                                      /* Do a partial write. Need to wakeup reader
26049
26050
                                       * since we'll suspend ourself in read_write()
26051
26052
                                      release(rip, READ, susp_count);
26053
                                      return(1);
26054
26055
26056
26057
                              suspend(XPIPE); /* stop writer -- pipe full */
26058
                      return(SUSPEND);
26059
26060
26061
               /* Writing to an empty pipe. Search for suspended reader. */
26062
              if (position == 0 && !notouch)
26063
                      release(rip, READ, susp_count);
26064
26065
26066
         *canwrite = 0;
26067
         return(1);
26068
26070
                                      suspend
26072
       *=======*/
26073 PUBLIC void suspend(task)
26074 int task;
                                      /* who is proc waiting for? (PIPE = pipe) */
```

```
book.txt
Feb 25, 11 15:18
                                                                       Page 353/393
       File: Page: 990 servers/fs/pipe.c
26075
26076
      /* Take measures to suspend the processing of the present system call.
26077
       * Store the parameters to be used upon resuming in the process table.
26078
       * (Actually they are not used when a process is waiting for an I/O device,
       * but they are needed for pipes, and it is not worth making the distinction.)
26079
26080
       * The SUSPEND pseudo error should be returned after calling suspend().
26081
26082
26083
        if (task == XPIPE | task == XPOPEN) susp_count++;/* #procs susp'ed on pipe*/
        fp->fp_suspended = SUSPENDED;
26084
26085
         fp->fp fd = m in.fd << 8 | call nr;
26086
         fp->fp task = -task;
26087
        if (task == XLOCK) {
              fp->fp_buffer`= (char *) m_in.namel;
                                                     /* third arg to fcntl() */
26088
              fp->fp_nbytes = m_in.request;
                                                     /* second arg to fcntl() */
26089
26090
        } else {
26091
              fp->fp_buffer = m_in.buffer;
                                                      /* for reads and writes */
26092
              fp->fp_nbytes = m_in.nbytes;
26093
26094
26096
      /*==================================
26097
                                     release
26098
26099 PUBLIC void release(ip, call_nr, count)
26100
      register struct inode *ip;
                                  /* inode of pipe */
                                     /* READ, WRITE, OPEN or CREAT */
26101 int call nr;
26102 int count;
                                     /* max number of processes to release */
26103
26104 /* Check to see if any process is hanging on the pipe whose inode is in 'ip'.
       * If one is, and it was trying to perform the call indicated by 'call_nr',
26105
26106
       * release it
26107
       * /
26108
26109
        register struct fproc *rp;
26110
        struct filp *f;
26111
26112
         /* Trying to perform the call also includes SELECTing on it with that
26113
         * operation.
26114
        if (call_nr == READ || call_nr == WRITE) {
26115
26116
                int op;
26117
                if (call_nr == READ)
26118
                      op = SEL_RD;
26119
26120
                      op = SEL WR;
26121
                for(f = &filp[0]; f < &filp[NR_FILPS]; f++) {
26122
                      if (f->filp_count < 1 | !(f->filp_pipe_select_ops & op) ||
26123
                         f->filp_ino != ip)
26124
                              continue;
26125
                       select_callback(f, op);
                      f->filp_pipe_select_ops &= ~op;
26126
26127
26128
26129
26130
         /* Search the proc table. */
        for (rp = &fproc[0]; rp < &fproc[NR_PROCS]; rp++) {
26131
              if (rp->fp_suspended == SUSPENDED &&
26132
                              rp->fp_revived == NOT_REVIVING &&
26133
26134
                              (rp->fp fd & BYTE) == call nr &&
```

```
Feb 25, 11 15:18
                                    book.txt
                                                                  Page 354/393
      File: Page: 991 servers/fs/pipe.c
26135
                            rp->fp_filp[rp->fp_fd>>8]->filp_ino == ip) {
                     revive((int)(rp - fproc), 0);
susp_count--; /* keep track of who is suspended */
26136
26137
26138
                     if (--count == 0) return;
26139
26140
26141 }
26143
     26144
                                   revive
26145
26146 PUBLIC void revive(proc_nr, returned)
                                   /* process to revive */
26147 int proc nr;
26148 int returned;
                                   /* if hanging on task, how many bytes read */
26149
26150
      /* Revive a previously blocked process. When a process hangs on tty, this
26151
       * is the way it is eventually released.
26152
26153
26154
        register struct fproc *rfp;
26155
        register int task;
26156
26157
        if (proc_nr < 0 || proc_nr >= NR_PROCS)
             panic(__FILE__, "revive err", proc_nr);
26158
26159
        rfp = &fproc[proc_nr];
26160
        if (rfp->fp_suspended == NOT_SUSPENDED | rfp->fp_revived == REVIVING)return;
26161
26162
        /* The 'reviving' flag only applies to pipes. Processes waiting for TTY get
         * a message right away. The revival process is different for TTY and pipes.
26163
         * For select and TTY revival, the work is already done, for pipes it is not:
26164
26165
         * the proc must be restarted so it can try again.
26166
26167
        task = -rfp->fp_task;
26168
        if (task == XPIPE | task == XLOCK) {
26169
              /* Revive a process suspended on a pipe or lock. */
26170
              rfp->fp_revived = REVIVING;
26171
             reviving++;
                                   /* process was waiting on pipe or lock */
        } else {
26172
26173
             rfp->fp_suspended = NOT_SUSPENDED;
              if (task == XPOPEN) /* process blocked in open or create */
26174
26175
                     reply(proc_nr, rfp->fp_fd>>8);
26176
              else if (task == XSELECT) {
26177
                     reply(proc_nr, returned);
26178
               else {
26179
                     /* Revive a process suspended on TTY or other device. */
                     rfp->fp_nbytes = returned;
26180
                                                  /*pretend it wants only what the
re is*/
26181
                     reply(proc_nr, returned);
                                                  /* unblock the process */
26182
26183
26184
26187
                                   do unpause
26188
       26189
      PUBLIC int do unpause()
26190
26191
        * A signal has been sent to a user who is paused on the file system.
       * Abort the system call with the EINTR error message.
26192
26193
26194
```

```
Feb 25, 11 15:18
                                    book.txt
                                                                   Page 355/393
      File: Page: 992 servers/fs/pipe.c
26195
        register struct fproc *rfp;
26196
        int proc_nr, task, fild;
26197
        struct filp *f;
26198
        dev t dev;
26199
        message mess;
26200
        if (who > PM_PROC_NR) return(EPERM);
26201
26202
        proc_nr = m_in.pro;
26203
        if (proc_nr < 0 || proc_nr >= NR_PROCS)
             panic(__FILE__, "unpause err 1", proc_nr);
26204
26205
        rfp = &fproc[proc nr];
26206
        if (rfp->fp suspended == NOT SUSPENDED) return(OK);
26207
        task = -rfp->fp_task;
26208
26209
        switch (task) {
26210
             case XPIPE:
                                     /* process trying to read or write a pipe */
26211
                     break;
26212
             case XLOCK:
26213
                                     /* process trying to set a lock with FCNTL */
26214
                     break;
26215
26216
             case XSELECT:
                                     /* process blocking on select() */
26217
                     select_forget(proc_nr);
26218
                     break;
26219
26220
              case XPOPEN:
                                     /* process trying to open a fifo */
26221
                    break;
26222
26223
              default:
                                     /* process trying to do device I/O (e.g. tty)*/
                     fild = (rfp->fp_fd >> 8) & BYTE;/* extract file descriptor */
26224
                     if (fild < 0 | fild >= OPEN_MAX)
26225
26226
                            panic(__FILE__, "unpause err 2", NO_NUM);
26227
                     f = rfp->fp_filp[fild];
26228
                     dev = (dev_t) f->filp_ino->i_zone[0]; /* device hung on */
26229
                     mess.TTY_LINE = (dev >> MINOR) & BYTE;
26230
                     mess.PROC_NR = proc_nr;
26231
                     /* Tell kernel R or W. Mode is from current call, not open. */
26232
26233
                     mess.COUNT = (rfp->fp_fd & BYTE) == READ ? R_BIT : W_BIT;
                     mess.m_type = CANCEL;
26234
26235
                                   /* hack - ctty_io uses fp */
                     fp = rfp;
                     (*dmap[(dev >> MAJOR) & BYTE].dmap io)(task, &mess);
26236
26237
26238
        rfp->fp suspended = NOT SUSPENDED;
26239
26240
        reply(proc nr, EINTR);
                                   /* signal interrupted call */
26241
        return(OK);
26242
26245
                                  select_request_pipe
26246
       26247 PUBLIC int select_request_pipe(struct filp *f, int *ops, int block)
26248
26249
             int orig_ops, r = 0, err, canwrite;
26250
             orig_ops = *ops;
             if ((*ops & SEL_RD)) {
26251
26252
                     if ((err = pipe_check(f->filp_ino, READING, 0,
26253
                            1, f->filp_pos, &canwrite, 1)) != SUSPEND)
26254
                            r |= SEL RD;
```

```
Feb 25, 11 15:18
                                 book.txt
                                                            Page 356/393
      File: Page: 993 servers/fs/pipe.c
                   if (err < 0 && err != SUSPEND && (*ops & SEL_ERR))
26255
26256
                          r |= SEL_ERR;
26257
26258
             if ((*ops & SEL_WR)) {
                   if ((err = pipe_check(f->filp_ino, WRITING, 0,
26259
26260
                          1, f->filp_pos, &canwrite, 1)) != SUSPEND)
26261
                          r |= SEL_WR;
                   if (err < 0 && err != SUSPEND && (*ops & SEL_ERR))
26262
26263
                         r |= SEL ERR;
26264
26265
26266
             *ops = r;
26267
26268
            if (!r && block) {
26269
                   f->filp pipe select ops |= orig ops;
26270
26271
26272
            return SEL_OK;
26273 }
26275
     /*----*
26276
                                select_match_pipe
26277
      26278 PUBLIC int select_match_pipe(struct filp *f)
26279 {
26280
             /* recognize either pipe or named pipe (FIFO) */
             if (f && f->filp_ino && (f->filp_ino->i_mode & I_NAMED_PIPE))
26281
26282
                   return 1;
26283
            return 0;
26284 }
servers/fs/path.c
26300 /* This file contains the procedures that look up path names in the directory
26301 * system and determine the inode number that goes with a given path name.
26302
26303
      * The entry points into this file are
                     the 'main' routine of the path-to-inode conversion mechanism
26304
         eat path:
                     find the final directory on a given path
26305
          last dir:
26306
          advance:
                     parse one component of a path name
26307
          search_dir: search a directory for a string and return its inode number
26308
26309
26310 #include "fs.h"
26311 #include <string.h>
26312 #include <minix/callnr.h>
26313 #include "buf.h"
26314 #include "file.h"
26315 #include "fproc.h"
26316 #include "inode.h"
26317 #include "super.h"
26318
26319 PUBLIC char dot1[2] = ".";
                                /* used for search dir to bypass the access */
```

```
Feb 25, 11 15:18
                                 book.txt
                                                              Page 357/393
      File: Page: 994 servers/fs/path.c
26320 PUBLIC char dot2[3] = "..";
                                 /* permissions for . and ..
26321
26322 FORWARD _PROTOTYPE( char *get_name, (char *old_name, char string [NAME_MAX]) );
26323
26324 /*==========*
26325 *
                                 eat_path
26327 PUBLIC struct inode *eat_path(path)
26328 char *path;
                                /* the path name to be parsed */
26329
     /* Parse the path 'path' and put its inode in the inode table. If not possible,
26330
26331 * return NIL INODE as function value and an error code in 'err code'.
26332
26333
       register struct inode *ldip, *rip;
26334
26335
       char string[NAME MAX];
                                /* hold 1 path component name here */
26336
26337
        /* First open the path down to the final directory. */
26338
       if ( (ldip = last_dir(path, string)) == NIL_INODE) {
26339
             return(NIL_INODE); /* we couldn't open final directory */
26340
26341
       /* The path consisting only of "/" is a special case, check for it. */
26342
       if (string[0] == '\0') return(ldip);
26343
26344
26345
       /* Get final component of the path. */
       rip = advance(ldip, string);
26346
26347
       put inode(ldip);
26348
       return(rip);
26349
26351 /*===========*
26352 *
                      last_dir
26354 PUBLIC struct inode *last_dir(path, string)
                         /* the path name to be parsed */
26355 char *path;
                               /* the final component is returned here */
26356 char string[NAME_MAX];
26357
26358 /* Given a path, 'path', located in the fs address space, parse it as
      * far as the last directory, fetch the inode for the last directory into
26359
      * the inode table, and return a pointer to the inode. In
26360
      * addition, return the final component of the path in 'string'.
      * If the last directory can't be opened, return NIL_INODE and
26362
26363
      * the reason for failure in 'err_code'.
26364
26365
26366
       register struct inode *rip;
26367
       register char *new_name;
26368
       register struct inode *new_ip;
26369
26370
       /* Is the path absolute or relative? Initialize 'rip' accordingly. */
26371
       rip = (*path == '/' ? fp->fp_rootdir : fp->fp_workdir);
26372
26373
         * If dir has been removed or path is empty, return ENOENT. */
26374
       if (rip->i_nlinks == 0 || *path == '\0') {
26375
            err code = ENOENT;
            return(NIL INODE);
26376
26377
26378
26379
       dup inode(rip);
                                 /* inode will be returned with put inode */
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 358/393
      File: Page: 995 servers/fs/path.c
26380
26381
         /* Scan the path component by component. */
26382
        while (TRUE) {
26383
              /* Extract one component. */
              if ( (new_name = get_name(path, string)) == (char*) 0) {
26384
26385
                     put_inode(rip); /* bad path in user space */
26386
                     return(NIL_INODE);
26387
              if (*new name == '\0') {
26388
26389
                     if ( (rip->i_mode & I_TYPE) == I_DIRECTORY) {
26390
                             return(rip); /* normal exit */
26391
                             /* last file of path prefix is not a directory */
26392
26393
                             put_inode(rip);
26394
                             err code = ENOTDIR;
26395
                             return(NIL INODE);
26396
26397
26398
              /* There is more path. Keep parsing. */
26399
              new_ip = advance(rip, string);
26400
26401
              put_inode(rip);
                                    /* rip either obsolete or irrelevant */
              if (new_ip == NIL_INODE) return(NIL_INODE);
26402
26403
26404
              /* The call to advance() succeeded. Fetch next component. */
26405
              path = new name;
              rip = new ip;
26406
26407
26408 }
26411 *
                                    get name
26413 PRIVATE char *get_name(old_name, string)
26414 char *old_name;
26415 char string[NAME_MAX];
                                    /* path name to parse */
                                    /* component extracted from 'old_name' */
26416
26417 /* Given a pointer to a path name in fs space, 'old_name', copy the next
26418
       * component to 'string' and pad with zeros. A pointer to that part of
       * the name as yet unparsed is returned. Roughly speaking,
26419
26420
       * 'get name' = 'old name' - 'string'.
26421
       * This routine follows the standard convention that /usr/ast, /usr//ast,
26422
26423
       * //usr///ast and /usr/ast/ are all equivalent.
26424
26425
26426
        register int c;
26427
        register char *np, *rnp;
26428
26429
        np = string;
                                    /* 'np' points to current position */
                                    /* 'rnp' points to unparsed string */
26430
        rnp = old_name;
        while ((c = *rnp) == '/') rnp++; /* skip leading slashes */
26431
26432
26433
        /* Copy the unparsed path, 'old_name', to the array, 'string'. */
        while ( rnp < &old_name[PATH_MAX] && c != '/' && c != '\0') {
   if (np < &string[NAME_MAX]) *np++ = c;</pre>
26434
26435
26436
                                    /* advance to next character */
              c = *++rnp;
26437
26438
26439
        /* To make /usr/ast/ equivalent to /usr/ast, skip trailing slashes. */
```

```
Feb 25, 11 15:18
                                      book.txt
                                                                      Page 359/393
       File: Page: 996 servers/fs/path.c
26440
        while (c == '/' && rnp < \bar{\text{wold}} name[PATH_MAX]) c = *++rnp;
26441
        if (np < &string[NAME_MAX]) *np = '\0';</pre>
26442
                                                     /* Terminate string */
26443
26444
        if (rnp >= &old_name[PATH_MAX]) {
26445
              err_code = ENAMETOOLONG;
26446
              return((char *) 0);
26447
26448
        return(rnp);
26449
26451
      /*----*
26452
                                     advance
26453
       26454 PUBLIC struct inode *advance(dirp, string)
      struct inode *dirp;
                                     /* inode for directory to be searched */
26455
26456
      char string[NAME_MAX];
                                     /* component name to look for */
26457
26458
      /* Given a directory and a component of a path, look up the component in
       * the directory, find the inode, open it, and return a pointer to its inode
26459
       * slot. If it can't be done, return NIL_INODE.
26461
26462
26463
        register struct inode *rip;
        struct inode *rip2;
26464
26465
        register struct super block *sp;
26466
        int r, inumb;
26467
        dev t mnt dev;
26468
        ino_t numb;
26469
26470
        /* If 'string' is empty, yield same inode straight away. */
26471
        if (string[0] == '\0') { return(get_inode(dirp->i_dev, (int) dirp->i_num)); }
26472
26473
        /* Check for NIL INODE. */
        if (dirp == NIL_INODE) { return(NIL_INODE); }
26474
26475
26476
        /* If 'string' is not present in the directory, signal error. */
26477
        if ( (r = search_dir(dirp, string, &numb, LOOK_UP)) != OK) {
26478
              err code = r;
26479
              return(NIL_INODE);
26480
26481
        /* Don't go beyond the current root directory, unless the string is dot2. */
if (dirp == fp->fp_rootdir && strcmp(string, "..") == 0 && string != dot2)
26482
26483
                      return(get_inode(dirp->i_dev, (int) dirp->i_num));
26484
26485
26486
         /* The component has been found in the directory. Get inode. */
        if ((rip = get_inode(dirp->i_dev, (int) numb)) == NIL_INODE) {
26487
26488
              return(NIL_INODE);
26489
26490
26491
        if (rip->i_num == ROOT_INODE)
              if (dirp->i_num == ROOT_INODE) {
26492
                  if (string[1] == '.') {
26493
26494
                      for (sp = &super_block[1]; sp < &super_block[NR_SUPERS]; sp++){
                              if (sp->s_dev == rip->i_dev) {
26495
                                      /* Release the root inode. Replace by the
26496
                                       * inode mounted on.
26497
26498
26499
                                      put inode(rip);
```

```
Feb 25, 11 15:18
                                      book.txt
                                                                      Page 360/393
      File: Page: 997 servers/fs/path.c
26500
                                     mnt_dev = sp->s_imount->i_dev;
26501
                                     inumb = (int) sp->s_imount->i_num;
26502
                                     rip2 = get_inode(mnt_dev, inumb);
26503
                                     rip = advance(rip2, string);
26504
                                     put_inode(rip2);
26505
26506
26507
26508
26509
26510
        if (rip == NIL INODE) return(NIL INODE);
26511
        /st See if the inode is mounted on. If so, switch to root directory of the
26512
         * mounted file system. The super_block provides the linkage between the
26513
26514
         * inode mounted on and the root directory of the mounted file system.
26515
26516
        while (rip != NIL_INODE && rip->i_mount == I_MOUNT) {
26517
              /* The inode is indeed mounted on. */
26518
              for (sp = &super_block[0]; sp < &super_block[NR_SUPERS]; sp++) {
26519
                      if (sp->s_imount == rip) {
26520
                             /* Release the inode mounted on. Replace by the
26521
                               * inode of the root inode of the mounted device.
26522
26523
                              put inode(rip);
26524
                              rip = get_inode(sp->s_dev, ROOT_INODE);
                              break;
26525
26526
26527
26528
26529
        return(rip);
                             /* return pointer to inode's component */
26530
26532 /*============*
26533
                                    search dir
26534
      *-----*/
26535 PUBLIC int search_dir(ldir_ptr, string, numb, flag)
26536 register struct inode *ldir_ptr; /* ptr to inode for dir to search */
                                     /* component to search for */
26537 char string[NAME_MAX];
26538 ino_t *numb;
                                      /* pointer to inode number */
26539
                                      /* LOOK_UP, ENTER, DELETE or IS_EMPTY */
      int flag;
26540
26541 /* This function searches the directory whose inode is pointed to by 'ldip':
       * if (flag == ENTER) enter 'string' in the directory with inode # '*numb';
* if (flag == DELETE) delete 'string' from the directory;
26542
26543
       * if (flag == LOOK UP) search for 'string' and return inode # in 'numb';
26544
       * if (flag == IS_EMPTY) return OK if only . and .. in dir else ENOTEMPTY;
26545
26546
26547
            if 'string' is dot1 or dot2, no access permissions are checked.
26548
26549
26550
        register struct direct *dp = NULL;
26551
        register struct buf *bp = NULL;
26552
        int i, r, e_hit, t, match;
26553
        mode t bits;
26554
        off_t pos;
26555
        unsigned new_slots, old_slots;
26556
        block t b;
26557
        struct super block *sp;
26558
        int extended = 0;
26559
```

```
book.txt
Feb 25, 11 15:18
                                                                        Page 361/393
       File: Page: 998 servers/fs/path.c
        /* If 'ldir_ptr' is not a pointer to a dir inode, error. */
26560
26561
         if ( (ldir_ptr->i_mode & I_TYPE) != I_DIRECTORY) return(ENOTDIR);
26562
26563
        r = OK;
26564
26565
        if (flag != IS_EMPTY) {
26566
               bits = (flag == LOOK_UP ? X_BIT : W_BIT | X_BIT);
26567
26568
               if (string == dot1 || string == dot2) {
26569
                       if (flag != LOOK_UP) r = read_only(ldir_ptr);
26570
                                            /* only a writable device is required. */
26571
26572
               else r = forbidden(ldir ptr, bits); /* check access permissions */
26573
26574
         if (r != OK) return(r);
26575
26576
         /* Step through the directory one block at a time. */
26577
         old_slots = (unsigned) (ldir_ptr->i_size/DIR_ENTRY_SIZE);
26578
        new slots = 0;
26579
        e hit = FALSE;
26580
        match = 0;
                                      /* set when a string match occurs */
26581
26582
         for (pos = 0; pos < ldir_ptr->i_size; pos += ldir_ptr->i_sp->s_block_size) {
               b = read_map(ldir_ptr, pos);    /* get block number */
26583
26584
26585
               /* Since directories don't have holes, 'b' cannot be NO BLOCK. */
26586
               26587
26588
               if (bp == NO_BLOCK)
                      panic( FILE , "get block returned NO BLOCK", NO NUM);
26589
26590
26591
               /* Search a directory block. */
26592
               for (dp = \&bp -> b_dir[0];
26593
                      dp < &bp->b_dir[NR_DIR_ENTRIES(ldir_ptr->i_sp->s_block_size)];
26594
                       dp++) {
26595
                       if (++new_slots > old_slots) { /* not found, but room left */
26596
                              if (flag == ENTER) e_hit = TRUE;
26597
                              break;
26598
26599
26600
                       /* Match occurs if string found. */
                       if (flag != ENTER && dp->d_ino != 0) {
26601
                              if (flag == IS_EMPTY) {
26602
26603
                                       /* If this test succeeds, dir is not empty. */
                                      if (strcmp(dp->d_name, ".") != 0 &&
    strcmp(dp->d_name, "..") != 0) match = 1;
26604
26605
26606
                               } else {
                                       if (strncmp(dp->d_name, string, NAME_MAX) == 0)
26607
26608
                                              match = 1;
26609
26610
26611
26612
26613
                       if (match)
26614
                               /* LOOK UP or DELETE found what it wanted. */
                              r = OK;
26615
26616
                              if (flag == IS EMPTY) r = ENOTEMPTY;
                               else if (flag == DELETE) {
26617
26618
                                      /* Save d ino for recovery. */
26619
                                      t = NAME MAX - sizeof(ino t);
```

```
Feb 25, 11 15:18
                                         book.txt
                                                                            Page 362/393
       File: Page: 999 servers/fs/path.c
26620
                                         *((ino_t *) &dp->d_name[t]) = dp->d_ino;
26621
                                         dp->d_ino = 0; /* erase entry */
26622
                                         bp->b_dirt = DIRTY;
26623
                                         ldir_ptr->i_update |= CTIME | MTIME;
26624
                                         ldir_ptr->i_dirt = DIRTY;
26625
26626
                                         sp = ldir_ptr->i_sp; /* 'flag' is LOOK_UP */
26627
                                         *numb = conv4(sp->s_native, (int) dp->d_ino);
26628
                                put_block(bp, DIRECTORY_BLOCK);
26629
26630
                                return(r);
26631
26632
26633
                        /* Check for free slot for the benefit of ENTER. */
                        if (flag == ENTER && dp->d_ino == 0) {
26634
26635
                                e hit = TRUE; /* we found a free slot */
26636
                                break;
26637
26638
26639
26640
                /* The whole block has been searched or ENTER has a free slot. */
26641
               if (e hit) break;
                                        /* e_hit set if ENTER can be performed now */
26642
               put_block(bp, DIRECTORY_BLOCK); /* otherwise, continue searching dir */
26643
26644
26645
          /* The whole directory has now been searched. */
26646
         if (flag != ENTER) {
               return(flag == IS_EMPTY ? OK : ENOENT);
26647
26648
26649
26650
         /* This call is for ENTER. If no free slot has been found so far, try to
26651
          * extend directory.
26652
26653
         if (e_hit == FALSE) { /* directory is full and no room left in last block */
26654
               new slots++;
                                        /* increase directory size by 1 entry */
               if (new slots == 0) return(EFBIG); /* dir size limited by slot count */
26655
26656
               if ( (bp = new_block(ldir_ptr, ldir_ptr->i_size)) == NIL_BUF)
26657
                       return(err_code);
26658
               dp = \&bp -> b dir[0];
26659
               extended = \overline{1};
26660
26661
         /* 'bp' now points to a directory block with space. 'dp' points to slot. */ (void) memset(dp->d_name, 0, (size_t) NAME_MAX); /* clear entry */ ...
26662
26663
         for (i = 0; string[i] && i < NAME MAX; i++) dp->d name[i] = string[i];
26664
26665
         sp = ldir_ptr->i_sp;
26666
         dp->d_ino = conv4(sp->s_native, (int) *numb);
26667
         bp->b_dirt = DIRTY;
26668
         put_block(bp, DIRECTORY_BLOCK);
26669
         ldir_ptr->i_update |= CTIME | MTIME; /* mark mtime for update later */
26670
         ldir_ptr->i_dirt = DIRTY;
26671
         if (new_slots > old_slots)
               ldir_ptr->i_size = (off_t) new_slots * DIR_ENTRY_SIZE;
26672
                /* Send the change to disk if the directory is extended. */
26673
26674
               if (extended) rw_inode(ldir_ptr, WRITING);
26675
26676
         return(OK);
26677 }
```

```
book.txt
Feb 25, 11 15:18
                                                                Page 363/393
      File: Page: 1000 servers/fs/mount.c
servers/fs/mount.c
26700 /* This file performs the MOUNT and UMOUNT system calls.
26701
26702
      * The entry points into this file are
26703 * do_mount: perform the MOUNT system call 26704 * do_umount: perform the UMOUNT system call
26705 */
26706
26707 #include "fs.h"
26708 #include <fcntl.h>
26709 #include <minix/com.h>
26710 #include <sys/stat.h>
26711 #include "buf.h"
26712 #include "file.h"
26713 #include "fproc.h"
26714 #include "inode.h"
26715 #include "param.h"
26716 #include "super.h"
26717
26718 FORWARD _PROTOTYPE( dev_t name_to_dev, (char *path)
26719
26720 /*============*
26721
                                 do mount
26722
       *======*/
26723
      PUBLIC int do_mount()
26724
26725 /* Perform the mount(name, mfile, rd only) system call. */
26726
26727
        register struct inode *rip, *root_ip;
26728
        struct super_block *xp, *sp;
26729
        dev_t dev;
26730
        mode_t bits;
26731
        int rdir, mdir;
                                  /* TRUE iff {root|mount} file is dir */
26732
        int r. found;
26733
26734
        /* Only the super-user may do MOUNT. */
26735
        if (!super user) return(EPERM);
26736
        /* If 'name' is not for a block special file, return error. */
26737
26738
        if (fetch_name(m_in.name1, m_in.name1_length, M1) != OK) return(err_code);
        if ( (dev = name to dev(user path)) == NO DEV) return(err code);
26739
26740
26741
        /* Scan super block table to see if dev already mounted & find a free slot.*/
26742
        sp = NIL SUPER;
26743
        found = FALSE;
26744
        for (xp = &super_block[0]; xp < &super_block[NR_SUPERS]; xp++) {</pre>
26745
             if (xp->s_dev == dev) found = TRUE; /* is it mounted already? */
26746
             if (xp->s_dev == NO_DEV) sp = xp;
                                                /* record free slot */
26747
        if (found) return(EBUSY); /* already mounted */
26748
26749
        if (sp == NIL_SUPER) return(ENFILE); /* no super block available */
26750
26751
          * Open the device the file system lives on. */
        if (dev_open(dev, who, m_in.rd_only ? R_BIT : (R_BIT|W_BIT)) != OK)
26752
26753
             return(EINVAL);
26754
```

```
Feb 25, 11 15:18
                                       book.txt
                                                                         Page 364/393
       File: Page: 1001 servers/fs/mount.c
26755
         /* Make the cache forget about blocks it has open on the filesystem */
26756
         (void) do_sync();
26757
         invalidate(dev);
26758
26759
         /* Fill in the super block. */
26760
         sp->s_dev = dev;
                                       /* read_super() needs to know which dev */
26761
         r = read_super(sp);
26762
26763
         /* Is it recognized as a Minix filesystem? */
26764
         if (r != OK) {
26765
               dev close(dev);
26766
               sp->s dev = NO DEV;
26767
              return(r);
26768
26769
26770
         /* Now get the inode of the file to be mounted on. */
26771
         if (fetch_name(m_in.name2, m_in.name2_length, M1) != OK) {
26772
               dev_close(dev);
26773
               sp->s_dev = NO_DEV;
26774
               return(err_code);
26775
26776
         if ( (rip = eat_path(user_path)) == NIL_INODE) {
26777
               dev_close(dev);
26778
               sp->s dev = NO DEV;
26779
              return(err_code);
26780
26781
26782
         /* It may not be busy. */
26783
         r = OK;
26784
         if (rip->i count > 1) r = EBUSY;
26785
26786
         /* It may not be special. */
26787
         bits = rip->i_mode & I_TYPE;
26788
         if (bits == I_BLOCK_SPECIAL | | bits == I_CHAR_SPECIAL) r = ENOTDIR;
26789
26790
         /* Get the root inode of the mounted file system. */
         root_ip = NIL_INODE;
26791
                                      /* if 'r' not OK, make sure this is defined */
26792
         if (r == OK) {
26793
               if ( (root_ip = get_inode(dev, ROOT_INODE)) == NIL_INODE) r = err_code;
26794
26795
         if (root_ip != NIL_INODE && root_ip->i_mode == 0) {
26796
              r = EINVAL;
26797
26798
26799
         /* File types of 'rip' and 'root ip' may not conflict. */
26800
         if (r == OK)
               mdir = ((rip->i_mode & I_TYPE) == I_DIRECTORY); /* TRUE iff dir */
26801
26802
               rdir = ((root_ip->i_mode & I_TYPE) == I_DIRECTORY);
26803
               if (!mdir && rdir) r = EISDIR;
26804
26805
26806
         /* If error, return the super block and both inodes; release the maps. */
         if (r != OK)
26807
26808
              put inode(rip);
26809
               put_inode(root_ip);
26810
               (void) do_sync();
26811
               invalidate(dev);
26812
               dev close(dev);
26813
               sp->s_dev = NO_DEV;
26814
              return(r);
```

```
book.txt
Feb 25, 11 15:18
                                                                 Page 365/393
      File: Page: 1002 servers/fs/mount.c
26815
26816
26817
        /* Nothing else can go wrong. Perform the mount. */
26818
       rip->i_mount = I_MOUNT; /* this bit says the inode is mounted on */
26819
        sp->s_imount = rip;
26820
        sp->s_isup = root_ip;
26821
        sp->s_rd_only = m_in.rd_only;
26822
       return(OK);
26823 }
26825
26826
                                 do umount
26827
       *=======*/
26828
      PUBLIC int do_umount()
26829
26830
      /* Perform the umount(name) system call. */
26831
       dev_t dev;
26832
26833
        /* Only the super-user may do UMOUNT. */
26834
        if (!super_user) return(EPERM);
26835
26836
        /* If 'name' is not for a block special file, return error. */
26837
        if (fetch_name(m_in.name, m_in.name_length, M3) != OK) return(err_code);
       if ( (dev = name_to_dev(user_path)) == NO_DEV) return(err_code);
26838
26839
26840
        return(unmount(dev));
26841 }
26843 /*============*
26845 *==========*/
26846 PUBLIC int unmount(dev)
26847 Dev_t dev;
26848
     /* Unmount a file system by device number. */
26849
26850
      register struct inode *rip;
26851
        struct super_block *sp, *sp1;
26852
       int count;
26853
26854
        /* See if the mounted device is busy. Only 1 inode using it should be
26855
         * open -- the root inode -- and that inode only 1 time.
26856
26857
        count = 0;
26858
        for (rip = &inode[0]; rip< &inode[NR_INODES]; rip++)</pre>
             if (rip->i_count > 0 && rip->i_dev == dev) count += rip->i_count;
26859
26860
        if (count > 1) return(EBUSY); /* can't umount a busy file system */
26861
        /* Find the super block. */
26862
26863
        sp = NIL_SUPER;
26864
        for (sp1 = &super_block[0]; sp1 < &super_block[NR_SUPERS]; sp1++) {</pre>
26865
             if (sp1->s_dev == dev) {
26866
                    sp = sp1;
26867
                    break;
26868
26869
26870
        /* Sync the disk, and invalidate cache. */
26871
26872
        (void) do sync();
                                   /* force any cached blocks out of memory */
                                   /* invalidate cache entries for this dev */
26873
        invalidate(dev);
26874
        if (sp == NIL SUPER) {
```

```
Feb 25, 11 15:18
                                  book.txt
                                                               Page 366/393
      File: Page: 1003 servers/fs/mount.c
26875
             return(EINVAL);
26876
26877
26878
        /* Close the device the file system lives on. */
26879
        dev_close(dev);
26880
26881
        /* Finish off the unmount. */
26882
        sp->s_imount->i_mount = NO_MOUNT; /* inode returns to normal */
26883
        put_inode(sp->s_imount);
                               /* release the inode mounted on */
26884
        put_inode(sp->s_isup);
                                  /* release the root inode of the mounted fs */
26885
        sp->s imount = NIL INODE;
26886
        sp->s dev = NO DEV;
26887
        return(OK);
26888
26890 /*=========*
26891 *
                                 name to dev
26893 PRIVATE dev_t name_to_dev(path)
                                  /* pointer to path name */
26894 char *path;
26895
26896
      /* Convert the block special file 'path' to a device number. If 'path'
       * is not a block special file, return error code in 'err_code'.
26897
26898
26899
26900
        register struct inode *rip;
26901
        register dev t dev;
26902
26903
        /* If 'path' can't be opened, give up immediately. */
26904
        if ( (rip = eat path(path)) == NIL INODE) return(NO DEV);
26905
26906
        /* If 'path' is not a block special file, return error. */
26907
        if ( (rip->i_mode & I_TYPE) != I_BLOCK_SPECIAL) {
26908
             err_code = ENOTBLK;
26909
             put_inode(rip);
26910
             return(NO_DEV);
26911
26912
26913
        /* Extract the device number. */
26914
        dev = (dev_t) rip->i_zone[0];
26915
        put inode(rip);
26916
        return(dev);
26917 }
                               servers/fs/link.c
27000 /* This file handles the LINK and UNLINK system calls. It also deals with
27001 * deallocating the storage used by a file when the last UNLINK is done to a
      * file and the blocks must be returned to the free block pool.
27002
27003
27004
      * The entry points into this file are
      * do_link: perform the LINK system call
27005
      * do_unlink: perform the UNLINK and RMDIR system calls
      * do_rename: perform the RENAME system call
27007
27008 * truncate: release all the blocks associated with an inode
27009
```

```
Feb 25, 11 15:18
                                    book.txt
                                                                   Page 367/393
      File: Page: 1004 servers/fs/link.c
27010
27011 #include "fs.h"
27012 #include <sys/stat.h>
27013 #include <string.h>
27014 #include <minix/com.h>
27015 #include <minix/callnr.h>
27016 #include "buf.h"
27017 #include "file.h"
27018 #include "fproc.h"
27019 #include "inode.h"
27020 #include "param.h"
27021 #include "super.h"
27022
27023 #define SAME 1000
27024
27025 FORWARD PROTOTYPE( int remove dir, (struct inode *rldirp, struct inode *rip,
27026
                            char dir_name[NAME_MAX])
27027
27028 FORWARD _PROTOTYPE( int unlink_file, (struct inode *dirp, struct inode *rip,
27029
                            char file_name[NAME_MAX])
27030
27031 /*----*
27032 *
                                  do link
27033 *===========*/
27034 PUBLIC int do_link()
27035
27036 /* Perform the link(name1, name2) system call. */
27037
27038
        register struct inode *ip, *rip;
        register int r;
27039
27040
        char string[NAME MAX];
27041
        struct inode *new_ip;
27042
27043
        /* See if 'name' (file to be linked) exists. */
27044
        if (fetch_name(m_in.name1, m_in.name1_length, M1) != OK) return(err_code);
27045
        if ( (rip = eat_path(user_path)) == NIL_INODE) return(err_code);
27046
27047
        /* Check to see if the file has maximum number of links already. */
27048
27049
        if (rip->i_nlinks >= (rip->i_sp->s_version == V1 ? CHAR_MAX : SHRT_MAX))
27050
             r = EMI_iTNK;
27051
27052
        /* Only super_user may link to directories. */
27053
        if (r == OK)
27054
             if ( (rip->i mode & I TYPE) == I DIRECTORY && !super user) r = EPERM;
27055
27056
        /* If error with 'name', return the inode. */
27057
        if (r != OK) {
27058
             put_inode(rip);
27059
              return(r);
27060
27061
27062
        /* Does the final directory of 'name2' exist? */
27063
        if (fetch_name(m_in.name2, m_in.name2_length, M1) != OK) {
27064
              put_inode(rip);
27065
              return(err code);
27066
27067
        if ( (ip = last_dir(user_path, string)) == NIL_INODE) r = err_code;
27068
27069
        /* If 'name2' exists in full (even if no space) set 'r' to error. */
```

```
Feb 25, 11 15:18
                                    book.txt
                                                                  Page 368/393
      File: Page: 1005 servers/fs/link.c
27070
       if (r == OK) {
27071
             if ( (new_ip = advance(ip, string)) == NIL_INODE) {
27072
                    r = err_code;
27073
                     if (r == ENOENT) r = OK;
27074
27075
                    put_inode(new_ip);
27076
                    r = EEXIST;
27077
27078
27079
        /* Check for links across devices. */
27080
27081
        if (r == OK)
             if (rip->i dev != ip->i dev) r = EXDEV;
27082
27083
        /* Try to link. */
27084
27085
        if (r == OK)
27086
             r = search_dir(ip, string, &rip->i_num, ENTER);
27087
27088
        /* If success, register the linking. */
27089
        if (r == OK)
27090
             rip->i_nlinks++;
27091
             rip->i_update |= CTIME;
27092
             rip->i_dirt = DIRTY;
27093
27094
        /* Done. Release both inodes. */
27095
27096
        put inode(rip);
27097
        put inode(ip);
27098
        return(r);
27099
27101
     /*_____*
                                 do_unlink
27103
      27104 PUBLIC int do_unlink()
27105
27106 /* Perform the unlink(name) or rmdir(name) system call. The code for these two
      * is almost the same. They differ only in some condition testing. Unlink()
27107
27108
      * may be used by the superuser to do dangerous things; rmdir() may not.
27109
27110
27111
        register struct inode *rip;
        struct inode *rldirp;
27112
27113
        int r;
27114
        char string[NAME MAX];
27115
27116
        /* Get the last directory in the path. */
27117
        if (fetch_name(m_in.name, m_in.name_length, M3) != OK) return(err_code);
27118
        if ( (rldirp = last_dir(user_path, string)) == NIL_INODE)
27119
             return(err_code);
27120
27121
        /* The last directory exists. Does the file also exist? */
27122
27123
        if ( (rip = advance(rldirp, string)) == NIL_INODE) r = err_code;
27124
27125
        /* If error, return inode. */
27126
        if (r != OK) {
             put_inode(rldirp);
27127
27128
             return(r);
27129
```

```
book.txt
Feb 25, 11 15:18
                                                                      Page 369/393
      File: Page: 1006 servers/fs/link.c
27130
27131
         /* Do not remove a mount point. */
         if (rip->i_num == ROOT_INODE) {
27132
27133
              put_inode(rldirp);
27134
               put_inode(rip);
27135
              return(EBUSY);
27136
27137
27138
         /* Now test if the call is allowed, separately for unlink() and rmdir(). */
27139
        if (call_nr == UNLINK) {
27140
               /* Only the su may unlink directories, but the su can unlink any dir.*/
27141
               if ( (rip->i mode & I TYPE) == I DIRECTORY && !super user) r = EPERM;
27142
               /* Don't unlink a file if it is the root of a mounted file system. */
27143
27144
               if (rip->i num == ROOT INODE) r = EBUSY;
27145
27146
               /* Actually try to unlink the file; fails if parent is mode 0 etc. */
27147
               if (r == OK) r = unlink_file(rldirp, rip, string);
27148
27149
        } else {
27150
              r = remove_dir(rldirp, rip, string); /* call is RMDIR */
27151
27152
27153
         /* If unlink was possible, it has been done, otherwise it has not. */
        put_inode(rip);
27154
27155
        put inode(rldirp);
27156
        return(r);
27157
      /*===================================
27160
                                     do rename
27161
       *_____*/
27162 PUBLIC int do_rename()
27163
27164
      /* Perform the rename(name1, name2) system call. */
27165
27166
        struct inode *old_dirp, *old_ip;
struct inode *new_dirp, *new_ip;
                                             /* ptrs to old dir, file inodes */
27167
                                             /* ptrs to new dir, file inodes */
27168
        struct inode *new_superdirp, *next_new_superdirp;
27169
        int r = OK;
                                             /* error flag; initially no error */
                                             /* TRUE iff {old|new} file is dir */
        int odir, ndir;
27170
                                             /* TRUE iff parent dirs are the same */
27171
         int same pdir;
         char old_name[NAME_MAX], new_name[NAME_MAX];
27172
27173
        ino_t numb;
27174
        int r1;
27175
27176
         /* See if 'namel' (existing file) exists. Get dir and file inodes. */
27177
         if (fetch_name(m_in.name1, m_in.name1_length, M1) != OK) return(err_code);
27178
        if ( (old_dirp = last_dir(user_path, old_name)) == NIL_INODE) return(err_code);
27179
27180
        if ( (old_ip = advance(old_dirp, old_name)) == NIL_INODE) r = err_code;
27181
27182
         /* See if 'name2' (new name) exists. Get dir and file inodes. */
        if (fetch_name(m_in.name2, m_in.name2_length, M1) != OK) r = err_code;
27183
27184
        if ( (new_dirp = last_dir(user_path, new_name)) == NIL_INODE) r = err_code;
27185
        new_ip = advance(new_dirp, new_name); /* not required to exist */
27186
27187
        if (old ip != NIL INODE)
27188
               odir = ((old_ip->i_mode & I_TYPE) == I_DIRECTORY); /* TRUE iff dir */
27189
```

```
Feb 25, 11 15:18
                                         book.txt
                                                                           Page 370/393
       File: Page: 1007 servers/fs/link.c
27190
         /* If it is ok, check for a variety of possible errors. */
27191
         if (r == OK)
               same_pdir = (old_dirp == new_dirp);
27192
27193
27194
                /* The old inode must not be a superdirectory of the new last dir. */
27195
               if (odir && !same_pdir) {
                        dup_inode(new_superdirp = new_dirp);
27196
                                                /* may hang in a file system loop */
27197
                        while (TRUE) {
                                if (new_superdirp == old_ip) {
27198
27199
                                        r = EINVAL;
27200
                                        break;
27201
27202
                                next_new_superdirp = advance(new_superdirp, dot2);
27203
                                put_inode(new_superdirp);
27204
                                if (next new superdirp == new superdirp)
27205
                                        break; /* back at system root directory */
27206
                                new_superdirp = next_new_superdirp;
                                if (new_superdirp == NIL_INODE) {
27207
27208
                                        /* Missing ".." entry. Assume the worst. */
27209
                                        r = EINVAL;
27210
                                        break;
27211
27212
27213
                       put inode(new superdirp);
27214
27215
27216
                /* The old or new name must not be . or .. */
               if (strcmp(old_name, ".")==0 | strcmp(old_name, "..")==0 | strcmp(new_name, ".")==0 | strcmp(new_name, "..")==0) r = EINVAL;
27217
27218
27219
27220
               /* Both parent directories must be on the same device. */
27221
               if (old_dirp->i_dev != new_dirp->i_dev) r = EXDEV;
27222
27223
                /* Parent dirs must be writable, searchable and on a writable device */
               if ((r1 = forbidden(old_dirp, W_BIT | X_BIT)) != OK | |
27224
27225
                    (r1 = forbidden(new_dirp, W_BIT | X_BIT)) != OK) r = r1;
27226
27227
                /* Some tests apply only if the new path exists. */
               if (new_ip == NIL_INODE) {
     /* don't rename a file with a file system mounted on it. */
27228
27229
                        if (old_ip->i_dev != old_dirp->i_dev) r = EXDEV;
27230
                        if (odir && new dirp->i nlinks >=
27231
                            (new_dirp->i_sp->s_version == V1 ? CHAR_MAX : SHRT_MAX) &&
27232
27233
                            !same_pdir && r == OK) r = EMLINK;
27234
               } else {
27235
                        if (old ip == new ip) r = SAME; /* old=new */
27236
27237
                        /* has the old file or new file a file system mounted on it? */
27238
                        if (old_ip->i_dev != new_ip->i_dev) r = EXDEV;
27239
27240
                        ndir = ((new_ip->i_mode & I_TYPE) == I_DIRECTORY); /* dir ? */
27241
                        if (odir == TRUE && ndir == FALSE) r = ENOTDIR;
                        if (odir == FALSE && ndir == TRUE) r = EISDIR;
27242
27243
27244
27245
27246
         /* If a process has another root directory than the system root, we might
          * "accidently" be moving it's working directory to a place where it's
27247
          * root directory isn't a super directory of it anymore. This can make
27248
27249
          * the function chroot useless. If chroot will be used often we should
```

```
Feb 25, 11 15:18
                                         book.txt
                                                                           Page 371/393
       File: Page: 1008 servers/fs/link.c
27250
          * probably check for it here.
27251
27252
27253
         /* The rename will probably work. Only two things can go wrong now:
 * 1. being unable to remove the new file. (when new file already exists)
27254
27255
          * 2. being unable to make the new directory entry. (new file doesn't exists)
27256
                [directory has to grow by one block and cannot because the disk
27257
                 is completely full].
27258
27259
         if (r == OK) {
               if (new_ip != NIL_INODE) {
27260
27261
                          /* There is already an entry for 'new'. Try to remove it. */
27262
                        if (odir)
27263
                                r = remove_dir(new_dirp, new_ip, new_name);
27264
27265
                                r = unlink_file(new_dirp, new_ip, new_name);
27266
27267
                /* if r is OK, the rename will succeed, while there is now an
27268
                * unused entry in the new parent directory.
27269
27270
27271
27272
         if (r == OK) {
27273
               /* If the new name will be in the same parent directory as the old one,
27274
                * first remove the old name to free an entry for the new name,
27275
                * otherwise first try to create the new name entry to make sure
                * the rename will succeed.
27276
27277
               numb = old_ip->i_num;
                                                /* inode number of old file */
27278
27279
27280
               if (same pdir) {
27281
                       r = search_dir(old_dirp, old_name, (ino_t *) 0, DELETE);
27282
                                                         /* shouldn't go wrong. */
27283
                       if (r==OK) (void) search_dir(old_dirp, new_name, &numb, ENTER);
27284
               } else {
27285
                       r = search_dir(new_dirp, new_name, &numb, ENTER);
27286
                       if (r == OK)
27287
                            (void) search_dir(old_dirp, old_name, (ino_t *) 0, DELETE);
27288
27289
         /* If r is OK, the ctime and mtime of old_dirp and new_dirp have been marked
27290
27291
          * for update in search dir.
27292
27293
27294
         if (r == OK && odir && !same pdir) {
               /* Update the .. entry in the directory (still points to old_dirp). */
27295
27296
               numb = new_dirp->i_num;
27297
               (void) unlink_file(old_ip, NIL_INODE, dot2);
27298
               if (search_dir(old_ip, dot2, &numb, ENTER) == OK) {
27299
                       /* New link created. */
27300
                       new_dirp->i_nlinks++;
27301
                       new_dirp->i_dirt = DIRTY;
27302
27303
27304
27305
         /* Release the inodes. */
         put inode(old dirp);
27306
27307
         put inode(old ip);
27308
         put_inode(new_dirp);
27309
         put inode(new ip);
```

```
Feb 25, 11 15:18
                                     book.txt
                                                                    Page 372/393
      File: Page: 1009 servers/fs/link.c
27310
        return(r == SAME ? OK : r);
27311
27313 /*=========*
27314
                                    truncate
27315
      *-----*/
27316 PUBLIC void truncate(rip)
27317 register struct inode *rip;
                                     /* pointer to inode to be truncated */
27318
       * Remove all the zones from the inode 'rip' and mark it dirty. */
27319
27320
27321
        register block t b;
27322
        zone_t z, zone_size, z1;
27323
        off_t position;
        int i, scale, file type, waspipe, single, nr indirects;
27324
27325
        struct buf *bp;
27326
        dev_t dev;
27327
27328
                                            /* check to see if file is special */
        file_type = rip->i_mode & I_TYPE;
        if (file_type == I_CHAR_SPECIAL | file_type == I_BLOCK_SPECIAL) return;
27329
        dev = rip->i_dev;
27330
                                   /* device on which inode resides */
27331
        scale = rip->i_sp->s_log_zone_size;
27332
        zone_size = (zone_t) rip->i_sp->s_block_size << scale;</pre>
27333
        nr indirects = rip->i nindirs;
27334
27335
        /* Pipes can shrink, so adjust size to make sure all zones are removed. */
        waspipe = rip->i_pipe == I_PIPE;  /* TRUE is this was a pipe */
27336
27337
        if (waspipe) rip->i_size = PIPE_SIZE(rip->i_sp->s_block_size);
27338
27339
        /* Step through the file a zone at a time, finding and freeing the zones. */
27340
        for (position = 0; position < rip->i_size; position += zone_size) {
27341
              if ( (b = read_map(rip, position)) != NO_BLOCK) {
27342
                     z = (zone_t) b >> scale;
27343
                      free_zone(dev, z);
27344
27345
27346
        /* All the data zones have been freed. Now free the indirect zones. */
27347
27348
        rip->i dirt = DIRTY;
        if (waspipe) {
27349
27350
              wipe inode(rip);
                                     /* clear out inode for pipes */
27351
                                    /* indirect slots contain file positions */
              return;
27352
27353
        single = rip->i_ndzones;
27354
        free zone(dev, rip->i zone[single]); /* single indirect zone */
        if ((z = rip->i_zone[single+1]) != NO_ZONE) {
27355
27356
              /* Free all the single indirect zones pointed to by the double. */
27357
              b = (block_t) z << scale;
27358
              bp = get_block(dev, b, NORMAL); /* get double indirect zone */
27359
              for (i = 0; i < nr_indirects; i++) {
27360
                     z1 = rd_indir(bp, i);
27361
                      free_zone(dev, z1);
27362
27363
27364
              /* Now free the double indirect zone itself. */
27365
              put_block(bp, INDIRECT_BLOCK);
27366
              free zone(dev, z);
27367
27368
27369
        /* Leave zone numbers for de(1) to recover file after an unlink(2). */
```

```
book.txt
Feb 25, 11 15:18
                                                                   Page 373/393
      File: Page: 1010 servers/fs/link.c
27370 }
27372 /*========*
27373 *
                                  remove dir
27374 *========*/
27375 PRIVATE int remove_dir(rldirp, rip, dir_name)
27376 struct inode *rldirp;
                                          /* parent directory */
                                           /* directory to be removed */
27377 struct inode *rip;
27378 char dir name[NAME MAX];
                                         /* name of directory to be removed */
27379
        /\star A directory file has to be removed. Five conditions have to met:
27380
27381
            - The file must be a directory
             - The directory must be empty (except for . and ..)
27382
             - The final component of the path must not be . or .
27383
27384
             - The directory must not be the root of a mounted file system
27385
             - The directory must not be anybody's root/working directory
27386
27387
27388
        int r;
27389
        register struct fproc *rfp;
27390
27391
        /* search_dir checks that rip is a directory too. */
        if ((r = search_dir(rip, "", (ino_t *) 0, IS_EMPTY)) != OK) return r;
27392
27393
27394
        if (strcmp(dir_name, ".") == 0 || strcmp(dir_name, "..") == 0)return(EINVAL);
        if (rip->i num == ROOT INODE) return(EBUSY); /* can't remove 'root' */
27395
27396
        for (rfp = &fproc[INIT_PROC_NR + 1]; rfp < &fproc[NR_PROCS]; rfp++)
    if (rfp->fp_workdir == rip || rfp->fp_rootdir == rip) return(EBUSY);
27397
27398
27399
                                    /* can't remove anybody's working dir */
27400
27401
         /* Actually try to unlink the file; fails if parent is mode 0 etc. */
27402
        if ((r = unlink_file(rldirp, rip, dir_name)) != OK) return r;
27403
27404
        /* Unlink . and .. from the dir. The super user can link and unlink any dir,
27405
         * so don't make too many assumptions about them.
27406
27407
        (void) unlink_file(rip, NIL_INODE, dot1);
27408
        (void) unlink_file(rip, NIL_INODE, dot2);
        return(OK);
27409
27410
27413
                                  unlink_file
27415 PRIVATE int unlink file(dirp, rip, file name)
                          /* parent directory of file */
27416 struct inode *dirp;
27417 struct inode *rip;
                                   /* inode of file, may be NIL_INODE too. */
27418 char file_name[NAME_MAX];
                                  /* name of file to be removed */
27419
27420 /* Unlink 'file_name'; rip must be the inode of 'file_name' or NIL_INODE. */
27421
27422
                                    /* inode number */
        ino_t numb;
27423
        int r;
27424
27425
        /* If rip is not NIL_INODE, it is used to get faster access to the inode. */
        if (rip == NIL INODE) {
27426
              /* Search for file in directory and try to get its inode. */
27427
27428
              err_code = search_dir(dirp, file_name, &numb, LOOK_UP);
27429
             if (err code == OK) rip = get inode(dirp->i dev, (int) numb);
```

```
Feb 25, 11 15:18
                                 book.txt
                                                             Page 374/393
      File: Page: 1011 servers/fs/link.c
             if (err_code != OK || rip == NIL_INODE) return(err_code);
27430
27431
27432
             dup_inode(rip);
                                 /* inode will be returned with put_inode */
27433
27434
27435
        r = search_dir(dirp, file_name, (ino_t *) 0, DELETE);
27436
27437
        if (r == OK) {
27438
            rip->i_nlinks--;
                                 /* entry deleted from parent's dir */
             rip->i_update |= CTIME;
27439
27440
             rip->i dirt = DIRTY;
27441
27442
        put_inode(rip);
27443
27444
       return(r);
27445
servers/fs/stadir.c
27500 /* This file contains the code for performing four system calls relating to
27501 * status and directories.
27502
      * The entry points into this file are
27503
     * do_chdir: perform the CHDIR system call
      * do_chroot: perform the CHROOT system call
27505
27506
      * do_stat: perform the STAT system call
     * do_fstat: perform the FSTAT system call
* do_fstatfs: perform the FSTATFS system call
27507
27508
27509
27510
27511 #include "fs.h"
27512 #include <sys/stat.h>
27513 #include <sys/statfs.h>
27514 #include <minix/com.h>
27515 #include "file.h"
27516 #include "fproc.h"
27517 #include "inode.h"
27518 #include "param.h"
27519 #include "super.h"
27520
27521 FORWARD _PROTOTYPE( int change, (struct inode **iip, char *name_ptr, int len));
27522 FORWARD _PROTOTYPE( int change_into, (struct inode **iip, struct inode *ip));
27523 FORWARD _PROTOTYPE( int stat_inode, (struct inode *rip, struct filp *fil_ptr,
27524
                         char *user_addr)
27525
27526 /*==========*
27527 *
                                 do_fchdir
27528
      27529 PUBLIC int do_fchdir()
27530 {
27531
             /* Change directory on already-opened fd. */
            struct filp *rfilp;
27532
27533
27534
             /* Is the file descriptor valid? */
```

```
book.txt
Feb 25, 11 15:18
                                                                Page 375/393
      File: Page: 1012 servers/fs/stadir.c
27535
             if ( (rfilp = get_filp(m_in.fd)) == NIL_FILP) return(err_code);
27536
             return change_into(&fp->fp_workdir, rfilp->filp_ino);
27537
27539 /*=======*
27540 *
                                do_chdir
27541
       27542 PUBLIC int do_chdir()
27543
      ^{\prime\star} Change directory. This function is also called by MM to simulate a chdir
27544
      * in order to do EXEC, etc. It also changes the root directory, the uids and
27545
27546
      * gids, and the umask.
27547
27548
27549
27550
       register struct fproc *rfp;
27551
27552
       if (who == PM_PROC_NR) {
27553
             rfp = &fproc[m_in.slot1];
27554
             put_inode(fp->fp_rootdir);
27555
             dup_inode(fp->fp_rootdir = rfp->fp_rootdir);
27556
             put_inode(fp->fp_workdir);
27557
             dup_inode(fp->fp_workdir = rfp->fp_workdir);
27558
27559
             /* MM uses access() to check permissions. To make this work, pretend
27560
              * that the user's real ids are the same as the user's effective ids.
27561
              * FS calls other than access() do not use the real ids, so are not
27562
              * affected.
27563
27564
             fp->fp realuid =
             fp->fp_effuid = rfp->fp_effuid;
27565
27566
             fp->fp_realgid =
27567
             fp->fp_effgid = rfp->fp_effgid;
27568
             fp->fp_umask = rfp->fp_umask;
27569
             return(OK);
27570
27571
27572
        /* Perform the chdir(name) system call. */
27573
       r = change(&fp->fp_workdir, m_in.name, m_in.name_length);
27574
       return(r);
27575
27577
     /*==============*
27578
                                do_chroot
27579
27580
      PUBLIC int do chroot()
27581
27582
     /* Perform the chroot(name) system call. */
27583
27584
       register int r;
27585
27586
       if (!super_user) return(EPERM); /* only su may chroot() */
27587
       r = change(&fp->fp_rootdir, m_in.name, m_in.name_length);
27588
       return(r);
27589
```

```
book.txt
Feb 25, 11 15:18
                                                            Page 376/393
     File: Page: 1013 servers/fs/stadir.c
27591 /*==========*
27592
                               change
27593
     *-----*/
27594 PRIVATE int change(iip, name_ptr, len)
27595 struct inode **iip;
                                /* pointer to the inode pointer for the dir */
27596 char *name_ptr;
                                /* pointer to the directory name to change to */
                                /* length of the directory name string */
27597
     int len;
27598
27599
     /* Do the actual work for chdir() and chroot(). */
27600
       struct inode *rip;
27601
27602
       /* Try to open the new directory. */
       if (fetch_name(name_ptr, len, M3) != OK) return(err_code);
27603
27604
       if ( (rip = eat_path(user_path)) == NIL_INODE) return(err_code);
       return change into(iip, rip);
27605
27606
27608 /*============*
27609
                              change_into
27611 PRIVATE int change_into(iip, rip)
27612 struct inode **iip;
                                /* pointer to the inode pointer for the dir */
                               /* this is what the inode has to become */
27613 struct inode *rip;
27614
27615
       register int r;
27616
27617
       /* It must be a directory and also be searchable. */
27618
       if ( (rip->i_mode & I_TYPE) != I_DIRECTORY)
27619
            r = ENOTDIR;
27620
27621
            r = forbidden(rip, X BIT);
                                      /* check if dir is searchable */
27622
27623
       /* If error, return inode. */
27624
       if (r != OK) {
27625
            put_inode(rip);
27626
            return(r);
27627
27628
27629
       /* Everything is OK. Make the change. */
                                /* release the old directory */
27630
       put_inode(*iip);
                                /* acquire the new one */
27631
       *iip = rip;
       return(OK);
27632
27633
27636
                                do stat
27637
      *----*
27638
     PUBLIC int do_stat()
27639
27640
     /* Perform the stat(name, buf) system call. */
27641
27642
       register struct inode *rip;
27643
       register int r;
27644
27645
       /* Both stat() and fstat() use the same routine to do the real work. That
        * routine expects an inode, so acquire it temporarily.
27646
27647
27648
       if (fetch_name(m_in.name1, m_in.name1_length, M1) != OK) return(err_code);
27649
       if ( (rip = eat_path(user_path)) == NIL_INODE) return(err_code);
27650
       r = stat inode(rip, NIL FILP, m in.name2); /* actually do the work.*/
```

```
book.txt
Feb 25, 11 15:18
                                                              Page 377/393
      File: Page: 1014 servers/fs/stadir.c
27651
       put inode(rip);
                                 /* release the inode */
27652
       return(r);
27653 }
27655 /*============*
27656 *
                               do_fstat
27657
      27658 PUBLIC int do_fstat()
27659
27660
      /* Perform the fstat(fd, buf) system call. */
27661
27662
       register struct filp *rfilp;
27663
        /* Is the file descriptor valid? */
27664
27665
       if ( (rfilp = get_filp(m_in.fd)) == NIL_FILP) return(err_code);
27666
27667
       return(stat_inode(rfilp->filp_ino, rfilp, m_in.buffer));
27668 }
27671 *
                               stat_inode
27672 *===========*/
27673 PRIVATE int stat_inode(rip, fil_ptr, user_addr)
27674 register struct inode *rip; /* pointer to inode to stat */
27675 struct filp *fil_ptr;
                                 /* filp pointer, supplied by 'fstat' */
27676 char *user addr;
                                 /* user space address where stat buf goes */
27677
27678
     /* Common code for stat and fstat system calls. */
27679
27680
       struct stat statbuf;
27681
       mode t mo;
27682
       int r, s;
27683
27684
        /* Update the atime, ctime, and mtime fields in the inode, if need be. */
27685
       if (rip->i_update) update_times(rip);
27686
27687
       /* Fill in the statbuf struct. */
27688
       mo = rip->i_mode & I_TYPE;
27689
27690
       /* true iff special */
       s = (mo == I CHAR SPECIAL | mo == I BLOCK SPECIAL);
27691
27692
27693
       statbuf.st_dev = rip->i_dev;
27694
        statbuf.st_ino = rip->i_num;
27695
       statbuf.st mode = rip->i mode;
       statbuf.st_nlink = rip->i_nlinks;
27696
27697
       statbuf.st_uid = rip->i_uid;
27698
       statbuf.st_gid = rip->i_gid;
27699
       statbuf.st_rdev = (dev_t) (s ? rip->i_zone[0] : NO_DEV);
27700
       statbuf.st_size = rip->i_size;
27701
27702
       if (rip->i_pipe == I_PIPE) {
            statbuf.st_mode &= ~I_REGULAR; /* wipe out I_REGULAR bit for pipes */
27703
            if (fil_ptr != NIL_FILP && fil_ptr->filp_mode & R_BIT)
27704
27705
                   statbuf.st_size -= fil_ptr->filp_pos;
27706
27707
27708
        statbuf.st_atime = rip->i_atime;
27709
        statbuf.st_mtime = rip->i_mtime;
27710
       statbuf.st ctime = rip->i ctime;
```

```
Feb 25, 11 15:18
                                book.txt
                                                           Page 378/393
      File: Page: 1015 servers/fs/stadir.c
27711
27712
       /* Copy the struct to user space. */
       r = sys_datacopy(FS_PROC_NR, (vir_bytes) &statbuf,
27713
27714
                   who, (vir_bytes) user_addr, (phys_bytes) sizeof(statbuf));
27715
       return(r);
27716 }
      27718
27719
                             do fstatfs
      *-----*/
27720
27721
      PUBLIC int do fstatfs()
27722
27723
       /* Perform the fstatfs(fd, buf) system call. */
27724
       struct statfs st;
27725
       register struct filp *rfilp;
27726
       int r;
27727
27728
       /* Is the file descriptor valid? */
27729
       if ( (rfilp = get_filp(m_in.fd)) == NIL_FILP) return(err_code);
27730
27731
       st.f_bsize = rfilp->filp_ino->i_sp->s_block_size;
27732
       r = sys_datacopy(FS_PROC_NR, (vir_bytes) &st,
27733
27734
                   who, (vir_bytes) m_in.buffer, (phys_bytes) sizeof(st));
27735
27736
        return(r);
27737 }
servers/fs/protect.c
27800 /* This file deals with protection in the file system. It contains the code
27801
      * for four system calls that relate to protection.
27802
27803
      * The entry points into this file are
27804
      * do_chmod: perform the CHMOD system call
         do_chown:
27805
                   perform the CHOWN system call
         do_umask: perform the UMASK system call
27806
27807
         do_access: perform the ACCESS system call
27808 * forbidden: check to see if a given access is allowed on a given inode
27809 */
27810
27811 #include "fs.h"
27812 #include <unistd.h>
27813 #include <minix/callnr.h>
27814 #include "buf.h"
27815 #include "file.h"
27816 #include "fproc.h"
27817 #include "inode.h"
27818 #include "param.h"
27819 #include "super.h"
27820
```

```
book.txt
Feb 25, 11 15:18
                                                             Page 379/393
      File: Page: 1016 servers/fs/protect.c
27821
     27822
                              do_chmod
27823
      *-----*
27824
     PUBLIC int do_chmod()
27825
27826
     /* Perform the chmod(name, mode) system call. */
27827
27828
       register struct inode *rip;
27829
       register int r;
27830
27831
        /* Temporarily open the file. */
27832
       if (fetch name(m in.name, m in.name length, M3) != OK) return(err code);
27833
       if ( (rip = eat_path(user_path)) == NIL_INODE) return(err_code);
27834
27835
       /* Only the owner or the super user may change the mode of a file.
27836
        * No one may change the mode of a file on a read-only file system.
27837
27838
       if (rip->i_uid != fp->fp_effuid && !super_user)
27839
            r = EPERM;
27840
       else
27841
            r = read_only(rip);
27842
27843
       /* If error, return inode. */
27844
       if (r != OK) {
27845
            put_inode(rip);
27846
            return(r);
27847
27848
       /* Now make the change. Clear setgid bit if file is not in caller's grp */
27849
       rip->i mode = (rip->i mode & ~ALL MODES) | (m in.mode & ALL MODES);
27850
27851
       if (!super_user && rip->i_gid != fp->fp_effgid)rip->i_mode &= ~I_SET_GID_BIT;
27852
       rip->i_update |= CTIME;
27853
       rip->i_dirt = DIRTY;
27854
27855
       put_inode(rip);
       return(OK);
27856
27857
     /*========*
27860
                               do_chown
27861
       *======*/
27862
      PUBLIC int do chown()
27863
27864
      /* Perform the chown(name, owner, group) system call. */
27865
27866
       register struct inode *rip;
27867
       register int r;
27868
27869
       /* Temporarily open the file. */
27870
       if (fetch_name(m_in.name1, m_in.name1_length, M1) != OK) return(err_code);
27871
       if ( (rip = eat_path(user_path)) == NIL_INODE) return(err_code);
27872
27873
       /* Not permitted to change the owner of a file on a read-only file sys. */
27874
       r = read only(rip);
27875
       if (r == OK) {
             /* FS is R/W. Whether call is allowed depends on ownership, etc. */
27876
27877
            if (super user) {
27878
                   /* The super user can do anything. */
                   27879
27880
            } else {
```

```
book.txt
Feb 25, 11 15:18
                                                           Page 380/393
     File: Page: 1017 servers/fs/protect.c
27881
                  /* Regular users can only change groups of their own files. */
27882
                  if (rip->i_uid != fp->fp_effuid) r = EPERM;
27883
                  if (rip->i_uid != m_in.owner) r = EPERM; /* no giving away */
27884
                  if (fp->fp_effgid != m_in.group) r = EPERM;
27885
27886
27887
       if (r == OK) {
           rip->i_gid = m_in.group;
27888
            rip->i_mode &= ~(I_SET_UID_BIT | I_SET_GID_BIT);
27889
27890
            rip->i_update |= CTIME;
27891
            rip->i dirt = DIRTY;
27892
27893
27894
       put_inode(rip);
27895
       return(r);
27896
     /*_____*
27899
                              do umask
27900
     *-----*
27901 PUBLIC int do_umask()
27902
     /* Perform the umask(co_mode) system call. */
27903
27904
      register mode t r;
27905
                               /* set 'r' to complement of old mask */
27906
       r = \sim fp - > fp umask;
       fp->fp_umask = ~(m_in.co_mode & RWX_MODES);
27907
27908
       return(r);
                               /* return complement of old mask */
27909
27912
                               do access
27913
27914 PUBLIC int do_access()
27915
27916
     /* Perform the access(name, mode) system call. */
27917
27918
       struct inode *rip;
27919
       register int r;
27920
27921
       /* First check to see if the mode is correct. */
       if ( (m_in.mode & ~(R_OK | W_OK | X_OK)) != 0 && m_in.mode != F_OK)
27922
            return(EINVAL);
27923
27924
27925
       /* Temporarily open the file whose access is to be checked. */
27926
       if (fetch_name(m_in.name, m_in.name_length, M3) != OK) return(err_code);
27927
       if ( (rip = eat_path(user_path)) == NIL_INODE) return(err_code);
27928
27929
       /* Now check the permissions. */
27930
       r = forbidden(rip, (mode_t) m_in.mode);
27931
       put_inode(rip);
27932
       return(r);
27933
27936
                               forbidden
27937
      27938
     PUBLIC int forbidden(register struct inode *rip, mode_t access_desired)
27939
27940 /* Given a pointer to an inode, 'rip', and the access desired, determine
```

```
Feb 25, 11 15:18
                                      book.txt
                                                                       Page 381/393
       File: Page: 1018 servers/fs/protect.c
27941
       * if the access is allowed, and if not why not. The routine looks up the
27942
       * caller's uid in the 'fproc' table. If access is allowed, OK is returned
27943
       * if it is forbidden, EACCES is returned.
27944
27945
27946
        register struct inode *old_rip = rip;
27947
        register struct super_block *sp;
27948
        register mode_t bits, perm_bits;
27949
        int r, shift, test uid, test gid, type;
27950
27951
        if (rip->i mount == I MOUNT) /* The inode is mounted on. */
27952
               for (sp = &super_block[1]; sp < &super_block[NR_SUPERS]; sp++)
27953
                      if (sp->s_imount == rip) {
27954
                              rip = get_inode(sp->s_dev, ROOT_INODE);
27955
                              break;
27956
                      } /* if */
27957
27958
         /* Isolate the relevant rwx bits from the mode. */
27959
        bits = rip->i_mode;
        test_uid = (call_nr == ACCESS ? fp->fp_realuid : fp->fp_effuid);
27960
27961
         test_gid = (call_nr == ACCESS ? fp->fp_realgid : fp->fp_effgid);
        if (test_uid == SU_UID) {
27962
27963
               /* Grant read and write permission. Grant search permission for
               * directories. Grant execute permission (for non-directories) if
27964
27965
                * and only if one of the 'X' bits is set.
27966
27967
              if ( (bits & I TYPE) == I DIRECTORY | |
                   bits & ((X_BIT << 6) | (X_BIT << 3) | X_BIT))
perm_bits = R_BIT | W_BIT | X_BIT;
27968
27969
27970
27971
                      perm bits = R BIT | W BIT;
27972
         } else {
27973
              if (test_uid == rip->i_uid) shift = 6;
                                                              /* owner */
27974
              else if (test_gid == rip->i_gid ) shift = 3;
                                                             /* group */
                                                              /* other */
27975
              else shift = 0;
27976
              perm_bits = (bits >> shift) & (R_BIT | W_BIT | X_BIT);
27977
27978
27979
        /* If access desired is not a subset of what is allowed, it is refused. */
27980
27981
         if ((perm bits | access desired) != perm bits) r = EACCES;
27982
27983
         /* Check to see if someone is trying to write on a file system that is
27984
          * mounted read-only.
27985
27986
        type = rip->i mode & I TYPE;
27987
        if (r == OK)
27988
              if (access_desired & W_BIT)
27989
                      r = read_only(rip);
27990
27991
        if (rip != old_rip) put_inode(rip);
27992
27993
        return(r);
27994 }
27996
                                   read only
27998
       27999 PUBLIC int read_only(ip)
28000 struct inode *ip;
                                   /* ptr to inode whose file sys is to be cked */
```

```
Feb 25, 11 15:18
                                    book.txt
                                                                  Page 382/393
       File: Page: 1019 servers/fs/protect.c
28001
28002
      /* Check to see if the file system on which the inode 'ip' resides is mounted
28003
       * read only. If so, return EROFS, else return OK.
28004
28005
28006
        register struct super_block *sp;
28007
28008
        sp = ip->i_sp;
28009
       return(sp->s_rd_only ? EROFS : OK);
28010
servers/fs/dmap.c
28100 /* This file contains the table with device <-> driver mappings. It also
28101 * contains some routines to dynamically add and/ or remove device drivers
28102 * or change mappings.
28103 */
28104
28105 #include "fs.h"
28106 #include "fproc.h"
28107 #include <string.h>
28108 #include <stdlib.h>
28109 #include <ctype.h>
28110 #include <unistd.h>
28111 #include <minix/com.h>
28112 #include "param.h"
28113
28114
      /* Some devices may or may not be there in the next table. */
28115 #define DT(enable, opcl, io, driver, flags) \
28116
       { (enable?(opcl): no_dev), (enable?(io): 0), \
28117
            (enable?(driver): 0), (flags) },
28118 #define NC(x) (NR_CTRLRS >= (x))
28119
28120 /* The order of the entries here determines the mapping between major device
28121
       * numbers and tasks. The first entry (major device 0) is not used. The
       * next entry is major device 1, etc. Character and block devices can be
28122
28123
       * intermixed at random. The ordering determines the device numbers in /dev/.
       * Note that FS knows the device number of /dev/ram/ to load the RAM disk.
28124
28125
       * Also note that the major device numbers used in /dev/ are NOT the same as
       * the process numbers of the device drivers.
28126
28127
28128 /*
28129
       Driver enabled
                         Open/Cls I/O Driver # Flags Device File
28130
28131
28132 struct dmap dmap[NR_DEVICES];
                                                          /* actual map */
28133 PRIVATE struct dmap init_dmap[] = {
28134
        DT(1, no_dev, 0,
                              0,
                                           0)
                                                          /* 0 = not used
        DT(1, gen_opcl, gen_io, MEM_PROC_NR, 0)
28135
                                                          /*1 = /dev/mem
                               0,
28136
        DT(0, no_dev, 0,
DT(0, no_dev, 0,
                                           DMAP MUTABLE)
                                                         /* 2 = /dev/fd0
                                                         /* 3 = /\text{dev/c0}
28137
                                           DMAP_MUTABLE)
                                                          /* 4 = /\text{dev/tty00}
28138
        DT(1, tty_opcl, gen_io, TTY_PROC_NR, 0)
                                                          /* 5 = /dev/tty
28139
        DT(1, ctty_opcl,ctty_io, TTY_PROC_NR, 0)
                                                         /* 6 = /dev/lp
        DT(0, no_dev, 0,
28140
                               NONE,
                                           DMAP_MUTABLE)
        DT(1, no_dev, 0,
                                           DMAP MUTABLE)
                                                         /* 7 = /\text{dev/ip}
28141
                               0.
        DT(0, no_dev, 0,
                               NONE.
                                           DMAP MUTABLE)
                                                         /* 8 = /dev/c1
28142
                                                         /* 9 = not used
28143
        DT(0, 0,
                      0,
                               0,
                                           DMAP_MUTABLE)
        DT(0, no dev, 0,
                                           DMAP MUTABLE)
                                                         /*10 = /dev/c2
```

```
book.txt
Feb 25, 11 15:18
                                                               Page 383/393
      File: Page: 1020 servers/fs/dmap.c
28145
       DT(0, 0,
                                         DMAP MUTABLE)
                                                       /*11 = not used
                     0,
                             Ο.
28146
       DT(0, no_dev,
                     Ο.
                             NONE.
                                         DMAP_MUTABLE)
                                                       /*12 = /dev/c3
                                         DMAP_MUTABLE)
28147
       DT(0, no_dev, 0,
                             NONE.
                                                       /*13 = /dev/audio */
28148
       DT(0, no_dev, 0,
                                         DMAP MUTABLE)
                                                       /*14 = /dev/mixer */
                             NONE .
                                                       /*15 = /dev/klog */
28149
       DT(1, gen_opcl, gen_io,
                             LOG_PROC_NR, 0)
28150
       DT(0, no_dev, 0,
                             NONE,
                                         DMAP MUTABLE)
                                                      /*16 = /dev/random*/
28151
       DT(0, no_dev, 0,
                             NONE,
                                         DMAP_MUTABLE)
                                                       /*17 = /dev/cmos */
28152
28153
28154
      28155
                                 do devctl
28156
      PUBLIC int do_devctl()
28157
28158
        int result;
28159
28160
28161
        switch(m_in.ctl_req) {
28162
       case DEV_MAP:
28163
           /* Try to update device mapping. */
28164
           result = map_driver(m_in.dev_nr, m_in.driver_nr, m_in.dev_style);
28165
           break;
28166
        case DEV UNMAP:
           result = ENOSYS;
28167
28168
           break;
28169
       default:
28170
           result = EINVAL;
28171
28172
       return(result);
28173
28175
     /*===================================
28176
                                map_driver
28178 PUBLIC int map_driver(major, proc_nr, style)
28179 int major;
                                 /* major number of the device */
28180 int proc_nr;
                                 /* process number of the driver */
28181 int style;
                                 /* style of the device */
28182
28183 /* Set a new device driver mapping in the dmap table. Given that correct
      * arguments are given, this only works if the entry is mutable and the
28184
28185
       * current driver is not busy.
       * Normal error codes are returned so that this function can be used from
       * a system call that tries to dynamically install a new driver.
28187
28188
28189
       struct dmap *dp;
28190
28191
        /* Get pointer to device entry in the dmap table. */
28192
        if (major >= NR_DEVICES) return(ENODEV);
28193
       dp = &dmap[major];
28194
28195
        /* See if updating the entry is allowed. */
       if (! (dp->dmap_flags & DMAP_MUTABLE)) return(EPERM);
28196
        if (dp->dmap_flags & DMAP_BUSY) return(EBUSY);
28197
28198
28199
        /* Check process number of new driver. */
28200
       if (! isokprocnr(proc_nr)) return(EINVAL);
28201
28202
        /* Try to update the entry. */
28203
        switch (style) {
28204
       case STYLE DEV:
                            dp->dmap opcl = gen opcl;
                                                        break;
```

```
book.txt
Feb 25, 11 15:18
                                                                         Page 384/393
       File: Page: 1021 servers/fs/dmap.c
                                dp->dmap_opcl = tty_opcl;
28205
         case STYLE TTY:
                                                                 break;
28206
         case STYLE_CLONE:
                                dp->dmap_opcl = clone_opcl;
                                                                 break;
28207
         default:
                                return(EINVAL);
28208
28209
         dp->dmap_io = gen_io;
28210
         dp->dmap_driver = proc_nr;
28211
         return(OK);
28212
28214
       /*-----*
28215
                                       build dmap
28216
28217 PUBLIC void build dmap()
28218
       /* Initialize the table with all device <-> driver mappings. Then, map
28219
        * the boot driver to a controller and update the dmap table to that
28220
28221
        * selection. The boot driver and the controller it handles are set at
        * the boot monitor.
28222
28223
28224
        char driver[16];
28225
         char *controller = "c##";
28226
         int nr, major = -1;
28227
         int i.s;
28228
         struct dmap *dp;
28229
28230
         /* Build table with device <-> driver mappings. */
         for (i=0; i<NR DEVICES; i++) {
28231
28232
             dp = &dmap[i];
             if (i < sizeof(init_dmap)/sizeof(struct dmap) &&</pre>
28233
                     init_dmap[i].dmap_opcl != no_dev) {
                                                                /* a preset driver */
28234
                 dp->dmap_opcl = init_dmap[i].dmap_opcl;
28235
28236
                 dp->dmap_io = init_dmap[i].dmap_io;
28237
                 dp->dmap_driver = init_dmap[i].dmap_driver;
28238
                 dp->dmap_flags = init_dmap[i].dmap_flags;
28239
             } else {
                                                                /* no default */
28240
                 dp->dmap_opcl = no_dev;
28241
                 dp->dmap_io = 0;
28242
                 dp->dmap_driver = 0;
28243
                 dp->dmap_flags = DMAP_MUTABLE;
28244
28245
28246
         /* Get settings of 'controller' and 'driver' at the boot monitor. */ if ((s = env_get_param("label", driver, sizeof(driver))) != OK)
28247
28248
             panic( FILE , "couldn't get boot monitor parameter 'driver'", s);
28249
28250
         if ((s = env_get_param("controller", controller, sizeof(controller))) != OK)
28251
             panic(__FILE__, "couldn't get boot monitor parameter 'controller'", s);
28252
28253
         /* Determine major number to map driver onto. */
         if (controller[0] == 'f' && controller[1] == 'd') {
28254
28255
             major = FLOPPY_MAJOR;
28256
28257
         else if (controller[0] == 'c' && isdigit(controller[1])) {
             if ((nr = (unsigned) atoi(&controller[1])) > NR CTRLRS)
28258
28259
                 panic(__FILE__, "monitor 'controller' maximum 'c#' is", NR_CTRLRS);
28260
             major = CTRLR(nr);
28261
28262
         else {
28263
             panic(__FILE__, "monitor 'controller' syntax is 'c#' of 'fd'", NO_NUM);
28264
```

```
book.txt
Feb 25, 11 15:18
                                                              Page 385/393
      File: Page: 1022 servers/fs/dmap.c
28265
28266
        /* Now try to set the actual mapping and report to the user. */
28267
        if ((s=map_driver(major, DRVR_PROC_NR, STYLE_DEV)) != OK)
28268
           panic(__FILE__, "map_driver failed",s);
        printf("Boot medium driver: %s driver mapped onto controller %s.\n",
28269
28270
           driver controller);
28271
servers/fs/device.c
28300\, /* When a needed block is not in the cache, it must be fetched from the disk.
28301
      * Special character files also require I/O. The routines for these are here.
28302
28303
       * The entry points in this file are:
       * dev_open:
28304
                     FS opens a device
       * dev_close: FS closes a device
28305
28306
          dev_io:
                     FS does a read or write on a device
       * dev_status: FS processes callback request alert
28307
                     generic call to a task to perform an open/close
28308
         gen opcl:
28309
                     generic call to a task to perform an I/O operation
          gen_io:
28310
          no dev:
                     open/close processing for devices that don't exist
                     perform tty-specific processing for open/close
28311
          tty opcl:
          ctty_opcl:
                     perform controlling-tty-specific processing for open/close
28312
                     perform controlling-tty-specific processing for I/O
28313
          ctty_io:
       * do_ioctl:
                     perform the IOCTL system call
28314
28315
       * do setsid: perform the SETSID system call (FS side)
28316
28317
28318 #include "fs.h"
28319 #include <fcntl.h>
28320 #include <minix/callnr.h>
28321 #include <minix/com.h>
28322 #include "file.h"
28323 #include "fproc.h"
28324 #include "inode.h"
28325 #include "param.h"
28326
28327 #define ELEMENTS(a) (sizeof(a)/sizeof((a)[0]))
28328
28329 extern int dmap_size;
28330
28331 /*===========*
28332 *
                                dev_open
28334 PUBLIC int dev_open(dev, proc, flags)
28335 dev_t dev;
                                /* device to open */
28336 int proc;
                                 /* process to open for */
28337
                                 /* mode bits and flags */
      int flags;
28338
28339
        int major, r;
28340
        struct dmap *dp;
28341
        /* Determine the major device number call the device class specific
28342
28343
         * open/close routine. (This is the only routine that must check the
28344
         * device number for being in range. All others can trust this check.)
```

```
book.txt
Feb 25, 11 15:18
                                                               Page 386/393
      File: Page: 1023 servers/fs/device.c
28345
28346
        major = (dev >> MAJOR) & BYTE;
28347
        if (major >= NR_DEVICES) major = 0;
28348
        dp = &dmap[major];
        r = (*dp->dmap_opcl)(DEV_OPEN, dev, proc, flags);
28349
28350
        if (r == SUSPEND) panic(__FILE__, "suspend on open from", dp->dmap_driver);
28351
28352
28354
      /*-----*
28355
                                  dev close
28356
28357 PUBLIC void dev_close(dev)
28358
      dev_t dev;
                                  /* device to close */
28359
28360
        (void) (*dmap[(dev >> MAJOR) & BYTE].dmap_opcl)(DEV_CLOSE, dev, 0, 0);
28361
28363
      /*_____*
28364
                                  dev_status
28365
       28366
     PUBLIC void dev_status(message *m)
28367
28368
             message st.;
28369
             int d, get_more = 1;
28370
28371
             for(d = 0; d < NR DEVICES; d++)
                    if (dmap[d].dmap_driver == m->m_source)
28372
28373
28374
28375
             if (d >= NR_DEVICES)
28376
                    return;
28377
28378
             do {
28379
                    int r;
28380
                    st.m_type = DEV_STATUS;
28381
                    if ((r=sendrec(m->m_source, &st)) != OK)
28382
                           panic(__FILE__,"couldn't sendrec for DEV_STATUS", r);
28383
28384
                    switch(st.m_type) {
                           case DEV REVIVE:
28385
28386
                                  revive(st.REP_PROC_NR, st.REP_STATUS);
28387
                                  break;
28388
                           case DEV IO READY:
28389
                                  select notified(d, st.DEV MINOR, st.DEV SEL OPS)
28390
28391
                           default:
28392
                                  printf("FS: unrecognized reply %d to DEV_STATUS
\n", st.m_type);
                                  /* Fall through. */
28393
28394
                           case DEV_NO_STATUS:
28395
                                  get more = 0;
28396
                                  break;
28397
             } while(get_more);
28398
28399
28400
             return;
28401 }
```

```
book.txt
Feb 25, 11 15:18
                                                            Page 387/393
     File: Page: 1024 servers/fs/device.c
28403 /*=============*
28404 *
                       dev_io
28406 PUBLIC int dev_io(op, dev, proc, buf, pos, bytes, flags)
28407 int op;
                 /* DEV_READ, DEV_WRITE, DEV_IOCTL, etc. */
28408 dev_t dev;
                               /* major-minor device number */
                               /* in whose address space is buf? */
28409 int proc;
28410 void *buf;
                               /* virtual address of the buffer */
                               /* byte position */
28411 off t pos;
28412 int bytes;
                                /* how many bytes to transfer */
28413 int flags;
                                /* special flags, like O NONBLOCK */
28414
28415 /* Read or write from a device. The parameter 'dev' tells which one. */
       struct dmap *dp;
28416
       message dev mess;
28417
28418
28419
       /* Determine task dmap. */
28420
       dp = &dmap[(dev >> MAJOR) & BYTE];
28421
28422
       /* Set up the message passed to task. */
       dev_mess.m_type = op;
dev mess.DEVICE = (dev >> MINOR) & BYTE;
28423
28424
28425
       dev_mess.POSITION = pos;
28426
       dev mess.PROC NR = proc;
       dev_mess.ADDRESS = buf;
28427
       dev mess.COUNT = bytes;
28428
       dev_mess.TTY_FLAGS = flags;
28429
28430
28431
       /* Call the task. */
       (*dp->dmap io)(dp->dmap driver, &dev mess);
28432
28433
28434
       /* Task has completed. See if call completed. */
28435
       if (dev_mess.REP_STATUS == SUSPEND) {
28436
            if (flags & O_NONBLOCK) {
28437
                   /* Not supposed to block. */
28438
                   dev_mess.m_type = CANCEL;
28439
                   dev_mess.PROC_NR = proc;
28440
                   dev_mess.DEVICE = (dev >> MINOR) & BYTE;
28441
                   (*dp->dmap_io)(dp->dmap_driver, &dev_mess);
28442
                   if (dev_mess.REP_STATUS == EINTR) dev_mess.REP_STATUS = EAGAIN;
28443
                   /* Suspend user. */
28444
                   suspend(dp->dmap_driver);
28445
28446
                   return(SUSPEND);
28447
28448
28449
       return(dev_mess.REP_STATUS);
28450 }
gen_opcl
28455 PUBLIC int gen_opcl(op, dev, proc, flags)
28456 int op;
                               /* operation, DEV_OPEN or DEV_CLOSE */
                                /* device to open or close */
28457 dev_t dev;
28458 int proc;
                                /* process to open/close for */
28459 int flags;
                                /* mode bits and flags */
28460
/* Called from the dmap struct in table.c on opens & closes of special files.*/
28462 struct dmap *dp;
```

```
Feb 25, 11 15:18
                                 book.txt
                                                             Page 388/393
     File: Page: 1025 servers/fs/device.c
28463
       message dev mess;
28464
28465
       /* Determine task dmap. */
28466
       dp = &dmap[(dev >> MAJOR) & BYTE];
28467
28468
       dev_mess.m_type = op;
       dev_mess.DEVICE = (dev >> MINOR) & BYTE;
28469
28470
       dev_mess.PROC_NR = proc;
28471
       dev mess.COUNT = flags;
28472
28473
       /* Call the task. */
28474
       (*dp->dmap io)(dp->dmap driver, &dev mess);
28475
28476
       return(dev_mess.REP_STATUS);
28477 }
28479 /*----*
                     tty_opcl
28481 *========*/
28482 PUBLIC int tty_opcl(op, dev, proc, flags)
                                /* operation, DEV_OPEN or DEV_CLOSE */
28484 dev_t dev;
                                /* device to open or close */
28485 int proc;
                                /* process to open/close for */
                                /* mode bits and flags */
28486 int flags;
28487
      /* This procedure is called from the dmap struct on tty open/close. */
28488
28489
28490
       int r;
28491
       register struct fproc *rfp;
28492
28493
       /* Add O NOCTTY to the flags if this process is not a session leader, or
       * if it already has a controlling tty, or if it is someone elses
28494
28495
        * controlling tty.
28496
       if (!fp->fp_sesldr || fp->fp_tty != 0) {
28497
28498
            flags |= O_NOCTTY;
28499
       } else {
28500
            for (rfp = &fproc[0]; rfp < &fproc[NR_PROCS]; rfp++) {</pre>
28501
                   if (rfp->fp_tty == dev) flags |= O_NOCTTY;
28502
28503
28504
28505
       r = gen_opcl(op, dev, proc, flags);
28506
28507
       /* Did this call make the tty the controlling tty? */
28508
       if (r == 1) {
28509
            fp->fp_tty = dev;
28510
            r = OK;
28511
28512
       return(r);
28513 }
28515 /*========*
                            ctty opcl
28517
      *=======*/
28518 PUBLIC int ctty_opcl(op, dev, proc, flags)
28519 int op; /* operation, DEV_OPEN or DEV_CLOSE */
                               /* device to open or close */
/* process to open/close for */
/* mode bits and flags */
28520 dev_t dev;
28521 int proc;
28522 int flags;
```

```
Feb 25, 11 15:18
                               book.txt
                                                         Page 389/393
     File: Page: 1026 servers/fs/device.c
28523
28524
     /* This procedure is called from the dmap struct in table.c on opening/closing
      * /dev/tty, the magic device that translates to the controlling tty.
28525
28526
28527
28528
       return(fp->fp_tty == 0 ? ENXIO : OK);
28529 }
28531
    28532
                              do_setsid
28533
      28534 PUBLIC int do setsid()
28535
     /* Perform the FS side of the SETSID call, i.e. get rid of the controlling
28536
      * terminal of a process, and make the process a session leader.
28537
28538
28539
       register struct fproc *rfp;
28540
28541
       /* Only MM may do the SETSID call directly. */
28542
       if (who != PM_PROC_NR) return(ENOSYS);
28543
28544
       /* Make the process a session leader with no controlling tty. */
28545
       rfp = &fproc[m_in.slot1];
28546
       rfp->fp_sesldr = TRUE;
28547
       rfp->fp_ty = 0;
28548
       return(OK);
28549
28551
     28552
                             do ioctl
      28553
28554
     PUBLIC int do_ioctl()
28555
28556
     /* Perform the ioctl(ls_fd, request, argx) system call (uses m2 fmt). */
28557
28558
       struct filp *f;
28559
       register struct inode *rip;
28560
       dev_t dev;
28561
       if ( (f = get_filp(m_in.ls_fd)) == NIL_FILP) return(err_code);
28562
                              /* get inode pointer */
28563
       rip = f->filp_ino;
       if ( (rip->i_mode & I_TYPE) != I_CHAR_SPECIAL
28564
            && (rip->i_mode & I_TYPE) != I_BLOCK_SPECIAL) return(ENOTTY);
28565
28566
       dev = (dev_t) rip->i_zone[0];
28567
       return(dev_io(DEV_IOCTL, dev, who, m_in.ADDRESS, OL,
28568
28569
            m_in.REQUEST, f->filp_flags));
28570 }
28572 /*========*
28573 *
                              gen io
28574
     *-----*
28575 PUBLIC void gen_io(task_nr, mess_ptr)
28576 int task nr;
                              /* which task to call */
28577 message *mess_ptr;
                              /* pointer to message for task */
28578
28579
     /* All file system I/O ultimately comes down to I/O on major/minor device
      * pairs. These lead to calls on the following routines via the dmap table.
28580
28581
28582
```

```
Feb 25, 11 15:18
                                        book.txt
                                                                         Page 390/393
       File: Page: 1027 servers/fs/device.c
28583
        int r, proc_nr;
28584
         message local_m;
28585
28586
         proc_nr = mess_ptr->PROC_NR;
28587
         if (! isokprocnr(proc_nr)) {
28588
             printf("FS: warning, got illegal process number (%d) from %d\n",
28589
                 mess_ptr->PROC_NR, mess_ptr->m_source);
28590
             return;
28591
28592
28593
         while ((r = sendrec(task_nr, mess_ptr)) == ELOCKED)
28594
               /* sendrec() failed to avoid deadlock. The task 'task nr' is
                * trying to send a REVIVE message for an earlier request.
28595
28596
                * Handle it and go try again.
28597
28598
               if ((r = receive(task nr, &local m)) != OK) {
28599
                       break;
28600
28601
               /* If we're trying to send a cancel message to a task which has just
28602
28603
                * sent a completion reply, ignore the reply and abort the cancel
28604
                * request. The caller will do the revive for the process.
28605
28606
               if (mess_ptr->m_type == CANCEL && local_m.REP_PROC_NR == proc_nr) {
28607
                       return;
28608
28609
28610
               /* Otherwise it should be a REVIVE. */
28611
               if (local_m.m_type != REVIVE) {
28612
                       printf(
28613
                        "fs: strange device reply from %d, type = %d, proc = %d (1)\n",
28614
                               local_m.m_source,
28615
                               local_m.m_type, local_m.REP_PROC_NR);
28616
                       continue;
28617
28618
28619
               revive(local_m.REP_PROC_NR, local_m.REP_STATUS);
28620
28621
28622
         /* The message received may be a reply to this call, or a REVIVE for some
28623
         * other process.
28624
28625
         for (;;)
28626
               if (r != OK) {
                       if (r == EDEADDST) return;
28627
                                                       /* give up */
                       else panic(__FILE__,"call_task: can't send/receive", r);
28628
28629
28630
28631
               /* Did the process we did the sendrec() for get a result? */
28632
               if (mess_ptr->REP_PROC_NR == proc_nr) {
28633
                       break;
28634
               } else if (mess_ptr->m_type == REVIVE)
                       /* Otherwise it should be a REVIVE. */
28635
28636
                       revive(mess_ptr->REP_PROC_NR, mess_ptr->REP_STATUS);
28637
               } else {
28638
                       printf(
28639
                       "fs: strange device reply from %d, type = %d, proc = %d (2)\n",
28640
                               mess_ptr->m_source,
28641
                               mess_ptr->m_type, mess_ptr->REP_PROC_NR);
28642
                       return;
```

```
Feb 25, 11 15:18
                              book.txt
                                                       Page 391/393
     File: Page: 1028 servers/fs/device.c
28643
28644
28645
           r = receive(task_nr, mess_ptr);
28646
28647
28649 /*----*
28650 *
                             ctty_io
     28652 PUBLIC void ctty_io(task_nr, mess_ptr)
28653 int task nr;
                             /* not used - for compatibility with dmap_t */
28654 message *mess ptr;
                             /* pointer to message for task */
28655
* is to change the message to use the controlling terminal, instead of the
28657
28658
      * major/minor pair for /dev/tty itself.
28659
28660
28661
      struct dmap *dp;
28662
28663
      if (fp->fp_tty == 0) {
28664
           /* No controlling tty present anymore, return an I/O error. */
28665
           mess_ptr->REP_STATUS = EIO;
28666
28667
           /* Substitute the controlling terminal device. */
28668
           dp = &dmap[(fp->fp_tty >> MAJOR) & BYTE];
           mess ptr->DEVICE = (fp->fp tty >> MINOR) & BYTE;
28669
           (*dp->dmap_io)(dp->dmap_driver, mess_ptr);
28670
28671
28672 }
28674 /*============*
                            no_dev
28676 *===========*/
28677 PUBLIC int no_dev(op, dev, proc, flags)
                            /* operation, DEV_OPEN or DEV_CLOSE */
28679 dev_t dev;
                             /* device to open or close */
28680 int proc;
                             /* process to open/close for */
28681 int flags;
                             /* mode bits and flags */
28682
     /* Called when opening a nonexistent device. */
28683
28684
28685
      return(ENODEV);
28686
28688 /*============*
28689 *
                             clone_opcl
28691 PUBLIC int clone_opcl(op, dev, proc, flags)
                 /* operation, DEV_OPEN or DEV_CLOSE */
28692 int op;
28693 dev_t dev;
                             /* device to open or close */
28694 int proc;
                             /* process to open/close for */
                             /* mode bits and flags */
28695 int flags;
28696
28697 \not * Some devices need special processing upon open. Such a device is "cloned",
     * i.e. on a succesful open it is replaced by a new device with a new unique
28698
     * minor device number. This new device number identifies a new object (such
28700
      * as a new network connection) that has been allocated within a task.
28701
28702
      struct dmap *dp;
```

```
Feb 25, 11 15:18
                                      book.txt
                                                                     Page 392/393
       File: Page: 1029 servers/fs/device.c
28703
         int minor;
28704
         message dev_mess;
28705
28706
         /* Determine task dmap. */
28707
         dp = &dmap[(dev >> MAJOR) & BYTE];
28708
         minor = (dev >> MINOR) & BYTE;
28709
28710
         dev_mess.m_type = op;
         dev mess.DEVICE = minor;
28711
28712
         dev_mess.PROC_NR = proc;
28713
         dev mess.COUNT = flags;
28714
28715
         /* Call the task. */
28716
         (*dp->dmap_io)(dp->dmap_driver, &dev_mess);
28717
28718
         if (op == DEV_OPEN && dev_mess.REP_STATUS >= 0) {
28719
              if (dev_mess.REP_STATUS != minor) {
28720
                      /* A new minor device number has been returned. Create a
28721
                       * temporary device file to hold it.
28722
28723
                      struct inode *ip;
28724
28725
                      /* Device number of the new device. */
                      dev = (dev & ~(BYTE << MINOR)) | (dev_mess.REP_STATUS << MINOR);</pre>
28726
28727
28728
                      ip = alloc_inode(root_dev, ALL_MODES | I_CHAR_SPECIAL);
                      if (ip == NIL_INODE) {
28729
                              /* Oops, that didn't work. Undo open. */
28730
                              (void) clone_opcl(DEV_CLOSE, dev, proc, 0);
28731
28732
                             return(err code);
28733
28734
                      ip->i_zone[0] = dev;
28735
28736
                      put_inode(fp->fp_filp[m_in.fd]->filp_ino);
28737
                      fp->fp_filp[m_in.fd]->filp_ino = ip;
28738
28739
              dev mess.REP STATUS = OK;
28740
28741
         return(dev_mess.REP_STATUS);
28742
                                   servers/fs/time.c
28800 /* This file takes care of those system calls that deal with time.
28801
      * The entry points into this file are
28802
       * do_utime:
                          perform the UTIME system call
28803
       * do_stime:
28804
                              PM informs FS about STIME system call
28805
28806
28807
       #include "fs.h"
28808 #include <minix/callnr.h>
28809 #include <minix/com.h>
```

```
Feb 25, 11 15:18
                                 book.txt
                                                             Page 393/393
     File: Page: 1030 servers/fs/time.c
28810 #include "file.h"
28811 #include "fproc.h"
28812 #include "inode.h"
28813 #include "param.h"
28814
28815 /*----*
28816
                                do utime
28818 PUBLIC int do_utime()
28819
      /* Perform the utime(name, timep) system call. */
28820
28821
28822
       register struct inode *rip;
28823
       register int len, r;
28824
28825
       /* Adjust for case of 'timep' being NULL;
28826
       * utime_strlen then holds the actual size: strlen(name)+1.
28827
28828
       len = m_in.utime_length;
28829
       if (len == 0) len = m_in.utime_strlen;
28830
28831
       /* Temporarily open the file. */
28832
       if (fetch_name(m_in.utime_file, len, M1) != OK) return(err_code);
       if ( (rip = eat_path(user_path)) == NIL_INODE) return(err_code);
28833
28834
28835
       /* Only the owner of a file or the super_user can change its time. */
28836
       r = OK;
28837
       if (rip->i_uid != fp->fp_effuid && !super_user) r = EPERM;
28838
       if (m_in.utime_length == 0 && r != OK) r = forbidden(rip, W_BIT);
28839
       if (read_only(rip) != OK) r = EROFS; /* not even su can touch if R/O */
28840
       if (r == OK) {
28841
            if (m_in.utime_length == 0)
28842
                   rip->i_atime = clock_time();
28843
                   rip->i_mtime = rip->i_atime;
            } else {
28844
28845
                   rip->i_atime = m_in.utime_actime;
28846
                   rip->i_mtime = m_in.utime_modtime;
28847
28848
            rip->i_update = CTIME; /* discard any stale ATIME and MTIME flags */
28849
            rip->i_dirt = DIRTY;
28850
28851
28852
       put_inode(rip);
28853
       return(r);
28854 }
28856 /*========*
28857 *
                                do_stime
28858 *-----*/
28859 PUBLIC int do_stime()
28860
28861
     /* Perform the stime(tp) system call. */
28862
       boottime = (long) m_in.pm_stime;
28863
       return(OK);
28864 }
```