



AN INTRODUCTION TO GAMS¹

VÉRONIQUE ROBICHAUD, JANUARY 2017

Introduction

The GAMS (*General Algebraic Modeling System*) software was originally developed by a group of economists from the World Bank to facilitate the resolution of large and complex non-linear models on personal computers. In fact, GAMS allows us to solve simultaneous non-linear equation systems, with or without the optimization of some objective functions.

The main advantages of GAMS are (i) **simplicity** of implementation, (ii) **portability and transferability** between users and systems, and (iii) **ease of technical updates** thanks to the constant inclusion of new algorithms.

The seminal GAMS system was file oriented. The program must be created in ASCII format with any usual text editor run by a DOS command.

The development of the GAMS-IDE interface in the late 1990s makes it even easier to use. GAMS-IDE works as a general text editor compatible with WINDOWS and allows us to launch and monitor the compilation and execution of typical GAMS programs. In this introduction, we will present the general structure of the GAMS program followed by a detailed illustration including a description of the output file.

Architecture of GAMS programming: input file, resolution procedure and output settings


The structure of the input GAMS Code

Typically, a computable general equilibrium (CGE) model programmed in GAMS can be broken down to three modules: data entry, model specification and resolution (see Figure 1 below).

¹ This document is an extract from "GAMS an Introduction", a pedagogical paper written by Jean-Christophe Dumont and Véronique Robichaud in 2000.

The chart gives an overall illustration of the structure of the GAMS syntax. Note that the standard GAMS keywords appear in bold.

Figure 1: Organization chart of a typical GAMS code for CGE models



It is important to note that **declaration and definition**, or assignment, must be completed for each of the elements used in the model (i.e. sets, parameters, variables and equations).

Some general rules to follow during GAMS programming:

- As a general rule, it is necessary to complete the declaration of any element before using it. In particular, sets must be declared at the very beginning of the program.
- Even if it is not always necessary, a good habit is to end every statement with a semicolon in order to avoid unexpected compilation errors.
- Capital and small letters are not distinguished in GAMS.
- Finally, the main mathematical functions are described below:

Multiplication	*	Equality in an operation	=	Logarithm	LOG(.)
Subtraction	-	Summation	SUM(set domain,	Maximum	MAX(.,.)
			element)		
Addition	+	Product	PROD(set domain,	Minimum	MIN(.,.)
			element)		
Division	1	Absolute Value	ABS(.)		
Exponent	**	Exponential	EXP(.)		

Resolution procedure and output settings

Once the GAMS code has been written in a proper manner it must be saved with the extension .gms. To run the code, you can either choose the run command in the file menu, press F9, or click on the red arrow button.

The output file created by this process has the same prefix as the initial program but has the extension **.lst**. It contains either the initial program with compilation error identification if any, or the default output settings as described below.

Output in the file 'name.lst'

- Echo print of the initial program
- Equation listing
- Column listing
- Model statistics
- Solve summary
- Results

The next two sections will illustrate the content and terminology of GAMS programming. The example is taken from an adaptation of the model AUTA presented in: Decaluwé, B., A. Martens and L. Savard (2001), "La politique économique du développement et les modèles d'équilibre général calculable. Une introduction", Montreal, Presses de l'Université de Montréal, p.524.

Writing a GAMS Program

All statements previously presented are used in a complete GAMS program and some additional options are also introduced. For further information on any of these commands, please refer to the GAMS User's Guide² available under the help menu.

Calibration of a CGE model

The first part of the modeling process consists of entering data, which will be referred to as benchmark data, and evaluating parameters consistent with these values. This process is called the *calibration*. In the case of CGE modeling, the benchmark data is usually drawn from the Social Accounting Matrix (SAM). Parameters that can be calibrated will be determined by the benchmark data.

Title option

Although not necessary, the title option allows a more comprehensible output listing. The text following the **\$TITLE** command will appear as a header on every page of the output listing. A sub-title can also be added to this header using the command **\$STITLE**.

In the example below, MODEL AUTA will appear as the first line of each page in the output file and AUTARKY WITHOUT GOVERNMENT as the beginning of the second line. The following lines are comments; GAMS will not read lines beginning with an asterisk (*). The use of comments can be useful to the modeller in order to organize his/her program in a comprehensive manner. Another way to insert comments is to put the text between the **\$ONTEXT** and **\$OFFTEXT** command.

```
$TITLE MODEL AUTA

$STITLE AUTARKY WITHOUT GOVERNMENT

* Model of a closed economy without government producing 3 goods using

* 2 factors owned by 2 types of households.
```

² GAMS — A User's Guide. Tutorial by Richard E. Rosenthal c 2006. GAMS Development Corporation, Washington, DC, USA.

Set definition

The definition of sets is useful for multidimensional variables. It corresponds to the indexes in mathematical representations of models.

```
SETS I Industries and commodities

/ AGR agriculture

MAN manufacturing

SER services /

BNS(I) Goods

/ AGR agriculture

MAN manufacturing /

H Households

/ SAL labour endowed households

CAP capital endowed households /

ALIAS (i,j)

;
```

The **SETS** statement defines the sets of the model. In this example, three sets are defined. The first one, denoted by the letter I, contains elements are AGR, MAN and SER. After each symbol (AGR, MAN and SER) a description can be added. The elements of a set are placed between slashes (/). The second set, named BNS, is in fact a subset of I, indicated by the (I) part and includes only the two first elements. The last set represents households. A final command, ALIAS, is used to allow the modeller to use a second index (J) that represents exactly the same elements as set I. This is useful when using multi-indexed variables.

Parameters definition

The parameters should now be defined. Parameters are the elements in the equations that will not change after a simulation, such as elasticity, tax rates, distribution and scale coefficients. In addition to these parameters, benchmark variables are also defined by their value at the base year and will not change after simulation. A common way to define these variables is to add an "O" after the variable name so it will not be confused with the 'true' variable. Parameter and benchmark variable definition begins with the statement **PARAMETERS** and ends with a semicolon. Once again, it is useful to include a description after the parameter designation, as in the example. When a parameter is subject to an index, such as A_{j} , the set over which it is defined is written between parentheses, A(j).

```
PARAMETERS
               Scale parameter (Cobb-Douglas - production function)
A(j)
              Coefficient (Leontief - intermediate consumption)
aij(i,j)
alpha(j)
              Elasticity (Cobb-Douglas - production function)
              Share of commodity i in type h household consumption budget
gamma(i,h)
              Coefficient (Leontief - total intermediate consumption)
io(j)
              Share of capital income received by capitalists
lambda
              Share of commodity i in total investment expenditures
mu(i)
psi(h)
              Average propensity to save of type h household
               Coefficient (Leontief - value added)
v(j)
* Definition of variables for the base year
* Volume variables (quantities)
CO(i,h)
             Consumption of commodity i by type h households
              Total intermediate consumption of industry j
CIO(j)
DIO(i,j)
             Intermediate consumption of commodity i in industry j
              Total intermediate demand for commodity i
DITO(i)
INVO(i)
              Final demand of commodity i for investment purposes
               Industry j demand for capital
KDO(j)
              Capital supply in industry j
KSO(j)
              Industry j demand for labour
LDO(j)
LSO
               Total labour supply
              Value added of industry j
VAO(i)
XSO(j)
              Output of industry j
* Prices
              Price of commodity i
PO(i)
              Intermediate consumption price index of industry j
PCIO(j)
              Price of industry j value added
PVAO(j)
RO(j)
              Rental rate of capital in industry j
WO
               Wage rate
* Nominal variables (values)
CTHO(h) Consumption budget of type h households
DIVO
              Dividends
ITO
              Total investment
SFO
              Business savings
SHO(h)
              Savings of type h households
YFO
              Business income
YHO(h)
              Income of type h households
```

Data handling

Once the sets, parameters and benchmark variables are defined, data must be entered. This can be done using the **TABLE** command, which is useful for multidimensional variables. The syntax is as follows: TABLE name(row domain, column domain) description. For example:

TABLE	SAM(*,*)	Social	accounting	matrix					
	LD	KD	SAL	CAP	F	AGR	MAN	SER	ACC
LD						300	100	200	
KD						100	150	100	
SAL	600								
CAP		210			70				
F		140							
AGR			162	21		50	150	90	27
MAN			108	84		20	150	90	173
SER			270	105		30	75	120	
ACC			60	70	70				
TOT	600	350	600	280	140	500	625	600	200
;									

The table is named SAM and has two dimensions. When the column/row labels do not refer to any specific set, an asterisk is used. Here, we have used the entire SAM but with the elements of the sets, when relevant, as the title of each column and row. This will greatly facilitate data assignment. Values can be expressed with or without decimals but must fall under only one column title. A semicolon indicates the end of the table.

When data is entered in a table, it then has to be assigned to the relevant variable. In the example, the value of CO(i,h) can be found in the table SAM at the intersection of the row named i and the column h. When referring to a row or a column that does not represent an element of a defined set, brackets are used. For example, the value of dividends (DIVO) is given in table SAM at the intersection of row 'CAP' and column 'F'.

```
Assignment of variables
             = SAM('CAP', 'F');
DIVO
              = SAM('TOT','ACC');
ITO
SFO
               = SAM('ACC', 'F');
SHO(h)
               = SAM('ACC',h);
YFO
               = SAM('TOT', 'F');
               = SAM('TOT',h);
YHO(h)
XSO(j)
               = SAM('TOT',j);
               = SAM(i,h);
CO(i,h)
DIO(i,j)
               = SAM(i,j);
INVO(i)
               = SAM(i,'ACC');
KDO(j)
               = SAM('KD',j);
LDO(j)
               = SAM('LD',j);
```

Values for variables and parameters can also be entered simply as follows. In our example, all prices are set to one.

```
* Prices
WO = 1;
RO(j) = 1;
PO(i) = 1;
```

Calculation of variables and calibration

Other variables and parameters can be calculated or calibrated from the ones entered previously. The end of each calculation is indicated by a semicolon. The sequence in which they are calculated is very important because GAMS will use the last value assigned to a variable or a parameter.

```
* Computation of variables in volume
LDO(j) = LDO(j)/WO;
              = KDO(j)/RO(j);
KDO(j)
              = XSO(j)/PO(j);
XSO(j)
CO(i,h)
             = CO(i,h)/PO(i);
INVO(i)
              = INVO(i)/PO(i);
DIO(i,j)
              = DIO(i,j)/PO(i);
* Calibration of other variables
              = SUM[i,LDO(i)];
LSO
KSO(j)
              = KDO(j);
              = LDO(j)+KDO(j);
VAO(j)
PVAO(j)
              = {WO*LDO(j)+RO(j)*KDO(j)}/VAO(j);
             = SUM[j,DIO(i,j)];
DITO(i)
             = SUM[i,DIO(i,j)];
CIO(j)
PCIO(j)
             = SUM[i,PO(i)*DIO(i,j)]/CIO(j);
              = YHO(h)-SHO(h);
CTHO(h)
* Calibration of parameters
* Production (Cobb-Douglas and Leontief)
alpha(j) = WO*LDO(j)/{PVAO(j)*VAO(j)};
              = VAO(j)/{LDO(j)**alpha(j)*KDO(j)**(1-alpha(j))};
A(j)
              = VAO(j)/XSO(j);
v(j)
io(j)
             = CIO(j)/XSO(j);
aij(i,j)
              = DIO(i,j)/CIO(j);
* Distribution parameters
gamma(i,h) = PO(i)*CO(i,h)/CTHO(h);
              = {YHO('cap')-DIVO}/SUM[j,RO(j)*KDO(j)];
lambda
              = PO(i)*INVO(i)/ITO;
mu(i)
psi(h)
              = SHO(h)/YHO(h);
```

Displaying parameters and variables

In the output listing, values of parameters are not automatically printed. Use the **DISPLAY** option to show these values. Note that the names of parameters and benchmark variables are entered without dimension.

```
* Parameters to be displayed in the output file DISPLAY A, alpha, io, v, aij, gamma, psi, mu, lambda;
```

The model

Variable declaration

All variables, endogenous or exogenous, appearing in the equations must first be declared. The statement **VARIABLES** begins this procedure and ends with a semicolon. Following the variable name, for example \mathbb{W} , a brief optional description can be added. In the example below, we have grouped the variables by category.

```
VARIABLES
* Volume variables (quantities)
C(i,h) Consumption of commodity i by type h households
              Total intermediate consumption of industry j
CI(j)
DI(i,j)
              Intermediate consumption of commodity i in industry j
DIT(i)
              Total intermediate demand for commodity i
INV(i)
              Final demand of commodity i for investment purposes
              Industry j demand for capital
KD(j)
              Capital supply in industry j
KS(j)
LD(j)
              Industry j demand for labour
              Total labour supply
LS
VA(j)
              Value added of industry j
XS(j)
              Output of industry j
* Prices
P(i)
              Price of commodity i
             Intermediate consumption price index of industry j
Price of industry j value added
PCI(j)
PVA(j)
              Rental rate of capital in industry j
R(j)
              Wage rate
* Nominal variables (values)
CTH(h) Consumption budget of type h households
DIV
              Dividends
              Total investment
IT
SF
              Business savings
SH(h)
           Savings of type h households
              Business income
YF
YH(h)
              Income of type h households
* Other variable
LEON
        Excess supply on the market for services
```

Declaration of equations

As with the previous components of the model, the equation must be declared and defined. This step begins with the **EQUATIONS** statement followed by the symbols for which a description can be added. For example, the equation named XSEQ(j) is followed by a short description. Use a semicolon to indicate the end once all equations have been declared.

Assignment of equations

The syntax for defining equations is as follows. First, the name and dimension is stated followed by two dots. Then the equation is defined, ending with a semicolon. The =E= between the left hand side and the right hand side of the equation simply means "equals to" as opposed to =G= or =L= which represent "greater than" and "less than" respectively. Each equation can only be defined once but the variables can appear in several equations and on both sides of the same equation. Here, the order in which the equations are defined does not matter as all equations are solved simultaneously.

In the example below, we have grouped equations by category using multiple **EQUATIONS** statements. Each time the **EQUATIONS** statement is used, it ends with a semi-colon.

```
+ Production
EQUATIONS
                   Value added demand in industry j (Leontief)
Total intermediate consumption demand in industry j (Leontief)
XSEQ(j)
CIEQ(j)
VAEQ(j) Cobb-Douglas between labour and capital
LDEQ(j) Demand for labour by industry j
KDEQ(j) Demand for capital by industry j
DIEQ(i,j) Intermediate consumption of commodity i by sector j
XSEQ(j).. VA(j) = e = v(j) *XS(j);
CIEQ(j)..
VAEQ(j)..
LDEQ(j)..
KDEQ(j)..
                     CI(j) =e= io(j)*XS(j);
                     VA(j) =e= A(j)*LD(j)**alpha(j)*KD(j)**(1-alpha(j));
                    W*LD(j) =e= alpha(j)*PVA(j)*VA(j);
                    R(j)*KD(j) =e= (1-alpha(j))*PVA(j)*VA(j);
DIEQ(i,j).. DI(i,j) = e = aij(i,j)*CI(j);
* Income and savings
EOUATIONS
YHSEO
                     Household income (workers)
YHCEQ
                    Household income (capitalists)
YHCEQ Household income (ca
SHEQ(h) Household h savings
CTHEQ(h) Consumption budget
YFEQ
                     Firms income
SFEQ
                     Firms savings
YHSEQ..
                    YH('sal') =e= W*SUM[j,LD(j)];
YHSEQ..

YHCEQ..

YH('cap') =e= lambda*SUI

SHEQ(h)..

SH(h) =e= psi(h)*YH(h);

CTHEQ(h)..

CTH(h) =e= YH(h)-SH(h);

YFEQ..

YF =e= (1-lambda)*SUM[j

SF =e= YF-DIV;
                    YH('cap') =e= lambda*SUM[j,R(j)*KD(j)]+DIV;
                     YF =e= (1-lambda)*SUM[j,R(j)*KD(j)];
```

```
* Demand
EQUATIONS
              Household h consumption of commodity i
CEQ(i,h)
INVEQ(i)
               Investment in commodity i
DITEQ(i)
               Intermediate demand for commodity i
CEQ(i,h)..
               P(i) *C(i,h) =e= gamma(i,h) *CTH(h);
INVEQ(i)..
               P(i)*INV(i) =e= mu(i)*IT;
               DIT(i) =e= SUM[j,DI(i,j)];
DITEQ(i)..
* Prices
EQUATIONS
PCIEQ(j)
               Intermediate consumption price index
CPEQ(j)
               Production costs for sector j
PCIEQ(j)..
             PCI(j)*CI(j) =e= SUM[i,P(i)*DI(i,j)];
CPEQ(j)..
               P(j)*XS(j) =e= PVA(j)*VA(j)+PCI(j)*CI(j);
* Equilibrium
EQUATIONS
PEQ(bns)
              Domestic absorption
WEQ
               Labour market equilibrium
REQ(j)
               Capital market equilibrium
ITEQ
               Investment-savings equilibrium
PEQ(bns). XS(bns) = e = SUM[h, C(bns, h)] + DIT(bns) + INV(bns);
WEQ..
               LS =e= SUM[j,LD(j)];
REQ(j)..
               KS(j) = e = KD(j);
               IT =e= SUM[h,SH(h)]+SF;
ITEQ..
* Other
EQUATIONS
WALRAS
               Verification of the Walras law
                LEON =e= XS('ser')-SUM(h,C('ser',h))-DIT('ser')-INV('ser');
WALRAS..
```

Initialization procedure

A value must now be assigned to all variables previously declared. In order to solve the equations, GAMS needs to start from a benchmark value. If no value is associated with a variable, GAMS will use zero, which could cause problems if the variable appears as the denominator of a division. To do so, the suffix .L (for level) is used as follows:

```
* Initialisation of variables
C.1(i,h)
             = CO(i,h);
CI.1(j)
CTH.1(h)
             = CIO(j);
             = CTHO(h);
DI.1(i,j)
             = DIO(i,j);
DIT.1(i)
             = DITO(i);
DIV.1
              = DIVO;
INV.1(i)
            = INVO(i);
IT.1
              = ITO;
KD.1(j)
KS.1(j)
             = KDO(j);
              = KSO(j);
LD.1(j)
             = LDO(j);
LS.1
              = LSO;
P.1(i)
             = PO(i);
PCI.1(j)
             = PCIO(j);
PVA.1(j)
             = PVAO(j);
R.1(j)
             = RO(j);
SF.1
              = SFO;
SH.1(h)
             = SHO(h);
             = VAO(j);
VA.1(j)
W.1
              = WO;
XS.1(j)
             = XSO(j);
YF.1
              = YFO;
YH.1(h)
              = YHO(h);
```

For the exogenous variables, the suffix .FX (for fixed) is used:

```
* Closures

* P(AGR) is the numéraire
P.fx('agr') = PO('agr');

* Capital is sector specific
KS.fx(j) = KSO(j);

* Total labour suply is fixed
LS.fx = LSO;

* Dividends are exogenous
DIV.fx = DIVO;
```

In both cases, the syntax is very similar: the name of the variable, the suffix, the variable dimension, the equal sign (=), the benchmark value defined in the calibration process, and a semicolon.

Executing the model

Finally, two lines must be added to solve the equation system. The first defines the model. It begins with the MODEL statement, followed by a name (AUTA in the example), a brief description (AUTARKY WITHOUT GOVERNMENT), the list of equations to be resolved between slashes, and end s with a semicolon. When all equations are to be solved, use the keyword ALL instead of the complete list of equations.

The second line defines the procedure to be used to resolve the model. The **SOLVE** statement is followed by the name of the model, **USING** and the procedure to be used to resolve the model. The procedure to be used is determined by the type of model to be solved. For example, linear programs can be solved using the **LP** procedure, while non-linear programs can be solved using **NLP**. Each procedure uses a different solver (MINOS, CONOPT, MILES, ...). These solvers use different algorithms as some are efficient for resolving certain systems but less efficient in other cases. In our example, the **CNS** (Constrained non-linear system) procedure is used.

```
MODEL AUTA Autarky without government /ALL/;
SOLVE AUTA USING CNS;
```

Reading a GAMS output file

Once GAMS has solved an equation system, it creates an output file. This section describes the output file of the program presented in the previous section.

Echo print

The first part of the output file is simply the reproduction of the model with line numbers on the left hand side for further reference in the file. If there are errors in the program, this is the only part of the output that will appear. For example, there is a parenthesis missing at the end of the calculation of the parameter alpha. In the echo print of the initial program, GAMS will put four asterisks (****) below the line where a mistake has been detected followed by a dollar sign (\$) and a number corresponding to a specific error.

```
136 alpha(i) = WO*LDO(i)/{PVAO(i)*VAO(i); $8
```

Because of this error, GAMS was unable to solve the model, as such, another error is indicated on the last line of the program.

```
306 SOLVE AUTA USING CNS;
**** $257
```

A description of the error code is given at the end of the program's echo print to facilitate correction:

```
Error Messages
8 ')' expected
257 Solve statement not checked because of previous errors
```

When no errors are encountered, the following information also appears in the listing.

Displayed parameters

In the calibration process, the **DISPLAY** statement was used to print the value of some parameters in the output file. These values appear after the echo print as follow:

```
---- 153 PARAMETER A Scale parameter (Cobb-Douglas - production function)

AGR 1.755, MAN 1.960, SER 1.890

---- 153 PARAMETER alpha Elasticity (Cobb-Douglas - production function)

AGR 0.750, MAN 0.400, SER 0.667
```

Equation listing

This section presents, for each equation, the specific instance of the model that is created when actual values of the sets and parameters are used. At the end of the equation, the value of the left hand side is written between parenthesis (LHS= " "). When the value of the left hand side differs from the one on the right hand side, GAMS add four asterisks (****). This can be useful for finding problems linked to incorrect parameter calibration or improper initialization of the variable.

```
---- XSEQ =E= Value added demand in industry j (Leontief)

XSEQ(AGR).. VA(AGR) - 0.8*XS(AGR) =E= 0 ; (LHS = 0)

XSEQ(MAN).. VA(MAN) - 0.4*XS(MAN) =E= 0 ; (LHS = 0)

XSEQ(SER).. VA(SER) - 0.5*XS(SER) =E= 0 ; (LHS = 0)
```

Column listing

Following the equation listing, GAMS prints the equivalent information by column instead of by row. For each variable, the lower and upper bounds, the level calculated by the solver, and the value of the coefficient affecting the actual variable in each equation are given. If the coefficient is non-linear, it is put between parentheses. In the example below, consumption (noted C) has no lower bounds (thus -INF for minus infinity), no upper bounds (+INF) and the levels of initialization are 162, 21 and 108. The variable appears in two equations, CEQ(I,H) and PEQ(I).

```
---- C Consumption of commodity i by type h households
C(AGR, SAL)
                 (.LO, .L, .UP, .M = -INF, 162, +INF, 0)
                 CEQ (AGR, SAL)
        1
                 PEQ (AGR)
C (AGR, CAP)
                 (.LO, .L, .UP, .M = -INF, 21, +INF, 0)
        1
                 CEQ (AGR, CAP)
                 PEQ (AGR)
       -1
C (MAN, SAL)
                 (.LO, .L, .UP, .M = -INF, 108, +INF, 0)
       (1)
                 CEQ (MAN, SAL)
       -1
                 PEQ (MAN)
```

Model statistics

The purpose of this section is to provide information on the size and non-linearity of the model. The BLOCK gives the number of equations and variables in the model, 22 and 21 in our example respectively, while SINGLE gives the number of rows and columns generated by the solver, 58 and 58 in this case. The NON-ZERO ELEMENTS count refers to the number of non-zero coefficients. The four remaining entries provide information about the non-linearity of the model. Finally, this section indicates the time used to generate the model (GENERATION TIME).

MODEL STATISTICS								
BLOCKS OF EQUATIONS		22	SINGLE EQUA	ATION	IS		58	
BLOCKS OF VARIABLES		21	SINGLE VARI	ABLE	S		58	
NON ZERO ELEMENTS		193	NON LINEAR	N-Z			92	
DERIVATIVE POOL		20	CONSTANT PO	OOL			24	
CODE LENGTH		195						
FIXED EQUATIONS		58	FREE VARIA	BLES			58	
GENERATION TIME	=	0.000E+0000	SECONDS	4	MB	24.6.1	r55820	WEX-WEI

Solve Summary

While the previous sections explained the solving process, this section concerns the solution itself. The first topic on this matter is the solve summary. It recalls the name of the model (here AUTA), the type of model (CNS) and the solver used (CONOPT). The SOLVER STATUS indicates the way the solver terminated. If the resolution has been interrupted by the user or by the solver (because of errors) this is where it will be indicated. In our example, the solver terminated in a normal way, which is indicated by 1 NORMAL COMPLETION. While the SOLVER STATUS refers to the resolution process, the MODEL STATUS refers to the solution itself. The code "16 Solved" indicates a solution was found for the equation system.

```
SOLVE SUMMARY

MODEL AUTA
TYPE CNS
SOLVER CONOPT FROM LINE 334

**** SOLVER STATUS 1 Normal Completion
**** MODEL STATUS 16 Solved
```

Solution Listing

In this section, GAMS lists the solution found by the solver row-by-row then column-by-column. For each equation and each variable, it indicates the lower and upper bounds and the level. While the bounds are defined by the modeller, the level is calculated by the solver. A dot "." means zero. Here is an example of the equation list:

```
---- EQU XSEQ Value added demand in industry j (Leontief)

LOWER LEVEL UPPER

AGR . . .

MAN . . .

SER . . .
```

And an example of the variable listing:

	VAR	С	Consum	ption	of	commodity	i	bу	type	h	households
			LOWER	LEV	ÆL.	UPPER					
AGR.	SAL		-INF	162	.000	+INF					
AGR.	CAP		-INF	21.	.000	+INF					
MAN.	SAL		-INF	108	.000	+INF					
MAN.	CAP		-INF	84.	.000	+INF					
SER.	SAL		-INF	270.	.000	+INF					
SER.	CAP		-INF	105	.000	+INF					