7.5 Type Definitions

In Section 5.2, we used the #define directive to create a macro that could be used as a Boolean type:

```
#define BOOL int
```



There's a better way to set up a Boolean type, though, using a feature known as a type definition:

```
typedef int Bool;
```

Notice that the name of the type being defined comes *last*. Note also that I've capitalized the word Bool. Capitalizing the first letter of a type name isn't required; it's just a convention that some C programmers employ.

Using typedef to define Bool causes the compiler to add Bool to the list of type names that it recognizes. Bool can now be used in the same way as the built-in type names—in variable declarations, cast expressions, and elsewhere. For example, we might use Bool to declare variables:

```
Bool flag; /* same as int flag; */
```

The compiler treats Bool as a synonym for int; thus, flag is really nothing more than an ordinary int variable.

Advantages of Type Definitions

Type definitions can make a program more understandable (assuming that the programmer has been careful to choose meaningful type names). For example, suppose that the variables cash_in and cash_out will be used to store dollar amounts. Declaring Dollars as

```
typedef float Dollars;
and then writing
Dollars cash_in, cash_out;
is more informative than just writing
float cash_in, cash_out;
```

Type definitions can also make a program easier to modify. If we later decide that Dollars should really be defined as double, all we need do is change the type definition:

```
typedef double Dollars;
```