

Figure 1: Two oriented particles A and B having position vectors  $\vec{x}$  and  $\vec{y}$ , respectively, with respect to origin O. Their orientations are unit vectors  $\hat{p}$  and  $\hat{q}$ , respectively.

#### 1 Introduction

We will make use of system of particles which have six degrees of freedom per particle. Three degrees of freedom are associated with the position of the particle in space and the remaining three degrees of freedom are associated with the orientation of the particle in space. The energy of such particle systems will be calculated using the work of Szeliski and Tonnesen [2]. We will use rotation vectors to store the orientation of the particles as described in a document by Diebel [1]. A rotation vector represents a 3D rotation about an arbitrary axis passing through the origin. The magnitude of the rotation vector represents the angle of rotation and its direction is the unit vector along the axis.

Consider two oriented particles A and B as shown in Figure 1. Their position vectors are  $\vec{x}$  and  $\vec{y}$  respectively. Their orientations are represented by unit vectors  $\hat{p}$  and  $\hat{q}$ , respectively. The orientations unit vectors are themselves functions of rotation vectors  $\vec{u}$  and  $\vec{v}$  respectively. Let

$$\vec{r} = \vec{y} - \vec{x}$$
 $r = ||r||$ 

The energy of oriented particle systems (OPS) is calculated as

$$E = \alpha_M \phi_M(r) + \psi(r) \left( \alpha_N \phi_N(\hat{\boldsymbol{p}}, \hat{\boldsymbol{q}}, r) + \alpha_C \phi_C(\hat{\boldsymbol{p}}, \hat{\boldsymbol{q}}, r) \right). \tag{1}$$

 $\phi_M$  is the Morse potential with parameters  $D_e$ , a and  $r_e$ 

$$\phi_M = D_e \left( e^{-2a(r_e - r)} - 2e^{-a(r_e - r)} \right). \tag{2}$$

The co-normality potential,  $\phi_N$ , is

$$\phi_N = ||\hat{\boldsymbol{p}} - \hat{\boldsymbol{q}}||^2. \tag{3}$$

The co-circularity potential,  $\phi_C$ , is

$$\phi_C = ((\hat{\boldsymbol{p}} + \hat{\boldsymbol{q}}) \cdot \boldsymbol{r})^2. \tag{4}$$

The kernel function  $\psi$  with parameter b is

$$\psi(r) = Ke^{-\frac{r^2}{2b^2}}. (5)$$

Therefore, if  $x_j$  and  $y_j$  are the components of  $\vec{x}$  and  $\vec{y}$  respectively then

$$\frac{\partial \psi}{\partial x_j} = \frac{Kr_j}{b^2} e^{-(r^2/2b^2)} \tag{6}$$

$$\frac{\partial \psi}{\partial y_i} = -\frac{Kr_j}{b^2} e^{-(r^2/2b^2)} \tag{7}$$

### 2 Derivatives of Morse Potential

Taking derivatives of equation 2 with respect to  $x_j$  and  $y_j$  we get

$$\frac{\partial \phi_M}{\partial x_j} = \frac{2D_e a r_j}{r} \left( e^{-a(r_e - r)} - e^{-2a(r_e - r)} \right) \tag{8}$$

$$\frac{\partial \phi_M}{\partial y_i} = -\frac{2D_e a r_j}{r} \left( e^{-a(r_e - r)} - e^{-2a(r_e - r)} \right). \tag{9}$$

#### 3 Derivatives of Orientations

The orientations  $\hat{\boldsymbol{p}}$  and  $\hat{\boldsymbol{q}}$  can be obtained by rotating the global z-axis  $\hat{\boldsymbol{e}_z}$  by rotation vectors  $\vec{\boldsymbol{u}}$  and  $\vec{\boldsymbol{v}}$  respectively. Let  $u_i$  and  $v_i$  (with i=0,1,2) represent components of the rotation vector and

$$u = ||\vec{\boldsymbol{u}}||$$
$$v = ||\vec{\boldsymbol{v}}||.$$

The angle of rotations are then given by

$$\alpha = \frac{u}{2}$$
$$\beta = \frac{v}{2}.$$

The components of  $\hat{\boldsymbol{p}}$  are

$$p_0 = \frac{2\sin\alpha}{u^2} \left( u_1 u \cos\alpha + u_0 u_2 \sin\alpha \right) \tag{10}$$

$$p_1 = \frac{2\sin\alpha}{u^2} \left( u_1 u_2 \cos\alpha - u_0 u \sin\alpha \right) \tag{11}$$

$$p_2 = \cos^2 \alpha + \frac{\sin^2 \alpha}{u^2} \left( u_2^2 - u_1^2 - u_0^2 \right). \tag{12}$$

While calculating derivatives of  $\hat{p}$  and  $\hat{q}$  with respect to components of  $\vec{u}$  and  $\vec{v}$ , care must be taken that  $\alpha$  and  $\beta$  are also functions of the components of  $\vec{u}$  and  $\vec{v}$ , respectively.

The derivatives of components of  $\hat{p}$  with respect to components of  $\vec{u}$  are

$$\frac{\partial p_0}{\partial u_0} = \frac{2}{u^2} \left( -\frac{u_0 u_1}{2} \sin(\alpha) + u_2 \sin(\alpha) + \frac{u_0^2 u_2}{2u} \cos(\alpha) + \frac{u_0 u_1}{u} \cos(\alpha) \right) \sin(\alpha) 
+ \frac{u_0}{u^3} \left( u u_1 \cos(\alpha) + u_0 u_2 \sin(\alpha) \right) \cos(\alpha) - \frac{4u_0}{u^4} \left( u u_1 \cos(\alpha) + u_0 u_2 \sin(\alpha) \right) \sin(\alpha) 
\frac{\partial p_1}{\partial u_0} = \frac{2}{u^2} \left( u \sin(\alpha) + \frac{u_0^2}{2} \cos(\alpha) + \frac{u_0^2}{u} \sin(\alpha) - \frac{u_0 u_1 u_2}{2u} \sin(\alpha) \right) \sin(\alpha) 
+ \frac{u_0}{u^3} \left( u u_0 \sin(\alpha) + u_1 u_2 \cos(\alpha) \right) \cos(\alpha) - \frac{4u_0}{u^4} \left( u u_0 \sin(\alpha) + u_1 u_2 \cos(\alpha) \right) \sin(\alpha)$$
(13a)

$$\frac{\partial p_2}{\partial u_0} = -\frac{u_0}{u} \sin(\alpha) \cos(\alpha) - \frac{2u_0}{u^2} \sin^2(\alpha) + \frac{u_0}{u^3} \left( -u_0^2 - u_1^2 + u_2^2 \right) \sin(\alpha) \cos(\alpha) - \frac{2u_0}{u^4} \left( -u_0^2 - u_1^2 + u_2^2 \right) \sin^2(\alpha) \tag{13c}$$

$$\frac{\partial p_0}{\partial u_1} = \frac{2}{u^2} \left( u \cos\left(\alpha\right) - \frac{u_1^2}{2} \sin\left(\alpha\right) + \frac{u_0 u_1 u_2}{2u} \cos\left(\alpha\right) + \frac{u_1^2}{u} \cos\left(\alpha\right) \right) \sin\left(\alpha\right) \\
+ \frac{u_1}{u^3} \left( u u_1 \cos\left(\alpha\right) + u_0 u_2 \sin\left(\alpha\right) \right) \cos\left(\alpha\right) - \frac{4u_1}{u^4} \left( u u_1 \cos\left(\alpha\right) + u_0 u_2 \sin\left(\alpha\right) \right) \sin\left(\alpha\right) \tag{14a}$$

$$\frac{\partial p_1}{\partial u_1} = \frac{2}{u^2} \left( \frac{u_0 u_1}{2} \cos(\alpha) + u_2 \cos(\alpha) + \frac{u_0 u_1}{u} \sin(\alpha) - \frac{u_1^2 u_2}{2u} \sin(\alpha) \right) \sin(\alpha) 
+ \frac{u_1}{u^3} \left( u u_0 \sin(\alpha) + u_1 u_2 \cos(\alpha) \right) \cos(\alpha) - \frac{4u_1}{u^4} \left( u u_0 \sin(\alpha) + u_1 u_2 \cos(\alpha) \right) \sin(\alpha)$$
(14b)

$$\frac{\partial p_2}{\partial u_1} = -\frac{u_1}{u} \sin(\alpha) \cos(\alpha) - \frac{2u_1}{u^2} \sin^2(\alpha) + \frac{u_1}{u^3} \left( -u_0^2 - u_1^2 + u_2^2 \right) \sin(\alpha) \cos(\alpha) 
- \frac{2u_1}{u^4} \left( -u_0^2 - u_1^2 + u_2^2 \right) \sin^2(\alpha)$$
(14c)

$$\frac{\partial p_0}{\partial u_2} = \frac{2}{u^2} \left( u_0 \sin\left(\alpha\right) - \frac{u_1 u_2}{2} \sin\left(\alpha\right) + \frac{u_0 u_2^2}{2u} \cos\left(\alpha\right) + \frac{u_1 u_2}{u} \cos\left(\alpha\right) \right) \sin\left(\alpha\right) \\
+ \frac{u_2}{u^3} \left( u u_1 \cos\left(\alpha\right) + u_0 u_2 \sin\left(\alpha\right) \right) \cos\left(\alpha\right) - \frac{4u_2}{u^4} \left( u u_1 \cos\left(\alpha\right) + u_0 u_2 \sin\left(\alpha\right) \right) \sin\left(\alpha\right) \tag{15a}$$

$$\frac{\partial p_1}{\partial u_2} = \frac{2}{u^2} \left( \frac{u_0 u_2}{2} \cos(\alpha) + u_1 \cos(\alpha) + \frac{u_0 u_2}{u} \sin(\alpha) - \frac{u_1 u_2^2}{2u} \sin(\alpha) \right) \sin(\alpha) 
+ \frac{u_2}{u^3} \left( u u_0 \sin(\alpha) + u_1 u_2 \cos(\alpha) \right) \cos(\alpha) - \frac{4u_2}{u^4} \left( u u_0 \sin(\alpha) + u_1 u_2 \cos(\alpha) \right) \sin(\alpha)$$
(15b)

$$\frac{\partial p_2}{\partial u_2} = -\frac{u_2}{u} \sin(\alpha) \cos(\alpha) + \frac{2u_2}{u^2} \sin^2(\alpha) + \frac{u_2}{u^3} \left( -u_0^2 - u_1^2 + u_2^2 \right) \sin(\alpha) \cos(\alpha) 
- \frac{2u_2}{u^4} \left( -u_0^2 - u_1^2 + u_2^2 \right) \sin^2(\alpha)$$
(15c)

Similarly, the derivatives of  $\hat{q}$  with respect to components of  $\vec{v}$  can be calculated. Let's denote the derivatives of components of orientations with respect to components of rotation vectors as

$$M_{ij} = \frac{\partial p_j}{\partial u_i} \tag{16}$$

$$N_{ij} = \frac{\partial q_j}{\partial v_i},\tag{17}$$

where i, j = 0, 1, 2.

## 4 Derivatives of Co-Normality Potential

We can write the co-normality potential (equation 3) as

$$\phi_N = p_i p_i + q_i q_i - 2p_i q_i,$$

where i = 0, 1, 2 and summation is implied over repeated indices. Therefore, differentiating with respect to  $p_j$  and  $q_j$  gives,

$$\frac{\partial \phi_N}{\partial p_j} = 2\left(p_j - q_j\right) \tag{18}$$

$$\frac{\partial \phi_N}{\partial q_i} = -2\left(p_j - q_j\right) \tag{19}$$

Therefore, derivatives of  $\phi_N$  with respect to  $u_i$  and  $v_i$  are

$$\frac{\partial \phi_N}{\partial u_i} = \frac{\partial \phi_N}{\partial p_i} \frac{\partial p_j}{\partial u_i} \tag{20}$$

$$\frac{\partial \phi_N}{\partial v_i} = \frac{\partial \phi_N}{\partial q_j} \frac{\partial q_j}{\partial v_i} \tag{21}$$

If we let  $m_j = p_j - q_j$  then we can write the above equations concisely as,

$$\frac{\partial \phi_N}{\partial u_i} = 2M_{ij}m_j \tag{22}$$

$$\frac{\partial \phi_N}{\partial v_i} = -2N_{ij}m_j \tag{23}$$

### 5 Derivatives of Co-circularity Potential

If we let

$$n_i = p_i + q_i$$
$$r_i = y_i - x_i,$$

then we can write the co-circularity potential (equation 4) as

$$\phi_c = \left(\frac{n_i r_i}{r}\right)^2$$

Differentiating with respect to  $x_i$  and  $y_i$ , we get

$$\frac{\partial \phi_C}{\partial x_j} = \frac{2n_i r_i}{r^4} \left( (n_i r_i) r_j - r^2 n_j \right) \tag{24}$$

$$\frac{\partial \phi_C}{\partial y_j} = \frac{2n_i r_i}{r^4} \left( r^2 n_j - (n_i r_i) r_j \right) \tag{25}$$

To differentiate  $\phi_C$  with respect to  $p_k$  and  $q_k$  we can write it as

$$\phi_C = \left(\frac{(p_i + q_i) \, r_i}{r}\right)^2$$

Therefore, we get

$$\frac{\partial \phi_C}{\partial p_k} = \frac{\partial \phi_C}{\partial q_k} = \frac{2n_i r_i}{r^2} r_k \tag{26}$$

We can use chain rule to differentiate  $\phi_C$  with respect to  $u_i$  and  $v_i$ .

$$\frac{\partial \phi_C}{\partial u_i} = \frac{\partial \phi_C}{\partial p_k} \frac{\partial p_k}{\partial u_i} = \frac{2n_j r_j}{r^2} M_{ik} r_k \tag{27}$$

$$\frac{\partial \phi_C}{\partial v_i} = \frac{\partial \phi_C}{\partial q_k} \frac{\partial q_k}{\partial v_i} = \frac{2n_j r_j}{r^2} N_{ik} r_k \tag{28}$$

# 6 Derivatives of Total Energy

The most crucial part of the code implementation is to calculate the matrices  $M_{ij}$  and  $N_{ij}$  carefully.

$$\frac{\partial E}{\partial x_j} = \alpha_M \frac{\partial \phi_M}{\partial x_j} + \psi(r) \left( \alpha_C \frac{\partial \phi_C}{\partial x_j} \right) + \frac{\partial \psi}{\partial x_j} \left( \alpha_N \phi_N + \alpha_C \phi_C \right)$$
 (29)

$$\frac{\partial E}{\partial y_j} = \alpha_M \frac{\partial \phi_M}{\partial y_j} + \psi(r) \left( \alpha_C \frac{\partial \phi_C}{\partial y_j} \right) + \frac{\partial \psi}{\partial y_j} \left( \alpha_N \phi_N + \alpha_C \phi_C \right)$$
 (30)

$$\frac{\partial E}{\partial u_j} = \psi(r) \left( \alpha_N \frac{\partial \phi_N}{\partial u_j} + \alpha_C \frac{\partial \phi_C}{\partial u_j} \right)$$
(31)

$$\frac{\partial E}{\partial v_j} = \psi(r) \left( \alpha_N \frac{\partial \phi_N}{\partial v_j} + \alpha_C \frac{\partial \phi_C}{\partial v_j} \right)$$
(32)

## References

- [1] James Diebel. Representing attitude: Euler angles, unit quaternions, and rotation vectors. Matrix, 58:1–35, 2006.
- [2] Richard Szeliski and David Tonnesen. Surface Modeling with Oriented Particle Systems. Sig-graph '92, 26(2):160, 1992.