





PHSA-CC-1-1-P: Mathematical Physics I

Instructor: Amit Kumar Bhattacharjee (AKB)

Course Webpage: https://amitbny.github.io/akb.github.io/scomphsa.html


Course timeline: Jul-Nov, 2018

Evaluation: Assignments/Classtest followed by Semester examination

Ebook resources: National digital library: https://ndl.iitkgp.ac.in http://nlist.inflibnet.ac.in



Way to access the webpage









Course Marks: TBD; Credits - 2

- Introduction and overview

 Computer architecture and organization, memory and Input/output devices.
- Basics of scientific computing → Binary and decimal arithmetic, Floating point numbers, algorithms, Sequence, Selection and Repetition, single and double precision arithmetic, underflow & overflow importance of making equations in terms of dimensionless variables, Iterative methods.








History of Computer Invented by Dr. C. Babbage, a Mathematics Professor in 19th century.

- 1st Generation (1937 1946) Dr. J.V. Atanasoff & C. Berry "Atanasoff Berry Computer" (ABC) \rightarrow Collosus-1943 (first computer for millitary) \rightarrow Electronic Numerical Integrator & Computer (ENIAC)-1946 (28k Kg weight, 18k vaccum tubes, single task machine without OS).
- 2nd Generation (1947 1962) Universal Automatic Computer (UNIVAC1)-1951 for public using Registers → International Business Machine (IBM) 650/700 (memory & OS).
- 3rd Generation (1963) MicroSoft Disk Operating System (MS-DOS)-1981, IBM introduced Personal Computer (PC) using Inegrated Circuit (IC) \rightarrow Apple Introduced Macintosh \rightarrow Windows in 1990.

Hardware

What is a Computer?

A computer is a device that can be instructed to carry out sequences of arithmetic or logical set of operations automatically via computer programming.



Hardware

What is a Computer?

A computer is a device that can be instructed to carry out sequences of arithmetic or logical set of operations automatically via computer programming.



Hardware

What is a Computer?

CPU consists of Arithmetic Logic Unit (ALU), Memory, Input/Output (I/O)









HDD

RAM

Graphics Card

& other components, like motherboard, heat-sink, power supply, Fan etc.

HDD (data-storage) is the secondary memory while RAM (volatile memory) is the primary memory. Graphics card is necessary for data-heavy applications.

AKB

ALU, Memory, I/O


- ALU performs 2 class of operations (arithmetic & logic), e.g. +, -, *, /, sin(), sqrt() etc. Some machines can operate only on whole numbers (integers), while others use floating point (real) numbers, but with limited precision. Also Boolean logic operations (AND, OR, NOT, XOR) are performed in ALU.
- Memory cell can store binary numbers in groups of 8 bits (or 1 byte). Each byte represents 256 different numbers ($2^8 = 256$): $\mathbb{R} \in [0,255], [-128,127]$. CPU contains memory cells (Registers) which are read/written more rapidly than RAM.
- I/O is the way a CPU exchanges information with the outside world, through Peripherals e.g. keyboard, mouse etc (input devices) & display, printer etc (output devices). HDD, optical disk drives, computer networking serve as both input and output devices.

Software

What is a Computer?

Computer Programs, libraries, Operating Systems (OS) etc. OS has many Variant: (i) Unix distro (Solaris Sun OS), IRIX etc,

(ii) GNU/Linux [CentOS, Fedora (Redhat), SUSE, Ubuntu/Mint]



What is a Computer?

Computer Programs, libraries, Operating Systems (OS) etc. OS has many Variant: (i) Unix distro (Solaris Sun OS), IRIX etc, (ii) GNU/Linux [CentOS, Fedora (Redhat), SUSE, Ubuntu/Mint]

Library: (i) Multimedia [DirectX, OpenGL, OpenAL, Vulkan (API)] (ii) Programming Library (GSL, NRCP etc)

Data: (i) Protocol (TCP/IP, FTP, HTTP, SMTP etc), (ii) File format (HTML, XML, JPEG, MPEG, PNG etc)

User Interface: GUI

Application Software: Office-suite, Graphics, Audio, Games, Software Engineering (Compiler, Assembler, Interpreter, Debugger, Text editor etc).

What is a Computer?

Programming Languages: (i) Low-level (e.g. Assembly language),
(ii) High-level (e.g. Basic, C/C++, Fortran 90/95

Java, Pascal),
(iii) Scripting (Python, Ruby, Perl).

Mathematical Softwares:

(i) Coding: LAPACK, LINPACK.

(ii) Coding/Visualization/Post-processing: Mathematica, Matlab/Octave, Maple.

(iii) Visualization: OpendX, Ovito, Paraview, VisIt, PyMol.

(iv) Supercomputing: LAMMPS, BoxLib, PETSc, Sundials.



Scientific Computing

17 Equations That Changed the World by Ian Stewart



$$a^2 + b^2 = c^2$$

Pythagoras, 530 BC

$$\log xy = \log x + \log y$$

John Napier, 1610

$$\frac{\mathrm{d}f}{\mathrm{d}t} = \lim_{h \to 0} = \frac{f(t+h) - f(t)}{h}$$

Newton, 1668

$$F = G \frac{m_1 m_2}{r^2}$$

Newton, 1687

The Square Root of Minus One

$$i^2 = -1$$

Euler, 1750

Euler's Formula for Polyhedra

$$V-E+F=2$$

Euler, 1751

$$\Phi(x) = \frac{1}{\sqrt{2\pi\rho}}e^{\frac{(x-\mu)^2}{2\rho^2}}$$

C.F. Gauss, 1810

$$\frac{\partial^2 u}{\partial t^2} = c^2 \frac{\partial^2 u}{\partial x^2}$$

J. d'Almbert, 1746

$$f(\omega) = \int_{-\infty}^{\infty} f(x)e^{-2\pi ix\omega} dx$$

J. Fourier, 1822

$$\rho\left(\frac{\partial \mathbf{v}}{\partial t} + \mathbf{v} \cdot \nabla \mathbf{v}\right) = -\nabla p + \nabla \cdot \mathbf{T} + \mathbf{f} \quad \text{C. Navier, G. Stokes, } 1845$$

11. Maxwell's Equations

$$\begin{array}{ll} \nabla \cdot \mathbf{E} = 0 & \nabla \cdot \mathbf{H} = 0 \\ \nabla \times \mathbf{E} = -\frac{1}{c} \frac{\partial \mathbf{H}}{\partial t} & \nabla \times \mathbf{H} = \frac{1}{c} \frac{\partial E}{\partial t} \\ \end{array}$$

$$\nabla \cdot \mathbf{H} = 0$$

 $\nabla \times \mathbf{H} = \frac{1}{2} \frac{\partial}{\partial x}$

J.C. Maxwell, 1865

Second Law of Thermodynamics

$$dS \ge 0$$

L. Boltzmann, 1874

Relativity

$$E = mc^2$$

Einstein, 1905

Schrodinger's Equation

$$i\hbar\frac{\partial}{\partial t}\Psi=H\Psi$$

E. Schrodinger, 1927

Information Theory

$$H = -\sum p(x)\log p(x)$$

C. Shannon, 1949

Chaos Theory

$$x_{t+1} = kx_t(1-x_t)$$

Robert May, 1975

17. Black-Scholes Equation

$$\frac{1}{2}\sigma^2S^2\frac{\partial^2V}{\partial S^2}+rS\frac{\partial V}{\partial S}+\frac{\partial V}{\partial t}-rV=0 \quad \text{ F. Black, M. Scholes, } 1990$$





Scientific Computing

- Domain beyond analytical approach (due to non-linearity, integrability, non-inversion and many other reasons): Numerical Mathematics/Applied Mathematics/Computational Science. Applications include, Computational Finance, Computational Biology, Computational Engineering, Computational Physics, Computational Chemistry, Computational Materials Science & so on.
- A well-executed computation can reproduce lab-based experiments quantitatively, and therefore can predict new phenomena by "numerical experiments" often hard to realize on a lab due to financial / timeframe / workforce restrictions.
- There goes the catch! Given a computer, is every computation is a well-executed computation? Answer is NO.

Binary and Decimal

Decimal (or denary) numeral system represents integer and non-integer numbers in base-10 positional number system. Decimal refers to digits 0, 1, 2, 3, 4, 5, 6, 7, 8, 9 in the decimal system containing a "decimal separator", e.g. 3.14. In general,

$$a_m a_{m-1} ... a_0 .b_1 b_2 ... b_n = a_m 10^m + a_{m-1} 10^{m-1} + ... + a_0 10^0 + \frac{b_1}{10^1} + \frac{b_2}{10^2} + ... + \frac{b_n}{10^n}$$

- Binary numeral system represents only two numbers 0 and 1 in base-2 number system. A human-understood decimal is converted to computer-understood binary to perform computation and back converted to decimal to decipher.

Most Significant Bit (MSB)

Least Significant Bit (LSB)

$$101100101_2 = 1 * 2^8 + 0 * 2^7 + 1 * 2^6 + 1 * 2^5 + 0 * 2^4 + 0 * 2^3 + 1 * 2^2 + 0 * 2^4 + 1 * 2^0 = 357_{10}.$$

Binary and Decimal

■ Conversion decimal binary: Repeated division-by-2 method:

```
294<sub>10</sub>: divide by 2 \rightarrow 147\{\text{remainder } 0(LSB)\}, divide by 2 \rightarrow 73 (remainder 1), divide by 2 \rightarrow 36 (remainder 1), divide by 2 \rightarrow 18 (remainder 0), divide by 2 \rightarrow 9 (remainder 0), divide by 2 \rightarrow 4 (remainder 1), divide by 2 \rightarrow 2 (remainder 0), divide by 2 \rightarrow 1 (remainder 0), divide by 2 \rightarrow 0\{\text{remainder } 1(MSB)\} 100100110<sub>2</sub>.
```

■ Fractions in binary terminate, if the denominator has 2 as the only prime factor. 1/10 doesn't have a finite binary representation which causes 10×0.1 not to be precisely equal to 1 in floating point arithmetic. To interpret the binary expression for $\frac{1}{3}$ =.010101...means= $0*2^{-1}+1*2^{-2}+0*2^{-3}+1*2^{-4}+...=0.3125+....$ So 1 and 0's alternate forever, if we want to reach the exact expression as a sum of inverse powers of 2 \Rightarrow source of Error!!

Scientific Computing

The Patriot Missile Failure On February 25, 1991, during the Gulf War, an American Patriot Missile battery in Saudi Arabia failed to track & intercept an incoming Iraqi Scud missile. It killed 28 soldiers & injured 100s of people. Cause of the failure turned out to be inaccurate calculation of the time due to arithmetic errors!! How????

What patriot saved in the system \bigcirc 0.00011001100110011001100 error in binary 0.0000000000000000000000011001100 lead to 0.000000095 in decimal. Multiplying by the number of tenths of a second in 100 hours gives 0.000000095×100×60×60×10=0.34 seconds.

- Significant Digits These are the first nonzero digit & all succeeding digits, *e.g.* 1.7320 has 5 significant digits, while 0.0491 has only 3.
- A floating point (real) number system have elements of the form $y = \pm m \times \beta^{e^{-t}}$, is characterized with 4 integer parameters:
- Base (or radix) β , precision t, exponent e & significand (or mantissa) m. Here $e_{min} \le e \le e_{max}$ & $0 \le m \le \beta^t - 1$. This gives the range of nonzero floating point numbers $\beta^{e_{min}-1} \le y \le \beta^{e_{max}} (1-\beta^{-t})$.
- Floating point numbers aren't equally spaced !! If $\beta = 2$, t = 3, $e_{min} = -1$, $e_{max} = 3$ then non-negative numbers are 0, 0.25, 0.3125, 0.3750, 0.4375, 0.5, 0.625, 0.750, 0.875, 1.0, 1.25, 1.50, 1.75, 2.0, 2.5, 3.0, 3.5, 4.0, 5.0, 6.0, 7.0.
- Spacing of the floating point numbers jumps by a factor 2 at each power of 2. Spacing can be characterized in terms of machine epsilon, which is the distance from 1.0 to the next larger floating point number. In Python, this can be seen as:

"import numpy as np", and then, "np.spacing(1)" yields 2.2204460492503131e-16.

In MATLAB/Octave, "eps" gives the same value. "realmax" & "realmin" represent the largest positive & smallest positive normalized floating point number. In Python, "import numpy as np", and then, "np.finfo(np.double).max" yields 1.7976931348623157e+308, while "np.finfo(np.double).tiny" yields

2.2250738585072014e-308.

IEEE Arithmetic IEEE standard defines a binary floating point system. The standard specifies floating point number formats, results of the basic floating point operations & comparisons, rounding modes, floating point exceptions & handling, conversion between different arithmetic formats.

Two main floating point formats are defined:

	Type	Size	Significand	Exponent U	J nit roundoff	Range
sion)	Single	32 bits	23+1 bits	8 bits	$2^{-24} \approx 5.96 \times 10^{-8}$	$10^{\pm 38}$
(precision)	Double	64 bits	52+1 bits	11 bits	2^{-53} $\approx 1.11 \times 10^{-16}$	$10^{\pm 308}$

In both formats one bit is reserved as a sign bit. The most significant bit is always 1 & not stored. This hidden bit accounts for the "+1" in the table.

- NaN (Not a number) is a special bit pattern with arbitrary significand. It's generated by operations such as $0/0,0\times\infty,\infty/\infty,(+\infty)+(-\infty)$. Infinity symbol is represented by zero significand & same exponent field as NaN, sign bit distinguishes between $\pm\infty$ with property, $\infty+\infty=\infty,(-1)\times\infty=-\infty$, finite/ $\infty=0$. Zero is represented by a zero exponent field & zero significand, with +0=-0.
- In MATLAB/Fortran 90/95, A(p:q, r:s) denotes submatrix of A formed of rows p to q & columns r to s. A(:, j) is the jth column of A, and A(i, :) the ith row of A.
- Evaluation of an expression in floating point arithmetic denoted by fl(.) is $fl(x op y) = (x op y)(1+\delta), |\delta| \le u$
 - u is called the *unit roundoff* (machine precision) $\approx 10^{-8} (\text{single}), 10^{-16} (\text{double}),$ $10^{-10} 10^{-12} (\text{pocket calculators}).$
- Computed quantities are denoted with hat. So, \hat{x} is the computed approximation of x.

- $\lfloor x \rfloor$ (floor x) is the largest integer $\leq x \& \lceil x \rceil$ (ceil x) is the smallest integer $\geq x$. Check with Python: "import math; math.floor(1.9) = 1.0", "math.ceil(1.9)=2.0".
- Remember, we compute single precision arithmetic ($u \approx 6 \times 10^{-8}$) by rounding, say, a double precision result with *unit roundoff* ($u \approx 1.1 \times 10^{-16}$) to single precision as well rounding result of every elementary operation to single precision.

Absolute & Relative Error \sum If \hat{x} is an approximation to real number x, then

$$E_{\text{abs}}(\hat{x}) = |x - \hat{x}|, \quad E_{\text{rel}}(\hat{x}) = \frac{|x - \hat{x}|}{|x|}$$

Note that relative error is scale independent: $x \rightarrow \alpha x$, $\hat{x} \rightarrow \alpha \hat{x}$, doesn't change $E_{\rm rel}(\hat{x})$.

- Relative error is connected with the notion of Correct significant digits, however relative error is a more precise, base independent measure.
- Sources of Error → (i) rounding, (ii) data uncertainty & (iii) truncation. Uncertainty in data can arise in several ways from errors of measurement, storing data on

Sources of Error

computer. Data errors can be analysed using perturbation theory, while intermediate rounding errors require an analysis specific to the given method & thus harder to understand.

- Truncation/discretization errors is when in Taylor's series to derive numerical methods, such as Trapezium rule for Quadrature, Euler's method for differential equations etc, finite terms are kept and later are omitted. This depends on choice of "h": $f(x+h)=f(x)+hf'(x)+\frac{h^2}{2I}f''(x)+\frac{h^3}{3I}f'''(x)+O(h^4)$
- "Rounding errors and instability are important & numerical analysts will always be the experts in these subjects & at pains to ensure that the unwary are not tripped up by them. But our central mission is to compute quantities that are typically uncomputable, from an analytic point of view, and to do it with lightning speed".



- Nick Trefethen, FRS, Univ. of Oxford.

Precision vs Accuracy Accuracy refers to the absolute/relative error of an approximate quantity. Precision is the accuracy with which the basic arithmetic operations (+, -, *, /) are performed & for floating point arithmetic is measured by the *unit roundoff* u. Accuracy & precision are the same for the scalar computation $c = a \times b$, but accuracy can be much worse than precision in the solution of a linear system of equations, e.g. stiff equations.

Conditioning Torward & Backward error is governed by sensitivity of solution to perturbations in the data or "conditioning" of the problem. Then,

$$\hat{y} - y = f(x + \triangle x) - f(x) = f'(x) \triangle x + \frac{(\triangle x)^2}{2} f''(x + \triangle x) + O((\triangle x)^3),$$

$$\hat{y} - y = (xf'(x)) \triangle x - ((A - x)^2) - (A - x)^2 + O((A - x)^2)$$

or $\frac{\hat{y}-y}{y} = \left(\frac{xf'(x)}{f(x)}\right) \frac{\triangle x}{x} + O((\triangle x)^2)$. Here $c(x) = \left|\frac{xf'(x)}{f(x)}\right|$ measures the relative

change in output for relative change in input or condition number of f. For example, consider $f(x)=\log x$, $c(x)=|1/\log x| \to \infty$ for $x\approx 1$. So a small relative change in x can produce large relative change in $\log x$ for $x\sim 1$.

Rule of thumb: forward error \(\leq \condition \) number \(\times \) backward error. So, computed solution to an ill-conditioned problem can have a large forward error, even if computed solution has \(small \) backward error. Backward stability implies forward stability. Cramer's rule for solving 2x2 linear system is forward stable but not backward stable.

The problem lies in the fact that, even though 1-c is exact, it has only 1 significant figure, so subtraction produces a result of the same size as the error in c. However, if the subtraction is avoided by rewriting $\cos x = 1 - 2\sin^2(x/2)$, $f(x) = \frac{1}{2}(\frac{\sin(x/2)}{x/2})^2$. The same procedure now yields f(x) = 0.5 correct to 10 significant digits.

■ Error in cancellation can be avoided by *estimating the damage*, it can't be unavoidable. Or computing ratio of differences of the same order of error so that numerator & denominator cancels out. Or, for example computing x + (y - z) for $x \gg y \approx z > 0$.




Roots of a Quadratic Equation Depending on the sign of the remainder b^2-4ac , for $a\neq 0$, $ax^2+bx+c=0$ have two roots (real-unequal, real-equal, imaginary) $x=\frac{-b\pm\sqrt{b^2-4ac}}{2a}$. If $b^2\gg 4ac$, then $x=\frac{-b\pm b}{2a}$ and for "+" sign it suffers massive cancellation that brings prominence of earlier rounding errors. To avoid, the largest (in absolute value) root is chosen $x_1=\frac{-b-\sqrt{b^2-4ac}}{2a}$ and the other from $x_1x_2=\frac{c}{a}$. But when $b^2\approx 4ac$, accuracy is lost & only way to guarantee accuracy is to use extended precision.

Overflow & Underflow If we apply $x = \frac{-b \pm \sqrt{b^2 - 4ac}}{2a}$ in single precision arithmetic to equation $10^{20} x^2 - 3 \times 10^{20} x + 2 \times 10^{20} = 0$, even when the roots are not harmful (x=1 & x=2), overflow occurs since the maximum floating point number is $\approx 10^{38}$. Analytically/numerically dividing by maximum (|a|, |b|, |c|) = 3×10^{20} is OK, but same strategy doesn't work for, say, $10^{-20} x^2 - 3x + 2 \times 10^{20} = 0$ whose roots are $10^{20} \& 2 \times 10^{20}$. Scaling the variable $x = 10^{20} y$ yields, $10^{20} y^2 - 3 \times 10^{20} y + 2 \times 10^{20} = 0$ which is the initial equation we started from.

Need for non-dimensionalization:

A well-known example in Condensed Matter Physics is the ϕ^4 kink, that gives a tanh solution of the domain wall formed between liquid-gas interface/magnetic domain walls having diverse consequences in many branches of physics.



■ To have a control over the dynamics of density variation, clearly one needs to control these parameters, r, u, c or a multi-dimensional diagram which is nearly impossible to control often because of many parameters with less-known activity.

Need for non-dimensionalization:

Notice that
$$\mathscr{F} = -\frac{1}{2}r\phi^2 + u\phi^4$$
 have two minima, that we see from
$$\frac{\partial \mathscr{F}}{\partial \phi} = 0 = -r\phi + 4u\phi^3 \text{ or } \phi = \pm \phi_0 = \sqrt{\frac{r}{4u}}. \text{ Then } \mathscr{F}_0 = -\frac{1}{2}r\phi^2 + u\phi^4 = -\frac{r^2}{16u} = -\frac{r\phi_0^2}{4}$$

■ But now notice that, $\mathscr{F} = -\frac{1}{2}r\phi^2 + u\phi^4 = -\frac{1}{2}r\frac{\phi^2}{\phi_0^2}\phi_0^2 + u\frac{\phi^4}{\phi_0^4}\phi_0^4 = -\frac{r^2}{8u}\hat{\phi}^2 + \frac{r^2}{16u}\hat{\phi}^4$ $= -\frac{r^2}{9u}\hat{\phi}^2 + \frac{r^2}{16u}\hat{\phi}^4 = -\frac{r^2}{16u}(2\hat{\phi}^2 - \hat{\phi}^4) = \mathcal{F}_0(2\hat{\phi}^2 - \hat{\phi}^4)$

■ Therefore, $\frac{\mathscr{F}}{\mathscr{F}} = \hat{\mathscr{F}} = 2\hat{\phi}^2 - \hat{\phi}^4$ & so, $\partial_t \hat{\phi} = 4(\hat{\phi} - \hat{\phi}^3)$. The dynamics is completely free of parameter. According to the scale, we can choose what to compute!!

Beautiful Example : Kibble mechanism in Cosmology → LCD screen defect applications. Both are governed by same equation !!

