Data Link Layer

Lecture 7 Framing and introduction to CRC

in the data link layer, we try to "make sense" of the incoming bits

which bits together mean
something in the stream of data.

The resulting unit is called a frame.

In a frame, we first need to demarcate where the section begins/ends.

High-Level Data Link Control (HDLC) is used as Layer-2 technology in Wide Aea Networks.

(WANS)

The (HDLC) frame has a begin sequence, & bits header, 16 bits body, variable CRC, and 16 bits end sequence. 8 bits

The begin lend sequence are the same: 01111110

If there is nothing to send, we continuously send this

It also helps in clock synchronization.

What if this sequence appears elsewhere?
We do bit stuffing. Say OIIIIIO is somewhere in the middle.

Line insert bits.

What H.DLC does is:

→ If you see 5 consecutive is, insert a 0.

DIIIIIODOIIIIIIODOIIIIIIO

OIIIIIODOIIIIIIOIDOIIIIIO

At the receiver,

we somehow have to remove these stuffed bits.

Wherever you see 5 consecutive Is, remove the subsequent stuffed O. The end sequence still has 6 consecutive Is.

But what if there is some bit error?

0 → Remove (bit stuffing)

1111 { 10 → Assume end sequence}

11 — Assume error has occurred and discard the frame

(We discard everything until we see the sequence again)

This is very barebones though, we need something better for errors.

Cyclic Redundancy Check (CRC)

We just append the k-bit CRC to the n-bit dataword to get a (=16 here)

The space of datawords is the set of all 2° bit words. We keep it such that only 2° of the 2° hk (n+k)-bit strings are valid. An issue only arises when the error is such that the erroneous string is a codeword as well.

⇒ We need to ensure that codewords are "for apart".

Given $v, w \in \{0,1\}^n$, the Hamming distance between v and w is $d(v, w) = \{i \in [n] : v_i \neq w_i\}$.

(number of positions they are distinct) for a "code" $C \subseteq \{0,1\}^n$: the Hamming distance of C is min $\{d(v,w): v,w\in C,v\neq w\}$.


We want this distance to be large.

GF(2) = FF(2) is a finite field with elements $\{0,1\}$. Addition (+) has identity 0. (Note that a+b=a-b) Multiplication (x) has identity (. CRC is based on a cyclic code

If v is a codeword, cyclic shifts of value result in codewords.

To generate a CRC, we use long division (in F_2) The divisor/generator is of length k+1 bits.


For example, say k=3 and the generator or "divisor" is 1101 and n=10 with data word 110110



The codeword is then 110110111.

At the sender,

Long division for a given generator can be implemented using shift regristers. For generator 1101,



After Dataword 000 is emptied, the CRC is Left in the shift registers.

At the receiver, either

- 1. pass the dataword with k Os through the CRC circuit and verify that the CRCs match or
- 2. pass the entire received word through the CRC circuit and verify that you get all Ds.

Lecture 8 CRC Polynomial Arithmetic

So say we transmit some codeword with equivalent polynomial P(x). Let the error bitstring be E(x).

The received word is then P(x) + E(x). We divide the received polynomial by C(x) and if the resultant is D, we say there is no bit error L poly. corresponding to generator.

We want $\frac{P(x) + E(x)}{C(x)} \neq 0 \quad \text{if } E(x) \neq 0.$

→ Single bit errors. $E(x) = x^{i}$ for some i. $\frac{P(x) + E(x)}{C(x)} = \frac{P(x)}{C(x)} + \frac{E(x)}{C(x)} = \frac{E(x)}{C(x)}$.

If
$$C(x) = x^k + \cdots + 1$$
, single bit errors can be detected.
Do or 15

Elx) = $C(x) \cdot D(x)$

will have at least two non-zero powers of x.

(So for example, 1101 can detect single bit errors)

→ 2-bit ernors.

 $E(x) = x^{j} + x^{\bar{i}} = x^{i} (x^{j-i} + i)$ (suppose j > i) Write each polynomial as a product of irreducible polynomials.

$$\frac{E(x)}{C(x)} = \underbrace{g_1(x) \cdots g_t(x)}_{f_1(x)} \cdots f_m(x)$$

If C is of the form $x^k + \cdots + 1$, no $f_r(x)$ is of the form x^B . \Rightarrow no f_r will divide the x^i (if i > 0).

However, we could have

 $(x^k + \cdots + 1)(\cdots) = x^k + 1$ for some "large" Y. So if j-i is large (the errors are far apart), the bit errors might not be detected

The smallest Y such that C(x) divides x +1 is called its order.

It is known how to find C(x) of the form $x^k + \cdots + 1$ such that it has order $2^k - 1$.

So while this limits the length of the codeword that can be transmitted, it gets the job done quite well.

So if we have a 16 bit CRC, we can transmit data as large as $2^{16}-1-16$ while detecting 2-bit errors.

$$E(x) = x^{i_1} + x^{i_2} + \cdots + x^{i_{2r+1}}$$

If C(x) has (1+x) as a factor, it cannot divide x of this form. Indeed,

$$(1+1)$$
 $D(1)=0$ but $E(1)=0$.

Substituting $x=1$

$$D(x) \rightarrow 0001111000$$

$$XD(x) \rightarrow 00111110000$$

$$60100001000$$

$$\text{two Is in (1+x)D(x)}$$

If C(x) has an even number of terms, it can detect any error E(x) with an odd number of terms

HDLC uses
$$CRC - 16 - 18M$$

 $C(x) = x^{16} + x^{15} + x^{2} + 1$

CRC-32 has
$$C(x) = x^{32} + x^{26} + x^{23} + x^{22} + x^{16} + x^{12} + x^{11} + x^{10} + x$$

Lecture 9 ARQ

How do we detect a burst of errors?

That is, a bunch of contiguous bits become erroneous.

The error is of the form $E(x) = x^{i+l-1} + x^{i+l-2} + \cdots + x^{i+l} + x^{l}$

Let the CRC be of the form
$$C(x) = x^{K} + \cdots + 1$$
 anything

To be undetected, C(x) divides E(x).

$$\frac{E(x)}{c(x)} = \frac{x^{i} \left(x^{i-1} + x^{i-2} + \dots + 1\right)}{x^{k} + \dots + 1}$$
 this is the part that matters

If l-1 < k, then C(x) cannot divide $x^{l-1} + x^{l-2} + \cdots + 1$. So bursts of length at most k can be detected.

Another thing we shall study is ARQ-Automatic Repeat request Sometimes, if the link between two nodes is unreliable, some of the handling of reliability is done by the DLL. (TCP is quite slow) WiFi uses ARQ.

(the wireless link is prone to errors)

Suppose the sender sends out a frame that the receiver receives St later. How do we know if the frame has got there relievely? Speed of light delay

The receiver sends out an acknowledgement that is received after St. (ACK)

The ACK frame is quite small, it just acknowledges the specific frame. How long should the sender wait for the ACK?

This is quite non-trivial in TCP because there are factors such as where you are located.

Here, however, we are just concerned about a single link.

We need to figure out what the RTT is.

first bit of sent frame from sender to last bit of ACK frame to sender

The distance between the (WiFi) occess point and the device is usually a few 10s of meters.

It will take a couple of nenoseconds (not insignificant).

Wait 2-3 times the RTT and if ACK not received, retransmit.

Note that the time also depends on the size of the frame and ACK.


What if the ACK frame is in error/did not reach the sender? A timeout is said to occur. The sender assumes the worst case and resends the frame after the timeout (although the receiver has already received the frame).

It is also possible to run into problems if we set the timer to be too small. We receive the ACK for a previous version of the (same) frame while we are waiting for the current frame.


If the timer is too large, then we waste a lot of time if there is an issue with the frame (or ACK).

We must set the timer appropriately to cut down on resources and redundancy.

We often represent protocols using state diagrams or flowcharts. For example,



Each action is represented by a flowchart.



Wireless systems usually use ARQ.

Lecture 10 Medium Access

Recall the issue of medium access that we had (briefly) looked at.

The wire there is the "medium" of everyone tries to use the medium at the same time, the messages will collide/interfere.

It is more problematic in the wireless case since the signal decays very fact with distance.

For now, we shall look at Ethernet LAN, which uses CSMA - Carrier Sense Multiple Access.

There is a central bus (wire) and we want to prevent multiple people from simultaneously transmitting.

One idea is to have some central authority whose permission you need (this is used in wireless cellular networks).

Further, there is the issue of how this authority knows when someone wants to transmit. If we know how many nodes there are, we could do TDMA (Time Division Multiple Access) — give regular time slots during which (only) they can transmit. Obviously, this leads to massive inefficiency. What if a new person joins? What if the authority goes down.

If a node has data to send, it creates a frame and sends it. Broadcast signals are sent to everyone on the network.

The most common are unicast signals - there is a single destination node. There are also multicast signals.

This part of the pertinent information should be mentioned as well. In this scheme, what if there is a collision? Neither receiver receives the information if the information is sent by both users again, there could be another collision.

We also need a mechanism for collision detection.

If a collision is detected, we shouldn't have both senders try again immediately.

CSMA is a roundom access protocol— the schedule for transmission is not decided in advance.

At each sender node, we back off for some random amount of time before retransmitting.

The "Carrier Sense" means that if someone else is transmitting, we wait before sending our own message. This resolves the issue that occurs when one person retransmits slightly before the other-

This could still be problematic if many people are trying to communicate simultaneously, so we need to refine this idea.

|EEE 802.3 Uses CSMA - CD La Collision Detection

To do carrier sense, we can just check if there is some reasonable amount of energy on the wire.

(sufficiently larger than the noise energy)

How do we perform collision detection?

In wireless, just check if ACK is received.

In wired, when the signals add up, we could do something with Fourier analysis. More simply however, we see that the energy of the signal increases after two signals add up.


Keep another threshold. If the energy is greater, then declare that a collision has occurred.

So we have two thresholds - one for carrier sense and one for collision detection


Amother issue is: what if one side detects the collision much earlier and stops transmitting so the other side does not detect a collision?

So after the first side realizes there is a callision, it sends out a (short) jamming signal so the other side detects a collision (it is guaranteed that detection will happen by the time the jamming signal ends)

It is worth noting that there may be multiple "other side"s.



Frame details in 802.3:




Why minimum frame size?

We assume that the WAN is at most 2500 m wide.

RTT
$$\simeq \frac{5000}{2 \times 10^8}$$
 = 25 µs
close to speed of light but not exactly

If the frame transmission time is (much) larger than the RTT, it is possible that we do not detect a collision before the frame finishes transmitting.



Along the way, we also have repeaters that reproduce the signal. This may add some more time, so let us conservatively take 50 µs (instead of 25 µs).

64 bytes at 10 Mbps → 51.2 µs.

If we have larger distances or higher rates, the minimum frame size would be made larger.

Why maximum frame size?

- i. If we have a larger frame, the probability of getting an erroneous bit is high.

 If p is the probability of a particular bit going wrong (assume iid), the probability of getting an error is 1-(1-p) ? Llength
- 2. Other people do not get an opportunity to transmit for a long time.
- 3. Memory requirements at the NIC card go up Live need to store it for checking the CRC).

Finally, what distribution do we pick the random backoff from? If Δ is the minimum wait time, we pick uniformly from $\{\Delta u: u \in \{1, \cdots, 2^k\}\}$. We want k to be larger if more people have callided. How?

What we do is that we initially pick some (small) k. If a collision occurs, we increase k (and recurse). This system is known as exponential back off.

If we use linear instead, we might end up waiting for a long time before no collision occurs

A more complete flowchart of the above information is given on the next page.

