# HBI User's guide

So Ozawa

July 7, 2024

# 1 Introduction

Fortran 90 software HBI performs three-dimensional quasi-dynamic numerical simulations of sequences of earthquakes and aseismic slip (SEAS). It can handle arbitrary fault geometry such as branches, step-overs, and rough faults in an elastic half-space. 2D problems can also be solved in the same code. The computation is accelerated by taking advantage of  $\mathcal{H}$ -matrices.  $\mathcal{H}$ ACApK, open-source software for  $\mathcal{H}$ -matrices, is called for constructing and operating  $\mathcal{H}$ -matrices.

The code has been benchmarked by several SEAS problems under SCEC [Jiang et al., 2022, Erickson et al., 2023], as well as with fully-dynamic codes for 2D nonplanar fault problems [Romanet and Ozawa, 2022].

The latest versions can be found at https://github.com/sozawa94/hbi. Feel free to contact So Ozawa (sozawa@stanford.edu), if you have any questions.

# 2 License

This software is freely available under the MIT license. If you write a paper using this code, please cite the following manuscript [Ozawa et al., 2023].

So Ozawa, Akihiro Ida, Tetsuya Hoshino, Ryosuke Ando (2023), "Large-scale earthquake sequence simulations of 3D geometrically complex faults using the boundary element method accelerated by lattice H-matrices on distributed memory computer systems", Geophysical Journal International

## 3 How to run

```
Download the source codes from github. Type:

git clone http://github.com/sozawa94/hbi

To compile and link the code, type

make

You may need to modify Makefile depending on your environment.

To run a simulation, type:

./lhbiem (inputfile)

or use MPI parallelization;

mpirun -np 16 ./lhbiem (inputfile)
```

To run the code in parallel, the number of MPI processes must be a squared number. Several input files, including the benchmark problems of the SEAS project (https://strike.

scec.org/cvws/seas/), are available in examples (see the next section).

## 3.1 Note on Sherlock users

If you use HBI in Sherlock (cluster in Stanford University), you need to load required modules before make:

```
ml load ifort
ml load impi
```

You also need to switch compiler options by editing Makefile. As of June 2024, the Intel MPI is not working in Sherlock. I recommend the users to use open MP parallelism.

# 3.2 Monitoring ongoing jobs

The standard output first shows the information about (lattice)  $\mathcal{H}$ -matrices (approximated integration kernel). Then, timestep and time (measured by year) are recorded.

job.log is a record of the start and normal stop of jobs.

# 4 Problem setting

# 4.1 Description of Input file

Various simulations can be performed by modifying the input file, rather than modifying the source code. The input variable list is:

| name              | $_{\mathrm{type}}$ | meaning  |
|-------------------|--------------------|--|
| filenumber        | integer            | job number (name of output files)  |
| problem           | character          | dimension, planar or non-planar, mesh, etc.                                |
| ncellg            | integer            | number of elements (not used in 3dp, 3dph, 3dht,3dnt)                      |
| nstep             | integer            | maximum number of time steps   |
| interval          | integer            | output & checkpointing every this time steps                               |
| dtout             | real               | output every this time (year)  |
| dtinit            | real               | initial time step width (s)  |
| $geometry\_file$  | character          | name of geometry file  |
| parameter_file    | character          | name of parameter file   |
| parameterfromfile | logical            | true if parameters are read from parameter_file                            |
| restart           | logical            | true if restarting a suspended job   |
| backslip          | logical            | true if loading is added by backflip                                       |
| vpl               | real               | the velocity of backslip (m/s) (used if backflip=T)                        |
| sr                | real               | the stressing rate (MPa/s) (used if backslip=F)                            |
| tmax              | real               | maximum time (year)  |
| sigmaconst        | logical            | true if normal stress is kept constant                                     |
| ds                | real               | element size (km) (used in 2dp, 3dp, 3dph)                                 |
| imax              | integer            | the number of elements in slip-parallel direction (used in 3dp, 3dph)      |
| jmax              | integer            | the number of elements in slip-perpendicular direction (used in 3dp, 3dph) |
| crake             | real               | rake angle (deg) in 3D problems (not used if parameterfromfile=T)          |
| dipangle          | real               | dip angle (deg) used in 3dph and 2dph                                      |
| evlaw             | character          | evolution law for RSF ("aging" or "slip', default="aging")                 |
| a                 | real               | a in RSF (not used if parameterfromfile=T)                                 |
| b                 | real               | b in RSF (not used if parameterfromfile=T)                                 |
| dc                | real               | dc in RSF (not used if parameterfromfile=T)                                |
| f0                | real               | f0 in RSF (not used if parameterfromfile=T)                                |
| tauinit           | real               | initial shear stress (MPa) (not used if parameterfromfile=T)               |
| sigmainit         | real               | initial normal stress (MPa) (not used if parameterfromfile=T)              |
| velinit           | real               | initial slip rate (m/s) (not used if parameterfromfile=T)                  |
| eps_h             | real               | error allowance in H matrix (default: 1e-4)                                |
| $eps\_r$          | real               | error allowance in Runge-Kutta (default: 1e-4)                             |
| velmax            | real               | computation stop if maximum velocity is above this value (default:1e7)     |
| velmin            | real               | computation stop if maximum velocity is below this value (default:1e-16)   |
| limitsigma        | logical            | true if you want to limit normal stress                                    |
| maxsig            | real               | maximum normal stress (MPa) (used if limitsigma=T)                         |
| minsig            | real               | minimum normal stress (MPa)(used if limitsigma=T)                          |

# 4.2 Problem

The list of problems are follows:

| problem | description  |
|---------|--|
| 2dp     | 2D planar fault in full-space (plane strain)   |
| 2dph    | 2D planar fault in half-space (plane strain)   |
| 2dn     | 2D nonplanar fault in full-space (plane strain)  |
| 2dnh    | 2D nonplanar fault in half-space (plane strain)  |
| 25d     | 2D nonplanar fault in full-space (plane strain) with finite fault width (2.5D approximation) |
| 2 dvs   | 2D vertical strike-slip fault  |
| 3dp     | 3D planar squared elements in full-space   |
| 3dph    | 3D planar squared elements in half-space   |
| 3 dnr   | 3D nonplanar squared elements in full-space  |
| 3dhr    | 3D nonplanar squared elements in half-space  |
| 3dnt    | 3D nonplanar unstructured triangular elements in full-space                                  |
| 3dht    | 3D nonplanar unstructured triangular elements in half-space                                  |

# 4.3 Physical variables and constants

The following units are assumed:

| quantity      | unit            |
|---------------|-----------------|
| time          | S               |
| location      | $\mathrm{km}$   |
| displacement  | $\mathbf{m}$    |
| slip velocity | m/s             |
| wave speed    | $\mathrm{km/s}$ |
| shear modulus | GPa             |
| stress        | MPa             |

The fundamental physical constants are set in m\_const.f90. The default values are

| quantity                   | default value        |
|----------------------------|----------------------|
| rigidity                   | 32.04GPa             |
| P-wave speed               | 6.000  km/s          |
| S-wave speed               | 3.464  km/s          |
| reference slip rate on RSF | $1 \mu \mathrm{m/s}$ |

# 4.4 Fault Geometry

For 2dp, 2dph, 3dp, and 3dph, fault geometry is set in inputfile. For other problems, an additional geometry\_file is necessary.

### 4.4.1 2dp, 2dvs

The fault geometry is uniquely characterized by its element size ds and the number of elements ncellg.

## 4.4.2 3dp

The fault geometry is uniquely characterized by its element size ds and the number of elements along strike and dip (imax, jmax).

## 4.4.3 2dph

The fault geometry is characterized by its element size ds, the number of elements ncellg, and dip angle in degree dipangle. For nonplanar case, use 2dnh.




Figure 1: Fault geometry

## 4.4.4 3dph

The fault geometry is characterized by its element size ds, the number of elements along strike and dip (imax, jmax), and dip angle in degree dipangle. See also Figure 1.

### 4.4.5 2dn, 2dnh, 25d

The coordinates of two edges of a straight line have the geometrical information of an element. xel<xer is necessary. geometry\_file has the following format:

```
xel(1) xer(1) yel(1) yer(1) xel(2) xer(2) yel(2) yer(2)
```

For 2dnh, the structure geomerty\_file is the same with 2dn. Here, y = 0 is assumed to be the free surface and y-axis is downward (i.e., y is always positive).

#### 4.4.6 3dnt, 3dht

The coordinates of the three edges of a triangle have the geometric information of an element. geometry\_file should have STL (ASCII) format:

```
facet normal normal_vector(1:3)
  outer loop
    vertex xs1 ys1 zs1
    vertex xs2 ys2 zs2
    vertex xs3 ys3 zs3
  endloop
endfacet
```

This structure repeats ncellg times. For 3dht, z=0 is the free surface and all elements must be located below the free surface (i.e., z<0).

#### 4.4.7 3dnr, 3dhr

Cell size ds must be specified in the inputfile. geometry\_file should have STL (ASCII) format:

```
x(1) y(1) z(1) strike(1) dip(1)
x(2) y(2) z(2) strike(2) dip(2)
```

Here, x,y,z are the center of the square, strike and dip are measured in radian.

## 4.5 Parameters and Initial conditions

The following parameters and initial values are needed for each element.

#### 4.5.1 Rake angle

In 3D problems, it is also necessary to specify the direction of slip (rake angle) for each element. The angle of rake is defined as 90 = reverse faulting, 0 = right lateral strike-slip faulting, and -90=normal faulting. The code does not allow for a time-varying slip direction. In the uniform case, set crake in inputfile.

Alternatively, rake angle for each element can be calculated from the plate convergence orientation for subduction zone simulations. Users use rakefromglobal = T, and set convangle for the orientation of the plate (0 degree for west-east (positive in x-axis) direction and anticlockwise). For example, Cascadia subduction zone has convangle of 10 - 20 degrees.

2D problems do not use rake values.

### 4.5.2 Friction parameters

HBI uses the regularized version of the rate and state friction law (RSF), which is employed in the SEAS benchmark problems. The friction coefficient are given by

$$\tau/\sigma = a\sinh^{-1}(Ve^{\psi/a}/2V_0). \tag{1}$$

The state evolution is governed either by the aging law

$$\frac{d\psi}{dt} = \frac{bV_0}{d_c} \exp[(f_0 - \psi)/b] - \frac{bV}{d_c}.$$
 (2)

or the slip law

$$\frac{d\psi}{dt} = -\frac{V_0}{d_c}(f - f_{ss})\tag{3}$$

$$f_{ss} = f_0 + (a - b) \log \frac{V}{V_0} \tag{4}$$

The evolution law is the aging law as default. Set evlaw to slip in the inputfile to switch. The values of parameters  $(a, b, d_c, f_0)$  are set in inputfile in the case of uniform parameters.

#### 4.5.3 Initial conditions

The initial condition is uniquely determined by the value of normal stress, shear stress, and slip rate at each element (the state variable is determined by these three accordingly). In the case of uniform initial values of  $(\sigma, \tau, V)$ , these values are set in inputfile as sigmainit, tauinit, and velinit. Users can also set muinit for initial  $\tau/\sigma$ , which overwrite tauinit.

## 4.5.4 External loading

To have repeated ruptures on the same fault, external loading is necessary. taudot and sigdot are the stressing rates for shear and normal stresses, respectively. In the uniform case, taudot is sr and sigdot is zero. the value of sr must be specified in inputfile.

Alternatively, the code has "backslip" loading option. If backslip=T, then the loading is added by slip deficit rate, that is,

$$\dot{\tau}_i = -V_{pl} \sum_j K_{ij} \tag{5}$$

$$\dot{\sigma}_i = -V_{pl} \sum_j L_{ij} \tag{6}$$

where  $K_{ij}$  and  $L_{ij}$  are kernel matrices for shear and normal stresses, respectively. The value of vpl must be specified in inputfile. Spatially non-uniform backslip has not been implemented.

### 4.5.5 Format of parameterfile

If you want to use non-uniform parameters and initial values, set parameterfromfile T in inputfile and create parameter\_file. parameter\_file has following structure:

## 4.6 Stop control

The simulation stops when any of the following is satisfied.

- 1. the time-step reaches nstep
- 2. the maximum slip rate is greater than velmax [m/s].
- 3. the maximum slip rate is smaller than velmin [m/s].
- 4. the physical time reaches tmax [year].

#### 4.7 Useful functions

If sigmaconst=T, then normal stresses do not change over time as assumed in many studies. If sigmaconst=F (as the default value), the normal stress changes with time. The computation can fail if the normal stress becomes very large or small. To avoid this, the user can set limits on the value of normal stress by setting limitsigma=T. In this case, maxsig and minsig are the maximum and minimum normal stresses, which should be stated in inputfile.

# 5 Visualization

For those familiar with Python, Analysis2D.ipynb and Analysis3D.ipynb are some examples for processing and visualizing data.

Here, the structure of the output files is briefly shown. monitorX.dat records the following information at every time step.

```
timestep time \max(\log 10(\text{vel})) \max(\text{disp}) \max(\text{tau/sigma}) \max(\text{sigma}) \min(\text{sigma}) \text{error-of-RK} \text{stepwidth} \text{wall-clock-time}
```

For example, if you want to view the temporal change of the maximum slip rate in gnuplot, type pl 'monitorX.dat' u 2:3 w 1

The earthquake catalog is saved in eventX.dat. This file lists the event number, the onset time, and the moment magnitude. //

The field data are saved in binary stream files. xyzX.dat is the coordinates of the elements. velX.dat, tauX.dat, sigmaX.dat, and slipX.dat are slip velocity, shear stress, normal stress, and slip every interval time steps, respectively. These are binary stream files.

## 5.1 Paraview

# 6 HBI-Fluid (2D)

This is a different version of HBI that allows fault-zone fluid flow and pore pressure evolution. To switch to the fluid version, you have to compile main\_fv.f90 instead of main\_LH.f90. The fluid version is only available for 2D planar/nonplanar faults (2dp or 2dn) and parallel computation is not yet supported.

# 6.1 Governing equations

The fluid version of HBI additionally solves the fluid pressure diffusion equation

$$\beta \phi \frac{\partial p}{\partial t} = \frac{\partial}{\partial x} \left( \frac{k}{\eta} \frac{\partial p}{\partial x} \right). \tag{7}$$

The boundary conditions for both ends are either Dirichlet (fixed pressure) or Neumann (fixed flow rate), which can be specified by parameter pbcl and pbcr.

Permeability k evolves as.

$$\frac{\partial k}{\partial t} = \frac{V}{L}(k_{\text{max}} - k) + \frac{1}{T}(k_{\text{min}} - k), \tag{8}$$

where T is the healing time and L is the permeability enhancement distance. Initial permeability is kpmin, so setting kpmax = kpmin disables permeability evolution.

The fluid pressure is related to the shear stress with the effective stress law

$$\tau = f(\sigma - p). \tag{9}$$

| namo                  | type                  | meaning                         |                         |
|-----------------------|-----------------------|---------------------------------|-------------------------|
| name                  | V I                   |                                 |                         |
| kpmax                 | $\operatorname{real}$ | Maximum permeability            | unit: m <sup>2</sup>    |
| kpmin                 | real                  | Initial (minimum) permeability  | unit: m <sup>2</sup>    |
| kL                    | real                  | Permeability evolution distance | unit: m                 |
| kT                    | real                  | Permeability healing time       | unit: s                 |
| beta                  | real                  | Compressibility                 | unit: $Pa^{-1}$         |
| eta                   | real                  | Fluid viscosity                 | unit: Pa s              |
| phi0                  | real                  | Porosity                        | unit: none              |
| bcl                   | character             | Left boundary condition         | Dirichlet or Neumann    |
| $_{\rm bcr}$          | character             | Right boundary condition        | Dirichlet or Neumann    |
| $\operatorname{pbcl}$ | real                  | Fluid pressure at the left BC   | Used when bcl=Dirichlet |
| $\operatorname{pbcr}$ | real                  | Fluid pressure at the right BC  | Used when bcr=Dirichlet |
| q0                    | real                  | Flow rate at the boundary       | unit: m/s               |

## 6.2 Setting for 2D

There are several different initial and boundary conditions for fluid models. Users specify one of the following for the parameter **setting** in the inputfile.

### 6.2.1 injectionp

This is fluid injection at the fault center with constant pressure pinj (MPa).

## 6.2.2 injectionq

This is fluid injection at the fault center with constant flow rate q0 (m/s). The duration of injection is tinj (year). SEAS BP6 can be solved with this setting (see examples/bp6a.in).

#### 6.2.3 swarm

This is constant pressure injection at the left end (x = 0) of the fault. The injection pressure is pbcl (MPa). bcl must be Dirichlet to enforce the injection.

#### 6.2.4 thrust

(under construction)

# 7 HBI-Fluid (3D)

main\_fv3dp.f90 is for 3D fluid pressure diffusion on a 3D planar fault. MPI parallization is supported. It solves 2D pressure diffusion equation on the fault.

$$\beta \phi \frac{\partial p}{\partial t} = \frac{\partial}{\partial x} \left( \frac{k}{\eta} \frac{\partial p}{\partial x} \right) + \frac{\partial}{\partial y} \left( \frac{k}{\eta} \frac{\partial p}{\partial y} \right) \tag{10}$$

Permeability evolution law is the same with 2D.

Nonuniform friction parameters can be used. Currently, the parameter file has a different structure with HBI. Parameter file has friction parameter a, b, dc, f0 at each element, which is ordered like  $(1,1),(1,2),\cdots,(1,\text{jmax}),(2,\text{i}),\cdots,(2,\text{jmax}),\cdots,(\text{imax},1),\cdots,(\text{max},\text{jmax}).$ 

Currently 3D code only has injectionq setting, but allows a slightly complicated injection protocol using an external injection file.

The injection file includes:

```
nwells (number of wells) i j (indexes of the locations of the wells) nq (data of qVals and qTimes) qVals (injection rate at t=qTimes (m/s)) qTimes (time (s))
```

See examples/wells.dat for an example of injection file, which is used in inputfile examples/3dinjection2.in.

# 8 Troubleshooting

1. Compare the input file with another input file that worked (many errors are due to wrong values in the input file).

```
diff inXXX inYYY
```

- 2. Check the first line of the monitorXX.dat to see if the initial values were set appropriately.
- head monitorXX.dat
- 3. Check if the simulation was finalized by looking at job.log (sometimes the simulation worked but the visualization script has a bug).

```
cat job.log
```

# 9 References

[Tse and Rice, 1986] and [Rice, 1993] are early examples of earthquake cycle simulations on a planar fault with rate and state friction. For nonplanar fault geometry, [Segall, 2010] is a great reference to the theoretical foundation of the BEM kernel. For the implementation of 2dn, we use the formula in [Ando et al., 2007]. 3dhr and 3dph are based on [?]. 3dnt and 3dht are based on the expression of [Nikkhoo and Walter, 2015]. The time-stepping algorithm is based on "Numerical Recipe for Fortran90" [Press et al., 2002].

# 10 Acknowledgements

I learned about the earthquake cycle simulations with boundary element method from Nobuki Kame and Makiko Ohtani when I was an undergraduate student. The basic structure of HBI is derived from their codes. HACApK library used in HBI was primarily developed by Akihiro Ida. I thank Ryoya Matsushima for finding many bugs in the code. I also thank Ryosuke Ando, Brittany Erickson, Eric M. Dunham, Pierre Romanet, Tetsuya Hoshino, and Natalia Berrios-Rivera for their suggestions that improved the performance, accuracy, stability, and readability of the code.

# References

- [Ando et al., 2007] Ando, R., Kame, N., and Yamashita, T. (2007). An efficient boundary integral equation method applicable to the analysis of non-planar fault dynamics. *Earth, planets and space*, 59:363–373.
- [Erickson et al., 2023] Erickson, B. A., Jiang, J., Lambert, V., Barbot, S. D., Abdelmeguid, M., Almquist, M., Ampuero, J.-P., Ando, R., Cattania, C., Chen, A., et al. (2023). Incorporating full elastodynamic effects and dipping fault geometries in community code verification exercises for simulations of earthquake sequences and aseismic slip (seas). Bulletin of the Seismological Society of America, 113(2):499–523.
- [Jiang et al., 2022] Jiang, J., Erickson, B. A., Lambert, V. R., Ampuero, J.-P., Ando, R., Barbot, S. D., Cattania, C., Zilio, L. D., Duan, B., Dunham, E. M., et al. (2022). Community-driven code comparisons for three-dimensional dynamic modeling of sequences of earthquakes and aseismic slip. *Journal of Geophysical Research: Solid Earth*, 127(3):e2021JB023519.
- [Nikkhoo and Walter, 2015] Nikkhoo, M. and Walter, T. R. (2015). Triangular dislocation: an analytical, artefact-free solution. *Geophysical Journal International*, 201(2):1119–1141.
- [Ozawa et al., 2023] Ozawa, S., Ida, A., Hoshino, T., and Ando, R. (2023). Large-scale earthquake sequence simulations on 3-d non-planar faults using the boundary element method accelerated by lattice h-matrices. *Geophysical Journal International*, 232(3):1471–1481.
- [Press et al., 2002] Press, W., Tenkolsky, W., et al. (2002). Numerical recipes in fortran 90: The art of parallel scientific computing.
- [Rice, 1993] Rice, J. R. (1993). Spatio-temporal complexity of slip on a fault. *Journal of Geophysical Research: Solid Earth*, 98(B6):9885–9907.
- [Romanet and Ozawa, 2022] Romanet, P. and Ozawa, S. (2022). Fully dynamic earthquake cycle simulations on a nonplanar fault using the spectral boundary integral element method (sbiem). Bulletin of the Seismological Society of America, 112(1):78–97.
- [Segall, 2010] Segall, P. (2010). Earthquake and volcano deformation. Princeton University Press.
- [Tse and Rice, 1986] Tse, S. T. and Rice, J. R. (1986). Crustal earthquake instability in relation to the depth variation of frictional slip properties. *Journal of Geophysical Research: Solid Earth*, 91(B9):9452–9472.