Homogeneous Coordinates

Translations of points in \mathbb{R}^n does not correspond directly to a linear transform. Homogeneous coordinates are used to model translations using matrix multiplication.

Homogeneous Coordinates in \mathbb{R}^2

Each point (x, y) in \mathbb{R}^2 can be identified with the point (x, y, H), $H \neq 0$, on the plane in \mathbb{R}^3 that lies H units above the xy-plane.

(x,y)
ightarrow (x+h,y+k) can be represented by,

$$\begin{pmatrix} 1 & 0 & h \\ 0 & 1 & k \\ 0 & 0 & 1 \end{pmatrix} \begin{pmatrix} x \\ y \\ 1 \end{pmatrix} = \begin{pmatrix} x+h \\ y+k \\ 1 \end{pmatrix}$$

Now rotate a triangle ((1,1),(2,4),(3,1)) by $\frac{\pi}{2}$ radians counterclockwise about the point (0,1).

$$d=egin{bmatrix}1&2&3\1&4&1\1&1&1\end{bmatrix}$$
 Shift down by 1, $\begin{bmatrix}1&0&0\end{bmatrix}$ $\begin{bmatrix}1&2&3\end{bmatrix}$

$$\begin{bmatrix} 1 & 0 & 0 \\ 0 & 1 & -1 \\ 0 & 0 & 1 \end{bmatrix} d = \begin{bmatrix} 1 & 2 & 3 \\ 0 & 3 & 0 \\ 1 & 1 & 1 \end{bmatrix}$$

Now rotate,

$$\begin{bmatrix} 0 & -1 & 0 \\ 1 & 0 & 0 \\ 0 & 0 & 1 \end{bmatrix} \begin{bmatrix} 1 & 0 & 0 \\ 0 & 1 & -1 \\ 0 & 0 & 1 \end{bmatrix} d = \begin{bmatrix} 0 & -3 & 0 \\ 1 & 2 & 3 \\ 1 & 1 & 1 \end{bmatrix}$$
Shift up by 1,

$$\begin{bmatrix} 1 & 0 & 0 \\ 0 & 1 & 1 \\ 0 & 0 & 1 \end{bmatrix} \begin{bmatrix} 0 & -3 & 0 \\ 1 & 2 & 3 \\ 1 & 1 & 1 \end{bmatrix} = \begin{bmatrix} 0 & -3 & 0 \\ 2 & 3 & 4 \\ 1 & 1 & 1 \end{bmatrix}$$

This give us the points, (0,2),(-3,3),(0,4)

In \mathbb{R}^3

So, $(x, y, z) \rightarrow (x + h, y + k, z + l)$ can be represented by,

$$\begin{pmatrix} 1 & 0 & 0 & h \\ 0 & 1 & 0 & k \\ 0 & 0 & 1 & l \\ 0 & 0 & 0 & 1 \end{pmatrix} \begin{pmatrix} x \\ y \\ z \\ 1 \end{pmatrix} = \begin{pmatrix} x+h \\ y+k \\ z+l \\ 1 \end{pmatrix}$$

Rotation in \mathbb{R}^3

about x_2 -axis by π rads.

To find $A = (a_1, a_2, a_3)$. We can find $T(e_1)$ as $T(e_1) = Ae_1 = a_1$. We can similarly find all the columns of A.

$$T(e_1) = egin{bmatrix} -1 \ 0 \ 0 \end{bmatrix} \ T(e_2) = egin{bmatrix} 0 \ 1 \ 0 \end{bmatrix} \ T(e_3) = egin{bmatrix} 0 \ 0 \ -1 \end{bmatrix} \ A = egin{bmatrix} -1 & 0 & 0 \ 0 & 1 & 0 \ 0 & 0 & -1 \end{bmatrix}$$

Projection

Onto the plane $x_3 = 4$ What should we do?

- 1. Shift everything down by 4 (Homogeneous Coordinates)
- 2. Apply the projection (Homogeneous Coordinates)
- 3. Shift everything back up by 4 (Homogeneous Coordinates) Amusing a vector \vec{v} ,

$$\begin{bmatrix} 1 & 0 & 0 & 0 \\ 0 & 1 & 0 & 0 \\ 0 & 0 & 1 & 4 \\ 0 & 0 & 0 & 1 \end{bmatrix} \begin{bmatrix} 1 & 0 & 0 & 0 \\ 0 & 1 & 0 & 0 \\ 0 & 0 & 0 & 0 \\ 0 & 0 & 0 & 1 \end{bmatrix} \begin{bmatrix} 1 & 0 & 0 & 0 \\ 0 & 1 & 0 & 0 \\ 0 & 0 & 1 & -4 \\ 0 & 0 & 0 & 1 \end{bmatrix} \vec{v}$$

You could drive the matrix but that is trivial and left as an exercise to the reader.

$$egin{bmatrix} 1 & 0 & 0 & 0 \ 0 & 1 & 0 & 0 \ 0 & 0 & 0 & 4 \ 0 & 0 & 0 & 1 \end{bmatrix} ec{v}$$