MIPS system calls

(from SPIM S20: A MIPS R2000 Simulator, James J. Larus, University of Wisconsin-Madison)

SPIM provides a small set of operating-system-like services through the MIPS system call (syscall) instruction. To request a service, a program loads the system call code (see Table below) into register \$v0 and the arguments into registers \$a0, ..., \$a3 (or \$f12 for floating point values). System calls that return values put their result in register \$v0 (or \$f0 for floating point results).

Service	System Call Code	Arguments	Result
print integer	1	\$a0 = value	(none)
print float	2	\$f12 = float value	(none)
print double	3	\$f12 = double value	(none)
print string	4	\$a0 = address of string	(none)
read integer	5	(none)	\$v0 = value read
read float	6	(none)	\$f0 = value read
read double	7	(none)	\$f0 = value read
read string	8	\$a0 = address where string to be stored $$a1 = number$ of characters to read $+ 1$	(none)
memory allocation	9	\$a0 = number of bytes of storage desired	\$v0 = address of block
exit (end of program)	10	(none)	(none)
print character	11	\$a0 = integer	(none)
read character	12	(none)	char in \$v0

For example, to print "the answer = 5", use the commands:

- **print int** passes an integer and prints it on the console.
- **print float** prints a single floating point number.
- print double prints a double precision number.
- **print string** passes a pointer to a null-terminated string
- read int, read float, and read double read an entire line of input up to and including a newline.
- **read string** has the same semantics as the Unix library routine fgets. It reads up to n 1 characters into a buffer and terminates the string with a null byte. If there are fewer characters on the current line, it reads through the newline and again null-terminates the string.
- **sbrk** returns a pointer to a block of memory containing *n* additional bytes.
- exit stops a program from running.